
# CS107, Lecture 12 Assembly: Arithmetic and Logic

Reading: B&O 3.5-3.6

# CS107 Topic 6: How does a computer interpret and execute C programs?

### **Learning Assembly**



**Reference Sheet**: cs107.stanford.edu/resources/x86-64-reference.pdf
See more guides on Resources page of course website!

# **Learning Goals**

Learn how to perform arithmetic and logical operations in assembly

#### **Plan For Today**

- Recap: Assembly and mov
- Data and Register Sizes
- The **lea** Instruction
- Logical and Arithmetic Operations

#### **Plan For Today**

- Recap: Assembly and mov
- Data and Register Sizes
- The **lea** Instruction
- Logical and Arithmetic Operations

### Assembly

- **Assembly code** is a human-readable form of the machine code your computer actually executes when running your programs.
- Assembly works at a lower level of abstraction than C code. It works with 64-bit spaces called **registers** that act as "scratch paper" for the processor.
- Operations in your C program ultimately are converted to operations that read or write to registers and perform calculations on these registers.

#### **Our First Assembly**

#### 00000000004005b6 <sum\_array>:

```
ba 00 00 00 00
                                     $0x0,%edx
4005b6:
                              mov
4005bb:
       b8 00 00 00 00
                                     $0x0,%eax
                              mov
4005c0:
       eb 09
                                     4005cb <sum array+0x15>
                              jmp
                              movslq %edx,%rcx
4005c2:
          48 63 ca
                                     (%rdi,%rcx,4),%eax
          03 04 8f
                              add
4005c5:
       83 c2 01
                                     $0x1,%edx
                              add
4005c8:
       39 f2
                                     %esi,%edx
4005cb:
                              cmp
       7c f3
                              j1
4005cd:
                                     4005c2 <sum array+0xc>
          f3 c3
4005cf:
                              repz reta
```

#### **Our First Assembly**

```
00000000000005b6 <sum_array>: 4005b6: ba 00 00 00 00
```

4005bb: b8 00 00 00 00

4005c0: eb 09

4005c2: 48 63 ca

4005c5: 03 04 8f

4005c8: 83 c2 01

4005cb: 39 f2

4005cd: 7c f3

4005cf: f3 c3

```
mov $0x0,%edx
mov $0x0,%eax
jmp 4005cb <sum_array+0x15>
movslq %edx,%rcx
add (%rdi,%rcx,4),%eax
add $0x1,%edx
cap %esi,%edx
j. 4005c2 <sum_array+0xc>
repz retq
```

Each instruction has an operation name ("opcode").

#### **Our First Assembly**

```
0000000000004005b6 <sum_array>:
    4005b6:    ba 00 00 00 00
    4005c0:    b8 00 00 00 00
    4005c2:    48 63 ca
    4005c5:    03 04 8f
    4005cb:    39 f2
```

7c f3

f3 c3

4005cd:

4005cf:

```
mov $0x0,%edx
mov $0x0,%eax
jmp 4005cb <sum_array+0x15>
movslq %edx,%rcx
add (%rdi,%rcx,4),%eax
add $0x1,%edx
cmp %esi,%edx
jl 4005c2 <sum_array+0xc>
```

Each instruction can also have arguments ("operands").

#### mov

The **mov** instruction <u>copies</u> bytes from one place to another.

mov

src,dst

The **src** and **dst** can each be one of:

- Immediate (constant value, like a number) (only src)
- Register
- Memory Location (at most one of src, dst)

# **Memory Location Syntax**

Syntax	Meaning	
0x104	Address 0x104 (no \$)	
(%rax)	What's in %rax	
4(%rax)	What's in %rax, plus 4	
(%rax, %rdx)	Sum of what's in %rax and %rdx	
4(%rax, %rdx)	Sum of values in %rax and %rdx, plus 4	
(, %rcx, 4)	What's in %rcx, times 4 (multiplier can be 1, 2, 4, 8)	
(%rax, %rcx, 2)	What's in %rax, plus 2 times what's in %rcx	
8(%rax, %rcx, 2)	What's in %rax, plus 2 times what's in %rcx, plus 8	

#### **Operand Forms**

Туре	Form	Operand Value	Name
Immediate	\$Imm	Imm	Immediate
Register	$r_a$	$R[r_a]$	Register
Memory	Imm	M[Imm]	Absolute
Memory	$(r_a)$	$M[R[r_a]]$	Indirect
Memory	$Imm(r_b)$	$M[Imm + R[r_b]]$	Base + displacement
Memory	$(r_b, r_i)$	$M[R[r_b] + R[r_i]]$	Indexed
Memory	$Imm(r_b, r_i)$	$M[Imm + R[r_b] + R[r_i]]$	Indexed
Memory	$(r_i, s)$	$M[R[r_i] \cdot s]$	Scaled indexed
Memory	$Imm(,r_i,s)$	$M[Imm + R[r_i] \cdot s]$	Scaled indexed
Memory	$(r_b, r_i, s)$	$M[R[r_b] + R[r_i] \cdot s]$	Scaled indexed
Memory	$Imm(r_b, r_i, s)$	$M[Imm + R[r_b] + R[r_i] \cdot s]$	Scaled indexed

**Figure 3.3 from the book: "Operand forms.** Operands can denote immediate (constant) values, register values, or values from memory. The scaling factor *s* must be either. 1, 2, 4, or 8."

### Plan For Today

- Recap: Assembly and mov
- Data and Register Sizes
- The **lea** Instruction
- Logical and Arithmetic Operations
- Control
  - Condition Codes
  - Assembly Instructions
- Practice: Reverse-Engineering

#### **Data Sizes**

Data sizes in assembly have slightly different terminology to get used to:

- A **byte** is....well, 1 byte!
- A word is 2 bytes.
- A double word is 4 bytes.
- A quad word is 8 bytes.


Assembly instructions can have suffixes to refer to these sizes:

- b means byte
- w means word
- 1 means double word
- q means quad word


# Register Sizes

Bit:	63	31	15	7 0
	%rax	%eax	%ax	%al
	%rbx	%ebx	%bx	%b1
	%rcx	%ecx	%сх	%c1
	%rdx	%edx	%dx	%d1
	%rsi	%esi	%si	%sil
	%rdi	%edi	%di	%dil

# **Register Sizes**



## **Register Sizes**



#### Register Responsibilities

Some registers take on special responsibilities during program execution.

- %rax stores the return value
- %rdi stores the first parameter to a function
- %rsi stores the second parameter to a function
- %rdx stores the third parameter to a function
- %rip stores the address of the next instruction to execute
- %rsp stores the address of the current top of the stack

See the x86-64 Guide and Reference Sheet on the Resources webpage for more!

#### mov Variants

- mov can take an optional suffix (b,w,l,q) that specifies the size of data to move: movb, movw, movl, movq
- mov only updates the specific register bytes or memory locations indicated.
  - Exception: movI writing to a register will also set high order 4 bytes to 0.

#### **Practice: mov And Data Sizes**

For each of the following mov instructions, determine the appropriate suffix based on the operands (e.g. **movb**, **movw**, **movl** or **movq**).

```
    mov___ %eax, (%rsp)
    mov___ (%rax), %dx
    mov___ $0xff, %bl
    mov___ (%rsp,%rdx,4),%dl
    mov___ (%rdx), %rax
    mov %dx, (%rax)
```

#### **Practice: mov And Data Sizes**

For each of the following mov instructions, determine the appropriate suffix based on the operands (e.g. **movb**, **movw**, **movl** or **movq**).

movl %eax, (%rsp)
 movw (%rax), %dx
 movb \$0xff, %bl
 movb (%rsp,%rdx,4),%dl
 movq (%rdx), %rax
 movw %dx, (%rax)

#### mov

- The movabsq instruction is used to write a 64-bit Immediate (constant) value.
- The regular **movq** instruction can only take 32-bit immediates.
- 64-bit immediate as source, only register as destination.

movabsq \$0x0011223344556677, %rax

#### movz and movs

- There are two mov instructions that can be used to copy a smaller source to a larger destination: **movz** and **movs**.
- movz fills the remaining bytes with zeros
- movs fills the remaining bytes by sign-extending the most significant bit in the source.
- The source must be from memory or a register, and the destination is a register.

#### movz and movs

MOVZ S,R

R ← ZeroExtend(S)

Instruction	Description
movzbw	Move zero-extended byte to word
movzbl	Move zero-extended byte to double word
movzwl	Move zero-extended word to double word
movzbq	Move zero-extended byte to quad word
movzwq	Move zero-extended word to quad word

#### movz and movs

MOVS S,R

$$R \leftarrow SignExtend(S)$$

Instruction	Description
movsbw	Move sign-extended byte to word
movsbl	Move sign-extended byte to double word
movswl	Move sign-extended word to double word
movsbq	Move sign-extended byte to quad word
movswq	Move sign-extended word to quad word
movslq	Move sign-extended double word to quad word
cltq	Sign-extend %eax to %rax %rax <- SignExtend(%eax)

#### **Plan For Today**

- Recap: Assembly and mov
- Data and Register Sizes
- The **lea** Instruction
- Logical and Arithmetic Operations
- Control
  - Condition Codes
  - Assembly Instructions
- Practice: Reverse-Engineering

#### lea

The **lea** instruction <u>copies</u> an "effective address" from one place to another.

lea src, dst

Unlike **mov**, which copies data <u>at</u> the address src to the destination, **lea** copies the value of src *itself* to the destination.

The syntax for the destinations is the same as **mov**. The difference is how it handles the src.

Operands	mov Interpretation	lea Interpretation
6(%rax), %rdx	Go to the address (6 + what's in %rax), and copy data there into %rdx	Copy 6 + what's in %rax into %rdx.

Operands	mov Interpretation	lea Interpretation
6(%rax), %rdx	Go to the address (6 + what's in %rax), and copy data there into %rdx	Copy 6 + what's in %rax into %rdx.
(%rax, %rcx), %rdx	Go to the address (what's in %rax + what's in %rcx) and copy data there into %rdx	Copy (what's in %rax + what's in %rcx) into %rdx.

Operands	mov Interpretation	lea Interpretation
6(%rax), %rdx	Go to the address (6 + what's in %rax), and copy data there into %rdx	Copy 6 + what's in %rax into %rdx.
(%rax, %rcx), %rdx	Go to the address (what's in %rax + what's in %rcx) and copy data there into %rdx	Copy (what's in %rax + what's in %rcx) into %rdx.
(%rax, %rcx, 4), %rdx	Go to the address (%rax + 4 * %rcx) and copy data there into %rdx.	Copy (%rax + 4 * %rcx) into %rdx.

Operands	mov Interpretation	lea Interpretation
6(%rax), %rdx	Go to the address (6 + what's in %rax), and copy data there into %rdx	Copy 6 + what's in %rax into %rdx.
(%rax, %rcx), %rdx	Go to the address (what's in %rax + what's in %rcx) and copy data there into %rdx	Copy (what's in %rax + what's in %rcx) into %rdx.
(%rax, %rcx, 4), %rdx	Go to the address (%rax + 4 * %rcx) and copy data there into %rdx.	Copy (%rax + 4 * %rcx) into %rdx.
7(%rax, %rax, 8), %rdx	Go to the address (7 + %rax + 8 * %rax) and copy data there into %rdx.	Copy (7 + %rax + 8 * %rax) into %rdx.

Unlike **mov**, which copies data <u>at</u> the address src to the destination, **lea** copies the value of src *itself* to the destination.

#### **Plan For Today**

- Recap: Assembly and mov
- Data and Register Sizes
- The **lea** Instruction
- Logical and Arithmetic Operations
- Control
  - Condition Codes
  - Assembly Instructions
- Practice: Reverse-Engineering

#### **Unary Instructions**

The following instructions operate on a single operand (register or memory):

Instruction	Effect	Description
inc D	D ← D + 1	Increment
dec D	D ← D - 1	Decrement
neg D	D ← -D	Negate
not D	D ← ~D	Complement

#### **Examples:**

```
incq 16(%rax)
dec %rdx
not %rcx
```

#### **Binary Instructions**

The following instructions operate on two operands (register or memory). Both cannot be memory locations. Read it as, e.g. "Subtract S from D":

Instruction	Effect	Description
add S, D	$D \leftarrow D + S$	Add
sub S, D	D ← D - S	Subtract
imul S, D	D ← D * S	Multiply
xor S, D	D ← D ^ S	Exclusive-or
or S, D	D ← D   S	Or
and S, D	D ← D & S	And

#### **Examples:**

```
addq %rcx,(%rax)
xorq $16,(%rax, %rdx, 8)
subq %rdx,8(%rax)
```

#### Large Multiplication

- Multiplying 64-bit numbers can produce a 128-bit result. How does x86-64 support this with only 64-bit registers?
- If you specify two operands to **imul**, it multiplies them together and truncates until it fits in a 64-bit register.

imul S, D D 
$$\leftarrow$$
 D \* S

• If you specify one operand, it multiplies that by **%rax**, and splits the product across **2** registers. It puts the high-order 64 bits in **%rdx** and the low-order 64 bits in **%rax**.

Instruction	Effect	Description
imulq S	$R[%rdx]:R[%rax] \leftarrow S \times R[%rax]$	Signed full multiply
mulq S	$R[%rdx]:R[%rax] \leftarrow S \times R[%rax]$	Unsigned full multiply

#### **Division and Remainder**

Instruction	Effect	Description
idivq S	$R[rdx] \leftarrow R[rdx]:R[rax] \mod S;$	Signed divide
	$R[\$rax] \leftarrow R[\$rdx]:R[\$rax] \div S$	
divq S	$R[\$rdx] \leftarrow R[\$rdx]:R[\$rax] \mod S;$	Unsigned divide
	$R[\$rax] \leftarrow R[\$rdx]:R[\$rax] \div S$	

- <u>Terminology</u>: <u>dividend</u> / <u>divisor</u> = <u>quotient</u> + <u>remainder</u>
- x86-64 supports dividing up to a 128-bit value by a 64-bit value.
- The high-order 64 bits of the dividend are in %rdx, and the low-order 64 bits are in %rax. The divisor is the operand to the instruction.
- The quotient is stored in %rax, and the remainder in %rdx.

#### **Division and Remainder**

Instruction	Effect	Description
cqto	$R[\rdx]:R[\rdx] \leftarrow SignExtend(R[\rdx])$	Convert to oct word
idivq S	$R[\$rdx] \leftarrow R[\$rdx]:R[\$rax] \mod S;$	Signed divide
	$R[\$rax] \leftarrow R[\$rdx]:R[\$rax] \div S$	
divq S	$R[\$rdx] \leftarrow R[\$rdx]:R[\$rax] \mod S;$	Unsigned divide
	$R[\$rax] \leftarrow R[\$rdx]:R[\$rax] \div S$	

- <u>Terminology</u>: <u>dividend</u> / <u>divisor</u> = <u>quotient</u> + <u>remainder</u>
- The high-order 64 bits of the dividend are in %rdx, and the low-order 64 bits are in %rax. The divisor is the operand to the instruction.
- Most division uses only 64 bit dividends. The **cqto** instruction sign-extends the 64-bit value in **%rax** into **%rdx** to fill both registers with the dividend, as the division instruction expects.

#### **Shift Instructions**

The following instructions operate on two operands, one the shift amount and the other the destination to shift. The shift amount **k** can be either an immediate value, or the byte register **%cl** (and only that register!)

Instruction	Effect	Description
sal k, D	$D \leftarrow\!$	Left shift
shl k, D	$D \leftarrow\!$	Left shift (same as sal)
sar k, D	$D \leftarrow\!$	Arithmetic right shift
shr k, D	$D \leftarrow\!$	Logical right shift

#### **Examples:**

```
shll $3,(%rax)
shrl %cl,(%rax,%rdx,8)
sarl $4,8(%rax)
```


#### **Shift Amount**

Instruction	Effect	Description
sal k, D	$D \leftarrow\!$	Left shift
shl k, D	$D \leftarrow\!$	Left shift (same as sal)
sar k, D	$D \leftarrow\!$	Arithmetic right shift
shr k, D	$D \leftarrow\!$	Logical right shift

- When using **%cl**, the width of what you are shifting determines how much of **%cl** it is shifted by.
- For w bits of data, it looks at the low-order log2(w) bits of %cl to know how much to shift.
  - If %cl = 0xff, then: shlb shifts by 7 because it considers only the low-order log2(8) = 3 bits, which represent 7. shlw shifts by 15 because it considers only the low-order log2(16) = 4 bits, which represent 15.

#### **Announcements**

- Midterms have been graded information and grades will be posted this afternoon.
- Regrade requests for grading errors will open tomorrow through next Tuesday.



Median: 89, Mean: 86

#### **Assembly Exploration**

- Let's pull these different commands together and see how some C code we write may be translated into assembly.
- Compiler Explorer is a handy website that lets you write C code and see its
  assembly translation without having to log into Myth or compile/disassemble a
  program. Let's check it out!
- https://godbolt.org/z/NLYhVf

#### Code Reference: add\_to\_first

```
// Returns the sum of x and the first element in arr
int add to first(int x, int arr[]) {
    int sum = x;
    sum += arr[0];
    return sum;
add to first:
 movl %edi, %eax
  addl (%rsi), %eax
  ret
```

#### Code Reference: full\_divide

```
// Returns x/y, stores remainder in location stored in remainder ptr
long full divide(long x, long y, long *remainder ptr) {
    long quotient = x / y;
    long remainder = x % y;
    *remainder ptr = remainder;
    return quotient;
full divide:
  movq %rdx, %rcx
 movq %rdi, %rax
  cqto
  idivq %rsi
  movq %rdx, (%rcx)
```

ret

#### Recap

- Recap: Assembly and mov
- Data and Register Sizes
- The **lea** Instruction
- Logical and Arithmetic Operations

**Next time:** Control flow in assembly