

Cisco Software Manager Server Installation Guide

This installation guide provides instructions on installing CSM Server and other components on your Linux distribution. CSM Server is written in Python. Almost all Linux distributions come with a Python interpreter. The required Python version is Python 2.7 or above. CSM Server also uses other Python libraries and tools such as Flask (a Python micro framework) and Gunicorn (a Python WSGI HTTP Server), as well as MySQL database for data storage.

If your system has Python 2.7.x (x represents a minor release number), you may skip the Python installation section. If your system has MySQL installed, you may skip the MySQL installation section. At some point, you will be asked to give a username and password for CSM Server to connect to MySQL. You may want to create a new database user instead of using the root user.

You will need root access to install all the components. If you are a trusted user with administrative access to a system, you can add **sudo** to the beginning of an administrative command to execute it as if it were run by the root user. The server that hosts CSM Server will need to have Internet connectivity so it can download and install the necessary components. If a proxy is required to reach secure sites (e.g. HTTPS), include the following statements in your ~/.bashrc in your user directory. Here is an example,

1

export http_proxy=http://proxy-wsa.esl.cisco.com:80
export https_proxy=\$http_proxy

Table of Contents

System Specifications	3
2 Identify Your Linux Distribution	3
3 Install Python	3
4 Install MySQL	4
 4.1 On CentOS/RedHat 4.2 On Ubuntu/Debian 4.3 Build from Source (Other Linux) 	4
5 Create a Database User	5
6 Unpack CSM Server Code	6
7 Install pip	6
7.1 On Ubuntu/Debian7.2 On Others	
8 Use Virtual Environment	7
9 Install Other Libraries	8
9.1 Install Libraries using requirement.txt9.2 Install Libraries One by One	
10 Launch CSM Server	9
11 Connect to CSM Server	10
12 LDAP for User Authentication	10
12.1 On CentOS/RedHat	
13 SSL Support for CSM Server	11
14 Known Issues	14
14.1 pip failed on certain Ubuntu versions	14

1 System Specifications

Below are suggested system requirements. If you plan to download lots of SMUs and software packages for multiple releases, the storage requirement may need to be increased. CSM Server data is stored in the MySQL database as well as in the csm_data directory. The csm_data directory stores logs and downloaded software. It is created when CSM Server first starts and can be located on the same level as the csm directory.

Linux Virtual Machine

• CPU: Dual-core processor

• Memory: 4 GB, Storage: 64 GB

2 Identify Your Linux Distribution

Run the commands below to identify your Linux distribution. Once your Linux distribution is identified, follow only the instructions specific for your distribution (RedHat / CentOS / Debian / Ubuntu), or follow the Build from Source instructions (i.e. directly building the component from the source code).

If the command below returns information, you are likely on **RedHat** or **CentOS**.

cat /etc/redhat-release

Ubuntu or **Debian** will respond to the command below.

lsb release -a

3 Install Python

If your system python version is not 2.7 or above, follow these steps to build python from the source code. CSM Server is tested on python 2.7.6. However, any 2.7.x should work.

Change directory to /usr/local (you may use a different directory if so desired), and use 'wget' to download the Python Gzipped source tar ball. This command requires root user privilege.

sudo wget https://www.python.org/ftp/python/2.7.6/Python-2.7.6.tgz

Or download Python 2.7.6 from https://www.python.org/download/releases/2.7.6 (select the Gzipped source tar ball) and copy it to /usr/local. Then, extract the contents using 'tar' and build it as shown below.

```
tar xvzf Python-2.7.6.tgz
cd Python-2.7.6
./configure
make
```

make install

4 Install MySQL

Select the section that applies to your Linux distribution to install MySQL

4.1 On CentOS/RedHat

If you have CentOS6, skip this step. For CentOS7, use the instruction below to add mysql-community to your repository.

```
rpm -Uvh http://dev.mysql.com/get/mysql-community-release-el7-5.noarch.rpm
```

Install the MySQL server through the Package Manager by running the following commands at a command prompt:

```
sudo yum install mysql-server
sudo /sbin/service mysqld start
```

Then, run the following command:

```
sudo /usr/bin/mysql secure installation
```

Press enter to give no password for root. However, when asked to set the root password, answer 'Y' and enter the password. To apply some reasonable security to your new MySQL server, answer "yes" to all the questions. In order, those questions enable you to set the root password, remove anonymous users, disable remote root logins, delete the test database that the installer included, and then reload the privileges so that your changes will take effect.

4.2 On Ubuntu/Debian

Install the MySQL by running the following command.

```
sudo apt-get update
sudo apt-get install mysql-server
```

During the installation, you will be asked to assign a password to the root user. mysqld will be started automatically.

4.3 Build from Source (Other Linux)

Download MySQL from http://dev.mysql.com/downloads/mysql.

- 1. Select the correct Linux platform
- 2. Use 'uname –a' to identify if your platform is 32 or 64-bit system.
- 3. Based on your platform, download either the 32 or 64-bit tar file

The example below show a 64-bit Linux – Generic distribution

```
rpm -ivh MySQL-server-5.6.16-1.linux_glibc2.5.x86_64.rpm rpm -ivh MySQL-client-5.6.16-1.linux_glibc2.5.x86_64.rpm
```

Start/Stop MySQL Server

You will need to start the MySQL daemon so CSM server can connect to it later.

```
service mysgl start
```

Since CSM Server is always running (24x7), you seldom need to stop the mysql daemon. In fact, you may want to include it in the startup script so it runs when the machine is booted up. To stop the daemon, type

```
service mysql stop
```

Step Up Root Password

A newly installed MySQL may or may not have password for the root user. Depending on the Linux distribution, the temporary password may be found below:

```
cat /root/.mysql_secret
```

To set the password, run the mysql client.

```
mysql -u root -p
```

After that, it will prompt for the root password. Either enter the temporary password or hit <Enter> for no password. This should give you a mysql prompt. To assign a password to the root user, enter

```
mysql> SET PASSWORD=PASSWORD('new password');
```

To exit mysql client, type 'quit' on the mysql prompt.

5 Create a Database User

At this point, a root username and password should have been created for the new MySQL installation. If you don't want CSM Server to use the root username and password to connect to

MySQL, following the steps below to create a new database user. Run mysql client to connect to the MySQL server, enter the root password when prompted.

```
mysql -u root -p
```

Substitute 'newuser' with the new username and 'password' with the new password:

```
mysql> CREATE USER 'newuser'@'localhost' IDENTIFIED BY 'password';
```

The newly created user will need privileges. Remember to substitute 'newuser' with the new username.

```
mysql> GRANT ALL PRIVILEGES ON csmdb.* TO newuser@localhost;
```

Reload all the privileges once the new user is created.

```
mysql> FLUSH PRIVILEGES;
```

Type 'quit' to exit mysql client.

6 Unpack CSM Server Code

You should have received a zip file in the format of csm-x.x.zip (x.x is CSM version). While issuing the commands below, be sure to replace x.x with the correct version string.

```
cd /usr/local
cp <directory path>/csm-x.x.zip .
sudo unzip csm-x.x.zip
```

7 Install pip

The pip tool is a package management system used for installing and managing Python packages. It will be used to install components that are required by CSM Server. If you already have pip installed, skip these steps.

Use pip With HTTP Proxy

If your system requires HTTP proxy to access the Internet, you will need to use the '-E' flag when using pip with sudo. Make sure you have the HTTP proxy setup and it has already been exported. Below is an example of the usage.

```
sudo -E pip install -r requirements.txt
```

References

For more information about pip, read http://pip.readthedocs.org/en/latest/installing.html

7.1 On Ubuntu/Debian

sudo apt-get install python-pip

7.2 On Others

sudo easy install pip

or

sudo wget https://bootstrap.pypa.io/get-pip.py
sudo python get-pip.py

8 Use Virtual Environment

This section is optional. virtualenv is a tool to create an isolated Python virtual environment. It creates an environment that has its own installation directories and doesn't share libraries with other virtual environments (and optionally doesn't access the globally installed libraries either). If your system has several python applications, using virtualenv will ensure that the installed libraries won't conflict with your existing applications. All python components used by CSM Server will be installed inside the virtual environment. When launching CSM Server, it must be done inside the virtual environment. To remove CSM Server and related python libraries, simply remove the virtual environment directory (i.e. 'env' as used below)

sudo pip install virtualenv

Create a Virtual Environment

To create a virtual environment and copy the correct version of the python interpreter inside it, use the '-p' flag along with the python interpreter path (use 'which python' or 'which python2.7' to identify the path). If your system requires HTTP proxy to access the Internet, you will need to use the '-E' flag. The word 'env' is the virtual environment name.

cd /usr/local/csm/csmserver
sudo -E virtualenv -p /usr/bin/python2.7 env

Enter the Virtual Environment

To enter the virtual environment, from /usr/local/csm/csmserver, type

source env/bin/activate

You should see a new shell prompt with '(env)' as the prefix. This indicates that you are inside the virtual environment.

Exit the Virtual Environment

Type 'deactivate' and the normal shell prompt will re-appear (i.e. without '(env)').

deactivate

9 Install Other Libraries

If you are using a virtual environment, make sure you are inside the virtual environment before proceeding. Refer to Enter the Virtual Environment. One of the libraries, pysftp (SFTP support), requires Python Development Tool. Follow the steps below to install it.

On CentOS/RedHat

sudo yum install python-devel

On Ubuntu/Debian

sudo apt-get install python-dev

9.1 Install Libraries using requirement.txt

This file contains a list of libraries that are used by CSM Server. Using this method to install libraries saves time and typing.

```
cd /usr/local/csm/csmserver
sudo pip install -r requirements.txt
```

9.2 Install Libraries One by One

If using the requirements.txt method above fails, follow these steps to install libraries one at a time to identify the issue.

```
cd /usr/local/csm/csmserver

sudo pip install Flask==0.10.1

sudo pip install Flask-Login==0.2.11

sudo pip install Flask-HTTPAuth==2.5.0

sudo pip install SQLAlchemy==0.9.8

sudo pip install WTForms==2.0.2

sudo pip install PyMySQL==0.6.3

sudo pip install requests==2.5.1
```

```
sudo pip install ordereddict==1.1
sudo pip install gunicorn==19.2.1
sudo pip install xlutils==1.7.1
sudo pip install pysftp==0.2.8
sudo pip install csmpe==1.0.1
sudo pip install scp==0.10.2
```

10 Launch CSM Server

A launch script called csmserver is provided in the csm/csmserver directory to start or stop CSM Server. If your system's python 2.7.x interpreter is not callable by the name "python", edit the csmserver launch script and update the following line.

PYTHON="python" to PYTHON="python2.7"

```
cd /usr/local/csm/csmserver
sudo vi csmserver
```

Configure Database Parameters

In the csmserver directory, a file called database.ini contains the database connection information. This information enables CSM Server to connect to MySQL. Edit this file and replace 'root' with the preferred database user's username and password. Once the file is read, the username and password will be encrypted.

sudo vi database.ini

```
[Database]
drivername = mysql+pymysql
host = localhost
port = 3306
username = root
password = root
database = csmdb
```

To Start CSM Server

If you are using a virtual environment, make sure you are inside the virtual environment before proceeding. Refer to Enter the Virtual Environment. Use the command below to start CSM Server.

sudo ./csmserver start

If the following error messages are observed when you attempt to start CSM Server, it means CSM Server is already running.

```
[4596] [INFO] Starting gunicorn 19.1.1

[2015-02-11 12:36:46 +0000] [4596] [ERROR] Connection in use: ('0.0.0.0', 5000)

[2015-02-11 12:36:46 +0000] [4596] [ERROR] Retrying in 1 second.
```

To Stop CSM Server

sudo ./csmserver stop

11 Connect to CSM Server

Once the CSM Server is running, type the following into a browser:

```
http://<IPAddress or Domain Name>:5000
```

You should see the Login dialog. The default username and password is '**root/root**'. Once logged in, change the password by clicking Tools – Edit My Profile.

12 LDAP for User Authentication

LDAP (Lightweight Directory Access Protocol) is a software protocol for accessing and maintaining distributed directory information services over an IP network. One common usage of LDAP is for user authentication across many organizational services. Instead of creating each user for CSM Server, CSM Server can connect to your LDAP server to authenticate users. Authenticated users will have network administrator privilege. If you are not planning to use LDAP, you can skip this section.

CSM Server uses python-ldap which is an object-oriented API to access LDAP directory servers. It requires OpenLDAP libraries on your Linux distribution. Follow the instruction below to install required libraries.

12.1 On CentOS/RedHat

```
sudo yum install python-devel
sudo yum install openldap-devel
sudo pip install python-ldap (for Redhat RHEL above 5.5)
sudo pip install python-ldap==2.3.13 (for Redhat RHEL equals 5.5)
```

12.2 On Ubuntu/Debian

```
sudo apt-get update
sudo apt-get install python-dev libldap2-dev libsas12-dev
sudo apt-get install python-ldap
```

Configure LDAP

If LDAP and its required libraries are not installed successfully, a message "LDAP authentication is not supported because it has not been installed" will be printed on the terminal when CSM Server is started and the GUI below will not be available on Tools – Admin Dashboard. If LDAP is installed successfully, follow the steps below to configure it.

To configure LDAP, click Tools – Admin Dashboard on CSM Server and enter the relevant information. Be sure to click the Save button.



13 SSL Support for CSM Server

The Gunicorn web server installed with CSM Server can support SSL. Follow the steps below to generate a self-signed digital certificate for secure Intranet deployment if desirable.

Generate the SSL Private Key

The ssl.key file created contains the private key information.

```
cd /usr/local/csm/csmserver sudo openssl genrsa -out ssl.key 2048
```

Generate the SSL Certificate

The number 5000 is the number of days this certificate is valid for. You may increase the number if desired. The following command will generate the ssl.cert file for the digital certificate.

```
sudo openssl req -new -x509 -nodes -sha1 -days 5000 -key ssl.key -out ssl.cert
```

You will be prompted to enter Country, State, City, Organization, Common Name, and etc. The Common Name is a fully qualified domain name (FQDN) of your server. This must match exactly what you type in your web browser or you will receive an error. You may also enter the IP Address if desired. Skip all data fields after the email address.

To Start Secure CSM Server

sudo ./csmserver start secure

To Stop CSM Server

sudo ./csmserver stop

Connect to Secure CSM Server

From a web browser, type https://IPAddressOrDomain:5000

https://<IPAddress|Domain>:5000

Self-signed Certificate with Google Chrome

Because the digital certificate is self-signed, it is not considered as trusted by browsers (i.e. not issued by Certificate Authority). Some browsers allow users to add self-signed certificate as an exception. However, Google Chrome browser displays a red-cross icon as below even though the data is still encrypted. To resolve this, the digital certificate needs to be added to the trusted store on the system.



On Windows, Export the certificate from Chrome, and then import the certificate into your trusted root certification authority store. Go to Start | and run the command "certmgr.msc".

Expand the tree to get to Trusted Root Certification Authorities | Certificates. Right click on Certificates and go to All Tasks, choose Import and import the certificate in question.

To export the certificate from Chrome, click on the Certificate icon in the address bar. Click on Certificate Information | Details and then Copy to File.

Apache as Reverse-Proxy to Gunicorn

In this setup scenario, Apache will proxy the requests to Gunicorn, and Gunicorn to CSM Server. To support this setup, the mod_proxy module must be installed. The mod_proxy module implements a proxy (or gateway) for applications running on the back-end. Follow the instructions in 'Installing Apache and mod_proxy' section in the link below and skip the <VirtualHost> modification as we will be using SSL Reverse-Proxy.

https://www.digitalocean.com/community/tutorials/how-to-use-apache-http-server-as-reverse-proxy-using-mod proxy-extension

Enabling SSL Support

To use Apache2 SSL, you must enable the mod_ssl module. This can be achieved by using the a2enmod tool.

a2enmod ssl

At this point, you should have acquired a SSL certificate for your domain. Your SSL Virtual Host configurations should have a reference to the certificate.

Enabling SSL Reverse-Proxy Support

The following configurations must be present in the SSL Virtual Host configurations.

```
<VirtualHost default :443>
    . 1. .
    . 1. .
   SSLEngine on
    # This will avoid SSL handshake error if the SSL certificate
    # for CSM Server is a self-signed certificate.
   SSLProxyEngine on
   SSLProxyVerify none
    SSLProxyCheckPeerCN off
    SSLProxyCheckPeerName off
   {\tt SSLProxyCheckPeerExpire\ off}
    # Reference the SSL certificate of your domain
    SSLCertificateFile /etc/apache2/ssl/server.pem
   SSLCertificateKeyFile /etc/apache2/ssl/server.key
    # If CSM Server resides on the same host as Apache,
    # use localhost as the IP address. This ensures only
    # local connection is allowed to reach port 5000. Otherwise,
    # replace it with the host IP where CSM Server is running from.
    ProxyPass / https://localhost:5000/
    ProxyPassReverse / https://localhost:5000/
```

CSM Server Script Modification

If CSM Server resides on the same host as Apache, you will need to modify CSM Server launch script to have it listen to just the localhost instead of 0.0.0.0 (all external IP addresses) to ensure all requests are proxied from Apache. Open /usr/local/csm/csmserver and change

```
LISTENING IP=0.0.0.0
```

To

LISTENING_IP=localhost

Restart the Apache Server

sudo /etc/init.d/apache2 restart

Useful References

https://www.digitalocean.com/community/tutorials/how-to-use-apache-http-server-as-reverse-proxy-using-mod proxy-extension

https://www.debian-administration.org/article/349/Setting_up_an_SSL_server_with_Apache2

14 Known Issues

14.1 pip failed on certain Ubuntu versions

Symptom:

ImportError: cannot import name IncompleteRead

Workaround:

The workaround requires removing python-pip and getting a newer version.

```
sudo apt-get purge python-pip
sudo wget https://bootstrap.pypa.io/get-pip.py
sudo python get-pip.py
sudo apt-get install python-pip
```

End of Document