Parametric Curve

Nobuyuki Umetani

February 7, 2018

Contents

1	Parametric Curve	1
2	Bezier Curve	1
	2.1 De Casteljau's algorithm	1 2
3	B-Spline Curve	2
	3.1 Knot Vector	2
	3.2 Cox - De Boor's algorithm	2
	3.3 Knot Insertion	2 2 2 4
4	NURBS Curve	5
	4.1 How NURBS can Represent a Perfect Circle	5
1	Parametric Curve	
	$\int_0^1 \sqrt{\left(\frac{d\mathbf{p}}{dt}(t)\right)^2} dt$	(1)
		(2)
2	Bezier Curve	
	$\mathbf{p}(t) = (1-t)^3 \mathbf{p}_0 + 3(1-t)^2 t \mathbf{p}_1 + 3(1-t)t^2 \mathbf{p}_2 + t^3 \mathbf{p}_3$	(3)

$$\mathbf{p}(t) = (1-t)^3 \mathbf{p}_0 + 3(1-t)^2 t \mathbf{p}_1 + 3(1-t)t^2 \mathbf{p}_2 + t^3 \mathbf{p}_3$$
 (3)

Tangent

$$\frac{d\mathbf{p}}{dt}(t) = -3(1-t)^2\mathbf{p}_0 + 3(3t-1)(t-1)\mathbf{p}_1 - 3t(3t-2)\mathbf{p}_2 + 3t^2\mathbf{p}_3$$
 (4)

2.1 De Casteljau's algorithm

3 B-Spline Curve

B-Spline curve is constructed from the three ingredients.

- the degree of the polynominal basis p.
- a set of *n* control points $\{\mathbf{p}_0, \dots, \mathbf{p}_{n-1}\}\$,
- a knot vector **u** of m+1 non-descending real number $\{u_0 \le u_1 \le u_2 \dots \le u_m\}$ where m=n+p.

It is a bit confusing but, if the basis is p degree polynominal, the B-Spline curve is called p+1 order. The order of the B-Spline means that up to p+1 control points affects a position of a point on the curve.

From the knot vector and p, we can define a basis function $N_{i,p}(u)$ which takes value in the range $u \in [u_0, u_m]$. Then, the resulting equation of the curve becomes

$$\mathbf{p}(u) = \sum_{i=0}^{n-1} N_{i,p}(u)\mathbf{p}_i$$
 (5)

3.1 Knot Vector

The knot vector **u** defines segments on the parameter the curve. This allows non-uniformly sized segments and gives the B-Spline higher degree of expression. Quite frequently, the interval between knots become zero 0 if the knot takes the same value. The number of the time the knot duplicate is called *knots multiplicity*.

3.2 Cox - De Boor's algorithm

The basis function is defined hierarchically. In other words, we build up the basis function based on the basis function of one order lower.

We start from 0 degree basis function which is piecewise constant over the interval

$$N_{i,0}(u) = \begin{cases} 1 & if \ u_i < u < u_{i+1} \\ 0 & otherwize \end{cases}$$
 (6)

Then, for p > 0, we define the basis functions using the basis function of p - 1 degree as

$$N_{i,p}(u) = \frac{u - u_i}{u_{i+p} - u_i} N_{i,p-1}(u) + \frac{u_{i+p+1} - u}{u_{i+p+1} - u_{i+1}} N_{i+1,p-1}(u)$$
(7)

Figure 1 show the basis functions of the B-Spline with different degrees.

Please notice that, the degree p basis function have a domain of p+1 intervals. So if you go up in the higher degree, the influence of a control point gets wider, meaning that the function become smoother. Further more, given a parameter $t \in [t_0, t_m]$, it will cover by up to p+1 basis function. This means that p+1 control points influence a point on the B-Spline curve.




Figure 1: Basis functions of a B-Spline curve with uniform knots. The degree of the basis function increases from top row (p = 0) to be bottom row (p = 3).

Figure 2 shows that example of the B-Spline basis function construction from the basis functions of p=1 to one of p=2 using the (7). Starting from two neighboring basis functions we call left and right functions, we multiply a linear functions for each. For the left basis function we multiply a linear function that goes from zero to one over the domain of the function. Domain of the function means where the function takes value other than zero. In this case p=1 functions takes two segments as the domain. Similarly, we multiply the right basis function to a linear function that linearly goes down from one to zero over its domain. If we multiply a linear function to p degree function, we get a p+1 degree function. Adding up these two functions, we get a new basis. Because the left and right basis function have domains different by one segment, the new basis function gets a one segment wider.




Figure 2: Cox - De Boors algorithm applied to two neighboring piece-wise linear basis functions to produce a piece-wize quadratic basis function.

3.3 Knot Insertion

We can insert a knot in the knot vector without changing the curve shape.

Let's say we insert a knot u in the knot vector. Because the knot values need to be monotonically increase, the u need to be insert in the segment $[u_k, u_{k+1}]$ where $u_k \le u \le u_{k+1}$. If we add one knot value, one control point need to be added (remember the relation n = m + p). There are p + 1 number of basis functions whose domain include u are $N_{k-p,p}, \ldots, N_{k,p}$. As these basis functions are determined by the knot vales, thus affected by the knot insertion, the corresponding control points $\mathbf{p}_{k-p}, \ldots, \mathbf{p}_k$ need to be relocated as the basis functions change. Let's say we change the control points $\mathbf{p}_{k-p}, \ldots, \mathbf{p}_k$ into the $\mathbf{q}_{k-p}, \ldots, \mathbf{q}_k, \mathbf{q}_{k+1}$.

De Boor's algorithm says the new control point locations are on the polyline connecting the old control points. For example, the new control point \mathbf{q}_i lies on the line segment connecting \mathbf{p}_{i-1} and \mathbf{p}_i .

$$\mathbf{q}_i = (1 - a_i)\mathbf{p}_i + a_i\mathbf{p}_{i+1} \tag{8}$$

$$a_i = \frac{u - u_i}{u_{i+p} - u_i} \tag{9}$$

4 NURBS Curve

The NURBS is the abbreviation of \underline{N} on- \underline{U} niform \underline{R} ational \underline{B} - \underline{S} pline curve. "non-uniform" means that the interval of the knots can be uneven. Rational means there are weight w for the control points.


$$\mathbf{p}(u) = \frac{\sum_{i=0}^{n-1} N_{i,p}(u) w_i \mathbf{p}_i}{\sum_{i=0}^{n-1} N_{i,p} w_i}$$
(10)


This weight gives further control ability to the curve.

Each control points have a weight w_i . If all the weight is 1 it becomes a B-Spline curve with non-uniform knot interval.

4.1 How NURBS can Represent a Perfect Circle

Let's use a homogeneous coordinate to understand how the NURBS can successfully define a perfect circle. Here we think about two dimensional space where. A homogeneous coordinate has additional one dimension w in addition to the xy. The point (x, y, w) in homogeneous coordinate corresponds to the two dimensional point (x/w, y/w). Such a homogeneous coordinate is called Affine transformation and is very useful in computer graphics to define perspective transformation.





$$u_0, u_1, u_2, u_3, u_4, u_5, u_6, u_7$$
 (11)

$$0, x, y, w, w = 1 (12)$$

$$\mathbf{p}_{k-p-1}, \mathbf{p}_{k-p}, \mathbf{p}_k, \mathbf{p}_{k+1} \tag{13}$$

$$\mathbf{q}_{k-p-1}, \mathbf{q}_{k-p}, \mathbf{q}_k, \mathbf{q}_{k+1} \tag{14}$$