

Nginx, Inc.

NGINX Plus Reference Guide

NGINX Plus - release 24, based on 1.19.10 core $_{\rm April~13,~2021}$

Copyright Notice

© 2012-2021 Nginx, Inc. All rights reserved. NGINX, NGINX Plus and any Nginx, Inc. product or service name or logo used herein are trademarks of Nginx, Inc. All other trademarks used herein belong to their respective owners. The trademarks and logos displayed herein may not be used without the prior written consent of Nginx, Inc. or their respective owners.

This documentation is provided "AS IS" and is subject to change without notice and should not be interpreted as a commitment by Nginx, Inc. This documentation may not be copied, modified or distributed without authorization of Nginx, Inc. and may be used only in connection with Nginx, Inc. products and services. Nginx, Inc. assumes no responsibility or liability for any errors or inaccuracies that may appear in this documentation.

Preface

About NGINX

NGINX® ("engine x") is a high performance, high concurrency web server excelling at large scale content delivery, web acceleration and protecting application containers. Its precise integration with modern operating systems allows unprecedented levels of efficiency even when running on commodity hardware.

Nginx, Inc. develops and maintains NGINX open source distribution, and offers commercial support and professional services for NGINX.

About NGINX Plus

- Offers additional features on top of the free open source NGINX version.
- Prepared, tested and supported by NGINX core engineering team led by the original author Igor Sysoev.

For more information

- Find more details about NGINX products and support at https://www.nginx.com/.
- For online NGINX documentation visit https://nginx.org/en/docs.
- NGINX and NGINX Plus Tutorial and Admin Guide is available here: https://www.nginx.com/resources/admin-guide/.
- For general inquiries, please use: nginx-inquiries@nginx.com

Contents

Title							
Preface							
Ta	able c	of Contents	3				
1	Cor	e modules	6				
	1.1	Core functionality	6				
	1.2	Setting up hashes	16				
	1.3	Connection processing methods	17				
	1.4	Logging to syslog	18				
2	HT	ΓP server modules 1	9				
	2.1	Module ngx_http_core_module	19				
	2.2		59				
	2.3		31				
	2.4	Module ngx_http_api_module	33				
	2.5	Module ngx_http_auth_basic_module	10				
	2.6	Module ngx_http_auth_jwt_module					
	2.7	Module ngx_http_auth_request_module					
	2.8	Module ngx_http_autoindex_module					
	2.9	Module ngx_http_browser_module	20				
	2.10	Module ngx_http_charset_module	22				
	2.11	Module ngx_http_dav_module	25				
	2.12	Module ngx_http_empty_gif_module	28				
	2.13	Module ngx_http_f4f_module	29				
	2.14	Module ngx_http_fastcgi_module	30				
	2.15	Module ngx_http_flv_module	51				
	2.16	Module ngx_http_geo_module	52				
	2.17	Module ngx_http_geoip_module	55				
	2.18	Module ngx_http_grpc_module	58				
	2.19	Module ngx_http_gunzip_module	37				
		Module ngx_http_gzip_module					
		Module ngx_http_gzip_static_module					
		Module ngx_http_headers_module					
		Module ngx_http_hls_module					
		Module ngx http image filter module					

CONTENTS CONTENTS

2.25	Module ngx_http_index_module
2.26	Module ngx_http_js_module
2.27	Module ngx_http_keyval_module
2.28	Module ngx_http_limit_conn_module
	Module ngx_http_limit_req_module
	Module ngx_http_log_module
	Module ngx_http_map_module
	Module ngx_http_memcached_module
	Module ngx_http_mirror_module
	Module ngx_http_mp4_module
	Module ngx_http_perl_module
	Module ngx_http_proxy_module
	Module ngx_http_random_index_module
	Module ngx_http_realip_module
	Module ngx_http_referer_module
	Module ngx_http_rewrite_module
	Module ngx_http_scgi_module
	Module ngx_http_secure_link_module
	Module ngx_http_session_log_module
	Module ngx_http_slice_module
	Module ngx_http_split_clients_module
	Module ngx_http_spint_chents_module
	Module ngx_http_ssl_module
	Module ngx_http_status_module
	Module ngx_http_stub_status_module
	Module ngx_http_sub_module
	Module ngx_http_upstream_module
	Module ngx_http_upstream_conf_module
	Module ngx_http_upstream_hc_module
	Module ngx_http_userid_module
	Module ngx_http_uwsgi_module
	Module ngx_http_v2_module
2.57	Module ngx_http_xslt_module
Stro	eam server modules 383
3.1	Module ngx_stream_core_module
3.2	Module ngx_stream_access_module
3.3	Module ngx_stream_geo_module
3.4	Module ngx_stream_geoip_module
3.5	Module ngx_stream_js_module
3.6	Module ngx_stream_keyval_module
3.7	Module ngx_stream_limit_conn_module
3.8	Module ngx_stream_log_module
3.9	Module ngx_stream_map_module
3.10	Module ngx_stream_proxy_module
3.11	Module ngx_stream_realip_module

3

Nginx, Inc. p.4 of 506

CONTENTS

	3 19	Module ngx_stream_return_module	122
		Module ngx_stream_set_module	
		Module ngx_stream_split_clients_module	
		Module ngx_stream_ssl_module	
		Module ngx_stream_ssl_preread_module	
	3.17	Module ngx_stream_upstream_module	437
	3.18	Module ngx_stream_upstream_hc_module	445
	3.19	Module ngx_stream_zone_sync_module	449
4	Mai	l server modules	457
	4.1	Module ngx_mail_core_module	457
	4.2	Module ngx_mail_auth_http_module	
	4.3	Module ngx_mail_proxy_module	
	4.4	Module ngx_mail_realip_module	
	4.5	Module ngx_mail_ssl_module	
	4.6	Module ngx_mail_imap_module	
	4.0		
		Module ngx_mail_pop3_module	
	4.8	Module ngx_mail_smtp_module	481
5	Mis	cellaneous	483
	5.1	Command-line parameters	483
A	Cha	ngelog for NGINX Plus	485
В	Lega	al Notices	494
In	dex		499

Nginx, Inc. p.5 of 506

Chapter 1

Core modules

1.1 Core functionality

1.1.1	Example Configuration
1.1.2	Directives
	accept_mutex
	accept_mutex_delay
	daemon
	debug_connection
	debug_points 8
	env
	error_log
	events
	include
	load_module
	lock_file
	master_process
	multi_accept
	pcre_jit
	pid
	ssl_engine
	thread_pool
	timer_resolution
	use
	user
	worker_aio_requests
	worker_connections
	worker_cpu_affinity
	worker_priority
	worker_processes
	worker_rlimit_core
	worker_rlimit_nofile
	worker_shutdown_timeout
	working_directory

1.1.1 Example Configuration

```
user www www;
worker_processes 2;
error_log /var/log/nginx-error.log info;
events {
   use kqueue;
   worker_connections 2048;
}
...
```

1.1.2 Directives

$accept_mutex$

```
SYNTAX: accept_mutex on | off;

DEFAULT off

CONTEXT: events
```

If accept_mutex is enabled, worker processes will accept new connections by turn. Otherwise, all worker processes will be notified about new connections, and if volume of new connections is low, some of the worker processes may just waste system resources.

There is no need to enable accept_mutex on systems that support the EPOLLEXCLUSIVE flag (1.11.3) or when using reuseport.

Prior to version 1.11.3, the default value was on.

accept_mutex_delay

```
SYNTAX: accept_mutex_delay time;
DEFAULT 500ms
CONTEXT: events
```

If accept_mutex is enabled, specifies the maximum time during which a worker process will try to restart accepting new connections if another worker process is currently accepting new connections.

daemon

```
SYNTAX: daemon on | off;
Default on
Context: main
```

Determines whether nginx should become a daemon. Mainly used during development.

Nginx, Inc. p.7 of 506

debug_connection

```
SYNTAX: debug_connection address | CIDR | unix:; Default — Context: events
```

Enables debugging log for selected client connections. Other connections will use logging level set by the error_log directive. Debugged connections are specified by IPv4 or IPv6 (1.3.0, 1.2.1) address or network. A connection may also be specified using a hostname. For connections using UNIX-domain sockets (1.3.0, 1.2.1), debugging log is enabled by the "unix:" parameter.

```
events {
    debug_connection 127.0.0.1;
    debug_connection localhost;
    debug_connection 192.0.2.0/24;
    debug_connection ::1;
    debug_connection 2001:0db8::/32;
    debug_connection unix:;
    ...
}
```

For this directive to work, nginx needs to be built with --with-debug, see "A debugging log".

debug_points

```
SYNTAX: debug_points abort | stop;
DEFAULT —
CONTEXT: main
```

This directive is used for debugging.

When internal error is detected, e.g. the leak of sockets on restart of working processes, enabling debug_points leads to a core file creation (abort) or to stopping of a process (stop) for further analysis using a system debugger.

env

```
SYNTAX: env variable[=value];
DEFAULT TZ
CONTEXT: main
```

By default, nginx removes all environment variables inherited from its parent process except the TZ variable. This directive allows preserving some of the inherited variables, changing their values, or creating new environment variables. These variables are then:

- inherited during a live upgrade of an executable file;
- used by the ngx_http_perl_module module;

Nginx, Inc. p.8 of 506

• used by worker processes. One should bear in mind that controlling system libraries in this way is not always possible as it is common for libraries to check variables only during initialization, well before they can be set using this directive. An exception from this is an above mentioned live upgrade of an executable file.

The TZ variable is always inherited and available to the ngx_http_perl_module module, unless it is configured explicitly.

Usage example:

```
env MALLOC_OPTIONS;
env PERL5LIB=/data/site/modules;
env OPENSSL_ALLOW_PROXY_CERTS=1;
```

The NGINX environment variable is used internally by nginx and should not be set directly by the user.

error_log

SYNTAX: error_log file [level];
DEFAULT logs/error.log error

CONTEXT: main, http, mail, stream, server, location

Configures logging. Several logs can be specified on the same configuration level (1.5.2). If on the main configuration level writing a log to a file is not explicitly defined, the default file will be used.

The first parameter defines a *file* that will store the log.

The special value stderr selects the standard error file. Logging to syslog can be configured by specifying the "syslog:" prefix. Logging to a cyclic memory buffer can be configured by specifying the "memory:" prefix and buffer size, and is generally used for debugging (1.7.11).

The second parameter determines the *level* of logging, and can be one of the following: debug, info, notice, warn, error, crit, alert, or emerg. Log levels above are listed in the order of increasing severity. Setting a certain log level will cause all messages of the specified and more severe log levels to be logged. For example, the default level error will cause error, crit, alert, and emerg messages to be logged. If this parameter is omitted then error is used.

For debug logging to work, nginx needs to be built with --with-debug, see "A debugging log".

The directive can be specified on the stream level starting from version 1.7.11, and on the mail level starting from version 1.9.0.

Nginx, Inc. p.9 of 506

events

```
SYNTAX: events { ...}

DEFAULT —

CONTEXT: main
```

Provides the configuration file context in which the directives that affect connection processing are specified.

include

```
SYNTAX: include file | mask;

DEFAULT —

CONTEXT: any
```

Includes another *file*, or files matching the specified *mask*, into configuration. Included files should consist of syntactically correct directives and blocks.

Usage example:

```
include mime.types;
include vhosts/*.conf;
```

load_module

```
SYNTAX: load_module file;

DEFAULT —

CONTEXT: main
```

This directive appeared in version 1.9.11.

Loads a dynamic module.

Example:

```
load_module modules/ngx_mail_module.so;
```

lock_file

SYNTAX: lock_file;
DEFAULT logs/nginx.lock

Context: main

nginx uses the locking mechanism to implement accept_mutex and serialize access to shared memory. On most systems the locks are implemented using atomic operations, and this directive is ignored. On other systems the "lock file" mechanism is used. This directive specifies a prefix for the names of lock files.

Nginx, Inc. p.10 of 506

master_process

```
SYNTAX: master_process on | off;
DEFAULT on
CONTEXT: main
```

Determines whether worker processes are started. This directive is intended for nginx developers.

multi_accept

```
SYNTAX: multi_accept on | off;
Default off
Context: events
```

If multi_accept is disabled, a worker process will accept one new connection at a time. Otherwise, a worker process will accept all new connections at a time.

The directive is ignored if kqueue connection processing method is used, because it reports the number of new connections waiting to be accepted.

pcre_jit

```
SYNTAX: pcre_jit on | off;

Default off

Context: main

This directive appeared in version 1.1.12.
```

Enables or disables the use of "just-in-time compilation" (PCRE JIT) for the regular expressions known by the time of configuration parsing.

PCRE JIT can speed up processing of regular expressions significantly.

The JIT is available in PCRE libraries starting from version 8.20 built with the --enable-jit configuration parameter. When the PCRE library is built with nginx (--with-pcre=), the JIT support is enabled via the --with-pcre-jit configuration parameter.

pid

```
SYNTAX: pid file;
DEFAULT logs/nginx.pid
CONTEXT: main
```

Defines a *file* that will store the process ID of the main process.

ssl_engine

```
SYNTAX: ssl_engine device;

DEFAULT —

CONTEXT: main
```

Nginx, Inc. p.11 of 506

Defines the name of the hardware SSL accelerator.

$thread_pool$

SYNTAX: **thread_pool** name threads=number [max_queue=number];

DEFAULT default threads=32 max_queue=65536

Context: main

This directive appeared in version 1.7.11.

Defines the *name* and parameters of a thread pool used for multi-threaded reading and sending of files without blocking worker processes.

The threads parameter defines the number of threads in the pool.

In the event that all threads in the pool are busy, a new task will wait in the queue. The max_queue parameter limits the number of tasks allowed to be waiting in the queue. By default, up to 65536 tasks can wait in the queue. When the queue overflows, the task is completed with an error.

timer_resolution

SYNTAX: timer_resolution interval;

Default — Context: main

Reduces timer resolution in worker processes, thus reducing the number of gettimeofday system calls made. By default, gettimeofday is called each time a kernel event is received. With reduced resolution, gettimeofday is only called once per specified *interval*.

Example:

```
timer_resolution 100ms;
```

Internal implementation of the interval depends on the method used:

- the EVFILT_TIMER filter if kqueue is used;
- timer_create if eventport is used;
- setitimer otherwise.

use

SYNTAX: use method;

Default — Context: events

Specifies the connection processing *method* to use. There is normally no need to specify it explicitly, because nginx will by default use the most efficient method.

Nginx, Inc. p.12 of 506

user

SYNTAX: **user** user [group]; DEFAULT nobody nobody

Context: main

Defines *user* and *group* credentials used by worker processes. If *group* is omitted, a group whose name equals that of *user* is used.

worker_aio_requests

SYNTAX: worker_aio_requests number;

DEFAULT 32 CONTEXT: events

This directive appeared in versions 1.1.4 and 1.0.7.

When using alo with the epoll connection processing method, sets the maximum *number* of outstanding asynchronous I/O operations for a single worker process.

worker_connections

SYNTAX: worker_connections number;

DEFAULT 512 CONTEXT: events

Sets the maximum number of simultaneous connections that can be opened by a worker process.

It should be kept in mind that this number includes all connections (e.g. connections with proxied servers, among others), not only connections with clients. Another consideration is that the actual number of simultaneous connections cannot exceed the current limit on the maximum number of open files, which can be changed by worker_rlimit_nofile.

worker_cpu_affinity

```
SYNTAX: worker_cpu_affinity cpumask...;
SYNTAX: worker_cpu_affinity auto [cpumask];
DEFAULT —
```

Context: main

Binds worker processes to the sets of CPUs. Each CPU set is represented by a bitmask of allowed CPUs. There should be a separate set defined for each of the worker processes. By default, worker processes are not bound to any specific CPUs.

For example,

```
worker_processes 4;
worker_cpu_affinity 0001 0010 0100 1000;
```

binds each worker process to a separate CPU, while

Nginx, Inc. p.13 of 506

```
worker_processes 2;
worker_cpu_affinity 0101 1010;
```

binds the first worker process to CPU0/CPU2, and the second worker process to CPU1/CPU3. The second example is suitable for hyper-threading.

The special value auto (1.9.10) allows binding worker processes automatically to available CPUs:

```
worker_processes auto;
worker_cpu_affinity auto;
```

The optional mask parameter can be used to limit the CPUs available for automatic binding:

```
worker_cpu_affinity auto 01010101;
```

The directive is only available on FreeBSD and Linux.

worker_priority

SYNTAX: worker_priority number;

Default 0 Context: main

Defines the scheduling priority for worker processes like it is done by the nice command: a negative *number* means higher priority. Allowed range normally varies from -20 to 20.

Example:

```
worker_priority -10;
```

worker_processes

 ${\tt SYNTAX:} \quad \textbf{worker_processes} \ number \mid \texttt{auto};$

Default 1 Context: main

Defines the number of worker processes.

The optimal value depends on many factors including (but not limited to) the number of CPU cores, the number of hard disk drives that store data, and load pattern. When one is in doubt, setting it to the number of available CPU cores would be a good start (the value "auto" will try to autodetect it).

The auto parameter is supported starting from versions 1.3.8 and 1.2.5.

Nginx, Inc. p.14 of 506

worker rlimit core

SYNTAX: worker_rlimit_core size;

Default — Context: main

Changes the limit on the largest size of a core file (RLIMIT_CORE) for worker processes. Used to increase the limit without restarting the main process.

worker_rlimit_nofile

SYNTAX: worker_rlimit_nofile number;
DEFAULT —
CONTEXT: main

Changes the limit on the maximum number of open files (RLIMIT_NOFILE) for worker processes. Used to increase the limit without restarting the main process.

worker_shutdown_timeout

SYNTAX: worker_shutdown_timeout time;

Default — Context: main

This directive appeared in version 1.11.11.

Configures a timeout for a graceful shutdown of worker processes. When the *time* expires, nginx will try to close all the connections currently open to facilitate shutdown.

working_directory

SYNTAX: working_directory directory;

Default — Context: main

Defines the current working directory for a worker process. It is primarily used when writing a core-file, in which case a worker process should have write permission for the specified directory.

Nginx, Inc. p.15 of 506

1.2 Setting up hashes

1.2.1 Overview

To quickly process static sets of data such as server names, map directive's values, MIME types, names of request header strings, nginx uses hash tables. During the start and each re-configuration nginx selects the minimum possible sizes of hash tables such that the bucket size that stores keys with identical hash values does not exceed the configured parameter (hash bucket size). The size of a table is expressed in buckets. The adjustment is continued until the table size exceeds the hash max size parameter. Most hashes have the corresponding directives that allow changing these parameters, for example, for the server names hash they are server_names_hash_max_size and server_names_hash_bucket_size.

The hash bucket size parameter is aligned to the size that is a multiple of the processor's cache line size. This speeds up key search in a hash on modern processors by reducing the number of memory accesses. If hash bucket size is equal to one processor's cache line size then the number of memory accesses during the key search will be two in the worst case — first to compute the bucket address, and second during the key search inside the bucket. Therefore, if nginx emits the message requesting to increase either hash max size or hash bucket size then the first parameter should first be increased.

Nginx, Inc. p.16 of 506

1.3 Connection processing methods

1.3.1 Overview

nginx supports a variety of connection processing methods. The availability of a particular method depends on the platform used. On platforms that support several methods nginx will normally select the most efficient method automatically. However, if needed, a connection processing method can be selected explicitly with the use directive.

The following connection processing methods are supported:

- select standard method. The supporting module is built automatically on platforms that lack more efficient methods. The --with-select_module and --without-select_module configuration parameters can be used to forcibly enable or disable the build of this module.
- poll standard method. The supporting module is built automatically on platforms that lack more efficient methods. The --with-poll_module and --without-poll_module configuration parameters can be used to forcibly enable or disable the build of this module.
- kqueue efficient method used on FreeBSD 4.1+, OpenBSD 2.9+, NetBSD 2.0, and macOS.
- epol1 efficient method used on Linux 2.6+.

The EPOLLRDHUP (Linux 2.6.17, glibc 2.8) and EPOLLEXCLUSIVE (Linux 4.5, glibc 2.24) flags are supported since 1.11.3.

Some older distributions like SuSE 8.2 provide patches that add epoll support to 2.4 kernels.

- /dev/poll efficient method used on Solaris 7 11/99+, HP/UX 11.22+ (eventport), IRIX 6.5.15+, and Tru64 UNIX 5.1A+.
- eventport event ports, method used on Solaris 10+ (due to known issues, it is recommended using the /dev/poll method instead).

Nginx, Inc. p.17 of 506

1.4 Logging to syslog

1.4.1 Overview

The error_log and access_log directives support logging to syslog. The following parameters configure logging to syslog:

server=address

Defines the address of a syslog server. The address can be specified as a domain name or IP address, with an optional port, or as a UNIX-domain socket path specified after the "unix:" prefix. If port is not specified, the UDP port 514 is used. If a domain name resolves to several IP addresses, the first resolved address is used.

facility=string

Sets facility of syslog messages, as defined in RFC 3164. Facility can be one of "kern", "user", "mail", "daemon", "auth", "intern", "lpr", "news", "uucp", "clock", "authpriv", "ftp", "ntp", "audit", "alert", "cron", "local0". "local7". Default is "local7".

severity=string

Sets severity of syslog messages for access_log, as defined in RFC 3164. Possible values are the same as for the second parameter (level) of the error_log directive. Default is "info".

Severity of error messages is determined by nginx, thus the parameter is ignored in the error_log directive.

tag=string

Sets the tag of syslog messages. Default is "nginx".

nohostname

Disables adding the "hostname" field into the syslog message header (1.9.7).

Example syslog configuration:

```
error_log syslog:server=192.168.1.1 debug;
access_log syslog:server=unix:/var/log/nginx.sock,nohostname;
access_log syslog:server=[2001:db8::1]:12345,facility=local7,tag=nginx,severity =info combined;
```

Logging to syslog is available since version 1.7.1. As part of our commercial subscription logging to syslog is available since version 1.5.3.

Nginx, Inc. p.18 of 506

Chapter 2

HTTP server modules

${\bf 2.1}\quad Module\ ngx_http_core_module\\$

2.1.1	Directives
	absolute_redirect
	aio
	aio_write
	alias
	auth_delay
	chunked_transfer_encoding
	client_body_buffer_size
	client_body_in_file_only
	client_body_in_single_buffer
	client_body_temp_path
	client_body_timeout
	client_header_buffer_size
	client_header_timeout
	client_max_body_size
	connection_pool_size
	default_type
	directio
	directio_alignment
	disable_symlinks
	error_page
	etag
	http
	if_modified_since
	ignore_invalid_headers
	internal
	keepalive_disable
	keepalive_requests
	keepalive_time
	keepalive_timeout
	large_client_header_buffers

limit_except	32
$\operatorname{limit_rate}$	32
limit_rate_after	 33
lingering_close	 33
lingering_time	 34
${ m lingering_timeout}$	 34
listen	 35
location	38
$\log_{not_found} \dots \dots \dots \dots$	 39
$\log_{ ext{subrequest}}$	 40
max_ranges	 40
merge_slashes	 40
msie_padding	 41
msie_refresh	41
open_file_cache	 41
open_file_cache_errors	 42
open_file_cache_min_uses	 42
open_file_cache_valid	42
output_buffers	 42
port_in_redirect	 42
- postpone_output	43
read_ahead	43
recursive_error_pages	43
request_pool_size	43
reset_timedout_connection	43
resolver	44
resolver_timeout	 45
root	45
$\operatorname{satisfy}$	45
$\operatorname{send_lowat}$	46
send_timeout	46
$\operatorname{sendfile}$	46
sendfile_max_chunk	47
server	47
server_name	47
server_name_in_redirect	49
server_names_hash_bucket_size	49
server_names_hash_max_size	49
server_tokens	50
subrequest_output_buffer_size	50
tcp_nodelay	50
tcp_nopush	50
try_files	51
types	53
types_hash_bucket_size	53
types_hash_max_size	53
v, p ===================================	 -

Nginx, Inc. p.20 of 506

	underscores_in_headers									54
	variables_hash_bucket_size									54
	variables_hash_max_size .									54
2.1.2	Embedded Variables									54

2.1.1 Directives

absolute_redirect

```
SYNTAX: absolute_redirect on | off;
Default on
Context: http, server, location
This directive appeared in version 1.11.8.
```

If disabled, redirects issued by nginx will be relative.

See also server_name_in_redirect and port_in_redirect directives.

aio

```
SYNTAX: aio on | off | threads[=pool];
DEFAULT off
CONTEXT: http, server, location
This directive appeared in version 0.8.11.
```

Enables or disables the use of asynchronous file I/O (AIO) on FreeBSD and Linux:

```
location /video/ {
    aio         on;
    output_buffers 1 64k;
}
```

On FreeBSD, AIO can be used starting from FreeBSD 4.3. Prior to FreeBSD 11.0, AIO can either be linked statically into a kernel:

```
options VFS_AIO
```

or loaded dynamically as a kernel loadable module:

```
kldload aio
```

On Linux, AIO can be used starting from kernel version 2.6.22. Also, it is necessary to enable directio, or otherwise reading will be blocking:

On Linux, directio can only be used for reading blocks that are aligned on 512-byte boundaries (or 4K for XFS). File's unaligned end is read in blocking

Nginx, Inc. p.21 of 506

mode. The same holds true for byte range requests and for FLV requests not from the beginning of a file: reading of unaligned data at the beginning and end of a file will be blocking.

When both AIO and sendfile are enabled on Linux, AIO is used for files that are larger than or equal to the size specified in the directio directive, while sendfile is used for files of smaller sizes or when directio is disabled.

```
location /video/ {
   sendfile on;
   aio on;
   directio 8m;
}
```

Finally, files can be read and sent using multi-threading (1.7.11), without blocking a worker process:

```
location /video/ {
   sendfile on;
   aio threads;
}
```

Read and send file operations are offloaded to threads of the specified pool. If the pool name is omitted, the pool with the name "default" is used. The pool name can also be set with variables:

```
aio threads=pool$disk;
```

By default, multi-threading is disabled, it should be enabled with the --with-threads configuration parameter. Currently, multi-threading is compatible only with the epoll, kqueue, and eventport methods. Multi-threaded sending of files is only supported on Linux.

See also the sendfile directive.

aio_write

```
SYNTAX: aio_write on | off;
DEFAULT off
CONTEXT: http, server, location
This directive appeared in version 1.9.13.
```

If aio is enabled, specifies whether it is used for writing files. Currently, this only works when using aio threads and is limited to writing temporary files with data received from proxied servers.

alias

```
SYNTAX: alias path;
DEFAULT —
CONTEXT: location
```

Defines a replacement for the specified location. For example, with the following configuration

Nginx, Inc. p.22 of 506

```
location /i/ {
    alias /data/w3/images/;
}
```

on request of "/i/top.gif", the file /data/w3/images/top.gif will be sent.

The path value can contain variables, except $\$document_root$ and $\$realpath_root$.

If alias is used inside a location defined with a regular expression then such regular expression should contain captures and alias should refer to these captures (0.7.40), for example:

```
location ~ ^/users/(.+\.(?:gif|jpe?g|png))$ {
    alias /data/w3/images/$1;
}
```

When location matches the last part of the directive's value:

```
location /images/ {
    alias /data/w3/images/;
}
```

it is better to use the root directive instead:

```
location /images/ {
   root /data/w3;
}
```

auth_delay

```
SYNTAX: auth_delay time;
```

Default 0s

Context: http, server, location

This directive appeared in version 1.17.10.

Delays processing of unauthorized requests with 401 response code to prevent timing attacks when access is limited by password, by the result of subrequest, or by JWT.

chunked_transfer_encoding

```
SYNTAX: chunked_transfer_encoding on | off;
```

Default on

Context: http, server, location

Allows disabling chunked transfer encoding in HTTP/1.1. It may come in handy when using a software failing to support chunked encoding despite the standard's requirement.

Nginx, Inc. p.23 of 506

client_body_buffer_size

SYNTAX: client_body_buffer_size size;

Default 8k|16k

Context: http, server, location

Sets buffer size for reading client request body. In case the request body is larger than the buffer, the whole body or only its part is written to a temporary file. By default, buffer size is equal to two memory pages. This is 8K on x86, other 32-bit platforms, and x86-64. It is usually 16K on other 64-bit platforms.

client_body_in_file_only

SYNTAX: client_body_in_file_only on | clean | off;

Default off

Context: http, server, location

Determines whether nginx should save the entire client request body into a file. This directive can be used during debugging, or when using the \$request_body_file variable, or the \$r->request_body_file method of the module ngx_http_perl_module.

When set to the value on, temporary files are not removed after request processing.

The value clean will cause the temporary files left after request processing to be removed.

client_body_in_single_buffer

SYNTAX: client_body_in_single_buffer on | off;

Default off

Context: http, server, location

Determines whether nginx should save the entire client request body in a single buffer. The directive is recommended when using the *\$request_body* variable, to save the number of copy operations involved.

client_body_temp_path

SYNTAX: client_body_temp_path path [level1 [level2 [level3]]];

DEFAULT client_body_temp CONTEXT: http, server, location

Defines a directory for storing temporary files holding client request bodies. Up to three-level subdirectory hierarchy can be used under the specified directory. For example, in the following configuration

```
client_body_temp_path /spool/nginx/client_temp 1 2;
```

a path to a temporary file might look like this:

Nginx, Inc. p.24 of 506

/spool/nginx/client_temp/7/45/00000123457

client_body_timeout

 ${\tt SYNTAX:} \quad \textbf{client_body_timeout} \ time;$

DEFAULT 60s

Context: http, server, location

Defines a timeout for reading client request body. The timeout is set only for a period between two successive read operations, not for the transmission of the whole request body. If a client does not transmit anything within this time, the request is terminated with the 408 Request Time-out error.

client_header_buffer_size

SYNTAX: client_header_buffer_size size;

Default 1k

Context: http, server

Sets buffer size for reading client request header. For most requests, a buffer of 1K bytes is enough. However, if a request includes long cookies, or comes from a WAP client, it may not fit into 1K. If a request line or a request header field does not fit into this buffer then larger buffers, configured by the large_client_header_buffers directive, are allocated.

client_header_timeout

SYNTAX: client_header_timeout time;

Default 60s

CONTEXT: http, server

Defines a timeout for reading client request header. If a client does not transmit the entire header within this time, the request is terminated with the 408 Request Time-out error.

client_max_body_size

SYNTAX: client_max_body_size size;

Default 1m

Context: http, server, location

Sets the maximum allowed size of the client request body. If the size in a request exceeds the configured value, the 413 Request Entity Too Large error is returned to the client. Please be aware that browsers cannot correctly display this error. Setting *size* to 0 disables checking of client request body size.

Nginx, Inc. p.25 of 506

connection_pool_size

SYNTAX: connection_pool_size size;

DEFAULT 256 | 512 CONTEXT: http, server

Allows accurate tuning of per-connection memory allocations. This directive has minimal impact on performance and should not generally be used. By default, the size is equal to 256 bytes on 32-bit platforms and 512 bytes on 64-bit platforms.

Prior to version 1.9.8, the default value was 256 on all platforms.

$default_type$

SYNTAX: **default_type** *mime-type*;

DEFAULT text/plain

Context: http, server, location

Defines the default MIME type of a response. Mapping of file name extensions to MIME types can be set with the types directive.

directio

SYNTAX: **directio** *size* | off;

Default off

Context: http, server, location
This directive appeared in version 0.7.7.

Enables the use of the O_DIRECT flag (FreeBSD, Linux), the F_NOCACHE flag (macOS), or the directio function (Solaris), when reading files that are larger than or equal to the specified *size*. The directive automatically disables (0.7.15) the use of sendfile for a given request. It can be useful for serving large files:

```
directio 4m;
```

or when using aio on Linux.

directio_alignment

SYNTAX: directio alignment size;

Default 512

Context: http, server, location
This directive appeared in version 0.8.11.

Sets the alignment for directio. In most cases, a 512-byte alignment is enough. However, when using XFS under Linux, it needs to be increased to 4K.

Nginx, Inc. p.26 of 506

disable_symlinks

SYNTAX: **disable_symlinks** off;

SYNTAX: **disable_symlinks** on | if_not_owner [from=part];

Default off

Context: http, server, location
This directive appeared in version 1.1.15.

Determines how symbolic links should be treated when opening files:

off

Symbolic links in the pathname are allowed and not checked. This is the default behavior.

on

If any component of the pathname is a symbolic link, access to a file is denied.

```
if_not_owner
```

Access to a file is denied if any component of the pathname is a symbolic link, and the link and object that the link points to have different owners.

from=part

When checking symbolic links (parameters on and if_not_owner), all components of the pathname are normally checked. Checking of symbolic links in the initial part of the pathname may be avoided by specifying additionally the from=part parameter. In this case, symbolic links are checked only from the pathname component that follows the specified initial part. If the value is not an initial part of the pathname checked, the whole pathname is checked as if this parameter was not specified at all. If the value matches the whole file name, symbolic links are not checked. The parameter value can contain variables.

Example:

```
disable_symlinks on from=$document_root;
```

This directive is only available on systems that have the openat and fstatat interfaces. Such systems include modern versions of FreeBSD, Linux, and Solaris.

Parameters on and if_not_owner add a processing overhead.

On systems that do not support opening of directories only for search, to use these parameters it is required that worker processes have read permissions for all directories being checked.

The ngx_http_autoindex_module, ngx_http_random_index_module, and ngx_http_dav_module modules currently ignore this directive.

Nginx, Inc. p.27 of 506

error_page

```
SYNTAX: error_page code ... [=[response]] uri;
DEFAULT —
```

CONTEXT: http, server, location, if in location

Defines the URI that will be shown for the specified errors. A *uri* value can contain variables.

Example:

```
error_page 404 /404.html;
error_page 500 502 503 504 /50x.html;
```

This causes an internal redirect to the specified *uri* with the client request method changed to "GET" (for all methods other than "GET" and "HEAD").

Furthermore, it is possible to change the response code to another using the "=response" syntax, for example:

```
error_page 404 =200 /empty.gif;
```

If an error response is processed by a proxied server or a FastCGI/uwsgi/SCGI/gRPC server, and the server may return different response codes (e.g., 200, 302, 401 or 404), it is possible to respond with the code it returns:

```
error_page 404 = /404.php;
```

If there is no need to change URI and method during internal redirection it is possible to pass error processing into a named location:

```
location / {
    error_page 404 = @fallback;
}
location @fallback {
    proxy_pass http://backend;
}
```

If *uri* processing leads to an error, the status code of the last occurred error is returned to the client.

It is also possible to use URL redirects for error processing:

In this case, by default, the response code 302 is returned to the client. It can only be changed to one of the redirect status codes (301, 302, 303, 307, and 308).

Nginx, Inc. p.28 of 506

The code 307 was not treated as a redirect until versions 1.1.16 and 1.0.13.

The code 308 was not treated as a redirect until version 1.13.0.

These directives are inherited from the previous configuration level if and only if there are no error_page directives defined on the current level.

etag

```
SYNTAX: etag on | off;

DEFAULT on

CONTEXT: http, server, location

This directive appeared in version 1.3.3.
```

Enables or disables automatic generation of the ETag response header field for static resources.

http

```
SYNTAX: http { ... }
DEFAULT —
CONTEXT: main
```

Provides the configuration file context in which the HTTP server directives are specified.

if_modified_since

```
SYNTAX: if_modified_since off | exact | before;
DEFAULT exact
CONTEXT: http, server, location
This directive appeared in version 0.7.24.
```

Specifies how to compare modification time of a response with the time in the If-Modified-Since request header field:

```
off
the If-Modified-Since request header field is ignored (0.7.34);
exact
exact match;
before
modification time of a response is less than or equal to the time in the
If-Modified-Since request header field.
```

ignore_invalid_headers

```
SYNTAX: ignore_invalid_headers on | off;
DEFAULT on
CONTEXT: http, server
```

Nginx, Inc. p.29 of 506

Controls whether header fields with invalid names should be ignored. Valid names are composed of English letters, digits, hyphens, and possibly underscores (as controlled by the underscores_in_headers directive).

If the directive is specified on the server level, its value is only used if a server is a default one. The value specified also applies to all virtual servers listening on the same address and port.

internal

SYNTAX: internal;
DEFAULT —
CONTEXT: location

Specifies that a given location can only be used for internal requests. For external requests, the client error 404 Not Found is returned. Internal requests are the following:

- requests redirected by the error_page, index, random_index, and try_files directives;
- requests redirected by the X-Accel-Redirect response header field from an upstream server;
- subrequests formed by the "include virtual" command of the ngx_http_ssi_module module, by the ngx_http_addition_module module directives, and by auth_request and mirror directives;
- requests changed by the rewrite directive.

Example:

```
error_page 404 /404.html;
location = /404.html {
   internal;
}
```

There is a limit of 10 internal redirects per request to prevent request processing cycles that can occur in incorrect configurations. If this limit is reached, the error 500 Internal Server Error is returned. In such cases, the "rewrite or internal redirection cycle" message can be seen in the error log.

keepalive_disable

SYNTAX: **keepalive_disable** none | browser ...;

DEFAULT msie6

Context: http, server, location

Nginx, Inc. p.30 of 506

Disables keep-alive connections with misbehaving browsers. The browser parameters specify which browsers will be affected. The value msie6 disables keep-alive connections with old versions of MSIE, once a POST request is received. The value safari disables keep-alive connections with Safari and Safari-like browsers on macOS and macOS-like operating systems. The value none enables keep-alive connections with all browsers.

Prior to version 1.1.18, the value safari matched all Safari and Safarilike browsers on all operating systems, and keep-alive connections with them were disabled by default.

keepalive_requests

SYNTAX: keepalive_requests number;

Default 1000

Context: http, server, location
This directive appeared in version 0.8.0.

Sets the maximum number of requests that can be served through one keep-alive connection. After the maximum number of requests are made, the connection is closed.

Closing connections periodically is necessary to free per-connection memory allocations. Therefore, using too high maximum number of requests could result in excessive memory usage and not recommended.

Prior to version 1.19.10, the default value was 100.

keepalive_time

SYNTAX: **keepalive_time** *time*;

DEFAULT 1h

Context: http, server, location

This directive appeared in version 1.19.10.

Limits the maximum time during which requests can be processed through one keep-alive connection. After this time is reached, the connection is closed following the subsequent request processing.

keepalive_timeout

SYNTAX: **keepalive_timeout** [header_timeout];

Default 75s

Context: http, server, location

The first parameter sets a timeout during which a keep-alive client connection will stay open on the server side. The zero value disables keep-alive client connections. The optional second parameter sets a value in the Keep-Alive: timeout=time response header field. Two parameters may differ.

Nginx, Inc. p.31 of 506

The Keep-Alive: timeout=time header field is recognized by Mozilla and Konqueror. MSIE closes keep-alive connections by itself in about 60 seconds.

large_client_header_buffers

```
SYNTAX: large_client_header_buffers number size;
DEFAULT 4 8k
```

Context: http, server

Sets the maximum *number* and *size* of buffers used for reading large client request header. A request line cannot exceed the size of one buffer, or the 414 Request-URI Too Large error is returned to the client. A request header field cannot exceed the size of one buffer as well, or the 400 Bad Request error is returned to the client. Buffers are allocated only on demand. By default, the buffer size is equal to 8K bytes. If after the end of request processing a connection is transitioned into the keep-alive state, these buffers are released.

limit_except

```
SYNTAX: limit_except method ... { ... }

DEFAULT —

CONTEXT: location
```

Limits allowed HTTP methods inside a location. The *method* parameter can be one of the following: GET, HEAD, POST, PUT, DELETE, MKCOL, COPY, MOVE, OPTIONS, PROPFIND, PROPPATCH, LOCK, UNLOCK, or PATCH. Allowing the GET method makes the HEAD method also allowed. Access to other methods can be limited using the ngx_http_access_module, ngx_http_auth_basic_module, and ngx_http_auth_jwt_module (1.13.10) modules directives:

```
limit_except GET {
   allow 192.168.1.0/32;
   deny all;
}
```

Please note that this will limit access to all methods **except** GET and HEAD.

limit_rate

SYNTAX: limit_rate rate;

Default 0

Context: http, server, location, if in location

Limits the rate of response transmission to a client. The *rate* is specified in bytes per second. The zero value disables rate limiting.

The limit is set per a request, and so if a client simultaneously opens two connections, the overall rate will be twice as much as the specified limit.

Nginx, Inc. p.32 of 506

Parameter value can contain variables (1.17.0). It may be useful in cases where rate should be limited depending on a certain condition:

```
map $slow $rate {
    1    4k;
    2    8k;
}
limit_rate $rate;
```

Rate limit can also be set in the *\$limit_rate* variable, however, since version 1.17.0, this method is not recommended:

```
server {
    if ($slow) {
        set $limit_rate 4k;
    }
    ...
}
```

Rate limit can also be set in the X-Accel-Limit-Rate header field of a proxied server response. This capability can be disabled using the proxy_ignore_headers, fastcgi_ignore_headers, uwsgi_ignore_headers, and scgi_ignore_headers directives.

limit_rate_after

SYNTAX: limit_rate_after size;

Default 0

CONTEXT: http, server, location, if in location

This directive appeared in version 0.8.0.

Sets the initial amount after which the further transmission of a response to a client will be rate limited. Parameter value can contain variables (1.17.0). Example:

lingering_close

SYNTAX: lingering_close off | on | always;

Default on

Context: http, server, location

This directive appeared in versions 1.1.0 and 1.0.6.

Controls how nginx closes client connections.

Nginx, Inc. p.33 of 506

The default value "on" instructs nginx to wait for and process additional data from a client before fully closing a connection, but only if heuristics suggests that a client may be sending more data.

The value "always" will cause nginx to unconditionally wait for and process additional client data.

The value "off" tells nginx to never wait for more data and close the connection immediately. This behavior breaks the protocol and should not be used under normal circumstances.

To control closing HTTP/2 connections, the directive must be specified on the server level (1.19.1).

lingering_time

SYNTAX: lingering_time time;

DEFAULT 30s

Context: http, server, location

When lingering_close is in effect, this directive specifies the maximum time during which nginx will process (read and ignore) additional data coming from a client. After that, the connection will be closed, even if there will be more data.

lingering_timeout

 ${\tt SYNTAX:} \quad \textbf{lingering_timeout} \ time;$

DEFAULT 5s

Context: http, server, location

When lingering_close is in effect, this directive specifies the maximum waiting time for more client data to arrive. If data are not received during this time, the connection is closed. Otherwise, the data are read and ignored, and nginx starts waiting for more data again. The "wait-read-ignore" cycle is repeated, but no longer than specified by the lingering_time directive.

Nginx, Inc. p.34 of 506

listen

```
listen address[:port] [default_server] [ssl] [http2 | spdy]
          [proxy_protocol] [setfib=number] [fastopen=number]
          [backlog=number] [rcvbuf=size] [sndbuf=size]
          [accept_filter=filter] [deferred] [bind] [ipv6only=on|off]
          [reuseport] [so_keepalive=on|off|[keepidle]:[keepintvl]:[keepcnt]];
          listen port [default_server] [ssl] [http2 | spdy]
SYNTAX:
          [proxy_protocol] [setfib=number] [fastopen=number]
          [backlog=number] [rcvbuf=size] [sndbuf=size]
          [accept_filter=filter] [deferred] [bind] [ipv6only=on|off]
          [reuseport] [so_keepalive=on|off|[keepidle]:[keepintvl]:[keepcnt]];
SYNTAX:
          listen unix: path [default_server] [ssl] [http2 | spdy]
          [proxy_protocol] [backlog=number] [rcvbuf=size] [sndbuf=size]
          [accept_filter=filter] [deferred] [bind]
          [so_keepalive=on|off|[keepidle]:[keepintvl]:[keepcnt]];
DEFAULT *:80 | *:8000
Context: server
```

Sets the *address* and *port* for IP, or the *path* for a UNIX-domain socket on which the server will accept requests. Both *address* and *port*, or only *address* or only *port* can be specified. An *address* may also be a hostname, for example:

```
listen 127.0.0.1:8000;
listen 127.0.0.1;
listen 8000;
listen *:8000;
listen localhost:8000;
```

IPv6 addresses (0.7.36) are specified in square brackets:

```
listen [::]:8000;
listen [::1];
```

UNIX-domain sockets (0.8.21) are specified with the "unix:" prefix:

```
listen unix:/var/run/nginx.sock;
```

If only address is given, the port 80 is used.

If the directive is not present then either \star :80 is used if nginx runs with the superuser privileges, or \star :8000 otherwise.

The default_server parameter, if present, will cause the server to become the default server for the specified *address:port* pair. If none of the directives have the default_server parameter then the first server with the *address:port* pair will be the default server for this pair.

In versions prior to 0.8.21 this parameter is named simply default.

The ssl parameter (0.7.14) allows specifying that all connections accepted on this port should work in SSL mode. This allows for a more compact configuration for the server that handles both HTTP and HTTPS requests.

Nginx, Inc. p.35 of 506

The http2 parameter (1.9.5) configures the port to accept HTTP/2 connections. Normally, for this to work the ssl parameter should be specified as well, but nginx can also be configured to accept HTTP/2 connections without SSL.

The spdy parameter (1.3.15-1.9.4) allows accepting SPDY connections on this port. Normally, for this to work the ssl parameter should be specified as well, but nginx can also be configured to accept SPDY connections without SSL.

The proxy_protocol parameter (1.5.12) allows specifying that all connections accepted on this port should use the PROXY protocol.

The PROXY protocol version 2 is supported since version 1.13.11.

The listen directive can have several additional parameters specific to socket-related system calls. These parameters can be specified in any listen directive, but only once for a given *address:port* pair.

In versions prior to 0.8.21, they could only be specified in the listen directive together with the default parameter.

setfib=number

this parameter (0.8.44) sets the associated routing table, FIB (the SO_SETFIB option) for the listening socket. This currently works only on FreeBSD.

fastopen = number

enables "TCP Fast Open" for the listening socket (1.5.8) and limits the maximum length for the queue of connections that have not yet completed the three-way handshake.

Do not enable this feature unless the server can handle receiving the same SYN packet with data more than once.

backlog=number

sets the backlog parameter in the listen call that limits the maximum length for the queue of pending connections. By default, backlog is set to -1 on FreeBSD, DragonFly BSD, and macOS, and to 511 on other platforms.

rcvbuf=size

sets the receive buffer size (the SO_RCVBUF option) for the listening socket.

sndbuf=size

sets the send buffer size (the SO_SNDBUF option) for the listening socket.

accept filter=filter

sets the name of accept filter (the SO_ACCEPTFILTER option) for the listening socket that filters incoming connections before passing them to accept. This works only on FreeBSD and NetBSD 5.0+. Possible values are dataready and httpready.

Nginx, Inc. p.36 of 506

deferred

instructs to use a deferred accept (the TCP_DEFER_ACCEPT socket option) on Linux.

bind

instructs to make a separate bind call for a given address:port pair. This is useful because if there are several listen directives with the same port but different addresses, and one of the listen directives listens on all addresses for the given port (*:port), nginx will bind only to *:port. It should be noted that the getsockname system call will be made in this case to determine the address that accepted the connection. If the setfib, backlog, rcvbuf, sndbuf, accept_filter, deferred, ipv6only, or so_keepalive parameters are used then for a given address:port pair a separate bind call will always be made.

ipv6only=on|off

this parameter (0.7.42) determines (via the IPV6_V6ONLY socket option) whether an IPv6 socket listening on a wildcard address [::] will accept only IPv6 connections or both IPv6 and IPv4 connections. This parameter is turned on by default. It can only be set once on start.

Prior to version 1.3.4, if this parameter was omitted then the operating system's settings were in effect for the socket.

reuseport

this parameter (1.9.1) instructs to create an individual listening socket for each worker process (using the SO_REUSEPORT socket option on Linux 3.9+ and DragonFly BSD, or SO_REUSEPORT_LB on FreeBSD 12+), allowing a kernel to distribute incoming connections between worker processes. This currently works only on Linux 3.9+, DragonFly BSD, and FreeBSD 12+ (1.15.1).

Inappropriate use of this option may have its security implications.

so_keepalive=on|off|[keepidle]:[keepintvl]:[keepcnt]

this parameter (1.1.11) configures the "TCP keepalive" behavior for the listening socket. If this parameter is omitted then the operating system's settings will be in effect for the socket. If it is set to the value "on", the SO_KEEPALIVE option is turned on for the socket. If it is set to the value "off", the SO_KEEPALIVE option is turned off for the socket. Some operating systems support setting of TCP keepalive parameters on a per-socket basis using the TCP_KEEPIDLE, TCP_KEEPINTVL, and TCP_KEEPCNT socket options. On such systems (currently, Linux 2.4+, NetBSD 5+, and FreeBSD 9.0-STABLE), they can be configured using the keepidle, keepintvl, and keepcnt parameters. One or two parameters may be omitted, in which case the system default setting for the corresponding socket option will be in effect. For example,

so_keepalive=30m::10

Nginx, Inc. p.37 of 506

will set the idle timeout (TCP_KEEPIDLE) to 30 minutes, leave the probe interval (TCP_KEEPINTVL) at its system default, and set the probes count (TCP_KEEPCNT) to 10 probes.

Example:

```
listen 127.0.0.1 default_server accept_filter=dataready backlog=1024;
```

location

```
SYNTAX: location [ = | \sim | \sim * | ^{\sim} ] uri \{ ... \}
SYNTAX: location @ name \{ ... \}
DEFAULT —
CONTEXT: server, location
```

0011121111 0011011

Sets configuration depending on a request URI.

The matching is performed against a normalized URI, after decoding the text encoded in the "%XX" form, resolving references to relative path components "." and "..", and possible compression of two or more adjacent slashes into a single slash.

A location can either be defined by a prefix string, or by a regular expression. Regular expressions are specified with the preceding "~*" modifier (for case-insensitive matching), or the "~" modifier (for case-sensitive matching). To find location matching a given request, nginx first checks locations defined using the prefix strings (prefix locations). Among them, the location with the longest matching prefix is selected and remembered. Then regular expressions are checked, in the order of their appearance in the configuration file. The search of regular expressions terminates on the first match, and the corresponding configuration is used. If no match with a regular expression is found then the configuration of the prefix location remembered earlier is used.

location blocks can be nested, with some exceptions mentioned below.

For case-insensitive operating systems such as macOS and Cygwin, matching with prefix strings ignores a case (0.7.7). However, comparison is limited to one-byte locales.

Regular expressions can contain captures (0.7.40) that can later be used in other directives.

If the longest matching prefix location has the "^~" modifier then regular expressions are not checked.

Also, using the "=" modifier it is possible to define an exact match of URI and location. If an exact match is found, the search terminates. For example, if a "/" request happens frequently, defining "location = /" will speed up the processing of these requests, as search terminates right after the first comparison. Such a location cannot obviously contain nested locations.

Nginx, Inc. p.38 of 506

In versions from 0.7.1 to 0.8.41, if a request matched the prefix location without the "=" and "^~" modifiers, the search also terminated and regular expressions were not checked.

Let's illustrate the above by an example:

```
location = / {
    [ configuration A ]
}

location / {
    [ configuration B ]
}

location /documents/ {
    [ configuration C ]
}

location ^~ /images/ {
    [ configuration D ]
}

location ~* \.(gif|jpg|jpeg)$ {
    [ configuration E ]
}
```

The "/" request will match configuration A, the "/index.html" request will match configuration B, the "/documents/document.html" request will match configuration C, the "/images/1.gif" request will match configuration D, and the "/documents/1.jpg" request will match configuration E.

The "@" prefix defines a named location. Such a location is not used for a regular request processing, but instead used for request redirection. They cannot be nested, and cannot contain nested locations.

If a location is defined by a prefix string that ends with the slash character, and requests are processed by one of proxy_pass, fastcgi_pass, uwsgi_pass, scgi_pass, memcached_pass, or grpc_pass, then the special processing is performed. In response to a request with URI equal to this string, but without the trailing slash, a permanent redirect with the code 301 will be returned to the requested URI with the slash appended. If this is not desired, an exact match of the URI and location could be defined like this:

```
location /user/ {
    proxy_pass http://user.example.com;
}
location = /user {
    proxy_pass http://login.example.com;
}
```

log_not_found

```
SYNTAX: log_not_found on | off;
DEFAULT on
```

Context: http, server, location

Nginx, Inc. p.39 of 506

Enables or disables logging of errors about not found files into error_log.

log_subrequest

```
SYNTAX: log_subrequest on | off;
DEFAULT off
```

Context: http, server, location

Enables or disables logging of subrequests into access_log.

max_ranges

```
SYNTAX: max_ranges number;

Default —

Context: http, server, location

This directive appeared in version 1.1.2.
```

Limits the maximum allowed number of ranges in byte-range requests. Requests that exceed the limit are processed as if there were no byte ranges specified. By default, the number of ranges is not limited. The zero value disables the byte-range support completely.

merge_slashes

```
SYNTAX: merge_slashes on | off;
Default on
Context: http, server
```

Enables or disables compression of two or more adjacent slashes in a URI into a single slash.

Note that compression is essential for the correct matching of prefix string and regular expression locations. Without it, the "//scripts/one.php" request would not match

```
location /scripts/ {
    ...
}
```

and might be processed as a static file. So it gets converted to "/scripts/one.php".

Turning the compression off can become necessary if a URI contains base64-encoded names, since base64 uses the "/" character internally. However, for security considerations, it is better to avoid turning the compression off.

If the directive is specified on the server level, its value is only used if a server is a default one. The value specified also applies to all virtual servers listening on the same address and port.

Nginx, Inc. p.40 of 506

msie_padding

```
SYNTAX: msie_padding on | off;
```

Default on

Context: http, server, location

Enables or disables adding comments to responses for MSIE clients with status greater than 400 to increase the response size to 512 bytes.

msie_refresh

SYNTAX: msie_refresh on | off;

Default off

Context: http, server, location

Enables or disables issuing refreshes instead of redirects for MSIE clients.

open_file_cache

```
SYNTAX: open_file_cache off;
```

SYNTAX: **open_file_cache** max=N [inactive=time];

Default off

CONTEXT: http, server, location

Configures a cache that can store:

- open file descriptors, their sizes and modification times;
- information on existence of directories;
- file lookup errors, such as "file not found", "no read permission", and so on.

Caching of errors should be enabled separately by the open_file_cache_errors directive.

The directive has the following parameters:

max

sets the maximum number of elements in the cache; on cache overflow the least recently used (LRU) elements are removed;

inactive

defines a time after which an element is removed from the cache if it has not been accessed during this time; by default, it is 60 seconds;

off

disables the cache.

Example:

Nginx, Inc. p.41 of 506

open_file_cache_errors

Syntax: open_file_cache_errors on | off;

Default off

Context: http, server, location

Enables or disables caching of file lookup errors by open_file_cache.

open_file_cache_min_uses

SYNTAX: open_file_cache_min_uses number;

Default 1

Context: http, server, location

Sets the minimum *number* of file accesses during the period configured by the inactive parameter of the open_file_cache directive, required for a file descriptor to remain open in the cache.

open_file_cache_valid

SYNTAX: open_file_cache_valid time;

DEFAULT 60s

Context: http, server, location

Sets a time after which open_file_cache elements should be validated.

output_buffers

SYNTAX: output_buffers number size;

Default 2 32k

Context: http, server, location

Sets the *number* and *size* of the buffers used for reading a response from a disk.

Prior to version 1.9.5, the default value was 1 32k.

port_in_redirect

SYNTAX: port_in_redirect on | off;

Default on

Context: http, server, location

Enables or disables specifying the port in absolute redirects issued by nginx. The use of the primary server name in redirects is controlled by the server_-

name_in_redirect directive.

Nginx, Inc. p.42 of 506

postpone_output

SYNTAX: postpone_output size;

Default 1460

Context: http, server, location

If possible, the transmission of client data will be postponed until nginx has at least *size* bytes of data to send. The zero value disables postponing data transmission.

read_ahead

SYNTAX: read_ahead size;

Default 0

CONTEXT: http, server, location

Sets the amount of pre-reading for the kernel when working with file.

On Linux, the posix_fadvise(0, 0, 0, POSIX_FADV_SEQUENTIAL) system call is used, and so the *size* parameter is ignored.

On FreeBSD, the fcntl (O_READAHEAD, *size*) system call, supported since FreeBSD 9.0-CURRENT, is used. FreeBSD 7 has to be patched.

recursive_error_pages

SYNTAX: recursive_error_pages on | off;

Default off

Context: http, server, location

Enables or disables doing several redirects using the error_page directive. The number of such redirects is limited.

request_pool_size

SYNTAX: request_pool_size size;

Default 4k

Context: http, server

Allows accurate tuning of per-request memory allocations. This directive has minimal impact on performance and should not generally be used.

$reset_timedout_connection$

SYNTAX: reset_timedout_connection on | off;

Default off

Context: http, server, location

Enables or disables resetting timed out connections and connections closed with the non-standard code 444 (1.15.2). The reset is performed as follows. Before closing a socket, the SO_LINGER option is set on it with a timeout value of 0. When the socket is closed, TCP RST is sent to the client, and

Nginx, Inc. p.43 of 506

all memory occupied by this socket is released. This helps avoid keeping an already closed socket with filled buffers in a FIN_WAIT1 state for a long time.

It should be noted that timed out keep-alive connections are closed normally.

resolver

```
SYNTAX: resolver address ... [valid=time] [ipv6=on|off] [status_zone=zone];

DEFAULT —

CONTEXT: http, server, location
```

Configures name servers used to resolve names of upstream servers into addresses, for example:

```
resolver 127.0.0.1 [::1]:5353;
```

The address can be specified as a domain name or IP address, with an optional port (1.3.1, 1.2.2). If port is not specified, the port 53 is used. Name servers are queried in a round-robin fashion.

Before version 1.1.7, only a single name server could be configured. Specifying name servers using IPv6 addresses is supported starting from versions 1.3.1 and 1.2.2.

By default, nginx will look up both IPv4 and IPv6 addresses while resolving. If looking up of IPv6 addresses is not desired, the ipv6=off parameter can be specified.

Resolving of names into IPv6 addresses is supported starting from version 1.5.8.

By default, nginx caches answers using the TTL value of a response. An optional valid parameter allows overriding it:

```
resolver 127.0.0.1 [::1]:5353 valid=30s;
```

Before version 1.1.9, tuning of caching time was not possible, and nginx always cached answers for the duration of 5 minutes.

To prevent DNS spoofing, it is recommended configuring DNS servers in a properly secured trusted local network.

The optional status_zone parameter (1.17.1) enables collection of DNS server statistics of requests and responses in the specified *zone*. The parameter is available as part of our commercial subscription.

Nginx, Inc. p.44 of 506

resolver_timeout

SYNTAX: resolver_timeout time;

DEFAULT 30s

CONTEXT: http, server, location

Sets a timeout for name resolution, for example:

```
resolver_timeout 5s;
```

root

SYNTAX: root path;
DEFAULT html

CONTEXT: http, server, location, if in location

Sets the root directory for requests. For example, with the following configuration

```
location /i/ {
   root /data/w3;
}
```

The /data/w3/i/top.gif file will be sent in response to the "/i/top.gif" request.

The path value can contain variables, except $\$document_root$ and $\$realpath_root$.

A path to the file is constructed by merely adding a URI to the value of the root directive. If a URI has to be modified, the alias directive should be used.

satisfy

SYNTAX: **satisfy** all | any;

Default all

Context: http, server, location

Allows access if all (all) or at least one (any) of the ngx_http_access_module, ngx_http_auth_basic_module, ngx_http_auth_request_module, or ngx_http_auth_jwt_module modules allow access.

Example:

```
location / {
    satisfy any;

allow 192.168.1.0/32;
    deny all;

auth_basic     "closed site";
    auth_basic_user_file conf/htpasswd;
}
```

Nginx, Inc. p.45 of 506

send lowat

SYNTAX: send_lowat size;

Default 0

CONTEXT: http, server, location

If the directive is set to a non-zero value, nginx will try to minimize the number of send operations on client sockets by using either NOTE_LOWAT flag of the kqueue method or the SO_SNDLOWAT socket option. In both cases the specified *size* is used.

This directive is ignored on Linux, Solaris, and Windows.

send_timeout

SYNTAX: send_timeout *time*;

DEFAULT 60s

Context: http, server, location

Sets a timeout for transmitting a response to the client. The timeout is set only between two successive write operations, not for the transmission of the whole response. If the client does not receive anything within this time, the connection is closed.

sendfile

SYNTAX: **sendfile** on | off;

Default off

Context: http, server, location, if in location

Enables or disables the use of sendfile.

Starting from nginx 0.8.12 and FreeBSD 5.2.1, aio can be used to pre-load data for sendfile:

In this configuration, sendfile is called with the SF_NODISKIO flag which causes it not to block on disk I/O, but, instead, report back that the data are not in memory. nginx then initiates an asynchronous data load by reading one byte. On the first read, the FreeBSD kernel loads the first 128K bytes of a file into memory, although next reads will only load data in 16K chunks. This can be changed using the read_ahead directive.

Before version 1.7.11, pre-loading could be enabled with all send-file; \cdot

Nginx, Inc. p.46 of 506

sendfile max chunk

SYNTAX: sendfile_max_chunk size;

Default 0

Context: http, server, location

When set to a non-zero value, limits the amount of data that can be transferred in a single sendfile call. Without the limit, one fast connection may seize the worker process entirely.

server

```
SYNTAX: server { ... }

DEFAULT —

CONTEXT: http
```

Sets configuration for a virtual server. There is no clear separation between IP-based (based on the IP address) and name-based (based on the Host request header field) virtual servers. Instead, the listen directives describe all addresses and ports that should accept connections for the server, and the server_name directive lists all server names. Example configurations are provided in the "How nginx processes a request" document.

server_name

```
SYNTAX: server_name name ...;

DEFAULT ""

CONTEXT: server
```

Sets names of a virtual server, for example:

```
server {
    server_name example.com www.example.com;
}
```

The first name becomes the primary server name.

Server names can include an asterisk (" \star ") replacing the first or last part of a name:

```
server {
    server_name example.com *.example.com www.example.*;
}
```

Such names are called wildcard names.

The first two of the names mentioned above can be combined in one:

```
server {
   server_name .example.com;
}
```

It is also possible to use regular expressions in server names, preceding the name with a tilde (" \sim "):

Nginx, Inc. p.47 of 506

```
server {
    server_name www.example.com ~^www\d+\.example\.com$;
}
```

Regular expressions can contain captures (0.7.40) that can later be used in other directives:

```
server {
    server_name ~^(www\.)?(.+)$;

    location / {
        root /sites/$2;
    }
}
server {
    server_name _;
    location / {
        root /sites/default;
    }
}
```

Named captures in regular expressions create variables (0.8.25) that can later be used in other directives:

```
server {
    server_name ~^(www\.)?(?<domain>.+)$;

    location / {
        root /sites/$domain;
    }
}

server {
    server_name _;
    location / {
        root /sites/default;
    }
}
```

If the directive's parameter is set to "\$hostname" (0.9.4), the machine's hostname is inserted.

It is also possible to specify an empty server name (0.7.11):

```
server {
   server_name www.example.com "";
}
```

It allows this server to process requests without the Host header field — instead of the default server — for the given address:port pair. This is the default setting.

Before 0.8.48, the machine's hostname was used by default.

During searching for a virtual server by name, if the name matches more than one of the specified variants, (e.g. both a wildcard name and regular

Nginx, Inc. p.48 of 506

expression match), the first matching variant will be chosen, in the following order of priority:

- 1. the exact name
- 2. the longest wildcard name starting with an asterisk, e.g. "*.example.com"
- 3. the longest wildcard name ending with an asterisk, e.g. "mail.*"
- 4. the first matching regular expression (in order of appearance in the configuration file)

Detailed description of server names is provided in a separate Server names document.

server_name_in_redirect

SYNTAX: server name in redirect on | off;

Default off

Context: http, server, location

Enables or disables the use of the primary server name, specified by the server_name directive, in absolute redirects issued by nginx. When the use of the primary server name is disabled, the name from the Host request header field is used. If this field is not present, the IP address of the server is used.

The use of a port in redirects is controlled by the port_in_redirect directive.

server_names_hash_bucket_size

SYNTAX: server_names_hash_bucket_size size;

DEFAULT 32 | 64 | 128

Context: http

Sets the bucket size for the server names hash tables. The default value depends on the size of the processor's cache line. The details of setting up hash tables are provided in a separate document.

server_names_hash_max_size

SYNTAX: server_names_hash_max_size size;

DEFAULT 512 CONTEXT: http

Sets the maximum *size* of the server names hash tables. The details of setting up hash tables are provided in a separate document.

Nginx, Inc. p.49 of 506

server tokens

SYNTAX: server_tokens on | off | build | string;

Default on

Context: http, server, location

Enables or disables emitting nginx version on error pages and in the Server response header field.

The build parameter (1.11.10) enables emitting a build name along with nginx version.

Additionally, as part of our commercial subscription, starting from version 1.9.13 the signature on error pages and the Server response header field value can be set explicitly using the *string* with variables. An empty string disables the emission of the Server field.

subrequest_output_buffer_size

SYNTAX: subrequest_output_buffer_size size;

Default 4k|8k

Context: http, server, location

This directive appeared in version 1.13.10.

Sets the *size* of the buffer used for storing the response body of a subrequest. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform. It can be made smaller, however.

The directive is applicable only for subrequests with response bodies saved into memory. For example, such subrequests are created by SSI.

tcp_nodelay

SYNTAX: tcp_nodelay on | off;

Default on

Context: http, server, location

Enables or disables the use of the TCP_NODELAY option. The option is enabled when a connection is transitioned into the keep-alive state. Additionally, it is enabled on SSL connections, for unbuffered proxying, and for WebSocket proxying.

tcp_nopush

SYNTAX: tcp_nopush on | off;

Default off

Context: http, server, location

Enables or disables the use of the TCP_NOPUSH socket option on FreeBSD or the TCP_CORK socket option on Linux. The options are enabled only when sendfile is used. Enabling the option allows

• sending the response header and the beginning of a file in one packet, on Linux and FreeBSD 4.*;

Nginx, Inc. p.50 of 506

• sending a file in full packets.

try_files

```
SYNTAX: try_files file ... uri;
SYNTAX: try_files file ... = code;
DEFAULT —
CONTEXT: server, location
```

Checks the existence of files in the specified order and uses the first found file for request processing; the processing is performed in the current context. The path to a file is constructed from the *file* parameter according to the root and alias directives. It is possible to check directory's existence by specifying a slash at the end of a name, e.g. "\$uri/". If none of the files were found, an internal redirect to the *uri* specified in the last parameter is made. For example:

```
location /images/ {
    try_files $uri /images/default.gif;
}
location = /images/default.gif {
    expires 30s;
}
```

The last parameter can also point to a named location, as shown in examples below. Starting from version 0.7.51, the last parameter can also be a *code*:

```
location / {
    try_files $uri $uri/index.html $uri.html =404;
}
```

Example in proxying Mongrel:

Example for Drupal/FastCGI:

```
location / {
    try_files $uri $uri/ @drupal;
}
location ~ \.php$ {
    try_files $uri @drupal;
    fastcgi_pass ...;
    fastcgi_param SCRIPT_FILENAME /path/to$fastcgi_script_name;
```

Nginx, Inc. p.51 of 506

In the following example,

```
location / {
    try_files $uri $uri/ @drupal;
}
```

the try_files directive is equivalent to

```
location / {
    error_page 404 = @drupal;
    log_not_found off;
}
```

And here,

```
location ~ \.php$ {
    try_files $uri @drupal;
    fastcgi_pass ...;
    fastcgi_param SCRIPT_FILENAME /path/to$fastcgi_script_name;
    ...
}
```

try_files checks the existence of the PHP file before passing the request to the FastCGI server.

Example for Wordpress and Joomla:

```
location / {
    try_files $uri $uri/ @wordpress;
}

location ~ \.php$ {
    try_files $uri @wordpress;

    fastcgi_pass ...;

    fastcgi_param SCRIPT_FILENAME /path/to$fastcgi_script_name;
    ... other fastcgi_param's
}

location @wordpress {
    fastcgi_pass ...;

    fastcgi_param SCRIPT_FILENAME /path/to/index.php;
    ... other fastcgi_param's
```

Nginx, Inc. p.52 of 506

```
[ }
```

types

```
SYNTAX: types { ...}

DEFAULT text/html html; image/gif gif; image/jpeg jpg;

CONTEXT: http, server, location
```

Maps file name extensions to MIME types of responses. Extensions are case-insensitive. Several extensions can be mapped to one type, for example:

```
types {
   application/octet-stream bin exe dll;
   application/octet-stream deb;
   application/octet-stream dmg;
}
```

A sufficiently full mapping table is distributed with nginx in the $conf/\neg$ mime.types file.

To make a particular location emit the "application/octet-stream" MIME type for all requests, the following configuration can be used:

```
location /download/ {
   types { }
   default_type application/octet-stream;
}
```

types_hash_bucket_size

```
SYNTAX: types_hash_bucket_size size;
DEFAULT 64
CONTEXT: http, server, location
```

Sets the bucket size for the types hash tables. The details of setting up hash tables are provided in a separate document.

Prior to version 1.5.13, the default value depended on the size of the processor's cache line.

types_hash_max_size

```
SYNTAX: types_hash_max_size size;
DEFAULT 1024
CONTEXT: http, server, location
```

Sets the maximum *size* of the types hash tables. The details of setting up hash tables are provided in a separate document.

Nginx, Inc. p.53 of 506

underscores in headers

SYNTAX: underscores_in_headers on | off;

Default off Context: http, server

Enables or disables the use of underscores in client request header fields. When the use of underscores is disabled, request header fields whose names contain underscores are marked as invalid and become subject to the ignore—invalid headers directive.

If the directive is specified on the server level, its value is only used if a server is a default one. The value specified also applies to all virtual servers listening on the same address and port.

variables_hash_bucket_size

SYNTAX: variables_hash_bucket_size size;

DEFAULT 64 CONTEXT: http

Sets the bucket size for the variables hash table. The details of setting up hash tables are provided in a separate document.

variables_hash_max_size

SYNTAX: variables_hash_max_size size;

DEFAULT 1024 CONTEXT: http

Sets the maximum *size* of the variables hash table. The details of setting up hash tables are provided in a separate document.

Prior to version 1.5.13, the default value was 512.

2.1.2 Embedded Variables

The ngx_http_core_module module supports embedded variables with names matching the Apache Server variables. First of all, these are variables representing client request header fields, such as \$http_user_agent, \$http_cookie, and so on. Also there are other variables:

 $\$arg_name$

argument name in the request line

\$args

arguments in the request line

 $$binary_remote_addr$

client address in a binary form, value's length is always 4 bytes for IPv4 addresses or 16 bytes for IPv6 addresses

Nginx, Inc. p.54 of 506

```
\$body\_bytes\_sent
```

number of bytes sent to a client, not counting the response header; this variable is compatible with the "%B" parameter of the mod_log_config Apache module

\$bytes_sent

number of bytes sent to a client (1.3.8, 1.2.5)

\$connection

connection serial number (1.3.8, 1.2.5)

 $$connection_requests$

current number of requests made through a connection (1.3.8, 1.2.5)

\$connection_time

connection time in seconds with a milliseconds resolution (1.19.10)

 $$content_length$

Content-Length request header field

\$content_type

Content-Type request header field

 $$cookie_name$$

the *name* cookie

 $\$document_root$

root or alias directive's value for the current request

\$document_uri

same as \$uri

\$host

in this order of precedence: host name from the request line, or host name from the Host request header field, or the server name matching a request

\$hostname

host name

\$http_name

arbitrary request header field; the last part of a variable name is the field name converted to lower case with dashes replaced by underscores

\$https

"on" if connection operates in SSL mode, or an empty string otherwise $\$is_args$

"?" if a request line has arguments, or an empty string otherwise $\$limit_rate$

setting this variable enables response rate limiting; see limit_rate \$msec

current time in seconds with the milliseconds resolution (1.3.9, 1.2.6)

 $nginx_version$

nginx version

\$pid

PID of the worker process

\$pipe

"p" if request was pipelined, "." otherwise (1.3.12, 1.2.7)

Nginx, Inc. p.55 of 506

$proxy_protocol_addr$

client address from the PROXY protocol header (1.5.12)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

$proxy_protocol_port$

client port from the PROXY protocol header (1.11.0)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

$\$proxy_protocol_server_addr$

server address from the PROXY protocol header (1.17.6)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

\$proxy_protocol_server_port

server port from the PROXY protocol header (1.17.6)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

\$query_string

same as \$args

$\$realpath_root$

an absolute pathname corresponding to the root or alias directive's value for the current request, with all symbolic links resolved to real paths

$\$remote_addr$

client address

\$remote_port

client port

\$remote_user

user name supplied with the Basic authentication

\$request

full original request line

\$request_body

request body

The variable's value is made available in locations processed by the proxy_pass, fastcgi_pass, uwsgi_pass, and scgi_pass directives when the request body was read to a memory buffer.

\$request_body_file

name of a temporary file with the request body

At the end of processing, the file needs to be removed. To always write the request body to a file, client_body_in_file_only needs to be enabled. When the name of a temporary file is passed in a proxied request or in a request to a FastCGI/uwsgi/SCGI server, passing the request body should be disabled by the proxy_pass_request_body off, fastcgi_pass_request_body off, uwsgi_pass_request_body off, or scgi_pass_request_body off directives, respectively.

$\$reguest_completion$

"OK" if a request has completed, or an empty string otherwise

Nginx, Inc. p.56 of 506

\$request_filename

file path for the current request, based on the root or alias directives, and the request URI

\$request_id

unique request identifier generated from 16 random bytes, in hexadecimal (1.11.0)

\$request_length

request length (including request line, header, and request body) (1.3.12, 1.2.7)

 $request_method$

request method, usually "GET" or "POST"

\$request_time

request processing time in seconds with a milliseconds resolution (1.3.9, 1.2.6); time elapsed since the first bytes were read from the client

\$request_uri

full original request URI (with arguments)

\$scheme

request scheme, "http" or "https"

 $\$sent_http_name$

arbitrary response header field; the last part of a variable name is the field name converted to lower case with dashes replaced by underscores

\$sent_trailer_name

arbitrary field sent at the end of the response (1.13.2); the last part of a variable name is the field name converted to lower case with dashes replaced by underscores

 $\$server_addr$

an address of the server which accepted a request

Computing a value of this variable usually requires one system call. To avoid a system call, the listen directives must specify addresses and use the bind parameter.

\$server_name

name of the server which accepted a request

\$server_port

port of the server which accepted a request

\$server_protocol

request protocol, usually "HTTP/1.0", "HTTP/1.1", or "HTTP/2.0"

\$status

response status (1.3.2, 1.2.2)

\$tcpinfo_rtt, \$tcpinfo_rttvar, \$tcpinfo_snd_cwnd, \$tcpinfo_rcv_space information about the client TCP connection; available on systems that support the TCP_INFO socket option

 $$time_iso8601$

local time in the ISO 8601 standard format (1.3.12, 1.2.7)

 $$time_local$$

local time in the Common Log Format (1.3.12, 1.2.7)

Nginx, Inc. p.57 of 506

\$uri

current URI in request, normalized

The value of *\$uri* may change during request processing, e.g. when doing internal redirects, or when using index files.

Nginx, Inc. p.58 of 506

2.2 Module ngx_http_access_module

2.2.1	Summary	59
2.2.2	Example Configuration	59
2.2.3	Directives	59
	allow	59
	denv	59

2.2.1 Summary

The ngx_http_access_module module allows limiting access to certain client addresses.

Access can also be limited by password, by the result of subrequest, or by JWT. Simultaneous limitation of access by address and by password is controlled by the satisfy directive.

2.2.2 Example Configuration

```
location / {
    deny 192.168.1.1;
    allow 192.168.1.0/24;
    allow 10.1.1.0/16;
    allow 2001:0db8::/32;
    deny all;
}
```

The rules are checked in sequence until the first match is found. In this example, access is allowed only for IPv4 networks 10.1.1.0/16 and 192.168.1.0/24 excluding the address 192.168.1.1, and for IPv6 network 2001:0db8::/32. In case of a lot of rules, the use of the ngx_http_geo_module module variables is preferable.

2.2.3 Directives

allow

```
SYNTAX: allow address | CIDR | unix: | all; DEFAULT — CONTEXT: http, server, location, limit_except
```

Allows access for the specified network or address. If the special value unix: is specified (1.5.1), allows access for all UNIX-domain sockets.

deny

```
SYNTAX: deny address | CIDR | unix: | all;
DEFAULT —
CONTEXT: http, server, location, limit_except
```

Nginx, Inc. p.59 of 506

Denies access for the specified network or address. If the special value unix: is specified (1.5.1), denies access for all UNIX-domain sockets.

Nginx, Inc. p.60 of 506

2.3 Module ngx_http_addition_module

2.3.1	Summary	61
2.3.2	Example Configuration	61
2.3.3	Directives	61
	add_before_body	61
	add_after_body	61
	addition_types	62

2.3.1 Summary

The ngx_http_addition_module module is a filter that adds text before and after a response. This module is not built by default, it should be enabled with the --with-http_addition_module configuration parameter.

2.3.2 Example Configuration

```
location / {
   add_before_body /before_action;
   add_after_body /after_action;
}
```

2.3.3 Directives

add_before_body

```
SYNTAX: add_before_body uri;
DEFAULT —
CONTEXT: http, server, location
```

Adds the text returned as a result of processing a given subrequest before the response body. An empty string ("") as a parameter cancels addition inherited from the previous configuration level.

add_after_body

```
SYNTAX: add_after_body uri;

DEFAULT —

CONTEXT: http, server, location
```

Adds the text returned as a result of processing a given subrequest after the response body. An empty string ("") as a parameter cancels addition inherited from the previous configuration level.

Nginx, Inc. p.61 of 506

$addition_types$

SYNTAX: addition_types mime-type ...;

DEFAULT text/html

Context: http, server, location
This directive appeared in version 0.7.9.

Allows adding text in responses with the specified MIME types, in addition to "text/html". The special value " \star " matches any MIME type (0.8.29).

Nginx, Inc. p.62 of 506

2.4 Module ngx_http_api_module

2.4.1	Summary	63
2.4.2	Example Configuration	63
2.4.3	Directives	64
	api	64
	status_zone	65
2.4.4	Compatibility	65
2.4.5	Endpoints	66
2.4.6	Response Objects	88

2.4.1 Summary

The ngx_http_api_module module (1.13.3) provides REST API for accessing various status information, configuring upstream server groups on-the-fly, and managing key-value pairs without the need of reconfiguring nginx.

The module supersedes the ngx_http_status_module and ngx_http_upstream_conf_module modules.

When using the PATCH or POST methods, make sure that the payload does not exceed the buffer size for reading the client request body, otherwise, the 413 Request Entity Too Large error may be returned.

This module is available as part of our commercial subscription.

2.4.2 Example Configuration

```
http {
    upstream backend {
        zone http_backend 64k;

        server backend1.example.com weight=5;
        server backend2.example.com;
    }

    proxy_cache_path /data/nginx/cache_backend keys_zone=cache_backend:10m;

    server {
        server_name backend.example.com;

        location / {
            proxy_pass http://backend;
            proxy_cache cache_backend;

            health_check;
        }

        status_zone server_backend;
    }

    keyval_zone zone=one:32k state=one.keyval;
    keyval_sarg_text $text zone=one;
```

Nginx, Inc. p.63 of 506

```
server {
        listen 127.0.0.1;
        location /api {
           api write=on;
            allow 127.0.0.1;
            deny all;
stream {
    upstream backend {
        zone stream_backend 64k;
        server backend1.example.com:12345 weight=5;
        server backend2.example.com:12345;
    server {
                  127.0.0.1:12345;
       listen
       proxy_pass backend;
        status_zone server_backend;
       health_check;
```

All API requests include a supported API version in the URI. Examples of API requests with this configuration:

```
http://127.0.0.1/api/6/
http://127.0.0.1/api/6/nginx
http://127.0.0.1/api/6/connections
http://127.0.0.1/api/6/http/requests
http://127.0.0.1/api/6/http/server_zones/server_backend
http://127.0.0.1/api/6/http/caches/cache_backend
http://127.0.0.1/api/6/http/upstreams/backend
http://127.0.0.1/api/6/http/upstreams/backend/servers/
http://127.0.0.1/api/6/http/upstreams/backend/servers/
http://127.0.0.1/api/6/http/upstreams/backend/servers/1
http://127.0.0.1/api/6/http/keyvals/one?key=arg1
http://127.0.0.1/api/6/stream/
http://127.0.0.1/api/6/stream/server_zones/server_backend
http://127.0.0.1/api/6/stream/upstreams/
http://127.0.0.1/api/6/stream/upstreams/backend
http://127.0.0.1/api/6/stream/upstreams/backend
```

2.4.3 Directives

api

```
SYNTAX: api [write=on|off];
DEFAULT —
CONTEXT: location
```

Turns on the REST API interface in the surrounding location. Access to this location should be limited.

The write parameter determines whether the API is read-only or readwrite. By default, the API is read-only.

All API requests should contain a supported API version in the URI. If the request URI equals the location prefix, the list of supported API versions

Nginx, Inc. p.64 of 506

is returned. The current API version is "6".

The optional "fields" argument in the request line specifies which fields of the requested objects will be output:

```
http://127.0.0.1/api/6/nginx?fields=version,build
```

status_zone

SYNTAX: status_zone zone;

Default —

CONTEXT: server, location, if in location This directive appeared in version 1.13.12.

Enables collection of virtual http or stream server status information in the specified *zone*. Several servers may share the same zone.

Starting from 1.17.0, status information can be collected per location. The special value off disables statistics collection in nested location blocks. Note that the statistics is collected in the context of a location where processing ends. It may be different from the original location, if an internal redirect happens during request processing.

2.4.4 Compatibility

- The /stream/limit_conns/ data were added in version 6.
- The /http/limit_conns/ data were added in version 6.
- The /http/limit_reqs/ data were added in version 6.
- The "expire" parameter of a key-value pair can be set or changed since version 5.
- The /resolvers/ data were added in version 5.
- The /http/location_zones/ data were added in version 5.
- The path and method fields of nginx error object were removed in version 4. These fields continue to exist in earlier api versions, but show an empty value.
- The /stream/zone_sync/ data were added in version 3.
- The drain parameter was added in version 2.
- The /stream/keyvals/ data were added in version 2.

Nginx, Inc. p.65 of 506

2.4.5 Endpoints

Supported methods:

• GET - Return list of root endpoints

Returns a list of root endpoints.

Possible responses:

- 200 Success, returns an array of strings
- 404 Unknown version (Unknown Version), returns Error

/nginx

Supported methods:

• GET - Return status of nginx running instance

Returns nginx version, build name, address, number of configuration reloads, IDs of master and worker processes.

Request parameters:

```
fields (string, optional)
```

Limits which fields of nginx running instance will be output.

Possible responses:

- 200 Success, returns nginx
- 404 Unknown version (UnknownVersion), returns Error

/processes

Supported methods:

• GET - Return nginx processes status

Returns the number of abnormally terminated and respawned child processes.

Possible responses:

- 200 Success, returns Processes
- 404 Unknown version (Unknown Version), returns Error

DELETE - Reset nginx processes statistics

Resets counters of abnormally terminated and respawned child processes.

Possible responses:

- 204 Success
 - 404 Unknown version (Unknown Version), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/connections

Supported methods:

Nginx, Inc. p.66 of 506

• GET - Return client connections statistics

Returns statistics of client connections.

Request parameters:

fields (string, optional)

Limits which fields of the connections statistics will be output.

Possible responses:

- 200 Success, returns Connections
- 404 Unknown version (Unknown Version), returns Error

DELETE - Reset client connections statistics

Resets statistics of accepted and dropped client connections.

Possible responses:

- 204 Success
 - 404 Unknown version (Unknown Version), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/slabs/

Supported methods:

• GET - Return status of all slabs

Returns status of slabs for each shared memory zone with slab allocator.

Request parameters:

```
fields (string, optional)
```

Limits which fields of slab zones will be output. If the "fields" value is empty, then only zone names will be output.

Possible responses:

- 200 Success, returns a collection of "Shared memory zone with slab allocator" objects for all slabs
- 404 Unknown version (Unknown Version), returns Error

/slabs/{slabZoneName}

Parameters common for all methods:

```
slabZoneName (string, required)
```

The name of the shared memory zone with slab allocator.

Supported methods:

• GET - Return status of a slab

Returns status of slabs for a particular shared memory zone with slab allocator.

Request parameters:

```
fields (string, optional)
```

Limits which fields of the slab zone will be output.

Nginx, Inc. p.67 of 506

Possible responses:

- 200 Success, returns Shared memory zone with slab allocator
- 404 Slab not found (SlabNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset slab statistics

Resets the "reqs" and "fails" metrics for each memory slot.

Possible responses:

- 204 Success
 - 404 Slab not found (SlabNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/

Supported methods:

• GET - Return list of HTTP-related endpoints Returns a list of first level HTTP endpoints.

Possible responses:

- 200 Success, returns an array of strings
- 404 Unknown version (UnknownVersion), returns Error

/http/requests

Supported methods:

• GET - Return HTTP requests statistics

Returns status of client HTTP requests.

Request parameters:

fields (string, optional)

Limits which fields of client HTTP requests statistics will be output.

Possible responses:

- 200 Success, returns HTTP Requests
- 404 Unknown version (Unknown Version), returns Error

DELETE - Reset HTTP requests statistics

Resets the number of total client HTTP requests.

Possible responses:

- 204 Success
 - 404 Unknown version (Unknown Version), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/server_zones/

Supported methods:

Nginx, Inc. p.68 of 506

• GET - Return status of all HTTP server zones

Returns status information for each HTTP server zone.

Request parameters:

fields (string, optional)

Limits which fields of server zones will be output. If the "fields" value is empty, then only server zone names will be output.

Possible responses:

- 200 Success, returns a collection of "HTTP Server Zone" objects for all HTTP server zones
- 404 Unknown version (UnknownVersion), returns Error

/http/server_zones/{httpServerZoneName}

Parameters common for all methods:

httpServerZoneName (string, required)

The name of an HTTP server zone.

Supported methods:

 $\bullet\,$ GET - Return status of an HTTP server zone

Returns status of a particular HTTP server zone.

Request parameters:

fields (string, optional)

Limits which fields of the server zone will be output.

Possible responses:

- 200 Success, returns HTTP Server Zone
- 404 Server zone not found (ServerZoneNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset statistics for an HTTP server zone

Resets statistics of accepted and discarded requests, responses, received and sent bytes in a particular HTTP server zone.

Possible responses:

- 204 Success
 - 404 Server zone not found (ServerZoneNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/location_zones/

Supported methods:

• GET - Return status of all HTTP location zones Returns status information for each HTTP location zone. Request parameters:

Nginx, Inc. p.69 of 506

fields (string, optional)

Limits which fields of location zones will be output. If the "fields" value is empty, then only zone names will be output.

Possible responses:

- 200 Success, returns a collection of "HTTP Location Zone" objects for all HTTP location zones
- 404 Unknown version (Unknown Version), returns Error

/http/location_zones/{httpLocationZoneName}

Parameters common for all methods:

httpLocationZoneName (string, required)

The name of an HTTP location zone.

Supported methods:

• GET - Return status of an HTTP location zone

Returns status of a particular HTTP location zone.

Request parameters:

fields (string, optional)

Limits which fields of the location zone will be output.

Possible responses:

- 200 Success, returns HTTP Location Zone
- 404 Location zone not found (LocationZoneNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset statistics for a location zone.

Resets statistics of accepted and discarded requests, responses, received and sent bytes in a particular location zone.

Possible responses:

- - 204 Success
 - 404 Location zone not found (LocationZoneNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/caches/

Supported methods:

• GET - Return status of all caches

Returns status of each cache configured by proxy_cache_path and other "*_cache_path" directives.

Request parameters:

fields (string, optional)

Limits which fields of cache zones will be output. If the "fields" value is empty, then only names of cache zones will be output.

Nginx, Inc. p.70 of 506

Possible responses:

- 200 Success, returns a collection of "HTTP Cache" objects for all HTTP caches
- 404 Unknown version (UnknownVersion), returns Error

/http/caches/{httpCacheZoneName}

Parameters common for all methods:

httpCacheZoneName (string, required)

The name of the cache zone.

Supported methods:

• GET - Return status of a cache

Returns status of a particular cache.

Request parameters:

fields (string, optional)

Limits which fields of the cache zone will be output.

Possible responses:

- 200 Success, returns HTTP Cache
- 404 Cache not found (CacheNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset cache statistics

Resets statistics of cache hits/misses in a particular cache zone.

Possible responses:

- 204 Success
 - 404 Cache not found (CacheNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/limit_conns/

Supported methods:

• GET - Return status of all HTTP limit_conn zones

Returns status information for each HTTP limit_conn zone.

Request parameters:

fields (string, optional)

Limits which fields of limit_conn zones will be output. If the "fields" value is empty, then only zone names will be output.

Possible responses:

- 200 Success, returns a collection of "HTTP Connections Limiting" objects for all HTTP limit conns
- 404 Unknown version (Unknown Version), returns Error

Nginx, Inc. p.71 of 506

/http/limit_conns/{httpLimitConnZoneName}

Parameters common for all methods:

httpLimitConnZoneName (string, required)

The name of a limit_conn zone.

Supported methods:

• GET - Return status of an HTTP limit_conn zone Returns status of a particular HTTP limit_conn zone.

Request parameters:

fields (string, optional)

Limits which fields of the <u>limit_conn</u> zone will be output.

Possible responses:

- 200 Success, returns HTTP Connections Limiting
- 404 limit_conn not found (LimitConnNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset statistics for an HTTP limit_conn zone

Resets the connection limiting statistics.

Possible responses:

- 204 Success
 - 404 limit_conn not found (LimitConnNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/limit_reqs/

Supported methods:

• GET - Return status of all HTTP limit_req zones

Returns status information for each HTTP limit_reg zone.

Request parameters:

```
fields (string, optional)
```

Limits which fields of limit_req zones will be output. If the "fields" value is empty, then only zone names will be output.

Possible responses:

- 200 Success, returns a collection of "HTTP Requests Rate Limiting" objects for all HTTP limit regs
- 404 Unknown version (Unknown Version), returns Error

/http/limit_regs/{httpLimitRegZoneName}

Parameters common for all methods:

httpLimitRegZoneName (string, required)

The name of a limit_req zone.

Supported methods:

Nginx, Inc. p.72 of 506

• GET - Return status of an HTTP limit_req zone Returns status of a particular HTTP limit_req zone.

Request parameters:

fields (string, optional)

Limits which fields of the <u>limit_req</u> zone will be output.

Possible responses:

- 200 Success, returns HTTP Requests Rate Limiting
- 404 limit_req not found (LimitReqNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset statistics for an HTTP limit_req zone

Resets the requests limiting statistics.

Possible responses:

- 204 Success
 - 404 limit_req not found (LimitReqNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/upstreams/

Supported methods:

• GET - Return status of all HTTP upstream server groups Returns status of each HTTP upstream server group and its servers. Request parameters:

fields (string, optional)

Limits which fields of upstream server groups will be output. If the "fields" value is empty, only names of upstreams will be output.

Possible responses:

- $-\,$ 200 Success, returns a collection of "HTTP Upstream" objects for all HTTP upstreams
- 404 Unknown version (Unknown Version), returns Error

/http/upstreams/{httpUpstreamName}/

Parameters common for all methods:

httpUpstreamName (string, required)

The name of an HTTP upstream server group.

Supported methods:

 GET - Return status of an HTTP upstream server group Returns status of a particular HTTP upstream server group and its servers.

Request parameters:

Nginx, Inc. p.73 of 506

fields (string, optional)

Limits which fields of the upstream server group will be output.

Possible responses:

- 200 Success, returns HTTP Upstream
- 400 Upstream is static (UpstreamStatic), returns Error
- 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error

DELETE - Reset statistics of an HTTP upstream server group

Resets the statistics for each upstream server in an upstream server group and queue statistics.

Possible responses:

- - 204 Success
 - 400 Upstream is static (UpstreamStatic), returns Error
 - 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/http/upstreams/{httpUpstreamName}/servers/

Parameters common for all methods:

httpUpstreamName (string, required)

The name of an upstream server group.

Supported methods:

• GET - Return configuration of all servers in an HTTP upstream server group

Returns configuration of each server in a particular HTTP upstream server group.

Possible responses:

- 200 Success, returns an array of HTTP Upstream Servers
- 400 Upstream is static (UpstreamStatic), returns Error
- 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error

POST - Add a server to an HTTP upstream server group

Adds a new server to an HTTP upstream server group. Server parameters are specified in the JSON format.

Request parameters:

postHttpUpstreamServer (HTTP Upstream Server, required)

Address of a new server and other optional parameters in the JSON format. The "ID", "backup", and "service" parameters cannot be changed.

Possible responses:

Nginx, Inc. p.74 of 506

- 201 Created, returns HTTP Upstream Server
- 400 Upstream is static (UpstreamStatic), invalid "parameter" value (UpstreamConfFormatError), missing "server" argument (UpstreamConfFormatError), un $known\ parameter\ "name"\ ({\tt UpstreamConfFormatError}),$ nested object or list (UpstreamConfFormatError), "error" while parsing (UpstreamBadAddress), have service upstream "host" may not (UpstreamBadAddress), service upstream "host" requires domain name (UpstreamBadAddress), invalid "weight" (UpstreamBadWeight), invalid conns" (UpstreamBadMaxConns), invalid "max_fails" "fail timeout" (UpstreamBadMaxFails), invalid (UpstreamBadFailTimeout), "slow_start" invalid (UpstreamBadSlowStart), reading request body failed BodyReadError), route is too long (UpstreamBadRoute), "service" is empty (UpstreamBadService), no resolver defined to resolve (UpstreamConfNoResolver), upstream "name" has no backup (UpstreamNoBackup), upstream "name" memory exhausted (UpstreamOutOfMemory), returns Error
- 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error
- 405 Method disabled (MethodDisabled), returns Error
- 409 Entry exists (EntryExists), returns Error
- 415 JSON error (JsonError), returns Error

/http/upstreams/{httpUpstreamName}/servers/
 {httpUpstreamServerId}

Parameters common for all methods:

httpUpstreamName (string, required)

The name of the upstream server group.

httpUpstreamServerId (string, required)

The ID of the server.

Supported methods:

• GET - Return configuration of a server in an HTTP upstream server group

Returns configuration of a particular server in the HTTP upstream server group.

Possible responses:

- 200 Success, returns HTTP Upstream Server
- 400 Upstream is static (UpstreamStatic), invalid server ID (UpstreamBadServerId), returns Error

Nginx, Inc. p.75 of 506

Server with "id" -404ID does exist not (UpstreamServerNotFound), unknown verupstream (UnknownVersion), not found (UpstreamNotFound), returns Error

PATCH - Modify a server in an HTTP upstream server group Modifies settings of a particular server in an HTTP upstream server group. Server parameters are specified in the JSON format. Request parameters:

- patchHttpUpstreamServer (HTTP Upstream Server, required)
 Server parameters, specified in the JSON format. The "ID", "backup", and "service" parameters cannot be changed.
 Possible responses:
 - 200 Success, returns HTTP Upstream Server
 - 400 Upstream is static (UpstreamStatic), invalid "parameter" value (UpstreamConfFormatError), known parameter "name" (UpstreamConfFormatError), nested object or list (UpstreamConfFormatError), "error" while parsing (UpstreamBadAddress), "server" valid argument (UpstreamBadAddress), (UpstreamBadServerId), invalid server ID invalid "weight" "max -(UpstreamBadWeight), invalid (UpstreamBadMaxConns), invalid "max_fails" (UpstreamBadMaxFails), invalid "fail timeout" (UpstreamBadFailTimeout), invalid "slow_start" (UpstreamBadSlowStart), reading request body failed BodyReadError), route is too long (UpstreamBadRoute), "service" is empty (UpstreamBadService), server "ID" address is immutable (UpstreamServerImmutable), server "ID" weight is immutable (UpstreamServerWeightImmutable), upstream "name" memory exhausted (UpstreamOutOfMemory), returns Error
 - 404 Server with ID "id" does not exist (UpstreamServerNotFound), unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error
 - 405 Method disabled (MethodDisabled), returns Error
 - 415 JSON error (JsonError), returns Error

DELETE - Remove a server from an HTTP upstream server group Removes a server from an HTTP upstream server group. Possible responses:

• - 200 - Success, returns an array of HTTP Upstream Servers

Nginx, Inc. p.76 of 506

- 400 Upstream is static (UpstreamStatic), invalid server ID (UpstreamBadServerId), server "id" not removable (UpstreamServerImmutable), returns Error
- 404 Server with ID "id" does not exist
 (UpstreamServerNotFound), unknown version (UnknownVersion), upstream not found
 (UpstreamNotFound), returns Error
- 405 Method disabled (MethodDisabled), returns Error

/http/keyvals/

Supported methods:

GET - Return key-value pairs from all HTTP keyval zones
 Returns key-value pairs for each HTTP keyval shared memory zone.
 Request parameters:

fields (string, optional)

If the "fields" value is empty, then only HTTP keyval zone names will be output.

Possible responses:

- 200 Success, returns a collection of "HTTP Keyval Shared Memory Zone" objects for all HTTP keyvals
- 404 Unknown version (UnknownVersion), returns Error

/http/keyvals/{httpKeyvalZoneName}

Parameters common for all methods:

httpKeyvalZoneName (string, required)

The name of an HTTP keyval shared memory zone.

Supported methods:

GET - Return key-value pairs from an HTTP keyval zone
 Returns key-value pairs stored in a particular HTTP keyval shared memory zone.

Request parameters:

key (string, optional)

Get a particular key-value pair from the HTTP keyval zone.

Possible responses:

- 200 Success, returns HTTP Keyval Shared Memory Zone
- 404 Keyval not found (KeyvalNotFound), keyval key not found (KeyvalKeyNotFound), unknown version (UnknownVersion), returns Error

POST - Add a key-value pair to the HTTP keyval zone

Adds a new key-value pair to the HTTP keyval shared memory zone. Several key-value pairs can be entered if the HTTP keyval shared memory zone is empty.

Nginx, Inc. p.77 of 506

Request parameters:

• Key-value (HTTP Keyval Shared Memory Zone, required)

A key-value pair is specified in the JSON format. Several key-value pairs can be entered if the HTTP keyval shared memory zone is empty. Expiration time in milliseconds can be specified for a key-value pair with the expire parameter which overrides the timeout parameter of the keyval_zone directive.

Possible responses:

- 201 Created
- 400 Invalid JSON (KeyvalFormatError), invalid key format (KeyvalFormatError), key required (KeyvalFormatError), keyval timeout is not enabled (KeyvalFormatError), only one key can be added (KeyvalFormatError), reading request body failed BodyReadError), returns Error
- 404 Keyval not found (KeyvalNotFound), unknown version (UnknownVersion), returns Error
- 405 Method disabled (MethodDisabled), returns Error
- 409 Entry exists (EntryExists), key already exists (KeyvalKeyExists), returns Error
- 413 Request Entity Too Large, returns Error
- 415 JSON error (JsonError), returns Error

PATCH - Modify a key-value or delete a key

Changes the value of the selected key in the key-value pair, deletes a key by setting the key value to null, changes expiration time of a key-value pair. If synchronization of keyval zones in a cluster is enabled, deletes a key only on a target cluster node. Expiration time in milliseconds can be specified for a key-value pair with the expire parameter which overrides the timeout parameter of the keyval_zone directive.

Request parameters:

• httpKeyvalZoneKeyValue (HTTP Keyval Shared Memory Zone, required)

A new value for the key is specified in the JSON format.

Possible responses:

- 204 Success
- 400 Invalid JSON (KeyvalFormatError), key required (KeyvalFormatError), keyval timeout is not enabled (KeyvalFormatError), only one key can be updated (KeyvalFormatError), reading request body failed BodyReadError), returns Error
- 404 Keyval not found (KeyvalNotFound), keyval key not found (KeyvalKeyNotFound), unknown version (UnknownVersion), returns Error

Nginx, Inc. p.78 of 506

- 405 Method disabled (MethodDisabled), returns Error
- 413 Request Entity Too Large, returns Error
- 415 JSON error (JsonError), returns Error

DELETE - Empty the HTTP keyval zone

Deletes all key-value pairs from the HTTP keyval shared memory zone. If synchronization of keyval zones in a cluster is enabled, empties the keyval zone only on a target cluster node.

Possible responses:

- 204 Success
 - 404 Keyval not found (KeyvalNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/stream/

Supported methods:

- GET Return list of stream-related endpoints Returns a list of first level stream endpoints.
 - Possible responses:
 - 200 Success, returns an array of strings
 - 404 Unknown version (Unknown Version), returns Error

/stream/server_zones/

Supported methods:

• GET - Return status of all stream server zones

Returns status information for each stream server zone.

Request parameters:

fields (string, optional)

Limits which fields of server zones will be output. If the "fields" value is empty, then only server zone names will be output.

Possible responses:

- 200 Success, returns a collection of "Stream Server Zone" objects for all stream server zones
- 404 Unknown version (Unknown Version), returns Error

/stream/server_zones/{streamServerZoneName}

Parameters common for all methods:

streamServerZoneName (string, required)

The name of a stream server zone.

Supported methods:

Nginx, Inc. p.79 of 506

• GET - Return status of a stream server zone

Returns status of a particular stream server zone.

Request parameters:

fields (string, optional)

Limits which fields of the server zone will be output.

Possible responses:

- 200 Success, returns Stream Server Zone
- 404 Server zone not found (ServerZoneNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset statistics for a stream server zone

Resets statistics of accepted and discarded connections, sessions, received and sent bytes in a particular stream server zone.

Possible responses:

- 204 Success
 - 404 Server zone not found (ServerZoneNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/stream/limit_conns/

Supported methods:

• GET - Return status of all stream limit_conn zones Returns status information for each stream limit_conn zone. Request parameters:

```
fields (string, optional)
```

Limits which fields of limit_conn zones will be output. If the "fields" value is empty, then only zone names will be output.

Possible responses:

- 200 Success, returns a collection of "Stream Connections Limiting" objects for all stream limit conns
- 404 Unknown version (Unknown Version), returns Error

/stream/limit conns/{streamLimitConnZoneName}

Parameters common for all methods:

streamLimitConnZoneName (string, required)

The name of a limit_conn zone.

Supported methods:

• GET - Return status of an stream limit_conn zone Returns status of a particular stream limit_conn zone. Request parameters:

```
fields (string, optional)
```

Limits which fields of the limit_conn zone will be output.

Nginx, Inc. p.80 of 506

Possible responses:

- 200 Success, returns Stream Connections Limiting
- 404 limit_conn not found (LimitConnNotFound), unknown version (UnknownVersion), returns Error

DELETE - Reset statistics for a stream limit_conn zone

Resets the connection limiting statistics.

Possible responses:

- 204 Success
 - 404 limit_conn not found (LimitConnNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/stream/upstreams/

Supported methods:

• GET - Return status of all stream upstream server groups Returns status of each stream upstream server group and its servers. Request parameters:

```
fields (string, optional)
```

Limits which fields of upstream server groups will be output. If the "fields" value is empty, only names of upstreams will be output.

Possible responses:

- 200 Success, returns a collection of "Stream Upstream" objects for all stream upstreams
- 404 Unknown version (Unknown Version), returns Error

/stream/upstreams/{streamUpstreamName}/

Parameters common for all methods:

streamUpstreamName (string, required)

The name of a stream upstream server group.

Supported methods:

 GET - Return status of a stream upstream server group
 Returns status of a particular stream upstream server group and its servers.

Request parameters:

```
fields (string, optional)
```

Limits which fields of the upstream server group will be output.

Possible responses:

- 200 Success, returns Stream Upstream
- 400 Upstream is static (UpstreamStatic), returns Error

Nginx, Inc. p.81 of 506

- 404 - Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error

DELETE - Reset statistics of a stream upstream server group Resets the statistics for each upstream server in an upstream server group.

Possible responses:

- - 204 Success
 - 400 Upstream is static (UpstreamStatic), returns Error
 - 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/stream/upstreams/{streamUpstreamName}/servers/ Parameters common for all methods:

 $\verb|streamUpstreamName| (string, required)|$

The name of an upstream server group.

Supported methods:

• GET - Return configuration of all servers in a stream upstream server group

Returns configuration of each server in a particular stream upstream server group.

Possible responses:

- 200 Success, returns an array of Stream Upstream Servers
- 400 Upstream is static (UpstreamStatic), returns Error
- 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error

POST - Add a server to a stream upstream server group

Adds a new server to a stream upstream server group. Server parameters are specified in the JSON format.

Request parameters:

• postStreamUpstreamServer (Stream Upstream Server, required)

Address of a new server and other optional parameters in the JSON format. The "ID", "backup", and "service" parameters cannot be changed.

Possible responses:

- 201 Created, returns Stream Upstream Server
- 400 Upstream is static (UpstreamStatic), invalid "parameter" value (UpstreamConfFormatError), missing "server" argument (UpstreamConfFormatError), unknown parameter "name" (UpstreamConfFormatError),

Nginx, Inc. p.82 of 506

nested object or list(UpstreamConfFormatError), "error" while parsing (UpstreamBadAddress), "host" no port server (UpstreamBadAddress), upstream "host." may not have service (UpstreamBadAddress), service upstream "host" requires domain name (UpstreamBadAddress), "weight" (UpstreamBadWeight), invalid "max conns" (UpstreamBadMaxConns), invalid "max_-"fail fails" (UpstreamBadMaxFails), invalid timeout" (UpstreamBadFailTimeout), invalid "slow start" (UpstreamBadSlowStart), "service" is empty (UpstreamBadService), no resolver defined to resolve (UpstreamConfNoResolver), upstream "name" has no backup (UpstreamNoBackup), upstream "name" memory exhausted (UpstreamOutOfMemory), reading request body failed BodyReadError), returns Error

- 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), returns Error
- 405 Method disabled (MethodDisabled), returns Error
- 409 Entry exists (EntryExists), returns Error
- 415 JSON error (JsonError), returns Error

/stream/upstreams/{streamUpstreamName}/servers/
 {streamUpstreamServerId}

Parameters common for all methods:

streamUpstreamName (string, required)

The name of the upstream server group.

streamUpstreamServerId (string, required)

The ID of the server.

Supported methods:

• GET - Return configuration of a server in a stream upstream server group

Returns configuration of a particular server in the stream upstream server group.

Possible responses:

- 200 Success, returns Stream Upstream Server
- 400 Upstream is static (UpstreamStatic), invalid server
 ID (UpstreamBadServerId), returns Error
- 404 Unknown version (UnknownVersion), upstream not found (UpstreamNotFound), server with ID "id" does not exist (UpstreamServerNotFound), returns Error

PATCH - Modify a server in a stream upstream server group Modifies settings of a particular server in a stream upstream server group. Server parameters are specified in the JSON format.

Nginx, Inc. p.83 of 506

Request parameters:

• patchStreamUpstreamServer (Stream Upstream Server, required)

Server parameters, specified in the JSON format. The "ID", "backup", and "service" parameters cannot be changed.

Possible responses:

- 200 Success, returns Stream Upstream Server
- 400 Upstream is static (UpstreamStatic), invalid "parameter" value (UpstreamConfFormatError), known parameter "name" (UpstreamConfFormatError), nested object or list (UpstreamConfFormatError), "error" while parsing (UpstreamBadAddress), in-"server" argument (UpstreamBadAddress), "host" (UpstreamBadAddress), no port in server invalid server ID (UpstreamBadServerId), invalid "weight" (UpstreamBadWeight), invalid "max -(UpstreamBadMaxConns), conns" invalid "max -"fail_fails" (UpstreamBadMaxFails), invalid timeout" (UpstreamBadFailTimeout), invalid "slow_start" (UpstreamBadSlowStart), reading body failed BodyReadError), "service" is empty (UpstreamBadService), server "ID" address is immutable (UpstreamServerImmutable), server "ID" weight is immutable (UpstreamServerWeightImmutable), upstream "name" memory exhausted (UpstreamOutOfMemory), returns Error
- "id" -404_ Server with IDdoes not exist (UpstreamServerNotFound). unknown ver-(UnknownVersion), upstream not found (UpstreamNotFound), returns Error
- 405 Method disabled (MethodDisabled), returns Error
- 415 JSON error (JsonError), returns Error

DELETE - Remove a server from a stream upstream server group Removes a server from a stream server group.

Possible responses:

- - 200 Success, returns an array of Stream Upstream Servers
 - 400 Upstream is static (UpstreamStatic), invalid server ID (UpstreamBadServerId), server "id" not removable (UpstreamServerImmutable), returns Error
 - "id" -404ID Server with does not exist (UpstreamServerNotFound), unknown ver-(UnknownVersion), upstream not found (UpstreamNotFound), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

Nginx, Inc. p.84 of 506

/stream/keyvals/ Supported methods:

GET - Return key-value pairs from all stream keyval zones
 Returns key-value pairs for each stream keyval shared memory zone.
 Request parameters:

fields (string, optional)

If the "fields" value is empty, then only stream keyval zone names will be output.

Possible responses:

- 200 Success, returns a collection of "Stream Keyval Shared Memory Zone" objects for all stream keyvals
- 404 Unknown version (UnknownVersion), returns Error

/stream/keyvals/{streamKeyvalZoneName}

Parameters common for all methods:

streamKeyvalZoneName (string, required)

The name of a stream keyval shared memory zone.

Supported methods:

GET - Return key-value pairs from a stream keyval zone
 Returns key-value pairs stored in a particular stream keyval shared memory zone.

Request parameters:

key (string, optional)

Get a particular key-value pair from the stream keyval zone.

Possible responses:

- 200 Success, returns Stream Keyval Shared Memory Zone
- 404 Keyval not found (KeyvalNotFound), keyval key not found (KeyvalKeyNotFound), unknown version (UnknownVersion), returns Error

POST - Add a key-value pair to the stream keyval zone

Adds a new key-value pair to the stream keyval shared memory zone. Several key-value pairs can be entered if the stream keyval shared memory zone is empty.

Request parameters:

• Key-value (Stream Keyval Shared Memory Zone, required)

A key-value pair is specified in the JSON format. Several key-value pairs can be entered if the stream keyval shared memory zone is empty. Expiration time in milliseconds can be specified for a key-value pair with the expire parameter which overrides the timeout parameter of the keyval_zone directive.

Possible responses:

Nginx, Inc. p.85 of 506

- 201 Created
- 400 Invalid JSON (KeyvalFormatError), invalid key format (KeyvalFormatError), key required (KeyvalFormatError), keyval timeout is not enabled (KeyvalFormatError), only one key can be added (KeyvalFormatError), reading request body failed BodyReadError), returns Error
- 404 Keyval not found (KeyvalNotFound), unknown version (UnknownVersion), returns Error
- 405 Method disabled (MethodDisabled), returns Error
- 409 Entry exists (EntryExists), key already exists (KeyvalKeyExists), returns Error
- 413 Request Entity Too Large, returns Error
- 415 JSON error (JsonError), returns Error

PATCH - Modify a key-value or delete a key

Changes the value of the selected key in the key-value pair, deletes a key by setting the key value to null, changes expiration time of a key-value pair. If synchronization of keyval zones in a cluster is enabled, deletes a key only on a target cluster node. Expiration time is specified in milliseconds with the expire parameter which overrides the timeout parameter of the keyval zone directive.

Request parameters:

• streamKeyvalZoneKeyValue (Stream Keyval Shared Memory Zone, required)

A new value for the key is specified in the JSON format.

Possible responses:

- 204 Success
- 400 Invalid JSON (KeyvalFormatError), key required (KeyvalFormatError), keyval timeout is not enabled (KeyvalFormatError), only one key can be updated (KeyvalFormatError), reading request body failed BodyReadError), returns Error
- 404 Keyval not found (KeyvalNotFound), keyval key not found (KeyvalKeyNotFound), unknown version (UnknownVersion), returns Error
- 405 Method disabled (MethodDisabled), returns Error
- 413 Request Entity Too Large, returns Error
- 415 JSON error (JsonError), returns Error

DELETE - Empty the stream keyval zone

Deletes all key-value pairs from the stream keyval shared memory zone. If synchronization of keyval zones in a cluster is enabled, empties the keyval zone only on a target cluster node.

Nginx, Inc. p.86 of 506

Possible responses:

- - 204 Success
 - 404 Keyval not found (KeyvalNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/stream/zone_sync/

Supported methods:

• GET - Return sync status of a node Returns synchronization status of a cluster node.

Possible responses:

- 200 Success, returns Stream Zone Sync Node
- 404 Unknown version (Unknown Version), returns Error

/resolvers/

Supported methods:

• GET - Return status for all resolver zones

Returns status information for each resolver zone.

Request parameters:

fields (string, optional)

Limits which fields of resolvers statistics will be output.

Possible responses:

- 200 Success, returns a collection of "Resolver Zone" objects for all resolvers
- 404 Unknown version (Unknown Version), returns Error

/resolvers/{resolverZoneName}

Parameters common for all methods:

resolverZoneName (string, required)

The name of a resolver zone.

Supported methods:

• GET - Return statistics of a resolver zone

Returns statistics stored in a particular resolver zone.

Request parameters:

fields (string, optional)

Limits which fields of the resolver zone will be output (requests, responses, or both).

Possible responses:

- 200 Success, returns Resolver Zone
- 404 Resolver zone not found (ResolverZoneNotFound), unknown version (UnknownVersion), returns Error

Nginx, Inc. p.87 of 506

DELETE - Reset statistics for a resolver zone.

Resets statistics in a particular resolver zone.

Possible responses:

- - 204 Success
 - 404 Resolver zone not found (ResolverZoneNotFound), unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

/ssl

Supported methods:

• GET - Return SSL statistics

Returns SSL statistics.

Request parameters:

fields (string, optional)

Limits which fields of SSL statistics will be output.

Possible responses:

- 200 Success, returns SSL
- 404 Unknown version (UnknownVersion), returns Error

DELETE - Reset SSL statistics

Resets counters of SSL handshakes and session reuses.

Possible responses:

- - 204 Success
 - 404 Unknown version (UnknownVersion), returns Error
 - 405 Method disabled (MethodDisabled), returns Error

2.4.6 Response Objects

• nginx:

General information about nginx:

```
version (string)
```

Version of nginx.

build (string)

Name of nginx build.

address (string)

The address of the server that accepted status request.

generation (integer)

The total number of configuration reloads.

load timestamp (string)

Time of the last reload of configuration, in the ISO 8601 format with millisecond resolution.

Nginx, Inc. p.88 of 506

```
timestamp (string)
```

Current time in the ISO 8601 format with millisecond resolution.

```
pid (integer)
```

The ID of the worker process that handled status request.

```
ppid (integer)
```

The ID of the master process that started the worker process.

Example:

```
{
   "nginx" : {
     "version" : "1.17.3",
     "build" : "nginx-plus-r19",
     "address" : "206.251.255.64",
     "generation" : 6,
     "load_timestamp" : "2019-10-01T11:15:44.467Z",
     "timestamp" : "2019-10-01T09:26:07.305Z",
     "pid" : 32212,
     "ppid" : 32210
   }
}
```

• Processes:

```
respawned (integer)
```

The total number of abnormally terminated and respawned child processes.

Example:

```
{
   "respawned" : 0
}
```

• Connections:

The number of accepted, dropped, active, and idle connections.

```
accepted (integer)
```

The total number of accepted client connections.

```
dropped (integer)
```

The total number of dropped client connections.

```
active (integer)
```

The current number of active client connections.

```
idle (integer)
```

The current number of idle client connections.

Example:

```
{
    "accepted" : 4968119,
    "dropped" : 0,
    "active" : 5,
```

Nginx, Inc. p.89 of 506

```
"idle" : 117
}
```

• SSL:

```
handshakes (integer)
The total number of successful SSL handshakes.
handshakes_failed (integer)
The total number of failed SSL handshakes.
session_reuses (integer)
The total number of session reuses during SSL handshake.
```

Example:

```
{
  "handshakes" : 79572,
  "handshakes_failed" : 21025,
  "session_reuses" : 15762
}
```

• Shared memory zone with slab allocator:

```
The number of free and used memory pages.

used (integer)

The current number of used memory pages.

free (integer)

The current number of free memory pages.

slots

Status data for memory slots (8, 16, 32, 64, 128, etc.)

A collection of "Memory Slot" objects
```

Example:

```
{
    "pages" : {
        "used" : 1143,
        "free" : 2928
},
    "slots" : {
        "8" : {
            "used" : 0,
            "free" : 0,
            "reqs" : 0,
            "fails" : 0
},
    "16" : {
            "used" : 0,
            "free" : 0,
            "reqs" : 0,
            "freils" : 0
},
    "sails" : 0
},
    "32" : {
        "used" : 0,
```

Nginx, Inc. p.90 of 506

```
"free": 0,
    "reqs": 0,
    "fails": 0
},
    "64": {
    "used": 1,
        "free": 63,
        "reqs": 1,
        "fails": 0
},
    "128": {
        "used": 0,
        "free": 0,
        "reqs": 0,
        "fails": 0
},
    "256": {
        "used": 18078,
        "free": 178,
        "reqs": 1635736,
        "fails": 0
}
}
```

• Memory Slot:

```
used (integer)
```

The current number of used memory slots.

```
free (integer)
```

The current number of free memory slots.

```
reqs (integer)
```

The total number of attempts to allocate memory of specified size.

```
fails (integer)
```

The number of unsuccessful attempts to allocate memory of specified size.

HTTP Requests:

total (integer)

The total number of client requests.

```
current (integer)
```

The current number of client requests.

Example:

```
{
  "total" : 10624511,
  "current" : 4
}
```

• HTTP Server Zone:

```
processing (integer)
```

The number of client requests that are currently being processed.

Nginx, Inc. p.91 of 506

```
requests (integer)
```

The total number of client requests received from clients.

responses

The total number of responses sent to clients and the number of responses with status codes "1xx", "2xx", "3xx", "4xx", and "5xx".

```
1xx (integer)
```

The number of responses with "1xx" status codes.

```
2xx (integer)
```

The number of responses with "2xx" status codes.

```
3xx (integer)
```

The number of responses with "3xx" status codes.

```
4xx (integer)
```

The number of responses with "4xx" status codes.

```
5xx (integer)
```

The number of responses with "5xx" status codes.

```
total (integer)
```

The total number of responses sent to clients.

```
discarded (integer)
```

The total number of requests completed without sending a response.

```
received (integer)
```

The total number of bytes received from clients.

```
sent (integer)
```

The total number of bytes sent to clients.

Example:

```
{
    "processing" : 1,
    "requests" : 706690,
    "responses" : {
        "1xx" : 0,
        "2xx" : 699482,
        "3xx" : 4522,
        "4xx" : 907,
        "5xx" : 266,
        "total" : 705177
    },
    "discarded" : 1513,
    "received" : 172711587,
    "sent" : 19415530115
}
```

• HTTP Location Zone:

```
requests (integer)
```

The total number of client requests received from clients.

responses

The total number of responses sent to clients and the number of responses with status codes "1xx", "2xx", "3xx", "4xx", and "5xx".

```
1xx (integer)
```

The number of responses with "1xx" status codes.

Nginx, Inc. p.92 of 506

```
2xx (integer)
   The number of responses with "2xx" status codes.
3xx (integer)
   The number of responses with "3xx" status codes.
4xx (integer)
   The number of responses with "4xx" status codes.
5xx (integer)
   The number of responses with "5xx" status codes.
total (integer)
   The total number of responses sent to clients.
```

discarded (integer)

The total number of requests completed without sending a response.

received (integer)

The total number of bytes received from clients.

sent (integer)

The total number of bytes sent to clients.

Example:

```
"requests" : 706690,
"responses" : {
    "1xx" : 0,
    "2xx" : 699482,
    "3xx" : 4522,
    "4xx" : 907,
    "5xx" : 266,
    "total" : 705177
},
"discarded" : 1513,
    "received" : 172711587,
    "sent" : 19415530115
}
```

• HTTP Cache:

```
The current size of the cache.

max_size (integer)

The limit on the maximum size of the cache specified in the configuration.

cold (boolean)

A boolean value indicating whether the "cache loader" process is still loading data from disk into the cache.

hit

responses (integer)

The total number of valid responses read from the cache.

bytes (integer)

The total number of bytes read from the cache.

stale
```

Nginx, Inc. p.93 of 506

```
responses (integer)
       The total number of expired responses read from the cache
       (see proxy_cache_use_stale and other "*_cache_use_stale"
       directives).
    bytes (integer)
       The total number of bytes read from the cache.
updating
    responses (integer)
       The total number of expired responses read from the cache while
       responses were being updated (see proxy_cache_use_stale and
       other "*_cache_use_stale" directives).
    bytes (integer)
       The total number of bytes read from the cache.
revalidated
    responses (integer)
       The total number of expired and revalidated responses read
       from the cache (see proxy_cache_revalidate and other "*_-
       cache_revalidate" directives.
    bytes (integer)
       The total number of bytes read from the cache.
miss
    responses (integer)
       The total number of responses not found in the cache.
    bytes (integer)
       The total number of bytes read from the proxied server.
    responses written (integer)
       The total number of responses written to the cache.
    bytes written (integer)
       The total number of bytes written to the cache.
expired
    responses (integer)
       The total number of expired responses not taken from the cache.
    bytes (integer)
       The total number of bytes read from the proxied server.
    responses_written (integer)
       The total number of responses written to the cache.
    bytes_written (integer)
       The total number of bytes written to the cache.
bypass
    responses (integer)
       The total number of responses not looked up in the cache
       due to the proxy_cache_bypass and other "*_cache_bypass"
       directives.
    bytes (integer)
```

Nginx, Inc. p.94 of 506

The total number of bytes read from the proxied server.

responses_written (integer)

The total number of responses written to the cache.

bytes_written (integer)

The total number of bytes written to the cache.

Example:

```
"size" : 530915328,
"max_size" : 536870912,
"cold" : false,
"hit" : {
 "responses" : 254032,
 "bytes": 6685627875
"stale" : {
 "responses" : 0,
 "bytes" : 0
"updating" : {
 "responses" : 0,
 "bytes" : 0
"revalidated" : {
  "responses" : 0,
 "bytes" : 0
"miss" : {
 "responses" : 1619201,
  "bytes" : 53841943822
"expired" : {
 "responses": 45859,
 "bytes" : 1656847080,
  "responses_written" : 44992,
  "bytes_written" : 1641825173
"bypass" : {
 "responses" : 200187,
 "bytes": 5510647548,
  "responses_written" : 200173,
  "bytes_written": 44992
```

• HTTP Connections Limiting:

```
passed (integer)
```

The total number of connections that were neither limited nor accounted as limited.

```
rejected (integer)
```

The total number of connections that were rejected.

```
rejected_dry_run (integer)
```

The total number of connections accounted as rejected in the dry run mode.

Example:

Nginx, Inc. p.95 of 506

```
{
  "passed" : 15,
  "rejected" : 0,
  "rejected_dry_run" : 2
}
```

• HTTP Requests Rate Limiting:

```
passed (integer)
```

The total number of requests that were neither limited nor accounted as limited.

```
delayed (integer)
```

The total number of requests that were delayed.

```
rejected (integer)
```

The total number of requests that were rejected.

```
delayed_dry_run (integer)
```

The total number of requests accounted as delayed in the dry run mode.

```
rejected_dry_run (integer)
```

The total number of requests accounted as rejected in the dry run mode.

Example:

```
"passed" : 15,
  "delayed" : 4,
  "rejected" : 0,
  "delayed_dry_run" : 1,
  "rejected_dry_run" : 2
}
```

• HTTP Upstream:

server.

```
An array of:

id (integer)

The ID of the server.

server (string)

An address of the server.

service (string)

The service parameter value of the server directive.

name (string)

The name of the server specified in the server directive.

backup (boolean)

A boolean value indicating whether the server is a backup
```

Nginx, Inc. p.96 of 506

```
weight (integer)
  Weight of the server.
state (string)
  Current state, which may be one of "up", "draining", "down",
  "unavail", "checking", and "unhealthy".
active (integer)
  The current number of active connections.
max_conns (integer)
  The max_conns limit for the server.
requests (integer)
  The total number of client requests forwarded to this server.
responses
    1xx (integer)
      The number of responses with "1xx" status codes.
    2xx (integer)
      The number of responses with "2xx" status codes.
    3xx (integer)
      The number of responses with "3xx" status codes.
    4xx (integer)
      The number of responses with "4xx" status codes.
    5xx (integer)
      The number of responses with "5xx" status codes.
    total (integer)
      The total number of responses obtained from this server.
sent (integer)
  The total number of bytes sent to this server.
received (integer)
  The total number of bytes received from this server.
fails (integer)
  The total number of unsuccessful attempts to communicate
  with the server.
unavail (integer)
  How many times the server became unavailable for client
  requests (state "unavail") due to the number of unsuccessful
  attempts reaching the max_fails threshold.
health checks
    checks (integer)
      The total number of health check requests made.
    fails (integer)
      The number of failed health checks.
    unhealthy (integer)
      How many times the server became unhealthy (state
      "unhealthy").
    last_passed (boolean)
      Boolean indicating if the last health check request was
```

Nginx, Inc. p.97 of 506

successful and passed tests.

```
downtime (integer)
```

Total time the server was in the "unavail", "checking", and "unhealthy" states.

```
downstart (string)
```

The time when the server became "unavail", "checking", or "unhealthy", in the ISO 8601 format with millisecond resolution.

```
selected (string)
```

The time when the server was last selected to process a request, in the ISO 8601 format with millisecond resolution.

```
header_time (integer)
```

The average time to get the response header from the server.

```
response_time (integer)
```

The average time to get the full response from the server.

```
keepalive (integer)
```

The current number of idle keepalive connections.

```
zombies (integer)
```

The current number of servers removed from the group but still processing active client requests.

```
zone (string)
```

The name of the shared memory zone that keeps the group's configuration and run-time state.

queue

For the requests queue, the following data are provided:

```
size (integer)
```

The current number of requests in the queue.

```
max_size (integer)
```

The maximum number of requests that can be in the queue at the same time.

```
overflows (integer)
```

The total number of requests rejected due to the queue overflow.

Example:

Nginx, Inc. p.98 of 506

```
"1xx" : 0,
      "2xx" : 666310,
"3xx" : 0,
      "4xx" : 915,
      "5xx" : 6,
       "total" : 667231
     "sent" : 251946292,
    "received" : 19222475454,
    "fails" : 0,
     "unavail" : 0,
     "health_checks" : {
      "checks" : 26214,
      "fails" : 0,
      "unhealthy" : 0,
      "last_passed" : true
    "downtime" : 0,
    "downstart": "2019-10-01T11:09:21.602Z",
    "selected" : "2019-10-01T15:01:25.000Z"
    "id" : 1,
    "server": "10.0.0.1:8089",
"name": "10.0.0.1:8089",
    "backup" : true,
     "weight" : 1,
    "state": "unhealthy",
"active": 0,
     "max_conns" : 20,
     "requests" : 0,
     "responses" : {
      "1xx" : 0,
"2xx" : 0,
"3xx" : 0,
      "4xx" : 0,
      "5xx" : 0,
       "total" : 0
     "sent" : 0,
    "received" : 0,
    "fails" : 0,
     "unavail" : 0,
     "health_checks" : {
      "checks" : 26284,
      "fails" : 26284,
      "unhealthy" : 1,
      "last_passed" : false
     "downtime" : 262925617,
    "downstart": "2019-10-01T11:09:21.602Z",
"selected": "2019-10-01T15:01:25.000Z"
"keepalive" : 0,
"zombies" : 0,
"zone" : "upstream_backend"
```

• HTTP Upstream Server:

Dynamically configurable parameters of an HTTP upstream server:

```
id (integer)
```

The ID of the HTTP upstream server. The ID is assigned automatically and cannot be changed.

Nginx, Inc. p.99 of 506

```
server (string)
```

Same as the address parameter of the HTTP upstream server. When adding a server, it is possible to specify it as a domain name. In this case, changes of the IP addresses that correspond to a domain name will be monitored and automatically applied to the upstream configuration without the need of restarting nginx. This requires the resolver directive in the "http" block. See also the resolve parameter of the HTTP upstream server.

```
service (string)
```

Same as the service parameter of the HTTP upstream server. This parameter cannot be changed.

```
weight (integer)
```

Same as the weight parameter of the HTTP upstream server.

```
max_conns (integer)
```

Same as the max_conns parameter of the HTTP upstream server.

```
max_fails (integer)
```

Same as the max_fails parameter of the HTTP upstream server.

```
fail_timeout (string)
```

Same as the fail_timeout parameter of the HTTP upstream server.

```
slow_start (string)
```

Same as the slow_start parameter of the HTTP upstream server.

```
route (string)
```

Same as the route parameter of the HTTP upstream server.

```
backup (boolean)
```

When true, adds a backup server. This parameter cannot be changed.

```
down (boolean)
```

Same as the down parameter of the HTTP upstream server.

```
drain (boolean)
```

Same as the drain parameter of the HTTP upstream server.

```
parent (string)
```

Parent server ID of the resolved server. The ID is assigned automatically and cannot be changed.

```
host (string)
```

Hostname of the resolved server. The hostname is assigned automatically and cannot be changed.

Example:

```
"id" : 1,
   "server" : "10.0.0.1:8089",
   "weight" : 4,
   "max_conns" : 0,
   "max_fails" : 0,
   "fail_timeout" : "10s",
   "slow_start" : "10s",
   "route" : "",
   "backup" : true,
   "down" : true
```

Nginx, Inc. p.100 of 506

```
}
```

• HTTP Keyval Shared Memory Zone:

Contents of an HTTP keyval shared memory zone when using the GET method.

Example:

```
{
    "key1" : "value1",
    "key2" : "value2",
    "key3" : "value3"
}
```

• HTTP Keyval Shared Memory Zone:

Contents of an HTTP keyval shared memory zone when using the POST or PATCH methods.

Example:

```
{
    "key1" : "value1",
    "key2" : "value2",
    "key3" : {
        "value" : "value3",
        "expire" : 30000
    }
}
```

• Stream Server Zone:

```
processing (integer)
```

The number of client connections that are currently being processed. ${\tt connections}$ (integer)

The total number of connections accepted from clients.

sessions

The total number of completed sessions, and the number of sessions completed with status codes "2xx", "4xx", or "5xx".

```
2xx (integer)
```

The total number of sessions completed with status codes "2xx".

```
4xx (integer)
```

The total number of sessions completed with status codes "4xx".

```
5xx (integer)
```

The total number of sessions completed with status codes "5xx".

```
total (integer)
```

The total number of completed client sessions.

Nginx, Inc. p.101 of 506

```
discarded (integer)
```

The total number of connections completed without creating a session.

```
received (integer)
```

The total number of bytes received from clients.

```
sent (integer)
```

The total number of bytes sent to clients.

Example:

```
"dns" : {
    "processing" : 1,
    "connections" : 155569,
    "sessions" : {
        "2xx" : 155564,
        "4xx" : 0,
        "5xx" : 0,
        "total" : 155569
        },
        "discarded" : 0,
        "received" : 4200363,
        "sent" : 20489184
        }
}
```

• Stream Connections Limiting:

```
passed (integer)
```

The total number of connections that were neither limited nor accounted as limited.

```
rejected (integer)
```

The total number of connections that were rejected.

```
rejected_dry_run (integer)
```

The total number of connections accounted as rejected in the dry run mode.

Example:

```
{
  "passed" : 15,
  "rejected" : 0,
  "rejected_dry_run" : 2
}
```

• Stream Upstream:

```
An array of:

id (integer)

The ID of the server.
```

Nginx, Inc. p.102 of 506

```
server (string)
   An address of the server.
service (string)
   The service parameter value of the server directive.
name (string)
   The name of the server specified in the server directive.
backup (boolean)
   A boolean value indicating whether the server is a backup
   server.
weight (integer)
   Weight of the server.
state (string)
   Current state, which may be one of "up", "down", "unavail",
   "checking", or "unhealthy".
active (integer)
   The current number of connections.
max_conns (integer)
   The max_conns limit for the server.
connections (integer)
   The total number of client connections forwarded to this server.
connect_time (integer)
   The average time to connect to the upstream server.
first byte time (integer)
   The average time to receive the first byte of data.
response_time (integer)
   The average time to receive the last byte of data.
sent (integer)
   The total number of bytes sent to this server.
received (integer)
   The total number of bytes received from this server.
fails (integer)
   The total number of unsuccessful attempts to communicate
   with the server.
unavail (integer)
   How many times the server became unavailable for client
   connections (state "unavail") due to the number of
   unsuccessful attempts reaching the max_fails threshold.
health_checks
    checks (integer)
      The total number of health check requests made.
    fails (integer)
      The number of failed health checks.
    unhealthy (integer)
      How many times the server became unhealthy (state
      "unhealthy").
```

Nginx, Inc. p.103 of 506

```
last_passed (boolean)
```

Boolean indicating whether the last health check request was successful and passed tests.

```
downtime (integer)
```

Total time the server was in the "unavail", "checking", and "unhealthy" states.

```
downstart (string)
```

The time when the server became "unavail", "checking", or "unhealthy", in the ISO 8601 format with millisecond resolution.

```
selected (string)
```

The time when the server was last selected to process a connection, in the ISO 8601 format with millisecond resolution.

```
zombies (integer)
```

The current number of servers removed from the group but still processing active client connections.

```
zone (string)
```

The name of the shared memory zone that keeps the group's configuration and run-time state.

Example:

```
"dns" : {
  "peers" : [
       "id" : 0,
       "server": "10.0.0.1:12347",
       "name" : "10.0.0.1:12347",
       "backup" : false,
       "weight": 5,

"state": "up"

"active": 0,
       "max_conns" : 50,
       "connections" : 667231,
       "sent" : 251946292,
       "received" : 19222475454,
       "fails" : 0,
       "unavail" : 0,
       "health_checks" : {
         "checks" : 26214,
         "fails" : 0,
         "unhealthy" : 0,
         "last_passed" : true
       "downtime" : 0,
       "downstart": "2019-10-01T11:09:21.602Z",
"selected": "2019-10-01T15:01:25.000Z"
       "id" : 1,
       "server": "10.0.0.1:12348",
"name": "10.0.0.1:12348",
       "backup" : true,
       "weight" : 1,
"state" : "unhealthy",
       "active" : 0,
       "max_conns" : 50,
       "connections" : 0,
```

Nginx, Inc. p.104 of 506

```
"sent": 0,
    "received": 0,
    "fails": 0,
    "unavail": 0,
    "health_checks": {
        "checks": 26284,
        "fails": 26284,
        "unhealthy": 1,
        "last_passed": false
    },
        "downtime": 262925617,
        "downstart": "2019-10-01T11:09:21.602Z",
        "selected": "2019-10-01T15:01:25.000Z"
    }
    ],
    "zombies": 0,
    "zone": "dns"
}
```

• Stream Upstream Server:

Dynamically configurable parameters of a stream upstream server:

```
id (integer)
```

The ID of the stream upstream server. The ID is assigned automatically and cannot be changed.

```
server (string)
```

Same as the address parameter of the stream upstream server. When adding a server, it is possible to specify it as a domain name. In this case, changes of the IP addresses that correspond to a domain name will be monitored and automatically applied to the upstream configuration without the need of restarting nginx. This requires the resolver directive in the "stream" block. See also the resolve parameter of the stream upstream server.

```
service (string)
```

Same as the service parameter of the stream upstream server. This parameter cannot be changed.

```
weight (integer)
```

Same as the weight parameter of the stream upstream server.

```
max conns (integer)
```

Same as the max_conns parameter of the stream upstream server.

```
max fails (integer)
```

Same as the max_fails parameter of the stream upstream server.

```
fail_timeout (string)
```

Same as the fail_timeout parameter of the stream upstream server.

slow_start (string)

Same as the slow_start parameter of the stream upstream server.

```
backup (boolean)
```

When true, adds a backup server. This parameter cannot be changed.

```
down (boolean)
```

Same as the down parameter of the stream upstream server.

Nginx, Inc. p.105 of 506

```
parent (string)
```

Parent server ID of the resolved server. The ID is assigned automatically and cannot be changed.

```
host (string)
```

Hostname of the resolved server. The hostname is assigned automatically and cannot be changed.

Example:

```
"id" : 0,
   "server" : "10.0.0.1:12348",
   "weight" : 1,
   "max_conns" : 0,
   "max_fails" : 1,
   "fail_timeout" : "10s",
   "slow_start" : 0,
   "backup" : false,
   "down" : false
}
```

• Stream Keyval Shared Memory Zone:

Contents of a stream keyval shared memory zone when using the GET method.

Example:

```
{
    "key1" : "value1",
    "key2" : "value2",
    "key3" : "value3"
}
```

• Stream Keyval Shared Memory Zone:

Contents of a stream keyval shared memory zone when using the POST or PATCH methods.

Example:

```
{
  "key1" : "value1",
  "key2" : "value2",
  "key3" : {
     "value" : "value3",
     "expire" : 30000
  }
}
```

• Stream Zone Sync Node:

zones

Synchronization information per each shared memory zone. A collection of "Sync Zone" objects

Nginx, Inc. p.106 of 506

```
status
```

Synchronization information per node in a cluster.

```
bytes_in (integer)
```

The number of bytes received by this node.

```
msgs_in (integer)
```

The number of messages received by this node.

```
msqs_out (integer)
```

The number of messages sent by this node.

```
bytes_out (integer)
```

The number of bytes sent by this node.

```
nodes_online (integer)
```

The number of peers this node is connected to.

Example:

```
"zones" : {
    "zone1" : {
        "records_pending" : 2061,
        "records_total" : 260575
    },
    "zone2" : {
        "records_pending" : 0,
        "records_total" : 14749
    }
},
    "status" : {
        "bytes_in" : 1364923761,
        "msgs_in" : 337236,
        "msgs_out" : 346717,
        "bytes_out" : 1402765472,
        "nodes_online" : 15
}
```

• Sync Zone:

Synchronization status of a shared memory zone.

```
records_pending (integer)
```

The number of records that need to be sent to the cluster.

```
records_total (integer)
```

The total number of records stored in the shared memory zone.

Resolver Zone:

Statistics of DNS requests and responses per particular resolver zone.

requests

```
name (integer)
```

The total number of requests to resolve names to addresses. srv (integer)

The total number of requests to resolve SRV records.

Nginx, Inc. p.107 of 506

```
addr (integer)
      The total number of requests to resolve addresses to names.
responses
    noerror (integer)
      The total number of successful responses.
    formerr (integer)
      The total number of FORMERR (Format error) responses.
    servfail (integer)
      The total number of SERVFAIL (Server failure) re-
      sponses.
    nxdomain (integer)
      The total number of NXDOMAIN (Host not found)
      responses.
    notimp (integer)
      The total number of NOTIMP (Unimplemented) responses.
    refused (integer)
      The total number of REFUSED (Operation refused)
      responses.
    timedout (integer)
      The total number of timed out requests.
```

Example:

unknown (integer)

```
{
    "resolver_zonel" : {
        "requests" : {
            "name" : 25460,
            "srv" : 130,
            "addr" : 2580
        },
        "responses" : {
            "noerror" : 26499,
            "formerr" : 0,
            "servfail" : 3,
            "nxdomain" : 0,
            "notimp" : 0,
            "refused" : 0,
            "timedout" : 243,
            "unknown" : 478
        }
    }
}
```

The total number of requests completed with an unknown error.

• Error:

nginx error object.

```
error
status (integer)
HTTP error code.
```

Nginx, Inc. p.108 of 506

text (string)
Error description.
code (string)
Internal nginx error code.

request_id (string)

The ID of the request, equals the value of the \$request_id variable. href (string)

Link to reference documentation.

Nginx, Inc. p.109 of 506

2.5 Module ngx_http_auth_basic_module

2.5.1	Summary	0
2.5.2	Example Configuration	0
2.5.3	Directives	0
	auth_basic	0
	auth basic user file	n

2.5.1 Summary

The ngx_http_auth_basic_module module allows limiting access to resources by validating the user name and password using the "HTTP Basic Authentication" protocol.

Access can also be limited by address, by the result of subrequest, or by JWT. Simultaneous limitation of access by address and by password is controlled by the satisfy directive.

2.5.2 Example Configuration

```
location / {
   auth_basic      "closed site";
   auth_basic_user_file conf/htpasswd;
}
```

2.5.3 Directives

auth_basic

```
SYNTAX: auth_basic string | off;
```

Default off

Context: http, server, location, limit_except

Enables validation of user name and password using the "HTTP Basic Authentication" protocol. The specified parameter is used as a *realm*. Parameter value can contain variables (1.3.10, 1.2.7). The special value off cancels the effect of the auth_basic directive inherited from the previous configuration level.

auth_basic_user_file

```
SYNTAX: auth_basic_user_file;
```

Default —

Context: http, server, location, limit_except

Specifies a file that keeps user names and passwords, in the following format:

```
# comment
name1:password1
name2:password2:comment
```

Nginx, Inc. p.110 of 506

name3:password3

The file name can contain variables.

The following password types are supported:

- encrypted with the crypt function; can be generated using the "htpasswd" utility from the Apache HTTP Server distribution or the "openssl passwd" command;
- hashed with the Apache variant of the MD5-based password algorithm (apr1); can be generated with the same tools;
- specified by the "{scheme} data" syntax (1.0.3+) as described in RFC 2307; currently implemented schemes include PLAIN (an example one, should not be used), SHA (1.3.13) (plain SHA-1 hashing, should not be used) and SSHA (salted SHA-1 hashing, used by some software packages, notably OpenLDAP and Dovecot).

Support for SHA scheme was added only to aid in migration from other web servers. It should not be used for new passwords, since unsalted SHA-1 hashing that it employs is vulnerable to rainbow table attacks.

Nginx, Inc. p.111 of 506

2.6 Module ngx_http_auth_jwt_module

2.6.1	Summary
2.6.2	Supported Algorithms
2.6.3	Example Configuration
2.6.4	Directives
	auth_jwt
	auth_jwt_claim_set
	auth_jwt_header_set
	auth_jwt_key_file
	auth_jwt_key_request
	auth_jwt_leeway
	auth_jwt_type
2.6.5	Embedded Variables

2.6.1 Summary

The ngx_http_auth_jwt_module module (1.11.3) implements client authorization by validating the provided JSON Web Token (JWT) using the specified keys. JWT claims can be encoded in a JSON Web Signature (JWS) or JSON Web Encryption (JWE) (1.19.7) structure. The module can be used for OpenID Connect authentication.

The module may be combined with other access modules, such as ngx_http_access_module, ngx_http_auth_basic_module, and ngx_http_auth_request_module, via the satisfy directive.

This module is available as part of our commercial subscription.

2.6.2 Supported Algorithms

The module supports the following JSON Web Algorithms. JWS algorithms:

- HS256, HS384, HS512
- RS256, RS384, RS512
- ES256, ES384, ES512
- EdDSA (Ed25519 and Ed448 signatures) (1.15.7)

Prior to version 1.13.7, only HS256, RS256, ES256 algorithms were supported.

JWE content encryption algorithms (1.19.7):

• A128CBC-HS256, A192CBC-HS384, A256CBC-HS512

Nginx, Inc. p.112 of 506

• A128GCM, A192GCM, A256GCM

JWE key management algorithms (1.19.9):

- A128KW, A192KW, A256KW
- A128GCMKW, A192GCMKW, A256GCMKW
- dir direct use of a shared symmetric key as the content encryption key

2.6.3 Example Configuration

```
location / {
    auth_jwt "closed site";
    auth_jwt_key_file conf/keys.json;
}
```

2.6.4 Directives

auth_jwt

```
SYNTAX: auth_jwt string [token=$variable] | off;
Default off
Context: http, server, location, limit_except
```

Enables validation of JSON Web Token. The specified *string* is used as a realm. Parameter value can contain variables.

The optional token parameter specifies a variable that contains JSON Web Token. By default, JWT is passed in the Authorization header as a Bearer Token. JWT may be also passed as a cookie or a part of a query string:

```
auth_jwt "closed site" token=$cookie_auth_token;
```

The special value off cancels the effect of the auth_jwt directive inherited from the previous configuration level.

auth_jwt_claim_set

```
SYNTAX: auth_jwt_claim_set $variable name ...;

DEFAULT —

CONTEXT: http

This directive appeared in version 1.11.10.
```

Sets the *variable* to a JWT claim parameter identified by key names. Name matching starts from the top level of the JSON tree. For arrays, the variable keeps a list of array elements separated by commas.

```
auth_jwt_claim_set $email info e-mail;
auth_jwt_claim_set $job info "job title";
```

Nginx, Inc. p.113 of 506

Prior to version 1.13.7, only one key name could be specified, and the result was undefined for arrays.

Variable values for tokens encrypted with JWE are available only after decryption which occurs during the Access phase.

auth_jwt_header_set

```
SYNTAX: auth_jwt_header_set $variable name ...;

DEFAULT —

CONTEXT: http

This directive appeared in version 1.11.10.
```

Sets the *variable* to a JOSE header parameter identified by key names. Name matching starts from the top level of the JSON tree. For arrays, the variable keeps a list of array elements separated by commas.

Prior to version 1.13.7, only one key name could be specified, and the result was undefined for arrays.

auth_jwt_key_file

```
SYNTAX: auth_jwt_key_file file;

DEFAULT —

CONTEXT: http, server, location, limit_except
```

Specifies a *file* in JSON Web Key Set format for validating JWT signature. Parameter value can contain variables.

auth_jwt_key_request

```
SYNTAX: auth_jwt_key_request uri;

DEFAULT —

CONTEXT: http, server, location, limit_except
This directive appeared in version 1.15.6.
```

Allows retrieving a JSON Web Key Set file from a subrequest for validating JWT signature and sets the URI where the subrequest will be sent to. Parameter value can contain variables. To avoid validation overhead, it is recommended to cache the key file:

Nginx, Inc. p.114 of 506

```
location = /jwks_uri {
    internal;
    proxy_cache foo;
    proxy_pass http://idp.example.com/keys;
}
```

auth_jwt_leeway

SYNTAX: auth_jwt_leeway time;

Default 0s

Context: http, server, location

This directive appeared in version 1.13.10.

Sets the maximum allowable leeway to compensate clock skew when verifying the exp and nbf JWT claims.

auth_jwt_type

SYNTAX: **auth_jwt_type** signed | encrypted;

DEFAULT signed

Context: http, server, location, limit_except

This directive appeared in version 1.19.7.

Specifies which type of JSON Web Token to expect: JWS (signed) or JWE (encrypted).

2.6.5 Embedded Variables

The ngx_http_auth_jwt_module module supports embedded variables:

\$jwt_header_name

returns the value of a specified JOSE header

\$jwt_claim_name

returns the value of a specified JWT claim

For nested claims and claims including a dot ("."), the value of the variable cannot be evaluated; the auth_jwt_claim_set directive should be used instead.

Variable values for tokens encrypted with JWE are available only after decryption which occurs during the Access phase.

Nginx, Inc. p.115 of 506

2.7 Module ngx_http_auth_request_module

2.7.1	Summary
2.7.2	Example Configuration
2.7.3	Directives
	auth_request
	auth_request_set

2.7.1 Summary

The ngx_http_auth_request_module module (1.5.4+) implements client authorization based on the result of a subrequest. If the subrequest returns a 2xx response code, the access is allowed. If it returns 401 or 403, the access is denied with the corresponding error code. Any other response code returned by the subrequest is considered an error.

For the 401 error, the client also receives the WWW-Authenticate header from the subrequest response.

This module is not built by default, it should be enabled with the --with-http_auth_request_module configuration parameter.

The module may be combined with other access modules, such as ngx_http_access_module, ngx_http_auth_basic_module, and ngx_http_auth_jwt_module, via the satisfy directive.

Before version 1.7.3, responses to authorization subrequests could not be cached (using proxy_cache, proxy_store, etc.).

2.7.2 Example Configuration

```
location /private/ {
    auth_request /auth;
    ...
}
location = /auth {
    proxy_pass ...
    proxy_pass_request_body off;
    proxy_set_header Content-Length "";
    proxy_set_header X-Original-URI $request_uri;
}
```

2.7.3 Directives

$auth_request$

SYNTAX: **auth_request** $uri \mid off;$

Default off

Context: http, server, location

Nginx, Inc. p.116 of 506

Enables authorization based on the result of a subrequest and sets the URI to which the subrequest will be sent.

$auth_request_set$

 ${\tt SYNTAX:} \quad \textbf{auth_request_set} \ \$variable \ value;$

Default —

CONTEXT: http, server, location

Sets the request variable to the given value after the authorization request completes. The value may contain variables from the authorization request, such as $\$upstream_http_*$.

Nginx, Inc. p.117 of 506

2.8 Module ngx_http_autoindex_module

2.8.1	Summary									118
2.8.2	Example Configuration									118
2.8.3	Directives									118
	autoindex									118
	$autoindex_exact_size$.									118
	autoindex_format									118
	autoindex_localtime									119

2.8.1 Summary

The ngx_http_autoindex_module module processes requests ending with the slash character ('/') and produces a directory listing. Usually a request is passed to the ngx_http_autoindex_module module when the ngx_http_index_module module cannot find an index file.

2.8.2 Example Configuration

```
location / {
   autoindex on;
}
```

2.8.3 Directives

autoindex

SYNTAX: autoindex on | off;

Default off

Context: http, server, location

Enables or disables the directory listing output.

autoindex_exact_size

SYNTAX: autoindex_exact_size on | off;

Default on

Context: http, server, location

For the HTML format, specifies whether exact file sizes should be output in the directory listing, or rather rounded to kilobytes, megabytes, and gigabytes.

autoindex_format

SYNTAX: autoindex_format html | xml | json | jsonp;

DEFAULT html

Context: http, server, location
This directive appeared in version 1.7.9.

Nginx, Inc. p.118 of 506

Sets the format of a directory listing.

When the JSONP format is used, the name of a callback function is set with the callback request argument. If the argument is missing or has an empty value, then the JSON format is used.

The XML output can be transformed using the ngx_http_xslt_module module.

autoindex_localtime

SYNTAX: autoindex_localtime on | off;

Default off

Context: http, server, location

For the HTML format, specifies whether times in the directory listing should be output in the local time zone or UTC.

Nginx, Inc. p.119 of 506

2.9 Module ngx_http_browser_module

2.9.1	Summary \dots	0
2.9.2	Example Configuration	0
2.9.3	Directives	1
	ancient_browser	1
	ancient_browser_value	1
	$modern_browser \dots \dots$	1
	modern_browser_value	1

2.9.1 Summary

The ngx_http_browser_module module creates variables whose values depend on the value of the User-Agent request header field:

$\$modern_browser$

equals the value set by the modern_browser_value directive, if a browser was identified as modern;

$\$ancient_browser$

equals the value set by the ancient_browser_value directive, if a browser was identified as ancient;

\$msie

equals "1" if a browser was identified as MSIE of any version.

2.9.2 Example Configuration

Choosing an index file:

```
modern_browser_value "modern.";
modern_browser msie 5.5;
modern_browser gecko 1.0.0;
modern_browser opera 9.0;
modern_browser safari 413;
modern_browser konqueror 3.0;
index index.${modern_browser}html index.html;
```

Redirection for old browsers:

```
modern_browser msie 5.0;
modern_browser gecko 0.9.1;
modern_browser opera 8.0;
modern_browser safari 413;
modern_browser konqueror 3.0;

modern_browser unlisted;
ancient_browser Links Lynx netscape4;
if ($ancient_browser) {
   rewrite ^ /ancient.html;
}
```

Nginx, Inc. p.120 of 506

2.9.3 Directives

ancient_browser

SYNTAX: ancient_browser $string \dots;$

Default —

Context: http, server, location

If any of the specified substrings is found in the User-Agent request header field, the browser will be considered ancient. The special string "netscape4" corresponds to the regular expression "^Mozilla/[1-4]".

ancient_browser_value

SYNTAX: ancient_browser_value string;

Default 1

CONTEXT: http, server, location

Sets a value for the *\$ancient_browser* variables.

modern_browser

SYNTAX: modern_browser browser version;

SYNTAX: modern_browser unlisted;

Default —

Context: http, server, location

Specifies a version starting from which a browser is considered modern. A browser can be any one of the following: msie, gecko (browsers based on Mozilla), opera, safari, or konqueror.

Versions can be specified in the following formats: X, X.X, X.X.X, or X.X.X.X. The maximum values for each of the format are 4000, 4000.99, 4000.99.99, and 4000.99.99.99, respectively.

The special value unlisted specifies to consider a browser as modern if it was not listed by the modern_browser and ancient_browser directives. Otherwise such a browser is considered ancient. If a request does not provide the User-Agent field in the header, the browser is treated as not being listed.

modern_browser_value

SYNTAX: modern_browser_value string;

Default 1

Context: http, server, location

Sets a value for the \$modern_browser variables.

Nginx, Inc. p.121 of 506

2.10 Module ngx_http_charset_module

2.10.1	Summary
2.10.2	Example Configuration
2.10.3	Directives
	charset
	charset_map
	charset_types
	override_charset
	source_charset

2.10.1 Summary

The ngx_http_charset_module module adds the specified charset to the Content-Type response header field. In addition, the module can convert data from one charset to another, with some limitations:

- conversion is performed one way from server to client,
- only single-byte charsets can be converted
- or single-byte charsets to/from UTF-8.

2.10.2 Example Configuration

```
include conf/koi-win;
charset windows-1251;
source_charset koi8-r;
```

2.10.3 Directives

charset

SYNTAX: **charset** charset | off;

Default off

CONTEXT: http, server, location, if in location

Adds the specified charset to the Content-Type response header field. If this charset is different from the charset specified in the source_charset directive, a conversion is performed.

The parameter off cancels the addition of charset to the Content-Type response header field.

A charset can be defined with a variable:

```
charset $charset;
```

Nginx, Inc. p.122 of 506

In such a case, all possible values of a variable need to be present in the configuration at least once in the form of the charset_map, charset, or source_charset directives. For utf-8, windows-1251, and koi8-r charsets, it is sufficient to include the files conf/koi-win, conf/koi-utf, and conf-/win-utf into configuration. For other charsets, simply making a fictitious conversion table works, for example:

```
charset_map iso-8859-5 _ { }
```

In addition, a charset can be set in the X-Accel-Charset response header field. This capability can be disabled using the proxy_ignore_headers, fastcgi_ignore_headers, uwsgi_ignore_headers, scgi_ignore_headers, and grpc_ignore_headers directives.

charset_map

```
SYNTAX: charset_map charset1 charset2 { ...}

DEFAULT —

CONTEXT: http
```

Describes the conversion table from one charset to another. A reverse conversion table is built using the same data. Character codes are given in hexadecimal. Missing characters in the range 80-FF are replaced with "?". When converting from UTF-8, characters missing in a one-byte charset are replaced with "&#XXXX;".

Example:

```
charset_map koi8-r windows-1251 {
   C0 FE; # small yu
   C1 E0; # small a
   C2 E1; # small b
   C3 F6; # small ts
   ...
}
```

When describing a conversion table to UTF-8, codes for the UTF-8 charset should be given in the second column, for example:

```
charset_map koi8-r utf-8 {
    C0 D18E; # small yu
    C1 D0B0; # small a
    C2 D0B1; # small b
    C3 D186; # small ts
    ...
}
```

Full conversion tables from koi8-r to windows-1251, and from koi8-r and windows-1251 to utf-8 are provided in the distribution files conf/¬koi-win, conf/koi-utf, and conf/win-utf.

Nginx, Inc. p.123 of 506

charset_types

SYNTAX: charset_types mime-type ...;

DEFAULT text/html text/xml text/plain text/vnd.wap.wml

application/javascript application/rss+xml

Context: http, server, location
This directive appeared in version 0.7.9.

Enables module processing in responses with the specified MIME types in addition to "text/html". The special value "*" matches any MIME type (0.8.29).

Until version 1.5.4, "application/x-javascript" was used as the default MIME type instead of "application/javascript".

override_charset

SYNTAX: override_charset on | off;

Default off

Context: http, server, location, if in location

Determines whether a conversion should be performed for answers received from a proxied or a FastCGI/uwsgi/SCGI/gRPC server when the answers already carry a charset in the Content-Type response header field. If conversion is enabled, a charset specified in the received response is used as a source charset.

It should be noted that if a response is received in a subrequest then the conversion from the response charset to the main request charset is always performed, regardless of the override_charset directive setting.

$source_charset$

SYNTAX: source_charset charset;

Default —

CONTEXT: http, server, location, if in location

Defines the source charset of a response. If this charset is different from the charset specified in the charset directive, a conversion is performed.

Nginx, Inc. p.124 of 506

2.11 Module ngx_http_dav_module

2.11.1	Summary										125
2.11.2	Example Configuration										125
2.11.3	Directives										125
	$create_full_put_path$										125
	dav_access										126
	$dav_methods \dots .$										126
	min_delete_depth										126

2.11.1 Summary

The ngx_http_dav_module module is intended for file management automation via the WebDAV protocol. The module processes HTTP and WebDAV methods PUT, DELETE, MKCOL, COPY, and MOVE.

This module is not built by default, it should be enabled with the --with-http_dav_module configuration parameter.

WebDAV clients that require additional WebDAV methods to operate will not work with this module.

2.11.2 Example Configuration

2.11.3 Directives

create_full_put_path

```
SYNTAX: create_full_put_path on | off;
DEFAULT off
CONTEXT: http, server, location
```

The WebDAV specification only allows creating files in already existing directories. This directive allows creating all needed intermediate directories.

Nginx, Inc. p.125 of 506

dav_access

SYNTAX: dav_access users:permissions ...;

DEFAULT user:rw

Context: http, server, location

Sets access permissions for newly created files and directories, e.g.:

```
dav_access user:rw group:rw all:r;
```

If any group or all access permissions are specified then user permissions may be omitted:

```
dav_access group:rw all:r;
```

dav_methods

SYNTAX: dav_methods off | method ...;

Default off

Context: http, server, location

Allows the specified HTTP and WebDAV methods. The parameter off denies all methods processed by this module. The following methods are supported: PUT, DELETE, MKCOL, COPY, and MOVE.

A file uploaded with the PUT method is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the persistent store can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both saved files and a directory holding temporary files, set by the client_body_temp_path directive, are put on the same file system.

When creating a file with the PUT method, it is possible to specify the modification date by passing it in the Date header field.

min_delete_depth

SYNTAX: min_delete_depth number;

Default 0

Context: http, server, location

Allows the DELETE method to remove files provided that the number of elements in a request path is not less than the specified number. For example, the directive

```
min_delete_depth 4;
```

allows removing files on requests

```
/users/00/00/name
/users/00/00/name/pic.jpg
```

Nginx, Inc. p.126 of 506

/users/00/00/page.html

and denies the removal of

/users/00/00

Nginx, Inc. p.127 of 506

2.12 Module ngx_http_empty_gif_module

2.12.1	Summary	128
2.12.2	Example Configuration	128
2.12.3	Directives	128
	empty_gif	128

2.12.1 Summary

The ngx_http_empty_gif_module module emits single-pixel transparent GIF.

2.12.2 Example Configuration

```
location = /_.gif {
   empty_gif;
}
```

2.12.3 Directives

$empty_gif$

SYNTAX: empty_gif;

Default —

Context: location

Turns on module processing in a surrounding location.

Nginx, Inc. p.128 of 506

2.13 Module ngx_http_f4f_module

2.13.1	Summary	129
2.13.2	Example Configuration	129
2.13.3	Directives	129
	f4f	129
	f4f_buffer_size	129

2.13.1 **Summary**

The ngx_http_f4f_module module provides server-side support for Adobe HTTP Dynamic Streaming (HDS).

This module implements handling of HTTP Dynamic Streaming requests in the "/videoSeg1-Frag1" form — extracting the needed fragment from the videoSeg1.f4f file using the videoSeg1.f4x index file. This module is an alternative to the Adobe's f4f module (HTTP Origin Module) for Apache.

Usual pre-processing with Adobe's f4fpackager is required, see relevant documentation for details.

This module is available as part of our commercial subscription.

2.13.2 Example Configuration

```
location /video/ {
   f4f;
   ...
}
```

2.13.3 Directives

f4f

```
SYNTAX: f4f;
DEFAULT —
CONTEXT: location
```

Turns on module processing in the surrounding location.

f4f_buffer_size

```
SYNTAX: f4f_buffer_size size;
DEFAULT 512k
CONTEXT: http, server, location
```

Sets the *size* of the buffer used for reading the .f4x index file.

Nginx, Inc. p.129 of 506

${\bf 2.14}\quad {\bf Module~ngx_http_fastcgi_module}$

2.14.1	Summary
2.14.2	Example Configuration
2.14.3	Directives
	fastegi_bind
	fastcgi_buffer_size
	fastcgi_buffering
	fastcgi_buffers
	fastcgi_busy_buffers_size
	fastcgi_cache
	fastcgi_cache_background_update
	fastcgi_cache_bypass
	fastcgi_cache_key
	fastcgi_cache_lock
	fastcgi_cache_lock_age
	fastcgi_cache_lock_timeout
	fastcgi_cache_max_range_offset
	fastcgi_cache_methods
	fastcgi_cache_min_uses
	fastcgi_cache_path
	fastcgi_cache_purge
	fastcgi_cache_revalidate
	fastcgi_cache_use_stale
	fastcgi_cache_valid
	fastcgi_catch_stderr
	fastcgi_connect_timeout
	fastcgi_force_ranges
	fastcgi_hide_header
	fastcgi_ignore_client_abort
	fastcgi_ignore_headers
	fastcgi_index
	fastcgi_intercept_errors
	fastcgi_keep_conn
	fastcgi_limit_rate
	fastcgi_max_temp_file_size
	fastcgi_next_upstream
	fastcgi_next_upstream_timeout
	fastcgi_next_upstream_tries
	fastcgi_no_cache
	fastcgi_param
	fastcgi_pass
	fastcgi_pass_header
	fastcgi_pass_request_body
	fastcgi_pass_request_headers
	fastcgi_read_timeout

Nginx, Inc. p.130 of 506

	fastcgi_request_buffering
	fastcgi_send_lowat
	fastcgi_send_timeout
	fastcgi_socket_keepalive
	fastcgi_split_path_info
	fastcgi_store
	fastcgi_store_access
	fastcgi_temp_file_write_size
	fastcgi_temp_path
14.4	Parameters Passed to a FastCGI Server
14.5	Embedded Variables

2.14.1 Summary

2.
 2.

The ngx_http_fastcgi_module module allows passing requests to a FastCGI server.

2.14.2 Example Configuration

2.14.3 Directives

fastcgi_bind

```
SYNTAX: fastcgi_bind address [transparent] | off;
DEFAULT —
CONTEXT: http, server, location
This directive appeared in version 0.8.22.
```

Makes outgoing connections to a FastCGI server originate from the specified local IP address with an optional port (1.11.2). Parameter value can contain variables (1.3.12). The special value off (1.3.12) cancels the effect of the fastcgi_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address and port.

The transparent parameter (1.11.0) allows outgoing connections to a FastCGI server originate from a non-local IP address, for example, from a real IP address of a client:

```
fastcgi_bind $remote_addr transparent;
```

Nginx, Inc. p.131 of 506

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required (1.13.8) as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the FastCGI server.

fastcgi_buffer_size

SYNTAX: fastcgi_buffer_size size;

DEFAULT 4k | 8k

Context: http, server, location

Sets the *size* of the buffer used for reading the first part of the response received from the FastCGI server. This part usually contains a small response header. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform. It can be made smaller, however.

fastcgi_buffering

SYNTAX: **fastcgi_buffering** on | off;

Default on

Context: http, server, location
This directive appeared in version 1.5.6.

Enables or disables buffering of responses from the FastCGI server.

When buffering is enabled, nginx receives a response from the FastCGI server as soon as possible, saving it into the buffers set by the fastcgi_buffer_size and fastcgi_buffers directives. If the whole response does not fit into memory, a part of it can be saved to a temporary file on the disk. Writing to temporary files is controlled by the fastcgi_max_temp_file_size and fastcgi_temp_file_write_size directives.

When buffering is disabled, the response is passed to a client synchronously, immediately as it is received. nginx will not try to read the whole response from the FastCGI server. The maximum size of the data that nginx can receive from the server at a time is set by the fastcgi_buffer_size directive.

Buffering can also be enabled or disabled by passing "yes" or "no" in the X-Accel-Buffering response header field. This capability can be disabled using the fastcgi_ignore_headers directive.

fastcgi_buffers

SYNTAX: fastcgi_buffers number size;

Default 8 4k | 8k

Context: http, server, location

Sets the *number* and *size* of the buffers used for reading a response from the FastCGI server, for a single connection. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

Nginx, Inc. p.132 of 506

fastcgi_busy_buffers_size

SYNTAX: fastcgi_busy_buffers_size size;

Default 8k|16k

Context: http, server, location

When buffering of responses from the FastCGI server is enabled, limits the total *size* of buffers that can be busy sending a response to the client while the response is not yet fully read. In the meantime, the rest of the buffers can be used for reading the response and, if needed, buffering part of the response to a temporary file. By default, *size* is limited by the size of two buffers set by the fastcgi_buffer_size and fastcgi_buffers directives.

fastcgi_cache

SYNTAX: **fastcgi_cache** zone | off;

Default off

Context: http, server, location

Defines a shared memory zone used for caching. The same zone can be used in several places. Parameter value can contain variables (1.7.9). The off parameter disables caching inherited from the previous configuration level.

fastcgi_cache_background_update

SYNTAX: fastcgi_cache_background_update on | off;

Default off

Context: http, server, location

This directive appeared in version 1.11.10.

Allows starting a background subrequest to update an expired cache item, while a stale cached response is returned to the client. Note that it is necessary to allow the usage of a stale cached response when it is being updated.

fastcgi_cache_bypass

SYNTAX: fastcgi_cache_bypass string ...;

Default —

CONTEXT: http, server, location

Defines conditions under which the response will not be taken from a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be taken from the cache:

```
fastcgi_cache_bypass $cookie_nocache $arg_nocache$arg_comment;
fastcgi_cache_bypass $http_pragma $http_authorization;
```

Can be used along with the fastcgi_no_cache directive.

Nginx, Inc. p.133 of 506

fastcgi_cache_key

SYNTAX: fastcgi_cache_key string;

Default —

CONTEXT: http, server, location

Defines a key for caching, for example

fastcgi_cache_key localhost:9000\$request_uri;

$fastcgi_cache_lock$

SYNTAX: **fastcgi_cache_lock** on | off;

Default off

Context: http, server, location
This directive appeared in version 1.1.12.

When enabled, only one request at a time will be allowed to populate a new cache element identified according to the fastcgi_cache_key directive by passing a request to a FastCGI server. Other requests of the same cache element will either wait for a response to appear in the cache or the cache lock for this element to be released, up to the time set by the fastcgi_cache_lock_timeout directive.

fastcgi_cache_lock_age

SYNTAX: fastcgi_cache_lock_age time;

Default 5s

Context: http, server, location
This directive appeared in version 1.7.8.

If the last request passed to the FastCGI server for populating a new cache element has not completed for the specified *time*, one more request may be passed to the FastCGI server.

fastcgi_cache_lock_timeout

SYNTAX: fastcgi_cache_lock_timeout time;

Default 5s

CONTEXT: http, server, location

This directive appeared in version 1.1.12.

Sets a timeout for fastcgi_cache_lock. When the *time* expires, the request will be passed to the FastCGI server, however, the response will not be cached.

Before 1.7.8, the response could be cached.

Nginx, Inc. p.134 of 506

fastcgi_cache_max_range_offset

```
SYNTAX: fastcgi_cache_max_range_offset number;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.11.6.
```

Sets an offset in bytes for byte-range requests. If the range is beyond the offset, the range request will be passed to the FastCGI server and the response will not be cached.

fastcgi_cache_methods

```
SYNTAX: fastcgi_cache_methods GET | HEAD | POST ...;

DEFAULT GET HEAD

CONTEXT: http, server, location

This directive appeared in version 0.7.59.
```

If the client request method is listed in this directive then the response will be cached. "GET" and "HEAD" methods are always added to the list, though it is recommended to specify them explicitly. See also the fastcgi_no_cache directive.

fastcgi_cache_min_uses

```
SYNTAX: fastcgi_cache_min_uses number;
DEFAULT 1
CONTEXT: http, server, location
```

Sets the *number* of requests after which the response will be cached.

fastcgi_cache_path

```
SYNTAX: fastcgi_cache_path path [levels=levels]

[use_temp_path=on|off] keys_zone=name:size [inactive=time]

[max_size=size] [min_free=size] [manager_files=number]

[manager_sleep=time] [manager_threshold=time]

[loader_files=number] [loader_sleep=time]

[loader_threshold=time] [purger=on|off]

[purger_files=number] [purger_sleep=time]

[purger_threshold=time];

Default —

Context: http
```

Sets the path and other parameters of a cache. Cache data are stored in files. Both the key and file name in a cache are a result of applying the MD5 function to the proxied URL.

The levels parameter defines hierarchy levels of a cache: from 1 to 3, each level accepts values 1 or 2. For example, in the following configuration

Nginx, Inc. p.135 of 506

fastcgi_cache_path /data/nginx/cache levels=1:2 keys_zone=one:10m;

file names in a cache will look like this:

/data/nginx/cache/c/29/b7f54b2df7773722d382f4809d65029c

A cached response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the cache can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both cache and a directory holding temporary files are put on the same file system. A directory for temporary files is set based on the use_temp_path parameter (1.7.10). If this parameter is omitted or set to the value on, the directory set by the fastcgi_temp_path directive for the given location will be used. If the value is set to off, temporary files will be put directly in the cache directory.

In addition, all active keys and information about data are stored in a shared memory zone, whose *name* and *size* are configured by the keys_zone parameter. One megabyte zone can store about 8 thousand keys.

As part of commercial subscription, the shared memory zone also stores extended cache information, thus, it is required to specify a larger zone size for the same number of keys. For example, one megabyte zone can store about 4 thousand keys.

Cached data that are not accessed during the time specified by the inactive parameter get removed from the cache regardless of their freshness. By default, inactive is set to 10 minutes.

The special "cache manager" process monitors the maximum cache size set by the max_size parameter, and the minimum amount of free space set by the min_free (1.19.1) parameter on the file system with cache. When the size is exceeded or there is not enough free space, it removes the least recently used data. The data is removed in iterations configured by manager_files, manager_threshold, and manager_sleep parameters (1.11.5). During one iteration no more than manager_files items are deleted (by default, 100). The duration of one iteration is limited by the manager_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the manager_sleep parameter (by default, 50 milliseconds) is made.

A minute after the start the special "cache loader" process is activated. It loads information about previously cached data stored on file system into a cache zone. The loading is also done in iterations. During one iteration no more than loader_files items are loaded (by default, 100). Besides, the duration of one iteration is limited by the loader_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the loader_sleep parameter (by default, 50 milliseconds) is made.

Nginx, Inc. p.136 of 506

Additionally, the following parameters are available as part of our commercial subscription:

```
purger=on|off
```

Instructs whether cache entries that match a wildcard key will be removed from the disk by the cache purger (1.7.12). Setting the parameter to on (default is off) will activate the "cache purger" process that permanently iterates through all cache entries and deletes the entries that match the wildcard key.

```
purger files=number
```

Sets the number of items that will be scanned during one iteration (1.7.12). By default, purger_files is set to 10.

```
purger_threshold=number
```

Sets the duration of one iteration (1.7.12). By default, purger_-threshold is set to 50 milliseconds.

```
purger_sleep=number
```

Sets a pause between iterations (1.7.12). By default, purger_sleep is set to 50 milliseconds.

In versions 1.7.3, 1.7.7, and 1.11.10 cache header format has been changed. Previously cached responses will be considered invalid after upgrading to a newer nginx version.

fastcgi_cache_purge

```
SYNTAX: fastcgi_cache_purgestring ...;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.5.7.
```

Defines conditions under which the request will be considered a cache purge request. If at least one value of the string parameters is not empty and is not equal to "0" then the cache entry with a corresponding cache key is removed. The result of successful operation is indicated by returning the 204 No Content response.

If the cache key of a purge request ends with an asterisk (" \star "), all cache entries matching the wildcard key will be removed from the cache. However, these entries will remain on the disk until they are deleted for either inactivity, or processed by the cache purger (1.7.12), or a client attempts to access them.

Example configuration:

```
fastcgi_cache_path /data/nginx/cache keys_zone=cache_zone:10m;

map $request_method $purge_method {
   PURGE 1;
   default 0;
}

server {
   ...
```

Nginx, Inc. p.137 of 506

```
location / {
    fastcgi_pass backend;
    fastcgi_cache cache_zone;
    fastcgi_cache_key $uri;
    fastcgi_cache_purge $purge_method;
}
```

This functionality is available as part of our commercial subscription.

fastcgi_cache_revalidate

```
SYNTAX: fastcgi_cache_revalidate on | off;
Default off
Context: http, server, location
This directive appeared in version 1.5.7.
```

Enables revalidation of expired cache items using conditional requests with the If-Modified-Since and If-None-Match header fields.

fastcgi_cache_use_stale

```
SYNTAX: fastcgi_cache_use_stale error | timeout | invalid_header | updating | http_500 | http_503 | http_403 | http_404 | http_429 | off ...;

DEFAULT off
CONTEXT: http, server, location
```

Determines in which cases a stale cached response can be used when an error occurs during communication with the FastCGI server. The directive's parameters match the parameters of the fastcgi_next_upstream directive.

The error parameter also permits using a stale cached response if a FastCGI server to process a request cannot be selected.

Additionally, the updating parameter permits using a stale cached response if it is currently being updated. This allows minimizing the number of accesses to FastCGI servers when updating cached data.

Using a stale cached response can also be enabled directly in the response header for a specified number of seconds after the response became stale (1.11.10). This has lower priority than using the directive parameters.

- The "stale-while-revalidate" extension of the Cache-Control header field permits using a stale cached response if it is currently being updated.
- The "stale-if-error" extension of the Cache-Control header field permits using a stale cached response in case of an error.

To minimize the number of accesses to FastCGI servers when populating a new cache element, the fastcgi_cache_lock directive can be used.

Nginx, Inc. p.138 of 506

fastcgi_cache_valid

```
SYNTAX: fastcgi_cache_valid [code ...] time;
DEFAULT —
CONTEXT: http, server, location
```

Sets caching time for different response codes. For example, the following directives

set 10 minutes of caching for responses with codes 200 and 302 and 1 minute for responses with code 404.

If only caching *time* is specified

```
fastcgi_cache_valid 5m;
```

then only 200, 301, and 302 responses are cached.

In addition, the any parameter can be specified to cache any responses:

```
fastcgi_cache_valid 200 302 10m;
fastcgi_cache_valid 301 1h;
fastcgi_cache_valid any 1m;
```

Parameters of caching can also be set directly in the response header. This has higher priority than setting of caching time using the directive.

- The X-Accel-Expires header field sets caching time of a response in seconds. The zero value disables caching for a response. If the value starts with the @ prefix, it sets an absolute time in seconds since Epoch, up to which the response may be cached.
- If the header does not include the X-Accel-Expires field, parameters of caching may be set in the header fields Expires or Cache-Control.
- If the header includes the Set-Cookie field, such a response will not be cached.
- If the header includes the Vary field with the special value "*", such a response will not be cached (1.7.7). If the header includes the Vary field with another value, such a response will be cached taking into account the corresponding request header fields (1.7.7).

Processing of one or more of these response header fields can be disabled using the fastcgi_ignore_headers directive.

fastcgi_catch_stderr

```
SYNTAX: fastcgi_catch_stderr string;

DEFAULT —

CONTEXT: http, server, location
```

Nginx, Inc. p.139 of 506

Sets a string to search for in the error stream of a response received from a FastCGI server. If the *string* is found then it is considered that the FastCGI server has returned an invalid response. This allows handling application errors in nginx, for example:

```
location /php/ {
   fastcgi_pass backend:9000;
   ...
   fastcgi_catch_stderr "PHP Fatal error";
   fastcgi_next_upstream error timeout invalid_header;
}
```

$fastcgi_connect_timeout$

```
SYNTAX: fastcgi_connect_timeout time;
```

DEFAULT 60s

Context: http, server, location

Defines a timeout for establishing a connection with a FastCGI server. It should be noted that this timeout cannot usually exceed 75 seconds.

fastcgi_force_ranges

```
SYNTAX: fastcgi_force_ranges on | off;
DEFAULT off
CONTEXT: http, server, location
This directive appeared in version 1.7.7.
```

Enables byte-range support for both cached and uncached responses from the FastCGI server regardless of the Accept-Ranges field in these responses.

fastcgi_hide_header

```
SYNTAX: fastcgi_hide_header field;

DEFAULT —

CONTEXT: http, server, location
```

By default, nginx does not pass the header fields Status and X-Accel-... from the response of a FastCGI server to a client. The fastcgi_hide_header directive sets additional fields that will not be passed. If, on the contrary, the passing of fields needs to be permitted, the fastcgi_pass_header directive can be used.

fastcgi_ignore_client_abort

```
SYNTAX: fastcgi_ignore_client_abort on | off;
Default off
Context: http, server, location
```

Determines whether the connection with a FastCGI server should be closed when a client closes the connection without waiting for a response.

Nginx, Inc. p.140 of 506

fastcgi_ignore_headers

SYNTAX: fastcgi_ignore_headers field ...;
DEFAULT —

Context: http, server, location

Disables processing of certain response header fields from the FastCGI The following fields can be ignored: X-Accel-Redirect, X-Accel-Expires, X-Accel-Limit-Rate X-Accel-Buffering (1.1.6), X-Accel-Charset (1.1.6), Expires, Cache-Control, Set-Cookie (0.8.44), and Vary (1.7.7).

If not disabled, processing of these header fields has the following effect:

- X-Accel-Expires, Expires, Cache-Control, Set-Cookie, and Vary set the parameters of response caching;
- X-Accel-Redirect performs an internal redirect to the specified URI;
- X-Accel-Limit-Rate sets the rate limit for transmission of a response to a client;
- X-Accel-Buffering enables or disables buffering of a response;
- X-Accel-Charset sets the desired charset of a response.

fastcgi_index

SYNTAX: fastcgi_index name;

Default —

Context: http, server, location

Sets a file name that will be appended after a URI that ends with a slash, in the value of the \$fastcgi_script_name variable. For example, with these settings

```
fastcgi_index index.php;
fastcgi_param SCRIPT_FILENAME /home/www/scripts/php$fastcgi_script_name;
```

and the "/page.php" request, the SCRIPT_FILENAME parameter will be equal to "/home/www/scripts/php/page.php", and with the "/" request it will be equal to "/home/www/scripts/php/index.php".

fastcgi_intercept_errors

SYNTAX: fastcgi_intercept_errors on | off;

Default off

Context: http, server, location

Determines whether FastCGI server responses with codes greater than or equal to 300 should be passed to a client or be intercepted and redirected to nginx for processing with the error_page directive.

Nginx, Inc. p.141 of 506

fastcgi_keep_conn

SYNTAX: fastcgi_keep_conn on | off;

Default off

Context: http, server, location
This directive appeared in version 1.1.4.

By default, a FastCGI server will close a connection right after sending the response. However, when this directive is set to the value on, nginx will instruct a FastCGI server to keep connections open. This is necessary, in particular, for keepalive connections to FastCGI servers to function.

fastcgi_limit_rate

SYNTAX: fastcgi_limit_rate rate;

Default 0

Context: http, server, location
This directive appeared in version 1.7.7.

Limits the speed of reading the response from the FastCGI server. The rate is specified in bytes per second. The zero value disables rate limiting. The limit is set per a request, and so if nginx simultaneously opens two connections to the FastCFI server, the overall rate will be twice as much as the specified limit. The limitation works only if buffering of responses from the FastCGI server is enabled.

fastcgi_max_temp_file_size

SYNTAX: fastcgi_max_temp_file_size size;

DEFAULT 1024m

Context: http, server, location

When buffering of responses from the FastCGI server is enabled, and the whole response does not fit into the buffers set by the fastcgi_buffer_size and fastcgi_buffers directives, a part of the response can be saved to a temporary file. This directive sets the maximum size of the temporary file. The size of data written to the temporary file at a time is set by the fastcgi_temp_file_write_size directive.

The zero value disables buffering of responses to temporary files.

This restriction does not apply to responses that will be cached or stored on disk.

fastcgi_next_upstream

SYNTAX: **fastcgi_next_upstream** error | timeout | invalid_header | http_500 | http_503 | http_403 | http_404 | http_429 |

non_idempotent | off ...;

DEFAULT error timeout CONTEXT: http, server, location

Nginx, Inc. p.142 of 506

Specifies in which cases a request should be passed to the next server:

```
error
    an error occurred while establishing a connection with the server, passing
    a request to it, or reading the response header;
timeout
    a timeout has occurred while establishing a connection with the server,
    passing a request to it, or reading the response header;
invalid_header
    a server returned an empty or invalid response;
http_500
    a server returned a response with the code 500;
http 503
    a server returned a response with the code 503;
http 403
    a server returned a response with the code 403;
http 404
    a server returned a response with the code 404;
http 429
    a server returned a response with the code 429 (1.11.13);
non_idempotent
```

normally, requests with a non-idempotent method (POST, LOCK, PATCH) are not passed to the next server if a request has been sent to an upstream server (1.9.13); enabling this option explicitly allows retrying such requests;

off

disables passing a request to the next server.

One should bear in mind that passing a request to the next server is only possible if nothing has been sent to a client yet. That is, if an error or timeout occurs in the middle of the transferring of a response, fixing this is impossible.

The directive also defines what is considered an unsuccessful attempt of communication with a server. The cases of error, timeout and invalid_header are always considered unsuccessful attempts, even if they are not specified in the directive. The cases of http_500, http_503, and http_-429 are considered unsuccessful attempts only if they are specified in the directive. The cases of http_403 and http_404 are never considered unsuccessful attempts.

Passing a request to the next server can be limited by the number of tries and by time.

$fastcgi_next_upstream_timeout$

```
Syntax:
          fastcgi_next_upstream_timeout time;
Default 0
Context: http, server, location
This directive appeared in version 1.7.5.
```

Nginx, Inc. p.143 of 506 Limits the time during which a request can be passed to the next server. The 0 value turns off this limitation.

fastcgi_next_upstream_tries

This directive appeared in version 1.7.5.

SYNTAX: fastcgi_next_upstream_tries number;
DEFAULT 0
CONTEXT: http, server, location

Limits the number of possible tries for passing a request to the next server. The 0 value turns off this limitation.

fastcgi_no_cache

SYNTAX: **fastcgi_no_cache** string ...;

DEFAULT —

CONTEXT: http, server, location

Defines conditions under which the response will not be saved to a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be saved:

```
fastcgi_no_cache $cookie_nocache $arg_nocache$arg_comment;
fastcgi_no_cache $http_pragma $http_authorization;
```

Can be used along with the fastcgi_cache_bypass directive.

fastcgi_param

```
SYNTAX: fastcgi_param parameter value [if_not_empty];
DEFAULT —
CONTEXT: http, server, location
```

Sets a parameter that should be passed to the FastCGI server. The value can contain text, variables, and their combination. These directives are inherited from the previous configuration level if and only if there are no fastcgi_param directives defined on the current level.

The following example shows the minimum required settings for PHP:

```
fastcgi_param SCRIPT_FILENAME /home/www/scripts/php$fastcgi_script_name;
fastcgi_param QUERY_STRING $query_string;
```

The SCRIPT_FILENAME parameter is used in PHP for determining the script name, and the QUERY_STRING parameter is used to pass request parameters.

For scripts that process POST requests, the following three parameters are also required:

```
fastcgi_param REQUEST_METHOD $request_method;
fastcgi_param CONTENT_TYPE $content_type;
```

Nginx, Inc. p.144 of 506

```
fastcgi_param CONTENT_LENGTH $content_length;
```

If PHP was built with the --enable-force-cgi-redirect configuration parameter, the REDIRECT_STATUS parameter should also be passed with the value "200":

```
fastcgi_param REDIRECT_STATUS 200;
```

If the directive is specified with if_not_empty (1.1.11) then such a parameter will be passed to the server only if its value is not empty:

```
fastcgi_param HTTPS $https if_not_empty;
```

fastcgi_pass

SYNTAX: fastcgi_pass address;

Default —

Context: location, if in location

Sets the address of a FastCGI server. The address can be specified as a domain name or IP address, and a port:

```
fastcgi_pass localhost:9000;
```

or as a UNIX-domain socket path:

```
fastcgi_pass unix:/tmp/fastcgi.socket;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

Parameter value can contain variables. In this case, if an address is specified as a domain name, the name is searched among the described server groups, and, if not found, is determined using a resolver.

fastcgi_pass_header

SYNTAX: fastcgi_pass_header field;

Default —

Context: http, server, location

Permits passing otherwise disabled header fields from a FastCGI server to a client.

fastcgi_pass_request_body

SYNTAX: fastcgi_pass_request_body on | off;

Default on

Context: http, server, location

Nginx, Inc. p.145 of 506

Indicates whether the original request body is passed to the FastCGI server. See also the fastcgi_pass_request_headers directive.

$fastcgi_pass_request_headers$

```
\label{eq:SYNTAX:} \textbf{fastcgi\_pass\_request\_headers} \ \texttt{on} \ | \ \texttt{off};
```

Default on

CONTEXT: http, server, location

Indicates whether the header fields of the original request are passed to the FastCGI server. See also the fastcgi_pass_request_body directive.

fastcgi_read_timeout

```
SYNTAX: fastcgi_read_timeout time;
```

DEFAULT 60s

Context: http, server, location

Defines a timeout for reading a response from the FastCGI server. The timeout is set only between two successive read operations, not for the transmission of the whole response. If the FastCGI server does not transmit anything within this time, the connection is closed.

fastcgi_request_buffering

```
SYNTAX: fastcgi_request_buffering on | off;
```

Default on

Context: http, server, location
This directive appeared in version 1.7.11.

Enables or disables buffering of a client request body.

When buffering is enabled, the entire request body is read from the client before sending the request to a FastCGI server.

When buffering is disabled, the request body is sent to the FastCGI server immediately as it is received. In this case, the request cannot be passed to the next server if nginx already started sending the request body.

fastcgi_send_lowat

SYNTAX: fastcgi_send_lowat size;

Default 0

Context: http, server, location

If the directive is set to a non-zero value, nginx will try to minimize the number of send operations on outgoing connections to a FastCGI server by using either NOTE_LOWAT flag of the kqueue method, or the SO_SNDLOWAT socket option, with the specified *size*.

This directive is ignored on Linux, Solaris, and Windows.

Nginx, Inc. p.146 of 506

fastcgi_send_timeout

SYNTAX: fastcgi_send_timeout time;

DEFAULT 60s

Context: http, server, location

Sets a timeout for transmitting a request to the FastCGI server. The timeout is set only between two successive write operations, not for the transmission of the whole request. If the FastCGI server does not receive anything within this time, the connection is closed.

fastcgi_socket_keepalive

SYNTAX: fastcgi_socket_keepalive on | off;

Default off

Context: http, server, location
This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to a FastCGI server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

$fastcgi_split_path_info$

SYNTAX: fastcgi_split_path_info regex;

Default — Context: location

Defines a regular expression that captures a value for the \$fastcgi_path_info variable. The regular expression should have two captures: the first becomes a value of the \$fastcgi_script_name variable, the second becomes a value of the \$fastcgi_path_info variable. For example, with these settings

and the "/show.php/article/0001" request, the SCRIPT_FILENAME parameter will be equal to "/path/to/php/show.php", and the PATH_-INFO parameter will be equal to "/article/0001".

fastcgi_store

SYNTAX: fastcgi_store on | off | string;

Default off

CONTEXT: http, server, location

Enables saving of files to a disk. The on parameter saves files with paths corresponding to the directives alias or root. The off parameter disables

Nginx, Inc. p.147 of 506

saving of files. In addition, the file name can be set explicitly using the *string* with variables:

```
fastcgi_store /data/www$original_uri;
```

The modification time of files is set according to the received Last-Modified response header field. The response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the persistent store can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both saved files and a directory holding temporary files, set by the fastcgi_temp_path directive, are put on the same file system.

This directive can be used to create local copies of static unchangeable files, e.g.:

fastcgi_store_access

SYNTAX: fastcgi_store_access users:permissions ...;

DEFAULT user:rw

Context: http, server, location

Sets access permissions for newly created files and directories, e.g.:

```
fastcgi_store_access user:rw group:rw all:r;
```

If any group or all access permissions are specified then user permissions may be omitted:

```
fastcgi_store_access group:rw all:r;
```

Nginx, Inc. p.148 of 506

fastcgi_temp_file_write_size

SYNTAX: fastcgi_temp_file_write_size size;

Default 8k|16k

Context: http, server, location

Limits the *size* of data written to a temporary file at a time, when buffering of responses from the FastCGI server to temporary files is enabled. By default, *size* is limited by two buffers set by the fastcgi_buffer_size and fastcgi_buffers directives. The maximum size of a temporary file is set by the fastcgi_max_temp_file_size directive.

$fastcgi_temp_path$

```
SYNTAX: fastcgi_temp_path path [level1 [level2 [level3]]];
```

DEFAULT fastcgi_temp CONTEXT: http, server, location

Defines a directory for storing temporary files with data received from FastCGI servers. Up to three-level subdirectory hierarchy can be used underneath the specified directory. For example, in the following configuration

```
fastcgi_temp_path /spool/nginx/fastcgi_temp 1 2;
```

a temporary file might look like this:

```
/spool/nginx/fastcgi_temp/7/45/00000123457
```

See also the use_temp_path parameter of the fastcgi_cache_path directive.

2.14.4 Parameters Passed to a FastCGI Server

HTTP request header fields are passed to a FastCGI server as parameters. In applications and scripts running as FastCGI servers, these parameters are usually made available as environment variables. For example, the User-Agent header field is passed as the HTTP_USER_AGENT parameter. In addition to HTTP request header fields, it is possible to pass arbitrary parameters using the fastcgi_param directive.

2.14.5 Embedded Variables

The ngx_http_fastcgi_module module supports embedded variables that can be used to set parameters using the fastcgi_param directive:

```
fastcgi\_script\_name
```

request URI or, if a URI ends with a slash, request URI with an index file name configured by the fastcgi_index directive appended to it.

Nginx, Inc. p.149 of 506

This variable can be used to set the SCRIPT_FILENAME and PATH_-TRANSLATED parameters that determine the script name in PHP. For example, for the "/info/" request with the following directives

```
fastcgi_index index.php;
fastcgi_param SCRIPT_FILENAME /home/www/scripts/php$fastcgi_script_name;
```

the SCRIPT_FILENAME parameter will be equal to "/home/www/scripts/php/info/index.php".

When using the fastcgi_split_path_info directive, the \$fastcgi_script_name variable equals the value of the first capture set by the directive.

$\$fastcgi_path_info$

the value of the second capture set by the fastcgi_split_path_info
directive. This variable can be used to set the PATH_INFO parameter.

Nginx, Inc. p.150 of 506

2.15 Module ngx_http_flv_module

2.15.1	Summary	5.
2.15.2	Example Configuration	51
2.15.3	Directives	51
	flv 1.	5

2.15.1 **Summary**

The ngx_http_flv_module module provides pseudo-streaming server-side support for Flash Video (FLV) files.

It handles requests with the start argument in the request URI's query string specially, by sending back the contents of a file starting from the requested byte offset and with the prepended FLV header.

This module is not built by default, it should be enabled with the --with-http_flv_module configuration parameter.

2.15.2 Example Configuration

```
location ~ \.flv$ {
   flv;
}
```

2.15.3 Directives

 \mathbf{flv}

SYNTAX: **flv**;
DEFAULT —
CONTEXT: location

Turns on module processing in a surrounding location.

Nginx, Inc. p.151 of 506

2.16 Module ngx_http_geo_module

2.16.1	Summary	152
2.16.2	Example Configuration	52
2.16.3	Directives	52
	geo	52

2.16.1 Summary

The ngx_http_geo_module module creates variables with values depending on the client IP address.

2.16.2 Example Configuration

```
geo $geo {
    default          0;

    127.0.0.1          2;
    192.168.1.0/24 1;
    10.1.0.0/16     1;

    ::1          2;
    2001:0db8::/32 1;
}
```

2.16.3 Directives

geo

```
SYNTAX: geo [$address] $variable { ...}

Default —

Context: http
```

Describes the dependency of values of the specified variable on the client IP address. By default, the address is taken from the *\$remote_addr* variable, but it can also be taken from another variable (0.7.27), for example:

```
geo $arg_remote_addr $geo {
    ...;
}
```

Since variables are evaluated only when used, the mere existence of even a large number of declared "geo" variables does not cause any extra costs for request processing.

If the value of a variable does not represent a valid IP address then the "255.255.255" address is used.

Addresses are specified either as prefixes in CIDR notation (including individual addresses) or as ranges (0.7.23).

Nginx, Inc. p.152 of 506

IPv6 prefixes are supported starting from versions 1.3.10 and 1.2.7.

The following special parameters are also supported:

delete

deletes the specified network (0.7.23).

default

a value set to the variable if the client address does not match any of the specified addresses. When addresses are specified in CIDR notation, "0.0.0.0/0" and "::/0" can be used instead of default. When default is not specified, the default value will be an empty string.

include

includes a file with addresses and values. There can be several inclusions. proxy

defines trusted addresses (0.8.7, 0.7.63). When a request comes from a trusted address, an address from the X-Forwarded-For request header field will be used instead. In contrast to the regular addresses, trusted addresses are checked sequentially.

Trusted IPv6 addresses are supported starting from versions 1.3.0 and 1.2.1.

proxy_recursive

enables recursive address search (1.3.0, 1.2.1). If recursive search is disabled then instead of the original client address that matches one of the trusted addresses, the last address sent in X-Forwarded-For will be used. If recursive search is enabled then instead of the original client address that matches one of the trusted addresses, the last non-trusted address sent in X-Forwarded-For will be used.

ranges

indicates that addresses are specified as ranges (0.7.23). This parameter should be the first. To speed up loading of a geo base, addresses should be put in ascending order.

Example:

```
geo $country {
    default
                    ZZ:
    include
                    conf/geo.conf;
                   127.0.0.0/16;
    delete
                   192.168.100.0/24;
    proxy
                    2001:0db8::/32;
    proxy
    127.0.0.0/24
                    US;
    127.0.0.1/32
                    RU;
    10.1.0.0/16
                   RU:
    192.168.1.0/24 UK;
```

The conf/geo.conf file could contain the following lines:

Nginx, Inc. p.153 of 506

```
10.2.0.0/16 RU;
192.168.2.0/24 RU;
```

A value of the most specific match is used. For example, for the 127.0.0.1 address the value "RU" will be chosen, not "US".

Example with ranges:

Nginx, Inc. p.154 of 506

2.17 Module ngx_http_geoip_module

2.17.1	Summary)5
2.17.2	Example Configuration	5
2.17.3	Directives	5
	geoip_country	5
	geoip_city	6
	geoip_org	7
	geoip_proxy	7
	geoip_proxy_recursive	7

2.17.1 **Summary**

The ngx_http_geoip_module module (0.8.6+) creates variables with values depending on the client IP address, using the precompiled MaxMind databases.

When using the databases with IPv6 support (1.3.12, 1.2.7), IPv4 addresses are looked up as IPv4-mapped IPv6 addresses.

This module is not built by default, it should be enabled with the --with-http_geoip_module configuration parameter.

This module requires the MaxMind GeoIP library.

2.17.2 Example Configuration

2.17.3 Directives

geoip_country

```
SYNTAX: geoip_country file;
DEFAULT —
CONTEXT: http
```

Specifies a database used to determine the country depending on the client IP address. The following variables are available when using this database:

```
$geoip_country_code two-letter country code, for example, "RU", "US". $geoip_country_code3 three-letter country code, for example, "RUS", "USA".
```

Nginx, Inc. p.155 of 506

$$geoip_country_name$

country name, for example, "Russian Federation", "United States".

geoip_city

SYNTAX: **geoip_city** *file*;

Default — Context: http

Specifies a database used to determine the country, region, and city depending on the client IP address. The following variables are available when using this database:

\$geoip_area_code

telephone area code (US only).

This variable may contain outdated information since the corresponding database field is deprecated.

\$geoip_city_continent_code

two-letter continent code, for example, "EU", "NA".

\$qeoip_city_country_code

two-letter country code, for example, "RU", "US".

\$geoip_city_country_code3

three-letter country code, for example, "RUS", "USA".

 $\$geoip_city_country_name$

country name, for example, "Russian Federation", "United States".

\$qeoip_dma_code

DMA region code in US (also known as "metro code"), according to the geotargeting in Google AdWords API.

\$qeoip_latitude

latitude.

 $\$geoip_longitude$

longitude.

\$qeoip_region

two-symbol country region code (region, territory, state, province, federal land and the like), for example, "48", "DC".

\$geoip_region_name

country region name (region, territory, state, province, federal land and the like), for example, "Moscow City", "District of Columbia".

\$qeoip_city

city name, for example, "Moscow", "Washington".

\$geoip_postal_code

postal code.

Nginx, Inc. p.156 of 506

geoip_org

```
SYNTAX: geoip_org file;
```

DEFAULT — CONTEXT: http

This directive appeared in version 1.0.3.

Specifies a database used to determine the organization depending on the client IP address. The following variable is available when using this database:

```
$geoip_org
```

organization name, for example, "The University of Melbourne".

geoip_proxy

```
SYNTAX: geoip_proxy address | CIDR;
```

Default — Context: http

This directive appeared in versions 1.3.0 and 1.2.1.

Defines trusted addresses. When a request comes from a trusted address, an address from the X-Forwarded-For request header field will be used instead.

geoip_proxy_recursive

SYNTAX: **geoip_proxy_recursive** on | off;

DEFAULT off CONTEXT: http

This directive appeared in versions 1.3.0 and 1.2.1.

If recursive search is disabled then instead of the original client address that matches one of the trusted addresses, the last address sent in X-Forwarded-For will be used. If recursive search is enabled then instead of the original client address that matches one of the trusted addresses, the last non-trusted address sent in X-Forwarded-For will be used.

Nginx, Inc. p.157 of 506

2.18 Module ngx_http_grpc_module

2.18.1	Summary
2.18.2	Example Configuration
2.18.3	Directives
	grpc_bind
	grpc_buffer_size
	grpc_connect_timeout
	grpc_hide_header
	grpc_ignore_headers
	grpc_intercept_errors
	grpc_next_upstream
	grpc_next_upstream_timeout
	grpc_next_upstream_tries
	grpc_pass
	grpc_pass_header
	grpc_read_timeout
	grpc_send_timeout
	grpc_set_header
	grpc_socket_keepalive
	grpc_ssl_certificate
	grpc_ssl_certificate_key
	grpc_ssl_ciphers
	grpc_ssl_conf_command
	grpc_ssl_crl
	grpc_ssl_name
	grpc_ssl_password_file
	grpc_ssl_protocols
	grpc_ssl_server_name
	grpc_ssl_session_reuse
	grpc_ssl_trusted_certificate
	grpc_ssl_verify
	grpc_ssl_verify_depth

2.18.1 Summary

The ngx_http_grpc_module module allows passing requests to a gRPC server (1.13.10). The module requires the ngx_http_v2_module module.

2.18.2 Example Configuration

```
server {
    listen 9000 http2;

    location / {
        grpc_pass 127.0.0.1:9000;
    }
}
```

Nginx, Inc. p.158 of 506

2.18.3 Directives

grpc_bind

SYNTAX: **grpc_bind** address [transparent] | off;

Default —

Context: http, server, location

Makes outgoing connections to a gRPC server originate from the specified local IP address with an optional port. Parameter value can contain variables. The special value off cancels the effect of the grpc_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address and port.

The transparent parameter allows outgoing connections to a gRPC server originate from a non-local IP address, for example, from a real IP address of a client:

```
grpc_bind $remote_addr transparent;
```

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the gRPC server.

grpc_buffer_size

SYNTAX: grpc_buffer_size size;

DEFAULT 4k | 8k

Context: http, server, location

Sets the *size* of the buffer used for reading the response received from the gRPC server. The response is passed to the client synchronously, as soon as it is received.

grpc_connect_timeout

SYNTAX: grpc_connect_timeout time;

DEFAULT 60s

Context: http, server, location

Defines a timeout for establishing a connection with a gRPC server. It should be noted that this timeout cannot usually exceed 75 seconds.

Nginx, Inc. p.159 of 506

grpc_hide_header

SYNTAX: grpc_hide_header field;
DEFAULT —

Context: http, server, location

By default, nginx does not pass the header fields Date, Server, and X-Accel-... from the response of a gRPC server to a client. The grpc_hide_header directive sets additional fields that will not be passed. If, on the contrary, the passing of fields needs to be permitted, the grpc_pass_header directive can be used.

grpc_ignore_headers

```
SYNTAX: grpc_ignore_headers field ...;

DEFAULT —

CONTEXT: http, server, location
```

Disables processing of certain response header fields from the gRPC server. The following fields can be ignored: X-Accel-Redirect and X-Accel-Charset.

If not disabled, processing of these header fields has the following effect:

- X-Accel-Redirect performs an internal redirect to the specified URI;
- X-Accel-Charset sets the desired charset of a response.

grpc_intercept_errors

```
SYNTAX: grpc_intercept_errors on | off;
DEFAULT off
CONTEXT: http, server, location
```

Determines whether gRPC server responses with codes greater than or equal to 300 should be passed to a client or be intercepted and redirected to nginx for processing with the error_page directive.

grpc_next_upstream

```
SYNTAX: grpc_next_upstream error | timeout | invalid_header | http_500 | http_502 | http_503 | http_504 | http_403 | http_404 | http_429 | non_idempotent | off ...;

DEFAULT error timeout

CONTEXT: http, server, location
```

Specifies in which cases a request should be passed to the next server:

```
error
```

an error occurred while establishing a connection with the server, passing a request to it, or reading the response header;

Nginx, Inc. p.160 of 506

```
timeout
    a timeout has occurred while establishing a connection with the server,
    passing a request to it, or reading the response header;
invalid header
    a server returned an empty or invalid response;
http_500
    a server returned a response with the code 500;
http_502
    a server returned a response with the code 502;
http_503
    a server returned a response with the code 503;
http_504
    a server returned a response with the code 504;
http_403
    a server returned a response with the code 403;
http 404
    a server returned a response with the code 404;
http 429
    a server returned a response with the code 429;
non_idempotent
    normally, requests with a non-idempotent method (POST, LOCK, PATCH)
    are not passed to the next server if a request has been sent to an upstream
    server; enabling this option explicitly allows retrying such requests;
off
    disables passing a request to the next server.
```

One should bear in mind that passing a request to the next server is only possible if nothing has been sent to a client yet. That is, if an error or timeout occurs in the middle of the transferring of a response, fixing this is impossible.

The directive also defines what is considered an unsuccessful attempt of communication with a server. The cases of error, timeout and invalid_header are always considered unsuccessful attempts, even if they are not specified in the directive. The cases of http_500, http_502, http_503, http_504, and http_429 are considered unsuccessful attempts only if they are specified in the directive. The cases of http_403 and http_404 are never considered unsuccessful attempts.

Passing a request to the next server can be limited by the number of tries and by time.

grpc_next_upstream_timeout

```
SYNTAX: grpc_next_upstream_timeout time;
DEFAULT 0
CONTEXT: http, server, location
```

Limits the time during which a request can be passed to the next server. The 0 value turns off this limitation.

Nginx, Inc. p.161 of 506

grpc_next_upstream_tries

SYNTAX: grpc_next_upstream_tries number;

Default 0

Context: http, server, location

Limits the number of possible tries for passing a request to the next server. The 0 value turns off this limitation.

grpc_pass

SYNTAX: grpc_pass address;

Default —

Context: location, if in location

Sets the gRPC server address. The address can be specified as a domain name or IP address, and a port:

```
grpc_pass localhost:9000;
```

or as a UNIX-domain socket path:

```
grpc_pass unix:/tmp/grpc.socket;
```

Alternatively, the "grpc://" scheme can be used:

```
grpc_pass grpc://127.0.0.1:9000;
```

To use gRPC over SSL, the "grpcs://" scheme should be used:

```
grpc_pass grpcs://127.0.0.1:443;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

Parameter value can contain variables (1.17.8). In this case, if an address is specified as a domain name, the name is searched among the described server groups, and, if not found, is determined using a resolver.

grpc_pass_header

SYNTAX: grpc_pass_header field;

Default —

CONTEXT: http, server, location

Permits passing otherwise disabled header fields from a gRPC server to a client.

Nginx, Inc. p.162 of 506

grpc_read_timeout

SYNTAX: grpc_read_timeout time;

DEFAULT 60s

CONTEXT: http, server, location

Defines a timeout for reading a response from the gRPC server. The timeout is set only between two successive read operations, not for the transmission of the whole response. If the gRPC server does not transmit anything within this time, the connection is closed.

grpc_send_timeout

SYNTAX: grpc_send_timeout time;

DEFAULT 60s

Context: http, server, location

Sets a timeout for transmitting a request to the gRPC server. The timeout is set only between two successive write operations, not for the transmission of the whole request. If the gRPC server does not receive anything within this time, the connection is closed.

grpc_set_header

SYNTAX: grpc_set_header field value;

DEFAULT Content-Length \$content_length

Context: http, server, location

Allows redefining or appending fields to the request header passed to the gRPC server. The *value* can contain text, variables, and their combinations. These directives are inherited from the previous configuration level if and only if there are no grpc_set_header directives defined on the current level.

If the value of a header field is an empty string then this field will not be passed to a gRPC server:

```
grpc_set_header Accept-Encoding "";
```

grpc_socket_keepalive

SYNTAX: grpc_socket_keepalive on | off;

Default off

CONTEXT: http, server, location
This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to a gRPC server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

Nginx, Inc. p.163 of 506

grpc_ssl_certificate

SYNTAX: grpc_ssl_certificate file;

Default —

Context: http, server, location

Specifies a *file* with the certificate in the PEM format used for authentication to a gRPC SSL server.

grpc_ssl_certificate_key

```
SYNTAX: grpc_ssl_certificate_key file;
```

Default —

Context: http, server, location

Specifies a *file* with the secret key in the PEM format used for authentication to a gRPC SSL server.

The value engine: name: id can be specified instead of the file, which loads a secret key with a specified id from the OpenSSL engine name.

grpc_ssl_ciphers

SYNTAX: grpc_ssl_ciphers ciphers;

DEFAULT DEFAULT

Context: http, server, location

Specifies the enabled ciphers for requests to a gRPC SSL server. The ciphers are specified in the format understood by the OpenSSL library.

The full list can be viewed using the "openssl ciphers" command.

grpc_ssl_conf_command

SYNTAX: grpc_ssl_conf_command;

Default —

CONTEXT: http, server, location

This directive appeared in version 1.19.4.

Sets arbitrary OpenSSL configuration commands when establishing a connection with the gRPC SSL server.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several grpc_ssl_conf_command directives can be specified on the same level. These directives are inherited from the previous configuration level if and only if there are no grpc_ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

Nginx, Inc. p.164 of 506

grpc_ssl_crl

SYNTAX: grpc_ssl_crl file;

Default —

Context: http, server, location

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify the certificate of the gRPC SSL server.

grpc_ssl_name

SYNTAX: **grpc_ssl_name** name; DEFAULT host from grpc_pass CONTEXT: http, server, location

Allows overriding the server name used to verify the certificate of the gRPC SSL server and to be passed through SNI when establishing a connection with the gRPC SSL server.

By default, the host part from grpc_pass is used.

grpc_ssl_password_file

```
SYNTAX: grpc_ssl_password_file file;
```

Default —

Context: http, server, location

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

grpc_ssl_protocols

```
SYNTAX: grpc_ssl_protocols [SSLv2] [SSLv3] [TLSv1] [TLSv1.1]
```

[TLSv1.2] [TLSv1.3];

DEFAULT TLSv1 TLSv1.1 TLSv1.2

Context: http, server, location

Enables the specified protocols for requests to a gRPC SSL server.

grpc_ssl_server_name

```
SYNTAX: grpc_ssl_server_name on | off;
```

Default off

CONTEXT: http, server, location

Enables or disables passing of the server name through TLS Server Name Indication extension (SNI, RFC 6066) when establishing a connection with the gRPC SSL server.

Nginx, Inc. p.165 of 506

grpc_ssl_session_reuse

SYNTAX: grpc_ssl_session_reuse on | off;

Default on

Context: http, server, location

Determines whether SSL sessions can be reused when working with the gRPC server. If the errors "SSL3_GET_FINISHED:digest check failed" appear in the logs, try disabling session reuse.

grpc_ssl_trusted_certificate

```
SYNTAX: grpc_ssl_trusted_certificate file;
```

Default —

CONTEXT: http, server, location

Specifies a *file* with trusted CA certificates in the PEM format used to verify the certificate of the gRPC SSL server.

grpc_ssl_verify

```
SYNTAX: grpc_ssl_verify on | off;
```

Default off

CONTEXT: http, server, location

Enables or disables verification of the gRPC SSL server certificate.

grpc_ssl_verify_depth

```
SYNTAX: grpc_ssl_verify_depth number;
```

Default 1

Context: http, server, location

Sets the verification depth in the gRPC SSL server certificates chain.

Nginx, Inc. p.166 of 506

2.19 Module ngx_http_gunzip_module

2.19.1	Summary	167
2.19.2	Example Configuration	67
2.19.3	Directives	67
	gunzip	167
	gunzip_buffers	67

2.19.1 **Summary**

The ngx_http_gunzip_module module is a filter that decompresses responses with "Content-Encoding: gzip" for clients that do not support "gzip" encoding method. The module will be useful when it is desirable to store data compressed to save space and reduce I/O costs.

This module is not built by default, it should be enabled with the --with-http_qunzip_module configuration parameter.

2.19.2 Example Configuration

```
location /storage/ {
   gunzip on;
   ...
}
```

2.19.3 Directives

gunzip

SYNTAX: gunzip on | off;

Default off

Context: http, server, location

Enables or disables decompression of gzipped responses for clients that lack gzip support. If enabled, the following directives are also taken into account when determining if clients support gzip: gzip_http_version, gzip_proxied, and gzip_disable. See also the gzip_vary directive.

gunzip_buffers

SYNTAX: gunzip_buffers number size;

DEFAULT 32 4k | 16 8k CONTEXT: http, server, location

Sets the *number* and *size* of buffers used to decompress a response. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

Nginx, Inc. p.167 of 506

2.20 Module ngx_http_gzip_module

2.20.1	Summary	5
2.20.2	Example Configuration	8
2.20.3	Directives	8
	gzip	8
	gzip_buffers	9
	gzip_comp_level	9
	gzip_disable	9
	gzip_http_version	9
	gzip_min_length	9
	gzip_proxied	0
	gzip_types	
	gzip_vary	1
2.20.4	Embedded Variables	1

2.20.1 Summary

The ngx_http_gzip_module module is a filter that compresses responses using the "gzip" method. This often helps to reduce the size of transmitted data by half or even more.

When using the SSL/TLS protocol, compressed responses may be subject to BREACH attacks.

2.20.2 Example Configuration

The \$gzip_ratio variable can be used to log the achieved compression ratio.

2.20.3 Directives

gzip

 $\label{eq:Syntax:gzip} \text{Syntax:} \quad \textbf{gzip} \text{ on } | \text{ off};$

Default off

Context: http, server, location, if in location

Enables or disables gzipping of responses.

Nginx, Inc. p.168 of 506

gzip_buffers

SYNTAX: **gzip_buffers** number size;

DEFAULT 32 4k | 16 8k CONTEXT: http, server, location

Sets the *number* and *size* of buffers used to compress a response. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

Until version 0.7.28, four 4K or 8K buffers were used by default.

gzip_comp_level

SYNTAX: gzip_comp_level level;

Default 1

Context: http, server, location

Sets a gzip compression *level* of a response. Acceptable values are in the range from 1 to 9.

gzip_disable

```
SYNTAX: gzip_disable regex ...;
```

Default —

Context: http, server, location

This directive appeared in version 0.6.23.

Disables gzipping of responses for requests with User-Agent header fields matching any of the specified regular expressions.

The special mask "msie6" (0.7.12) corresponds to the regular expression "MSIE [4-6]\.", but works faster. Starting from version 0.8.11, "MSIE 6.0; ...SV1" is excluded from this mask.

gzip_http_version

```
SYNTAX: gzip_http_version 1.0 | 1.1;
```

Default 1.1

DEFAULT 1.1

Context: http, server, location

Sets the minimum HTTP version of a request required to compress a response.

gzip_min_length

SYNTAX: gzip_min_length length;

Default 20

Context: http, server, location

Sets the minimum length of a response that will be gzipped. The length is determined only from the Content-Length response header field.

Nginx, Inc. p.169 of 506

gzip_proxied

SYNTAX: **gzip_proxied** off | expired | no-cache | no-store | private | no_last_modified | no_etag | auth | any ...;

DEFAULT off

CONTEXT: http, server, location

Enables or disables gzipping of responses for proxied requests depending on the request and response. The fact that the request is proxied is determined by the presence of the Via request header field. The directive accepts multiple parameters:

off

disables compression for all proxied requests, ignoring other parameters; expired

enables compression if a response header includes the Expires field with a value that disables caching;

no-cache

enables compression if a response header includes the Cache-Control field with the "no-cache" parameter;

no-store

enables compression if a response header includes the Cache-Control field with the "no-store" parameter;

private

enables compression if a response header includes the Cache-Control field with the "private" parameter;

no last modified

enables compression if a response header does not include the Last-Modified field;

no_etag

enables compression if a response header does not include the ETag field; auth

enables compression if a request header includes the Authorization field;

any

enables compression for all proxied requests.

gzip_types

SYNTAX: gzip_types mime-type ...;

DEFAULT text/html

Context: http, server, location

Enables gzipping of responses for the specified MIME types in addition to "text/html". The special value "*" matches any MIME type (0.8.29). Responses with the "text/html" type are always compressed.

Nginx, Inc. p.170 of 506

gzip_vary

 $\label{eq:Syntax:gzip_vary} \textbf{Syntax:} \quad \textbf{gzip_vary} \; \textbf{on} \; | \; \textbf{off};$

Default off

CONTEXT: http, server, location

Enables or disables inserting the Vary: Accept-Encoding response header field if the directives gzip, gzip_static, or gunzip are active.

2.20.4 Embedded Variables

 $\$gzip_ratio$

achieved compression ratio, computed as the ratio between the original and compressed response sizes.

Nginx, Inc. p.171 of 506

2.21 Module ngx_http_gzip_static_module

2.21.1	Summary	172
2.21.2	Example Configuration	172
2.21.3	Directives	172
	gzip_static	172

2.21.1 Summary

The ngx_http_gzip_static_module module allows sending precompressed files with the ".gz" filename extension instead of regular files.

This module is not built by default, it should be enabled with the --with-http_gzip_static_module configuration parameter.

2.21.2 Example Configuration

```
gzip_static on;
gzip_proxied expired no-cache no-store private auth;
```

2.21.3 Directives

$gzip_static$

SYNTAX: gzip_static on | off | always;

Default off

CONTEXT: http, server, location

Enables ("on") or disables ("off") checking the existence of precompressed files. The following directives are also taken into account: gzip_http_version, gzip_proxied, gzip_disable, and gzip_vary.

With the "always" value (1.3.6), gzipped file is used in all cases, without checking if the client supports it. It is useful if there are no uncompressed files on the disk anyway or the ngx_http_gunzip_module is used.

The files can be compressed using the gzip command, or any other compatible one. It is recommended that the modification date and time of original and compressed files be the same.

Nginx, Inc. p.172 of 506

2.22 Module ngx_http_headers_module

2.22.1	Summary
2.22.2	Example Configuration
2.22.3	Directives
	add_header
	add_trailer
	expires

2.22.1 Summary

The ngx_http_headers_module module allows adding the Expires and Cache-Control header fields, and arbitrary fields, to a response header.

2.22.2 Example Configuration

```
expires 24h;
expires modified +24h;
expires @24h;
expires 0;
expires -1;
expires epoch;
expires $expires;
add_header Cache-Control private;
```

2.22.3 Directives

add_header

```
SYNTAX: add_header name value [always];
DEFAULT —
CONTEXT: http, server, location, if in location
```

Adds the specified field to a response header provided that the response code equals 200, 201 (1.3.10), 204, 206, 301, 302, 303, 304, 307 (1.1.16, 1.0.13), or 308 (1.13.0). Parameter value can contain variables.

There could be several add_header directives. These directives are inherited from the previous configuration level if and only if there are no add_header directives defined on the current level.

If the always parameter is specified (1.7.5), the header field will be added regardless of the response code.

add_trailer

```
SYNTAX: add_trailer name value [always];

DEFAULT —

CONTEXT: http, server, location, if in location

This directive appeared in version 1.13.2.
```

Nginx, Inc. p.173 of 506

Adds the specified field to the end of a response provided that the response code equals 200, 201, 206, 301, 302, 303, 307, or 308. Parameter value can contain variables.

There could be several add_trailer directives. These directives are inherited from the previous configuration level if and only if there are no add_trailer directives defined on the current level.

If the always parameter is specified the specified field will be added regardless of the response code.

expires

```
SYNTAX: expires [modified] time;
SYNTAX: expires epoch | max | off;
DEFAULT off
CONTEXT: http, server, location, if in location
```

Enables or disables adding or modifying the Expires and Cache-Control response header fields provided that the response code equals 200, 201 (1.3.10), 204, 206, 301, 302, 303, 304, 307 (1.1.16, 1.0.13), or 308 (1.13.0). The parameter can be a positive or negative time.

The time in the Expires field is computed as a sum of the current time and *time* specified in the directive. If the modified parameter is used (0.7.0, 0.6.32) then the time is computed as a sum of the file's modification time and the *time* specified in the directive.

In addition, it is possible to specify a time of day using the "@" prefix (0.7.9, 0.6.34):

```
expires @15h30m;
```

The contents of the Cache-Control field depends on the sign of the specified time:

- time is negative Cache-Control: no-cache.
- time is positive or zero Cache-Control: max-age=t, where t is a time specified in the directive, in seconds.

The epoch parameter sets Expires to the value "Thu, 01 Jan 1970 00:00:01 GMT", and Cache-Control to "no-cache".

The max parameter sets Expires to the value "Thu, 31 Dec 2037 23:55:55 GMT", and Cache-Control to 10 years.

The off parameter disables adding or modifying the Expires and Cache-Control response header fields.

The last parameter value can contain variables (1.7.9):

Nginx, Inc. p.174 of 506

expires \$expires;

Nginx, Inc. p.175 of 506

2.23 Module ngx_http_hls_module

2.23.1	Summary
2.23.2	Example Configuration
2.23.3	Directives
	hls
	hls_buffers
	hls_forward_args
	hls_fragment
	hls_mp4_buffer_size
	hls_mp4_max_buffer_size

2.23.1 Summary

The ngx_http_hls_module module provides HTTP Live Streaming (HLS) server-side support for MP4 and MOV media files. Such files typically have the .mp4, .m4v, .m4a, .mov, or .qt filename extensions. The module supports H.264 video codec, AAC and MP3 audio codecs.

For each media file, two URIs are supported:

- A playlist URI with the ".m3u8" filename extension. The URI can accept optional arguments:
 - "start" and "end" define playlist boundaries in seconds (1.9.0).
 - "offset" shifts an initial playback position to the time offset in seconds (1.9.0). A positive value sets a time offset from the beginning of the playlist. A negative value sets a time offset from the end of the last fragment in the playlist.
 - "len" defines the fragment length in seconds.
- A fragment URI with the ".ts" filename extension. The URI can accept optional arguments:
 - "start" and "end" define fragment boundaries in seconds.

This module is available as part of our commercial subscription.

2.23.2 Example Configuration

Nginx, Inc. p.176 of 506

With this configuration, the following URIs are supported for the "/var-/video/test.mp4" file:

```
http://hls.example.com/test.mp4.m3u8?offset=1.000&start=1.000&end=2.200
http://hls.example.com/test.mp4.m3u8?len=8.000
http://hls.example.com/test.mp4.ts?start=1.000&end=2.200
```

2.23.3 Directives

hls

SYNTAX: hls;
DEFAULT —
CONTEXT: location

Turns on HLS streaming in the surrounding location.

hls_buffers

SYNTAX: **hls_buffers** number size;

DEFAULT 8 2m

Context: http, server, location

Sets the maximum *number* and *size* of buffers that are used for reading and writing data frames.

hls_forward_args

```
SYNTAX: hls_forward_args on | off;
DEFAULT off
```

Context: http, server, location
This directive appeared in version 1.5.12.

Adds arguments from a playlist request to URIs of fragments. This may be useful for performing client authorization at the moment of requesting a fragment, or when protecting an HLS stream with the ngx_http_secure_link_module module.

For example, if a client requests a playlist http://example.com/hls/test.mp4.m3u8?a=1&b=2, the arguments a=1 and b=2 will be added to URIs of fragments after the arguments start and end:

```
#EXTM3U
#EXT-X-VERSION:3
#EXT-X-TARGETDURATION:15
#EXT-X-PLAYLIST-TYPE:VOD

#EXTINF:9.333,
test.mp4.ts?start=0.000&end=9.333&a=1&b=2
#EXTINF:7.167,
test.mp4.ts?start=9.333&end=16.500&a=1&b=2
#EXTINF:5.416,
test.mp4.ts?start=16.500&end=21.916&a=1&b=2
#EXTINF:5.500,
test.mp4.ts?start=21.916&end=27.416&a=1&b=2
```

Nginx, Inc. p.177 of 506

```
#EXTINF:15.167,
test.mp4.ts?start=27.416&end=42.583&a=1&b=2
#EXTINF:9.626,
test.mp4.ts?start=42.583&end=52.209&a=1&b=2
#EXT-X-ENDLIST
```

If an HLS stream is protected with the ngx_http_secure_link_module module, \$uri\$ should not be used in the secure_link_md5 expression because this will cause errors when requesting the fragments. Base URI should be used instead of \$uri\$ (\$hls_uri\$ in the example):

```
http {
    map $uri $hls_uri {
       ~^(?<base_uri>.*).m3u8$ $base_uri;
        ~^(?<base_uri>.*).ts$ $base_uri;
        default
                                $uri;
    server {
        location /hls/ {
            hls:
            hls_forward_args on;
            alias /var/videos/;
            secure_link $arg_md5,$arg_expires;
            secure_link_md5 "$secure_link_expires$hls_uri$remote_addr secret";
            if ($secure_link = "") {
                return 403;
            if ($secure_link = "0") {
                return 410;
        }
```

hls_fragment

SYNTAX: hls_fragment time;

Default 5s

Context: http, server, location

Defines the default fragment length for playlist URIs requested without the "len" argument.

hls_mp4_buffer_size

SYNTAX: hls_mp4_buffer_size size;

DEFAULT 512k

CONTEXT: http, server, location

Sets the initial size of the buffer used for processing MP4 and MOV files.

Nginx, Inc. p.178 of 506

$hls_mp4_max_buffer_size$

SYNTAX: hls_mp4_max_buffer_size size;

DEFAULT 10m

Context: http, server, location

During metadata processing, a larger buffer may become necessary. Its size cannot exceed the specified *size*, or else nginx will return the server error 500 Internal Server Error, and log the following message:

"/some/movie/file.mp4" mp4 moov atom is too large: 12583268, you may want to increase hls_mp4_max_buffer_size

Nginx, Inc. p.179 of 506

2.24 Module ngx_http_image_filter_module

2.24.1	Summary
2.24.2	Example Configuration
2.24.3	Directives
	image_filter
	image_filter_buffer
	image_filter_interlace
	image_filter_jpeg_quality
	image_filter_sharpen
	image_filter_transparency
	image_filter_webp_quality

2.24.1 **Summary**

The ngx_http_image_filter_module module (0.7.54+) is a filter that transforms images in JPEG, GIF, PNG, and WebP formats.

This module is not built by default, it should be enabled with the --with-http_image_filter_module configuration parameter.

This module utilizes the libgd library. It is recommended to use the latest available version of the library.

The WebP format support appeared in version 1.11.6. To transform images in this format, the libgd library must be compiled with the WebP support.

2.24.2 Example Configuration

```
location /img/ {
    proxy_pass http://backend;
    image_filter resize 150 100;
    image_filter rotate 90;
    error_page 415 = /empty;
}
location = /empty {
    empty_gif;
}
```

Nginx, Inc. p.180 of 506

2.24.3 Directives

image_filter

```
SYNTAX: image_filter off;
SYNTAX: image_filter test;
SYNTAX: image_filter size;
SYNTAX: image_filter rotate 90 | 180 | 270;
SYNTAX: image_filter resize width height;
SYNTAX: image_filter crop width height;
DEFAULT off
CONTEXT: location
```

Sets the type of transformation to perform on images:

off

turns off module processing in a surrounding location.

test

ensures that responses are images in either JPEG, GIF, PNG, or WebP format. Otherwise, the 415 Unsupported Media Type error is returned.

size

outputs information about images in a JSON format, e.g.:

```
{ "img" : { "width": 100, "height": 100, "type": "gif" } }
```

In case of an error, the output is as follows:

```
{}
```

```
rotate 90|180|270
```

rotates images counter-clockwise by the specified number of degrees. Parameter value can contain variables. This mode can be used either alone or along with the resize and crop transformations.

```
resize width height
```

proportionally reduces an image to the specified sizes. To reduce by only one dimension, another dimension can be specified as "-". In case of an error, the server will return code 415 Unsupported Media Type. Parameter values can contain variables. When used along with the rotate parameter, the rotation happens **after** reduction.

crop width height

proportionally reduces an image to the larger side size and crops extraneous edges by another side. To reduce by only one dimension, another dimension can be specified as "-". In case of an error, the server will return code 415 Unsupported Media Type. Parameter values can contain variables. When used along with the rotate parameter, the rotation happens **before** reduction.

Nginx, Inc. p.181 of 506

image_filter_buffer

SYNTAX: image_filter_buffer size;

Default 1M

Context: http, server, location

Sets the maximum size of the buffer used for reading images. When the size is exceeded the server returns error 415 Unsupported Media Type.

image_filter_interlace

SYNTAX: image_filter_interlace on | off;

Default off

Context: http, server, location
This directive appeared in version 1.3.15.

If enabled, final images will be interlaced. For JPEG, final images will be in "progressive JPEG" format.

image_filter_jpeg_quality

SYNTAX: image_filter_jpeg_quality quality;

Default 75

CONTEXT: http, server, location

Sets the desired *quality* of the transformed JPEG images. Acceptable values are in the range from 1 to 100. Lesser values usually imply both lower image quality and less data to transfer. The maximum recommended value is 95. Parameter value can contain variables.

image_filter_sharpen

SYNTAX: image_filter_sharpen percent;

Default 0

Context: http, server, location

Increases sharpness of the final image. The sharpness percentage can exceed 100. The zero value disables sharpening. Parameter value can contain variables.

image_filter_transparency

SYNTAX: image_filter_transparency on off;

Default on

Context: http, server, location

Defines whether transparency should be preserved when transforming GIF images or PNG images with colors specified by a palette. The loss of transparency results in images of a better quality. The alpha channel transparency in PNG is always preserved.

Nginx, Inc. p.182 of 506

$image_filter_webp_quality$

SYNTAX: image_filter_webp_quality quality;

Default 80

Context: http, server, location
This directive appeared in version 1.11.6.

Sets the desired *quality* of the transformed WebP images. Acceptable values are in the range from 1 to 100. Lesser values usually imply both lower image quality and less data to transfer. Parameter value can contain variables.

Nginx, Inc. p.183 of 506

2.25 Module ngx_http_index_module

2.25.1	Summary	84
2.25.2	Example Configuration	84
2.25.3	Directives	84
	index	84

2.25.1 Summary

The ngx_http_index_module module processes requests ending with the slash character ('/'). Such requests can also be processed by the ngx_http_autoindex_module and ngx_http_random_index_module modules.

2.25.2 Example Configuration

```
location / {
   index index.$geo.html index.html;
}
```

2.25.3 Directives

index

```
SYNTAX: index file ...;

DEFAULT index.html

CONTEXT: http, server, location
```

Defines files that will be used as an index. The *file* name can contain variables. Files are checked in the specified order. The last element of the list can be a file with an absolute path. Example:

```
index index.$geo.html index.0.html /index.html;
```

It should be noted that using an index file causes an internal redirect, and the request can be processed in a different location. For example, with the following configuration:

```
location = / {
   index index.html;
}
location / {
   ...
}
```

a "/" request will actually be processed in the second location as "/index.html".

Nginx, Inc. p.184 of 506

2.26 Module ngx_http_js_module

2.26.1	Summary	,
2.26.2	Example Configuration	5
2.26.3	Directives	6
	js_body_filter	6
	js_content	7
	js_header_filter	7
	js_import	7
	js_include	8
	js_path	8
	js_set	8
	js_var	ç
2.26.4	Request Argument	9

2.26.1 Summary

The ngx_http_js_module module is used to implement location and variable handlers in njs — a subset of the JavaScript language.

Download and install instructions are available here.

2.26.2 Example Configuration

The example works since 0.4.0.

The http.js file:

```
function foo(r) {
   r.log("hello from foo() handler");
   return "foo";
}
```

Nginx, Inc. p.185 of 506

```
function summary(r) {
    var a, s, h;
    s = "JS summary\n\n";
    s += "Method: " + r.method + " \n";
    s += "HTTP version: " + r.httpVersion + "\n";
    s += "Host: " + r.headersIn.host + "\n";
    s += "Remote Address: " + r.remoteAddress + "\n";
    s += "URI: " + r.uri + "\n";
    s += "Headers:\n";
    for (h in r.headersIn) {
        s += " header '" + h + "' is '" + r.headersIn[h] + "'\n";
    s += "Args:\n";
    for (a in r.args) {
        s += " arg '" + a + "' is '" + r.args[a] + "'\n";
    return s:
function baz(r) {
   r.status = 200;
   r.headersOut.foo = 1234;
    r.headersOut['Content-Type'] = "text/plain; charset=utf-8";
   r.headersOut['Content-Length'] = 15;
   r.sendHeader():
    r.send("nginx");
    r.send("java");
    r.send("script");
    r.finish();
function hello(r) {
    r.return(200, "Hello world!");
export default {foo, summary, baz, hello};
```

2.26.3 Directives

js_body_filter

```
SYNTAX: js_body_filter function | module.function [buffer_type=string | buffer];

DEFAULT —

CONTEXT: location, limit_except

This directive appeared in version 0.5.2.
```

Sets an njs function as a response body filter. The filter function is called for each data chunk of a response body with the following arguments:

```
the HTTP request object data
```

the incoming data chunk, may be a string or Buffer depending on the buffer_type value, by default is a string.

Nginx, Inc. p.186 of 506

```
flags
```

an object with the following properties:

```
last
```

a boolean value, true if data is a last buffer.

The filter function can pass its own modified version of the input data chunk to the next body filter by calling r.sendBuffer(). For example, to transform all the lowercase letters in the response body:

```
function filter(r, data, flags) {
    r.sendBuffer(data.toLowerCase(), flags);
}
```

To stop filtering (following data chunks will be passed to client without calling js_body_filter), r.done() can be used.

If the filter function changes the length of the response body, then it is required to clear out the Content-Length response header (if any) in js_header_filter to enforce chunked transfer encoding.

js_content

```
SYNTAX: js_content function | module.function;

DEFAULT —

CONTEXT: location, limit_except
```

Sets an njs function as a location content handler. Since 0.4.0, a module function can be referenced.

js_header_filter

```
SYNTAX: js_header_filter function | module.function;

DEFAULT —

CONTEXT: location, limit_except

This directive appeared in version 0.5.1.
```

Sets an njs function as a response header filter. The directive allows changing arbitrary header fields of a response header.

js_import

```
SYNTAX: js_import module.js | export_name from module.js;

DEFAULT —

CONTEXT: http

This directive appeared in version 0.4.0.
```

Imports a module that implements location and variable handlers in njs. The export_name is used as a namespace to access module functions. If the export_name is not specified, the module name will be used as a namespace.

```
js_import http.js;
```

Nginx, Inc. p.187 of 506

Here, the module name http is used as a namespace while accessing exports. If the imported module exports foo(), http.foo is used to refer to it.

Several js_import directives can be specified.

js_include

```
SYNTAX: js_include file;
DEFAULT —
CONTEXT: http
```

Specifies a file that implements location and variable handlers in njs:

```
nginx.conf:
js_include http.js;
location /version {
    js_content version;
}

http.js:
function version(r) {
    r.return(200, njs.version);
}
```

The directive is deprecated since 0.4.0, the js_import directive should be used instead.

js_path

```
SYNTAX: js_path path;

DEFAULT —

CONTEXT: http

This directive appeared in version 0.3.0.
```

Sets an additional path for njs modules.

js_set

```
SYNTAX: js_set $variable function | module.function;

DEFAULT —

CONTEXT: http
```

Sets an njs function for the specified variable. Since 0.4.0, a module function can be referenced.

The function is called when the variable is referenced for the first time for a given request. The exact moment depends on a phase at which the variable is referenced. This can be used to perform some logic not related to variable evaluation. For example, if the variable is referenced only in the log_format directive, its handler will not be executed until the log phase. This handler can be used to do some cleanup right before the request is freed.

Nginx, Inc. p.188 of 506

js_var

SYNTAX: js_var \$variable [value];

DEFAULT — CONTEXT: http

This directive appeared in version 0.5.3.

Declares a writable variable. The value can contain text, variables, and their combination. The variable is not overwritten after a redirect unlike variables created with the set directive.

2.26.4 Request Argument

Each HTTP njs handler receives one argument, a request object.

Nginx, Inc. p.189 of 506

2.27 Module ngx_http_keyval_module

2.27.1	Summary	90
2.27.2	Example Configuration	90
2.27.3	Directives	90
	keyval	90
	keyval_zone	91

2.27.1 Summary

The ngx_http_keyval_module module (1.13.3) creates variables with values taken from key-value pairs managed by the API or a variable (1.15.10) that can also be set with njs.

This module is available as part of our commercial subscription.

2.27.2 Example Configuration

```
http {
    keyval_zone zone=one:32k state=/var/lib/nginx/state/one.keyval;
    keyval $arg_text $text zone=one;
    ...
    server {
        incation / {
            return 200 $text;
        }
        location /api {
            api write=on;
        }
    }
}
```

2.27.3 Directives

keyval

```
SYNTAX: keyval key $variable zone=name;
DEFAULT —
CONTEXT: http
```

Creates a new *\$variable* whose value is looked up by the *key* in the key-value database. Matching rules are defined by the type parameter of the keyval_zone directive. The database is stored in a shared memory zone specified by the zone parameter.

Nginx, Inc. p.190 of 506

keyval_zone

```
SYNTAX: keyval_zone zone=name:size [state=file] [timeout=time] [type=string|ip|prefix] [sync];

DEFAULT —

CONTEXT: http
```

Sets the *name* and *size* of the shared memory zone that keeps the key-value database. Key-value pairs are managed by the API.

The optional state parameter specifies a *file* that keeps the current state of the key-value database in the JSON format and makes it persistent across nginx restarts.

Examples:

```
keyval_zone zone=one:32k state=/var/lib/nginx/state/one.keyval; # path for
    Linux
keyval_zone zone=one:32k state=/var/db/nginx/state/one.keyval; # path for
    FreeBSD
```

The optional timeout parameter (1.15.0) sets the time after which keyvalue pairs are removed from the zone.

The optional type parameter (1.17.1) activates an extra index optimized for matching the key of a certain type and defines matching rules when evaluating a keyval \$variable.

The index is stored in the same shared memory zone and thus requires additional storage.

```
type=string
```

default, no index is enabled; variable lookup is performed using exact match of the record key and a search key

```
type=ip
```

the search key is the textual representation of IPv4 or IPv6 address or CIDR range; to match a record key, the search key must belong to a subnet specified by a record key or exactly match an IP address

```
type=prefix
```

variable lookup is performed using prefix match of a record key and a search key (1.17.5); to match a record key, the record key must be a prefix of the search key

The optional sync parameter (1.15.0) enables synchronization of the shared memory zone. The synchronization requires the timeout parameter to be set.

If the synchronization is enabled, removal of key-value pairs (no matter one or all) will be performed only on a target cluster node. The same key-value pairs on other cluster nodes will be removed upon timeout.

Nginx, Inc. p.191 of 506

2.28 Module ngx_http_limit_conn_module

2.28.1	Summary
2.28.2	Example Configuration
2.28.3	Directives
	limit_conn
	limit_conn_dry_run
	limit_conn_log_level
	limit_conn_status
	limit_conn_zone
	limit_zone
2.28.4	Embedded Variables

2.28.1 Summary

The ngx_http_limit_conn_module module is used to limit the number of connections per the defined key, in particular, the number of connections from a single IP address.

Not all connections are counted. A connection is counted only if it has a request being processed by the server and the whole request header has already been read.

2.28.2 Example Configuration

```
http {
    limit_conn_zone $binary_remote_addr zone=addr:10m;
    ...
    server {
        ...
        location /download/ {
            limit_conn addr 1;
        }
}
```

2.28.3 Directives

limit_conn

SYNTAX: limit_conn zone number;

Default —

Context: http, server, location

Sets the shared memory zone and the maximum allowed number of connections for a given key value. When this limit is exceeded, the server will return the error in reply to a request. For example, the directives

Nginx, Inc. p.192 of 506

```
limit_conn_zone $binary_remote_addr zone=addr:10m;
server {
   location /download/ {
       limit_conn addr 1;
   }
```

allow only one connection per an IP address at a time.

In HTTP/2 and SPDY, each concurrent request is considered a separate connection.

There could be several limit_conn directives. For example, the following configuration will limit the number of connections to the server per a client IP and, at the same time, the total number of connections to the virtual server:

```
limit_conn_zone $binary_remote_addr zone=perip:10m;
limit_conn_zone $server_name zone=perserver:10m;
server {
    ...
    limit_conn perip 10;
    limit_conn perserver 100;
}
```

These directives are inherited from the previous configuration level if and only if there are no limit_conn directives defined on the current level.

limit_conn_dry_run

```
SYNTAX: limit_conn_dry_run on | off;
DEFAULT off
CONTEXT: http, server, location
This directive appeared in version 1.17.6.
```

Enables the dry run mode. In this mode, the number of connections is not limited, however, in the shared memory zone, the number of excessive connections is accounted as usual.

limit_conn_log_level

```
SYNTAX: limit_conn_log_level info | notice | warn | error;
DEFAULT error
CONTEXT: http, server, location
This directive appeared in version 0.8.18.
```

Sets the desired logging level for cases when the server limits the number of connections.

Nginx, Inc. p.193 of 506

limit conn status

SYNTAX: limit_conn_status code;

Default 503

Context: http, server, location
This directive appeared in version 1.3.15.

Sets the status code to return in response to rejected requests.

limit_conn_zone

SYNTAX: limit_conn_zone key zone=name:size;

Default — Context: http

Sets parameters for a shared memory zone that will keep states for various keys. In particular, the state includes the current number of connections. The *key* can contain text, variables, and their combination. Requests with an empty key value are not accounted.

Prior to version 1.7.6, a key could contain exactly one variable.

Usage example:

```
limit_conn_zone $binary_remote_addr zone=addr:10m;
```

Here, a client IP address serves as a key. Note that instead of \$remote_addr\$, the \$binary_remote_addr\$ variable is used here. The \$remote_addr\$ variable's size can vary from 7 to 15 bytes. The stored state occupies either 32 or 64 bytes of memory on 32-bit platforms and always 64 bytes on 64-bit platforms. The \$binary_remote_addr\$ variable's size is always 4 bytes for IPv4 addresses or 16 bytes for IPv6 addresses. The stored state always occupies 32 or 64 bytes on 32-bit platforms and 64 bytes on 64-bit platforms. One megabyte zone can keep about 32 thousand 32-byte states or about 16 thousand 64-byte states. If the zone storage is exhausted, the server will return the error to all further requests.

Additionally, as part of our commercial subscription, the status information for each such shared memory zone can be obtained or reset with the API since 1.17.7.

limit_zone

SYNTAX: limit_zone name \$variable size;

Default — Context: http

This directive was made obsolete in version 1.1.8 and was removed in version 1.7.6. An equivalent limit_conn_zone directive with a changed syntax should be used instead:

Nginx, Inc. p.194 of 506

limit_conn_zone \$variable zone=name:size;

2.28.4 Embedded Variables

 $\$limit_conn_status$

keeps the result of limiting the number of connections (1.17.6): PASSED, REJECTED, or REJECTED_DRY_RUN

Nginx, Inc. p.195 of 506

2.29 Module ngx_http_limit_req_module

2.29.1	Summary	6
2.29.2	Example Configuration	6
2.29.3	Directives	6
	limit_req	6
	limit_req_dry_run	7
	limit_req_log_level	7
	limit_req_status	8
	limit_req_zone	3
2.29.4	Embedded Variables	9

2.29.1 Summary

The ngx_http_limit_req_module module (0.7.21) is used to limit the request processing rate per a defined key, in particular, the processing rate of requests coming from a single IP address. The limitation is done using the "leaky bucket" method.

2.29.2 Example Configuration

```
http {
    limit_req_zone $binary_remote_addr zone=one:10m rate=1r/s;
    ...
    server {
        ...
        location /search/ {
             limit_req zone=one burst=5;
        }
}
```

2.29.3 Directives

limit_req

```
SYNTAX: limit_req zone=name [burst=number] [nodelay | delay=number];

DEFAULT —

CONTEXT: http, server, location
```

Sets the shared memory zone and the maximum burst size of requests. If the requests rate exceeds the rate configured for a zone, their processing is delayed such that requests are processed at a defined rate. Excessive requests are delayed until their number exceeds the maximum burst size in which case the request is terminated with an error. By default, the maximum burst size is equal to zero. For example, the directives

Nginx, Inc. p.196 of 506

```
limit_req_zone $binary_remote_addr zone=one:10m rate=1r/s;
server {
    location /search/ {
        limit_req zone=one burst=5;
    }
```

allow not more than 1 request per second at an average, with bursts not exceeding 5 requests.

If delaying of excessive requests while requests are being limited is not desired, the parameter nodelay should be used:

```
limit_req zone=one burst=5 nodelay;
```

The delay parameter (1.15.7) specifies a limit at which excessive requests become delayed. Default value is zero, i.e. all excessive requests are delayed.

There could be several limit_req directives. For example, the following configuration will limit the processing rate of requests coming from a single IP address and, at the same time, the request processing rate by the virtual server:

```
limit_req_zone $binary_remote_addr zone=perip:10m rate=1r/s;
limit_req_zone $server_name zone=perserver:10m rate=10r/s;
server {
    ...
    limit_req zone=perip burst=5 nodelay;
    limit_req zone=perserver burst=10;
}
```

These directives are inherited from the previous configuration level if and only if there are no limit_req directives defined on the current level.

limit_req_dry_run

```
SYNTAX: limit_req_dry_run on | off;
Default off
Context: http, server, location
This directive appeared in version 1.17.1.
```

Enables the dry run mode. In this mode, requests processing rate is not limited, however, in the shared memory zone, the number of excessive requests is accounted as usual.

limit_req_log_level

```
SYNTAX: limit_req_log_level info | notice | warn | error;

DEFAULT error

CONTEXT: http, server, location

This directive appeared in version 0.8.18.
```

Nginx, Inc. p.197 of 506

Sets the desired logging level for cases when the server refuses to process requests due to rate exceeding, or delays request processing. Logging level for delays is one point less than for refusals; for example, if "limit_req_log_-level notice" is specified, delays are logged with the info level.

limit_req_status

SYNTAX: limit_req_status code;

Default 503

Context: http, server, location
This directive appeared in version 1.3.15.

Sets the status code to return in response to rejected requests.

limit_req_zone

SYNTAX: **limit_req_zone** key zone=name:size rate=rate [sync];

Default — Context: http

Sets parameters for a shared memory zone that will keep states for various keys. In particular, the state stores the current number of excessive requests. The *key* can contain text, variables, and their combination. Requests with an empty key value are not accounted.

Prior to version 1.7.6, a key could contain exactly one variable.

Usage example:

```
limit_req_zone    $binary_remote_addr zone=one:10m rate=1r/s;
```

Here, the states are kept in a 10 megabyte zone "one", and an average request processing rate for this zone cannot exceed 1 request per second.

A client IP address serves as a key. Note that instead of \$remote_addr\$, the \$binary_remote_addr\$ variable is used here. The \$binary_remote_addr\$ variable's size is always 4 bytes for IPv4 addresses or 16 bytes for IPv6 addresses. The stored state always occupies 64 bytes on 32-bit platforms and 128 bytes on 64-bit platforms. One megabyte zone can keep about 16 thousand 64-byte states or about 8 thousand 128-byte states.

If the zone storage is exhausted, the least recently used state is removed. If even after that a new state cannot be created, the request is terminated with an error.

The rate is specified in requests per second (r/s). If a rate of less than one request per second is desired, it is specified in request per minute (r/m). For example, half-request per second is 30r/m.

The sync parameter (1.15.3) enables synchronization of the shared memory zone.

Nginx, Inc. p.198 of 506

The sync parameter is available as part of our commercial subscription.

Additionally, as part of our commercial subscription, the status information for each such shared memory zone can be obtained or reset with the API since 1.17.7.

2.29.4 Embedded Variables

 $\$limit_req_status$

keeps the result of limiting the request processing rate (1.17.6): PASSED, DELAYED, REJECTED, DELAYED_DRY_RUN, or REJECTED_DRY_RUN

Nginx, Inc. p.199 of 506

2.30 Module ngx_http_log_module

2.30.1	Summary
2.30.2	Example Configuration
2.30.3	Directives
	access_log
	log_format
	open_log_file_cache

2.30.1 Summary

The ngx_http_log_module module writes request logs in the specified format.

Requests are logged in the context of a location where processing ends. It may be different from the original location, if an internal redirect happens during request processing.

2.30.2 Example Configuration

2.30.3 Directives

access_log

Sets the path, format, and configuration for a buffered log write. Several logs can be specified on the same configuration level. Logging to syslog can be configured by specifying the "syslog:" prefix in the first parameter. The special value off cancels all access_log directives on the current level. If the format is not specified then the predefined "combined" format is used.

If either the buffer or gzip (1.3.10, 1.2.7) parameter is used, writes to log will be buffered.

The buffer size must not exceed the size of an atomic write to a disk file. For FreeBSD this size is unlimited.

When buffering is enabled, the data will be written to the file:

Nginx, Inc. p.200 of 506

- if the next log line does not fit into the buffer;
- if the buffered data is older than specified by the flush parameter (1.3.10, 1.2.7);
- when a worker process is re-opening log files or is shutting down.

If the gzip parameter is used, then the buffered data will be compressed before writing to the file. The compression level can be set between 1 (fastest, less compression) and 9 (slowest, best compression). By default, the buffer size is equal to 64K bytes, and the compression level is set to 1. Since the data is compressed in atomic blocks, the log file can be decompressed or read by "zcat" at any time.

Example:

```
access_log /path/to/log.gz combined gzip flush=5m;
```

For gzip compression to work, nginx must be built with the zlib library.

The file path can contain variables (0.7.6+), but such logs have some constraints:

- the user whose credentials are used by worker processes should have permissions to create files in a directory with such logs;
- buffered writes do not work;
- the file is opened and closed for each log write. However, since the descriptors of frequently used files can be stored in a cache, writing to the old file can continue during the time specified by the open_log_file_cache directive's valid parameter
- during each log write the existence of the request's root directory is checked, and if it does not exist the log is not created. It is thus a good idea to specify both root and access_log on the same configuration level:

```
server {
  root    /spool/vhost/data/$host;
  access_log /spool/vhost/logs/$host;
  ...
```

The if parameter (1.7.0) enables conditional logging. A request will not be logged if the *condition* evaluates to "0" or an empty string. In the following example, the requests with response codes 2xx and 3xx will not be logged:

```
map $status $loggable {
    ~^[23] 0;
    default 1;
}
access_log /path/to/access.log combined if=$loggable;
```

Nginx, Inc. p.201 of 506

log_format

SYNTAX: **log_format** name [escape=default|json|none] string ...;
DEFAULT combined "..."

Context: http

Specifies log format.

The escape parameter (1.11.8) allows setting json or default characters escaping in variables, by default, default escaping is used. The none value (1.13.10) disables escaping.

For default escaping, characters "", "\", and other characters with values less than 32 (0.7.0) or above 126 (1.1.6) are escaped as "\xXX". If the variable value is not found, a hyphen ("-") will be logged.

For json escaping, all characters not allowed in JSON strings will be escaped: characters "" and "\" are escaped as "\" and "\", characters with values less than 32 are escaped as "\n", "\r", "\t", "\b", "\f", or "\u00XX".

The log format can contain common variables, and variables that exist only at the time of a log write:

\$bytes_sent

the number of bytes sent to a client

\$connection

connection serial number

 $$connection_requests$

the current number of requests made through a connection (1.1.18)

\$msec

time in seconds with a milliseconds resolution at the time of the log write \$pipe

"p" if request was pipelined, "." otherwise

\$request_length

request length (including request line, header, and request body)

 $reguest_time$

request processing time in seconds with a milliseconds resolution; time elapsed between the first bytes were read from the client and the log write after the last bytes were sent to the client

\$status

response status

\$time_iso8601

local time in the ISO 8601 standard format

 $$time_local$$

local time in the Common Log Format

In the modern nginx versions variables status (1.3.2, 1.2.2), status (1.3.8, 1.2.5), sconnection (1.3.8, 1.2.5), sconnection requests (1.3.8, 1.2.5), smsec (1.3.9, 1.2.6), srequest_time (1.3.9, 1.2.6), spipe (1.3.12, 1.2.7), srequest_length (1.3.12, 1.2.7), stime_iso8601 (1.3.12, 1.2.7), and stime_local (1.3.12, 1.2.7) are also available as common variables.

Nginx, Inc. p.202 of 506

Header lines sent to a client have the prefix "sent_http_", for example, \$sent_http_content_range.

The configuration always includes the predefined "combined" format:

open_log_file_cache

```
{\tt SYNTAX:} \quad {\tt open\_log\_file\_cache} \; {\tt max} = N \; [{\tt inactive} = time] \; [{\tt min\_uses} = N]
```

[valid=time];

SYNTAX: open_log_file_cache off;

Default off

Context: http, server, location

Defines a cache that stores the file descriptors of frequently used logs whose names contain variables. The directive has the following parameters:

max

sets the maximum number of descriptors in a cache; if the cache becomes full the least recently used (LRU) descriptors are closed

inactive

sets the time after which the cached descriptor is closed if there were no access during this time; by default, 10 seconds

min uses

sets the minimum number of file uses during the time defined by the inactive parameter to let the descriptor stay open in a cache; by default, 1

valid

sets the time after which it should be checked that the file still exists with the same name; by default, 60 seconds

off

disables caching

Usage example:

```
open_log_file_cache max=1000 inactive=20s valid=1m min_uses=2;
```

Nginx, Inc. p.203 of 506

2.31 Module ngx_http_map_module

2.31.1	Summary)4
2.31.2	Example Configuration) 4
2.31.3	Directives) 4
	map)4
	map_hash_bucket_size)(
	map_hash_max_size)(

2.31.1 Summary

The ngx_http_map_module module creates variables whose values depend on values of other variables.

2.31.2 Example Configuration

```
map $http_host $name {
   hostnames;

   default 0;

   example.com 1;
   *.example.com 1;
   example.org 2;
   *.example.org 2;
   .example.net 3;
   wap.* 4;
}

map $http_user_agent $mobile {
   default 0;
   "~Opera Mini" 1;
}
```

2.31.3 Directives

map

```
SYNTAX: map string $variable { ...}

Default —

Context: http
```

Creates a new variable whose value depends on values of one or more of the source variables specified in the first parameter.

Before version 0.9.0 only a single variable could be specified in the first parameter.

Since variables are evaluated only when they are used, the mere declaration even of a large number of "map" variables does not add any extra costs to request processing.

Nginx, Inc. p.204 of 506

Parameters inside the map block specify a mapping between source and resulting values.

Source values are specified as strings or regular expressions (0.9.6).

Strings are matched ignoring the case.

A regular expression should either start from the "~" symbol for a case-sensitive matching, or from the "~*" symbols (1.0.4) for case-insensitive matching. A regular expression can contain named and positional captures that can later be used in other directives along with the resulting variable.

If a source value matches one of the names of special parameters described below, it should be prefixed with the "\" symbol.

The resulting value can contain text, variable (0.9.0), and their combination (1.11.0).

The following special parameters are also supported:

default value

sets the resulting value if the source value matches none of the specified variants. When default is not specified, the default resulting value will be an empty string.

hostnames

indicates that source values can be hostnames with a prefix or suffix mask:

```
*.example.com 1;
example.* 1;
```

The following two records

```
example.com 1;
*.example.com 1;
```

can be combined:

```
.example.com 1;
```

This parameter should be specified before the list of values.

include file

includes a file with values. There can be several inclusions.

volatile

indicates that the variable is not cacheable (1.11.7).

If the source value matches more than one of the specified variants, e.g. both a mask and a regular expression match, the first matching variant will be chosen, in the following order of priority:

- 1. string value without a mask
- 2. longest string value with a prefix mask, e.g. "*.example.com"
- 3. longest string value with a suffix mask, e.g. "mail.*"

Nginx, Inc. p.205 of 506

- 4. first matching regular expression (in order of appearance in a configuration file)
- 5. default value

map_hash_bucket_size

SYNTAX: map_hash_bucket_size size;

DEFAULT 32 | 64 | 128

Context: http

Sets the bucket size for the map variables hash tables. Default value depends on the processor's cache line size. The details of setting up hash tables are provided in a separate document.

map_hash_max_size

SYNTAX: map_hash_max_size size;

Default 2048 Context: http

Sets the maximum *size* of the map variables hash tables. The details of setting up hash tables are provided in a separate document.

Nginx, Inc. p.206 of 506

2.32 Module ngx_http_memcached_module

2.32.1	Summary
2.32.2	Example Configuration
2.32.3	Directives
	memcached_bind
	memcached_buffer_size
	memcached_connect_timeout
	memcached_force_ranges
	memcached_gzip_flag
	memcached_next_upstream
	memcached_next_upstream_timeout 209
	memcached_next_upstream_tries
	memcached_pass
	memcached_read_timeout
	memcached_send_timeout
	memcached_socket_keepalive
2 32 4	Embedded Variables

2.32.1 **Summary**

The ngx_http_memcached_module module is used to obtain responses from a memcached server. The key is set in the *\$memcached_key* variable. A response should be put in memcached in advance by means external to nginx.

2.32.2 Example Configuration

2.32.3 Directives

memcached_bind

```
SYNTAX: memcached_bind address [transparent ] | off;
DEFAULT —
CONTEXT: http, server, location
This directive appeared in version 0.8.22.
```

Makes outgoing connections to a memcached server originate from the specified local IP address with an optional port (1.11.2). Parameter value can

Nginx, Inc. p.207 of 506

contain variables (1.3.12). The special value off (1.3.12) cancels the effect of the memcached_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address and port.

The transparent parameter (1.11.0) allows outgoing connections to a memcached server originate from a non-local IP address, for example, from a real IP address of a client:

```
memcached_bind $remote_addr transparent;
```

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required (1.13.8) as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the memcached server.

memcached_buffer_size

SYNTAX: memcached_buffer_size size;

Default 4k|8k

Context: http, server, location

Sets the *size* of the buffer used for reading the response received from the memcached server. The response is passed to the client synchronously, as soon as it is received.

$memcached_connect_timeout$

SYNTAX: memcached_connect_timeout time;

Default 60s

Context: http, server, location

Defines a timeout for establishing a connection with a memcached server. It should be noted that this timeout cannot usually exceed 75 seconds.

memcached_force_ranges

SYNTAX: memcached_force_ranges on | off;

Default off

Context: http, server, location
This directive appeared in version 1.7.7.

Enables byte-range support for both cached and uncached responses from the memcached server regardless of the Accept-Ranges field in these responses.

Nginx, Inc. p.208 of 506

memcached_gzip_flag

SYNTAX: memcached_gzip_flag flag;
DEFAULT —
CONTEXT: http, server, location
This directive appeared in version 1.3.6.

Enables the test for the *flag* presence in the memcached server response and sets the "Content-Encoding" response header field to "gzip" if the flag is set.

memcached_next_upstream

not found

a response was not found on the server;

off

disables passing a request to the next server.

One should bear in mind that passing a request to the next server is only possible if nothing has been sent to a client yet. That is, if an error or timeout occurs in the middle of the transferring of a response, fixing this is impossible.

The directive also defines what is considered an unsuccessful attempt of communication with a server. The cases of error, timeout and invalid_response are always considered unsuccessful attempts, even if they are not specified in the directive. The case of not_found is never considered an unsuccessful attempt.

Passing a request to the next server can be limited by the number of tries and by time.

memcached_next_upstream_timeout

SYNTAX: memcached_next_upstream_timeout time;

Default 0

Context: http, server, location

Nginx, Inc. p.209 of 506

This directive appeared in version 1.7.5.

Limits the time during which a request can be passed to the next server. The 0 value turns off this limitation.

memcached_next_upstream_tries

SYNTAX: memcached_next_upstream_tries number;

Default 0

Context: http, server, location
This directive appeared in version 1.7.5.

Limits the number of possible tries for passing a request to the next server. The 0 value turns off this limitation.

$memcached_pass$

SYNTAX: memcached_pass address;

Default —

Context: location, if in location

Sets the memcached server address. The address can be specified as a domain name or IP address, and a port:

```
memcached_pass localhost:11211;
```

or as a UNIX-domain socket path:

```
memcached_pass unix:/tmp/memcached.socket;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

memcached_read_timeout

SYNTAX: memcached_read_timeout time;

DEFAULT 60s

Context: http, server, location

Defines a timeout for reading a response from the memcached server. The timeout is set only between two successive read operations, not for the transmission of the whole response. If the memcached server does not transmit anything within this time, the connection is closed.

memcached_send_timeout

SYNTAX: memcached_send_timeout time;

DEFAULT 60s

Context: http, server, location

Nginx, Inc. p.210 of 506

Sets a timeout for transmitting a request to the memcached server. The timeout is set only between two successive write operations, not for the transmission of the whole request. If the memcached server does not receive anything within this time, the connection is closed.

memcached_socket_keepalive

SYNTAX: memcached_socket_keepalive on | off;

Default off

Context: http, server, location
This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to a memcached server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

2.32.4 Embedded Variables

\$memcached_key

Defines a key for obtaining response from a memcached server.

Nginx, Inc. p.211 of 506

2.33 Module ngx_http_mirror_module

2.33.1	Summary	12
2.33.2	Example Configuration	12
2.33.3	Directives	12
	mirror	12
	mirror_request_body	12

2.33.1 **Summary**

The ngx_http_mirror_module module (1.13.4) implements mirroring of an original request by creating background mirror subrequests. Responses to mirror subrequests are ignored.

2.33.2 Example Configuration

```
location / {
    mirror /mirror;
    proxy_pass http://backend;
}
location = /mirror {
    internal;
    proxy_pass http://test_backend$request_uri;
}
```

2.33.3 Directives

mirror

```
SYNTAX: mirror uri | off; DEFAULT off
```

Context: http, server, location

Sets the URI to which an original request will be mirrored. Several mirrors can be specified on the same configuration level.

mirror_request_body

```
SYNTAX: mirror_request_body on | off;
Default on
Context: http, server, location
```

Indicates whether the client request body is mirrored. When enabled, the client request body will be read prior to creating mirror subrequests. In this case, unbuffered client request body proxying set by the proxy_request_buffering, fastcgi_request_buffering, scgi_request_buffering, and uwsgi_request_buffering directives will be disabled.

Nginx, Inc. p.212 of 506

```
location / {
    mirror /mirror;
    mirror_request_body off;
    proxy_pass http://backend;
}

location = /mirror {
    internal;
    proxy_pass http://log_backend;
    proxy_pass_request_body off;
    proxy_pass_request_body off;
    proxy_set_header Content-Length "";
    proxy_set_header X-Original-URI $request_uri;
}
```

Nginx, Inc. p.213 of 506

2.34 Module ngx_http_mp4_module

2.34.1	Summary	.4
2.34.2	Example Configuration	5
2.34.3	Directives	5
	mp4	.5
	mp4_buffer_size	.5
	$mp4_max_buffer_size$.5
	mp4_limit_rate	.6
	$mp4_limit_rate_after$	6

2.34.1 Summary

The ngx_http_mp4_module module provides pseudo-streaming serverside support for MP4 files. Such files typically have the .mp4, .m4v, or .m4a filename extensions.

Pseudo-streaming works in alliance with a compatible Flash player. The player sends an HTTP request to the server with the start time specified in the query string argument (named simply start and specified in seconds), and the server responds with the stream such that its start position corresponds to the requested time, for example:

```
http://example.com/elephants_dream.mp4?start=238.88
```

This allows performing a random seeking at any time, or starting playback in the middle of the timeline.

To support seeking, H.264-based formats store metadata in a so-called "moov atom". It is a part of the file that holds the index information for the whole file.

To start playback, the player first needs to read metadata. This is done by sending a special request with the start=0 argument. A lot of encoding software insert the metadata at the end of the file. This is suboptimal for pseudo-streaming, because the player has to download the entire file before starting playback. If the metadata are located at the beginning of the file, it is enough for nginx to simply start sending back the file contents. If the metadata are located at the end of the file, nginx must read the entire file and prepare a new stream so that the metadata come before the media data. This involves some CPU, memory, and disk I/O overhead, so it is a good idea to prepare an original file for pseudo-streaming in advance, rather than having nginx do this on every such request.

The module also supports the end argument of an HTTP request (1.5.13) which sets the end point of playback. The end argument can be specified with the start argument or separately:

```
http://example.com/elephants_dream.mp4?start=238.88&end=555.55
```

Nginx, Inc. p.214 of 506

For a matching request with a non-zero start or end argument, nginx will read the metadata from the file, prepare the stream with the requested time range, and send it to the client. This has the same overhead as described above.

If a matching request does not include the start and end arguments, there is no overhead, and the file is sent simply as a static resource. Some players also support byte-range requests, and thus do not require this module.

This module is not built by default, it should be enabled with the --with-http_mp4_module configuration parameter.

If a third-party mp4 module was previously used, it should be disabled.

A similar pseudo-streaming support for FLV files is provided by the ngx_http_flv_module module.

2.34.2 Example Configuration

2.34.3 Directives

mp4

```
SYNTAX: mp4;
DEFAULT —
CONTEXT: location
```

Turns on module processing in a surrounding location.

mp4_buffer_size

```
SYNTAX: mp4_buffer_size size;
DEFAULT 512K
CONTEXT: http, server, location
```

Sets the initial *size* of the buffer used for processing MP4 files.

mp4_max_buffer_size

```
SYNTAX: mp4_max_buffer_size size;
DEFAULT 10M
CONTEXT: http, server, location
```

Nginx, Inc. p.215 of 506

During metadata processing, a larger buffer may become necessary. Its size cannot exceed the specified *size*, or else nginx will return the 500 Internal Server Error server error, and log the following message:

```
"/some/movie/file.mp4" mp4 moov atom is too large:
12583268, you may want to increase mp4_max_buffer_size
```

mp4_limit_rate

SYNTAX: **mp4_limit_rate** on | off | factor;

Default off

Context: http, server, location

Limits the rate of response transmission to a client. The rate is limited based on the average bitrate of the MP4 file served. To calculate the rate, the bitrate is multiplied by the specified *factor*. The special value "on" corresponds to the factor of 1.1. The special value "off" disables rate limiting. The limit is set per a request, and so if a client simultaneously opens two connections, the overall rate will be twice as much as the specified limit.

This directive is available as part of our commercial subscription.

mp4_limit_rate_after

SYNTAX: mp4_limit_rate_after time;

DEFAULT 60s

Context: http, server, location

Sets the initial amount of media data (measured in playback time) after which the further transmission of the response to a client will be rate limited.

This directive is available as part of our commercial subscription.

Nginx, Inc. p.216 of 506

2.35 Module ngx_http_perl_module

2.35.1	Summary
2.35.2	Known Issues
2.35.3	Example Configuration
2.35.4	Directives
	perl
	perl_modules
	perl_require
	perl_set
2.35.5	Calling Perl from SSI
2.35.6	The \$r Request Object Methods

2.35.1 **Summary**

The ngx_http_perl_module module is used to implement location and variable handlers in Perl and insert Perl calls into SSI.

This module is not built by default, it should be enabled with the --with-http_perl_module configuration parameter.

This module requires Perl version 5.6.1 or higher. The C compiler should be compatible with the one used to build Perl.

2.35.2 Known Issues

The module is experimental, caveat emptor applies.

In order for Perl to recompile the modified modules during reconfiguration, it should be built with the -Dusemultiplicity=yes or -Dusethreads=yes parameters. Also, to make Perl leak less memory at run time, it should be built with the -Dusemymalloc=no parameter. To check the values of these parameters in an already built Perl (preferred values are specified in the example), run:

```
$ perl -V:usemultiplicity -V:usemymalloc
usemultiplicity='define';
usemymalloc='n';
```

Note that after rebuilding Perl with the new -Dusemultiplicity=yes or -Dusethreads=yes parameters, all binary Perl modules will have to be rebuilt as well — they will just stop working with the new Perl.

There is a possibility that the main process and then worker processes will grow in size after every reconfiguration. If the main process grows to an unacceptable size, the live upgrade procedure can be applied without changing the executable file.

While the Perl module is performing a long-running operation, such as resolving a domain name, connecting to another server, or querying a database, other requests assigned to the current worker process will not be processed. It

Nginx, Inc. p.217 of 506

is thus recommended to perform only such operations that have predictable and short execution time, such as accessing the local file system.

2.35.3 Example Configuration

```
http {
    perl_modules perl/lib;
    perl_require hello.pm;

    perl_set $msie6 '

        sub {
            my $r = shift;
            my $ua = $r->header_in("User-Agent");

            return "" if $ua =~ /Opera/;
            return "1" if $ua =~ / MSIE [6-9]\.\d+/;
            return "";
        }

        ';

        server {
            location / {
                 perl hello::handler;
        }
    }
}
```

The perl/lib/hello.pm module:

```
package hello;
use nginx;
sub handler {
    my $r = shift;
    $r->send_http_header("text/html");
    return OK if $r->header_only;
    $r->print("hello!\n<br/>br/>");
    if (-f $r->filename or -d _) {
        $r->print($r->uri, " exists!\n");
    }
    return OK;
}

1;
__END__
```

2.35.4 Directives

perl

```
SYNTAX: per1 module::function|'sub { ...}';
DEFAULT —
CONTEXT: location, limit_except
```

Nginx, Inc. p.218 of 506

Sets a Perl handler for the given location.

perl_modules

```
SYNTAX: perl_modules path;
DEFAULT —
CONTEXT: http
```

Sets an additional path for Perl modules.

perl_require

```
SYNTAX: perl_require module;
DEFAULT —
CONTEXT: http
```

Defines the name of a module that will be loaded during each reconfiguration. Several perl_require directives can be present.

perLset

```
SYNTAX: perl_set $variable module::function|'sub { ...}';
DEFAULT —
CONTEXT: http
```

Installs a Perl handler for the specified variable.

2.35.5 Calling Perl from SSI

An SSI command calling Perl has the following format:

```
<!--# perl sub="module::function" arg="parameter1" arg="parameter2" ...
```

2.35.6 The \$r Request Object Methods

```
$r->args
    returns request arguments.
$r->filename
    returns a filename corresponding to the request URI.
$r->has_request_body(handler)
```

returns 0 if there is no body in a request. If there is a body, the specified handler is set for the request and 1 is returned. After reading the request body, nginx will call the specified handler. Note that the handler function should be passed by reference. Example:

```
package hello;
use nginx;
```

Nginx, Inc. p.219 of 506

```
sub handler {
    my $r = shift;

    if ($r->request_method ne "POST") {
        return DECLINED;
    }

    if ($r->has_request_body(\&post)) {
        return OK;
    }

    return HTTP_BAD_REQUEST;
}

sub post {
    my $r = shift;

    $r->send_http_header;

    $r->print("request_body: \"", $r->request_body, "\"<br/>$r->print("request_body_file: \"", $r->request_body_file, "\"<br/>br/>\n ");
    return OK;
}

1;
__END__
```

\$r->allow_ranges

enables the use of byte ranges when sending responses.

\$r->discard_request_body

instructs nginx to discard the request body.

\$r->header_in(field)

returns the value of the specified client request header field.

\$r->header_only

determines whether the whole response or only its header should be sent to the client.

\$r->header_out(field, value)

sets a value for the specified response header field.

\$r->internal_redirect(uri)

does an internal redirect to the specified *uri*. An actual redirect happens after the Perl handler execution is completed.

Since version 1.17.2, the method accepts escaped URIs and supports redirections to named locations.

```
$r->log_error(errno, message)
```

writes the specified *message* into the error_log. If *errno* is non-zero, an error code and its description will be appended to the message.

```
$r->print(text, ...)
```

passes data to a client.

\$r->request_body

returns the client request body if it has not been written to a temporary file. To ensure that the client request body is in memory, its size should

Nginx, Inc. p.220 of 506

be limited by client_max_body_size, and a sufficient buffer size should be set using client_body_buffer_size.

\$r->request_body_file

returns the name of the file with the client request body. After the processing, the file should be removed. To always write a request body to a file, client_body_in_file_only should be enabled.

\$r->request_method

returns the client request HTTP method.

\$r->remote_addr

returns the client IP address.

\$r->flush

immediately sends data to the client.

\$r->sendfile(name[, offset[, length]])

sends the specified file content to the client. Optional parameters specify the initial offset and length of the data to be transmitted. The actual data transmission happens after the Perl handler has completed.

\$r->send_http_header([type])

sends the response header to the client. The optional *type* parameter sets the value of the Content-Type response header field. If the value is an empty string, the Content-Type header field will not be sent.

\$r->status(code)

sets a response code.

\$r->sleep(milliseconds, handler)

sets the specified handler and stops request processing for the specified time. In the meantime, nginx continues to process other requests. After the specified time has elapsed, nginx will call the installed handler. Note that the handler function should be passed by reference. In order to pass data between handlers, \$r->variable() should be used. Example:

```
package hello;
use nginx;
sub handler {
   my r = shift;
    $r->discard_request_body;
    $r->variable("var", "OK");
    $r->sleep(1000, \&next);
    return OK:
sub next {
   my $r = shift;
    $r->send_http_header;
    $r->print($r->variable("var"));
    return OK;
}
1;
__END_
```

Nginx, Inc. p.221 of 506

\$r->unescape(text)

decodes a text encoded in the "%XX" form.

\$r->uri

returns a request URI.

\$r->variable(name[, value])

returns or sets the value of the specified variable. Variables are local to each request.

Nginx, Inc. p.222 of 506

${\bf 2.36}\quad {\bf Module~ngx_http_proxy_module}$

2.36.1	Summary	4
2.36.2	Example Configuration	4
2.36.3	Directives	5
	proxy_bind	5
	proxy_buffer_size	5
	proxy_buffering	5
	proxy_buffers	6
	proxy_busy_buffers_size	6
	proxy_cache	6
	proxy_cache_background_update	6
	proxy_cache_bypass	7
	proxy_cache_convert_head	7
	proxy_cache_key	7
	proxy_cache_lock	7
	proxy_cache_lock_age	8
	proxy_cache_lock_timeout	8
	proxy_cache_max_range_offset	8
	proxy_cache_methods	28
	proxy_cache_min_uses	9
	proxy_cache_path	9
	proxy_cache_purge	
	proxy_cache_revalidate	1
	proxy_cache_use_stale	2
	proxy_cache_valid	2
	proxy_connect_timeout	3
	proxy_cookie_domain	3
	proxy_cookie_flags	4
	proxy_cookie_path	5
	proxy_force_ranges	5
	proxy_headers_hash_bucket_size	
	proxy_headers_hash_max_size	6
	proxy_hide_header	6
	proxy_http_version	6
	proxy_ignore_client_abort	6
	proxy_ignore_headers	7
	proxy_intercept_errors	7
	proxy_limit_rate	7
	proxy_max_temp_file_size	
	proxy_method	
	proxy_next_upstream	
	proxy_next_upstream_timeout	
	proxy_next_upstream_tries	
	proxy_no_cache	
	proxy_pass	

Nginx, Inc. p.223 of 506

proxy_pass_header	1
proxy_pass_request_body	2
proxy_pass_request_headers	.2
proxy_read_timeout	
proxy_redirect	
proxy_request_buffering	
proxy_send_lowat	
proxy_send_timeout	
proxy_set_body	5
proxy_set_header	
proxy_socket_keepalive	
proxy_ssl_certificate	
proxy_ssl_certificate_key	
proxy_ssl_ciphers	
proxy_ssl_conf_command	
proxy_ssl_crl	
proxy_ssl_name	
proxy_ssl_password_file	7
proxy_ssl_protocols	
proxy_ssl_server_name	
proxy_ssl_session_reuse	8
proxy_ssl_trusted_certificate	
proxy_ssl_verify	
proxy_ssl_verify_depth	
proxy_store	9
proxy_store_access	
proxy_temp_file_write_size	
proxy_temp_path	

2.36.1 Summary

The ngx_http_proxy_module module allows passing requests to another server.

2.36.2 Example Configuration

```
location / {
   proxy_pass http://localhost:8000;
   proxy_set_header Host $host;
   proxy_set_header X-Real-IP $remote_addr;
}
```

Nginx, Inc. p.224 of 506

2.36.3 Directives

proxy_bind

SYNTAX: **proxy_bind** address [transparent] | off;

Default —

Context: http, server, location
This directive appeared in version 0.8.22.

Makes outgoing connections to a proxied server originate from the specified local IP address with an optional port (1.11.2). Parameter value can contain variables (1.3.12). The special value off (1.3.12) cancels the effect of the proxy_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address and port.

The transparent parameter (1.11.0) allows outgoing connections to a proxied server originate from a non-local IP address, for example, from a real IP address of a client:

```
proxy_bind $remote_addr transparent;
```

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required (1.13.8) as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the proxied server.

proxy_buffer_size

SYNTAX: proxy_buffer_size size;

DEFAULT 4k | 8k

Context: http, server, location

Sets the *size* of the buffer used for reading the first part of the response received from the proxied server. This part usually contains a small response header. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform. It can be made smaller, however.

proxy_buffering

SYNTAX: **proxy_buffering** on | off;

Default on

Context: http, server, location

Enables or disables buffering of responses from the proxied server.

When buffering is enabled, nginx receives a response from the proxied server as soon as possible, saving it into the buffers set by the proxy_buffer_size and proxy_buffers directives. If the whole response does not fit into memory, a part of it can be saved to a temporary file on the disk. Writing to temporary files

Nginx, Inc. p.225 of 506

is controlled by the proxy_max_temp_file_size and proxy_temp_file_write_size directives.

When buffering is disabled, the response is passed to a client synchronously, immediately as it is received. nginx will not try to read the whole response from the proxied server. The maximum size of the data that nginx can receive from the server at a time is set by the proxy_buffer_size directive.

Buffering can also be enabled or disabled by passing "yes" or "no" in the X-Accel-Buffering response header field. This capability can be disabled using the proxy_ignore_headers directive.

proxy_buffers

SYNTAX: **proxy_buffers** number size;

DEFAULT 8 4k | 8k

Context: http, server, location

Sets the *number* and *size* of the buffers used for reading a response from the proxied server, for a single connection. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

proxy_busy_buffers_size

SYNTAX: proxy_busy_buffers_size size;

DEFAULT 8k|16k

Context: http, server, location

When buffering of responses from the proxied server is enabled, limits the total *size* of buffers that can be busy sending a response to the client while the response is not yet fully read. In the meantime, the rest of the buffers can be used for reading the response and, if needed, buffering part of the response to a temporary file. By default, *size* is limited by the size of two buffers set by the proxy_buffer_size and proxy_buffers directives.

proxy_cache

SYNTAX: **proxy_cache** zone | off;

Default off

Context: http, server, location

Defines a shared memory zone used for caching. The same zone can be used in several places. Parameter value can contain variables (1.7.9). The off parameter disables caching inherited from the previous configuration level.

proxy_cache_background_update

SYNTAX: proxy_cache_background_update on | off;

Default off

Context: http, server, location

This directive appeared in version 1.11.10.

Nginx, Inc. p.226 of 506

Allows starting a background subrequest to update an expired cache item, while a stale cached response is returned to the client. Note that it is necessary to allow the usage of a stale cached response when it is being updated.

proxy_cache_bypass

```
SYNTAX: proxy_cache_bypass string ...;

DEFAULT —

CONTEXT: http, server, location
```

Defines conditions under which the response will not be taken from a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be taken from the cache:

```
proxy_cache_bypass $cookie_nocache $arg_nocache$arg_comment;
proxy_cache_bypass $http_pragma $http_authorization;
```

Can be used along with the proxy_no_cache directive.

proxy_cache_convert_head

```
SYNTAX: proxy_cache_convert_head on | off;
DEFAULT on
CONTEXT: http, server, location
This directive appeared in version 1.9.7.
```

Enables or disables the conversion of the "HEAD" method to "GET" for caching. When the conversion is disabled, the cache key should be configured to include the \$request_method.

proxy_cache_key

```
SYNTAX: proxy_cache_key string;
DEFAULT $scheme$proxy_host$request_uri
CONTEXT: http, server, location
```

Defines a key for caching, for example

```
proxy_cache_key "$host$request_uri $cookie_user";
```

By default, the directive's value is close to the string

```
proxy_cache_key $scheme$proxy_host$uri$is_args$args;
```

proxy_cache_lock

```
SYNTAX: proxy_cache_lock on | off;
Default off
Context: http, server, location
This directive appeared in version 1.1.12.
```

Nginx, Inc. p.227 of 506

When enabled, only one request at a time will be allowed to populate a new cache element identified according to the proxy_cache_key directive by passing a request to a proxied server. Other requests of the same cache element will either wait for a response to appear in the cache or the cache lock for this element to be released, up to the time set by the proxy_cache_lock_timeout directive.

proxy_cache_lock_age

SYNTAX: proxy_cache_lock_age time;

DEFAULT 5s

Context: http, server, location
This directive appeared in version 1.7.8.

If the last request passed to the proxied server for populating a new cache element has not completed for the specified *time*, one more request may be passed to the proxied server.

proxy_cache_lock_timeout

SYNTAX: proxy_cache_lock_timeout time;

Default 5s

CONTEXT: http, server, location
This directive appeared in version 1.1.12.

Sets a timeout for proxy_cache_lock. When the *time* expires, the request will be passed to the proxied server, however, the response will not be cached.

Before 1.7.8, the response could be cached.

proxy_cache_max_range_offset

SYNTAX: proxy_cache_max_range_offset number;

Default —

Context: http, server, location
This directive appeared in version 1.11.6.

Sets an offset in bytes for byte-range requests. If the range is beyond the offset, the range request will be passed to the proxied server and the response will not be cached.

proxy_cache_methods

SYNTAX: proxy_cache_methods GET | HEAD | POST ...;

DEFAULT GET HEAD

Context: http, server, location

This directive appeared in version 0.7.59.

If the client request method is listed in this directive then the response will be cached. "GET" and "HEAD" methods are always added to the list, though

Nginx, Inc. p.228 of 506

it is recommended to specify them explicitly. See also the proxy_no_cache directive.

proxy_cache_min_uses

```
SYNTAX: proxy_cache_min_uses number;
```

Default 1

Context: http, server, location

Sets the *number* of requests after which the response will be cached.

proxy_cache_path

```
SYNTAX: proxy_cache_path path [levels=levels]

[use_temp_path=on|off] keys_zone=name:size [inactive=time]

[max_size=size] [min_free=size] [manager_files=number]

[manager_sleep=time] [manager_threshold=time]

[loader_files=number] [loader_sleep=time]

[loader_threshold=time] [purger=on|off]

[purger_files=number] [purger_sleep=time]

[purger_threshold=time];

DEFAULT —

CONTEXT: http
```

Sets the path and other parameters of a cache. Cache data are stored in files. The file name in a cache is a result of applying the MD5 function to the cache key. The levels parameter defines hierarchy levels of a cache: from 1 to 3, each level accepts values 1 or 2. For example, in the following configuration

```
proxy_cache_path /data/nginx/cache levels=1:2 keys_zone=one:10m;
```

file names in a cache will look like this:

```
/data/nginx/cache/c/29/b7f54b2df7773722d382f4809d65029c
```

A cached response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the cache can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both cache and a directory holding temporary files are put on the same file system. The directory for temporary files is set based on the use_temp_path parameter (1.7.10). If this parameter is omitted or set to the value on, the directory set by the proxy_temp_path directive for the given location will be used. If the value is set to off, temporary files will be put directly in the cache directory.

In addition, all active keys and information about data are stored in a shared memory zone, whose *name* and *size* are configured by the keys_zone parameter. One megabyte zone can store about 8 thousand keys.

Nginx, Inc. p.229 of 506

As part of commercial subscription, the shared memory zone also stores extended cache information, thus, it is required to specify a larger zone size for the same number of keys. For example, one megabyte zone can store about 4 thousand keys.

Cached data that are not accessed during the time specified by the inactive parameter get removed from the cache regardless of their freshness. By default, inactive is set to 10 minutes.

The special "cache manager" process monitors the maximum cache size set by the max_size parameter, and the minimum amount of free space set by the min_free (1.19.1) parameter on the file system with cache. When the size is exceeded or there is not enough free space, it removes the least recently used data. The data is removed in iterations configured by manager_files, manager_threshold, and manager_sleep parameters (1.11.5). During one iteration no more than manager_files items are deleted (by default, 100). The duration of one iteration is limited by the manager_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the manager_sleep parameter (by default, 50 milliseconds) is made.

A minute after the start the special "cache loader" process is activated. It loads information about previously cached data stored on file system into a cache zone. The loading is also done in iterations. During one iteration no more than loader_files items are loaded (by default, 100). Besides, the duration of one iteration is limited by the loader_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the loader_sleep parameter (by default, 50 milliseconds) is made.

Additionally, the following parameters are available as part of our commercial subscription:

purger=on|off

Instructs whether cache entries that match a wildcard key will be removed from the disk by the cache purger (1.7.12). Setting the parameter to on (default is off) will activate the "cache purger" process that permanently iterates through all cache entries and deletes the entries that match the wildcard key.

purger_files=number

Sets the number of items that will be scanned during one iteration (1.7.12). By default, purger_files is set to 10.

purger_threshold=number

Sets the duration of one iteration (1.7.12). By default, purger_-threshold is set to 50 milliseconds.

purger_sleep=number

Sets a pause between iterations (1.7.12). By default, purger_sleep is set to 50 milliseconds.

Nginx, Inc. p.230 of 506

In versions 1.7.3, 1.7.7, and 1.11.10 cache header format has been changed. Previously cached responses will be considered invalid after upgrading to a newer nginx version.

proxy_cache_purge

```
SYNTAX: proxy_cache_purgestring ...;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.5.7.
```

Defines conditions under which the request will be considered a cache purge request. If at least one value of the string parameters is not empty and is not equal to "0" then the cache entry with a corresponding cache key is removed. The result of successful operation is indicated by returning the 204 No Content response.

If the cache key of a purge request ends with an asterisk (" \star "), all cache entries matching the wildcard key will be removed from the cache. However, these entries will remain on the disk until they are deleted for either inactivity, or processed by the cache purger (1.7.12), or a client attempts to access them.

Example configuration:

```
proxy_cache_path /data/nginx/cache keys_zone=cache_zone:10m;

map $request_method $purge_method {
    PURGE 1;
    default 0;
}

server {
    ...
    location / {
        proxy_pass http://backend;
        proxy_cache cache_zone;
        proxy_cache_key $uri;
        proxy_cache_purge $purge_method;
}
```

This functionality is available as part of our commercial subscription.

proxy_cache_revalidate

```
SYNTAX: proxy_cache_revalidate on | off;
Default off
Context: http, server, location
This directive appeared in version 1.5.7.
```

Enables revalidation of expired cache items using conditional requests with the If-Modified-Since and If-None-Match header fields.

Nginx, Inc. p.231 of 506

proxy_cache_use_stale

```
SYNTAX: proxy_cache_use_stale error | timeout | invalid_header | updating | http_500 | http_502 | http_503 | http_504 | http_403 | http_404 | http_429 | off ...;

DEFAULT off
CONTEXT: http, server, location
```

Determines in which cases a stale cached response can be used during communication with the proxied server. The directive's parameters match the parameters of the proxy_next_upstream directive.

The error parameter also permits using a stale cached response if a proxied server to process a request cannot be selected.

Additionally, the updating parameter permits using a stale cached response if it is currently being updated. This allows minimizing the number of accesses to proxied servers when updating cached data.

Using a stale cached response can also be enabled directly in the response header for a specified number of seconds after the response became stale (1.11.10). This has lower priority than using the directive parameters.

- The "stale-while-revalidate" extension of the Cache-Control header field permits using a stale cached response if it is currently being updated.
- The "stale-if-error" extension of the Cache-Control header field permits using a stale cached response in case of an error.

To minimize the number of accesses to proxied servers when populating a new cache element, the <u>proxy_cache_lock</u> directive can be used.

proxy_cache_valid

```
SYNTAX: proxy_cache_valid [code ...] time;
DEFAULT —
CONTEXT: http, server, location
```

Sets caching time for different response codes. For example, the following directives

```
proxy_cache_valid 200 302 10m;
proxy_cache_valid 404 1m;
```

set 10 minutes of caching for responses with codes 200 and 302 and 1 minute for responses with code 404.

If only caching *time* is specified

```
proxy_cache_valid 5m;
```

then only 200, 301, and 302 responses are cached.

In addition, the any parameter can be specified to cache any responses:

Nginx, Inc. p.232 of 506

```
proxy_cache_valid 200 302 10m;
proxy_cache_valid 301 1h;
proxy_cache_valid any 1m;
```

Parameters of caching can also be set directly in the response header. This has higher priority than setting of caching time using the directive.

- The X-Accel-Expires header field sets caching time of a response in seconds. The zero value disables caching for a response. If the value starts with the @ prefix, it sets an absolute time in seconds since Epoch, up to which the response may be cached.
- If the header does not include the X-Accel-Expires field, parameters of caching may be set in the header fields Expires or Cache-Control.
- If the header includes the Set-Cookie field, such a response will not be cached.
- If the header includes the Vary field with the special value "*", such a response will not be cached (1.7.7). If the header includes the Vary field with another value, such a response will be cached taking into account the corresponding request header fields (1.7.7).

Processing of one or more of these response header fields can be disabled using the proxy_ignore_headers directive.

proxy_connect_timeout

SYNTAX: proxy_connect_timeout time;

DEFAULT 60s

Context: http, server, location

Defines a timeout for establishing a connection with a proxied server. It should be noted that this timeout cannot usually exceed 75 seconds.

proxy_cookie_domain

SYNTAX: proxy_cookie_domain off;

SYNTAX: proxy_cookie_domain domain replacement;

Default off

Context: http, server, location
This directive appeared in version 1.1.15.

Sets a text that should be changed in the domain attribute of the Set-Cookie header fields of a proxied server response. Suppose a proxied server returned the Set-Cookie header field with the attribute "domain=localhost". The directive

```
proxy_cookie_domain localhost example.org;
```

Nginx, Inc. p.233 of 506

will rewrite this attribute to "domain=example.org".

A dot at the beginning of the *domain* and *replacement* strings and the domain attribute is ignored. Matching is case-insensitive.

The domain and replacement strings can contain variables:

```
proxy_cookie_domain www.$host $host;
```

The directive can also be specified using regular expressions. In this case, *domain* should start from the "~" symbol. A regular expression can contain named and positional captures, and *replacement* can reference them:

```
proxy_cookie_domain ~\.(?P<sl_domain>[-0-9a-z]+\.[a-z]+)$ $sl_domain;
```

Several proxy_cookie_domain directives can be specified on the same level:

```
proxy_cookie_domain localhost example.org;
proxy_cookie_domain ~\.([a-z]+\.[a-z]+)$ $1;
```

If several directives can be applied to the cookie, the first matching directive will be chosen.

The off parameter cancels the effect of the proxy_cookie_domain directives inherited from the previous configuration level.

proxy_cookie_flags

```
{\tt SYNTAX:} \quad \textbf{proxy\_cookie\_flags} \ \texttt{off} \ | \ \textit{cookie} \ [\textit{flag} \ \dots];
```

Default off

Context: http, server, location
This directive appeared in version 1.19.3.

Sets one or more flags for the cookie. The *cookie* can contain text, variables, and their combinations. The *flag* can contain text, variables, and their combinations (1.19.8). The secure, httponly, samesite=strict, samesite=lax, samesite=none parameters add the corresponding flags. The nosecure, nohttponly, nosamesite parameters remove the corresponding flags.

The cookie can also be specified using regular expressions. In this case, cookie should start from the " \sim " symbol.

Several proxy_cookie_flags directives can be specified on the same configuration level:

```
proxy_cookie_flags one httponly;
proxy_cookie_flags ~ nosecure samesite=strict;
```

If several directives can be applied to the cookie, the first matching directive will be chosen. In the example, the httponly flag is added to the cookie one, for all other cookies the samesite=strict flag is added and the secure flag is deleted.

Nginx, Inc. p.234 of 506

The off parameter cancels the effect of the proxy_cookie_flags directives inherited from the previous configuration level.

proxy_cookie_path

SYNTAX: proxy_cookie_path off;

SYNTAX: proxy_cookie_path path replacement;

Default off

Context: http, server, location
This directive appeared in version 1.1.15.

Sets a text that should be changed in the path attribute of the Set-Cookie header fields of a proxied server response. Suppose a proxied server returned the Set-Cookie header field with the attribute "path=/two/some/uri/". The directive

```
proxy_cookie_path /two/ /;
```

will rewrite this attribute to "path=/some/uri/".

The path and replacement strings can contain variables:

```
proxy_cookie_path $uri /some$uri;
```

The directive can also be specified using regular expressions. In this case, path should either start from the "~" symbol for a case-sensitive matching, or from the "~ \star " symbols for case-insensitive matching. The regular expression can contain named and positional captures, and replacement can reference them:

```
proxy_cookie_path ~*^/user/([^/]+) /u/$1;
```

Several proxy_cookie_path directives can be specified on the same level:

```
proxy_cookie_path /one/ /;
proxy_cookie_path / /two/;
```

If several directives can be applied to the cookie, the first matching directive will be chosen.

The off parameter cancels the effect of the proxy_cookie_path directives inherited from the previous configuration level.

proxy_force_ranges

```
SYNTAX: proxy_force_ranges on | off;
```

Default off

Context: http, server, location
This directive appeared in version 1.7.7.

Enables byte-range support for both cached and uncached responses from the proxied server regardless of the Accept-Ranges field in these responses.

Nginx, Inc. p.235 of 506

proxy_headers_hash_bucket_size

SYNTAX: proxy_headers_hash_bucket_size size;

Default 64

Context: http, server, location

Sets the bucket *size* for hash tables used by the proxy_hide_header and proxy_set_header directives. The details of setting up hash tables are provided in a separate document.

proxy_headers_hash_max_size

SYNTAX: proxy_headers_hash_max_size size;

Default 512

CONTEXT: http, server, location

Sets the maximum *size* of hash tables used by the proxy_hide_header and proxy_set_header directives. The details of setting up hash tables are provided in a separate document.

proxy_hide_header

SYNTAX: proxy_hide_header field;

Default —

Context: http, server, location

By default, nginx does not pass the header fields Date, Server, X-Pad, and X-Accel-... from the response of a proxied server to a client. The proxy_hide_header directive sets additional fields that will not be passed. If, on the contrary, the passing of fields needs to be permitted, the proxy_pass_header directive can be used.

proxy_http_version

SYNTAX: proxy_http_version 1.0 | 1.1;

Default 1.0

Context: http, server, location
This directive appeared in version 1.1.4.

Sets the HTTP protocol version for proxying. By default, version 1.0 is used. Version 1.1 is recommended for use with keepalive connections and NTLM authentication.

proxy_ignore_client_abort

SYNTAX: proxy_ignore_client_abort on | off;

Default off

Context: http, server, location

Determines whether the connection with a proxied server should be closed when a client closes the connection without waiting for a response.

Nginx, Inc. p.236 of 506

proxy_ignore_headers

SYNTAX: proxy_ignore_headers field ...;

Default —

Context: http, server, location

processing of certain response header fields from the proxied The following fields can be ignored: X-Accel-Expires, X-Accel-Redirect, X-Accel-Limit-Rate X-Accel-Buffering (1.1.6), X-Accel-Charset (1.1.6), Expires, Cache-Control, Set-Cookie (0.8.44), and Vary (1.7.7).

If not disabled, processing of these header fields has the following effect:

- X-Accel-Expires, Expires, Cache-Control, Set-Cookie, and Vary set the parameters of response caching;
- X-Accel-Redirect performs an internal redirect to the specified URI;
- X-Accel-Limit-Rate sets the rate limit for transmission of a response to a client;
- X-Accel-Buffering enables or disables buffering of a response;
- X-Accel-Charset sets the desired charset of a response.

proxy_intercept_errors

SYNTAX: proxy_intercept_errors on | off;

Default off

Context: http, server, location

Determines whether proxied responses with codes greater than or equal to 300 should be passed to a client or be intercepted and redirected to nginx for processing with the error_page directive.

proxy_limit_rate

SYNTAX: proxy_limit_rate rate;

Default 0

Context: http, server, location
This directive appeared in version 1.7.7.

Limits the speed of reading the response from the proxied server. The *rate* is specified in bytes per second. The zero value disables rate limiting. The limit is set per a request, and so if nginx simultaneously opens two connections to the proxied server, the overall rate will be twice as much as the specified limit. The limitation works only if buffering of responses from the proxied server is enabled.

Nginx, Inc. p.237 of 506

proxy_max_temp_file_size

SYNTAX: proxy_max_temp_file_size size;

DEFAULT 1024m

Context: http, server, location

When buffering of responses from the proxied server is enabled, and the whole response does not fit into the buffers set by the proxy_buffer_size and proxy_buffers directives, a part of the response can be saved to a temporary file. This directive sets the maximum *size* of the temporary file. The size of data written to the temporary file at a time is set by the proxy_temp_file_write_size directive.

The zero value disables buffering of responses to temporary files.

This restriction does not apply to responses that will be cached or stored on disk.

$proxy_method$

SYNTAX: **proxy_method** method;

Default —

Context: http, server, location

Specifies the HTTP *method* to use in requests forwarded to the proxied server instead of the method from the client request. Parameter value can contain variables (1.11.6).

proxy_next_upstream

```
SYNTAX: proxy_next_upstream error | timeout | invalid_header |
```

http_500 | http_502 | http_503 | http_504 | http_403 |

http_404 | http_429 | non_idempotent | off ...;

DEFAULT error timeout CONTEXT: http, server, location

Specifies in which cases a request should be passed to the next server:

error

an error occurred while establishing a connection with the server, passing a request to it, or reading the response header;

timeout

a timeout has occurred while establishing a connection with the server, passing a request to it, or reading the response header;

invalid_header

a server returned an empty or invalid response;

http_500

a server returned a response with the code 500;

http_502

a server returned a response with the code 502;

Nginx, Inc. p.238 of 506

```
http_503
    a server returned a response with the code 503;
http_504
    a server returned a response with the code 504;
http_403
    a server returned a response with the code 403;
http_404
    a server returned a response with the code 404;
http 429
    a server returned a response with the code 429 (1.11.13);
non_idempotent
    normally, requests with a non-idempotent method (POST, LOCK, PATCH)
    are not passed to the next server if a request has been sent to an
    upstream server (1.9.13); enabling this option explicitly allows retrying
    such requests;
off
    disables passing a request to the next server.
```

One should bear in mind that passing a request to the next server is only possible if nothing has been sent to a client yet. That is, if an error or timeout occurs in the middle of the transferring of a response, fixing this is impossible.

The directive also defines what is considered an unsuccessful attempt of communication with a server. The cases of error, timeout and invalid_header are always considered unsuccessful attempts, even if they are not specified in the directive. The cases of http_500, http_502, http_503, http_504, and http_429 are considered unsuccessful attempts only if they are specified in the directive. The cases of http_403 and http_404 are never considered unsuccessful attempts.

Passing a request to the next server can be limited by the number of tries and by time.

proxy_next_upstream_timeout

```
SYNTAX: proxy_next_upstream_timeout time;

DEFAULT 0

CONTEXT: http, server, location

This directive appeared in version 1.7.5.
```

Limits the time during which a request can be passed to the next server. The 0 value turns off this limitation.

proxy_next_upstream_tries

```
SYNTAX: proxy_next_upstream_tries number;

DEFAULT 0

CONTEXT: http, server, location

This directive appeared in version 1.7.5.
```

Nginx, Inc. p.239 of 506

Limits the number of possible tries for passing a request to the next server. The 0 value turns off this limitation.

proxy_no_cache

```
SYNTAX: proxy_no_cache string ...;

DEFAULT —

CONTEXT: http, server, location
```

Defines conditions under which the response will not be saved to a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be saved:

Can be used along with the proxy_cache_bypass directive.

proxy_pass

```
SYNTAX: proxy_pass URL;

DEFAULT —

CONTRIVED In this in the street in t
```

CONTEXT: location, if in location, limit_except

Sets the protocol and address of a proxied server and an optional URI to which a location should be mapped. As a protocol, "http" or "https" can be specified. The address can be specified as a domain name or IP address, and an optional port:

```
proxy_pass http://localhost:8000/uri/;
```

or as a UNIX-domain socket path specified after the word "unix" and enclosed in colons:

```
proxy_pass http://unix:/tmp/backend.socket:/uri/;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

Parameter value can contain variables. In this case, if an address is specified as a domain name, the name is searched among the described server groups, and, if not found, is determined using a resolver.

A request URI is passed to the server as follows:

• If the proxy_pass directive is specified with a URI, then when a request is passed to the server, the part of a normalized request URI matching the location is replaced by a URI specified in the directive:

```
location /name/ {
    proxy_pass http://127.0.0.1/remote/;
}
```

Nginx, Inc. p.240 of 506

• If proxy_pass is specified without a URI, the request URI is passed to the server in the same form as sent by a client when the original request is processed, or the full normalized request URI is passed when processing the changed URI:

```
location /some/path/ {
   proxy_pass http://127.0.0.1;
}
```

Before version 1.1.12, if proxy_pass is specified without a URI, the original request URI might be passed instead of the changed URI in some cases.

In some cases, the part of a request URI to be replaced cannot be determined:

 When location is specified using a regular expression, and also inside named locations.

In these cases, proxy_pass should be specified without a URI.

 When the URI is changed inside a proxied location using the rewrite directive, and this same configuration will be used to process a request (break):

```
location /name/ {
    rewrite     /name/([^/]+) /users?name=$1 break;
    proxy_pass http://127.0.0.1;
}
```

In this case, the URI specified in the directive is ignored and the full changed request URI is passed to the server.

When variables are used in proxy_pass:

```
location /name/ {
    proxy_pass http://127.0.0.1$request_uri;
}
```

In this case, if URI is specified in the directive, it is passed to the server as is, replacing the original request URI.

WebSocket proxying requires special configuration and is supported since version 1.3.13.

proxy_pass_header

```
SYNTAX: proxy_pass_header field;
DEFAULT —
CONTEXT: http, server, location
```

Permits passing otherwise disabled header fields from a proxied server to a client.

Nginx, Inc. p.241 of 506

proxy_pass_request_body

```
SYNTAX: proxy_pass_request_body on | off; DEFAULT on
```

CONTEXT: http, server, location

Indicates whether the original request body is passed to the proxied server.

```
location /x-accel-redirect-here/ {
   proxy_method GET;
   proxy_pass_request_body off;
   proxy_set_header Content-Length "";

   proxy_pass ...
}
```

See also the proxy_set_header and proxy_pass_request_headers directives.

proxy_pass_request_headers

```
SYNTAX: proxy_pass_request_headers on | off; Default on
```

CONTEXT: http, server, location

Indicates whether the header fields of the original request are passed to the proxied server.

```
location /x-accel-redirect-here/ {
   proxy_method GET;
   proxy_pass_request_headers off;
   proxy_pass_request_body off;

   proxy_pass ...
}
```

See also the proxy_set_header and proxy_pass_request_body directives.

proxy_read_timeout

```
{\tt SYNTAX:} \quad \textbf{proxy\_read\_timeout} \ time;
```

DEFAULT 60s

Context: http, server, location

Defines a timeout for reading a response from the proxied server. The timeout is set only between two successive read operations, not for the transmission of the whole response. If the proxied server does not transmit anything within this time, the connection is closed.

proxy_redirect

```
SYNTAX: proxy_redirect default;
SYNTAX: proxy_redirect off;
SYNTAX: proxy_redirect redirect replacement;
DEFAULT default
CONTEXT: http, server, location
```

Nginx, Inc. p.242 of 506

Sets the text that should be changed in the Location and Refresh header fields of a proxied server response. Suppose a proxied server returned the header field "Location: http://localhost:8000/two/some/uri/". The directive

```
proxy_redirect http://localhost:8000/two/ http://frontend/one/;
```

will rewrite this string to "Location: http://frontend/one/some/uri/".

A server name may be omitted in the *replacement* string:

```
proxy_redirect http://localhost:8000/two/ /;
```

then the primary server's name and port, if different from 80, will be inserted.

The default replacement specified by the default parameter uses the parameters of the location and proxy_pass directives. Hence, the two configurations below are equivalent:

```
location /one/ {
   proxy_pass http://upstream:port/two/;
   proxy_redirect default;
```

```
location /one/ {
   proxy_pass http://upstream:port/two/;
   proxy_redirect http://upstream:port/two/ /one/;
```

The default parameter is not permitted if proxy_pass is specified using variables.

A replacement string can contain variables:

```
proxy_redirect http://localhost:8000/ http://$host:$server_port/;
```

A redirect can also contain (1.1.11) variables:

```
proxy_redirect http://$proxy_host:8000/ /;
```

The directive can be specified (1.1.11) using regular expressions. In this case, redirect should either start with the "~" symbol for a case-sensitive matching, or with the "~*" symbols for case-insensitive matching. The regular expression can contain named and positional captures, and replacement can reference them:

```
proxy_redirect ~^(http://[^:]+):\d+(/.+)$ $1$2;
proxy_redirect ~*/user/([^/]+)/(.+)$ http://$1.example.com/$2;
```

Several proxy_redirect directives can be specified on the same level:

```
proxy_redirect default;
proxy_redirect http://localhost:8000/ /;
proxy_redirect http://www.example.com/ /;
```

Nginx, Inc. p.243 of 506

If several directives can be applied to the header fields of a proxied server response, the first matching directive will be chosen.

The off parameter cancels the effect of the proxy_redirect directives inherited from the previous configuration level.

Using this directive, it is also possible to add host names to relative redirects issued by a proxied server:

```
proxy_redirect / /;
```

proxy_request_buffering

```
SYNTAX: proxy_request_buffering on | off;
```

Default on

Context: http, server, location
This directive appeared in version 1.7.11.

Enables or disables buffering of a client request body.

When buffering is enabled, the entire request body is read from the client before sending the request to a proxied server.

When buffering is disabled, the request body is sent to the proxied server immediately as it is received. In this case, the request cannot be passed to the next server if nginx already started sending the request body.

When HTTP/1.1 chunked transfer encoding is used to send the original request body, the request body will be buffered regardless of the directive value unless HTTP/1.1 is enabled for proxying.

proxy_send_lowat

```
SYNTAX: proxy_send_lowat size;
```

Default 0

CONTEXT: http, server, location

If the directive is set to a non-zero value, nginx will try to minimize the number of send operations on outgoing connections to a proxied server by using either NOTE_LOWAT flag of the kqueue method, or the SO_SNDLOWAT socket option, with the specified *size*.

This directive is ignored on Linux, Solaris, and Windows.

proxy_send_timeout

SYNTAX: proxy_send_timeout time;

DEFAULT 60s

Context: http, server, location

Sets a timeout for transmitting a request to the proxied server. The timeout is set only between two successive write operations, not for the transmission of the whole request. If the proxied server does not receive anything within this time, the connection is closed.

Nginx, Inc. p.244 of 506

proxy_set_body

SYNTAX: proxy_set_body value;

Default —

CONTEXT: http, server, location

Allows redefining the request body passed to the proxied server. The *value* can contain text, variables, and their combination.

proxy_set_header

SYNTAX: proxy_set_header field value;

DEFAULT Host \$proxy_host DEFAULT Connection close CONTEXT: http, server, location

Allows redefining or appending fields to the request header passed to the proxied server. The *value* can contain text, variables, and their combinations. These directives are inherited from the previous configuration level if and only if there are no proxy_set_header directives defined on the current level. By default, only two fields are redefined:

If caching is enabled, the header fields If-Modified-Since, If-Unmodified-Since, If-None-Match, If-Match, Range, and If-Range from the original request are not passed to the proxied server.

An unchanged Host request header field can be passed like this:

```
proxy_set_header Host $http_host;
```

However, if this field is not present in a client request header then nothing will be passed. In such a case it is better to use the *\$host* variable - its value equals the server name in the Host request header field or the primary server name if this field is not present:

```
proxy_set_header Host $host;
```

In addition, the server name can be passed together with the port of the proxied server:

If the value of a header field is an empty string then this field will not be passed to a proxied server:

```
proxy_set_header Accept-Encoding "";
```

Nginx, Inc. p.245 of 506

proxy_socket_keepalive

SYNTAX: proxy_socket_keepalive on | off;

Default off

Context: http, server, location
This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to a proxied server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

proxy_ssl_certificate

SYNTAX: proxy_ssl_certificate file;

Default —

Context: http, server, location
This directive appeared in version 1.7.8.

Specifies a *file* with the certificate in the PEM format used for authentication to a proxied HTTPS server.

proxy_ssl_certificate_key

SYNTAX: proxy_ssl_certificate_key file;

Default —

Context: http, server, location
This directive appeared in version 1.7.8.

Specifies a *file* with the secret key in the PEM format used for authentication to a proxied HTTPS server.

The value engine: name: id can be specified instead of the file (1.7.9), which loads a secret key with a specified id from the OpenSSL engine name.

proxy_ssl_ciphers

SYNTAX: proxy_ssl_ciphers ciphers;

DEFAULT DEFAULT

Context: http, server, location
This directive appeared in version 1.5.6.

Specifies the enabled ciphers for requests to a proxied HTTPS server. The ciphers are specified in the format understood by the OpenSSL library.

The full list can be viewed using the "openssl ciphers" command.

proxy_ssl_conf_command

SYNTAX: proxy_ssl_conf_command command;

Default —

Context: http, server, location
This directive appeared in version 1.19.4.

Nginx, Inc. p.246 of 506

Sets arbitrary OpenSSL configuration commands when establishing a connection with the proxied HTTPS server.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several proxy_ssl_conf_command directives can be specified on the same level. These directives are inherited from the previous configuration level if and only if there are no proxy_ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

proxy_ssl_crl

SYNTAX: proxy_ssl_crl file;

Default —

Context: http, server, location
This directive appeared in version 1.7.0.

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify the certificate of the proxied HTTPS server.

proxy_ssl_name

SYNTAX: proxy_ssl_name name;

DEFAULT \$proxy_host
CONTEXT: http, server, location
This directive appeared in version 1.7.0.

Allows overriding the server name used to verify the certificate of the proxied HTTPS server and to be passed through SNI when establishing a connection with the proxied HTTPS server.

By default, the host part of the proxy_pass URL is used.

proxy_ssl_password_file

SYNTAX: proxy_ssl_password_file file;

Default —

Context: http, server, location
This directive appeared in version 1.7.8.

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

Nginx, Inc. p.247 of 506

proxy_ssl_protocols

```
SYNTAX: proxy_ssl_protocols [SSLv2] [SSLv3] [TLSv1] [TLSv1.1]

[TLSv1.2] [TLSv1.3];

DEFAULT TLSv1 TLSv1.1 TLSv1.2

CONTEXT: http, server, location

This directive appeared in version 1.5.6.
```

Enables the specified protocols for requests to a proxied HTTPS server.

proxy_ssl_server_name

```
SYNTAX: proxy_ssl_server_name on | off;
Default off
Context: http, server, location
This directive appeared in version 1.7.0.
```

Enables or disables passing of the server name through TLS Server Name Indication extension (SNI, RFC 6066) when establishing a connection with the proxied HTTPS server.

proxy_ssl_session_reuse

```
SYNTAX: proxy_ssl_session_reuse on | off;
Default on
Context: http, server, location
```

Determines whether SSL sessions can be reused when working with the proxied server. If the errors "SSL3_GET_FINISHED:digest check failed" appear in the logs, try disabling session reuse.

proxy_ssl_trusted_certificate

```
SYNTAX: proxy_ssl_trusted_certificate file;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.7.0.
```

Specifies a *file* with trusted CA certificates in the PEM format used to verify the certificate of the proxied HTTPS server.

proxy_ssl_verify

```
SYNTAX: proxy_ssl_verify on | off;
Default off
Context: http, server, location
This directive appeared in version 1.7.0.
```

Enables or disables verification of the proxied HTTPS server certificate.

Nginx, Inc. p.248 of 506

proxy_ssl_verify_depth

SYNTAX: proxy_ssl_verify_depth number;

Default 1

Context: http, server, location
This directive appeared in version 1.7.0.

Sets the verification depth in the proxied HTTPS server certificates chain.

proxy_store

```
SYNTAX: proxy_store on | off | string;
```

Default off

CONTEXT: http, server, location

Enables saving of files to a disk. The on parameter saves files with paths corresponding to the directives alias or root. The off parameter disables saving of files. In addition, the file name can be set explicitly using the *string* with variables:

```
proxy_store /data/www$original_uri;
```

The modification time of files is set according to the received Last-Modified response header field. The response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the persistent store can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both saved files and a directory holding temporary files, set by the proxy_temp_path directive, are put on the same file system.

This directive can be used to create local copies of static unchangeable files, e.g.:

or like this:

Nginx, Inc. p.249 of 506

proxy_store_access

```
SYNTAX: proxy_store_access users:permissions ...;
```

DEFAULT user:rw

Context: http, server, location

Sets access permissions for newly created files and directories, e.g.:

```
proxy_store_access user:rw group:rw all:r;
```

If any group or all access permissions are specified then user permissions may be omitted:

```
proxy_store_access group:rw all:r;
```

proxy_temp_file_write_size

SYNTAX: proxy_temp_file_write_size size;

DEFAULT 8k|16k

Context: http, server, location

Limits the *size* of data written to a temporary file at a time, when buffering of responses from the proxied server to temporary files is enabled. By default, *size* is limited by two buffers set by the proxy_buffer_size and proxy_buffers directives. The maximum size of a temporary file is set by the proxy_max_temp_file_size directive.

proxy_temp_path

SYNTAX: proxy_temp_path path [level1 [level2 [level3]]];

DEFAULT proxy_temp

CONTEXT: http, server, location

Defines a directory for storing temporary files with data received from proxied servers. Up to three-level subdirectory hierarchy can be used underneath the specified directory. For example, in the following configuration

```
proxy_temp_path /spool/nginx/proxy_temp 1 2;
```

a temporary file might look like this:

Nginx, Inc. p.250 of 506

/spool/nginx/proxy_temp/**7/45**/00000123**457**

See also the use_temp_path parameter of the proxy_cache_path directive.

2.36.4 Embedded Variables

The ngx_http_proxy_module module supports embedded variables that can be used to compose headers using the proxy_set_header directive:

$$proxy_host$

name and port of a proxied server as specified in the proxy_pass directive;

$$proxy_port$

port of a proxied server as specified in the proxy_pass directive, or the protocol's default port;

$proxy_add_x_forwarded_for$

the X-Forwarded-For client request header field with the \$remote_addr variable appended to it, separated by a comma. If the X-Forwarded-For field is not present in the client request header, the \$proxy_add_x_forwarded_for variable is equal to the \$remote_addr variable.

Nginx, Inc. p.251 of 506

2.37 Module ngx_http_random_index_module

2.37.1	Summary	52
2.37.2	Example Configuration	52
2.37.3	Directives	52
	random_index	52

2.37.1 Summary

The ngx_http_random_index_module module processes requests ending with the slash character ('/') and picks a random file in a directory to serve as an index file. The module is processed before the ngx_http_index_module module.

This module is not built by default, it should be enabled with the --with-http_random_index_module configuration parameter.

2.37.2 Example Configuration

```
location / {
   random_index on;
}
```

2.37.3 Directives

random_index

SYNTAX: random_index on | off;

Default off Context: location

Enables or disables module processing in a surrounding location.

Nginx, Inc. p.252 of 506

2.38 Module ngx_http_realip_module

2.38.1	Summary
2.38.2	Example Configuration
2.38.3	Directives
	set_real_ip_from
	real_ip_header
	real_ip_recursive
2.38.4	Embedded Variables

2.38.1 Summary

The ngx_http_realip_module module is used to change the client address and optional port to those sent in the specified header field.

This module is not built by default, it should be enabled with the --with-http_realip_module configuration parameter.

2.38.2 Example Configuration

```
set_real_ip_from 192.168.1.0/24;
set_real_ip_from 192.168.2.1;
set_real_ip_from 2001:0db8::/32;
real_ip_header X-Forwarded-For;
real_ip_recursive on;
```

2.38.3 Directives

set_real_ip_from

```
SYNTAX: set_real_ip_from address | CIDR | unix:;

DEFAULT —

CONTEXT: http, server, location
```

Defines trusted addresses that are known to send correct replacement addresses. If the special value unix: is specified, all UNIX-domain sockets will be trusted. Trusted addresses may also be specified using a hostname (1.13.1).

IPv6 addresses are supported starting from versions 1.3.0 and 1.2.1.

real_ip_header

```
SYNTAX: real_ip_header field | X-Real-IP | X-Forwarded-For | proxy_protocol;

DEFAULT X-Real-IP

CONTEXT: http, server, location
```

Nginx, Inc. p.253 of 506

Defines the request header field whose value will be used to replace the client address.

The request header field value that contains an optional port is also used to replace the client port (1.11.0). The address and port should be specified according to RFC 3986.

The proxy_protocol parameter (1.5.12) changes the client address to the one from the PROXY protocol header. The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

real_ip_recursive

SYNTAX: real_ip_recursive on | off;

Default off

Context: http, server, location

This directive appeared in versions 1.3.0 and 1.2.1.

If recursive search is disabled, the original client address that matches one of the trusted addresses is replaced by the last address sent in the request header field defined by the real_ip_header directive. If recursive search is enabled, the original client address that matches one of the trusted addresses is replaced by the last non-trusted address sent in the request header field.

2.38.4 Embedded Variables

\$realip_remote_addr keeps the original client address (1.9.7) \$realip_remote_port keeps the original client port (1.11.0)

Nginx, Inc. p.254 of 506

2.39 Module ngx_http_referer_module

2.39.1	Summary	 	 		. 255
2.39.2	Example Configuration	 	 		. 255
2.39.3	Directives	 	 		. 255
	referer_hash_bucket_size	 	 		. 255
	referer_hash_max_size	 	 		. 255
	valid_referers	 	 		. 256
2.39.4	Embedded Variables	 	 		. 256

2.39.1 Summary

The ngx_http_referer_module module is used to block access to a site for requests with invalid values in the Referer header field. It should be kept in mind that fabricating a request with an appropriate Referer field value is quite easy, and so the intended purpose of this module is not to block such requests thoroughly but to block the mass flow of requests sent by regular browsers. It should also be taken into consideration that regular browsers may not send the Referer field even for valid requests.

2.39.2 Example Configuration

2.39.3 Directives

referer_hash_bucket_size

SYNTAX: referer hash bucket size size;

Default 64

Context: server, location

This directive appeared in version 1.0.5.

Sets the bucket size for the valid referers hash tables. The details of setting up hash tables are provided in a separate document.

referer_hash_max_size

SYNTAX: referer_hash_max_size size;

Default 2048

Context: server, location

This directive appeared in version 1.0.5.

Nginx, Inc. p.255 of 506

Sets the maximum *size* of the valid referers hash tables. The details of setting up hash tables are provided in a separate document.

valid_referers

```
SYNTAX: valid_referers none | blocked | server_names | string ...;

DEFAULT —

CONTEXT: server, location
```

Specifies the Referer request header field values that will cause the embedded *\$invalid_referer* variable to be set to an empty string. Otherwise, the variable will be set to "1". Search for a match is case-insensitive.

Parameters can be as follows:

none

the Referer field is missing in the request header;

blocked

the Referer field is present in the request header, but its value has been deleted by a firewall or proxy server; such values are strings that do not start with "http://" or "https://";

```
server names
```

the Referer request header field contains one of the server names; arbitrary string

defines a server name and an optional URI prefix. A server name can have an "*" at the beginning or end. During the checking, the server's port in the Referer field is ignored;

regular expression

the first symbol should be a "~". It should be noted that an expression will be matched against the text starting after the "http://" or "https://".

Example:

```
valid_referers none blocked server_names
    *.example.com example.* www.example.org/galleries/
    ~\.google\.;
```

2.39.4 Embedded Variables

 $\$invalid_referer$

Empty string, if the Referer request header field value is considered valid, otherwise "1".

Nginx, Inc. p.256 of 506

2.40 Module ngx_http_rewrite_module

2.40.1	Summary																	257
2.40.2	Directives																	257
	break																	257
	if																	258
	return																	259
	rewrite																	259
	rewrite_log																	261
	set																	261
	uninitialize	d_{-}	va	ria	bl	e_	w	ar	n									261
2.40.3	Internal Im	la	en	ner	ıta	ti	01	า										261

2.40.1 **Summary**

The ngx_http_rewrite_module module is used to change request URI using PCRE regular expressions, return redirects, and conditionally select configurations.

The break, if, return, rewrite, and set directives are processed in the following order:

- the directives of this module specified on the server level are executed sequentially;
- repeatedly:
 - a location is searched based on a request URI;
 - the directives of this module specified inside the found location are executed sequentially;
 - the loop is repeated if a request URI was rewritten, but not more than 10 times.

2.40.2 Directives

break

SYNTAX: **break**;
DEFAULT —

CONTEXT: server, location, if

Stops processing the current set of ngx_http_rewrite_module directives.

If a directive is specified inside the location, further processing of the request continues in this location.

Example:

Nginx, Inc. p.257 of 506

```
if ($slow) {
    limit_rate 10k;
    break;
}
```

if

```
SYNTAX: if (condition) { ...}

DEFAULT —

CONTEXT: server, location
```

The specified *condition* is evaluated. If true, this module directives specified inside the braces are executed, and the request is assigned the configuration inside the if directive. Configurations inside the if directives are inherited from the previous configuration level.

A condition may be any of the following:

• a variable name; false if the value of a variable is an empty string or "0";

Before version 1.0.1, any string starting with "0" was considered a false value.

- comparison of a variable with a string using the "=" and "!=" operators;
- matching of a variable against a regular expression using the "~" (for case-sensitive matching) and "~*" (for case-insensitive matching) operators. Regular expressions can contain captures that are made available for later reuse in the \$1..\$9 variables. Negative operators "!~" and "!~*" are also available. If a regular expression includes the "}" or ";" characters, the whole expressions should be enclosed in single or double quotes.
- checking of a file existence with the "-f" and "!-f" operators;
- checking of a directory existence with the "-d" and "!-d" operators;
- checking of a file, directory, or symbolic link existence with the "-e" and "!-e" operators;
- checking for an executable file with the "-x" and "!-x" operators.

Examples:

```
if ($http_user_agent ~ MSIE) {
    rewrite ^(.*)$ /msie/$1 break;
}
if ($http_cookie ~* "id=([^;]+)(?:;|$)") {
    set $id $1;
}
if ($request_method = POST) {
    return 405;
```

Nginx, Inc. p.258 of 506

```
if ($slow) {
    limit_rate 10k;
}

if ($invalid_referer) {
    return 403;
}
```

A value of the *\$invalid_referer* embedded variable is set by the valid_referers directive.

return

```
SYNTAX: return code [text];
SYNTAX: return code URL;
SYNTAX: return URL;
DEFAULT —
CONTEXT: server, location, if
```

Stops processing and returns the specified *code* to a client. The non-standard code 444 closes a connection without sending a response header.

Starting from version 0.8.42, it is possible to specify either a redirect URL (for codes 301, 302, 303, 307, and 308) or the response body text (for other codes). A response body text and redirect URL can contain variables. As a special case, a redirect URL can be specified as a URI local to this server, in which case the full redirect URL is formed according to the request scheme (\$scheme) and the server_name_in_redirect and port_in_redirect directives.

In addition, a URL for temporary redirect with the code 302 can be specified as the sole parameter. Such a parameter should start with the "http://", "https://", or "\$scheme" string. A URL can contain variables.

```
Only the following codes could be returned before version 0.7.51: 204, 400, 402 - 406, 408, 410, 411, 413, 416, and <math>500 - 504.
```

The code 307 was not treated as a redirect until versions 1.1.16 and 1.0.13.

The code 308 was not treated as a redirect until version 1.13.0.

See also the error_page directive.

rewrite

```
SYNTAX: rewrite regex replacement [flag];
DEFAULT —
CONTEXT: server, location, if
```

If the specified regular expression matches a request URI, URI is changed as specified in the *replacement* string. The rewrite directives are executed

Nginx, Inc. p.259 of 506

sequentially in order of their appearance in the configuration file. It is possible to terminate further processing of the directives using flags. If a replacement string starts with "http://", "https://", or "\$scheme", the processing stops and the redirect is returned to a client.

An optional *flag* parameter can be one of:

last

stops processing the current set of ngx_http_rewrite_module directives and starts a search for a new location matching the changed URI;

break

stops processing the current set of ngx_http_rewrite_module directives as with the break directive;

redirect

returns a temporary redirect with the 302 code; used if a replacement string does not start with "http://", "https://", or "\$scheme"; permanent

returns a permanent redirect with the 301 code.

The full redirect URL is formed according to the request scheme (\$scheme) and the server_name_in_redirect and port_in_redirect directives.

Example:

```
server {
    ...
    rewrite ^(/download/.*)/media/(.*)\...*$ $1/mp3/$2.mp3 last;
    rewrite ^(/download/.*)/audio/(.*)\...*$ $1/mp3/$2.ra last;
    return 403;
    ...
}
```

But if these directives are put inside the "/download/" location, the last flag should be replaced by break, or otherwise nginx will make 10 cycles and return the 500 error:

```
location /download/ {
   rewrite ^(/download/.*)/media/(.*)\..*$ $1/mp3/$2.mp3 break;
   rewrite ^(/download/.*)/audio/(.*)\..*$ $1/mp3/$2.ra break;
   return 403;
}
```

If a *replacement* string includes the new request arguments, the previous request arguments are appended after them. If this is undesired, putting a question mark at the end of a replacement string avoids having them appended, for example:

```
rewrite ^/users/(.*)$ /show?user=$1? last;
```

If a regular expression includes the "}" or ";" characters, the whole expressions should be enclosed in single or double quotes.

Nginx, Inc. p.260 of 506

rewrite_log

```
SYNTAX: rewrite_log on | off;
Default off
Context: http, server, location, if
```

Enables or disables logging of ngx_http_rewrite_module module directives processing results into the error_log at the notice level.

\mathbf{set}

```
SYNTAX: set $variable value;
DEFAULT —
CONTEXT: server, location, if
```

Sets a *value* for the specified *variable*. The *value* can contain text, variables, and their combination.

uninitialized_variable_warn

```
SYNTAX: uninitialized_variable_warn on | off;
Default on
Context: http, server, location, if
```

Controls whether warnings about uninitialized variables are logged.

2.40.3 Internal Implementation

The ngx_http_rewrite_module module directives are compiled at the configuration stage into internal instructions that are interpreted during request processing. An interpreter is a simple virtual stack machine.

For example, the directives

```
location /download/ {
   if ($forbidden) {
      return 403;
   }
   if ($slow) {
      limit_rate 10k;
   }
   rewrite ^/(download/.*)/media/(.*)\..*$ /$1/mp3/$2.mp3 break;
}
```

will be translated into these instructions:

```
variable $forbidden
check against zero
return 403
end of code
variable $slow
check against zero
match of regular expression
copy "/"
copy $1
```

Nginx, Inc. p.261 of 506

```
copy "/mp3/"
copy $2
copy ".mp3"
end of regular expression
end of code
```

Note that there are no instructions for the limit_rate directive above as it is unrelated to the ngx_http_rewrite_module module. A separate configuration is created for the if block. If the condition holds true, a request is assigned this configuration where limit_rate equals to 10k.

The directive

```
rewrite ^/(download/.*)/media/(.*)\..*$ /$1/mp3/$2.mp3 break;
```

can be made smaller by one instruction if the first slash in the regular expression is put inside the parentheses:

```
rewrite ^(/download/.*)/media/(.*)\...*$ $1/mp3/$2.mp3 break;
```

The corresponding instructions will then look like this:

```
match of regular expression
copy $1
copy "/mp3/"
copy $2
copy ".mp3"
end of regular expression
end of code
```

Nginx, Inc. p.262 of 506

${\bf 2.41 \quad Module \ ngx_http_scgi_module}$

2.41.1	Summary	4
2.41.2	Example Configuration	4
2.41.3	Directives	4
	scgi_bind	4
	scgi_buffer_size	4
	scgi_buffering	5
	scgi_buffers	5
	scgi_busy_buffers_size	5
	scgi_cache	6
	scgi_cache_background_update	6
	scgi_cache_bypass	6
	scgi_cache_key	6
	scgi_cache_lock	6
	scgi_cache_lock_age	7
	scgi_cache_lock_timeout	7
	scgi_cache_max_range_offset	7
	scgi_cache_methods	7
	scgi_cache_min_uses	8
	scgi_cache_path	8
	scgi_cache_purge	0
	scgi_cache_revalidate	0
	scgi_cache_use_stale	0
	scgi_cache_valid	1
	scgi_connect_timeout	2
	scgi_force_ranges	2
	scgi_hide_header	2
	scgi_ignore_client_abort	3
	scgi_ignore_headers	3
	scgi_intercept_errors	3
	scgi_limit_rate	3
	scgi_max_temp_file_size	4
	scgi_next_upstream	4
	scgi_next_upstream_timeout	5
	scgi_next_upstream_tries	5
	scgi_no_cache	6
	scgi_param	6
	scgi_pass	6
	scgi_pass_header	7
	scgi_pass_request_body	7
	scgi_pass_request_headers	7
	scgi_read_timeout	7
	scgi_request_buffering	8
	scgi_send_timeout	8
	scgi_socket_keepalive	8

Nginx, Inc. p.263 of 506

scgi_store												278
scgi_store_access												279
scgi_temp_file_write_size												279
scgi temp path				_	_		_		_		_	280

2.41.1 Summary

The ngx_http_scgi_module module allows passing requests to an SCGI server.

2.41.2 Example Configuration

```
location / {
   include scgi_params;
   scgi_pass localhost:9000;
}
```

2.41.3 Directives

scgi_bind

```
SYNTAX: scgi_bind address [transparent] | off;
DEFAULT —
CONTEXT: http, server, location
```

Makes outgoing connections to an SCGI server originate from the specified local IP address with an optional port (1.11.2). Parameter value can contain variables (1.3.12). The special value off (1.3.12) cancels the effect of the scgi_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address and port.

The transparent parameter (1.11.0) allows outgoing connections to an SCGI server originate from a non-local IP address, for example, from a real IP address of a client:

```
scgi_bind $remote_addr transparent;
```

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required (1.13.8) as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the SCGI server.

scgi_buffer_size

```
SYNTAX: scgi_buffer_size size;
DEFAULT 4k | 8k
CONTEXT: http, server, location
```

Nginx, Inc. p.264 of 506

Sets the *size* of the buffer used for reading the first part of the response received from the SCGI server. This part usually contains a small response header. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform. It can be made smaller, however.

scgi_buffering

SYNTAX: scgi_buffering on | off;

Default on

Context: http, server, location

Enables or disables buffering of responses from the SCGI server.

When buffering is enabled, nginx receives a response from the SCGI server as soon as possible, saving it into the buffers set by the scgi_buffer_size and scgi_buffers directives. If the whole response does not fit into memory, a part of it can be saved to a temporary file on the disk. Writing to temporary files is controlled by the scgi_max_temp_file_size and scgi_temp_file_write_size directives.

When buffering is disabled, the response is passed to a client synchronously, immediately as it is received. nginx will not try to read the whole response from the SCGI server. The maximum size of the data that nginx can receive from the server at a time is set by the scgi_buffer_size directive.

Buffering can also be enabled or disabled by passing "yes" or "no" in the X-Accel-Buffering response header field. This capability can be disabled using the scgi_ignore_headers directive.

scgi_buffers

SYNTAX: scgi_buffers number size;

DEFAULT 8 4k | 8k

Context: http, server, location

Sets the *number* and *size* of the buffers used for reading a response from the SCGI server, for a single connection. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

scgi_busy_buffers_size

SYNTAX: scgi_busy_buffers_size size;

DEFAULT 8k|16k

Context: http, server, location

When buffering of responses from the SCGI server is enabled, limits the total *size* of buffers that can be busy sending a response to the client while the response is not yet fully read. In the meantime, the rest of the buffers can be used for reading the response and, if needed, buffering part of the response to a temporary file. By default, *size* is limited by the size of two buffers set by the scgi_buffer_size and scgi_buffers directives.

Nginx, Inc. p.265 of 506

scgi_cache

SYNTAX: scgi_cache zone | off;

Default off

Context: http, server, location

Defines a shared memory zone used for caching. The same zone can be used in several places. Parameter value can contain variables (1.7.9). The off parameter disables caching inherited from the previous configuration level.

scgi_cache_background_update

```
SYNTAX: scgi_cache_background_update on | off;
```

Default off

Context: http, server, location

This directive appeared in version 1.11.10.

Allows starting a background subrequest to update an expired cache item, while a stale cached response is returned to the client. Note that it is necessary to allow the usage of a stale cached response when it is being updated.

scgi_cache_bypass

```
SYNTAX: scgi_cache_bypass string ...;
```

Default —

Context: http, server, location

Defines conditions under which the response will not be taken from a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be taken from the cache:

```
scgi_cache_bypass $cookie_nocache $arg_nocache$arg_comment;
scgi_cache_bypass $http_pragma $http_authorization;
```

Can be used along with the scgi_no_cache directive.

scgi_cache_key

```
SYNTAX: scgi_cache_key string;
```

Default —

Context: http, server, location

Defines a key for caching, for example

```
scgi_cache_key localhost:9000$request_uri;
```

scgi_cache_lock

```
SYNTAX: scgi_cache_lock on | off;
```

Default off

Context: http, server, location

Nginx, Inc. p.266 of 506

This directive appeared in version 1.1.12.

When enabled, only one request at a time will be allowed to populate a new cache element identified according to the scgi_cache_key directive by passing a request to an SCGI server. Other requests of the same cache element will either wait for a response to appear in the cache or the cache lock for this element to be released, up to the time set by the scgi_cache_lock_timeout directive.

scgi_cache_lock_age

SYNTAX: scgi_cache_lock_age time;

Default 5s

Context: http, server, location
This directive appeared in version 1.7.8.

If the last request passed to the SCGI server for populating a new cache element has not completed for the specified *time*, one more request may be passed to the SCGI server.

scgi_cache_lock_timeout

SYNTAX: scgi_cache_lock_timeout time;

Default 5s

Context: http, server, location
This directive appeared in version 1.1.12.

Sets a timeout for scgi_cache_lock. When the *time* expires, the request will be passed to the SCGI server, however, the response will not be cached.

Before 1.7.8, the response could be cached.

scgi_cache_max_range_offset

```
SYNTAX: scgi_cache_max_range_offset number;
```

Default —

Context: http, server, location
This directive appeared in version 1.11.6.

Sets an offset in bytes for byte-range requests. If the range is beyond the offset, the range request will be passed to the SCGI server and the response will not be cached.

scgi_cache_methods

```
SYNTAX: scgi_cache_methods GET | HEAD | POST ...;
```

DEFAULT GET HEAD

Context: http, server, location

If the client request method is listed in this directive then the response will be cached. "GET" and "HEAD" methods are always added to the list, though it is recommended to specify them explicitly. See also the scgi_no_cache directive.

Nginx, Inc. p.267 of 506

scgi_cache_min_uses

SYNTAX: scgi_cache_min_uses number;

Default 1

Context: http, server, location

Sets the *number* of requests after which the response will be cached.

scgi_cache_path

```
SYNTAX: scgi_cache_path path [levels=levels] [use_temp_path=on|off] keys_zone=name:size [inactive=time] [max_size=size] [min_free=size] [manager_files=number] [manager_sleep=time] [manager_threshold=time] [loader_files=number] [loader_sleep=time] [loader_threshold=time] [purger=on|off] [purger_files=number] [purger_sleep=time] [purger_threshold=time];

DEFAULT —
CONTEXT: http
```

Sets the path and other parameters of a cache. Cache data are stored in files. The file name in a cache is a result of applying the MD5 function to the cache key. The levels parameter defines hierarchy levels of a cache: from 1 to 3, each level accepts values 1 or 2. For example, in the following configuration

```
scgi_cache_path /data/nginx/cache levels=1:2 keys_zone=one:10m;
```

file names in a cache will look like this:

```
/data/nginx/cache/c/29/b7f54b2df7773722d382f4809d65029c
```

A cached response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the cache can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both cache and a directory holding temporary files are put on the same file system. A directory for temporary files is set based on the use_temp_path parameter (1.7.10). If this parameter is omitted or set to the value on, the directory set by the scgi_temp_path directive for the given location will be used. If the value is set to off, temporary files will be put directly in the cache directory.

In addition, all active keys and information about data are stored in a shared memory zone, whose *name* and *size* are configured by the keys_zone parameter. One megabyte zone can store about 8 thousand keys.

As part of commercial subscription, the shared memory zone also stores extended cache information, thus, it is required to specify a larger zone size

Nginx, Inc. p.268 of 506

for the same number of keys. For example, one megabyte zone can store about 4 thousand keys.

Cached data that are not accessed during the time specified by the inactive parameter get removed from the cache regardless of their freshness. By default, inactive is set to 10 minutes.

The special "cache manager" process monitors the maximum cache size set by the max_size parameter, and the minimum amount of free space set by the min_free (1.19.1) parameter on the file system with cache. When the size is exceeded or there is not enough free space, it removes the least recently used data. The data is removed in iterations configured by manager_files, manager_threshold, and manager_sleep parameters (1.11.5). During one iteration no more than manager_files items are deleted (by default, 100). The duration of one iteration is limited by the manager_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the manager_sleep parameter (by default, 50 milliseconds) is made.

A minute after the start the special "cache loader" process is activated. It loads information about previously cached data stored on file system into a cache zone. The loading is also done in iterations. During one iteration no more than loader_files items are loaded (by default, 100). Besides, the duration of one iteration is limited by the loader_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the loader_sleep parameter (by default, 50 milliseconds) is made.

Additionally, the following parameters are available as part of our commercial subscription:

purger=on|off

Instructs whether cache entries that match a wildcard key will be removed from the disk by the cache purger (1.7.12). Setting the parameter to on (default is off) will activate the "cache purger" process that permanently iterates through all cache entries and deletes the entries that match the wildcard key.

purger_files=number

Sets the number of items that will be scanned during one iteration (1.7.12). By default, purger_files is set to 10.

purger_threshold=number

Sets the duration of one iteration (1.7.12). By default, purger_-threshold is set to 50 milliseconds.

purger_sleep=number

Sets a pause between iterations (1.7.12). By default, purger_sleep is set to 50 milliseconds.

In versions 1.7.3, 1.7.7, and 1.11.10 cache header format has been changed. Previously cached responses will be considered invalid after upgrading to a newer nginx version.

Nginx, Inc. p.269 of 506

scgi_cache_purge

```
SYNTAX: scgi_cache_purgestring ...;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.5.7.
```

Defines conditions under which the request will be considered a cache purge request. If at least one value of the string parameters is not empty and is not equal to "0" then the cache entry with a corresponding cache key is removed. The result of successful operation is indicated by returning the 204 No Content response.

If the cache key of a purge request ends with an asterisk (" \star "), all cache entries matching the wildcard key will be removed from the cache. However, these entries will remain on the disk until they are deleted for either inactivity, or processed by the cache purger (1.7.12), or a client attempts to access them.

Example configuration:

This functionality is available as part of our commercial subscription.

scgi_cache_revalidate

```
SYNTAX: scgi_cache_revalidate on | off;
DEFAULT off
CONTEXT: http, server, location
This directive appeared in version 1.5.7.
```

Enables revalidation of expired cache items using conditional requests with the If-Modified-Since and If-None-Match header fields.

scgi_cache_use_stale

```
SYNTAX: scgi_cache_use_stale error | timeout | invalid_header | updating | http_500 | http_503 | http_403 | http_404 | http_429 | off ...;

DEFAULT off
CONTEXT: http, server, location
```

Nginx, Inc. p.270 of 506

Determines in which cases a stale cached response can be used when an error occurs during communication with the SCGI server. The directive's parameters match the parameters of the scgi_next_upstream directive.

The error parameter also permits using a stale cached response if an SCGI server to process a request cannot be selected.

Additionally, the updating parameter permits using a stale cached response if it is currently being updated. This allows minimizing the number of accesses to SCGI servers when updating cached data.

Using a stale cached response can also be enabled directly in the response header for a specified number of seconds after the response became stale (1.11.10). This has lower priority than using the directive parameters.

- The "stale-while-revalidate" extension of the Cache-Control header field permits using a stale cached response if it is currently being updated.
- The "stale-if-error" extension of the Cache-Control header field permits using a stale cached response in case of an error.

To minimize the number of accesses to SCGI servers when populating a new cache element, the scgi_cache_lock directive can be used.

scgi_cache_valid

```
SYNTAX: scgi_cache_valid [code ...] time;

DEFAULT —

CONTEXT: http, server, location
```

Sets caching time for different response codes. For example, the following directives

```
scgi_cache_valid 200 302 10m;
scgi_cache_valid 404 1m;
```

set 10 minutes of caching for responses with codes 200 and 302 and 1 minute for responses with code 404.

If only caching *time* is specified

```
scgi_cache_valid 5m;
```

then only 200, 301, and 302 responses are cached.

In addition, the any parameter can be specified to cache any responses:

```
scgi_cache_valid 200 302 10m;
scgi_cache_valid 301 1h;
scgi_cache_valid any 1m;
```

Parameters of caching can also be set directly in the response header. This has higher priority than setting of caching time using the directive.

Nginx, Inc. p.271 of 506

- The X-Accel-Expires header field sets caching time of a response in seconds. The zero value disables caching for a response. If the value starts with the @ prefix, it sets an absolute time in seconds since Epoch, up to which the response may be cached.
- If the header does not include the X-Accel-Expires field, parameters of caching may be set in the header fields Expires or Cache-Control.
- If the header includes the Set-Cookie field, such a response will not be cached.
- If the header includes the Vary field with the special value "*", such a response will not be cached (1.7.7). If the header includes the Vary field with another value, such a response will be cached taking into account the corresponding request header fields (1.7.7).

Processing of one or more of these response header fields can be disabled using the scgi_ignore_headers directive.

$scgi_connect_timeout$

SYNTAX: scgi_connect_timeout time;

DEFAULT 60s

Context: http, server, location

Defines a timeout for establishing a connection with an SCGI server. It should be noted that this timeout cannot usually exceed 75 seconds.

scgi_force_ranges

SYNTAX: scgi_force_ranges on | off;

Default off

Context: http, server, location
This directive appeared in version 1.7.7.

Enables byte-range support for both cached and uncached responses from the SCGI server regardless of the Accept-Ranges field in these responses.

scgi_hide_header

SYNTAX: scgi_hide_header field;

Default —

Context: http, server, location

By default, nginx does not pass the header fields Status and X-Accel-... from the response of an SCGI server to a client. The scgi_-hide_header directive sets additional fields that will not be passed. If, on the contrary, the passing of fields needs to be permitted, the scgi_pass_header directive can be used.

Nginx, Inc. p.272 of 506

scgi_ignore_client_abort

```
SYNTAX: scgi_ignore_client_abort on | off;
```

Default off

Context: http, server, location

Determines whether the connection with an SCGI server should be closed when a client closes the connection without waiting for a response.

scgi_ignore_headers

```
SYNTAX: scgi_ignore_headers field ...;

DEFAULT —

CONTEXT: http, server, location
```

fields Disables processing certain response header from the **SCGI** The following fields can be ignored: X-Accel-Redirect, X-Accel-Expires, X-Accel-Limit-Rate (1.1.6), X-Accel-Buffering (1.1.6), X-Accel-Charset (1.1.6), Expires, Cache-Control, Set-Cookie (0.8.44), and Vary (1.7.7).

If not disabled, processing of these header fields has the following effect:

- X-Accel-Expires, Expires, Cache-Control, Set-Cookie, and Vary set the parameters of response caching;
- X-Accel-Redirect performs an internal redirect to the specified URI;
- X-Accel-Limit-Rate sets the rate limit for transmission of a response to a client;
- X-Accel-Buffering enables or disables buffering of a response;
- X-Accel-Charset sets the desired charset of a response.

scgi_intercept_errors

```
SYNTAX: scgi_intercept_errors on | off;
```

Default off

Context: http, server, location

Determines whether an SCGI server responses with codes greater than or equal to 300 should be passed to a client or be intercepted and redirected to nginx for processing with the error_page directive.

$scgi_limit_rate$

```
SYNTAX: scgi_limit_rate rate;
```

Default 0

Context: http, server, location
This directive appeared in version 1.7.7.

Nginx, Inc. p.273 of 506

Limits the speed of reading the response from the SCGI server. The *rate* is specified in bytes per second. The zero value disables rate limiting. The limit is set per a request, and so if nginx simultaneously opens two connections to the SCGI server, the overall rate will be twice as much as the specified limit. The limitation works only if buffering of responses from the SCGI server is enabled.

scgi_max_temp_file_size

SYNTAX: scgi_max_temp_file_size size;

DEFAULT 1024m

Context: http, server, location

When buffering of responses from the SCGI server is enabled, and the whole response does not fit into the buffers set by the scgi_buffer_size and scgi_buffers directives, a part of the response can be saved to a temporary file. This directive sets the maximum size of the temporary file. The size of data written to the temporary file at a time is set by the scgi_temp_file_write_size directive.

The zero value disables buffering of responses to temporary files.

This restriction does not apply to responses that will be cached or stored on disk.

$scgi_next_upstream$

```
SYNTAX: scgi_next_upstream error | timeout | invalid_header |
http_500 | http_503 | http_403 | http_404 | http_429 |
non_idempotent | off ...;

DEFAULT error timeout

CONTEXT: http, server, location
```

Specifies in which cases a request should be passed to the next server:

```
error
```

an error occurred while establishing a connection with the server, passing a request to it, or reading the response header;

timeout

a timeout has occurred while establishing a connection with the server, passing a request to it, or reading the response header;

```
invalid_header
```

a server returned an empty or invalid response;

http_500

a server returned a response with the code 500;

http_503

a server returned a response with the code 503;

http 403

a server returned a response with the code 403;

Nginx, Inc. p.274 of 506

```
http_404
a server returned a response with the code 404;
http_429
a server returned a response with the code 429 (1.11.13);
non_idempotent
normally, requests with a non-idempotent method (POST, LOCK, PATCH)
are not passed to the next server if a request has been sent to an upstream server (1.9.13); enabling this option explicitly allows retrying such requests;
off
```

disables passing a request to the next server.

One should bear in mind that passing a request to the next server is only possible if nothing has been sent to a client yet. That is, if an error or timeout occurs in the middle of the transferring of a response, fixing this is impossible.

The directive also defines what is considered an unsuccessful attempt of communication with a server. The cases of error, timeout and invalid_header are always considered unsuccessful attempts, even if they are not specified in the directive. The cases of http_500, http_503, and http_429 are considered unsuccessful attempts only if they are specified in the directive. The cases of http_403 and http_404 are never considered unsuccessful attempts.

Passing a request to the next server can be limited by the number of tries and by time.

$scgi_next_upstream_timeout$

SYNTAX: scgi_next_upstream_timeout time;

Default 0

Context: http, server, location
This directive appeared in version 1.7.5.

Limits the time during which a request can be passed to the next server. The 0 value turns off this limitation.

scgi_next_upstream_tries

SYNTAX: scgi_next_upstream_tries number;

Default 0

CONTEXT: http, server, location
This directive appeared in version 1.7.5.

Limits the number of possible tries for passing a request to the next server. The 0 value turns off this limitation.

Nginx, Inc. p.275 of 506

scgi_no_cache

```
SYNTAX: scgi_no_cache string ...;

DEFAULT —

CONTEXT: http, server, location
```

Defines conditions under which the response will not be saved to a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be saved:

```
scgi_no_cache $cookie_nocache $arg_nocache$arg_comment;
scgi_no_cache $http_pragma $http_authorization;
```

Can be used along with the scgi_cache_bypass directive.

scgi_param

```
SYNTAX: scgi_param parameter value [if_not_empty];
DEFAULT —
CONTEXT: http, server, location
```

Sets a *parameter* that should be passed to the SCGI server. The *value* can contain text, variables, and their combination. These directives are inherited from the previous configuration level if and only if there are no scgi_param directives defined on the current level.

Standard CGI environment variables should be provided as SCGI headers, see the scgi_params file provided in the distribution:

```
location / {
  include scgi_params;
  ...
}
```

If the directive is specified with if_not_empty (1.1.11) then such a parameter will be passed to the server only if its value is not empty:

```
scgi_param HTTPS $https if_not_empty;
```

scgi_pass

```
SYNTAX: scgi_pass address;
DEFAULT —
CONTEXT: location, if in location
```

Sets the address of an SCGI server. The address can be specified as a domain name or IP address, and a port:

```
scgi_pass localhost:9000;
```

or as a UNIX-domain socket path:

Nginx, Inc. p.276 of 506

```
scgi_pass unix:/tmp/scgi.socket;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

Parameter value can contain variables. In this case, if an address is specified as a domain name, the name is searched among the described server groups, and, if not found, is determined using a resolver.

scgi_pass_header

SYNTAX: scgi_pass_header field;

Default —

Context: http, server, location

Permits passing otherwise disabled header fields from an SCGI server to a client.

scgi_pass_request_body

SYNTAX: scgi_pass_request_body on | off;

Default on

Context: http, server, location

Indicates whether the original request body is passed to the SCGI server. See also the scgi_pass_request_headers directive.

scgi_pass_request_headers

SYNTAX: scgi_pass_request_headers on | off;

Default on

Context: http, server, location

Indicates whether the header fields of the original request are passed to the SCGI server. See also the scgi_pass_request_body directive.

scgi_read_timeout

SYNTAX: scgi_read_timeout time;

DEFAULT 60s

Context: http, server, location

Defines a timeout for reading a response from the SCGI server. The timeout is set only between two successive read operations, not for the transmission of the whole response. If the SCGI server does not transmit anything within this time, the connection is closed.

Nginx, Inc. p.277 of 506

scgi_request_buffering

SYNTAX: scgi_request_buffering on | off;

Default on

Context: http, server, location
This directive appeared in version 1.7.11.

Enables or disables buffering of a client request body.

When buffering is enabled, the entire request body is read from the client before sending the request to an SCGI server.

When buffering is disabled, the request body is sent to the SCGI server immediately as it is received. In this case, the request cannot be passed to the next server if nginx already started sending the request body.

When HTTP/1.1 chunked transfer encoding is used to send the original request body, the request body will be buffered regardless of the directive value.

$scgi_send_timeout$

SYNTAX: scgi_send_timeout time;

DEFAULT 60s

Context: http, server, location

Sets a timeout for transmitting a request to the SCGI server. The timeout is set only between two successive write operations, not for the transmission of the whole request. If the SCGI server does not receive anything within this time, the connection is closed.

scgi_socket_keepalive

SYNTAX: scgi_socket_keepalive on | off;

Default off

Context: http, server, location
This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to an SCGI server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

scgi_store

SYNTAX: scgi_store on | off | string;

Default off

Context: http, server, location

Enables saving of files to a disk. The on parameter saves files with paths corresponding to the directives alias or root. The off parameter disables saving of files. In addition, the file name can be set explicitly using the *string* with variables:

Nginx, Inc. p.278 of 506

```
scgi_store /data/www$original_uri;
```

The modification time of files is set according to the received Last-Modified response header field. The response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the persistent store can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both saved files and a directory holding temporary files, set by the scgi_temp_path directive, are put on the same file system.

This directive can be used to create local copies of static unchangeable files, e.g.:

scgi_store_access

```
{\tt SYNTAX:} \quad \textbf{scgi\_store\_access} \ \textit{users:permissions} \ \ldots;
```

DEFAULT user:rw

Context: http, server, location

Sets access permissions for newly created files and directories, e.g.:

```
scgi_store_access user:rw group:rw all:r;
```

If any group or all access permissions are specified then user permissions may be omitted:

```
scgi_store_access group:rw all:r;
```

scgi_temp_file_write_size

SYNTAX: scgi_temp_file_write_size size;

DEFAULT 8k|16k

Context: http, server, location

Nginx, Inc. p.279 of 506

Limits the *size* of data written to a temporary file at a time, when buffering of responses from the SCGI server to temporary files is enabled. By default, *size* is limited by two buffers set by the scgi_buffer_size and scgi_buffers directives. The maximum size of a temporary file is set by the scgi_max_temp_file_size directive.

scgi_temp_path

SYNTAX: scgi_temp_path path [level1 [level2 [level3]]];

DEFAULT scgi_temp

Context: http, server, location

Defines a directory for storing temporary files with data received from SCGI servers. Up to three-level subdirectory hierarchy can be used underneath the specified directory. For example, in the following configuration

```
scgi_temp_path /spool/nginx/scgi_temp 1 2;
```

a temporary file might look like this:

```
/spool/nginx/scgi_temp/7/45/00000123457
```

See also the use_temp_path parameter of the scgi_cache_path directive.

Nginx, Inc. p.280 of 506

2.42 Module ngx_http_secure_link_module

2.42.1	Summary										281
2.42.2	Directives										281
	secure_link										281
	$secure_link_md5$										282
	$secure_link_secret$										282
2.42.3	Embedded Variables										283

2.42.1 Summary

The ngx_http_secure_link_module module (0.7.18) is used to check authenticity of requested links, protect resources from unauthorized access, and limit link lifetime.

The authenticity of a requested link is verified by comparing the checksum value passed in a request with the value computed for the request. If a link has a limited lifetime and the time has expired, the link is considered outdated. The status of these checks is made available in the \$secure_link\$ variable.

The module provides two alternative operation modes. The first mode is enabled by the secure_link_secret directive and is used to check authenticity of requested links as well as protect resources from unauthorized access. The second mode (0.8.50) is enabled by the secure_link and secure_link_md5 directives and is also used to limit lifetime of links.

This module is not built by default, it should be enabled with the --with-http_secure_link_module configuration parameter.

2.42.2 Directives

secure_link

SYNTAX: secure_link expression;

Default —

CONTEXT: http, server, location

Defines a string with variables from which the checksum value and lifetime of a link will be extracted.

Variables used in an *expression* are usually associated with a request; see example below.

The checksum value extracted from the string is compared with the MD5 hash value of the expression defined by the secure_link_md5 directive. If the checksums are different, the \$secure_link\$ variable is set to an empty string. If the checksums are the same, the link lifetime is checked. If the link has a limited lifetime and the time has expired, the \$secure_link\$ variable is set to "0". Otherwise, it is set to "1". The MD5 hash value passed in a request is encoded in base64url.

If a link has a limited lifetime, the expiration time is set in seconds since Epoch (Thu, 01 Jan 1970 00:00:00 GMT). The value is specified in the expression after the MD5 hash, and is separated by a comma. The expiration

Nginx, Inc. p.281 of 506

time passed in a request is available through the *\$secure_link_expires* variable for a use in the <u>secure_link_md5</u> directive. If the expiration time is not specified, a link has the unlimited lifetime.

secure_link_md5

```
SYNTAX: secure_link_md5 expression;
DEFAULT —
CONTEXT: http, server, location
```

Defines an expression for which the MD5 hash value will be computed and compared with the value passed in a request.

The expression should contain the secured part of a link (resource) and a secret ingredient. If the link has a limited lifetime, the expression should also contain \$secure_link_expires.

To prevent unauthorized access, the expression may contain some information about the client, such as its address and browser version.

Example:

```
location /s/ {
    secure_link $arg_md5,$arg_expires;
    secure_link_md5 "$secure_link_expires$uri$remote_addr secret";

if ($secure_link = "") {
    return 403;
    }

if ($secure_link = "0") {
    return 410;
    }

...
}
```

The "/s/link?md5=_e4Nc3iduzkWRm01TBBNYw&expires=2147483647" link restricts access to "/s/link" for the client with the IP address 127.0.0.1. The link also has the limited lifetime until January 19, 2038 (GMT).

On UNIX, the md5 request argument value can be obtained as:

```
echo -n '2147483647/s/link127.0.0.1 secret' | \
openssl md5 -binary | openssl base64 | tr +/ -_ | tr -d =
```

secure_link_secret

```
SYNTAX: secure_link_secret word;
DEFAULT —
CONTEXT: location
```

Defines a secret *word* used to check authenticity of requested links.

The full URI of a requested link looks as follows:

```
/prefix/hash/link
```

Nginx, Inc. p.282 of 506

where *hash* is a hexadecimal representation of the MD5 hash computed for the concatenation of the link and secret word, and *prefix* is an arbitrary string without slashes.

If the requested link passes the authenticity check, the \$secure_link variable is set to the link extracted from the request URI. Otherwise, the \$secure_link variable is set to an empty string.

Example:

```
location /p/ {
    secure_link_secret secret;

if ($secure_link = "") {
    return 403;
  }

rewrite ^ /secure/$secure_link;
}

location /secure/ {
    internal;
}
```

A request of "/p/5e814704a28d9bc1914ff19fa0c4a00a/link" will be internally redirected to "/secure/link".

On UNIX, the hash value for this example can be obtained as:

```
echo -n 'linksecret' | openssl md5 -hex
```

2.42.3 Embedded Variables

\$secure_link

The status of a link check. The specific value depends on the selected operation mode.

\$secure_link_expires

The lifetime of a link passed in a request; intended to be used only in the secure_link_md5 directive.

Nginx, Inc. p.283 of 506

2.43 Module ngx_http_session_log_module

2.43.1	Summary
2.43.2	Example Configuration
2.43.3	Directives
	session_log
	session_log_format
	session_log_zone
2.43.4	Embedded Variables

2.43.1 Summary

The ngx_http_session_log_module module enables logging sessions (that is, aggregates of multiple HTTP requests) instead of individual HTTP requests.

This module is available as part of our commercial subscription.

2.43.2 Example Configuration

The following configuration sets up a session log and maps requests to sessions according to the request client address and User-Agent request header field:

2.43.3 Directives

session_log

```
SYNTAX: session_log name | off;
Default off
Context: http, server, location
```

Enables the use of the specified session log. The special value off cancels the effect of the session_log directives inherited from the previous configuration level.

session_log_format

```
SYNTAX: session_log_format name string ...;
DEFAULT combined "..."
CONTEXT: http
```

Nginx, Inc. p.284 of 506

Specifies the output format of a log. The value of the \$body_bytes_sent variable is aggregated across all requests in a session. The values of all other variables available for logging correspond to the first request in a session.

session_log_zone

```
SYNTAX: session_log_zone path zone=name:size [format=format] [timeout=time] [id=id] [md5=md5];
DEFAULT —
CONTEXT: http
```

Sets the path to a log file and configures the shared memory zone that is used to store currently active sessions.

A session is considered active for as long as the time elapsed since the last request in the session does not exceed the specified timeout (by default, 30 seconds). Once a session is no longer active, it is written to the log.

The id parameter identifies the session to which a request is mapped. The id parameter is set to the hexadecimal representation of an MD5 hash (for example, obtained from a cookie using variables). If this parameter is not specified or does not represent the valid MD5 hash, nginx computes the MD5 hash from the value of the md5 parameter and creates a new session using this hash. Both the id and md5 parameters can contain variables.

The format parameter sets the custom session log format configured by the session_log_format directive. If format is not specified, the predefined "combined" format is used.

2.43.4 Embedded Variables

The ngx_http_session_log_module module supports two embedded variables:

```
$session_log_id
current session ID;
$session_log_binary_id
current session ID in binary form (16 bytes).
```

Nginx, Inc. p.285 of 506

2.44 Module ngx_http_slice_module

2.44.1	Summary
2.44.2	Example Configuration
2.44.3	Directives
	slice
2.44.4	Embedded Variables

2.44.1 **Summary**

The ngx_http_slice_module module (1.9.8) is a filter that splits a request into subrequests, each returning a certain range of response. The filter provides more effective caching of big responses.

This module is not built by default, it should be enabled with the --with-http_slice_module configuration parameter.

2.44.2 Example Configuration

In this example, the response is split into 1-megabyte cacheable slices.

2.44.3 Directives

slice

SYNTAX: **slice** *size*; DEFAULT 0

Context: http, server, location

Sets the *size* of the slice. The zero value disables splitting responses into slices. Note that a too low value may result in excessive memory usage and opening a large number of files.

In order for a subrequest to return the required range, the *\$slice_range* variable should be passed to the proxied server as the Range request header field. If caching is enabled, *\$slice_range* should be added to the cache key and caching of responses with 206 status code should be enabled.

2.44.4 Embedded Variables

The ngx_http_slice_module module supports the following embedded variables:

Nginx, Inc. p.286 of 506

$\$slice_range$

the current slice range in HTTP byte range format, for example, bytes=0-1048575.

Nginx, Inc. p.287 of 506

2.45 Module ngx_http_split_clients_module

2.45.1	Summary	288
2.45.2	Example Configuration	288
2.45.3	Directives	288
	split_clients	288

2.45.1 Summary

The ngx_http_split_clients_module module creates variables suitable for A/B testing, also known as split testing.

2.45.2 Example Configuration

2.45.3 Directives

split_clients

```
SYNTAX: split_clients string $variable { ...} DEFAULT —
CONTEXT: http
```

Creates a variable for A/B testing, for example:

The value of the original string is hashed using MurmurHash2. In the example given, hash values from 0 to 21474835 (0.5%) correspond to the value ".one" of the \$variant variable, hash values from 21474836 to 107374180 (2%) correspond to the value ".two", and hash values from 107374181 to 4294967295 correspond to the value "" (an empty string).

Nginx, Inc. p.288 of 506

2.46 Module ngx_http_ssi_module

2.46.1	Summary	9
2.46.2	Example Configuration	9
2.46.3	Directives	9
	ssi	9
	ssi_last_modified	9
	ssi_min_file_chunk)
	ssi_silent_errors)
	ssi_types)
	ssi_value_length)
2.46.4	SSI Commands)
2.46.5	Embedded Variables	4

2.46.1 Summary

The ngx_http_ssi_module module is a filter that processes SSI (Server Side Includes) commands in responses passing through it. Currently, the list of supported SSI commands is incomplete.

2.46.2 Example Configuration

```
location / {
    ssi on;
    ...
}
```

2.46.3 Directives

ssi

```
SYNTAX: ssi on | off; DEFAULT off
```

Context: http, server, location, if in location

Enables or disables processing of SSI commands in responses.

ssi_last_modified

```
SYNTAX: ssi_last_modified on | off;
Default off
Context: http, server, location
This directive appeared in version 1.5.1.
```

Allows preserving the Last-Modified header field from the original response during SSI processing to facilitate response caching.

By default, the header field is removed as contents of the response are modified during processing and may contain dynamically generated elements or parts that are changed independently of the original response.

Nginx, Inc. p.289 of 506

ssi min file chunk

SYNTAX: **ssi_min_file_chunk** size;

Default 1k

Context: http, server, location

Sets the minimum *size* for parts of a response stored on disk, starting from which it makes sense to send them using sendfile.

ssi_silent_errors

SYNTAX: ssi_silent_errors on | off;

Default off

CONTEXT: http, server, location

If enabled, suppresses the output of the "[an error occurred while processing the directive]" string if an error occurred during SSI processing.

ssi_types

SYNTAX: ssi_types mime-type ...;

DEFAULT text/html

Context: http, server, location

Enables processing of SSI commands in responses with the specified MIME types in addition to "text/html". The special value "*" matches any MIME type (0.8.29).

ssi_value_length

SYNTAX: ssi_value_length length;

Default 256

Context: http, server, location

Sets the maximum length of parameter values in SSI commands.

2.46.4 SSI Commands

SSI commands have the following generic format:

```
<!--# command parameter1=value1 parameter2=value2 ... -->
```

The following commands are supported:

block

Defines a block that can be used as a stub in the include command. The block can contain other SSI commands. The command has the following parameter:

name

block name.

Nginx, Inc. p.290 of 506

Example:

```
<!--# block name="one" -->
stub
<!--# endblock -->
```

config

Sets some parameters used during SSI processing, namely:

errmsg

a string that is output if an error occurs during SSI processing. By default, the following string is output:

```
[an error occurred while processing the directive]
```

timefmt

a format string passed to the strftime function used to output date and time. By default, the following format is used:

```
"%A, %d-%b-%Y %H:%M:%S %Z"
```

The "%s" format is suitable to output time in seconds.

echo

Outputs the value of a variable. The command has the following parameters:

var

the variable name.

encoding

the encoding method. Possible values include none, url, and entity. By default, entity is used.

default

a non-standard parameter that sets a string to be output if a variable is undefined. By default, "(none)" is output. The command

```
<!--# echo var="name" default="no" -->
```

replaces the following sequence of commands:

```
<!--# if expr="$name" --><!--# echo var="name" --><!--# else -->no<!--# endif -->
```

if

Performs a conditional inclusion. The following commands are supported:

```
<!--# if expr="..." -->
...
<!--# elif expr="..." -->
...
```

Nginx, Inc. p.291 of 506

```
<!--# else -->
...
<!--# endif -->
```

Only one level of nesting is currently supported. The command has the following parameter:

expr

expression. An expression can be:

• variable existence check:

```
<!--# if expr="$name" -->
```

• comparison of a variable with a text:

```
<!--# if expr="$name = text" --> <!--# if expr="$name != text" -->
```

• comparison of a variable with a regular expression:

```
<!--# if expr="$name = /text/" -->
<!--# if expr="$name != /text/" -->
```

If a *text* contains variables, their values are substituted. A regular expression can contain positional and named captures that can later be used through variables, for example:

include

Includes the result of another request into a response. The command has the following parameters:

file

specifies an included file, for example:

```
<!--# include file="footer.html" -->
```

virtual

specifies an included request, for example:

```
<!--# include virtual="/remote/body.php?argument=value" -->
```

Several requests specified on one page and processed by proxied or FastCGI/uwsgi/SCGI/gRPC servers run in parallel. If sequential processing is desired, the wait parameter should be used.

Nginx, Inc. p.292 of 506

stub

a non-standard parameter that names the block whose content will be output if the included request results in an empty body or if an error occurs during the request processing, for example:

```
<!--# block name="one" -->&nbsp;<!--# endblock -->
<!--# include virtual="/remote/body.php?argument=value" stub="one"
-->
```

The replacement block content is processed in the included request context.

wait

a non-standard parameter that instructs to wait for a request to fully complete before continuing with SSI processing, for example:

```
<!--# include virtual="/remote/body.php?argument=value" wait="yes" -->
```

set

a non-standard parameter that instructs to write a successful result of request processing to the specified variable, for example:

```
<!--# include virtual="/remote/body.php?argument=value" set="one" -->
```

The maximum size of the response is set by the subrequest_output_-buffer_size directive (1.13.10):

```
location /remote/ {
    subrequest_output_buffer_size 64k;
    ...
}
```

Prior to version 1.13.10, only the results of responses obtained using the ngx_http_proxy_module, ngx_http_memcached_module, ngx_http_fastcgi_module (1.5.6), ngx_http_uwsgi_module (1.5.6), and ngx_http_scgi_module (1.5.6) modules could be written into variables. The maximum size of the response was set with the proxy_buffer_size, memcached_buffer_size, fastcgi_buffer_size, uwsgi_buffer_size, and scgi_buffer_size directives.

set

Sets a value of a variable. The command has the following parameters:

var

the variable name.

value

the variable value. If an assigned value contains variables, their values are substituted.

Nginx, Inc. p.293 of 506

2.46.5 Embedded Variables

The ngx_http_ssi_module module supports two embedded variables:

$\$date_local$

current time in the local time zone. The format is set by the config command with the timefmt parameter.

$\$date_gmt$

current time in GMT. The format is set by the config command with the timefmt parameter.

Nginx, Inc. p.294 of 506

2.47 Module ngx_http_ssl_module

2.47.1	Summary
2.47.2	Example Configuration
2.47.3	Directives
	ssl
	ssl_buffer_size
	ssl_certificate
	ssl_certificate_key
	ssl_ciphers
	ssl_client_certificate
	ssl_conf_command
	ssl_crl
	ssl_dhparam
	ssl_early_data
	ssl_ecdh_curve
	ssl_ocsp
	ssl_ocsp_cache
	ssl_ocsp_responder
	ssl_password_file
	ssl_prefer_server_ciphers
	ssl_protocols
	ssl_reject_handshake
	ssl_session_cache
	ssl_session_ticket_key
	ssl_session_tickets
	ssl_session_timeout
	ssl_stapling
	ssl_stapling_file
	ssl_stapling_responder
	ssl_stapling_verify
	ssl_trusted_certificate
	ssl_verify_client
	ssl_verify_depth
2.47.4	Error Processing
2.47.5	Embedded Variables

2.47.1 Summary

The $ngx_http_ssl_module$ module provides the necessary support for HTTPS.

This module is not built by default, it should be enabled with the --with-http_ssl_module configuration parameter.

This module requires the OpenSSL library.

Nginx, Inc. p.295 of 506

2.47.2 Example Configuration

To reduce the processor load it is recommended to

- set the number of worker processes equal to the number of processors,
- enable keep-alive connections,
- enable the shared session cache,
- disable the built-in session cache,
- and possibly increase the session lifetime (by default, 5 minutes):

2.47.3 Directives

ssl

```
SYNTAX: ssl on | off;
DEFAULT off
CONTEXT: http, server
```

This directive was made obsolete in version 1.15.0. The ssl parameter of the listen directive should be used instead.

ssl_buffer_size

```
SYNTAX: ssl_buffer_size size;
DEFAULT 16k
CONTEXT: http, server
This directive appeared in version 1.5.9.
```

Sets the size of the buffer used for sending data.

By default, the buffer size is 16k, which corresponds to minimal overhead when sending big responses. To minimize Time To First Byte it may be beneficial to use smaller values, for example:

Nginx, Inc. p.296 of 506

```
ssl_buffer_size 4k;
```

ssl_certificate

SYNTAX: ssl_certificate file;
DEFAULT —

Context: http, server

Specifies a *file* with the certificate in the PEM format for the given virtual server. If intermediate certificates should be specified in addition to a primary certificate, they should be specified in the same file in the following order: the primary certificate comes first, then the intermediate certificates. A secret key in the PEM format may be placed in the same file.

Since version 1.11.0, this directive can be specified multiple times to load certificates of different types, for example, RSA and ECDSA:

Only OpenSSL 1.0.2 or higher supports separate certificate chains for different certificates. With older versions, only one certificate chain can be used.

Since version 1.15.9, variables can be used in the *file* name when using OpenSSL 1.0.2 or higher:

```
ssl_certificate $ssl_server_name.crt;
ssl_certificate_key $ssl_server_name.key;
```

Note that using variables implies that a certificate will be loaded for each SSL handshake, and this may have a negative impact on performance.

The value data: \$variable can be specified instead of the file (1.15.10), which loads a certificate from a variable without using intermediate files. Note that inappropriate use of this syntax may have its security implications, such as writing secret key data to error log.

It should be kept in mind that due to the HTTPS protocol limitations for maximum interoperability virtual servers should listen on different IP addresses.

Nginx, Inc. p.297 of 506

ssl_certificate_key

SYNTAX: ssl_certificate_key file;

Default —

Context: http, server

Specifies a *file* with the secret key in the PEM format for the given virtual server.

The value engine: name: id can be specified instead of the file (1.7.9), which loads a secret key with a specified id from the OpenSSL engine name.

The value data: \$variable can be specified instead of the file (1.15.10), which loads a secret key from a variable without using intermediate files. Note that inappropriate use of this syntax may have its security implications, such as writing secret key data to error log.

Since version 1.15.9, variables can be used in the *file* name when using OpenSSL 1.0.2 or higher.

ssl_ciphers

SYNTAX: **ssl_ciphers** ciphers; DEFAULT HIGH:!aNULL:!MD5

Context: http, server

Specifies the enabled ciphers. The ciphers are specified in the format understood by the OpenSSL library, for example:

```
ssl_ciphers ALL:!aNULL:!EXPORT56:RC4+RSA:+HIGH:+MEDIUM:+LOW:+SSLv2:+EXP;
```

The full list can be viewed using the "openssl ciphers" command.

The previous versions of nginx used different ciphers by default.

$ssl_client_certificate$

SYNTAX: ssl_client_certificate file;

Default —

Context: http, server

Specifies a *file* with trusted CA certificates in the PEM format used to verify client certificates and OCSP responses if ssl_stapling is enabled.

The list of certificates will be sent to clients. If this is not desired, the ssl_trusted_certificate directive can be used.

ssl_conf_command

SYNTAX: ssl_conf_command command;

Default —

Context: http, server

This directive appeared in version 1.19.4.

Sets arbitrary OpenSSL configuration commands.

Nginx, Inc. p.298 of 506

The directive is supported when using OpenSSL 1.0.2 or higher.

Several ssl_conf_command directives can be specified on the same level:

```
ssl_conf_command Options PrioritizeChaCha;
ssl_conf_command Ciphersuites TLS_CHACHA20_POLY1305_SHA256;
```

These directives are inherited from the previous configuration level if and only if there are no ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

ssl_crl

SYNTAX: ssl_crl file;

Default —

Context: http, server

This directive appeared in version 0.8.7.

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify client certificates.

ssl_dhparam

SYNTAX: ssl_dhparam file;

Default —

Context: http, server

This directive appeared in version 0.7.2.

Specifies a *file* with DH parameters for DHE ciphers.

By default no parameters are set, and therefore DHE ciphers will not be used.

Prior to version 1.11.0, builtin parameters were used by default.

ssl_early_data

SYNTAX: ssl_early_data on | off;

DEFAULT off
CONTEXT: http, server

This directive appeared in version 1.15.3.

Enables or disables TLS 1.3 early data.

Requests sent within early data are subject to replay attacks. To protect against such attacks at the application layer, the \$ssl_early_data variable should be used.

Nginx, Inc. p.299 of 506

```
proxy_set_header Early-Data $ssl_early_data;
```

The directive is supported when using OpenSSL 1.1.1 or higher (1.15.4) and BoringSSL.

ssl_ecdh_curve

SYNTAX: ssl_ecdh_curve curve;

DEFAULT auto
CONTEXT: http, server

This directive appeared in versions 1.1.0 and 1.0.6.

Specifies a *curve* for ECDHE ciphers.

When using OpenSSL 1.0.2 or higher, it is possible to specify multiple curves (1.11.0), for example:

```
ssl_ecdh_curve prime256v1:secp384r1;
```

The special value auto (1.11.0) instructs nginx to use a list built into the OpenSSL library when using OpenSSL 1.0.2 or higher, or prime256v1 with older versions.

Prior to version 1.11.0, the prime256v1 curve was used by default.

When using OpenSSL 1.0.2 or higher, this directive sets the list of curves supported by the server. Thus, in order for ECDSA certificates to work, it is important to include the curves used in the certificates.

ssl_ocsp

SYNTAX: **ssl_ocsp** on | off | leaf;

Default off

Context: http, server

This directive appeared in version 1.19.0.

Enables OCSP validation of the client certificate chain. The leaf parameter enables validation of the client certificate only.

For the OCSP validation to work, the ssl_verify_client directive should be set to on or optional.

To resolve the OCSP responder hostname, the resolver directive should also be specified.

Example:

```
ssl_verify_client on;
ssl_ocsp on;
resolver 192.0.2.1;
```

Nginx, Inc. p.300 of 506

ssl_ocsp_cache

```
SYNTAX: ssl_ocsp_cache off | [shared:name:size];
DEFAULT off
CONTEXT: http, server
This directive appeared in version 1.19.0.
```

Sets name and size of the cache that stores client certificates status for OCSP validation. The cache is shared between all worker processes. A cache with the same name can be used in several virtual servers.

The off parameter prohibits the use of the cache.

ssl_ocsp_responder

```
SYNTAX: ssl_ocsp_responder url;

DEFAULT —

CONTEXT: http, server

This directive appeared in version 1.19.0.
```

Overrides the URL of the OCSP responder specified in the "Authority Information Access" certificate extension for validation of client certificates.

Only "http://" OCSP responders are supported:

```
ssl_ocsp_responder http://ocsp.example.com/;
```

$ssl_password_file$

```
SYNTAX: ssl_password_file file;

DEFAULT —

CONTEXT: http, server

This directive appeared in version 1.7.3.
```

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

Example:

```
http {
    ssl_password_file /etc/keys/global.pass;
    ...

server {
        server_name www1.example.com;
        ssl_certificate_key /etc/keys/first.key;
    }

server {
        server_name www2.example.com;

    # named pipe can also be used instead of a file ssl_password_file /etc/keys/fifo;
        ssl_certificate_key /etc/keys/second.key;
    }
}
```

Nginx, Inc. p.301 of 506

ssl_prefer_server_ciphers

```
SYNTAX: ssl_prefer_server_ciphers on | off;
Default off
Context: http, server
```

Specifies that server ciphers should be preferred over client ciphers when using the SSLv3 and TLS protocols.

ssl_protocols

```
SYNTAX: ssl_protocols [SSLv2] [SSLv3] [TLSv1] [TLSv1.1] [TLSv1.2] [TLSv1.3];

DEFAULT TLSv1 TLSv1.1 TLSv1.2

CONTEXT: http, server
```

Enables the specified protocols.

The TLSv1.1 and TLSv1.2 parameters (1.1.13, 1.0.12) work only when OpenSSL 1.0.1 or higher is used.

The TLSv1.3 parameter (1.13.0) works only when OpenSSL 1.1.1 built with TLSv1.3 support is used.

ssl_reject_handshake

```
SYNTAX: ssl_reject_handshake on | off;
DEFAULT off
CONTEXT: http, server
This directive appeared in version 1.19.4.
```

If enabled, SSL handshakes in the server block will be rejected.

For example, in the following configuration, SSL handshakes with server names other than example.com are rejected:

ssl_session_cache

Nginx, Inc. p.302 of 506

Sets the types and sizes of caches that store session parameters. A cache can be of any of the following types:

off

the use of a session cache is strictly prohibited: nginx explicitly tells a client that sessions may not be reused.

none

the use of a session cache is gently disallowed: nginx tells a client that sessions may be reused, but does not actually store session parameters in the cache.

builtin

a cache built in OpenSSL; used by one worker process only. The cache size is specified in sessions. If size is not given, it is equal to 20480 sessions. Use of the built-in cache can cause memory fragmentation.

shared

a cache shared between all worker processes. The cache size is specified in bytes; one megabyte can store about 4000 sessions. Each shared cache should have an arbitrary name. A cache with the same name can be used in several virtual servers.

Both cache types can be used simultaneously, for example:

```
ssl_session_cache builtin:1000 shared:SSL:10m;
```

but using only shared cache without the built-in cache should be more efficient.

ssl_session_ticket_key

SYNTAX: ssl_session_ticket_key file;

Default —

Context: http, server

This directive appeared in version 1.5.7.

Sets a *file* with the secret key used to encrypt and decrypt TLS session tickets. The directive is necessary if the same key has to be shared between multiple servers. By default, a randomly generated key is used.

If several keys are specified, only the first key is used to encrypt TLS session tickets. This allows configuring key rotation, for example:

```
ssl_session_ticket_key current.key;
ssl_session_ticket_key previous.key;
```

The *file* must contain 80 or 48 bytes of random data and can be created using the following command:

```
openssl rand 80 > ticket.key
```

Depending on the file size either AES256 (for 80-byte keys, 1.11.8) or AES128 (for 48-byte keys) is used for encryption.

Nginx, Inc. p.303 of 506

ssl session tickets

```
SYNTAX: ssl_session_tickets on | off;
```

Default on

Context: http, server

This directive appeared in version 1.5.9.

Enables or disables session resumption through TLS session tickets.

ssl_session_timeout

SYNTAX: ssl_session_timeout time;

DEFAULT 5m

Context: http, server

Specifies a time during which a client may reuse the session parameters.

ssl_stapling

```
SYNTAX: ssl_stapling on | off;
```

Default off

Context: http, server

This directive appeared in version 1.3.7.

Enables or disables stapling of OCSP responses by the server. Example:

```
ssl_stapling on; resolver 192.0.2.1;
```

For the OCSP stapling to work, the certificate of the server certificate issuer should be known. If the ssl_certificate file does not contain intermediate certificates, the certificate of the server certificate issuer should be present in the ssl_trusted_certificate file.

For a resolution of the OCSP responder hostname, the resolver directive should also be specified.

ssl_stapling_file

```
SYNTAX: ssl_stapling_file file;
```

Default —

Context: http, server

This directive appeared in version 1.3.7.

When set, the stapled OCSP response will be taken from the specified *file* instead of querying the OCSP responder specified in the server certificate.

The file should be in the DER format as produced by the "opensslocsp" command.

Nginx, Inc. p.304 of 506

ssl_stapling_responder

SYNTAX: ssl_stapling_responder url;

Default —

CONTEXT: http, server

This directive appeared in version 1.3.7.

Overrides the URL of the OCSP responder specified in the "Authority Information Access" certificate extension.

Only "http://" OCSP responders are supported:

```
ssl_stapling_responder http://ocsp.example.com/;
```

ssl_stapling_verify

SYNTAX: ssl_stapling_verify on | off;

Default off

Context: http, server

This directive appeared in version 1.3.7.

Enables or disables verification of OCSP responses by the server.

For verification to work, the certificate of the server certificate issuer, the root certificate, and all intermediate certificates should be configured as trusted using the ssl_trusted_certificate directive.

ssl_trusted_certificate

SYNTAX: ssl_trusted_certificate file;

Default —

Context: http, server

This directive appeared in version 1.3.7.

Specifies a *file* with trusted CA certificates in the PEM format used to verify client certificates and OCSP responses if ssl_stapling is enabled.

In contrast to the certificate set by ssl_client_certificate, the list of these certificates will not be sent to clients.

ssl_verify_client

SYNTAX: ssl_verify_client on | off | optional | optional_no_ca;

Default off Context: http, server

Enables verification of client certificates. The verification result is stored in the \$ssl_client_verify variable.

The optional parameter (0.8.7+) requests the client certificate and verifies it if the certificate is present.

The optional_no_ca parameter (1.3.8, 1.2.5) requests the client certificate but does not require it to be signed by a trusted CA certificate. This is intended for the use in cases when a service that is external to nginx

Nginx, Inc. p.305 of 506

performs the actual certificate verification. The contents of the certificate is accessible through the \$ssl_client_cert variable.

ssl_verify_depth

SYNTAX: ssl_verify_depth number;

Default 1

Context: http, server

Sets the verification depth in the client certificates chain.

2.47.4 Error Processing

The ngx_http_ssl_module module supports several non-standard error codes that can be used for redirects using the error_page directive:

495

an error has occurred during the client certificate verification;

496

a client has not presented the required certificate;

497

a regular request has been sent to the HTTPS port.

The redirection happens after the request is fully parsed and the variables, such as \$request_uri, \$uri, \$args\$ and others, are available.

2.47.5 Embedded Variables

The ngx_http_ssl_module module supports embedded variables:

\$ssl_cipher

returns the name of the cipher used for an established SSL connection; $$ssl_ciphers$

returns the list of ciphers supported by the client (1.11.7). Known ciphers are listed by names, unknown are shown in hexadecimal, for example:

```
AES128-SHA: AES256-SHA: 0x00ff
```

The variable is fully supported only when using OpenSSL version 1.0.2 or higher. With older versions, the variable is available only for new sessions and lists only known ciphers.

$$ssl_client_escaped_cert$

returns the client certificate in the PEM format (urlencoded) for an established SSL connection (1.13.5);

Nginx, Inc. p.306 of 506

\$ssl client cert

returns the client certificate in the PEM format for an established SSL connection, with each line except the first prepended with the tab character; this is intended for the use in the proxy_set_header directive;

The variable is deprecated, the *\$ssl_client_escaped_cert* variable should be used instead.

$$ssl_client_fingerprint$

returns the SHA1 fingerprint of the client certificate for an established SSL connection (1.7.1);

$$ssl_client_i_dn$

returns the "issuer DN" string of the client certificate for an established SSL connection according to RFC 2253 (1.11.6);

$ssl_client_i_dn_legacy$

returns the "issuer DN" string of the client certificate for an established SSL connection;

Prior to version 1.11.6, the variable name was \$ssl_client_i_dn.

$$ssl_client_raw_cert$

returns the client certificate in the PEM format for an established SSL connection;

$$ssl_client_s_dn$

returns the "subject DN" string of the client certificate for an established SSL connection according to RFC 2253 (1.11.6);

$ssl_client_s_dn_legacy$

returns the "subject DN" string of the client certificate for an established SSL connection;

Prior to version 1.11.6, the variable name was \$ssl_client_s_dn.

\$ssl_client_serial

returns the serial number of the client certificate for an established SSL connection;

$$ssl_client_v_end$

returns the end date of the client certificate (1.11.7);

$$ssl_client_v_remain$

returns the number of days until the client certificate expires (1.11.7);

$$ssl_client_v_start$

returns the start date of the client certificate (1.11.7);

\$ssl_client_verify

returns the result of client certificate verification: "SUCCESS", "FAILED: reason", and "NONE" if a certificate was not present;

Nginx, Inc. p.307 of 506

Prior to version 1.11.7, the "FAILED" result did not contain the *reason* string.

$$ssl_curves$

returns the list of curves supported by the client (1.11.7). Known curves are listed by names, unknown are shown in hexadecimal, for example:

```
0x001d:prime256v1:secp521r1:secp384r1
```

The variable is supported only when using OpenSSL version 1.0.2 or higher. With older versions, the variable value will be an empty string.

The variable is available only for new sessions.

$$ssl_early_data$

returns "1" if TLS 1.3 early data is used and the handshake is not complete, otherwise "" (1.15.3).

$$ssl_protocol$

returns the protocol of an established SSL connection;

\$ssl_server_name

returns the server name requested through SNI (1.7.0);

\$ssl_session_id

returns the session identifier of an established SSL connection;

$ssl_session_reused$

returns "r" if an SSL session was reused, or "." otherwise (1.5.11).

Nginx, Inc. p.308 of 506

${\bf 2.48 \quad Module \; ngx_http_status_module}$

2.48.1	Summary
2.48.2	Example Configuration
2.48.3	Directives
	status
	status_format
	status_zone
2.48.4	Data
2.48.5	Compatibility

2.48.1 Summary

The ngx_http_status_module module provides access to various status information.

This module was available as part of our commercial subscription until 1.13.10. It was superseded by the ngx_http_api_module module in 1.13.3.

2.48.2 Example Configuration

```
http {
    upstream backend {
       zone http_backend 64k;
        server backend1.example.com weight=5;
        server backend2.example.com;
    proxy_cache_path /data/nginx/cache_backend keys_zone=cache_backend:10m;
    server {
       server_name backend.example.com;
        location / {
            proxy_pass http://backend;
            proxy_cache cache_backend;
            health_check;
        status_zone server_backend;
    server {
       listen 127.0.0.1;
        location /upstream_conf {
           upstream_conf;
        location /status {
            status;
        location = /status.html {
```

Nginx, Inc. p.309 of 506

```
stream {
    upstream backend {
        zone stream_backend 64k;

        server backendl.example.com:12345 weight=5;
        server backend2.example.com:12345;
}

server {
    listen    127.0.0.1:12345;
    proxy_pass backend;
    status_zone server_backend;
    health_check;
}
```

Examples of status requests with this configuration:

```
http://127.0.0.1/status/nginx_version
http://127.0.0.1/status/nginx_version
http://127.0.0.1/status/caches/cache_backend
http://127.0.0.1/status/upstreams
http://127.0.0.1/status/upstreams/backend
http://127.0.0.1/status/upstreams/backend/peers/1
http://127.0.0.1/status/upstreams/backend/peers/1/weight
http://127.0.0.1/status/stream
http://127.0.0.1/status/stream/upstreams
http://127.0.0.1/status/stream/upstreams/backend
http://127.0.0.1/status/stream/upstreams/backend/peers/1
http://127.0.0.1/status/stream/upstreams/backend/peers/1
http://127.0.0.1/status/stream/upstreams/backend/peers/1/weight
```

The simple monitoring page is shipped with this distribution, accessible as "/status.html" in the default configuration. It requires the locations "/status" and "/status.html" to be configured as shown above.

2.48.3 Directives

status

```
SYNTAX: status;
DEFAULT —
CONTEXT: location
```

The status information will be accessible from the surrounding location. Access to this location should be limited.

status_format

```
SYNTAX: status_format json;
SYNTAX: status_format jsonp [callback];
DEFAULT json
CONTEXT: http, server, location
```

By default, status information is output in the JSON format.

Alternatively, data may be output as JSONP. The *callback* parameter specifies the name of a callback function. Parameter value can contain

Nginx, Inc. p.310 of 506

variables. If parameter is omitted, or the computed value is an empty string, then "ngx_status_jsonp_callback" is used.

status_zone

SYNTAX: **status_zone** zone;
DEFAULT —

Context: server

Enables collection of virtual http or stream (1.7.11) server status information in the specified *zone*. Several servers may share the same zone.

2.48.4 Data

The following status information is provided:

version

Version of the provided data set. The current version is 8.

nginx_version

Version of nginx.

nginx_build

Name of nginx build.

address

The address of the server that accepted status request.

generation

The total number of configuration reloads.

load_timestamp

Time of the last reload of configuration, in milliseconds since Epoch.

timestamp

Current time in milliseconds since Epoch.

pid

The ID of the worker process that handled status request.

ppid

The ID of the master process that started the worker process.

processes

respawned

The total number of abnormally terminated and respawned child processes.

connections

accepted

The total number of accepted client connections.

dropped

The total number of dropped client connections.

active

The current number of active client connections.

Nginx, Inc. p.311 of 506

```
idle
```

The current number of idle client connections.

ssl

handshakes

The total number of successful SSL handshakes.

handshakes_failed

The total number of failed SSL handshakes.

session_reuses

The total number of session reuses during SSL handshake.

requests

total

The total number of client requests.

current

The current number of client requests.

server_zones

For each status_zone:

processing

The number of client requests that are currently being processed.

requests

The total number of client requests received from clients.

responses

total

The total number of responses sent to clients.

1xx, 2xx, 3xx, 4xx, 5xx

The number of responses with status codes 1xx, 2xx, 3xx, 4xx, and 5xx.

discarded

The total number of requests completed without sending a response.

received

The total number of bytes received from clients.

sent

The total number of bytes sent to clients.

slabs

For each shared memory zone that uses slab allocator:

pages

used

The current number of used memory pages.

free

The current number of free memory pages.

slots

For each memory slot size (8, 16, 32, 64, 128, etc.) the following data are provided:

Nginx, Inc. p.312 of 506

```
used
             The current number of used memory slots.
             The current number of free memory slots.
             The total number of attempts to allocate memory of specified
             size.
          fails
             The number of unsuccessful attempts to allocate memory of
             specified size.
upstreams
    For each dynamically configurable group, the following data are provided:
         For each server, the following data are provided:
          id
             The ID of the server.
          server
             An address of the server.
          name
             The name of the server specified in the server directive.
          service
             The service parameter value of the server directive.
             A boolean value indicating whether the server is a backup
             server.
          weight
             Weight of the server.
             Current state, which may be one of "up", "draining", "down",
             "unavail", "checking", or "unhealthy".
             The current number of active connections.
          max conns
             The max_conns limit for the server.
          requests
             The total number of client requests forwarded to this server.
          responses
              total
                 The total number of responses obtained from this server.
              1xx, 2xx, 3xx, 4xx, 5xx
                 The number of responses with status codes 1xx, 2xx, 3xx,
                 4xx, and 5xx.
          sent
             The total number of bytes sent to this server.
```

Nginx, Inc. p.313 of 506

received

The total number of bytes received from this server.

fails

The total number of unsuccessful attempts to communicate with the server.

unavail

How many times the server became unavailable for client requests (state "unavail") due to the number of unsuccessful attempts reaching the max_fails threshold.

health_checks

checks

The total number of health check requests made.

fails

The number of failed health checks.

unhealthy

How many times the server became unhealthy (state "unhealthy").

last passed

Boolean indicating if the last health check request was successful and passed tests.

downtime

Total time the server was in the "unavail", "checking", and "unhealthy" states.

downstart

The time (in milliseconds since Epoch) when the server became "unavail", "checking", or "unhealthy".

selected

The time (in milliseconds since Epoch) when the server was last selected to process a request (1.7.5).

header time

The average time to get the response header from the server (1.7.10). Prior to version 1.11.6, the field was available only when using the least_time load balancing method.

response_time

The average time to get the full response from the server (1.7.10). Prior to version 1.11.6, the field was available only when using the least_time load balancing method.

keepalive

The current number of idle keepalive connections.

zombies

The current number of servers removed from the group but still processing active client requests.

zone

The name of the shared memory zone that keeps the group's configuration and run-time state.

Nginx, Inc. p.314 of 506

```
queue
        For the requests queue, the following data are provided:
             The current number of requests in the queue.
          max_size
             The maximum number of requests that can be in the queue at
             the same time.
          overflows
             The total number of requests rejected due to the queue overflow.
caches
    For each cache (configured by proxy_cache_path and the likes):
     size
         The current size of the cache.
     max size
         The limit on the maximum size of the cache specified in the
        configuration.
     cold
         A boolean value indicating whether the "cache loader" process is
        still loading data from disk into the cache.
     hit, stale, updating, revalidated
          responses
             The total number of responses read from the cache (hits, or
            stale responses due to proxy_cache_use_stale and the likes).
          bytes
             The total number of bytes read from the cache.
     miss, expired, bypass
          responses
             The total number of responses not taken from the cache (misses,
             expires, or bypasses due to proxy_cache_bypass and the likes).
         bytes
             The total number of bytes read from the proxied server.
          responses_written
             The total number of responses written to the cache.
          bytes_written
             The total number of bytes written to the cache.
stream
     server zones
        For each status_zone:
          processing
             The number of client connections that are currently being
             processed.
          connections
             The total number of connections accepted from clients.
```

Nginx, Inc. p.315 of 506

```
sessions
        total
           The total number of completed client sessions.
        2xx, 4xx, 5xx
           The number of sessions completed with status codes 2xx,
           4xx, or 5xx.
    discarded
       The total number of connections completed without creating a
       session.
    received
       The total number of bytes received from clients.
       The total number of bytes sent to clients.
upstreams
   For each dynamically configurable group, the following data are
   provided:
    peers
       For each server the following data are provided:
           The ID of the server.
         server
           An address of the server.
        name
           The name of the server specified in the server directive.
         service
           The service parameter value of the server directive.
           A boolean value indicating whether the server is a backup
           server.
        weight
           Weight of the server.
         state
           Current state, which may be one of "up", "down",
           "unavail", "checking", or "unhealthy".
        active
           The current number of connections.
        max conns
           The max_conns limit for the server.
           The total number of client connections forwarded to this
           server.
         connect time
           The average time to connect to the upstream server. Prior
           to version 1.11.6, the field was available only when using
           the least_time load balancing method.
```

Nginx, Inc. p.316 of 506

first_byte_time

The average time to receive the first byte of data. Prior to version 1.11.6, the field was available only when using the least_time load balancing method.

response_time

The average time to receive the last byte of data. Prior to version 1.11.6, the field was available only when using the least_time load balancing method.

sent

The total number of bytes sent to this server.

received

The total number of bytes received from this server.

fails

The total number of unsuccessful attempts to communicate with the server.

unavail

How many times the server became unavailable for client connections (state "unavail") due to the number of unsuccessful attempts reaching the max_fails threshold.

health checks

checks

The total number of health check requests made.

fails

The number of failed health checks.

unhealthy

How many times the server became unhealthy (state "unhealthy").

last_passed

Boolean indicating if the last health check request was successful and passed tests.

downtime

Total time the server was in the "unavail", "checking", and "unhealthy" states.

downstart

The time (in milliseconds since Epoch) when the server became "unavail", "checking", or "unhealthy".

selected

The time (in milliseconds since Epoch) when the server was last selected to process a connection.

zombies

The current number of servers removed from the group but still processing active client connections.

zone

The name of the shared memory zone that keeps the group's configuration and run-time state.

Nginx, Inc. p.317 of 506

2.48.5 Compatibility

• The zone field in http and stream upstreams was added in version 8.

2.48. MODULE NGX_HTTP_STATUS_MODULE

- The slabs status data were added in version 8.
- The checking state was added in version 8.
- The name and service fields in http and stream upstreams were added in version 8.
- The nginx_build and ppid fields were added in version 8.
- The sessions status data and the discarded field in stream server_zones were added in version 7.
- The zombies field was moved from nginx debug version in version 6.
- The ssl status data were added in version 6.
- The discarded field in server_zones was added in version 6.
- The queue status data were added in version 6.
- The pid field was added in version 6.
- The list of servers in upstreams was moved into peers in version 6.
- The keepalive field of an upstream server was removed in version 5.
- The stream status data were added in version 5.
- The generation field was added in version 5.
- The respawned field in processes was added in version 5.
- The header_time and response_time fields in upstreams were added in version 5.
- The selected field in upstreams was added in version 4.
- The draining state in upstreams was added in version 4.
- The id and max_conns fields in upstreams were added in version 3.
- The revalidated field in caches was added in version 3.
- The server_zones, caches, and load_timestamp status data were added in version 2.

Nginx, Inc. p.318 of 506

2.49 Module ngx_http_stub_status_module

2.49.1	Summary
2.49.2	Example Configuration
2.49.3	Directives
	stub_status
2.49.4	Data
2.49.5	Embedded Variables

2.49.1 Summary

The ngx_http_stub_status_module module provides access to basic status information.

This module is not built by default, it should be enabled with the --with-http_stub_status_module configuration parameter.

2.49.2 Example Configuration

```
location = /basic_status {
    stub_status;
}
```

This configuration creates a simple web page with basic status data which may look like as follows:

```
Active connections: 291
server accepts handled requests
16630948 16630948 31070465
Reading: 6 Writing: 179 Waiting: 106
```

2.49.3 Directives

$stub_status$

```
SYNTAX: stub_status;
DEFAULT —
```

Context: server, location

The basic status information will be accessible from the surrounding location.

In versions prior to 1.7.5, the directive syntax required an arbitrary argument, for example, "stub_status on".

Nginx, Inc. p.319 of 506

2.49.4 Data

The following status information is provided:

Active connections

The current number of active client connections including Waiting connections.

accepts

The total number of accepted client connections.

handled

The total number of handled connections. Generally, the parameter value is the same as accepts unless some resource limits have been reached (for example, the worker_connections limit).

requests

The total number of client requests.

Reading

The current number of connections where nginx is reading the request header.

Writing

The current number of connections where nginx is writing the response back to the client.

Waiting

The current number of idle client connections waiting for a request.

2.49.5 Embedded Variables

The ngx_http_stub_status_module module supports the following embedded variables (1.3.14):

\$connections_active

same as the Active connections value;

 $$connections_reading$

same as the Reading value;

 $$connections_writing$

same as the Writing value;

 $$connections_waiting$

same as the Waiting value.

Nginx, Inc. p.320 of 506

2.50 Module ngx_http_sub_module

2.50.1	Summary	21
2.50.2	Example Configuration	21
2.50.3	Directives	21
	sub_filter	21
	sub_filter_last_modified	21
	sub_filter_once	22
	sub_filter_types	22

2.50.1 Summary

The ngx_http_sub_module module is a filter that modifies a response by replacing one specified string by another.

This module is not built by default, it should be enabled with the --with-http_sub_module configuration parameter.

2.50.2 Example Configuration

```
location / {
   sub_filter '<a href="http://127.0.0.1:8080/' '<a href="https://$host/';
   sub_filter '<img src="http://127.0.0.1:8080/' '<img src="https://$host/';
   sub_filter_once on;
}</pre>
```

2.50.3 Directives

sub_filter

```
SYNTAX: sub_filter string replacement;
DEFAULT —
CONTEXT: http, server, location
```

Sets a string to replace and a replacement string. The string to replace is matched ignoring the case. The string to replace (1.9.4) and replacement string can contain variables. Several sub_filter directives can be specified on the same configuration level (1.9.4). These directives are inherited from the previous configuration level if and only if there are no sub_filter directives

sub_filter_last_modified

defined on the current level.

```
SYNTAX: sub_filter_last_modified on | off;
Default off
Context: http, server, location
This directive appeared in version 1.5.1.
```

Allows preserving the Last-Modified header field from the original response during replacement to facilitate response caching.

Nginx, Inc. p.321 of 506

By default, the header field is removed as contents of the response are modified during processing.

sub_filter_once

SYNTAX: **sub_filter_once** on | off;

Default on

Context: http, server, location

Indicates whether to look for each string to replace once or repeatedly.

sub_filter_types

SYNTAX: sub_filter_types mime-type ...;

DEFAULT text/html

Context: http, server, location

Enables string replacement in responses with the specified MIME types in addition to "text/html". The special value "*" matches any MIME type (0.8.29).

Nginx, Inc. p.322 of 506

2.51 Module ngx_http_upstream_module

2.51.1	Summary
2.51.2	Example Configuration
2.51.3	Directives
	upstream
	server
	zone
	state
	hash
	ip_hash
	keepalive
	keepalive_requests
	keepalive_time
	keepalive_timeout
	ntlm
	least_conn
	least_time
	queue
	random
	resolver
	resolver_timeout
	sticky
	sticky_cookie_insert
2.51.4	Embedded Variables

2.51.1 Summary

The ngx_http_upstream_module module is used to define groups of servers that can be referenced by the proxy_pass, fastcgi_pass, uwsgi_pass, scgi_pass, memcached_pass, and grpc_pass directives.

2.51.2 Example Configuration

Dynamically configurable group with periodic health checks is available as part of our commercial subscription:

Nginx, Inc. p.323 of 506

```
resolver 10.0.0.1;
upstream dynamic {
   zone upstream_dynamic 64k;
   server backend1.example.com
                                   weight=5;
   server backend2.example.com:8080 fail_timeout=5s slow_start=30s;
                              max_fails=3;
   server 192.0.2.1
   server backend3.example.com
   server backend4.example.com service=http resolve;
   server backup1.example.com:8080 backup;
   server backup2.example.com:8080 backup;
server {
   location / {
       proxy_pass http://dynamic;
       health_check;
```

2.51.3 Directives

upstream

```
SYNTAX: upstream name { ...}

DEFAULT —

CONTEXT: http
```

Defines a group of servers. Servers can listen on different ports. In addition, servers listening on TCP and UNIX-domain sockets can be mixed.

Example:

By default, requests are distributed between the servers using a weighted round-robin balancing method. In the above example, each 7 requests will be distributed as follows: 5 requests go to backendl.example.com and one request to each of the second and third servers. If an error occurs during communication with a server, the request will be passed to the next server, and so on until all of the functioning servers will be tried. If a successful response could not be obtained from any of the servers, the client will receive the result of the communication with the last server.

server

```
SYNTAX: server address [parameters];
DEFAULT —
CONTEXT: upstream
```

Nginx, Inc. p.324 of 506

Defines the *address* and other *parameters* of a server. The address can be specified as a domain name or IP address, with an optional port, or as a UNIX-domain socket path specified after the "unix:" prefix. If a port is not specified, the port 80 is used. A domain name that resolves to several IP addresses defines multiple servers at once.

The following parameters can be defined:

weight = number

sets the weight of the server, by default, 1.

 $max_conns = number$

limits the maximum *number* of simultaneous active connections to the proxied server (1.11.5). Default value is zero, meaning there is no limit. If the server group does not reside in the shared memory, the limitation works per each worker process.

If idle keepalive connections, multiple workers, and the shared memory are enabled, the total number of active and idle connections to the proxied server may exceed the max_conns value.

Since version 1.5.9 and prior to version 1.11.5, this parameter was available as part of our commercial subscription.

$max_fails = number$

sets the number of unsuccessful attempts to communicate with the server that should happen in the duration set by the fail_timeout parameter to consider the server unavailable for a duration also set by the fail_timeout parameter. By default, the number of unsuccessful attempts is set to 1. The zero value disables the accounting of attempts. What is considered an unsuccessful attempt is defined by the proxy_next_upstream, fastcgi_next_upstream, uwsgi_next_upstream, scgi_next_upstream, memcached_next_upstream, and grpc_next_upstream directives.

 $fail_timeout = time$ sets

- the time during which the specified number of unsuccessful attempts to communicate with the server should happen to consider the server unavailable;
- and the period of time the server will be considered unavailable.

By default, the parameter is set to 10 seconds.

backup

marks the server as a backup server. It will be passed requests when the primary servers are unavailable.

Nginx, Inc. p.325 of 506

The parameter cannot be used along with the hash, ip_hash, and random load balancing methods.

down

marks the server as permanently unavailable.

Additionally, the following parameters are available as part of our commercial subscription:

resolve

monitors changes of the IP addresses that correspond to a domain name of the server, and automatically modifies the upstream configuration without the need of restarting nginx (1.5.12). The server group must reside in the shared memory.

In order for this parameter to work, the resolver directive must be specified in the http block or in the corresponding upstream block.

route=string

sets the server route name.

service=name

enables resolving of DNS SRV records and sets the service name (1.9.13). In order for this parameter to work, it is necessary to specify the resolve parameter for the server and specify a hostname without a port number. If the service name does not contain a dot ("."), then the RFC-compliant name is constructed and the TCP protocol is added to the service prefix. For example, to look up the _http._tcp.backend.example.com SRV record, it is necessary to specify the directive:

```
server backend.example.com service=http resolve;
```

If the service name contains one or more dots, then the name is constructed by joining the service prefix and the server name. For example, to look up the _http._tcp.backend.example.com and server1.backend.example.com SRV records, it is necessary to specify the directives:

```
server backend.example.com service=_http._tcp resolve;
server example.com service=server1.backend resolve;
```

Highest-priority SRV records (records with the same lowest-number priority value) are resolved as primary servers, the rest of SRV records are resolved as backup servers. If the backup parameter is specified for the server, high-priority SRV records are resolved as backup servers, the rest of SRV records are ignored.

```
slow start = time
```

sets the *time* during which the server will recover its weight from zero to a nominal value, when unhealthy server becomes healthy, or when the server becomes available after a period of time it was considered unavailable. Default value is zero, i.e. slow start is disabled.

Nginx, Inc. p.326 of 506

The parameter cannot be used along with the hash, ip_hash, and random load balancing methods.

drain

puts the server into the "draining" mode (1.13.6). In this mode, only requests bound to the server will be proxied to it.

Prior to version 1.13.6, the parameter could be changed only with the API module.

If there is only a single server in a group, max_fails, fail_timeout and slow_start parameters are ignored, and such a server will never be considered unavailable.

zone

```
SYNTAX: zone name [size];
```

Default —

Context: upstream

This directive appeared in version 1.9.0.

Defines the *name* and *size* of the shared memory zone that keeps the group's configuration and run-time state that are shared between worker processes. Several groups may share the same zone. In this case, it is enough to specify the *size* only once.

Additionally, as part of our commercial subscription, such groups allow changing the group membership or modifying the settings of a particular server without the need of restarting nginx. The configuration is accessible via the API module (1.13.3).

Prior to version 1.13.3, the configuration was accessible only via a special location handled by upstream_conf.

state

```
SYNTAX: state file;
```

Default —

Context: upstream

This directive appeared in version 1.9.7.

Specifies a *file* that keeps the state of the dynamically configurable group. Examples:

```
state /var/lib/nginx/state/servers.conf; # path for Linux
state /var/db/nginx/state/servers.conf; # path for FreeBSD
```

The state is currently limited to the list of servers with their parameters. The file is read when parsing the configuration and is updated each time the

Nginx, Inc. p.327 of 506

upstream configuration is changed. Changing the file content directly should be avoided. The directive cannot be used along with the server directive.

Changes made during configuration reload or binary upgrade can be lost.

This directive is available as part of our commercial subscription.

hash

SYNTAX: **hash** *key* [consistent];

Default —

Context: upstream

This directive appeared in version 1.7.2.

Specifies a load balancing method for a server group where the client-server mapping is based on the hashed *key* value. The *key* can contain text, variables, and their combinations. Note that adding or removing a server from the group may result in remapping most of the keys to different servers. The method is compatible with the Cache::Memcached Perl library.

If the consistent parameter is specified, the ketama consistent hashing method will be used instead. The method ensures that only a few keys will be remapped to different servers when a server is added to or removed from the group. This helps to achieve a higher cache hit ratio for caching servers. The method is compatible with the Cache::Memcached::Fast Perl library with the ketama_points parameter set to 160.

ip_hash

SYNTAX: ip_hash;

Default —

Context: upstream

Specifies that a group should use a load balancing method where requests are distributed between servers based on client IP addresses. The first three octets of the client IPv4 address, or the entire IPv6 address, are used as a hashing key. The method ensures that requests from the same client will always be passed to the same server except when this server is unavailable. In the latter case client requests will be passed to another server. Most probably, it will always be the same server as well.

IPv6 addresses are supported starting from versions 1.3.2 and 1.2.2.

If one of the servers needs to be temporarily removed, it should be marked with the down parameter in order to preserve the current hashing of client IP addresses.

Example:

Nginx, Inc. p.328 of 506

```
upstream backend {
   ip_hash;

   server backend1.example.com;
   server backend2.example.com;
   server backend3.example.com down;
   server backend4.example.com;
}
```

Until versions 1.3.1 and 1.2.2, it was not possible to specify a weight for servers using the ip_hash load balancing method.

keepalive

```
SYNTAX: keepalive connections;

DEFAULT —

CONTEXT: upstream

This directive appeared in version 1.1.4.
```

Activates the cache for connections to upstream servers.

The *connections* parameter sets the maximum number of idle keepalive connections to upstream servers that are preserved in the cache of each worker process. When this number is exceeded, the least recently used connections are closed.

It should be particularly noted that the keepalive directive does not limit the total number of connections to upstream servers that an nginx worker process can open. The *connections* parameter should be set to a number small enough to let upstream servers process new incoming connections as well.

When using load balancing methods other than the default round-robin method, it is necessary to activate them before the keepalive directive.

Example configuration of memcached upstream with keepalive connections:

```
upstream memcached_backend {
    server 127.0.0.1:11211;
    server 10.0.0.2:11211;

    keepalive 32;
}
server {
    ...
    location /memcached/ {
        set $memcached_key $uri;
        memcached_pass memcached_backend;
    }
}
```

Nginx, Inc. p.329 of 506

For HTTP, the proxy_http_version directive should be set to "1.1" and the Connection header field should be cleared:

```
upstream http_backend {
    server 127.0.0.1:8080;

    keepalive 16;
}
server {
    ...

    location /http/ {
        proxy_pass http://http_backend;
        proxy_http_version 1.1;
        proxy_set_header Connection "";
    ...
    }
}
```

Alternatively, HTTP/1.0 persistent connections can be used by passing the Connection: Keep-Alive header field to an upstream server, though this method is not recommended.

For FastCGI servers, it is required to set fastcgi_keep_conn for keepalive connections to work:

```
upstream fastcgi_backend {
    server 127.0.0.1:9000;

    keepalive 8;
}
server {
    ...
    location /fastcgi/ {
        fastcgi_pass fastcgi_backend;
        fastcgi_keep_conn on;
    ...
    }
}
```

SCGI and uwsgi protocols do not have a notion of keepalive connections.

keepalive_requests

```
SYNTAX: keepalive_requests number;
```

Default 1000 Context: upstream

This directive appeared in version 1.15.3.

Sets the maximum number of requests that can be served through one keepalive connection. After the maximum number of requests is made, the connection is closed.

Nginx, Inc. p.330 of 506

Closing connections periodically is necessary to free per-connection memory allocations. Therefore, using too high maximum number of requests could result in excessive memory usage and not recommended.

Prior to version 1.19.10, the default value was 100.

keepalive_time

SYNTAX: **keepalive_time** time;

Default 1h Context: upstream

This directive appeared in version 1.19.10.

Limits the maximum time during which requests can be processed through one keepalive connection. After this time is reached, the connection is closed following the subsequent request processing.

keepalive_timeout

SYNTAX: **keepalive_timeout** timeout;

Default 60s Context: upstream

This directive appeared in version 1.15.3.

Sets a timeout during which an idle keepalive connection to an upstream server will stay open.

ntlm

SYNTAX: **ntlm**;
DEFAULT —

Context: upstream

This directive appeared in version 1.9.2.

Allows proxying requests with NTLM Authentication. The upstream connection is bound to the client connection once the client sends a request with the Authorization header field value starting with "Negotiate" or "NTLM". Further client requests will be proxied through the same upstream connection, keeping the authentication context.

In order for NTLM authentication to work, it is necessary to enable keepalive connections to upstream servers. The proxy_http_version directive should be set to "1.1" and the Connection header field should be cleared:

```
upstream http_backend {
    server 127.0.0.1:8080;
    ntlm;
}
server {
    ...
```

Nginx, Inc. p.331 of 506

```
location /http/ {
    proxy_pass http://http_backend;
    proxy_http_version 1.1;
    proxy_set_header Connection "";
    ...
}
```

When using load balancer methods other than the default round-robin method, it is necessary to activate them before the ntlm directive.

This directive is available as part of our commercial subscription.

least_conn

```
SYNTAX: least_conn;

DEFAULT —

CONTEXT: upstream

This directive appeared in versions 1.3.1 and 1.2.2.
```

Specifies that a group should use a load balancing method where a request is passed to the server with the least number of active connections, taking into account weights of servers. If there are several such servers, they are tried in turn using a weighted round-robin balancing method.

$least_time$

```
SYNTAX: least_time header | last_byte [inflight];

DEFAULT —

CONTEXT: upstream

This directive appeared in version 1.7.10.
```

Specifies that a group should use a load balancing method where a request is passed to the server with the least average response time and least number of active connections, taking into account weights of servers. If there are several such servers, they are tried in turn using a weighted round-robin balancing method.

If the header parameter is specified, time to receive the response header is used. If the last_byte parameter is specified, time to receive the full response is used. If the inflight parameter is specified (1.11.6), incomplete requests are also taken into account.

Prior to version 1.11.6, incomplete requests were taken into account by default.

This directive is available as part of our commercial subscription.

Nginx, Inc. p.332 of 506

queue

```
SYNTAX: queue number [timeout=time];
DEFAULT —
CONTEXT: upstream
This directive appeared in version 1.5.12.
```

If an upstream server cannot be selected immediately while processing a request, the request will be placed into the queue. The directive specifies the maximum *number* of requests that can be in the queue at the same time. If the queue is filled up, or the server to pass the request to cannot be selected

within the time period specified in the timeout parameter, the 502 Bad Gateway error will be returned to the client.

The default value of the timeout parameter is 60 seconds.

When using load balancer methods other than the default round-robin method, it is necessary to activate them before the queue directive.

This directive is available as part of our commercial subscription.

random

```
SYNTAX: random [two [method]];

DEFAULT —

CONTEXT: upstream

This directive appeared in version 1.15.1.
```

Specifies that a group should use a load balancing method where a request is passed to a randomly selected server, taking into account weights of servers.

The optional two parameter instructs nginx to randomly select two servers and then choose a server using the specified method. The default method is least_conn which passes a request to a server with the least number of active connections.

The least_time method passes a request to a server with the least average response time and least number of active connections. If least_-time=header is specified, the time to receive the response header is used. If least_time=last_byte is specified, the time to receive the full response is used.

The least_time method is available as a part of our commercial subscription.

resolver

```
SYNTAX: resolver address ... [valid=time] [ipv6=on|off] [status_zone=zone];

DEFAULT —

CONTEXT: upstream
```

Nginx, Inc. p.333 of 506

This directive appeared in version 1.17.5.

Configures name servers used to resolve names of upstream servers into addresses, for example:

```
resolver 127.0.0.1 [::1]:5353;
```

The address can be specified as a domain name or IP address, with an optional port. If port is not specified, the port 53 is used. Name servers are queried in a round-robin fashion.

By default, nginx will look up both IPv4 and IPv6 addresses while resolving. If looking up of IPv6 addresses is not desired, the ipv6=off parameter can be specified.

By default, nginx caches answers using the TTL value of a response. An optional valid parameter allows overriding it:

```
resolver 127.0.0.1 [::1]:5353 valid=30s;
```

To prevent DNS spoofing, it is recommended configuring DNS servers in a properly secured trusted local network.

The optional status_zone parameter enables collection of DNS server statistics of requests and responses in the specified *zone*.

This directive is available as part of our commercial subscription.

resolver_timeout

```
SYNTAX: resolver_timeout time;
```

Default 30s Context: upstream

This directive appeared in version 1.17.5.

Sets a timeout for name resolution, for example:

```
resolver_timeout 5s;
```

This directive is available as part of our commercial subscription.

sticky

```
SYNTAX: sticky cookie name [expires=time] [domain=domain] [httponly]
```

[samesite=strict|lax|none] [secure] [path=path];

SYNTAX: sticky route \$variable ...;

SYNTAX: **sticky** learn create=\$variable lookup=\$variable zone=name:size

[timeout=time] [header] [sync];

Default —

Context: upstream

Nginx, Inc. p.334 of 506

This directive appeared in version 1.5.7.

Enables session affinity, which causes requests from the same client to be passed to the same server in a group of servers. Three methods are available:

cookie

When the cookie method is used, information about the designated server is passed in an HTTP cookie generated by nginx:

```
upstream backend {
   server backend1.example.com;
   server backend2.example.com;

   sticky cookie srv_id expires=1h domain=.example.com path=/;
}
```

A request that comes from a client not yet bound to a particular server is passed to the server selected by the configured balancing method. Further requests with this cookie will be passed to the designated server. If the designated server cannot process a request, the new server is selected as if the client has not been bound yet.

The first parameter sets the name of the cookie to be set or inspected. The cookie value is a hexadecimal representation of the MD5 hash of the IP address and port, or of the UNIX-domain socket path. However, if the "route" parameter of the server directive is specified, the cookie value will be the value of the "route" parameter:

```
upstream backend {
   server backend1.example.com route=a;
   server backend2.example.com route=b;

   sticky cookie srv_id expires=lh domain=.example.com path=/;
}
```

In this case, the value of the "srv_id" cookie will be either a or b. Additional parameters may be as follows:

```
expires=time
```

Sets the *time* for which a browser should keep the cookie. The special value max will cause the cookie to expire on "31 Dec 2037 23:55:55 GMT". If the parameter is not specified, it will cause the cookie to expire at the end of a browser session.

```
domain=domain
```

Defines the *domain* for which the cookie is set. Parameter value can contain variables (1.11.5).

```
httponly
```

Adds the HttpOnly attribute to the cookie (1.7.11).

```
samesite=strict | lax | none
```

Adds the SameSite attribute to the cookie with one of the following values (1.19.4): Strict, Lax, or None.

secure

Adds the Secure attribute to the cookie (1.7.11).

Nginx, Inc. p.335 of 506

path=path

Defines the *path* for which the cookie is set.

If any parameters are omitted, the corresponding cookie fields are not set.

route

When the route method is used, proxied server assigns client a route on receipt of the first request. All subsequent requests from this client will carry routing information in a cookie or URI. This information is compared with the "route" parameter of the server directive to identify the server to which the request should be proxied. If the "route" parameter is not specified, the route name will be a hexadecimal representation of the MD5 hash of the IP address and port, or of the UNIX-domain socket path. If the designated server cannot process a request, the new server is selected by the configured balancing method as if there is no routing information in the request.

The parameters of the route method specify variables that may contain routing information. The first non-empty variable is used to find the matching server.

Example:

```
map $cookie_jsessionid $route_cookie {
    ~.+\.(?P<route>\w+)$ $route;
}
map $request_uri $route_uri {
    ~jsessionid=.+\.(?P<route>\w+)$ $route;
}
upstream backend {
    server backend1.example.com route=a;
    server backend2.example.com route=b;

    sticky route $route_cookie $route_uri;
}
```

Here, the route is taken from the "JSESSIONID" cookie if present in a request. Otherwise, the route from the URI is used.

learn

When the learn method (1.7.1) is used, nginx analyzes upstream server responses and learns server-initiated sessions usually passed in an HTTP cookie.

```
upstream backend {
   server backend1.example.com:8080;
   server backend2.example.com:8081;

   sticky learn
        create=$upstream_cookie_examplecookie
        lookup=$cookie_examplecookie
        zone=client_sessions:1m;
}
```

In the example, the upstream server creates a session by setting the cookie "EXAMPLECOOKIE" in the response. Further requests with this

Nginx, Inc. p.336 of 506

cookie will be passed to the same server. If the server cannot process the request, the new server is selected as if the client has not been bound yet.

The parameters create and lookup specify variables that indicate how new sessions are created and existing sessions are searched, respectively. Both parameters may be specified more than once, in which case the first non-empty variable is used.

Sessions are stored in a shared memory zone, whose *name* and *size* are configured by the zone parameter. One megabyte zone can store about 4000 sessions on the 64-bit platform. The sessions that are not accessed during the time specified by the timeout parameter get removed from the zone. By default, timeout is set to 10 minutes.

The header parameter (1.13.1) allows creating a session right after receiving response headers from the upstream server.

The sync parameter (1.13.8) enables synchronization of the shared memory zone.

This directive is available as part of our commercial subscription.

sticky_cookie_insert

SYNTAX: **sticky_cookie_insert** name [expires=time] [domain=domain]

[path=path];

Default —

Context: upstream

This directive is obsolete since version 1.5.7. An equivalent sticky directive with a new syntax should be used instead:

```
\begin{array}{lll} \texttt{sticky cookie} & name & [\texttt{expires} = time] & [\texttt{domain} = domain] \\ [\texttt{path} = path]; \end{array}
```

2.51.4 Embedded Variables

The ngx_http_upstream_module module supports the following embedded variables:

$\$upstream_addr$

keeps the IP address and port, or the path to the UNIX-domain socket of the upstream server. If several servers were contacted during request processing, their addresses are separated by commas, e.g. "192.168.1.1:80, 192.168.1.2:80, unix:/tmp/sock". If an internal redirect from one server group to another happens, initiated by X-Accel-Redirect or error_page, then the server addresses from different groups are separated by colons, e.g. "192.168.1.1:80, 192.168.1.2:80, unix:/tmp/sock

Nginx, Inc. p.337 of 506

: 192.168.10.1:80, 192.168.10.2:80". If a server cannot be selected, the variable keeps the name of the server group.

$$upstream_bytes_received$

number of bytes received from an upstream server (1.11.4). Values from several connections are separated by commas and colons like addresses in the \$upstream_addr variable.

$\$upstream_bytes_sent$

number of bytes sent to an upstream server (1.15.8). Values from several connections are separated by commas and colons like addresses in the \$upstream_addr variable.

$$upstream_cache_status$

keeps the status of accessing a response cache (0.8.3). The status can be either "MISS", "BYPASS", "EXPIRED", "STALE", "UPDATING", "REVALIDATED", or "HIT".

$\$upstream_connect_time$

keeps time spent on establishing a connection with the upstream server (1.9.1); the time is kept in seconds with millisecond resolution. In case of SSL, includes time spent on handshake. Times of several connections are separated by commas and colons like addresses in the \$upstream_addr variable.

$\$upstream_cookie_name$

cookie with the specified *name* sent by the upstream server in the Set-Cookie response header field (1.7.1). Only the cookies from the response of the last server are saved.

\$upstream_header_time

keeps time spent on receiving the response header from the upstream server (1.7.10); the time is kept in seconds with millisecond resolution. Times of several responses are separated by commas and colons like addresses in the \$upstream_addr variable.

$$upstream_http_name$$

keep server response header fields. For example, the Server response header field is available through the *\$upstream_http_server* variable. The rules of converting header field names to variable names are the same as for the variables that start with the "\$http_" prefix. Only the header fields from the response of the last server are saved.

$\$upstream_queue_time$

keeps time the request spent in the upstream queue (1.13.9); the time is kept in seconds with millisecond resolution. Times of several responses are separated by commas and colons like addresses in the \$upstream_addr variable.

$$upstream_response_length$

keeps the length of the response obtained from the upstream server (0.7.27); the length is kept in bytes. Lengths of several responses are separated by commas and colons like addresses in the \$upstream_addr variable.

Nginx, Inc. p.338 of 506

$\$upstream_response_time$

keeps time spent on receiving the response from the upstream server; the time is kept in seconds with millisecond resolution. Times of several responses are separated by commas and colons like addresses in the \$upstream_addr variable.

$\$upstream_status$

keeps status code of the response obtained from the upstream server. Status codes of several responses are separated by commas and colons like addresses in the supstream_addr variable. If a server cannot be selected, the variable keeps the 502 Bad Gateway status code.

$$upstream_trailer_name$

keeps fields from the end of the response obtained from the upstream server (1.13.10).

Nginx, Inc. p.339 of 506

2.52 Module ngx_http_upstream_conf_module

2.52.1	Summary	340
2.52.2	Example Configuration	340
2.52.3	Directives	340
	upstream_conf	340

2.52.1 Summary

The ngx_http_upstream_conf_module module allows configuring upstream server groups on-the-fly via a simple HTTP interface without the need of restarting nginx. The http or stream server group must reside in the shared memory.

This module was available as part of our commercial subscription until 1.13.10. It was superseded by the ngx_http_api_module module in 1.13.3.

2.52.2 Example Configuration

```
upstream backend {
    zone upstream_backend 64k;
    ...
}
server {
    location /upstream_conf {
        upstream_conf;
        allow 127.0.0.1;
        deny all;
    }
}
```

2.52.3 Directives

upstream_conf

```
SYNTAX: upstream_conf;
DEFAULT —
CONTEXT: location
```

Turns on the HTTP interface of upstream configuration in the surrounding location. Access to this location should be limited.

Configuration commands can be used to:

- view the group configuration;
- view, modify, or remove a server;
- add a new server.

Nginx, Inc. p.340 of 506

Since addresses in a group are not required to be unique, specific servers in a group are referenced by their IDs. IDs are assigned automatically and shown when adding a new server or viewing the group configuration.

A configuration command consists of parameters passed as request arguments, for example:

```
http://127.0.0.1/upstream_conf?upstream=backend
```

The following parameters are supported:

stream=

Selects a stream upstream server group. Without this parameter, selects an http upstream server group.

upstream=name

Selects a group to work with. This parameter is mandatory.

id=number

Selects a server for viewing, modifying, or removing.

remove=

Removes a server from the group.

add=

Adds a new server to the group.

backup=

Required to add a backup server.

Before version 1.7.2, backup= was also required to view, modify, or remove existing backup servers.

```
server=address
```

Same as the "address" parameter of the http or stream upstream server. When adding a server, it is possible to specify it as a domain name. In this case, changes of the IP addresses that correspond to a domain name will be monitored and automatically applied to the upstream configuration without the need of restarting nginx (1.7.2). This requires the "resolver" directive in the http or stream block. See also the "resolve" parameter of the http or stream upstream server.

service=name

Same as the "service" parameter of the http://http.or.stream.upstream.server (1.9.13).

weight=number

Same as the "weight" parameter of the http or stream upstream server.

max conns=number

Same as the "max_conns" parameter of the http or stream upstream server.

 $max_fails=number$

Same as the "max_fails" parameter of the http or stream upstream server.

Nginx, Inc. p.341 of 506

fail_timeout=time

Same as the "fail_timeout" parameter of the http or stream upstream server

slow_start=time

Same as the "slow_start" parameter of the http or stream upstream server.

down=

Same as the "down" parameter of the http or stream upstream server.

drain=

Puts the http upstream server into the "draining" mode (1.7.5). In this mode, only requests bound to the server will be proxied to it.

up=

The opposite of the "down" parameter of the http or stream upstream server.

route=string

Same as the "route" parameter of the http upstream server.

The first three parameters select an object. This can be either the whole http or stream upstream server group, or a specific server. Without other parameters, the configuration of the selected group or server is shown.

For example, to view the configuration of the whole group, send:

```
http://127.0.0.1/upstream_conf?upstream=backend
```

To view the configuration of a specific server, also specify its ID:

```
http://127.0.0.1/upstream_conf?upstream=backend&id=42
```

To add a new server, specify its address in the "server=" parameter. Without other parameters specified, a server will be added with other parameters set to their default values (see the http or stream "server" directive).

For example, to add a new primary server, send:

```
http://127.0.0.1/upstream_conf?add=&upstream=backend&server=127.0.0.1:8080
```

To add a new backup server, send:

```
http://127.0.0.1/upstream_conf?add=&upstream=backend&backup=&server =127.0.0.1:8080
```

To add a new primary server, set its parameters to non-default values and mark it as "down", send:

```
http://127.0.0.1/upstream_conf?add=&upstream=backend&server=127.0.0.1:8080& weight=2&down=
```

To remove a server, specify its ID:

Nginx, Inc. p.342 of 506

http://127.0.0.1/upstream_conf?remove=&upstream=backend&id=42

To mark an existing server as "down", send:

http://127.0.0.1/upstream_conf?upstream=backend&id=42&down=

To modify the address of an existing server, send:

 $\verb|http://127.0.0.1/upstream_conf?upstream=backend&id=42&server=192.0.2.3:8123|$

To modify other parameters of an existing server, send:

http://127.0.0.1/upstream_conf?upstream=backend&id=42&max_fails=3&weight=4

The above examples are for an http upstream server group. Similar examples for a stream upstream server group require the "stream=" parameter.

Nginx, Inc. p.343 of 506

2.53 Module ngx_http_upstream_hc_module

2.53.1	Summary	344
2.53.2	Example Configuration	344
2.53.3	Directives	345
	health_check	345
	match	346

2.53.1 **Summary**

The ngx_http_upstream_hc_module module allows enabling periodic health checks of the servers in a group referenced in the surrounding location. The server group must reside in the shared memory.

If a health check fails, the server will be considered unhealthy. If several health checks are defined for the same group of servers, a single failure of any check will make the corresponding server be considered unhealthy. Client requests are not passed to unhealthy servers and servers in the "checking" state.

Please note that most of the variables will have empty values when used with health checks.

This module is available as part of our commercial subscription.

2.53.2 Example Configuration

With this configuration, nginx will send "/" requests to each server in the backend group every five seconds. If any communication error or timeout occurs, or a proxied server responds with the status code other than 2xx or 3xx, the health check will fail, and the server will be considered unhealthy.

Health checks can be configured to test the status code of a response, presence of certain header fields and their values, and the body contents. Tests are configured separately using the match directive and referenced in the match parameter of the health_check directive:

Nginx, Inc. p.344 of 506

```
http {
    server {
        ...
            location / {
                 proxy_pass http://backend;
                 health_check match=welcome;
            }
     }

    match welcome {
        status 200;
        header Content-Type = text/html;
        body ~ "Welcome to nginx!";
     }
}
```

This configuration shows that in order for a health check to pass, the response to a health check request should succeed, have status 200, and contain "Welcome to nginx!" in the body.

2.53.3 Directives

health_check

SYNTAX: health_check [parameters];

Default — Context: location

Enables periodic health checks of the servers in a group referenced in the surrounding location.

The following optional parameters are supported:

```
interval=time
```

sets the interval between two consecutive health checks, by default, 5 seconds.

```
jitter=time
```

sets the time within which each health check will be randomly delayed, by default, there is no delay.

```
fails=number
```

sets the number of consecutive failed health checks of a particular server after which this server will be considered unhealthy, by default, 1.

```
passes = number
```

sets the number of consecutive passed health checks of a particular server after which the server will be considered healthy, by default, 1.

```
uri=uri
```

defines the URI used in health check requests, by default, "/".

```
mandatory [persistent]
```

sets the initial "checking" state for a server until the first health check is completed (1.11.7). Client requests are not passed to servers in the "checking" state. If the parameter is not specified, the server will be initially considered healthy.

Nginx, Inc. p.345 of 506

The persistent parameter (1.19.7) sets the initial "up" state for a server after reload if the server was considered healthy before reload.

```
match=name
```

specifies the match block configuring the tests that a response should pass in order for a health check to pass. By default, the response should have status code 2xx or 3xx.

```
port=number
```

defines the port used when connecting to a server to perform a health check (1.9.7). By default, equals the server port.

```
type=grpc [grpc_service=name] [grpc_status=code] enables periodic health checks of a gRPC server or a particular gRPC service specified with the optional grpc_service parameter (1.19.5). If the server does not support the gRPC Health Checking Protocol, the optional grpc_status parameter can be used to specify non-zero gRPC status (for example, status code "12" / "UNIMPLEMENTED") that will be treated as healthy:
```

```
health_check mandatory type=grpc grpc_status=12;
```

The type=grpc parameter must be specified after all other directive parameters, grpc_service and grpc_status must follow type=grpc. The parameter is not compatible with uri or match parameters.

match

```
SYNTAX: match name { ... }

DEFAULT —

CONTEXT: http
```

Defines the named test set used to verify responses to health check requests. The following items can be tested in a response:

```
status 200;
status is 200
status ! 500;
status is not 500
status 200 204;
status is 200 or 204
status ! 301 302;
status is neither 301 nor 302
status 200-399;
status is in the range from 200 to 399
status ! 400-599;
status is not in the range from 400 to 599
status 301-303 307;
status is either 301, 302, 303, or 307
```

Nginx, Inc. p.346 of 506

```
header Content-Type = text/html;
   header contains Content-Type with value text/html
header Content-Type != text/html;
   header contains Content-Type with value other than text/html
header Connection ~ close;
   header contains Connection with value matching regular expression
   close
header Connection !~ close;
   header contains Connection with value not matching regular
   expression close
header Host;
   header contains Host
header ! X-Accel-Redirect;
   header lacks X-Accel-Redirect
body ~ "Welcome to nginx!";
   body matches regular expression "Welcome to nginx!"
body !~ "Welcome to nginx!";
   body does not match regular expression "Welcome to nginx!"
require $variable ...;
   all specified variables are not empty and not equal to "0" (1.15.9).
```

If several tests are specified, the response matches only if it matches all tests.

Only the first 256k of the response body are examined.

Examples:

```
# status is 200, content type is "text/html",
# and body contains "Welcome to nginx!"
match welcome {
    status 200;
    header Content-Type = text/html;
    body ~ "Welcome to nginx!";
}
```

```
# status is not one of 301, 302, 303, or 307, and header does not have "Refresh
:"
match not_redirect {
    status ! 301-303 307;
    header ! Refresh;
}
```

```
# status ok and not in maintenance mode
match server_ok {
    status 200-399;
    body !~ "maintenance mode";
}
```

Nginx, Inc. p.347 of 506

```
# status is 200 or 204
map $upstream_status $good_status {
    200 1;
    204 1;
}
match server_ok {
    require $good_status;
}
```

Nginx, Inc. p.348 of 506

2.54 Module ngx_http_userid_module

2.54.1	Summary
2.54.2	Example Configuration
2.54.3	Directives
	userid
	userid_domain
	userid_expires
	userid_flags
	userid_mark
	userid_name
	userid_p3p
	userid_path
	userid_service
2.54.4	Embedded Variables

2.54.1 Summary

The ngx_http_userid_module module sets cookies suitable for client identification. Received and set cookies can be logged using the embedded variables \$uid_got and \$uid_set. This module is compatible with the mod_uid module for Apache.

2.54.2 Example Configuration

```
userid on;
userid_name uid;
userid_domain example.com;
userid_path /;
userid_expires 365d;
userid_p3p 'policyref="/w3c/p3p.xml", CP="CUR ADM OUR NOR STA NID"';
```

2.54.3 Directives

userid

v1

SYNTAX: userid on | v1 | log | off;

Default off

Context: http, server, location

Enables or disables setting cookies and logging the received cookies:

on enables the setting of version 2 cookies and logging of the received cookies;

enables the setting of version 1 cookies and logging of the received cookies;

Nginx, Inc. p.349 of 506

log

disables the setting of cookies, but enables logging of the received cookies; of f

disables the setting of cookies and logging of the received cookies.

userid_domain

SYNTAX: userid_domain name | none;

Default none

Context: http, server, location

Defines a domain for which the cookie is set. The none parameter disables setting of a domain for the cookie.

userid_expires

SYNTAX: **userid_expires** *time* | max | off;

Default off

Context: http, server, location

Sets a time during which a browser should keep the cookie. The parameter max will cause the cookie to expire on "31 Dec 2037 23:55:55 GMT". The parameter off will cause the cookie to expire at the end of a browser session.

userid_flags

SYNTAX: userid flags off | flag ...;

Default off

Context: http, server, location
This directive appeared in version 1.19.3.

If the parameter is not off, defines one or more additional flags for the cookie: secure, httponly, samesite=strict, samesite=lax, samesite=none.

userid_mark

SYNTAX: userid_mark letter | digit | = | off;

Default off

Context: http, server, location

If the parameter is not off, enables the cookie marking mechanism and sets the character used as a mark. This mechanism is used to add or change userid_p3p and/or a cookie expiration time while preserving the client identifier. A mark can be any letter of the English alphabet (case-sensitive), digit, or the "=" character.

If the mark is set, it is compared with the first padding symbol in the base64 representation of the client identifier passed in a cookie. If they do not

Nginx, Inc. p.350 of 506

match, the cookie is resent with the specified mark, expiration time, and P3P header.

userid_name

SYNTAX: userid_name name;

Default uid

Context: http, server, location

Sets the cookie name.

userid_p3p

SYNTAX: **userid_p3p** *string* | none;

Default none

Context: http, server, location

Sets a value for the P3P header field that will be sent along with the cookie. If the directive is set to the special value none, the P3P header will not be sent in a response.

userid_path

SYNTAX: userid_path path;

Default /

Context: http, server, location

Defines a path for which the cookie is set.

userid_service

SYNTAX: userid_service number;

DEFAULT IP address of the server

Context: http, server, location

If identifiers are issued by multiple servers (services), each service should be assigned its own *number* to ensure that client identifiers are unique. For version 1 cookies, the default value is zero. For version 2 cookies, the default value is the number composed from the last four octets of the server's IP address.

2.54.4 Embedded Variables

The ngx_http_userid_module module supports the following embedded variables:

\$uid_qot

The cookie name and received client identifier.

 $\$uid_reset$

If the variable is set to a non-empty string that is not "0", the client identifiers are reset. The special value "log" additionally leads to the output of messages about the reset identifiers to the error_log.

Nginx, Inc. p.351 of 506

$\$uid_set$

The cookie name and sent client identifier.

Nginx, Inc. p.352 of 506

${\bf 2.55}\quad {\bf Module~ngx_http_uwsgi_module}$

2.55.1	Summary
2.55.2	Example Configuration
2.55.3	Directives
	uwsgi_bind
	uwsgi_buffer_size
	uwsgi_buffering
	uwsgi_buffers
	uwsgi_busy_buffers_size
	uwsgi_cache
	uwsgi_cache_background_update
	uwsgi_cache_bypass
	uwsgi_cache_key
	uwsgi_cache_lock
	uwsgi_cache_lock_age
	uwsgi_cache_lock_timeout
	uwsgi_cache_max_range_offset
	uwsgi_cache_methods
	uwsgi_cache_min_uses
	uwsgi_cache_path
	uwsgi_cache_purge
	uwsgi_cache_revalidate
	uwsgi_cache_use_stale
	uwsgi_cache_valid
	uwsgi_connect_timeout
	uwsgi_force_ranges
	uwsgi_hide_header
	uwsgi_ignore_client_abort
	uwsgi_ignore_headers
	uwsgi_intercept_errors
	uwsgi_limit_rate
	uwsgi_max_temp_file_size
	uwsgi_modifier1
	uwsgi_modifier2
	uwsgi_next_upstream
	uwsgi_next_upstream_timeout
	uwsgi_next_upstream_tries
	uwsgi_no_cache
	uwsgi_param
	uwsgi_pass
	uwsgi_pass_header
	uwsgi_pass_request_body
	uwsgi_pass_request_headers
	uwsgi_read_timeout
	uwsgi_request_buffering

Nginx, Inc. p.353 of 506

uwsgi_send_timeout
uwsgi_socket_keepalive
uwsgi_ssl_certificate
uwsgi_ssl_certificate_key
uwsgi_ssl_ciphers
uwsgi_ssl_conf_command
uwsgi_ssl_crl
uwsgi_ssl_name
uwsgi_ssl_password_file
uwsgi_ssl_protocols
uwsgi_ssl_server_name
uwsgi_ssl_session_reuse
uwsgi_ssl_trusted_certificate
uwsgi_ssl_verify
uwsgi_ssl_verify_depth
uwsgi_store
uwsgi_store_access
uwsgi_temp_file_write_size
uwsgi_temp_path

2.55.1 **Summary**

The ngx_http_uwsgi_module module allows passing requests to a uwsgi server.

2.55.2 Example Configuration

```
location / {
   include   uwsgi_params;
   uwsgi_pass localhost:9000;
}
```

2.55.3 Directives

uwsgi_bind

```
SYNTAX: uwsgi_bind address [transparent] | off;
DEFAULT —
CONTEXT: http, server, location
```

Makes outgoing connections to a uwsgi server originate from the specified local IP address with an optional port (1.11.2). Parameter value can contain variables (1.3.12). The special value off (1.3.12) cancels the effect of the uwsgi_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address and port.

Nginx, Inc. p.354 of 506

The transparent parameter (1.11.0) allows outgoing connections to a uwsgi server originate from a non-local IP address, for example, from a real IP address of a client:

```
uwsgi_bind $remote_addr transparent;
```

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required (1.13.8) as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the uwsgi server.

uwsgi_buffer_size

SYNTAX: uwsgi_buffer_size size;

 $Default - 4k \mid 8k$

Context: http, server, location

Sets the *size* of the buffer used for reading the first part of the response received from the uwsgi server. This part usually contains a small response header. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform. It can be made smaller, however.

uwsgi_buffering

SYNTAX: uwsgi_buffering on | off;

Default on

Context: http, server, location

Enables or disables buffering of responses from the uwsgi server.

When buffering is enabled, nginx receives a response from the uwsgi server as soon as possible, saving it into the buffers set by the uwsgi_buffer_size and uwsgi_buffers directives. If the whole response does not fit into memory, a part of it can be saved to a temporary file on the disk. Writing to temporary files is controlled by the uwsgi_max_temp_file_size and uwsgi_temp_file_write_size directives.

When buffering is disabled, the response is passed to a client synchronously, immediately as it is received. nginx will not try to read the whole response from the uwsgi server. The maximum size of the data that nginx can receive from the server at a time is set by the uwsgi_buffer_size directive.

Buffering can also be enabled or disabled by passing "yes" or "no" in the X-Accel-Buffering response header field. This capability can be disabled using the uwsgi_ignore_headers directive.

Nginx, Inc. p.355 of 506

uwsgi_buffers

SYNTAX: uwsgi_buffers number size;

DEFAULT 8 4k | 8k

Context: http, server, location

Sets the *number* and *size* of the buffers used for reading a response from the uwsgi server, for a single connection. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

uwsgi_busy_buffers_size

SYNTAX: uwsgi_busy_buffers_size size;

Default 8k|16k

Context: http, server, location

When buffering of responses from the uwsgi server is enabled, limits the total *size* of buffers that can be busy sending a response to the client while the response is not yet fully read. In the meantime, the rest of the buffers can be used for reading the response and, if needed, buffering part of the response to a temporary file. By default, *size* is limited by the size of two buffers set by the uwsgi_buffer_size and uwsgi_buffers directives.

uwsgi_cache

SYNTAX: uwsgi_cache zone | off;

Default off

Context: http, server, location

Defines a shared memory zone used for caching. The same zone can be used in several places. Parameter value can contain variables (1.7.9). The off parameter disables caching inherited from the previous configuration level.

uwsgi_cache_background_update

SYNTAX: uwsgi_cache_background_update on | off;

Default off

Context: http, server, location

This directive appeared in version 1.11.10.

Allows starting a background subrequest to update an expired cache item, while a stale cached response is returned to the client. Note that it is necessary to allow the usage of a stale cached response when it is being updated.

uwsgi_cache_bypass

SYNTAX: uwsgi_cache_bypass string ...;

Default —

CONTEXT: http, server, location

Nginx, Inc. p.356 of 506

Defines conditions under which the response will not be taken from a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be taken from the cache:

```
uwsgi_cache_bypass $cookie_nocache $arg_nocache$arg_comment;
uwsgi_cache_bypass $http_pragma $http_authorization;
```

Can be used along with the uwsgi_no_cache directive.

uwsgi_cache_key

SYNTAX: uwsgi_cache_key string;

Default —

Context: http, server, location

Defines a key for caching, for example

```
uwsgi_cache_key localhost:9000$request_uri;
```

uwsgi_cache_lock

SYNTAX: uwsgi_cache_lock on | off;

Default off

Context: http, server, location

This directive appeared in version 1.1.12.

When enabled, only one request at a time will be allowed to populate a new cache element identified according to the uwsgi_cache_key directive by passing a request to a uwsgi server. Other requests of the same cache element will either wait for a response to appear in the cache or the cache lock for this element to be released, up to the time set by the uwsgi_cache_lock_timeout directive.

uwsgi_cache_lock_age

SYNTAX: uwsgi_cache_lock_age time;

Default 5s

Context: http, server, location
This directive appeared in version 1.7.8.

If the last request passed to the uwsgi server for populating a new cache element has not completed for the specified *time*, one more request may be passed to the uwsgi server.

uwsgi_cache_lock_timeout

SYNTAX: uwsgi_cache_lock_timeout time;

DEFAULT 5s

Context: http, server, location
This directive appeared in version 1.1.12.

Nginx, Inc. p.357 of 506

Sets a timeout for <u>uwsgi_cache_lock</u>. When the *time* expires, the request will be passed to the uwsgi server, however, the response will not be cached.

Before 1.7.8, the response could be cached.

uwsgi_cache_max_range_offset

```
SYNTAX: uwsgi_cache_max_range_offset number;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.11.6.
```

Sets an offset in bytes for byte-range requests. If the range is beyond the offset, the range request will be passed to the uwsgi server and the response will not be cached.

uwsgi_cache_methods

```
SYNTAX: uwsgi_cache_methods GET | HEAD | POST ...;
DEFAULT GET HEAD
CONTEXT: http, server, location
```

If the client request method is listed in this directive then the response will be cached. "GET" and "HEAD" methods are always added to the list, though it is recommended to specify them explicitly. See also the uwsgi_no_cachedirective.

uwsgi_cache_min_uses

```
SYNTAX: uwsgi_cache_min_uses number;
DEFAULT 1
CONTEXT: http, server, location
```

Sets the *number* of requests after which the response will be cached.

uwsgi_cache_path

```
SYNTAX: uwsgi_cache_path path [levels=levels]

[use_temp_path=on|off] keys_zone=name:size [inactive=time]

[max_size=size] [min_free=size] [manager_files=number]

[manager_sleep=time] [manager_threshold=time]

[loader_files=number] [loader_sleep=time]

[loader_threshold=time] [purger=on|off]

[purger_files=number] [purger_sleep=time]

[purger_threshold=time];

DEFAULT —

CONTEXT: http
```

Sets the path and other parameters of a cache. Cache data are stored in files. The file name in a cache is a result of applying the MD5 function to

Nginx, Inc. p.358 of 506

the cache key. The levels parameter defines hierarchy levels of a cache: from 1 to 3, each level accepts values 1 or 2. For example, in the following configuration

uwsgi_cache_path /data/nginx/cache levels=1:2 keys_zone=one:10m;

file names in a cache will look like this:

/data/nginx/cache/c/29/b7f54b2df7773722d382f4809d65029c

A cached response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the cache can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both cache and a directory holding temporary files are put on the same file system. A directory for temporary files is set based on the use_temp_path parameter (1.7.10). If this parameter is omitted or set to the value on, the directory set by the uwsgi_temp_path directive for the given location will be used. If the value is set to off, temporary files will be put directly in the cache directory.

In addition, all active keys and information about data are stored in a shared memory zone, whose *name* and *size* are configured by the keys_zone parameter. One megabyte zone can store about 8 thousand keys.

As part of commercial subscription, the shared memory zone also stores extended cache information, thus, it is required to specify a larger zone size for the same number of keys. For example, one megabyte zone can store about 4 thousand keys.

Cached data that are not accessed during the time specified by the inactive parameter get removed from the cache regardless of their freshness. By default, inactive is set to 10 minutes.

The special "cache manager" process monitors the maximum cache size set by the max_size parameter, and the minimum amount of free space set by the min_free (1.19.1) parameter on the file system with cache. When the size is exceeded or there is not enough free space, it removes the least recently used data. The data is removed in iterations configured by manager_files, manager_threshold, and manager_sleep parameters (1.11.5). During one iteration no more than manager_files items are deleted (by default, 100). The duration of one iteration is limited by the manager_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the manager_sleep parameter (by default, 50 milliseconds) is made.

A minute after the start the special "cache loader" process is activated. It loads information about previously cached data stored on file system into a cache zone. The loading is also done in iterations. During one iteration no more than loader_files items are loaded (by default, 100). Besides, the

Nginx, Inc. p.359 of 506

duration of one iteration is limited by the loader_threshold parameter (by default, 200 milliseconds). Between iterations, a pause configured by the loader_sleep parameter (by default, 50 milliseconds) is made.

Additionally, the following parameters are available as part of our commercial subscription:

```
purger=on|off
```

Instructs whether cache entries that match a wildcard key will be removed from the disk by the cache purger (1.7.12). Setting the parameter to on (default is off) will activate the "cache purger" process that permanently iterates through all cache entries and deletes the entries that match the wildcard key.

```
purger files=number
```

Sets the number of items that will be scanned during one iteration (1.7.12). By default, purger_files is set to 10.

```
purger threshold=number
```

Sets the duration of one iteration (1.7.12). By default, purger_-threshold is set to 50 milliseconds.

```
purger_sleep=number
```

Sets a pause between iterations (1.7.12). By default, purger_sleep is set to 50 milliseconds.

In versions 1.7.3, 1.7.7, and 1.11.10 cache header format has been changed. Previously cached responses will be considered invalid after upgrading to a newer nginx version.

uwsgi_cache_purge

```
SYNTAX: uwsgi_cache_purgestring ...;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.5.7.
```

Defines conditions under which the request will be considered a cache purge request. If at least one value of the string parameters is not empty and is not equal to "0" then the cache entry with a corresponding cache key is removed. The result of successful operation is indicated by returning the 204 No Content response.

If the cache key of a purge request ends with an asterisk (" \star "), all cache entries matching the wildcard key will be removed from the cache. However, these entries will remain on the disk until they are deleted for either inactivity, or processed by the cache purger (1.7.12), or a client attempts to access them.

Example configuration:

```
uwsgi_cache_path /data/nginx/cache keys_zone=cache_zone:10m;
map $request_method $purge_method {
   PURGE 1;
```

Nginx, Inc. p.360 of 506

This functionality is available as part of our commercial subscription.

uwsgi_cache_revalidate

```
SYNTAX: uwsgi_cache_revalidate on | off;
Default off
Context: http, server, location
This directive appeared in version 1.5.7.
```

Enables revalidation of expired cache items using conditional requests with the If-Modified-Since and If-None-Match header fields.

uwsgi_cache_use_stale

```
SYNTAX: uwsgi_cache_use_stale error | timeout | invalid_header | updating | http_500 | http_503 | http_403 | http_404 | http_429 | off ...;

DEFAULT off
CONTEXT: http, server, location
```

Determines in which cases a stale cached response can be used when an error occurs during communication with the uwsgi server. The directive's parameters match the parameters of the uwsgi_next_upstream directive.

The error parameter also permits using a stale cached response if a uwsgi server to process a request cannot be selected.

Additionally, the updating parameter permits using a stale cached response if it is currently being updated. This allows minimizing the number of accesses to uwsgi servers when updating cached data.

Using a stale cached response can also be enabled directly in the response header for a specified number of seconds after the response became stale (1.11.10). This has lower priority than using the directive parameters.

- The "stale-while-revalidate" extension of the Cache-Control header field permits using a stale cached response if it is currently being updated.
- The "stale-if-error" extension of the Cache-Control header field permits using a stale cached response in case of an error.

To minimize the number of accesses to uwsgi servers when populating a new cache element, the uwsgi_cache_lock directive can be used.

Nginx, Inc. p.361 of 506

uwsgi_cache_valid

```
SYNTAX: uwsgi_cache_valid [code ...] time;
```

Context: http, server, location

Sets caching time for different response codes. For example, the following directives

```
uwsgi_cache_valid 200 302 10m;
uwsgi_cache_valid 404 1m;
```

set 10 minutes of caching for responses with codes 200 and 302 and 1 minute for responses with code 404.

If only caching *time* is specified

```
uwsgi_cache_valid 5m;
```

then only 200, 301, and 302 responses are cached.

In addition, the any parameter can be specified to cache any responses:

```
uwsgi_cache_valid 200 302 10m;
uwsgi_cache_valid 301 1h;
uwsgi_cache_valid any 1m;
```

Parameters of caching can also be set directly in the response header. This has higher priority than setting of caching time using the directive.

- The X-Accel-Expires header field sets caching time of a response in seconds. The zero value disables caching for a response. If the value starts with the @ prefix, it sets an absolute time in seconds since Epoch, up to which the response may be cached.
- If the header does not include the X-Accel-Expires field, parameters of caching may be set in the header fields Expires or Cache-Control.
- If the header includes the Set-Cookie field, such a response will not be cached.
- If the header includes the Vary field with the special value "*", such a response will not be cached (1.7.7). If the header includes the Vary field with another value, such a response will be cached taking into account the corresponding request header fields (1.7.7).

Processing of one or more of these response header fields can be disabled using the <u>uwsgi_ignore_headers</u> directive.

$uwsgi_connect_timeout$

SYNTAX: uwsgi_connect_timeout time;

DEFAULT 60s

Context: http, server, location

Nginx, Inc. p.362 of 506

Defines a timeout for establishing a connection with a uwsgi server. It should be noted that this timeout cannot usually exceed 75 seconds.

uwsgi_force_ranges

```
SYNTAX: uwsgi_force_ranges on | off;

DEFAULT off

CONTEXT: http, server, location

This directive appeared in version 1.7.7.
```

Enables byte-range support for both cached and uncached responses from the uwsgi server regardless of the Accept-Ranges field in these responses.

uwsgi_hide_header

```
SYNTAX: uwsgi_hide_header field;
DEFAULT —
CONTEXT: http, server, location
```

By default, nginx does not pass the header fields Status and X-Accel-... from the response of a uwsgi server to a client. The uwsgi_-hide_header directive sets additional fields that will not be passed. If, on the contrary, the passing of fields needs to be permitted, the uwsgi_pass_header directive can be used.

uwsgi_ignore_client_abort

```
SYNTAX: uwsgi_ignore_client_abort on | off;
Default off
Context: http, server, location
```

Determines whether the connection with a uwsgi server should be closed when a client closes the connection without waiting for a response.

uwsgi_ignore_headers

```
SYNTAX: uwsgi_ignore_headers field ...;

DEFAULT —

CONTEXT: http, server, location
```

header fields from Disables processing of certain response the uwsgi The following fields can be ignored: X-Accel-Redirect, X-Accel-Expires, X-Accel-Limit-Rate X-Accel-Buffering (1.1.6), X-Accel-Charset (1.1.6), Expires, Cache-Control, Set-Cookie (0.8.44), and Vary (1.7.7).

If not disabled, processing of these header fields has the following effect:

- X-Accel-Expires, Expires, Cache-Control, Set-Cookie, and Vary set the parameters of response caching;
- X-Accel-Redirect performs an internal redirect to the specified URI;

Nginx, Inc. p.363 of 506

- X-Accel-Limit-Rate sets the rate limit for transmission of a response to a client;
- X-Accel-Buffering enables or disables buffering of a response;
- X-Accel-Charset sets the desired charset of a response.

uwsgi_intercept_errors

SYNTAX: uwsgi_intercept_errors on | off;

Default off

Context: http, server, location

Determines whether a uwsgi server responses with codes greater than or equal to 300 should be passed to a client or be intercepted and redirected to nginx for processing with the error_page directive.

uwsgi_limit_rate

SYNTAX: uwsgi_limit_rate rate;

Default 0

Context: http, server, location
This directive appeared in version 1.7.7.

Limits the speed of reading the response from the uwsgi server. The *rate* is specified in bytes per second. The zero value disables rate limiting. The limit is set per a request, and so if nginx simultaneously opens two connections to the uwsgi server, the overall rate will be twice as much as the specified limit. The limitation works only if buffering of responses from the uwsgi server is enabled.

uwsgi_max_temp_file_size

SYNTAX: uwsgi_max_temp_file_size size;

DEFAULT 1024m

Context: http, server, location

When buffering of responses from the uwsgi server is enabled, and the whole response does not fit into the buffers set by the uwsgi_buffer_size and uwsgi_buffers directives, a part of the response can be saved to a temporary file. This directive sets the maximum size of the temporary file. The size of data written to the temporary file at a time is set by the uwsgi_temp_file_write_size directive.

The zero value disables buffering of responses to temporary files.

This restriction does not apply to responses that will be cached or stored on disk.

Nginx, Inc. p.364 of 506

uwsgi_modifier1

SYNTAX: uwsgi_modifier1 number;

Default 0

Context: http, server, location

Sets the value of the modifier1 field in the uwsgi packet header.

uwsgi_modifier2

SYNTAX: uwsgi_modifier2 number;

Default 0

Context: http, server, location

Sets the value of the modifier 2 field in the uwsgi packet header.

uwsgi_next_upstream

```
SYNTAX: uwsgi_next_upstream error | timeout | invalid_header | http_500 | http_503 | http_403 | http_404 | http_429 | non_idempotent | off ...;
```

DEFAULT error timeout CONTEXT: http, server, location

Specifies in which cases a request should be passed to the next server:

error

an error occurred while establishing a connection with the server, passing a request to it, or reading the response header;

timeout

a timeout has occurred while establishing a connection with the server, passing a request to it, or reading the response header;

invalid_header

a server returned an empty or invalid response;

http_500

a server returned a response with the code 500;

http_503

a server returned a response with the code 503;

http_403

a server returned a response with the code 403;

http 404

a server returned a response with the code 404;

http_429

a server returned a response with the code 429 (1.11.13);

non idempotent

normally, requests with a non-idempotent method (POST, LOCK, PATCH) are not passed to the next server if a request has been sent to an upstream server (1.9.13); enabling this option explicitly allows retrying such requests;

Nginx, Inc. p.365 of 506

off

disables passing a request to the next server.

One should bear in mind that passing a request to the next server is only possible if nothing has been sent to a client yet. That is, if an error or timeout occurs in the middle of the transferring of a response, fixing this is impossible.

The directive also defines what is considered an unsuccessful attempt of communication with a server. The cases of error, timeout and invalid_header are always considered unsuccessful attempts, even if they are not specified in the directive. The cases of http_500, http_503, and http_429 are considered unsuccessful attempts only if they are specified in the directive. The cases of http_403 and http_404 are never considered unsuccessful attempts.

Passing a request to the next server can be limited by the number of tries and by time.

uwsgi_next_upstream_timeout

SYNTAX: uwsgi_next_upstream_timeout time;

Default 0

Context: http, server, location
This directive appeared in version 1.7.5.

Limits the time during which a request can be passed to the next server. The 0 value turns off this limitation.

uwsgi_next_upstream_tries

SYNTAX: uwsgi_next_upstream_tries number;

Default 0

Context: http, server, location
This directive appeared in version 1.7.5.

Limits the number of possible tries for passing a request to the next server. The 0 value turns off this limitation.

uwsgi_no_cache

```
SYNTAX: uwsgi_no_cache string ...;
```

Default —

Context: http, server, location

Defines conditions under which the response will not be saved to a cache. If at least one value of the string parameters is not empty and is not equal to "0" then the response will not be saved:

Can be used along with the <u>uwsgi_cache_bypass</u> directive.

Nginx, Inc. p.366 of 506

uwsgi_param

```
SYNTAX: uwsgi_param parameter value [if_not_empty];
DEFAULT —
CONTEXT: http, server, location
```

Sets a parameter that should be passed to the uwsgi server. The value can contain text, variables, and their combination. These directives are inherited from the previous configuration level if and only if there are no uwsgi_param directives defined on the current level.

Standard CGI environment variables should be provided as uwsgi headers, see the uwsgi_params file provided in the distribution:

```
location / {
  include uwsgi_params;
  ...
}
```

If the directive is specified with if_not_empty (1.1.11) then such a parameter will be passed to the server only if its value is not empty:

```
uwsgi_param HTTPS $https if_not_empty;
```

uwsgi_pass

```
SYNTAX: uwsgi_pass [protocol://]address;
DEFAULT —
CONTEXT: location, if in location
```

Sets the protocol and address of a uwsgi server. As a *protocol*, "uwsgi" or "suwsgi" (secured uwsgi, uwsgi over SSL) can be specified. The address can be specified as a domain name or IP address, and a port:

```
uwsgi_pass localhost:9000;
uwsgi_pass uwsgi://localhost:9000;
uwsgi_pass suwsgi://[2001:db8::1]:9090;
```

or as a UNIX-domain socket path:

```
uwsgi_pass unix:/tmp/uwsgi.socket;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

Parameter value can contain variables. In this case, if an address is specified as a domain name, the name is searched among the described server groups, and, if not found, is determined using a resolver.

Secured uwsgi protocol is supported since version 1.5.8.

Nginx, Inc. p.367 of 506

uwsgi_pass_header

```
SYNTAX: uwsgi_pass_header field;
```

Default —

Context: http, server, location

Permits passing otherwise disabled header fields from a uwsgi server to a client.

uwsgi_pass_request_body

```
SYNTAX: uwsgi_pass_request_body on | off;
```

Default on

CONTEXT: http, server, location

Indicates whether the original request body is passed to the uwsgi server. See also the uwsgi_pass_request_headers directive.

uwsgi_pass_request_headers

```
SYNTAX: uwsgi_pass_request_headers on | off;
```

Default on

Context: http, server, location

Indicates whether the header fields of the original request are passed to the uwsgi server. See also the uwsgi_pass_request_body directive.

uwsgi_read_timeout

```
SYNTAX: uwsgi_read_timeout time;
```

DEFAULT 60s

Context: http, server, location

Defines a timeout for reading a response from the uwsgi server. The timeout is set only between two successive read operations, not for the transmission of the whole response. If the uwsgi server does not transmit anything within this time, the connection is closed.

uwsgi_request_buffering

```
SYNTAX: uwsgi_request_buffering on | off;
```

Default on

CONTEXT: http, server, location
This directive appeared in version 1.7.11.

Enables or disables buffering of a client request body.

When buffering is enabled, the entire request body is read from the client before sending the request to a uwsgi server.

When buffering is disabled, the request body is sent to the uwsgi server immediately as it is received. In this case, the request cannot be passed to the next server if nginx already started sending the request body.

Nginx, Inc. p.368 of 506

When HTTP/1.1 chunked transfer encoding is used to send the original request body, the request body will be buffered regardless of the directive value.

$uwsgi_send_timeout$

 ${\tt SYNTAX:} \quad {\tt uwsgi_send_timeout} \ time;$

DEFAULT 60s

Context: http, server, location

Sets a timeout for transmitting a request to the uwsgi server. The timeout is set only between two successive write operations, not for the transmission of the whole request. If the uwsgi server does not receive anything within this time, the connection is closed.

uwsgi_socket_keepalive

SYNTAX: uwsgi_socket_keepalive on | off;

Default off

Context: http, server, location

This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to a uwsgi server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

$uwsgi_ssl_certificate$

SYNTAX: uwsgi_ssl_certificate file;

Default —

Context: http, server, location

This directive appeared in version 1.7.8.

Specifies a *file* with the certificate in the PEM format used for authentication to a secured uwsgi server.

uwsgi_ssl_certificate_key

SYNTAX: uwsgi_ssl_certificate_key file;

Default —

Context: http, server, location

This directive appeared in version 1.7.8.

Specifies a *file* with the secret key in the PEM format used for authentication to a secured uwsgi server.

The value engine: name: id can be specified instead of the file (1.7.9), which loads a secret key with a specified id from the OpenSSL engine name.

Nginx, Inc. p.369 of 506

uwsgi_ssl_ciphers

SYNTAX: uwsgi_ssl_ciphers ciphers;

DEFAULT DEFAULT

Context: http, server, location
This directive appeared in version 1.5.8.

Specifies the enabled ciphers for requests to a secured uwsgi server. The ciphers are specified in the format understood by the OpenSSL library.

The full list can be viewed using the "openssl ciphers" command.

uwsgi_ssl_conf_command

SYNTAX: uwsgi_ssl_conf_command command;

Default —

Context: http, server, location
This directive appeared in version 1.19.4.

Sets arbitrary OpenSSL configuration commands when establishing a connection with the secured uwsgi server.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several uwsgi_ssl_conf_command directives can be specified on the same level. These directives are inherited from the previous configuration level if and only if there are no uwsgi_ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

uwsgi_ssl_crl

SYNTAX: uwsgi_ssl_crl file;

Default —

Context: http, server, location
This directive appeared in version 1.7.0.

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify the certificate of the secured uwsgi server.

uwsgi_ssl_name

SYNTAX: uwsgi_ssl_name name;
DEFAULT host from uwsgi_pass
CONTEXT: http, server, location
This directive appeared in version 1.7.0.

Allows overriding the server name used to verify the certificate of the secured uwsgi server and to be passed through SNI when establishing a connection with the secured uwsgi server.

Nginx, Inc. p.370 of 506

By default, the host part from uwsgi_pass is used.

uwsgi_ssl_password_file

```
SYNTAX: uwsgi_ssl_password_file file;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.7.8.
```

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

uwsgi_ssl_protocols

```
SYNTAX: uwsgi_ssl_protocols [SSLv2] [SSLv3] [TLSv1] [TLSv1.1]
[TLSv1.2] [TLSv1.3];

DEFAULT TLSv1 TLSv1.1 TLSv1.2

CONTEXT: http, server, location

This directive appeared in version 1.5.8.
```

Enables the specified protocols for requests to a secured uwsgi server.

uwsgi_ssl_server_name

```
SYNTAX: uwsgi_ssl_server_name on | off;
Default off
Context: http, server, location
This directive appeared in version 1.7.0.
```

Enables or disables passing of the server name through TLS Server Name Indication extension (SNI, RFC 6066) when establishing a connection with the secured uwsgi server.

uwsgi_ssl_session_reuse

```
SYNTAX: uwsgi_ssl_session_reuse on | off;
DEFAULT on
CONTEXT: http, server, location
This directive appeared in version 1.5.8.
```

Determines whether SSL sessions can be reused when working with a secured uwsgi server. If the errors "SSL3_GET_FINISHED:digest check failed" appear in the logs, try disabling session reuse.

$uwsgi_ssl_trusted_certificate$

```
SYNTAX: uwsgi_ssl_trusted_certificate file;

DEFAULT —

CONTEXT: http, server, location

This directive appeared in version 1.7.0.
```

Nginx, Inc. p.371 of 506

Specifies a *file* with trusted CA certificates in the PEM format used to verify the certificate of the secured uwsgi server.

uwsgi_ssl_verify

```
SYNTAX: uwsgi_ssl_verify on | off;
Default off
Context: http, server, location
This directive appeared in version 1.7.0.
```

Enables or disables verification of the secured uwsgi server certificate.

uwsgi_ssl_verify_depth

```
SYNTAX: uwsgi_ssl_verify_depth number;
DEFAULT 1
CONTEXT: http, server, location
This directive appeared in version 1.7.0.
```

Sets the verification depth in the secured uwsgi server certificates chain.

uwsgi_store

```
SYNTAX: uwsgi_store on | off | string;
Default off
Context: http, server, location
```

Enables saving of files to a disk. The on parameter saves files with paths corresponding to the directives alias or root. The off parameter disables saving of files. In addition, the file name can be set explicitly using the *string* with variables:

```
uwsgi_store /data/www$original_uri;
```

The modification time of files is set according to the received Last-Modified response header field. The response is first written to a temporary file, and then the file is renamed. Starting from version 0.8.9, temporary files and the persistent store can be put on different file systems. However, be aware that in this case a file is copied across two file systems instead of the cheap renaming operation. It is thus recommended that for any given location both saved files and a directory holding temporary files, set by the uwsgi_temp_path directive, are put on the same file system.

This directive can be used to create local copies of static unchangeable files, e.g.:

Nginx, Inc. p.372 of 506

```
uwsgi_pass backend:9000;
...

uwsgi_store on;
uwsgi_store_access user:rw group:rw all:r;
uwsgi_temp_path /data/temp;
alias /data/www/;
}
```

uwsgi_store_access

```
SYNTAX: uwsgi_store_access users:permissions ...;
```

DEFAULT user:rw

Context: http, server, location

Sets access permissions for newly created files and directories, e.g.:

```
uwsgi_store_access user:rw group:rw all:r;
```

If any group or all access permissions are specified then user permissions may be omitted:

```
uwsgi_store_access group:rw all:r;
```

uwsgi_temp_file_write_size

SYNTAX: uwsgi_temp_file_write_size size;

DEFAULT 8k|16k

Context: http, server, location

Limits the *size* of data written to a temporary file at a time, when buffering of responses from the uwsgi server to temporary files is enabled. By default, *size* is limited by two buffers set by the uwsgi_buffer_size and uwsgi_buffers directives. The maximum size of a temporary file is set by the uwsgi_max_temp_file_size directive.

$uwsgi_temp_path$

```
SYNTAX: uwsgi_temp_path path [level1 [level2 [level3]]];
```

DEFAULT uwsgi_temp

Context: http, server, location

Defines a directory for storing temporary files with data received from uwsgi servers. Up to three-level subdirectory hierarchy can be used underneath the specified directory. For example, in the following configuration

```
uwsgi_temp_path /spool/nginx/uwsgi_temp 1 2;
```

a temporary file might look like this:

Nginx, Inc. p.373 of 506

/spool/nginx/uwsgi_temp/**7**/**45**/00000123**457**

See also the use_temp_path parameter of the uwsgi_cache_path directive.

Nginx, Inc. p.374 of 506

2.56 Module ngx_http_v2_module

2.56.1	Summary
2.56.2	Known Issues
2.56.3	Example Configuration
2.56.4	Directives
	http2_body_preread_size
	http2_chunk_size
	http2_idle_timeout
	http2_max_concurrent_pushes
	http2_max_concurrent_streams
	http2_max_field_size
	http2_max_header_size
	http2_max_requests
	http2_push
	http2_push_preload
	http2_recv_buffer_size
	http2_recv_timeout
2.56.5	Embedded Variables

2.56.1 Summary

The ngx_http_v2_module module (1.9.5) provides support for HTTP/2 and supersedes the ngx_http_spdy_module module.

This module is not built by default, it should be enabled with the --with-http_v2_module configuration parameter.

2.56.2 Known Issues

Before version 1.9.14, buffering of a client request body could not be disabled regardless of proxy_request_buffering, fastcgi_request_buffering, uwsgi_request_buffering, and scgi_request_buffering directive values.

Before version 1.19.1, the lingering_close mechanism was not used to control closing HTTP/2 connections.

2.56.3 Example Configuration

```
server {
    listen 443 ssl http2;

    ssl_certificate server.crt;
    ssl_certificate_key server.key;
}
```

Note that accepting HTTP/2 connections over TLS requires the "Application-Layer Protocol Negotiation" (ALPN) TLS extension support, which is available only since OpenSSL version 1.0.2. Using the "Next Protocol

Nginx, Inc. p.375 of 506

Negotiation" (NPN) TLS extension for this purpose (available since OpenSSL version 1.0.1) is not guaranteed to work.

Also note that if the ssl_prefer_server_ciphers directive is set to the value "on", the ciphers should be configured to comply with RFC 7540, Appendix A black list and supported by clients.

2.56.4 Directives

http2_body_preread_size

SYNTAX: http2_body_preread_size size;

DEFAULT 64k CONTEXT: http, server

This directive appeared in version 1.11.0.

Sets the *size* of the buffer per each request in which the request body may be saved before it is started to be processed.

http2_chunk_size

SYNTAX: http2_chunk_size size;

Default 8k

Context: http, server, location

Sets the maximum size of chunks into which the response body is sliced. A too low value results in higher overhead. A too high value impairs prioritization due to HOL blocking.

http2_idle_timeout

SYNTAX: http2_idle_timeout time;

DEFAULT 3m

Context: http, server

This directive is obsolete since version 1.19.7. The keepalive_timeout directive should be used instead.

Sets the timeout of inactivity after which the connection is closed.

http2_max_concurrent_pushes

SYNTAX: http2_max_concurrent_pushes number;

Default 10

Context: http, server

This directive appeared in version 1.13.9.

Limits the maximum number of concurrent push requests in a connection.

Nginx, Inc. p.376 of 506

http2_max_concurrent_streams

SYNTAX: http2 max concurrent streams number;

Default 128

Context: http, server

Sets the maximum number of concurrent HTTP/2 streams in a connection.

http2_max_field_size

SYNTAX: http2_max_field_size size;

Default 4k

Context: http, server

This directive is obsolete since version 1.19.7. The large_client_header_buffers directive should be used instead.

Limits the maximum size of an HPACK-compressed request header field. The limit applies equally to both name and value. Note that if Huffman encoding is applied, the actual size of decompressed name and value strings may be larger. For most requests, the default limit should be enough.

http2_max_header_size

SYNTAX: http2_max_header_size size;

Default 16k

Context: http, server

This directive is obsolete since version 1.19.7. The large_client_header_buffers directive should be used instead.

Limits the maximum size of the entire request header list after HPACK decompression. For most requests, the default limit should be enough.

http2_max_requests

SYNTAX: http2_max_requests number;

DEFAULT 1000 Context: http, server

This directive appeared in version 1.11.6.

This directive is obsolete since version 1.19.7. The keepalive_requests directive should be used instead.

Sets the maximum number of requests (including push requests) that can be served through one HTTP/2 connection, after which the next client request will lead to connection closing and the need of establishing a new connection.

Closing connections periodically is necessary to free per-connection memory allocations. Therefore, using too high maximum number of requests could result in excessive memory usage and not recommended.

Nginx, Inc. p.377 of 506

http2_push

SYNTAX: http2_push uri | off;

Default off

Context: http, server, location
This directive appeared in version 1.13.9.

Pre-emptively sends (pushes) a request to the specified *uri* along with the response to the original request. Only relative URIs with absolute path will be processed, for example:

```
http2_push /static/css/main.css;
```

The *uri* value can contain variables.

Several http2_push directives can be specified on the same configuration level. The off parameter cancels the effect of the http2_push directives inherited from the previous configuration level.

http2_push_preload

SYNTAX: http2_push_preload on | off;

Default off

DEFAULT OIL

Context: http, server, location

This directive appeared in version 1.13.9.

Enables automatic conversion of preload links specified in the Link response header fields into push requests.

http2_recv_buffer_size

SYNTAX: http2_recv_buffer_size size;

DEFAULT 256k CONTEXT: http

Sets the size of the per worker input buffer.

http2_recv_timeout

SYNTAX: http2_recv_timeout time;

DEFAULT 30s

Context: http, server

This directive is obsolete since version 1.19.7. The client_header_timeout directive should be used instead.

Sets the timeout for expecting more data from the client, after which the connection is closed.

Nginx, Inc. p.378 of 506

2.56.5 Embedded Variables

The $ngx_http_v2_module$ module supports the following embedded variables:

\$http2

negotiated protocol identifier: "h2" for HTTP/2 over TLS, "h2c" for HTTP/2 over cleartext TCP, or an empty string otherwise.

Nginx, Inc. p.379 of 506

2.57 Module ngx_http_xslt_module

2.57.1	Summary
2.57.2	Example Configuration
2.57.3	Directives
	xml_entities
	xslt_last_modified
	xslt_param
	xslt_string_param
	xslt_stylesheet
	xslt_types

2.57.1 Summary

The ngx_http_xslt_module (0.7.8+) is a filter that transforms XML responses using one or more XSLT stylesheets.

This module is not built by default, it should be enabled with the --with-http_xslt_module configuration parameter.

This module requires the libxml2 and libxslt libraries.

2.57.2 Example Configuration

```
location / {
   xml_entities /site/dtd/entities.dtd;
   xslt_stylesheet /site/xslt/one.xslt param=value;
   xslt_stylesheet /site/xslt/two.xslt;
}
```

2.57.3 Directives

xml_entities

```
SYNTAX: xml_entities path;
```

Default —

Context: http, server, location

Specifies the DTD file that declares character entities. This file is compiled at the configuration stage. For technical reasons, the module is unable to use the external subset declared in the processed XML, so it is ignored and a specially defined file is used instead. This file should not describe the XML structure. It is enough to declare just the required character entities, for example:

```
<!ENTITY nbsp "&#xa0;">
```

Nginx, Inc. p.380 of 506

xslt last modified

SYNTAX: **xslt_last_modified** on | off; Default off

Context: http, server, location
This directive appeared in version 1.5.1.

Allows preserving the Last-Modified header field from the original response during XSLT transformations to facilitate response caching.

By default, the header field is removed as contents of the response are modified during transformations and may contain dynamically generated elements or parts that are changed independently of the original response.

$xslt_param$

SYNTAX: **xslt_param** parameter value;

Default —

Context: http, server, location
This directive appeared in version 1.1.18.

Defines the parameters for XSLT stylesheets. The *value* is treated as an XPath expression. The *value* can contain variables. To pass a string value to a stylesheet, the xslt_string_param directive can be used.

There could be several xslt_param directives. These directives are inherited from the previous configuration level if and only if there are no xslt_param and xslt_string_param directives defined on the current level.

xslt_string_param

SYNTAX: **xslt_string_param** parameter value;

Default —

Context: http, server, location
This directive appeared in version 1.1.18.

Defines the string parameters for XSLT stylesheets. XPath expressions in the *value* are not interpreted. The *value* can contain variables.

There could be several xslt_string_param directives. These directives are inherited from the previous configuration level if and only if there are no xslt_param and xslt_string_param directives defined on the current level.

xslt_stylesheet

 $\begin{tabular}{lll} Syntax: & \textbf{xslt_stylesheet} & stylesheet & [parameter=value \dots]; \\ Default & --- \end{tabular}$

CONTEXT: location

Defines the XSLT stylesheet and its optional parameters. A stylesheet is compiled at the configuration stage.

Parameters can either be specified separately, or grouped in a single line using the ":" delimiter. If a parameter includes the ":" character, it should be

Nginx, Inc. p.381 of 506

escaped as "%3A". Also, libxslt requires to enclose parameters that contain non-alphanumeric characters into single or double quotes, for example:

```
param1='http%3A//www.example.com':param2=value2
```

The parameters description can contain variables, for example, the whole line of parameters can be taken from a single variable:

```
location / {
    xslt_stylesheet /site/xslt/one.xslt
    $arg_xslt_params
    param1='$value1':param2=value2
    param3=value3;
}
```

It is possible to specify several stylesheets. They will be applied sequentially in the specified order.

$xslt_types$

SYNTAX: **xslt_types** mime-type ...;

DEFAULT text/xml

Context: http, server, location

Enables transformations in responses with the specified MIME types in addition to "text/xml". The special value "*" matches any MIME type (0.8.29). If the transformation result is an HTML response, its MIME type is changed to "text/html".

Nginx, Inc. p.382 of 506

Chapter 3

Stream server modules

3.1 Module ngx_stream_core_module

3.1.1	Summary	3
3.1.2	Example Configuration	3
3.1.3	Directives	4
	listen	4
	preread_buffer_size	6
	preread_timeout	6
	proxy_protocol_timeout	7
	resolver	7
	resolver_timeout	7
	server	8
	stream	8
	tcp_nodelay	8
	variables_hash_bucket_size	8
	variables_hash_max_size	8
3.1.4	Embedded Variables	9

3.1.1 Summary

The ngx_stream_core_module module is available since version 1.9.0. This module is not built by default, it should be enabled with the --with-stream configuration parameter.

3.1.2 Example Configuration

```
worker_processes auto;
error_log /var/log/nginx/error.log info;
events {
    worker_connections 1024;
}
stream {
    upstream backend {
```

```
hash $remote_addr consistent;
   server backend1.example.com:12345 weight=5;
   server 127.0.0.1:12345 max_fails=3 fail_timeout=30s;
   server unix:/tmp/backend3;
upstream dns {
  server 192.168.0.1:53535;
  server dns.example.com:53;
server {
   listen 12345;
   proxy_connect_timeout 1s;
   proxy_timeout 3s;
   proxy_pass backend;
server {
   listen 127.0.0.1:53 udp reuseport;
   proxy_timeout 20s;
   proxy_pass dns;
   listen [::1]:12345;
   proxy_pass unix:/tmp/stream.socket;
```

3.1.3 Directives

listen

Sets the *address* and *port* for the socket on which the server will accept connections. It is possible to specify just the port. The address can also be a hostname, for example:

```
listen 127.0.0.1:12345;
listen *:12345;
listen 12345;  # same as *:12345
listen localhost:12345;
```

IPv6 addresses are specified in square brackets:

```
listen [::1]:12345;
listen [::]:12345;
```

UNIX-domain sockets are specified with the "unix:" prefix:

```
listen unix:/var/run/nginx.sock;
```

Nginx, Inc. p.384 of 506

Port ranges (1.15.10) are specified with the first and last port separated by a hyphen:

```
listen 127.0.0.1:12345-12399;
listen 12345-12399;
```

The ssl parameter allows specifying that all connections accepted on this port should work in SSL mode.

The udp parameter configures a listening socket for working with datagrams (1.9.13). In order to handle packets from the same address and port in the same session, the reuseport parameter should also be specified.

The proxy_protocol parameter (1.11.4) allows specifying that all connections accepted on this port should use the PROXY protocol.

The PROXY protocol version 2 is supported since version 1.13.11.

The listen directive can have several additional parameters specific to socket-related system calls.

backlog=number

sets the backlog parameter in the listen call that limits the maximum length for the queue of pending connections (1.9.2). By default, backlog is set to -1 on FreeBSD, DragonFly BSD, and macOS, and to 511 on other platforms.

rcvbuf=size

sets the receive buffer size (the SO_RCVBUF option) for the listening socket (1.11.13).

sndbuf=size

sets the send buffer size (the SO_SNDBUF option) for the listening socket (1.11.13).

bind

this parameter instructs to make a separate bind call for a given address:port pair. The fact is that if there are several listen directives with the same port but different addresses, and one of the listen directives listens on all addresses for the given port (*:port), nginx will bind only to *:port. It should be noted that the getsockname system call will be made in this case to determine the address that accepted the connection. If the ipv6only or so_keepalive parameters are used then for a given address:port pair a separate bind call will always be made.

ipv6only=on|off

this parameter determines (via the IPV6_V6ONLY socket option) whether an IPv6 socket listening on a wildcard address [::] will accept only IPv6 connections or both IPv6 and IPv4 connections. This parameter is turned on by default. It can only be set once on start.

reuseport

this parameter (1.9.1) instructs to create an individual listening socket for each worker process (using the SO_REUSEPORT socket option on Linux

Nginx, Inc. p.385 of 506

3.9+ and DragonFly BSD, or SO_REUSEPORT_LB on FreeBSD 12+), allowing a kernel to distribute incoming connections between worker processes. This currently works only on Linux 3.9+, DragonFly BSD, and FreeBSD 12+ (1.15.1).

Inappropriate use of this option may have its security implications.

so_keepalive=on|off|[keepidle]:[keepintvl]:[keepcnt]

this parameter configures the "TCP keepalive" behavior for the listening socket. If this parameter is omitted then the operating system's settings will be in effect for the socket. If it is set to the value "on", the SO_KEEPALIVE option is turned on for the socket. If it is set to the value "off", the SO_KEEPALIVE option is turned off for the socket. Some operating systems support setting of TCP keepalive parameters on a per-socket basis using the TCP_KEEPIDLE, TCP_KEEPINTVL, and TCP_KEEPCNT socket options. On such systems (currently, Linux 2.4+, NetBSD 5+, and FreeBSD 9.0-STABLE), they can be configured using the keepidle, keepintvl, and keepcnt parameters. One or two parameters may be omitted, in which case the system default setting for the corresponding socket option will be in effect. For example,

```
so_keepalive=30m::10
```

will set the idle timeout (TCP_KEEPIDLE) to 30 minutes, leave the probe interval (TCP_KEEPINTVL) at its system default, and set the probes count (TCP_KEEPCNT) to 10 probes.

Different servers must listen on different address: port pairs.

preread_buffer_size

SYNTAX: preread_buffer_size size;

Default 16k

Context: stream, server

This directive appeared in version 1.11.5.

Specifies a *size* of the preread buffer.

preread_timeout

SYNTAX: preread_timeout timeout;

Default 30s

Context: stream, server

This directive appeared in version 1.11.5.

Specifies a *timeout* of the preread phase.

Nginx, Inc. p.386 of 506

proxy_protocol_timeout

SYNTAX: proxy_protocol_timeout timeout;

DEFAULT 30s

Context: stream, server

This directive appeared in version 1.11.4.

Specifies a *timeout* for reading the PROXY protocol header to complete. If no entire header is transmitted within this time, the connection is closed.

resolver

```
SYNTAX: resolver address...[valid=time] [ipv6=on|off] [status_zone=zone];

DEFAULT —
```

Context: stream, server

This directive appeared in version 1.11.3.

Configures name servers used to resolve names of upstream servers into addresses, for example:

```
resolver 127.0.0.1 [::1]:5353;
```

The address can be specified as a domain name or IP address, with an optional port. If port is not specified, the port 53 is used. Name servers are queried in a round-robin fashion.

By default, nginx will look up both IPv4 and IPv6 addresses while resolving. If looking up of IPv6 addresses is not desired, the ipv6=off parameter can be specified.

By default, nginx caches answers using the TTL value of a response. The optional valid parameter allows overriding it:

```
resolver 127.0.0.1 [::1]:5353 valid=30s;
```

To prevent DNS spoofing, it is recommended configuring DNS servers in a properly secured trusted local network.

The optional status_zone parameter (1.17.1) enables collection of DNS server statistics of requests and responses in the specified *zone*. The parameter is available as part of our commercial subscription.

Before version 1.11.3, this directive was available as part of our commercial subscription.

resolver_timeout

SYNTAX: resolver_timeout time;

DEFAULT 30s

Context: stream, server

Nginx, Inc. p.387 of 506

This directive appeared in version 1.11.3.

Sets a timeout for name resolution, for example:

```
resolver_timeout 5s;
```

Before version 1.11.3, this directive was available as part of our commercial subscription.

server

```
SYNTAX: server { ...}

DEFAULT —

CONTEXT: stream
```

Sets the configuration for a server.

stream

```
SYNTAX: stream { ... }

DEFAULT —

CONTEXT: main
```

Provides the configuration file context in which the stream server directives are specified.

tcp_nodelay

```
SYNTAX: tcp_nodelay on | off;
DEFAULT on
CONTEXT: stream, server
This directive appeared in version 1.9.4.
```

Enables or disables the use of the TCP_NODELAY option. The option is enabled for both client and proxied server connections.

variables_hash_bucket_size

```
SYNTAX: variables_hash_bucket_size size;

DEFAULT 64

CONTEXT: stream

This directive appeared in version 1.11.2.
```

Sets the bucket size for the variables hash table. The details of setting up hash tables are provided in a separate document.

variables_hash_max_size

```
SYNTAX: variables_hash_max_size size;
DEFAULT 1024
CONTEXT: stream
```

Nginx, Inc. p.388 of 506

This directive appeared in version 1.11.2.

Sets the maximum *size* of the variables hash table. The details of setting up hash tables are provided in a separate document.

3.1.4 Embedded Variables

The ngx_stream_core_module module supports variables since 1.11.2.

 $\$binary_remote_addr$

client address in a binary form, value's length is always 4 bytes for IPv4 addresses or 16 bytes for IPv6 addresses

\$bytes_received

number of bytes received from a client (1.11.4)

 $$bytes_sent$

number of bytes sent to a client

\$connection

connection serial number

\$hostname

host name

\$msec

current time in seconds with the milliseconds resolution

\$nqinx_version

nginx version

\$pid

PID of the worker process

\$protocol

protocol used to communicate with the client: TCP or UDP (1.11.4)

 $proxy_protocol_addr$

client address from the PROXY protocol header (1.11.4)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

\$proxy_protocol_port

client port from the PROXY protocol header (1.11.4)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

\$proxy_protocol_server_addr

server address from the PROXY protocol header (1.17.6)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

\$proxy_protocol_server_port

server port from the PROXY protocol header (1.17.6)

The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

 $\$remote_addr$

client address

Nginx, Inc. p.389 of 506

\$remote_port

client port

 $\$server_addr$

an address of the server which accepted a connection

Computing a value of this variable usually requires one system call. To avoid a system call, the listen directives must specify addresses and use the bind parameter.

\$server_port

port of the server which accepted a connection

 $\$session_time$

session duration in seconds with a milliseconds resolution (1.11.4);

\$status

session status (1.11.4), can be one of the following:

200

session completed successfully

400

client data could not be parsed, for example, the PROXY protocol header

403

access forbidden, for example, when access is limited for certain client addresses

500

internal server error

502

bad gateway, for example, if an upstream server could not be selected or reached.

503

service unavailable, for example, when access is limited by the number of connections

 $$time_iso8601$

local time in the ISO 8601 standard format

 $$time_local$$

local time in the Common Log Format

Nginx, Inc. p.390 of 506

3.2 Module ngx_stream_access_module

3.2.1	Summary
3.2.2	Example Configuration
3.2.3	Directives
	allow
	deny 39

3.2.1 Summary

The ngx_stream_access_module module (1.9.2) allows limiting access to certain client addresses.

3.2.2 Example Configuration

```
server {
    ...
    deny 192.168.1.1;
    allow 192.168.1.0/24;
    allow 10.1.1.0/16;
    allow 2001:0db8::/32;
    deny all;
}
```

The rules are checked in sequence until the first match is found. In this example, access is allowed only for IPv4 networks 10.1.1.0/16 and 192.168.1.0/24 excluding the address 192.168.1.1, and for IPv6 network 2001:0db8::/32.

3.2.3 Directives

allow

```
SYNTAX: allow address | CIDR | unix: | all; Default — Context: stream, server
```

Allows access for the specified network or address. If the special value unix: is specified, allows access for all UNIX-domain sockets.

deny

```
SYNTAX: deny address | CIDR | unix: | all;
DEFAULT —
CONTEXT: stream, server
```

Denies access for the specified network or address. If the special value unix: is specified, denies access for all UNIX-domain sockets.

Nginx, Inc. p.391 of 506

3.3 Module ngx_stream_geo_module

3.3.1	Summary	92
3.3.2	Example Configuration	92
3.3.3	Directives	92
	geo	92

3.3.1 Summary

The ngx_stream_geo_module module (1.11.3) creates variables with values depending on the client IP address.

3.3.2 Example Configuration

```
geo $geo {
    default 0;

    127.0.0.1 2;
    192.168.1.0/24 1;
    10.1.0.0/16 1;

    ::1 2;
    2001:0db8::/32 1;
}
```

3.3.3 Directives

geo

```
SYNTAX: geo [$address] $variable { ...}

Default —

Context: stream
```

Describes the dependency of values of the specified variable on the client IP address. By default, the address is taken from the *\$remote_addr* variable, but it can also be taken from another variable, for example:

```
geo $arg_remote_addr $geo {
    ...;
}
```

Since variables are evaluated only when used, the mere existence of even a large number of declared "geo" variables does not cause any extra costs for connection processing.

If the value of a variable does not represent a valid IP address then the "255.255.255.255" address is used.

Addresses are specified either as prefixes in CIDR notation (including individual addresses) or as ranges.

The following special parameters are also supported:

Nginx, Inc. p.392 of 506

delete

deletes the specified network.

default

a value set to the variable if the client address does not match any of the specified addresses. When addresses are specified in CIDR notation, "0.0.0.0/0" and "::/0" can be used instead of default. When default is not specified, the default value will be an empty string.

include

includes a file with addresses and values. There can be several inclusions. ranges

indicates that addresses are specified as ranges. This parameter should be the first. To speed up loading of a geo base, addresses should be put in ascending order.

Example:

The conf/geo.conf file could contain the following lines:

```
10.2.0.0/16 RU;
192.168.2.0/24 RU;
```

A value of the most specific match is used. For example, for the 127.0.0.1 address the value "RU" will be chosen, not "US".

Example with ranges:

Nginx, Inc. p.393 of 506

3.4 Module ngx_stream_geoip_module

3.4.1	Summary
3.4.2	Example Configuration
3.4.3	Directives
	geoip_country
	geoip_city
	geoip_org

3.4.1 Summary

The ngx_stream_geoip_module module (1.11.3) creates variables with values depending on the client IP address, using the precompiled MaxMind databases.

When using the databases with IPv6 support, IPv4 addresses are looked up as IPv4-mapped IPv6 addresses.

This module is not built by default, it should be enabled with the --with-stream_geoip_module configuration parameter.

This module requires the MaxMind GeoIP library.

3.4.2 Example Configuration

3.4.3 Directives

geoip_country

```
SYNTAX: geoip_country file;
DEFAULT —
CONTEXT: stream
```

Specifies a database used to determine the country depending on the client IP address. The following variables are available when using this database:

```
$geoip_country_code two-letter country code, for example, "RU", "US".
```

Nginx, Inc. p.394 of 506

 $\$geoip_country_code3$

three-letter country code, for example, "RUS", "USA".

\$geoip_country_name

country name, for example, "Russian Federation", "United States".

geoip_city

SYNTAX: geoip_city file;

Default — Context: stream

Specifies a database used to determine the country, region, and city depending on the client IP address. The following variables are available when using this database:

\$qeoip_area_code

telephone area code (US only).

This variable may contain outdated information since the corresponding database field is deprecated.

\$geoip_city_continent_code

two-letter continent code, for example, "EU", "NA".

\$geoip_city_country_code

two-letter country code, for example, "RU", "US".

\$qeoip_city_country_code3

three-letter country code, for example, "RUS", "USA".

 $\$geoip_city_country_name$

country name, for example, "Russian Federation", "United States".

\$geoip_dma_code

DMA region code in US (also known as "metro code"), according to the geotargeting in Google AdWords API.

 $\$geoip_latitude$

latitude.

\$geoip_longitude

longitude.

\$qeoip_region

two-symbol country region code (region, territory, state, province, federal land and the like), for example, "48", "DC".

\$geoip_region_name

country region name (region, territory, state, province, federal land and the like), for example, "Moscow City", "District of Columbia".

\$aeoip_citu

city name, for example, "Moscow", "Washington".

 $postal_code$

postal code.

Nginx, Inc. p.395 of 506

geoip_org

SYNTAX: **geoip_org** *file*;

Default —

Context: stream

Specifies a database used to determine the organization depending on the client IP address. The following variable is available when using this database:

 $\$geoip_org$

organization name, for example, "The University of Melbourne".

Nginx, Inc. p.396 of 506

3.5 Module ngx_stream_js_module

3.5.1	Summary
3.5.2	Example Configuration
3.5.3	Directives
	js_access
	js_filter
	js_import
	js_include
	js_path
	js_preread
	js_set
	js_var
3.5.4	Session Object Properties

3.5.1 Summary

The ngx_stream_js_module module is used to implement handlers in njs — a subset of the JavaScript language.

Download and install instructions are available here.

3.5.2 Example Configuration

The example works since 0.4.0.

```
stream {
    js_import stream.js;
    js_set $bar stream.bar;
    js_set $req_line stream.req_line;
    server {
        listen 12345;
        js_preread stream.preread;
        return $req_line;
    server {
        listen 12346;
        js_access stream.access;
        proxy_pass 127.0.0.1:8000;
js_filter stream.header_inject;
}
http {
    server {
        listen 8000;
        location / {
            return 200 $http_foo\n;
}
```

The stream.js file:

Nginx, Inc. p.397 of 506

```
var line = '';
function bar(s) {
   var v = s.variables;
    s.log("hello from bar() handler!");
   return "bar-var" + v.remote_port + "; pid=" + v.pid;
function preread(s) {
    s.on('upload', function (data, flags) {
        var n = data.indexOf(' \n');
        if (n != -1) {
            line = data.substr(0, n);
            s.done();
    });
function req_line(s) {
   return line;
// Read HTTP request line.
// Collect bytes in 'req' until
// request line is read.
// Injects HTTP header into a client's request
var my_header = 'Foo: foo';
function header_inject(s) {
    var req = '';
    s.on('upload', function(data, flags) {
       req += data;
        var n = req.search(' \ ' \ ');
        if (n != -1) {
            var rest = req.substr(n + 1);
            req = req.substr(0, n + 1);
            s.send(req + my_header + '\r\n' + rest, flags);
            s.off('upload');
    });
function access(s) {
   if (s.remoteAddress.match('^192.*')) {
        s.deny();
        return;
    s.allow();
export default {bar, preread, req_line, header_inject, access};
```

3.5.3 Directives

js_access

```
SYNTAX: js_access function | module.function;
DEFAULT —
CONTEXT: stream, server
```

Sets an njs function which will be called at the access phase. Since 0.4.0, a module function can be referenced.

Nginx, Inc. p.398 of 506

js_filter

```
SYNTAX: js_filter function | module.function;
DEFAULT —
CONTEXT: stream, server
```

Sets a data filter. Since 0.4.0, a module function can be referenced.

js_import

```
SYNTAX: js_import module.js | export_name from module.js;

DEFAULT —

CONTEXT: stream

This directive appeared in version 0.4.0.
```

Imports a module that implements location and variable handlers in njs. The export_name is used as a namespace to access module functions. If the export_name is not specified, the module name will be used as a namespace.

```
js_import stream.js;
```

Here, the module name stream is used as a namespace while accessing exports. If the imported module exports foo(), stream.foo is used to refer to it.

Several js_import directives can be specified.

js_include

```
SYNTAX: js_include file;
DEFAULT —
CONTEXT: stream
```

Specifies a file that implements server and variable handlers in njs:

```
nginx.conf:
js_include stream.js;
js_set    $js_addr address;
server {
    listen 127.0.0.1:12345;
    return $js_addr;
}
stream.js:
function address(s) {
    return s.remoteAddress;
}
```

The directive is deprecated since 0.4.0, the js_import directive should be used instead.

js_path

```
SYNTAX: js_path path;
DEFAULT —
CONTEXT: stream
```

Nginx, Inc. p.399 of 506

This directive appeared in version 0.3.0.

Sets an additional path for njs modules.

js_preread

```
SYNTAX: js_preread function | module.function;
DEFAULT —
CONTEXT: stream, server
```

Sets an njs function which will be called at the preread phase. Since 0.4.0, a module function can be referenced.

js_set

```
SYNTAX: js_set $variable function | module.function;

DEFAULT —

CONTEXT: stream
```

Sets an njs function for the specified variable. Since 0.4.0, a module function can be referenced.

The function is called when the variable is referenced for the first time for a given request. The exact moment depends on a phase at which the variable is referenced. This can be used to perform some logic not related to variable evaluation. For example, if the variable is referenced only in the log_format directive, its handler will not be executed until the log phase. This handler can be used to do some cleanup right before the request is freed.

js_var

```
SYNTAX: js_var $variable [value];
DEFAULT —
CONTEXT: stream
This directive appeared in version 0.5.3.
```

Declares a writable variable. The value can contain text, variables, and their combination.

3.5.4 Session Object Properties

Each stream nis handler receives one argument, a stream session object.

Nginx, Inc. p.400 of 506

3.6 Module ngx_stream_keyval_module

3.6.1	Summary
3.6.2	Example Configuration
3.6.3	Directives
	keyval
	keyval_zone

3.6.1 Summary

The ngx_stream_keyval_module module (1.13.7) creates variables with values taken from key-value pairs managed by the API.

This module is available as part of our commercial subscription.

3.6.2 Example Configuration

3.6.3 Directives

keyval

```
SYNTAX: keyval key $variable zone=name;
DEFAULT —
CONTEXT: stream
```

Creates a new *\$variable* whose value is looked up by the *key* in the key-value database. Matching rules are defined by the type parameter of the keyval_zone directive. The database is stored in a shared memory zone specified by the zone parameter.

Nginx, Inc. p.401 of 506

keyval_zone

```
SYNTAX: keyval_zone zone=name:size [state=file] [timeout=time] [type=string|ip|prefix] [sync];

DEFAULT —

CONTEXT: stream
```

Sets the *name* and *size* of the shared memory zone that keeps the key-value database. Key-value pairs are managed by the API.

The optional state parameter specifies a *file* that keeps the current state of the key-value database in the JSON format and makes it persistent across nginx restarts.

Examples:

```
keyval_zone zone=one:32k state=/var/lib/nginx/state/one.keyval; # path for
    Linux
keyval_zone zone=one:32k state=/var/db/nginx/state/one.keyval; # path for
    FreeBSD
```

The optional timeout parameter (1.15.0) sets the time after which keyvalue pairs are removed from the zone.

The optional type parameter (1.17.1) activates an extra index optimized for matching the key of a certain type and defines matching rules when evaluating a keyval \$variable.

The index is stored in the same shared memory zone and thus requires additional storage.

```
type=string
```

default, no index is enabled; variable lookup is performed using exact match of the record key and a search key

```
type=ip
```

the search key is the textual representation of IPv4 or IPv6 address or CIDR range; to match a record key, the search key must belong to a subnet specified by a record key or exactly match an IP address

```
type=prefix
```

variable lookup is performed using prefix match of a record key and a search key (1.17.5); to match a record key, the record key must be a prefix of the search key

The optional sync parameter (1.15.0) enables synchronization of the shared memory zone. The synchronization requires the timeout parameter to be set.

If the synchronization is enabled, removal of key-value pairs (no matter one or all) will be performed only on a target cluster node. The same key-value pairs on other cluster nodes will be removed upon timeout.

Nginx, Inc. p.402 of 506

3.7 Module ngx_stream_limit_conn_module

3.7.1	Summary
3.7.2	Example Configuration
3.7.3	Directives
	limit_conn
	limit_conn_dry_run
	limit_conn_log_level
	limit_conn_zone
374	Embedded Variables 409

3.7.1 Summary

The ngx_stream_limit_conn_module module (1.9.3) is used to limit the number of connections per the defined key, in particular, the number of connections from a single IP address.

3.7.2 Example Configuration

3.7.3 Directives

limit_conn

```
SYNTAX: limit_conn zone number;
Default —
Context: stream, server
```

Sets the shared memory zone and the maximum allowed number of connections for a given key value. When this limit is exceeded, the server will close the connection. For example, the directives

```
limit_conn_zone $binary_remote_addr zone=addr:10m;
server {
    ...
    limit_conn addr 1;
}
```

Nginx, Inc. p.403 of 506

allow only one connection per an IP address at a time.

When several limit_conn directives are specified, any configured limit will apply.

These directives are inherited from the previous configuration level if and only if there are no limit_conn directives defined on the current level.

limit_conn_dry_run

SYNTAX: limit_conn_dry_run on | off;

Default off

Context: stream, server

This directive appeared in version 1.17.6.

Enables the dry run mode. In this mode, the number of connections is not limited, however, in the shared memory zone, the number of excessive connections is accounted as usual.

limit_conn_log_level

SYNTAX: limit_conn_log_level info | notice | warn | error;

DEFAULT error CONTEXT: stream, server

Sets the desired logging level for cases when the server limits the number of connections.

limit_conn_zone

SYNTAX: limit_conn_zone key zone=name:size;

Default — Context: stream

Sets parameters for a shared memory zone that will keep states for various keys. In particular, the state includes the current number of connections. The *key* can contain text, variables, and their combinations (1.11.2). Connections with an empty key value are not accounted. Usage example:

```
limit_conn_zone $binary_remote_addr zone=addr:10m;
```

Here, the key is a client IP address set by the \$binary_remote_addr variable. The size of \$binary_remote_addr is 4 bytes for IPv4 addresses or 16 bytes for IPv6 addresses. The stored state always occupies 32 or 64 bytes on 32-bit platforms and 64 bytes on 64-bit platforms. One megabyte zone can keep about 32 thousand 32-byte states or about 16 thousand 64-byte states. If the zone storage is exhausted, the server will close the connection.

Additionally, as part of our commercial subscription, the status information for each such shared memory zone can be obtained or reset with the API since 1.17.7.

Nginx, Inc. p.404 of 506

3.7.4 Embedded Variables

 $\$limit_conn_status$

keeps the result of limiting the number of connections (1.17.6): PASSED, REJECTED, or REJECTED_DRY_RUN

Nginx, Inc. p.405 of 506

3.8 Module ngx_stream_log_module

3.8.1	Summary
3.8.2	Example Configuration
3.8.3	Directives
	access_log
	log_format
	open_log_file_cache

3.8.1 Summary

The ngx_stream_log_module module (1.11.4) writes session logs in the specified format.

3.8.2 Example Configuration

3.8.3 Directives

access_log

Sets the path, format, and configuration for a buffered log write. Several logs can be specified on the same configuration level. Logging to syslog can be configured by specifying the "syslog:" prefix in the first parameter. The special value off cancels all access_log directives on the current level.

If either the buffer or gzip parameter is used, writes to log will be buffered.

The buffer size must not exceed the size of an atomic write to a disk file. For FreeBSD this size is unlimited.

When buffering is enabled, the data will be written to the file:

- if the next log line does not fit into the buffer;
- if the buffered data is older than specified by the flush parameter;
- when a worker process is re-opening log files or is shutting down.

Nginx, Inc. p.406 of 506

If the gzip parameter is used, then the buffered data will be compressed before writing to the file. The compression level can be set between 1 (fastest, less compression) and 9 (slowest, best compression). By default, the buffer size is equal to 64K bytes, and the compression level is set to 1. Since the data is compressed in atomic blocks, the log file can be decompressed or read by "zcat" at any time.

Example:

```
access_log /path/to/log.gz basic gzip flush=5m;
```

For gzip compression to work, nginx must be built with the zlib library.

The file path can contain variables, but such logs have some constraints:

- the user whose credentials are used by worker processes should have permissions to create files in a directory with such logs;
- buffered writes do not work;
- the file is opened and closed for each log write. However, since the descriptors of frequently used files can be stored in a cache, writing to the old file can continue during the time specified by the open_log_file_cache directive's valid parameter

The if parameter enables conditional logging. A session will not be logged if the *condition* evaluates to "0" or an empty string.

log_format

```
SYNTAX: log_format name [escape=default|json|none] string ...;

DEFAULT —

CONTEXT: stream
```

Specifies the log format, for example:

The escape parameter (1.11.8) allows setting json or default characters escaping in variables, by default, default escaping is used. The none parameter (1.13.10) disables escaping.

For default escaping, characters "", "\", and other characters with values less than 32 or above 126 are escaped as "\xXX". If the variable value is not found, a hyphen ("-") will be logged.

For json escaping, all characters not allowed in JSON strings will be escaped: characters "" and "\" are escaped as "\" and "\\", characters with values less than 32 are escaped as "\n", "\r", "\t", "\t", "\t", "\f", or "\u00XX".

Nginx, Inc. p.407 of 506

open_log_file_cache

 ${\tt SYNTAX:} \quad {\tt open_log_file_cache} \; {\tt max} = N \; [{\tt inactive} = time] \; [{\tt min_uses} = N]$

[valid=time];

SYNTAX: open_log_file_cache off;

Default off

Context: stream, server

Defines a cache that stores the file descriptors of frequently used logs whose names contain variables. The directive has the following parameters:

max

sets the maximum number of descriptors in a cache; if the cache becomes full the least recently used (LRU) descriptors are closed

inactive

sets the time after which the cached descriptor is closed if there were no access during this time; by default, 10 seconds

min_uses

sets the minimum number of file uses during the time defined by the inactive parameter to let the descriptor stay open in a cache; by default, 1

valid

sets the time after which it should be checked that the file still exists with the same name; by default, 60 seconds

off

disables caching

Usage example:

```
open_log_file_cache max=1000 inactive=20s valid=1m min_uses=2;
```

Nginx, Inc. p.408 of 506

3.9 Module ngx_stream_map_module

3.9.1	Summary
3.9.2	Example Configuration
3.9.3	Directives
	map
	map_hash_bucket_size
	map_hash_max_size

3.9.1 Summary

The ngx_stream_map_module module (1.11.2) creates variables whose values depend on values of other variables.

3.9.2 Example Configuration

```
map $remote_addr $limit {
    127.0.0.1 "";
    default    $binary_remote_addr;
}
limit_conn_zone $limit zone=addr:10m;
limit_conn addr 1;
```

3.9.3 Directives

map

```
Syntax: map string $variable { ...}

Default —

Context: stream
```

Creates a new variable whose value depends on values of one or more of the source variables specified in the first parameter.

Since variables are evaluated only when they are used, the mere declaration even of a large number of "map" variables does not add any extra costs to connection processing.

Parameters inside the map block specify a mapping between source and resulting values.

Source values are specified as strings or regular expressions.

Strings are matched ignoring the case.

A regular expression should either start from the "~" symbol for a case-sensitive matching, or from the "~*" symbols for case-insensitive matching. A regular expression can contain named and positional captures that can later be used in other directives along with the resulting variable.

Nginx, Inc. p.409 of 506

If a source value matches one of the names of special parameters described below, it should be prefixed with the "\" symbol.

The resulting value can contain text, variable, and their combination.

The following special parameters are also supported:

default value

sets the resulting value if the source value matches none of the specified variants. When default is not specified, the default resulting value will be an empty string.

hostnames

indicates that source values can be hostnames with a prefix or suffix mask:

```
*.example.com 1;
example.* 1;
```

The following two records

```
example.com 1;
*.example.com 1;
```

can be combined:

```
.example.com 1;
```

This parameter should be specified before the list of values.

include file

includes a file with values. There can be several inclusions.

volatile

indicates that the variable is not cacheable (1.11.7).

If the source value matches more than one of the specified variants, e.g. both a mask and a regular expression match, the first matching variant will be chosen, in the following order of priority:

- 1. string value without a mask
- 2. longest string value with a prefix mask, e.g. "*.example.com"
- 3. longest string value with a suffix mask, e.g. "mail.*"
- 4. first matching regular expression (in order of appearance in a configuration file)
- 5. default value

map_hash_bucket_size

```
SYNTAX: map_hash_bucket_size size;
DEFAULT 32|64|128
```

Context: stream

Nginx, Inc. p.410 of 506

Sets the bucket size for the map variables hash tables. Default value depends on the processor's cache line size. The details of setting up hash tables are provided in a separate document.

map_hash_max_size

 ${\tt SYNTAX:} \quad {\tt map_hash_max_size} \ size;$

Default 2048 Context: stream

Sets the maximum *size* of the map variables hash tables. The details of setting up hash tables are provided in a separate document.

Nginx, Inc. p.411 of 506

3.10 Module ngx_stream_proxy_module

3.10.1	Summary
3.10.2	Example Configuration
	Directives
	proxy_bind
	proxy_buffer_size
	proxy_connect_timeout
	proxy_download_rate
	proxy_next_upstream
	proxy_next_upstream_timeout 414
	proxy_next_upstream_tries
	proxy_pass
	proxy_protocol
	proxy_requests
	proxy_responses
	proxy_session_drop
	proxy_socket_keepalive
	proxy_ssl
	proxy_ssl_certificate
	proxy_ssl_certificate_key
	proxy_ssl_ciphers
	proxy_ssl_conf_command
	proxy_ssl_crl
	proxy_ssl_name
	proxy_ssl_password_file
	proxy_ssl_protocols
	proxy_ssl_server_name
	proxy_ssl_session_reuse
	proxy_ssl_trusted_certificate
	proxy_ssl_verify
	proxy_ssl_verify_depth
	proxy_timeout
	proxy_upload_rate

3.10.1 Summary

The ngx_stream_proxy_module module (1.9.0) allows proxying data streams over TCP, UDP (1.9.13), and UNIX-domain sockets.

3.10.2 Example Configuration

```
server {
    listen 127.0.0.1:12345;
    proxy_pass 127.0.0.1:8080;
}
```

Nginx, Inc. p.412 of 506

```
server {
    listen 12345;
    proxy_connect_timeout 1s;
    proxy_timeout 1m;
    proxy_pass example.com:12345;
}

server {
    listen 53 udp reuseport;
    proxy_timeout 20s;
    proxy_pass dns.example.com:53;
}

server {
    listen [::1]:12345;
    proxy_pass unix:/tmp/stream.socket;
}
```

3.10.3 Directives

proxy_bind

```
SYNTAX: proxy_bind address [transparent] | off;
Default —
Context: stream, server
This directive appeared in version 1.9.2.
```

Makes outgoing connections to a proxied server originate from the specified local IP *address*. Parameter value can contain variables (1.11.2). The special value off cancels the effect of the proxy_bind directive inherited from the previous configuration level, which allows the system to auto-assign the local IP address.

The transparent parameter (1.11.0) allows outgoing connections to a proxied server originate from a non-local IP address, for example, from a real IP address of a client:

```
proxy_bind $remote_addr transparent;
```

In order for this parameter to work, it is usually necessary to run nginx worker processes with the superuser privileges. On Linux it is not required (1.13.8) as if the transparent parameter is specified, worker processes inherit the CAP_NET_RAW capability from the master process. It is also necessary to configure kernel routing table to intercept network traffic from the proxied server.

proxy_buffer_size

```
SYNTAX: proxy_buffer_size size;

DEFAULT 16k

CONTEXT: stream, server

This directive appeared in version 1.9.4.
```

Sets the *size* of the buffer used for reading data from the proxied server. Also sets the *size* of the buffer used for reading data from the client.

Nginx, Inc. p.413 of 506

proxy_connect_timeout

SYNTAX: proxy_connect_timeout time;

DEFAULT 60s

Context: stream, server

Defines a timeout for establishing a connection with a proxied server.

proxy_download_rate

SYNTAX: proxy_download_rate rate;

Default 0

Context: stream, server

This directive appeared in version 1.9.3.

Limits the speed of reading the data from the proxied server. The rate is specified in bytes per second. The zero value disables rate limiting. The limit is set per a connection, so if nginx simultaneously opens two connections to the proxied server, the overall rate will be twice as much as the specified limit.

Parameter value can contain variables (1.17.0). It may be useful in cases where rate should be limited depending on a certain condition:

```
map $slow $rate {
          4k;
          8k;
proxy_download_rate $rate;
```

proxy_next_upstream

SYNTAX: proxy_next_upstream on | off;

Default on

Context: stream, server

When a connection to the proxied server cannot be established, determines whether a client connection will be passed to the next server.

Passing a connection to the next server can be limited by the number of tries and by time.

proxy_next_upstream_timeout

SYNTAX: proxy_next_upstream_timeout time;

Default 0

Context: stream, server

Limits the time allowed to pass a connection to the next server. The 0 value turns off this limitation.

Nginx, Inc. p.414 of 506

proxy_next_upstream_tries

SYNTAX: proxy_next_upstream_tries number;

Default 0

CONTEXT: stream, server

Limits the number of possible tries for passing a connection to the next server. The 0 value turns off this limitation.

proxy_pass

SYNTAX: **proxy_pass** address;

Default — Context: server

Sets the address of a proxied server. The address can be specified as a domain name or IP address, and a port:

```
proxy_pass localhost:12345;
```

or as a UNIX-domain socket path:

```
proxy_pass unix:/tmp/stream.socket;
```

If a domain name resolves to several addresses, all of them will be used in a round-robin fashion. In addition, an address can be specified as a server group.

The address can also be specified using variables (1.11.3):

```
proxy_pass $upstream;
```

In this case, the server name is searched among the described server groups, and, if not found, is determined using a resolver.

proxy_protocol

SYNTAX: **proxy_protocol** on | off;

Default off

Context: stream, server

This directive appeared in version 1.9.2.

Enables the PROXY protocol for connections to a proxied server.

proxy_requests

SYNTAX: proxy_requests number;

Default 0

Context: stream, server

This directive appeared in version 1.15.7.

Nginx, Inc. p.415 of 506

Sets the number of client datagrams at which binding between a client and existing UDP stream session is dropped. After receiving the specified number of datagrams, next datagram from the same client starts a new session. The session terminates when all client datagrams are transmitted to a proxied server and the expected number of responses is received, or when it reaches a timeout.

proxy_responses

```
SYNTAX: proxy_responses number;
```

Default —

Context: stream, server

This directive appeared in version 1.9.13.

Sets the number of datagrams expected from the proxied server in response to a client datagram if the UDP protocol is used. The number serves as a hint for session termination. By default, the number of datagrams is not limited.

If zero value is specified, no response is expected. However, if a response is received and the session is still not finished, the response will be handled.

proxy_session_drop

```
SYNTAX: proxy_session_drop on | off;
```

Default off

Context: stream, server

This directive appeared in version 1.15.8.

Enables terminating all sessions to a proxied server after it was removed from the group or marked as permanently unavailable. This can occur because of re-resolve or with the API DELETE command. A server can be marked as permanently unavailable if it is considered unhealthy or with the API PATCH command. Each session is terminated when the next read or write event is processed for the client or proxied server.

This directive is available as part of our commercial subscription.

proxy_socket_keepalive

```
SYNTAX: proxy_socket_keepalive on | off;
```

Default off

Context: stream, server

This directive appeared in version 1.15.6.

Configures the "TCP keepalive" behavior for outgoing connections to a proxied server. By default, the operating system's settings are in effect for the socket. If the directive is set to the value "on", the SO_KEEPALIVE socket option is turned on for the socket.

Nginx, Inc. p.416 of 506

proxy_ssl

SYNTAX: **proxy_ssl** on | off;

Default off

Context: stream, server

Enables the SSL/TLS protocol for connections to a proxied server.

proxy_ssl_certificate

SYNTAX: proxy_ssl_certificate file;

Default —

Context: stream, server

Specifies a *file* with the certificate in the PEM format used for authentication to a proxied server.

proxy_ssl_certificate_key

SYNTAX: proxy_ssl_certificate_key file;

Default —

Context: stream, server

Specifies a *file* with the secret key in the PEM format used for authentication to a proxied server.

proxy_ssl_ciphers

SYNTAX: proxy_ssl_ciphers ciphers;

DEFAULT DEFAULT
CONTEXT: stream, server

Specifies the enabled ciphers for connections to a proxied server. The ciphers are specified in the format understood by the OpenSSL library.

The full list can be viewed using the "openssl ciphers" command.

proxy_ssl_conf_command

SYNTAX: proxy_ssl_conf_command command;

Default —

Context: stream, server

This directive appeared in version 1.19.4.

Sets arbitrary OpenSSL configuration commands when establishing a connection with the proxied server.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several proxy_ssl_conf_command directives can be specified on the same level. These directives are inherited from the previous configuration level

Nginx, Inc. p.417 of 506

if and only if there are no proxy_ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

proxy_ssl_crl

```
SYNTAX: proxy_ssl_crl file;
DEFAULT —
CONTEXT: stream, server
```

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify the certificate of the proxied server.

proxy_ssl_name

```
SYNTAX: proxy_ssl_name name;
DEFAULT host from proxy_pass
CONTEXT: stream, server
```

Allows overriding the server name used to verify the certificate of the proxied server and to be passed through SNI when establishing a connection with the proxied server. The server name can also be specified using variables (1.11.3).

By default, the host part of the proxy_pass address is used.

proxy_ssl_password_file

```
SYNTAX: proxy_ssl_password_file file;

DEFAULT —

CONTEXT: stream, server
```

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

proxy_ssl_protocols

```
SYNTAX: proxy_ssl_protocols [SSLv2] [SSLv3] [TLSv1.1] [TLSv1.2] [TLSv1.3];

DEFAULT TLSv1.1 TLSv1.2

CONTEXT: stream, server
```

Enables the specified protocols for connections to a proxied server.

proxy_ssl_server_name

```
SYNTAX: proxy_ssl_server_name on | off;
Default off
Context: stream, server
```

Nginx, Inc. p.418 of 506

Enables or disables passing of the server name through TLS Server Name Indication extension (SNI, RFC 6066) when establishing a connection with the proxied server.

proxy_ssl_session_reuse

```
SYNTAX: proxy_ssl_session_reuse on | off;
```

Default on

Context: stream, server

Determines whether SSL sessions can be reused when working with the proxied server. If the errors "SSL3_GET_FINISHED:digest check failed" appear in the logs, try disabling session reuse.

proxy_ssl_trusted_certificate

```
SYNTAX: proxy_ssl_trusted_certificate file;
```

Default —

Context: stream, server

Specifies a *file* with trusted CA certificates in the PEM format used to verify the certificate of the proxied server.

proxy_ssl_verify

```
SYNTAX: proxy_ssl_verify on | off;
```

Default off

Context: stream, server

Enables or disables verification of the proxied server certificate.

proxy_ssl_verify_depth

```
SYNTAX: proxy_ssl_verify_depth number;
```

Default 1

Context: stream, server

Sets the verification depth in the proxied server certificates chain.

proxy_timeout

SYNTAX: proxy_timeout timeout;

DEFAULT 10m

Context: stream, server

Sets the *timeout* between two successive read or write operations on client or proxied server connections. If no data is transmitted within this time, the connection is closed.

Nginx, Inc. p.419 of 506

proxy_upload_rate

SYNTAX: proxy_upload_rate rate;

Default 0

Context: stream, server

This directive appeared in version 1.9.3.

Limits the speed of reading the data from the client. The *rate* is specified in bytes per second. The zero value disables rate limiting. The limit is set per a connection, so if the client simultaneously opens two connections, the overall rate will be twice as much as the specified limit.

Parameter value can contain variables (1.17.0). It may be useful in cases where rate should be limited depending on a certain condition:

```
map $slow $rate {
    1     4k;
    2     8k;
}
proxy_upload_rate $rate;
```

Nginx, Inc. p.420 of 506

3.11 Module ngx_stream_realip_module

3.11.1	Summary
3.11.2	Example Configuration
3.11.3	Directives
	set_real_ip_from
3.11.4	Embedded Variables

3.11.1 Summary

The ngx_stream_realip_module module is used to change the client address and port to the ones sent in the PROXY protocol header (1.11.4). The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

This module is not built by default, it should be enabled with the --with-stream_realip_module configuration parameter.

3.11.2 Example Configuration

```
listen 12345 proxy_protocol;

set_real_ip_from 192.168.1.0/24;
set_real_ip_from 192.168.2.1;
set_real_ip_from 2001:0db8::/32;
```

3.11.3 Directives

set_real_ip_from

```
SYNTAX: set_real_ip_from address | CIDR | unix:;

DEFAULT —

CONTEXT: stream, server
```

Defines trusted addresses that are known to send correct replacement addresses. If the special value unix: is specified, all UNIX-domain sockets will be trusted.

3.11.4 Embedded Variables

```
$realip_remote_addr
keeps the original client address
$realip_remote_port
keeps the original client port
```

Nginx, Inc. p.421 of 506

3.12 Module ngx_stream_return_module

3.12.1	Summary	22
3.12.2	Example Configuration	22
3.12.3	Directives	22
	return 4	22

3.12.1 Summary

The ngx_stream_return_module module (1.11.2) allows sending a specified value to the client and then closing the connection.

3.12.2 Example Configuration

```
server {
   listen 12345;
   return $time_iso8601;
}
```

3.12.3 Directives

return

SYNTAX: return value;

Default — Context: server

Specifies a *value* to send to the client. The value can contain text, variables, and their combination.

Nginx, Inc. p.422 of 506

3.13 Module ngx_stream_set_module

3.13.1	Summary
3.13.2	Example Configuration
3.13.3	Directives
	set

3.13.1 Summary

The ngx_stream_set_module module (1.19.3) allows setting a value for a variable.

3.13.2 Example Configuration

```
server {
    listen 12345;
    set $true 1;
}
```

3.13.3 Directives

 \mathbf{set}

SYNTAX: set \$variable value;

Default — Context: server

Sets a *value* for the specified *variable*. The *value* can contain text, variables, and their combination.

Nginx, Inc. p.423 of 506

3.14 Module ngx_stream_split_clients_module

3.14.1	Summary	4
3.14.2	Example Configuration	4
3.14.3	Directives	4
	split_clients	4

3.14.1 Summary

The ngx_stream_split_clients_module module (1.11.3) creates variables suitable for A/B testing, also known as split testing.

3.14.2 Example Configuration

3.14.3 Directives

split_clients

```
SYNTAX: split_clients string $variable { ...}

DEFAULT —

CONTEXT: stream
```

Creates a variable for A/B testing, for example:

The value of the original string is hashed using MurmurHash2. In the example given, hash values from 0 to 21474835 (0.5%) correspond to the value ".one" of the \$variant variable, hash values from 21474836 to 107374180 (2%) correspond to the value ".two", and hash values from 107374181 to 4294967295 correspond to the value "" (an empty string).

Nginx, Inc. p.424 of 506

3.15 Module ngx_stream_ssl_module

3.15.1	Summary
3.15.2	Example Configuration
3.15.3	Directives
	ssl_certificate
	ssl_certificate_key
	ssl_ciphers
	ssl_client_certificate
	ssl_conf_command
	ssLcrl
	ssl_dhparam
	ssl_ecdh_curve
	ssl_handshake_timeout
	ssl_password_file
	ssl_prefer_server_ciphers
	ssl_protocols
	ssl_session_cache
	ssl_session_ticket_key
	ssl_session_tickets
	ssl_session_timeout
	ssl_trusted_certificate
	ssl_verify_client
	ssl_verify_depth
3.15.4	Embedded Variables

3.15.1 Summary

The ngx_stream_ssl_module module (1.9.0) provides the necessary support for a stream proxy server to work with the SSL/TLS protocol. This module is not built by default, it should be enabled with the --with-stream_ssl_module configuration parameter.

3.15.2 Example Configuration

To reduce the processor load, it is recommended to

- set the number of worker processes equal to the number of processors,
- enable the shared session cache,
- disable the built-in session cache,
- and possibly increase the session lifetime (by default, 5 minutes):

Nginx, Inc. p.425 of 506

3.15.3 Directives

ssl_certificate

```
SYNTAX: ssl_certificate file;
DEFAULT —
CONTEXT: stream, server
```

Specifies a *file* with the certificate in the PEM format for the given server. If intermediate certificates should be specified in addition to a primary certificate, they should be specified in the same file in the following order: the primary certificate comes first, then the intermediate certificates. A secret key in the PEM format may be placed in the same file.

Since version 1.11.0, this directive can be specified multiple times to load certificates of different types, for example, RSA and ECDSA:

Only OpenSSL 1.0.2 or higher supports separate certificate chains for different certificates. With older versions, only one certificate chain can be used.

Since version 1.15.9, variables can be used in the *file* name when using OpenSSL 1.0.2 or higher:

```
ssl_certificate $ssl_server_name.crt;
```

Nginx, Inc. p.426 of 506

```
ssl_certificate_key $ssl_server_name.key;
```

Note that using variables implies that a certificate will be loaded for each SSL handshake, and this may have a negative impact on performance.

The value data: \$variable can be specified instead of the file (1.15.10), which loads a certificate from a variable without using intermediate files. Note that inappropriate use of this syntax may have its security implications, such as writing secret key data to error log.

ssl_certificate_key

SYNTAX: ssl_certificate_key file;
DEFAULT —

Context: stream, server

Specifies a *file* with the secret key in the PEM format for the given server. The value engine: name: id can be specified instead of the *file*, which loads a secret key with a specified id from the OpenSSL engine name.

The value data: \$variable can be specified instead of the file (1.15.10), which loads a secret key from a variable without using intermediate files. Note that inappropriate use of this syntax may have its security implications, such as writing secret key data to error log.

Since version 1.15.9, variables can be used in the *file* name when using OpenSSL 1.0.2 or higher.

ssl_ciphers

SYNTAX: **ssl_ciphers** ciphers;
DEFAULT HIGH:!aNULL:!MD5
CONTEXT: stream, server

Specifies the enabled ciphers. The ciphers are specified in the format understood by the OpenSSL library, for example:

```
ssl_ciphers ALL:!aNULL:!EXPORT56:RC4+RSA:+HIGH:+MEDIUM:+LOW:+SSLv2:+EXP;
```

The full list can be viewed using the "openssl ciphers" command.

ssl_client_certificate

SYNTAX: ssl_client_certificate file;

DEFAULT —

CONTEXT: stream, server

This directive appeared in version 1.11.8.

Specifies a *file* with trusted CA certificates in the PEM format used to verify client certificates.

The list of certificates will be sent to clients. If this is not desired, the ssl_trusted_certificate directive can be used.

Nginx, Inc. p.427 of 506

ssl_conf_command

SYNTAX: ssl_conf_command command;

Default —

Context: stream, server

This directive appeared in version 1.19.4.

Sets arbitrary OpenSSL configuration commands.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several ssl_conf_command directives can be specified on the same level:

```
ssl_conf_command Options PrioritizeChaCha;
ssl_conf_command Ciphersuites TLS_CHACHA20_POLY1305_SHA256;
```

These directives are inherited from the previous configuration level if and only if there are no ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

ssl_crl

SYNTAX: ssl_crl file;

Default —

Context: stream, server

This directive appeared in version 1.11.8.

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify client certificates.

ssl_dhparam

SYNTAX: ssl_dhparam file;

Default —

Context: stream, server

Specifies a *file* with DH parameters for DHE ciphers.

By default no parameters are set, and therefore DHE ciphers will not be used.

Prior to version 1.11.0, builtin parameters were used by default.

ssl_ecdh_curve

SYNTAX: ssl_ecdh_curve curve;

DEFAULT auto

Context: stream, server

Nginx, Inc. p.428 of 506

Specifies a curve for ECDHE ciphers.

When using OpenSSL 1.0.2 or higher, it is possible to specify multiple curves (1.11.0), for example:

```
ssl_ecdh_curve prime256v1:secp384r1;
```

The special value auto (1.11.0) instructs nginx to use a list built into the OpenSSL library when using OpenSSL 1.0.2 or higher, or prime256v1 with older versions.

Prior to version 1.11.0, the prime256v1 curve was used by default.

When using OpenSSL 1.0.2 or higher, this directive sets the list of curves supported by the server. Thus, in order for ECDSA certificates to work, it is important to include the curves used in the certificates.

ssl_handshake_timeout

```
SYNTAX: ssl_handshake_timeout time;
DEFAULT 60s
CONTEXT: stream, server
```

Specifies a timeout for the SSL handshake to complete.

ssl_password_file

```
SYNTAX: ssl_password_file file;

DEFAULT —

CONTEXT: stream, server
```

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

Example:

```
stream {
    ssl_password_file /etc/keys/global.pass;
    ...

server {
        listen 127.0.0.1:12345;
        ssl_certificate_key /etc/keys/first.key;
    }

server {
        listen 127.0.0.1:12346;

        # named pipe can also be used instead of a file ssl_password_file /etc/keys/fifo;
        ssl_certificate_key /etc/keys/second.key;
    }
}
```

Nginx, Inc. p.429 of 506

ssl_prefer_server_ciphers

SYNTAX: ssl_prefer_server_ciphers on | off;

Default off

Context: stream, server

Specifies that server ciphers should be preferred over client ciphers when the SSLv3 and TLS protocols are used.

ssl_protocols

```
SYNTAX: ssl_protocols [SSLv2] [SSLv3] [TLSv1] [TLSv1.1] [TLSv1.2]
```

[TLSv1.3];

DEFAULT TLSv1 TLSv1.1 TLSv1.2

Context: stream, server

Enables the specified protocols.

The TLSv1.1 and TLSv1.2 parameters work only when OpenSSL 1.0.1 or higher is used.

The TLSv1.3 parameter (1.13.0) works only when OpenSSL 1.1.1 built with TLSv1.3 support is used.

ssl_session_cache

SYNTAX: ssl_session_cache off | none | [builtin[:size]]

[shared:name:size];

Default none

Context: stream, server

Sets the types and sizes of caches that store session parameters. A cache can be of any of the following types:

off

the use of a session cache is strictly prohibited: nginx explicitly tells a client that sessions may not be reused.

none

the use of a session cache is gently disallowed: nginx tells a client that sessions may be reused, but does not actually store session parameters in the cache.

builtin

a cache built in OpenSSL; used by one worker process only. The cache size is specified in sessions. If size is not given, it is equal to 20480 sessions. Use of the built-in cache can cause memory fragmentation.

shared

a cache shared between all worker processes. The cache size is specified in bytes; one megabyte can store about 4000 sessions. Each shared cache

Nginx, Inc. p.430 of 506

should have an arbitrary name. A cache with the same name can be used in several servers.

Both cache types can be used simultaneously, for example:

```
ssl_session_cache builtin:1000 shared:SSL:10m;
```

but using only shared cache without the built-in cache should be more efficient.

ssl_session_ticket_key

```
SYNTAX: ssl_session_ticket_key file;
DEFAULT —
CONTEXT: stream, server
```

Sets a *file* with the secret key used to encrypt and decrypt TLS session tickets. The directive is necessary if the same key has to be shared between multiple servers. By default, a randomly generated key is used.

If several keys are specified, only the first key is used to encrypt TLS session tickets. This allows configuring key rotation, for example:

```
ssl_session_ticket_key current.key;
ssl_session_ticket_key previous.key;
```

The *file* must contain 80 or 48 bytes of random data and can be created using the following command:

```
openssl rand 80 > ticket.key
```

Depending on the file size either AES256 (for 80-byte keys, 1.11.8) or AES128 (for 48-byte keys) is used for encryption.

ssl_session_tickets

```
SYNTAX: ssl_session_tickets on | off; Default on
```

Context: stream, server

Enables or disables session resumption through TLS session tickets.

ssl_session_timeout

```
SYNTAX: ssl_session_timeout time;
DEFAULT 5m
```

Context: stream, server

Specifies a time during which a client may reuse the session parameters.

Nginx, Inc. p.431 of 506

ssl trusted certificate

SYNTAX: ssl_trusted_certificate file;

Default —

Context: stream, server

This directive appeared in version 1.11.8.

Specifies a *file* with trusted CA certificates in the PEM format used to verify client certificates.

In contrast to the certificate set by ssl_client_certificate, the list of these certificates will not be sent to clients.

ssl_verify_client

SYNTAX: **ssl_verify_client** on | off | optional | optional_no_ca;

Default off

Context: stream, server

This directive appeared in version 1.11.8.

Enables verification of client certificates. The verification result is stored in the \$ssl_client_verify variable. If an error has occurred during the client certificate verification or a client has not presented the required certificate, the connection is closed.

The optional parameter requests the client certificate and verifies it if the certificate is present.

The optional_no_ca parameter requests the client certificate but does not require it to be signed by a trusted CA certificate. This is intended for the use in cases when a service that is external to nginx performs the actual certificate verification. The contents of the certificate is accessible through the \$ssl_client_cert variable.

ssl_verify_depth

SYNTAX: ssl_verify_depth number;

Default 1

Context: stream, server

This directive appeared in version 1.11.8.

Sets the verification depth in the client certificates chain.

3.15.4 Embedded Variables

The ngx_stream_ssl_module module supports variables since 1.11.2.

\$ssl_cipher

returns the name of the cipher used for an established SSL connection; $\$ssl_ciphers$

returns the list of ciphers supported by the client (1.11.7). Known ciphers are listed by names, unknown are shown in hexadecimal, for example:

Nginx, Inc. p.432 of 506

AES128-SHA: AES256-SHA: 0x00ff

The variable is fully supported only when using OpenSSL version 1.0.2 or higher. With older versions, the variable is available only for new sessions and lists only known ciphers.

$$ssl_client_cert$

returns the client certificate in the PEM format for an established SSL connection, with each line except the first prepended with the tab character (1.11.8);

\$ssl_client_fingerprint

returns the SHA1 fingerprint of the client certificate for an established SSL connection (1.11.8);

$$ssl_client_i_dn$

returns the "issuer DN" string of the client certificate for an established SSL connection according to RFC 2253 (1.11.8);

\$ssl_client_raw_cert

returns the client certificate in the PEM format for an established SSL connection (1.11.8);

$$ssl_client_s_dn$

returns the "subject DN" string of the client certificate for an established SSL connection according to RFC 2253 (1.11.8);

$$ssl_client_serial$

returns the serial number of the client certificate for an established SSL connection (1.11.8);

$$ssl_client_v_end$

returns the end date of the client certificate (1.11.8);

$ssl_client_v_remain$

returns the number of days until the client certificate expires (1.11.8);

$$ssl_client_v_start$

returns the start date of the client certificate (1.11.8);

\$ssl_client_verify

returns the result of client certificate verification (1.11.8): "SUCCESS", "FAILED: reason", and "NONE" if a certificate was not present;

\$ssl_curves

returns the list of curves supported by the client (1.11.7). Known curves are listed by names, unknown are shown in hexadecimal, for example:

```
0x001d:prime256v1:secp521r1:secp384r1
```

The variable is supported only when using OpenSSL version 1.0.2 or higher. With older versions, the variable value will be an empty string.

Nginx, Inc. p.433 of 506

The variable is available only for new sessions.

\$ssl_protocol

returns the protocol of an established SSL connection;

 $$ssl_server_name$

returns the server name requested through SNI;

 $$ssl_session_id$$

returns the session identifier of an established SSL connection;

 $\$ssl_session_reused$

returns "r" if an SSL session was reused, or "." otherwise.

Nginx, Inc. p.434 of 506

3.16 Module ngx_stream_ssl_preread_module

3.16.1	Summary									435
3.16.2	Example Configuration .									435
3.16.3	Directives									436
	ssl_preread									436
3.16.4	Embedded Variables									436

3.16.1 **Summary**

The ngx_stream_ssl_preread_module module (1.11.5) allows extracting information from the ClientHello message without terminating SSL/TLS, for example, the server name requested through SNI or protocols advertised in ALPN. This module is not built by default, it should be enabled with the --with-stream_ssl_preread_module configuration parameter.

3.16.2 Example Configuration

Selecting an upstream based on server name:

```
map $ssl_preread_server_name $name {
    backend.example.com    backend;
    default    backend2;
}

upstream backend {
    server 192.168.0.1:12345;
    server 192.168.0.2:12345;
}

upstream backend2 {
    server 192.168.0.3:12345;
    server 192.168.0.4:12345;
}

server {
    listen    12346;
    proxy_pass    $name;
    ssl_preread on;
}
```

Selecting an upstream based on protocol:

Selecting an upstream based on SSL protocol version:

Nginx, Inc. p.435 of 506

3.16.3 Directives

ssl_preread

```
SYNTAX: ssl_preread on | off;
Default off
Context: stream, server
```

Enables extracting information from the ClientHello message at the preread phase.

3.16.4 Embedded Variables

```
$ssl\_preread\_protocol
```

the highest SSL protocol version supported by the client (1.15.2)

 $$ssl_preread_server_name$

server name requested through SNI

 $ssl_preread_alpn_protocols$

list of protocols advertised by the client through ALPN (1.13.10). The values are separated by commas.

Nginx, Inc. p.436 of 506

3.17 Module ngx_stream_upstream_module

3.17.1	Summary
3.17.2	Example Configuration
3.17.3	Directives
	upstream
	server
	zone
	state
	hash
	least_conn
	least_time
	random
	resolver
	resolver_timeout
3.17.4	Embedded Variables

3.17.1 Summary

The ngx_stream_upstream_module module (1.9.0) is used to define groups of servers that can be referenced by the proxy_pass directive.

3.17.2 Example Configuration

```
upstream backend {
   hash $remote_addr consistent;

   server backend1.example.com:12345 weight=5;
   server backend2.example.com:12345;
   server unix:/tmp/backend3;

   server backup1.example.com:12345 backup;
   server backup2.example.com:12345 backup;
}

server {
   listen 12346;
   proxy_pass backend;
}
```

Dynamically configurable group with periodic health checks is available as part of our commercial subscription:

Nginx, Inc. p.437 of 506

```
server backup2.example.com:12345 backup;
}
server {
    listen 12346;
    proxy_pass dynamic;
    health_check;
}
```

3.17.3 Directives

upstream

```
SYNTAX: upstream name { ...}

DEFAULT —

CONTEXT: stream
```

Defines a group of servers. Servers can listen on different ports. In addition, servers listening on TCP and UNIX-domain sockets can be mixed.

Example:

By default, connections are distributed between the servers using a weighted round-robin balancing method. In the above example, each 7 connections will be distributed as follows: 5 connections go to backendl.example.com:12345 and one connection to each of the second and third servers. If an error occurs during communication with a server, the connection will be passed to the next server, and so on until all of the functioning servers will be tried. If communication with all servers fails, the connection will be closed.

server

```
SYNTAX: server address [parameters];
DEFAULT —
CONTEXT: upstream
```

Defines the *address* and other *parameters* of a server. The address can be specified as a domain name or IP address with an obligatory port, or as a UNIX-domain socket path specified after the "unix:" prefix. A domain name that resolves to several IP addresses defines multiple servers at once.

The following parameters can be defined:

```
weight=number
sets the weight of the server, by default, 1.
```

Nginx, Inc. p.438 of 506

max conns = number

limits the maximum *number* of simultaneous connections to the proxied server (1.11.5). Default value is zero, meaning there is no limit. If the server group does not reside in the shared memory, the limitation works per each worker process.

Prior to version 1.11.5, this parameter was available as part of our commercial subscription.

$max_fails = number$

sets the number of unsuccessful attempts to communicate with the server that should happen in the duration set by the fail_timeout parameter to consider the server unavailable for a duration also set by the fail_timeout parameter. By default, the number of unsuccessful attempts is set to 1. The zero value disables the accounting of attempts. Here, an unsuccessful attempt is an error or timeout while establishing a connection with the server.

 $\begin{array}{c} \texttt{fail_timeout} {=} time \\ \texttt{sets} \end{array}$

- the time during which the specified number of unsuccessful attempts to communicate with the server should happen to consider the server unavailable;
- and the period of time the server will be considered unavailable.

By default, the parameter is set to 10 seconds.

backup

marks the server as a backup server. Connections to the backup server will be passed when the primary servers are unavailable.

The parameter cannot be used along with the hash and random load balancing methods.

down

marks the server as permanently unavailable.

Additionally, the following parameters are available as part of our commercial subscription:

resolve

monitors changes of the IP addresses that correspond to a domain name of the server, and automatically modifies the upstream configuration without the need of restarting nginx. The server group must reside in the shared memory.

In order for this parameter to work, the resolver directive must be specified in the stream block or in the corresponding upstream block.

Nginx, Inc. p.439 of 506

service=name

enables resolving of DNS SRV records and sets the service name (1.9.13). In order for this parameter to work, it is necessary to specify the resolve parameter for the server and specify a hostname without a port number. If the service name does not contain a dot ("."), then the RFC-compliant name is constructed and the TCP protocol is added to the service prefix. For example, to look up the _http._tcp.backend.example.com SRV record, it is necessary to specify the directive:

```
server backend.example.com service=http resolve;
```

If the service name contains one or more dots, then the name is constructed by joining the service prefix and the server name. For example, to look up the _http._tcp.backend.example.com and server1.backend.example.com SRV records, it is necessary to specify the directives:

```
server backend.example.com service=_http._tcp resolve;
server example.com service=server1.backend resolve;
```

Highest-priority SRV records (records with the same lowest-number priority value) are resolved as primary servers, the rest of SRV records are resolved as backup servers. If the backup parameter is specified for the server, high-priority SRV records are resolved as backup servers, the rest of SRV records are ignored.

```
slow start = time
```

sets the *time* during which the server will recover its weight from zero to a nominal value, when unhealthy server becomes healthy, or when the server becomes available after a period of time it was considered unavailable. Default value is zero, i.e. slow start is disabled.

The parameter cannot be used along with the hash and random load balancing methods.

If there is only a single server in a group, max_fails, fail_timeout and slow_start parameters are ignored, and such a server will never be considered unavailable.

zone

SYNTAX: zone name [size];

Default —

Context: upstream

Defines the *name* and *size* of the shared memory zone that keeps the group's configuration and run-time state that are shared between worker processes. Several groups may share the same zone. In this case, it is enough to specify the *size* only once.

Nginx, Inc. p.440 of 506

Additionally, as part of our commercial subscription, such groups allow changing the group membership or modifying the settings of a particular server without the need of restarting nginx. The configuration is accessible via the API module (1.13.3).

Prior to version 1.13.3, the configuration was accessible only via a special location handled by upstream_conf.

state

SYNTAX: state file;

Default —

Context: upstream

This directive appeared in version 1.9.7.

Specifies a *file* that keeps the state of the dynamically configurable group. Examples:

```
state /var/lib/nginx/state/servers.conf; # path for Linux
state /var/db/nginx/state/servers.conf; # path for FreeBSD
```

The state is currently limited to the list of servers with their parameters. The file is read when parsing the configuration and is updated each time the upstream configuration is changed. Changing the file content directly should be avoided. The directive cannot be used along with the server directive.

Changes made during configuration reload or binary upgrade can be lost.

This directive is available as part of our commercial subscription.

hash

```
SYNTAX: hash key [consistent];
```

Default —

Context: upstream

Specifies a load balancing method for a server group where the client-server mapping is based on the hashed key value. The key can contain text, variables, and their combinations (1.11.2). Usage example:

```
hash $remote_addr;
```

Note that adding or removing a server from the group may result in remapping most of the keys to different servers. The method is compatible with the Cache::Memcached Perl library.

If the consistent parameter is specified, the ketama consistent hashing method will be used instead. The method ensures that only a few keys will be remapped to different servers when a server is added to or removed from the

Nginx, Inc. p.441 of 506

group. This helps to achieve a higher cache hit ratio for caching servers. The method is compatible with the Cache::Memcached::Fast Perl library with the ketama_points parameter set to 160.

least_conn

SYNTAX: least_conn;
DEFAULT —
CONTEXT: upstream

Specifies that a group should use a load balancing method where a connection is passed to the server with the least number of active connections, taking into account weights of servers. If there are several such servers, they are tried in turn using a weighted round-robin balancing method.

least_time

```
SYNTAX: least_time connect | first_byte | last_byte [inflight];

DEFAULT —

CONTEXT: upstream
```

Specifies that a group should use a load balancing method where a connection is passed to the server with the least average time and least number of active connections, taking into account weights of servers. If there are several such servers, they are tried in turn using a weighted round-robin balancing method.

If the connect parameter is specified, time to connect to the upstream server is used. If the first_byte parameter is specified, time to receive the first byte of data is used. If the last_byte is specified, time to receive the last byte of data is used. If the inflight parameter is specified (1.11.6), incomplete connections are also taken into account.

Prior to version 1.11.6, incomplete connections were taken into account by default.

This directive is available as part of our commercial subscription.

random

```
SYNTAX: random [two [method]];
DEFAULT —
CONTEXT: upstream
This directive appeared in version 1.15.1.
```

Specifies that a group should use a load balancing method where a connection is passed to a randomly selected server, taking into account weights of servers.

The optional two parameter instructs nginx to randomly select two servers and then choose a server using the specified method. The default method is

Nginx, Inc. p.442 of 506

least_conn which passes a connection to a server with the least number of active connections.

The least_time method passes a connection to a server with the least average time and least number of active connections. If least_time=connect parameter is specified, time to connect to the upstream server is used. If least_time=first_byte parameter is specified, time to receive the first byte of data is used. If least_time=last_byte is specified, time to receive the last byte of data is used.

The least_time method is available as a part of our commercial subscription.

resolver

Configures name servers used to resolve names of upstream servers into addresses, for example:

```
resolver 127.0.0.1 [::1]:5353;
```

The address can be specified as a domain name or IP address, with an optional port. If port is not specified, the port 53 is used. Name servers are queried in a round-robin fashion.

By default, nginx will look up both IPv4 and IPv6 addresses while resolving. If looking up of IPv6 addresses is not desired, the ipv6=off parameter can be specified.

By default, nginx caches answers using the TTL value of a response. The optional valid parameter allows overriding it:

```
resolver 127.0.0.1 [::1]:5353 valid=30s;
```

To prevent DNS spoofing, it is recommended configuring DNS servers in a properly secured trusted local network.

The optional status_zone parameter enables collection of DNS server statistics of requests and responses in the specified *zone*.

This directive is available as part of our commercial subscription.

Nginx, Inc. p.443 of 506

resolver timeout

SYNTAX: resolver_timeout time;

Default 30s Context: upstream

This directive appeared in version 1.17.5.

Sets a timeout for name resolution, for example:

```
resolver_timeout 5s;
```

This directive is available as part of our commercial subscription.

3.17.4 Embedded Variables

The ngx_stream_upstream_module module supports the following embedded variables:

$\$upstream_addr$

keeps the IP address and port, or the path to the UNIX-domain socket of the upstream server (1.11.4). If several servers were contacted during proxying, their addresses are separated by commas, e.g. "192.168.1.1:12345, 192.168.1.2:12345, unix:/tmp/sock". If a server cannot be selected, the variable keeps the name of the server group.

\$upstream_bytes_received

number of bytes received from an upstream server (1.11.4). Values from several connections are separated by commas like addresses in the **\$upstream_addr** variable.

$$upstream_bytes_sent$

number of bytes sent to an upstream server (1.11.4). Values from several connections are separated by commas like addresses in the \$upstream_-addr variable.

\$upstream_connect_time

time to connect to the upstream server (1.11.4); the time is kept in seconds with millisecond resolution. Times of several connections are separated by commas like addresses in the \$upstream_addr variable.

\$upstream_first_byte_time

time to receive the first byte of data (1.11.4); the time is kept in seconds with millisecond resolution. Times of several connections are separated by commas like addresses in the \$upstream_addr variable.

$\$upstream_session_time$

session duration in seconds with millisecond resolution (1.11.4). Times of several connections are separated by commas like addresses in the \$upstream_addr variable.

Nginx, Inc. p.444 of 506

3.18 Module ngx_stream_upstream_hc_module

3.18.1	Summary
3.18.2	Example Configuration
3.18.3	Directives
	health_check
	health_check_timeout
	match

3.18.1 **Summary**

The ngx_stream_upstream_hc_module module (1.9.0) allows enabling periodic health checks of the servers in a group. The server group must reside in the shared memory.

If a health check fails, the server will be considered unhealthy. If several health checks are defined for the same group of servers, a single failure of any check will make the corresponding server be considered unhealthy. Client connections are not passed to unhealthy servers and servers in the "checking" state.

This module is available as part of our commercial subscription.

3.18.2 Example Configuration

```
upstream tcp {
   zone upstream_tcp 64k;

   server backend1.example.com:12345 weight=5;
   server backend2.example.com:12345 fail_timeout=5s slow_start=30s;
   server 192.0.2.1:12345 max_fails=3;

   server backup1.example.com:12345 backup;
   server backup2.example.com:12345 backup;
}

server {
   listen 12346;
   proxy_pass tcp;
   health_check;
}
```

With this configuration, nginx will check the ability to establish a TCP connection to each server in the tcp group every five seconds. When a connection to the server cannot be established, the health check will fail, and the server will be considered unhealthy.

Health checks can be configured for the UDP protocol:

```
upstream dns_upstream {
```

Nginx, Inc. p.445 of 506

In this case, the absence of ICMP "Destination Unreachable" message is expected in reply to the sent string "nginx health check".

Health checks can also be configured to test data obtained from the server. Tests are configured separately using the match directive and referenced in the match parameter of the health_check directive.

3.18.3 Directives

health_check

```
SYNTAX: health_check [parameters];
DEFAULT —
CONTEXT: server
```

Enables periodic health checks of the servers in a group.

The following optional parameters are supported:

```
interval=time
```

sets the interval between two consecutive health checks, by default, 5 seconds.

```
jitter=time
```

sets the time within which each health check will be randomly delayed, by default, there is no delay.

```
fails=number
```

sets the number of consecutive failed health checks of a particular server after which this server will be considered unhealthy, by default, 1.

```
passes=number
```

sets the number of consecutive passed health checks of a particular server after which the server will be considered healthy, by default, 1.

```
mandatory
```

sets the initial "checking" state for a server until the first health check is completed (1.11.7). Client connections are not passed to servers in the "checking" state. If the parameter is not specified, the server will be initially considered healthy.

```
match=name
```

specifies the match block configuring the tests that a successful connection should pass in order for a health check to pass. By default, for TCP, only the ability to establish a TCP connection with the server is checked. For UDP, the absence of ICMP "Destination"

Nginx, Inc. p.446 of 506

Unreachable" message is expected in reply to the sent string "nginx health check".

Prior to version 1.11.7, by default, UDP health check required a match block with the send and expect parameters.

```
port=number
```

defines the port used when connecting to a server to perform a health check (1.9.7). By default, equals the server port.

udp

specifies that the UDP protocol should be used for health checks instead of the default TCP protocol (1.9.13).

health_check_timeout

SYNTAX: health check timeout timeout;

Default 5s

Context: stream, server

Overrides the proxy_timeout value for health checks.

match

```
SYNTAX: match name { ...}

DEFAULT —

CONTEXT: stream
```

Defines the named test set used to verify server responses to health checks. The following parameters can be configured:

```
send string;
```

sends a *string* to the server;

```
expect string \mid \sim regex;
```

a literal string (1.9.12) or a regular expression that the data obtained from the server should match. The regular expression is specified with the preceding " $\sim \star$ " modifier (for case-insensitive matching), or the " \sim " modifier (for case-sensitive matching).

Both send and expect parameters can contain hexadecimal literals with the prefix "\x" followed by two hex digits, for example, "\x80" (1.9.12).

Health check is passed if:

- the TCP connection was successfully established;
- the *string* from the send parameter, if specified, was sent;
- the data obtained from the server matched the string or regular expression from the expect parameter, if specified;
- the time elapsed does not exceed the value specified in the health_check_timeout directive.

Nginx, Inc. p.447 of 506

Example:

```
upstream backend {
   zone    upstream_backend 10m;
   server   127.0.0.1:12345;
}
match http {
   send    "GET / HTTP/1.0\r\nHost: localhost\r\n\r\n";
   expect ~ "200 OK";
}
server {
   listen    12346;
   proxy_pass   backend;
   health_check match=http;
}
```

Only the first proxy_buffer_size bytes of data obtained from the server are examined.

Nginx, Inc. p.448 of 506

3.19 Module ngx_stream_zone_sync_module

3.19.1	Summary
3.19.2	Example Configuration
3.19.3	Directives
	zone_sync
	zone_sync_buffers
	zone_sync_connect_retry_interval
	zone_sync_connect_timeout
	zone_sync_interval
	zone_sync_recv_buffer_size
	zone_sync_server
	zone_sync_ssl
	zone_sync_ssl_certificate
	zone_sync_ssl_certificate_key
	zone_sync_ssl_ciphers
	zone_sync_ssl_conf_command
	zone_sync_ssl_crl
	zone_sync_ssl_name
	zone_sync_ssl_password_file
	zone_sync_ssl_protocols
	zone_sync_ssl_server_name
	zone_sync_ssl_trusted_certificate
	zone_sync_ssl_verify
	zone_sync_ssl_verify_depth
	zone_sync_timeout
3.19.4	API endpoints
3.19.5	Starting, stopping, removing a cluster node 455

3.19.1 **Summary**

The ngx_stream_zone_sync_module module (1.13.8) provides the necessary support for synchronizing contents of shared memory zones between nodes of a cluster. To enable synchronization for a particular zone, a corresponding module must support this feature. Currently, it is possible to synchronize HTTP sticky sessions, information about excessive HTTP requests, and key-value pairs both in http and stream.

This module is available as part of our commercial subscription.

3.19.2 Example Configuration

Minimal configuration:

Nginx, Inc. p.449 of 506

```
http {
    upstream backend {
       server backend1.example.com:8080;
      server backend2.example.com:8081;
       sticky learn
             create=$upstream_cookie_examplecookie
              lookup=$cookie_examplecookie
              zone=client_sessions:1m sync;
stream {
    server {
       zone_sync;
       listen 127.0.0.1:12345;
        # cluster of 2 nodes
        zone_sync_server a.example.com:12345;
        zone_sync_server b.example.com:12345;
    }
```

A more complex configuration with SSL enabled and with cluster members defined by DNS:

```
. . .
stream {
    resolver 127.0.0.1 valid=10s;
    server {
       zone_sync;
        # the name resolves to multiple addresses that correspond to cluster
            nodes
        zone_sync_server cluster.example.com:12345 resolve;
       listen 127.0.0.1:4433 ssl;
        ssl_certificate
                          localhost.crt;
        ssl_certificate_key localhost.key;
        zone_sync_ssl on;
                                    localhost.crt;
       zone_sync_ssl_certificate
        zone_sync_ssl_certificate_key localhost.key;
```

Nginx, Inc. p.450 of 506

3.19.3 Directives

zone_sync

SYNTAX: zone_sync;

Default — Context: server

Enables the synchronization of shared memory zones between cluster nodes. Cluster nodes are defined using zone_sync_server directives.

zone_sync_buffers

SYNTAX: zone_sync_buffers number size;

DEFAULT 8 4k | 8k CONTEXT: stream, server

Sets the *number* and *size* of the per-zone buffers used for pushing zone contents. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

A single buffer must be large enough to hold any entry of each zone being synchronized.

zone_sync_connect_retry_interval

SYNTAX: zone_sync_connect_retry_interval time;

DEFAULT 1s

Context: stream, server

Defines an interval between connection attempts to another cluster node.

zone_sync_connect_timeout

SYNTAX: zone_sync_connect_timeout time;

Default 5s

Context: stream, server

Defines a timeout for establishing a connection with another cluster node.

zone_sync_interval

SYNTAX: zone_sync_interval time;

DEFAULT 1s

Context: stream, server

Defines an interval for polling updates in a shared memory zone.

Nginx, Inc. p.451 of 506

zone_sync_recv_buffer_size

```
SYNTAX: zone_sync_recv_buffer_size size;
DEFAULT 4k | 8k
CONTEXT: stream, server
```

Sets *size* of a per-connection receive buffer used to parse incoming stream of synchronization messages. The buffer size must be equal or greater than one of the zone_sync_buffers. By default, the buffer size is equal to zone_sync_buffers *size* multiplied by *number*.

zone_sync_server

```
SYNTAX: zone_sync_server address [resolve];
DEFAULT —
CONTEXT: server
```

Defines the *address* of a cluster node. The address can be specified as a domain name or IP address with a mandatory port, or as a UNIX-domain socket path specified after the "unix:" prefix. A domain name that resolves to several IP addresses defines multiple nodes at once.

The resolve parameter instructs nginx to monitor changes of the IP addresses that correspond to a domain name of the node and automatically modify the configuration without the need of restarting nginx.

Cluster nodes are specified either dynamically as a single zone_sync_-server directive with the resolve parameter, or statically as a series of several directives without the parameter.

Each cluster node should be specified only once.

All cluster nodes should use the same configuration.

In order for the resolve parameter to work, the resolver directive must be specified in the stream block. Example:

```
stream {
    resolver 10.0.0.1;

    server {
        zone_sync;
        zone_sync_server cluster.example.com:12345 resolve;
        ...
    }
}
```

zone_sync_ssl

```
SYNTAX: zone_sync_ssl on | off;
Default off
Context: stream, server
```

Enables the SSL/TLS protocol for connections to another cluster server.

Nginx, Inc. p.452 of 506

zone_sync_ssl_certificate

```
SYNTAX: zone_sync_ssl_certificate file;
```

Default —

Context: stream, server

Specifies a *file* with the certificate in the PEM format used for authentication to another cluster server.

zone_sync_ssl_certificate_key

```
SYNTAX: zone_sync_ssl_certificate_key file;

DEFAULT —

CONTEXT: stream, server
```

Specifies a *file* with the secret key in the PEM format used for authentication to another cluster server.

zone_sync_ssl_ciphers

SYNTAX: zone_sync_ssl_ciphers ciphers;

DEFAULT DEFAULT
CONTEXT: stream, server

Specifies the enabled ciphers for connections to another cluster server. The ciphers are specified in the format understood by the OpenSSL library.

The full list can be viewed using the "openssl ciphers" command.

zone_sync_ssl_conf_command

```
SYNTAX: zone_sync_ssl_conf_command command;

DEFAULT —

CONTEXT: stream, server

This directive appeared in version 1.19.4.
```

Sets arbitrary OpenSSL configuration commands when establishing a connection with another cluster server.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several zone_sync_ssl_conf_command directives can be specified on the same level. These directives are inherited from the previous configuration level if and only if there are no zone_sync_ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

Nginx, Inc. p.453 of 506

zone_sync_ssl_crl

```
SYNTAX: zone_sync_ssl_crl file;
Default —
Context: stream, server
```

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify the certificate of another cluster server.

zone_sync_ssl_name

```
SYNTAX: zone_sync_ssl_name name;

DEFAULT host from zone_sync_server

CONTEXT: stream, server

This directive appeared in version 1.15.7.
```

Allows overriding the server name used to verify the certificate of a cluster server and to be passed through SNI when establishing a connection with the cluster server.

By default, the host part of the zone_sync_server address is used, or resolved IP address if the resolve parameter is specified.

zone_sync_ssl_password_file

```
SYNTAX: zone_sync_ssl_password_file file;
DEFAULT —
CONTEXT: stream, server
```

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

zone_sync_ssl_protocols

```
SYNTAX: zone_sync_ssl_protocols [SSLv2] [SSLv3] [TLSv1] [TLSv1.1]

[TLSv1.2] [TLSv1.3];

DEFAULT TLSv1 TLSv1.1 TLSv1.2

CONTEXT: stream, server
```

Enables the specified protocols for connections to another cluster server.

zone_sync_ssl_server_name

```
SYNTAX: zone_sync_ssl_server_name on | off;

DEFAULT off

CONTEXT: stream, server

This directive appeared in version 1.15.7.
```

Enables or disables passing of the server name through TLS Server Name Indication extension (SNI, RFC 6066) when establishing a connection with another cluster server.

Nginx, Inc. p.454 of 506

zone_sync_ssl_trusted_certificate

```
zone sync ssl trusted certificate file;
```

Default

Context: stream, server

Specifies a file with trusted CA certificates in the PEM format used to verify the certificate of another cluster server.

zone_sync_ssl_verify

```
SYNTAX: zone_sync_ssl_verify on | off;
```

Default off

Context: stream, server

Enables or disables verification of another cluster server certificate.

zone_sync_ssl_verify_depth

```
SYNTAX: zone_sync_ssl_verify_depth number;
```

Default 1

Context: stream, server

Sets the verification depth in another cluster server certificates chain.

zone_sync_timeout

```
SYNTAX: zone_sync_timeout timeout;
```

Default 5s

Context: stream, server

Sets the timeout between two successive read or write operations on connection to another cluster node. If no data is transmitted within this time, the connection is closed.

3.19.4API endpoints

The synchronization status of a node is available via the /stream/zone_sync/ endpoint of the API which returns the following metrics.

3.19.5Starting, stopping, removing a cluster node

To start a new node, update a DNS record of a cluster hostname with the IP address of the new node and start an instance. The new node will discover other nodes from DNS or static configuration and will start sending updates to them. Other nodes will eventually discover the new node using DNS and start pushing updates to it. In case of static configuration, other nodes need to be reloaded in order to send updates to the new node.

To stop a node, send the QUIT signal to the instance. The node will finish zone synchronization and gracefully close open connections.

Nginx, Inc. p.455 of 506 To remove a node, update a DNS record of a cluster hostname and remove the IP address of the node. All other nodes will eventually discover that the node is removed, close connections to the node, and will no longer try to connect to it. After the node is removed, it can be stopped as described above. In case of static configuration, other nodes need to be reloaded in order to stop sending updates to the removed node.

Nginx, Inc. p.456 of 506

Chapter 4

Mail server modules

4.1 Module ngx_mail_core_module

4.1.1	Summary
4.1.2	Example Configuration
4.1.3	Directives
	listen
	mail
	protocol
	resolver
	resolver_timeout
	server
	server_name
	timeout 469

4.1.1 Summary

This module is not built by default, it should be enabled with the --with-mail configuration parameter.

4.1.2 Example Configuration

```
smtp_auth login plain cram-md5;
smtp_capabilities "SIZE 10485760" ENHANCEDSTATUSCODES 8BITMIME DSN;
xclient
               off:
server {
   listen 25;
   protocol smtp;
server {
   listen 110;
   protocol pop3;
   proxy_pass_error_message on;
server {
   listen 143;
   protocol imap;
server {
   listen 587;
   protocol smtp;
```

4.1.3 Directives

listen

Sets the *address* and *port* for the socket on which the server will accept requests. It is possible to specify just the port. The address can also be a hostname, for example:

```
listen 127.0.0.1:110;
listen *:110;
listen 110;  # same as *:110
listen localhost:110;
```

IPv6 addresses (0.7.58) are specified in square brackets:

```
listen [::1]:110;
listen [::]:110;
```

UNIX-domain sockets (1.3.5) are specified with the "unix:" prefix:

```
listen unix:/var/run/nginx.sock;
```

Different servers must listen on different address: port pairs.

The ssl parameter allows specifying that all connections accepted on this port should work in SSL mode.

The proxy_protocol parameter (1.19.8) allows specifying that all connections accepted on this port should use the PROXY protocol. Obtained

Nginx, Inc. p.458 of 506

information is passed to the authentication server and can be used to change the client address.

The listen directive can have several additional parameters specific to socket-related system calls.

backlog=number

sets the backlog parameter in the listen call that limits the maximum length for the queue of pending connections (1.9.2). By default, backlog is set to -1 on FreeBSD, DragonFly BSD, and macOS, and to 511 on other platforms.

rcvbuf=size

sets the receive buffer size (the SO_RCVBUF option) for the listening socket (1.11.13).

sndbuf=size

sets the send buffer size (the SO_SNDBUF option) for the listening socket (1.11.13).

bind

this parameter instructs to make a separate bind call for a given address:port pair. The fact is that if there are several listen directives with the same port but different addresses, and one of the listen directives listens on all addresses for the given port (*:port), nginx will bind only to *:port. It should be noted that the getsockname system call will be made in this case to determine the address that accepted the connection. If the ipv6only or so_keepalive parameters are used then for a given address:port pair a separate bind call will always be made.

ipv6only=on|off

this parameter determines (via the IPV6_V6ONLY socket option) whether an IPv6 socket listening on a wildcard address [::] will accept only IPv6 connections or both IPv6 and IPv4 connections. This parameter is turned on by default. It can only be set once on start.

so_keepalive=on|off|[keepidle]:[keepintvl]:[keepcnt]

this parameter configures the "TCP keepalive" behavior for the listening socket. If this parameter is omitted then the operating system's settings will be in effect for the socket. If it is set to the value "on", the SO_KEEPALIVE option is turned on for the socket. If it is set to the value "off", the SO_KEEPALIVE option is turned off for the socket. Some operating systems support setting of TCP keepalive parameters on a per-socket basis using the TCP_KEEPIDLE, TCP_KEEPINTVL, and TCP_KEEPCNT socket options. On such systems (currently, Linux 2.4+, NetBSD 5+, and FreeBSD 9.0-STABLE), they can be configured using the keepidle, keepintvl, and keepcnt parameters. One or two parameters may be omitted, in which case the system default setting for the corresponding socket option will be in effect. For example,

so_keepalive=30m::10

Nginx, Inc. p.459 of 506

will set the idle timeout (TCP_KEEPIDLE) to 30 minutes, leave the probe interval (TCP_KEEPINTVL) at its system default, and set the probes count (TCP_KEEPCNT) to 10 probes.

mail

```
SYNTAX: mail { ... }

DEFAULT —

CONTEXT: main
```

Provides the configuration file context in which the mail server directives are specified.

protocol

```
SYNTAX: protocol imap | pop3 | smtp;
DEFAULT —
CONTEXT: server
```

Sets the protocol for a proxied server. Supported protocols are IMAP, POP3, and SMTP.

If the directive is not set, the protocol can be detected automatically based on the well-known port specified in the <u>listen</u> directive:

```
imap: 143, 993pop3: 110, 995smtp: 25, 587, 465
```

Unnecessary protocols can be disabled using the configuration parameters --without-mail_imap_module, --without-mail_pop3_module, and --without-mail_smtp_module.

resolver

Configures name servers used to find the client's hostname to pass it to the authentication server, and in the XCLIENT command when proxying SMTP. For example:

```
resolver 127.0.0.1 [::1]:5353;
```

The address can be specified as a domain name or IP address, with an optional port (1.3.1, 1.2.2). If port is not specified, the port 53 is used. Name servers are queried in a round-robin fashion.

Nginx, Inc. p.460 of 506

Before version 1.1.7, only a single name server could be configured. Specifying name servers using IPv6 addresses is supported starting from versions 1.3.1 and 1.2.2.

By default, nginx will look up both IPv4 and IPv6 addresses while resolving. If looking up of IPv6 addresses is not desired, the ipv6=off parameter can be specified.

Resolving of names into IPv6 addresses is supported starting from version 1.5.8.

By default, nginx caches answers using the TTL value of a response. An optional valid parameter allows overriding it:

```
resolver 127.0.0.1 [::1]:5353 valid=30s;
```

Before version 1.1.9, tuning of caching time was not possible, and nginx always cached answers for the duration of 5 minutes.

To prevent DNS spoofing, it is recommended configuring DNS servers in a properly secured trusted local network.

The optional status_zone parameter (1.17.1) enables collection of DNS server statistics of requests and responses in the specified *zone*. The parameter is available as part of our commercial subscription.

The special value off disables resolving.

resolver_timeout

SYNTAX: resolver_timeout time;

DEFAULT 30s

Context: mail, server

Sets a timeout for DNS operations, for example:

```
resolver_timeout 5s;
```

server

SYNTAX: **server** { ...}
DEFAULT —

Default — Context: mail

Sets the configuration for a server.

Nginx, Inc. p.461 of 506

server_name

SYNTAX: server_name name;

DEFAULT hostname CONTEXT: mail, server

Sets the server name that is used:

- in the initial POP3/SMTP server greeting;
- in the salt during the SASL CRAM-MD5 authentication;
- in the EHLO command when connecting to the SMTP backend, if the passing of the XCLIENT command is enabled.

If the directive is not specified, the machine's hostname is used.

timeout

SYNTAX: timeout time;

DEFAULT 60s

Context: mail, server

Sets the timeout that is used before proxying to the backend starts.

Nginx, Inc. p.462 of 506

4.2 Module ngx_mail_auth_http_module

4.2.1	Directives
	auth_http
	auth_http_header
	auth_http_pass_client_cert
	auth_http_timeout
4.2.2	Protocol

4.2.1 Directives

auth_http

SYNTAX: auth_http URL;

Default —

Context: mail, server

Sets the URL of the HTTP authentication server. The protocol is described below.

auth_http_header

SYNTAX: auth_http_header header value;

Default —

Context: mail, server

Appends the specified header to requests sent to the authentication server. This header can be used as the shared secret to verify that the request comes from nginx. For example:

```
auth_http_header X-Auth-Key "secret_string";
```

auth_http_pass_client_cert

SYNTAX: auth_http_pass_client_cert on | off;

Default off

Context: mail, server

This directive appeared in version 1.7.11.

Appends the Auth-SSL-Cert header with the client certificate in the PEM format (urlencoded) to requests sent to the authentication server.

auth_http_timeout

SYNTAX: auth_http_timeout time;

DEFAULT 60s

Context: mail, server

Sets the timeout for communication with the authentication server.

Nginx, Inc. p.463 of 506

4.2.2 Protocol

The HTTP protocol is used to communicate with the authentication server. The data in the response body is ignored, the information is passed only in the headers.

Examples of requests and responses:

Request:

```
GET /auth HTTP/1.0
Host: localhost
Auth-Method: plain # plain/apop/cram-md5/external
Auth-User: user
Auth-Pass: password
Auth-Protocol: imap # imap/pop3/smtp
Auth-Login-Attempt: 1
Client-IP: 192.0.2.42
Client-Host: client.example.org
```

Good response:

```
HTTP/1.0 200 OK
Auth-Status: OK
Auth-Server: 198.51.100.1
Auth-Port: 143
```

Bad response:

```
HTTP/1.0 200 OK
Auth-Status: Invalid login or password
Auth-Wait: 3
```

If there is no Auth-Wait header, an error will be returned and the connection will be closed. The current implementation allocates memory for each authentication attempt. The memory is freed only at the end of a session. Therefore, the number of invalid authentication attempts in a single session must be limited — the server must respond without the Auth-Wait header after 10-20 attempts (the attempt number is passed in the Auth-Login-Attempt header).

When the APOP or CRAM-MD5 are used, request-response will look as follows:

```
GET /auth HTTP/1.0
Host: localhost
Auth-Method: apop
Auth-User: user
Auth-Salt: <238188073.1163692009@mail.example.com>
Auth-Pass: auth_response
Auth-Protocol: imap
Auth-Login-Attempt: 1
Client-IP: 192.0.2.42
Client-Host: client.example.org
```

Good response:

```
HTTP/1.0 200 OK
Auth-Status: OK
Auth-Server: 198.51.100.1
```

Nginx, Inc. p.464 of 506

```
Auth-Port: 143
Auth-Pass: plain-text-pass
```

If the Auth-User header exists in the response, it overrides the username used to authenticate with the backend.

For the SMTP, the response additionally takes into account the Auth-Error-Code header — if exists, it is used as a response code in case of an error. Otherwise, the 535 5.7.0 code will be added to the Auth-Status header.

For example, if the following response is received from the authentication server:

```
HTTP/1.0 200 OK
Auth-Status: Temporary server problem, try again later
Auth-Error-Code: 451 4.3.0
Auth-Wait: 3
```

then the SMTP client will receive an error

```
451 4.3.0 Temporary server problem, try again later
```

If proxying SMTP does not require authentication, the request will look as follows:

```
GET /auth HTTP/1.0

Host: localhost

Auth-Method: none

Auth-User:

Auth-Pass:

Auth-Protocol: smtp

Auth-Login-Attempt: 1

Client-IP: 192.0.2.42

Client-Host: client.example.org

Auth-SMTP-Helo: client.example.org

Auth-SMTP-From: MAIL FROM: <>

Auth-SMTP-To: RCPT TO: <postmaster@mail.example.com>
```

For the SSL/TLS client connection (1.7.11), the Auth-SSL header is added, and Auth-SSL-Verify will contain the result of client certificate verification, if enabled: "SUCCESS", "FAILED: reason", and "NONE" if a certificate was not present.

Prior to version 1.11.7, the "FAILED" result did not contain the *reason* string.

When the client certificate was present, its details are passed in the following request headers: Auth-SSL-Subject, Auth-SSL-Issuer, Auth-SSL-Serial, and Auth-SSL-Fingerprint. If auth_http_pass_client_cert is enabled, the certificate itself is passed in the Auth-SSL-Cert header. The request will look as follows:

```
GET /auth HTTP/1.0
Host: localhost
```

Nginx, Inc. p.465 of 506

```
Auth-Method: plain
Auth-User: user
Auth-Pass: password
Auth-Protocol: imap
Auth-Login-Attempt: 1
Client-IP: 192.0.2.42
Auth-SSL: on
Auth-SSL-Verify: SUCCESS
Auth-SSL-Subject: /CN=example.com
Auth-SSL-Issuer: /CN=example.com
Auth-SSL-Issuer: /CN=example.com
Auth-SSL-Serial: C07AD56B846B5BFF
Auth-SSL-Fingerprint: 29d6a80a123d13355ed16b4b04605e29cb55a5ad
```

When the PROXY protocol is used, its details are passed in the following request headers: Proxy-Protocol-Addr, Proxy-Protocol-Port, Proxy-Protocol-Server-Addr, and Proxy-Protocol-Server-Port (1.19.8).

Nginx, Inc. p.466 of 506

4.3 Module ngx_mail_proxy_module

4.3.1	Directives	37
	proxy_buffer	67
	proxy_pass_error_message	67
	proxy_protocol	67
	proxy_smtp_auth	68
	proxy_timeout	68
	xclient 40	68

4.3.1 Directives

proxy_buffer

SYNTAX: proxy_buffer size;

Default 4k | 8k Context: mail, server

Sets the size of the buffer used for proxying. By default, the buffer size is equal to one memory page. Depending on a platform, it is either 4K or 8K.

proxy_pass_error_message

SYNTAX: proxy_pass_error_message on | off;

Default off

Context: mail, server

Indicates whether to pass the error message obtained during the authentication on the backend to the client.

Usually, if the authentication in nginx is a success, the backend cannot return an error. If it nevertheless returns an error, it means some internal error has occurred. In such case the backend message can contain information that should not be shown to the client. However, responding with an error for the correct password is a normal behavior for some POP3 servers. For example, CommuniGatePro informs a user about mailbox overflow or other events by periodically outputting the authentication error. The directive should be enabled in this case.

proxy_protocol

SYNTAX: **proxy_protocol** on | off;

Default off

CONTEXT: mail, server

This directive appeared in version 1.19.8.

Enables the PROXY protocol for connections to a backend.

Nginx, Inc. p.467 of 506

proxy_smtp_auth

SYNTAX: **proxy_smtp_auth** on | off; Default off Context: mail, server This directive appeared in version 1.19.4.

Enables or disables user authentication on the SMTP backend using the AUTH command.

If XCLIENT is also enabled, then the XCLIENT command will not send the LOGIN parameter.

proxy_timeout

SYNTAX: **proxy_timeout** timeout;
DEFAULT 24h
CONTEXT: mail, server

Sets the *timeout* between two successive read or write operations on client or proxied server connections. If no data is transmitted within this time, the connection is closed.

xclient

SYNTAX: **xclient** on | off;
DEFAULT on
CONTEXT: mail. server

Enables or disables the passing of the XCLIENT command with client parameters when connecting to the SMTP backend.

With XCLIENT, the MTA is able to write client information to the log and apply various limitations based on this data.

If XCLIENT is enabled then nginx passes the following commands when connecting to the backend:

- EHLO with the server name
- XCLIENT
- EHLO or HELO, as passed by the client

If the name found by the client IP address points to the same address, it is passed in the NAME parameter of the XCLIENT command. If the name could not be found, points to a different address, or resolver is not specified, the [UNAVAILABLE] is passed in the NAME parameter. If an error has occurred in the process of resolving, the [TEMPUNAVAIL] value is used.

If XCLIENT is disabled then nginx passes the EHLO command with the server name when connecting to the backend if the client has passed EHLO, or HELO with the server name, otherwise.

Nginx, Inc. p.468 of 506

4.4 Module ngx_mail_realip_module

4.4.1	Summary	39
4.4.2	Example Configuration	39
4.4.3	Directives	39
	set_real_ip_from	39

4.4.1 Summary

The ngx_mail_realip_module module is used to change the client address and port to the ones sent in the PROXY protocol header (1.19.8). The PROXY protocol must be previously enabled by setting the proxy_protocol parameter in the listen directive.

4.4.2 Example Configuration

```
listen 110 proxy_protocol;
set_real_ip_from 192.168.1.0/24;
set_real_ip_from 192.168.2.1;
set_real_ip_from 2001:0db8::/32;
```

4.4.3 Directives

$set_real_ip_from$

```
SYNTAX: set_real_ip_from address | CIDR | unix:;

DEFAULT —

CONTEXT: mail, server
```

Defines trusted addresses that are known to send correct replacement addresses. If the special value unix: is specified, all UNIX-domain sockets will be trusted.

Nginx, Inc. p.469 of 506

4.5 Module ngx_mail_ssl_module

4.5.1	Summary
4.5.2	Example Configuration
4.5.3	Directives
	ssl
	ssl_certificate
	ssl_certificate_key
	ssl_ciphers
	ssl_client_certificate
	ssl_conf_command
	ssl_crl
	ssl_dhparam
	ssl_ecdh_curve
	ssl_password_file
	ssl_prefer_server_ciphers
	ssl_protocols
	ssl_session_cache
	ssl_session_ticket_key
	ssl_session_tickets
	ssl_session_timeout
	ssl_trusted_certificate
	ssl_verify_client
	ssl_verify_depth
	starttls
	DOME OF DESCRIPTION OF THE PROPERTY OF THE PRO

4.5.1 Summary

The ngx_mail_ssl_module module provides the necessary support for a mail proxy server to work with the SSL/TLS protocol.

This module is not built by default, it should be enabled with the --with-mail_ssl_module configuration parameter.

This module requires the OpenSSL library.

4.5.2 Example Configuration

To reduce the processor load, it is recommended to

- set the number of worker processes equal to the number of processors,
- enable the shared session cache,
- disable the built-in session cache,
- and possibly increase the session lifetime (by default, 5 minutes):

Nginx, Inc. p.470 of 506

4.5.3 Directives

ssl

```
SYNTAX: ssl on | off;
DEFAULT off
CONTEXT: mail. server
```

This directive was made obsolete in version 1.15.0. The ssl parameter of the listen directive should be used instead.

ssl_certificate

```
SYNTAX: ssl_certificate file;
DEFAULT —
CONTEXT: mail, server
```

Specifies a *file* with the certificate in the PEM format for the given server. If intermediate certificates should be specified in addition to a primary certificate, they should be specified in the same file in the following order: the primary certificate comes first, then the intermediate certificates. A secret key in the PEM format may be placed in the same file.

Since version 1.11.0, this directive can be specified multiple times to load certificates of different types, for example, RSA and ECDSA:

Nginx, Inc. p.471 of 506

Only OpenSSL 1.0.2 or higher supports separate certificate chains for different certificates. With older versions, only one certificate chain can be used.

The value data: certificate can be specified instead of the file (1.15.10), which loads a certificate without using intermediate files. Note that inappropriate use of this syntax may have its security implications, such as writing secret key data to error log.

ssl_certificate_key

SYNTAX: ssl_certificate_key file;

Default —

Context: mail, server

Specifies a *file* with the secret key in the PEM format for the given server. The value engine:name:id can be specified instead of the file (1.7.9), which loads a secret key with a specified id from the OpenSSL engine name.

The value data: key can be specified instead of the file (1.15.10), which loads a secret key without using intermediate files. Note that inappropriate use of this syntax may have its security implications, such as writing secret key data to error log.

ssl_ciphers

SYNTAX: **ssl_ciphers** ciphers;
DEFAULT HIGH:!aNULL:!MD5

Context: mail, server

Specifies the enabled ciphers. The ciphers are specified in the format understood by the OpenSSL library, for example:

```
ssl_ciphers ALL:!aNULL:!EXPORT56:RC4+RSA:+HIGH:+MEDIUM:+LOW:+SSLv2:+EXP;
```

The full list can be viewed using the "openssl ciphers" command.

The previous versions of nginx used different ciphers by default.

ssl_client_certificate

SYNTAX: ssl_client_certificate file;

Default —

Context: mail, server

This directive appeared in version 1.7.11.

Specifies a *file* with trusted CA certificates in the PEM format used to verify client certificates.

The list of certificates will be sent to clients. If this is not desired, the ssl_trusted_certificate directive can be used.

Nginx, Inc. p.472 of 506

ssl_conf_command

SYNTAX: ssl_conf_command command;

Default —

Context: mail, server

This directive appeared in version 1.19.4.

Sets arbitrary OpenSSL configuration commands.

The directive is supported when using OpenSSL 1.0.2 or higher.

Several ssl_conf_command directives can be specified on the same level:

```
ssl_conf_command Options PrioritizeChaCha;
ssl_conf_command Ciphersuites TLS_CHACHA20_POLY1305_SHA256;
```

These directives are inherited from the previous configuration level if and only if there are no ssl_conf_command directives defined on the current level.

Note that configuring OpenSSL directly might result in unexpected behavior.

ssl_crl

SYNTAX: ssl_crl file;

Default —

Context: mail, server

This directive appeared in version 1.7.11.

Specifies a *file* with revoked certificates (CRL) in the PEM format used to verify client certificates.

ssl_dhparam

SYNTAX: ssl_dhparam file;

Default —

Context: mail, server

This directive appeared in version 0.7.2.

Specifies a *file* with DH parameters for DHE ciphers.

By default no parameters are set, and therefore DHE ciphers will not be used.

Prior to version 1.11.0, builtin parameters were used by default.

ssl_ecdh_curve

SYNTAX: ssl_ecdh_curve curve;

DEFAULT auto
CONTEXT: mail, server

Nginx, Inc. p.473 of 506

This directive appeared in versions 1.1.0 and 1.0.6.

Specifies a *curve* for ECDHE ciphers.

When using OpenSSL 1.0.2 or higher, it is possible to specify multiple curves (1.11.0), for example:

```
ssl_ecdh_curve prime256v1:secp384r1;
```

The special value auto (1.11.0) instructs nginx to use a list built into the OpenSSL library when using OpenSSL 1.0.2 or higher, or prime256v1 with older versions.

Prior to version 1.11.0, the prime256v1 curve was used by default.

When using OpenSSL 1.0.2 or higher, this directive sets the list of curves supported by the server. Thus, in order for ECDSA certificates to work, it is important to include the curves used in the certificates.

ssl_password_file

```
SYNTAX: ssl_password_file file;

DEFAULT —

CONTEXT: mail, server

This directive appeared in version 1.7.3.
```

Specifies a *file* with passphrases for secret keys where each passphrase is specified on a separate line. Passphrases are tried in turn when loading the key.

Example:

```
mail {
    ssl_password_file /etc/keys/global.pass;
    ...

    server {
        server_name mail1.example.com;
        ssl_certificate_key /etc/keys/first.key;
    }

    server {
        server_name mail2.example.com;

        # named pipe can also be used instead of a file ssl_password_file /etc/keys/fifo;
        ssl_certificate_key /etc/keys/second.key;
    }
}
```

ssl_prefer_server_ciphers

```
SYNTAX: ssl_prefer_server_ciphers on | off;
Default off
Context: mail, server
```

Nginx, Inc. p.474 of 506

Specifies that server ciphers should be preferred over client ciphers when the SSLv3 and TLS protocols are used.

$ssl_protocols$

```
SYNTAX: ssl_protocols [SSLv2] [SSLv3] [TLSv1.1] [TLSv1.1] [TLSv1.2] [TLSv1.3];
```

DEFAULT TLSv1 TLSv1.1 TLSv1.2

Context: mail, server

Enables the specified protocols.

The TLSv1.1 and TLSv1.2 parameters (1.1.13, 1.0.12) work only when OpenSSL 1.0.1 or higher is used.

The TLSv1.3 parameter (1.13.0) works only when OpenSSL 1.1.1 built with TLSv1.3 support is used.

ssl_session_cache

```
{\tt SYNTAX:} \quad \textbf{ssl\_session\_cache} \ {\tt off} \ | \ {\tt none} \ | \ [{\tt builtin}[:size]]
```

[shared:name:size];

Default none

Context: mail, server

Sets the types and sizes of caches that store session parameters. A cache can be of any of the following types:

off

the use of a session cache is strictly prohibited: nginx explicitly tells a client that sessions may not be reused.

none

the use of a session cache is gently disallowed: nginx tells a client that sessions may be reused, but does not actually store session parameters in the cache.

```
builtin
```

a cache built in OpenSSL; used by one worker process only. The cache size is specified in sessions. If size is not given, it is equal to 20480 sessions. Use of the built-in cache can cause memory fragmentation.

shared

a cache shared between all worker processes. The cache size is specified in bytes; one megabyte can store about 4000 sessions. Each shared cache should have an arbitrary name. A cache with the same name can be used in several servers.

Both cache types can be used simultaneously, for example:

```
ssl_session_cache builtin:1000 shared:SSL:10m;
```

Nginx, Inc. p.475 of 506

but using only shared cache without the built-in cache should be more efficient.

ssl_session_ticket_key

```
SYNTAX: ssl_session_ticket_key file;

DEFAULT —

CONTEXT: mail, server

This directive appeared in version 1.5.7.
```

Sets a *file* with the secret key used to encrypt and decrypt TLS session tickets. The directive is necessary if the same key has to be shared between multiple servers. By default, a randomly generated key is used.

If several keys are specified, only the first key is used to encrypt TLS session tickets. This allows configuring key rotation, for example:

```
ssl_session_ticket_key current.key;
ssl_session_ticket_key previous.key;
```

The *file* must contain 80 or 48 bytes of random data and can be created using the following command:

```
openssl rand 80 > ticket.key
```

Depending on the file size either AES256 (for 80-byte keys, 1.11.8) or AES128 (for 48-byte keys) is used for encryption.

ssl_session_tickets

```
SYNTAX: ssl_session_tickets on | off;
Default on
Context: mail, server
This directive appeared in version 1.5.9.
```

Enables or disables session resumption through TLS session tickets.

ssl_session_timeout

```
SYNTAX: ssl_session_timeout time;
DEFAULT 5m
CONTEXT: mail, server
```

Specifies a time during which a client may reuse the session parameters.

ssl_trusted_certificate

```
SYNTAX: ssl_trusted_certificate file;

DEFAULT —

CONTEXT: mail, server

This directive appeared in version 1.7.11.
```

Nginx, Inc. p.476 of 506

Specifies a *file* with trusted CA certificates in the PEM format used to verify client certificates.

In contrast to the certificate set by ssl_client_certificate, the list of these certificates will not be sent to clients.

ssl_verify_client

```
SYNTAX: ssl_verify_client on | off | optional | optional_no_ca;
DEFAULT off
CONTEXT: mail, server
This directive appeared in version 1.7.11.
```

Enables verification of client certificates. The verification result is passed in the Auth-SSL-Verify header of the authentication request.

The optional parameter requests the client certificate and verifies it if the certificate is present.

The optional_no_ca parameter requests the client certificate but does not require it to be signed by a trusted CA certificate. This is intended for the use in cases when a service that is external to nginx performs the actual certificate verification. The contents of the certificate is accessible through requests sent to the authentication server.

ssl_verify_depth

```
SYNTAX: ssl_verify_depth number;

DEFAULT 1

CONTEXT: mail, server

This directive appeared in version 1.7.11.
```

Sets the verification depth in the client certificates chain.

starttls

```
SYNTAX: starttls on | off | only;
DEFAULT off
CONTEXT: mail, server

on
allow usage of the STLS command for the POP3 and the STARTTLS command for the IMAP and SMTP;
off
deny usage of the STLS and STARTTLS commands;
only
require preliminary TLS transition.
```

Nginx, Inc. p.477 of 506

4.6 Module ngx_mail_imap_module

4.6.1	Directives												478
	imap_auth												478
	imap_capabilities												478
	imap_client_buffer												478

4.6.1 Directives

$imap_auth$

```
SYNTAX: imap_auth method ...;

DEFAULT plain

CONTEXT: mail, server
```

Sets permitted methods of authentication for IMAP clients. Supported methods are:

```
login
    AUTH=LOGIN

plain
    AUTH=PLAIN

cram-md5
    AUTH=CRAM-MD5. In order for this method to work, the password must be stored unencrypted.
external
```

imap_capabilities

```
SYNTAX: imap_capabilities extension ...;
DEFAULT IMAP4 IMAP4rev1 UIDPLUS
CONTEXT: mail, server
```

AUTH=EXTERNAL (1.11.6).

Sets the IMAP protocol extensions list that is passed to the client in response to the CAPABILITY command. The authentication methods specified in the imap_auth directive and STARTTLS are automatically added to this list depending on the starttls directive value.

It makes sense to specify the extensions supported by the IMAP backends to which the clients are proxied (if these extensions are related to commands used after the authentication, when nginx transparently proxies a client connection to the backend).

The current list of standardized extensions is published at www.iana.org.

imap_client_buffer

```
SYNTAX: imap_client_buffer size;
DEFAULT 4k | 8k
CONTEXT: mail. server
```

Nginx, Inc. p.478 of 506

Sets the size of the buffer used for reading IMAP commands. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

Nginx, Inc. p.479 of 506

4.7 Module ngx_mail_pop3_module

4.7.1	Directives												480
	pop3_auth												480
	pop3_capabilities								_			_	480

4.7.1 Directives

pop3_auth

```
SYNTAX: pop3_auth method ...;

DEFAULT plain

CONTEXT: mail, server
```

Sets permitted methods of authentication for POP3 clients. Supported methods are:

```
plain
```

USER/PASS, AUTH PLAIN, AUTH LOGIN. It is not possible to disable these methods.

apop

APOP. In order for this method to work, the password must be stored unencrypted.

cram-md5

AUTH CRAM-MD5. In order for this method to work, the password must be stored unencrypted.

external

AUTH EXTERNAL (1.11.6).

pop3_capabilities

```
SYNTAX: pop3_capabilities extension ...;
DEFAULT TOP USER UIDL
CONTEXT: mail. server
```

Sets the POP3 protocol extensions list that is passed to the client in response to the CAPA command. The authentication methods specified in the pop3_auth directive (SASL extension) and STLS are automatically added to this list depending on the starttls directive value.

It makes sense to specify the extensions supported by the POP3 backends to which the clients are proxied (if these extensions are related to commands used after the authentication, when nginx transparently proxies the client connection to the backend).

The current list of standardized extensions is published at www.iana.org.

Nginx, Inc. p.480 of 506

4.8 Module ngx_mail_smtp_module

4.8.1	Directives											481
	smtp_auth											481
	smtp_capabilities .											481
	$smtp_client_buffer$.											482
	smtp_greeting_delay											482

4.8.1 Directives

smtp_auth

```
SYNTAX: smtp_auth method ...;
DEFAULT login plain
CONTEXT: mail, server
```

Sets permitted methods of SASL authentication for SMTP clients. Supported methods are:

```
login
AUTH LOGIN
plain
AUTH PLAIN
cram-md5
```

AUTH CRAM-MD5. In order for this method to work, the password must be stored unencrypted.

```
external
```

```
AUTH EXTERNAL (1.11.6).
```

none

Authentication is not required.

$smtp_capabilities$

```
SYNTAX: smtp_capabilities extension ...;

DEFAULT —

CONTEXT: mail, server
```

Sets the SMTP protocol extensions list that is passed to the client in response to the EHLO command. The authentication methods specified in the smtp_auth directive and STARTTLS are automatically added to this list depending on the starttls directive value.

It makes sense to specify the extensions supported by the MTA to which the clients are proxied (if these extensions are related to commands used after the authentication, when nginx transparently proxies the client connection to the backend).

The current list of standardized extensions is published at www.iana.org.

Nginx, Inc. p.481 of 506

$smtp_client_buffer$

SYNTAX: smtp_client_buffer size;

Default 4k | 8k Context: mail, server

Sets the size of the buffer used for reading SMTP commands. By default, the buffer size is equal to one memory page. This is either 4K or 8K, depending on a platform.

smtp_greeting_delay

SYNTAX: smtp_greeting_delay time;

Default 0

Context: mail, server

Allows setting a delay before sending an SMTP greeting in order to reject clients who fail to wait for the greeting before sending SMTP commands.

Nginx, Inc. p.482 of 506

Chapter 5

Miscellaneous

5.1		Command	-line	paramet	ters
-----	--	---------	-------	---------	------

-		1																	10	0
ŀ	١.		()	verv	WOI														4×	.: 3

5.1.1 Overview

nginx supports the following command-line parameters:

- -? | -h print help for command-line parameters.
- -c file use an alternative configuration file instead of a default file.
- -e file use an alternative error log file to store the log instead of a default file (1.19.5). The special value stderr selects the standard error file.
- -g directives set global configuration directives, for example,

 nginx -g "pid /var/run/nginx.pid; worker_processes 'sysctl -n hw.ncpu';"

```
inglik g plu /val/luii/inglik.plu, wolkel_plocesses Systel ii iiw.iicpu ,
```

- -p prefix set nginx path prefix, i.e. a directory that will keep server files (default value is /usr/local/nginx).
- -q suppress non-error messages during configuration testing.
- -s signal send a signal to the master process. The argument signal can be one of:
 - stop shut down quickly
 - quit shut down gracefully
 - reload reload configuration, start the new worker process with a new configuration, gracefully shut down old worker processes.
 - reopen reopen log files
- -t test the configuration file: nginx checks the configuration for correct syntax, and then tries to open files referred in the configuration.

- -T same as -t, but additionally dump configuration files to standard output (1.9.2).
- $\bullet\,$ –v print nginx version.
- $\bullet\,$ –V print nginx version, compiler version, and configure parameters.

Nginx, Inc. p.484 of 506

Appendix A

Changelog for NGINX Plus

This appendix contains the most important changes that may apply to both NGINX Plus and nginx/OSS. Full changelog for nginx/OSS is available in the packages and by the following link: https://nginx.org/en/CHANGES

- NGINX Plus R24 (1.19.10), released Apr 27, 2021
 - Added support for JSON Web Encryption to the JSON Web Token authorization module (the auth_jwt_type directive).
 - Health checks: introduced the persistent parameter of the health_check directive that enables persistence to mandatory health checks after reload.
 - Flags in the proxy_cookie_flags directive can now contain variables.
 - Added PROXY protocol support for mail (the proxy_protocol parameter of the listen directive, the proxy_protocol and set_real_ip_from directives).
 - If free worker connections are exhausted, NGINX Plus starts closing not only keepalive connections, but also connections in lingering close.
 - The maximum duration of a persistent connection can be limited with the keepalive_time directive for http and upstream servers.
 - New variable, \$connection_time, contains connection time.
- NGINX Plus R23 (1.19.5), released Dec 8, 2020
 - gRPC health checks: introduced the type=grpc parameter in the health_check directive that enables active health checks of gRPC upstream servers.
 - Sticky cookie now can accept the SameSite attribute with Strict, Lax,or None values.
 - Support for cookie flags with the proxy_cookie_flags and userid_flags directives.
 - Introduced script that performs unprivileged installation of NGINX Plus.
 - New command-line switch to redefine an error log file: -e.
 - New set directive for stream that allows setting a value for a variable.
 - Added support for arbitrary OpenSSL configuration commands with the ssl_conf_command directive.
 - The ssl_reject_handshake directive that allows rejecting the SSL handshake in the server block.
 - Support for user authentication on the SMTP backend in mail proxy.
 - Cache manager improved to monitor the minimum amount of free space (see the min_free parameter of the proxy_cache_path directive).
- NGINX Plus R22 (1.19.0), released Jun 9, 2020

- Client certificate validation with OCSP.
- Unauthorized requests can now be delayed with the auth_delay directive.
- Updated status dashboard with new visualizations of limit_conn and limit_req statistics.
- NGINX Plus R21 (1.17.9), released Apr 7, 2020
 - The grpc_pass directive can now contain variables.
- NGINX Plus R20 (1.17.6), released Dec 3, 2019
 - Key-value storage: added support for matching a key based on a substring (the type parameter of the keyval_zone directive was extended with the prefix option).
 - DNS resolvers can now be specified in upstream context.
 - Rate limiting: the \$limit_req_status variable keeps the result of limiting a
 request processing rate. Corresponding metrics are available through the
 /http/limit_reqs/ endpoint in the API module.
 - The connection limiting facility now has dry run mode. The \$limit_conn_status variable keeps the result of limiting a number of connections. Correponding metrics are available through the /http/limit_conns/ endpoint in the API module.
 - Additional variables were introduced to keep original IP address and port of the server that a client originally connected to when PROXY protocol was used: \$proxy_protocol_server_addr, \$proxy_protocol_server_port.
- NGINX Plus R19 (1.17.3), released Sep 3, 2019
 - Metrics provided by the status_zone directive can now be collected per location.
 - A set of metrics related to DNS resolver functionality is now available (the status_zone parameter of the resolver directive).
 - The request limiting facility now has dry run mode.
 - Key-value storage now has optimized mode for storing IP addresses in CIDR notation (the type parameter of the keyval_zone directive).
 - Each key-value pair can now have its own custom expiration timer, either set at creation time for new entry, or modified for existing entry.
 - The limit_rate and limit_rate_after directives can now contain variables.
 - The proxy_download_rate and proxy_upload_rate directives can now contain variables.
 - Updated status dashboard with new visualizations for per-location statistic, resolver metrics, and zone sync status.
- NGINX Plus R18 (1.15.10), released Apr 9, 2019
 - Added support for dynamic SSL certificate loading, either from file or from key-value storage (variable should be prefixed with data: for the latter case).
 - Active health checks extended with additional logic of verifying arbitrary variables (the require parameter of the match directive).
 - Clustering enhancement: a single zone sync configuration can now be used for all instances in a cluster with the help of wildcard support in the listen directive.
 - Port ranges can now be used in the listen directive.
 - Stream proxy: added an ability to explicitly close existing connections to the
 particular upstream server after it was removed from the group due to health
 check failure, API call, or re-resolve action (the proxy_session_drop directive).

Nginx, Inc. p.486 of 506

New variable, \$upstream_bytes_sent, contains number of bytes sent to an upstream server.

• NGINX Plus R17 (1.15.7), released Dec 11, 2018

- Added support for TLS v1.3 early data. Check out the \$ssl_early_data variable which can be used to protect against replay attacks at the application layer.
- Introduced two-stage rate limiting (the delay parameter of the limit_req directive).
- Added support for retrieving JSON Web Key (JWK) set from a subrequest.
- Added support for the Ed25519 and Ed448 cryptographic algorithms to the JSON Web Token authorization module.
- Added an option to enable TCP keepalives for outgoing connections to proxied servers (the proxy_socket_keepalive and friends).
- Fine-grained control over persistent connections to upstreams with the keepalive_timeout and keepalive_requests directives.
- Added ability to restrict UDP session to a particular number of packets with the proxy_requests directive.

• NGINX Plus R16 (1.15.2), released Sep 5, 2018

- IMPORTANT: status and upstream_conf modules deprecated since R13 were finally removed in favor to the API module.
- Shared zones synchronization extended to support keyval and limit_req modules.
- Key-value pairs can now be expired after configured timeout (the timeout parameter of the keyval_zone directive).
- Introduced new load balancing algorithm: random with two choices (optional).
- UDP load balancing extended to support multiple incoming datagrams from a client within a single session, thus allowing to proxy/load balance of more complex applications.
- Added support for PROXY protocol version 2 in HTTP and stream modules.
- New variable, \$ssl_preread_protocol, of stream module contains the highest SSL protocol version supported by the client.

• NGINX Plus R15 (1.13.10), released Apr 10, 2018

- Added gRPC proxy support.
- Added HTTP/2 push support.
- Introduced shared zone synchronization between NGINX Plus nodes.
 Currently, it is possible to synchronize sticky sessions when using learn method.
- Added an ability to completely disable any escaping in access log (the escape=none parameter of the log_format directive).
- It is no longer required to run nginx under superuser when using the proxy_bind directive with transparent parameter on Linux, as worker processes now inherit the CAP_NET_RAW capability from the master process.
- Added the auth_jwt_leeway directive used to configure a leeway to account for clock skew when verifying exp and nbf claims, as per RFC 7519.
- Stream SSL pre-read module now can extract list of protocols advertised by the client through ALPN (the \$ssl_preread_alpn_protocols variable).
- New variable, \$upstream_queue_time, contains time the request spent in the upstream queue.

Nginx, Inc. p.487 of 506

• NGINX Plus R14 (1.13.7), released Dec 12, 2017

- Added refactored status dashboard v2 (dashboard.html in packages) that uses recently introduced API subsystem instead of older status and upstream_conf interfaces. Previous dashboard v1 is still available (status.html in packages). Please note that older status and upstream_conf interfaces, as well as dashboard v1, are going to be removed in NGINX Plus R16.
- Dynamic key-value pairs support added to the stream proxy. API version has changed to 2 (see the "Compatibility" section for details).
- The auth_jwt_header_set and auth_jwt_claim_set directives can now handle multiple values, providing complex JWT claims support.
- Additional cryptographic algorithms were introduced in the JSON Web Token authorization module.
- Upstream servers configured with the resolve parameter are now being pre-resolved on configuration reload.
- The drain parameter of the server directive can now be specified in configuration.
- New variable: \$ssl_client_escaped_cert.
- Swagger UI was adjusted to support custom ports in URLs.

• NGINX Plus R13 (1.13.4), released Aug 29, 2017

- Introduced new API for accessing various status information, configuring upstream server groups on-the-fly, and managing key-value pairs. Swagger specification and UI is bundled in the nginx-plus packages for easy try-out.
- Introduced new module that creates variables based on key-value pairs, dynamically managed by the new API.
- Introduced new module for mirroring requests by creating background mirror subrequests and ignoring their responses.
- Added support for HTTP trailers.
- New worker_shutdown_timeout directive allows configuring a timeout for graceful shutdown of worker processes.
- Sticky cookie with expires parameter now also includes the max-age attribute defined in RFC 6265.
- Sticky learn session affinity mechanism extended with the header parameter used to indicate that a session should be created immediately after receiving response headers from upstream server.
- The proxy_next_upstream directive extended with the new http_429 parameter ("Too Many Requests").
- $-\,$ Added the ability to specify network buffer sizes in stream and mail modules.
- SSL renegotiation is now allowed on backend connections.
- Added initial support for TLS 1.3.

• NGINX Plus R12 (1.11.10), released Mar 14, 2017

- Status module dataset updated with nginx build name (nginx_build), shared zones usage statistics (the slabs/ subtree), and additional upstream fields (name, service).
- Status dashboard now shows NGINX Plus version, response time metrics, shared zones memory usage, and server names in upstreams.
- Added support for the stale-while-revalidate and stale-if-error Cache-Control extensions, as defined by RFC 5861.
- Introduced flexible control of caching byte-range responses (the proxy_cache_max_range_offset directive).

Nginx, Inc. p.488 of 506

- Cache header Vary and ETag lenghts increased to 128 bytes. Note that the on-disk cache format has changed, so cached content will be invalidated after the upgrade.
- Introduced the mandatory parameter in the health_check directive, requiring all new servers to pass the associated health check before accepting real traffic.
- UDP health checks now may be configured without specifying match block.
- Stream module now supports client SSL certificates verification.
- Added a number of SSL variables representing various details about client certificates and capabilities (\$ssl_client_v_end, \$ssl_client_v_start, \$ssl_client_v_remain, \$ssl_curves, \$ssl_ciphers).
 The \$ssl_client_verify variable was extended to include a reason of failure.
- The \$ssl_client_i_dn and \$ssl_client_s_dn variables are now compliant with RFC 2253; legacy variants are available as \$ssl_client_i_dn_legacy and \$ssl_client_s_dn_legacy, accordingly.
- Support for accessing arbitrary JWT fields as variables.
- Added support for JSON escaping in access logs (the escape parameter of the log_format directive).
- WebP support added to the image filter module.
- Duplicate configuration parts excluded from nginx -T output.
- Various improvements in memory usage and performance, including upstream queue optimization.

• NGINX Plus R11 (1.11.5), released Oct 25, 2016

- Introduced dynamic modules binary compatibility between NGINX Plus and corresponding version of nginx/OSS.
- Stream module enhancements (custom logging with a number of additional variables, PROXY protocol support for incoming connections, support for obtaining real IP address and port from PROXY protocol header, ability to extract server name from SNI to a variable for various purposes, e.g. custom routing).
- Status module dataset updated with additional stream metrics (sessions, discarded).
- Cache manager improved to support iterative operations mode when deleting old cache files, reducing the disk load (see the manager_files, manager_threshold, and manager_sleep parameters of the proxy_cache_path directive).
- Added support for using variables in the domain parameter of the sticky directive.
- New variable: \$upstream_bytes_received.

• NGINX Plus R10 (1.11.3), released Aug 23, 2016

- New dynamic module: ModSecurity (package name is nginx-plus-module-modsecurity). This is the early release candidate of ModSecurity 3.0.
- New dynamic module: nginScript (package name is nginx-plus-module-njs).
- Support for client authorization using the JSON Web Token (JWT).
- Stream module enhancements (embedded variables, resolver support, map module, geo and geoip modules, A/B testing support).
- Support for multiple SSL certificate types per SSL server or SNI name (e.g., RSA and ECDSA).
- Transparent proxy mode support (the transparent parameter of the proxy_bind directive).

Nginx, Inc. p.489 of 506

- Support for the IP_BIND_ADDRESS_NO_PORT socket option where available, allowing for many more upstream connections.
- HTTP/2 improvements: unbuffered upload support, general bugfixes.
- New variables: \$request_id, \$proxy_protocol_port, \$realip_remote_port.
- Lua module updated to version 0.10.6 (nginx-plus-extras, nginx-plus-module-lua).
- Passenger module updated to version 5.0.30 (nginx-plus-extras, nginx-plus-module-passenger).
- headers-more module updated to version 0.31 (nginx-plus-extras, nginx-plus-module-headers-more).
- set-misc module updated to version 0.31 (nginx-plus-extras, nginx-plus-module-headers-more).

NGINX Plus R10 will be the last release to provide the NGINX Plus Extras package. Users should migrate to the NGINX Plus package and use the equivalent dynamic modules.

- NGINX Plus R9 (1.9.13), released Apr 12, 2016
 - Introduced a number of standalone packages with dynamic modules for NGINX Plus (both official and third-party). Packages with official modules:

```
* nginx-plus-module-geoip (doc)
```

- * nginx-plus-module-image-filter (doc)
- * nginx-plus-module-perl (doc)
- * nginx-plus-module-xslt (doc)

Packages with third-party modules:

- * nginx-plus-module-headers-more (site)
- * nginx-plus-module-lua (site)
- * nginx-plus-module-passenger (site)
- * nginx-plus-module-rtmp (site)
- * nginx-plus-module-set-misc (site)
- UDP proxy support added to the stream module.
- Added support for retrieving upstream servers configuration via DNS SRV records (the service parameter of the server directive).
- Resolver: added support for TCP fallback on retrieving large DNS responses.
- Change: requests with non-idempotent method (POST, LOCK, PATCH) are not passed to the next server in upstream group if a request has already been sent to an upstream server. Enabling the non_idempotent option in the proxy_next_upstream directive explicitly allows retrying such requests.
- Cache: improved meta-data accounting.
- Automatic binding of worker processes to available CPUs (the autoparameter of the worker_cpu_affinity directive).
- Some write operations can now be offloaded to thread pools.
- Added support for customizing the Server response header field, as well as the signature in standard error messages.
- Lua module updated to version 0.10.2 (nginx-plus-extras, nginx-plus-module-lua).
- Passenger module updated to version 5.0.26 (nginx-plus-extras, nginx-plus-module-passenger).
- headers-more module updated to version 0.29 (nginx-plus-extras, nginx-plus-module-headers-more).
- Updated status dashboard.

Nginx, Inc. p.490 of 506

- NGINX Plus R8 (1.9.9), released Dec 29, 2015
 - HTTP/2 support is now included into the nginx-plus and nginx-plus-extras packages. The nginx-plus-http2 and nginx-plus-lua packages are deprecated.
 - Caching improvements, including support of caching HEAD requests and more effective caching of big responses with the slice module.
 - Dynamically configured upstream groups now can be configured to keep states between reloads.
 - Support for arbitrary port in health check requests (the port parameter of the health_check directive).
 - Enhancement in the real IP module: the \$realip_remote_addr variable.
 - Enhancement in syslog logging: the nohostname parameter.
 - Lua module updated to version 0.9.20 (nginx-plus-extras).
 - The lua-resty-redis Lua module updated to version 0.21 (nginx-plus-extras).
 - Passenger module updated to version 5.0.22 (nginx-plus-extras).
 - headers-more module updated to version 0.28 (nginx-plus-extras).
 - Updated status dashboard.

• NGINX Plus R7 (1.9.4), released Sep 15, 2015

- Introduced separate family of nginx-plus-http2 packages with HTTP/2 support included in favor of SPDY. General nginx-plus packages still have SPDY support. Please refer to the listen directive documentation for the instructions on how to enable HTTP/2.
- TCP proxy enhancements (access control; connection limiting; upload and download bandwidth control; client-side PROXY protocol support; ability to choose local IP address for outgoing connections; the backlog parameter of the listen directive; the tcp_nodelay directive).
- More efficient connections distribution between worker processes (the reuseport parameter of the listen directive).
- Introduced thread pools used for multi-threaded reading and sending files without blocking worker processes.
- Enhanced support for modifying HTTP responses (multiple substitutions support, variables support in search strings).
- A number of additional metrics in the new version (6) of the status dataset (SSL handshakes and upstream queue overflows in particular).
- Updated status dashboard.
- Additional arguments to playlists in the HLS module (start, end and offset).
- Support for proxying requests with NTLM authentication.
- New command-line switch to dump configuration to standard output: -T.
- Added lua-resty-redis Lua module (nginx-plus-extras).
- Lua module updated to version 0.9.16 (nginx-plus-lua, nginx-plus-extras).
- Passenger module updated to version 5.0.15 (nginx-plus-extras).
- headers-more module updated to version 0.26 (nginx-plus-extras).
- set-misc module updated to version 0.29 (nginx-plus-extras).

• NGINX Plus R6 (1.7.11), released Apr 14, 2015

Nginx, Inc. p.491 of 506

- TCP proxy enhancements (health checks, dynamic reconfiguration, SSL support, logging, status counters).
- New least_time load balancing method.
- Unbuffered upload support (proxy_request_buffering and friends).
- Proxy SSL authentication support for http and uwsgi.
- Proxy cache enhancements (variables support in proxy_cache, use_temp_path parameter in proxy_cache_path).
- Client SSL certificates support in mail proxy.
- Autoindex module enhancement (the autoindex_format directive).
- New status dashboard.
- Lua module updated to version 0.9.16rc1 (nginx-plus-lua, nginx-plus-extras).
- Passenger module updated to version 4.0.59 (nginx-plus-extras).
- set-misc module updated to version 0.28 (nginx-plus-extras).

• NGINX Plus R5 (1.7.7), released Dec 1, 2014

- New TCP proxying and load balancing mode (the stream module).
- Sticky session timeout now applies from the most recent request in the session.
- Upstream "draining" can be used to remove an upstream server without interrupting any user sessions (the drain command of the upstream_conf dynamic configuration interface).
- Improved control over request retries in the event of failure, based on number of tries and time. Also available for fastcgi, uwsgi, scgi and memcached modules.
- Caching: the Vary response header is correctly handled (multiple variants of the same resource can be cached). Note that the on-disk cache format has changed, so cached content will be invalidated after the upgrade.
- Caching: improved support for byte-range requests.
- Ability to control upstream bandwidth with the proxy_limit_rate directive.
- Lua module updated to version 0.9.13 (nginx-plus-lua, nginx-plus-extras).
- Passenger module updated to version 4.0.53 (nginx-plus-extras).

• NGINX Plus R4 (1.7.3), released Jul 22, 2014

- MP4 module now supports the end query argument which sets the end point of playback.
- Added the ability to verify backend SSL certificates.
- Added support for SNI while working with SSL backends.
- Added conditional logging for requests (the if parameter of the access_log directive).
- New load balancing method based on user-defined keys with optional consistency.
- Cache revalidation now uses If-None-Match header if possible.
- Passphrases for SSL private keys can now be stored in an external file.
- Introduced a new session affinity mechanism (sticky learn) based on server-initiated sessions.
- Added the ability to retrieve a subset of the extended status data.
- Lua module updated to version 0.9.10 (nginx-plus-lua, nginx-plus-extras).

Nginx, Inc. p.492 of 506

- Passenger module updated to version 4.0.45 (nginx-plus-extras).
- NGINX Plus R3 (1.5.12), released Apr 2, 2014
 - SPDY protocol updated to version 3.1. SPDY/2 is no longer supported.
 - Added PROXY protocol support (the proxy_protocol parameter of the listen directive).
 - IPv6 support added to resolver.
 - DNS names in upstream groups are periodically re-resolved (the resolve parameter of the server directive).
 - Introduced limiting connections to upstream servers (the max_conns parameter) with optional support for connections queue.
- NGINX Plus R2 (1.5.7), released Dec 12, 2013
 - Enhanced sticky routing support.
 - Additional status metrics for virtual hosts and cache zones.
 - Cache purge support (also available for FastCGI).
 - Added support for cache revalidation.
 - New module: ngx_http_auth_request_module (authorization based on the result of a subrequest).
- NGINX Plus R1 (1.5.3), released Aug 12, 2013
 - Enhanced status monitoring.
 - Load balancing: slow start feature.
 - Added syslog support for both error_log and access_log.
 - Support for Apple HTTP Live Streaming.
- NGINX Plus 1.5.0-2, released May 27, 2013
 - Added support for active health checks.
- NGINX Plus 1.5.0, released May 7, 2013
 - Security: fixed CVE-2013-2028.
- NGINX Plus 1.3.16, released Apr 19, 2013
 - Added SPDY support.
- NGINX Plus 1.3.13, released Feb 22, 2013
 - Added sticky sessions support.
 - Added support for proxying WebSocket connections.
- NGINX Plus 1.3.11, released Jan 18, 2013
 - Added base module ngx_http_gunzip_module.
 - New extra module: ngx_http_f4f_module (Adobe HDS Dynamic Streaming).
 - New extra module: ngx_http_session_log_module (aggregated session logging).
- NGINX Plus 1.3.9-2, released Dec 20, 2012
 - License information updated.
 - End-User License Agreement added to the package.
- NGINX Plus 1.3.9, released Nov 27, 2012
 - Added dynamic upstream management feature.
 - PDF documentation bundled into package.
- NGINX Plus 1.3.7, released Oct 18, 2012
 - Initial release of NGINX Plus package.

Nginx, Inc. p.493 of 506

Appendix B

Legal Notices

Open source components included in the NGINX Plus (package name is nginx-plus) are:

• nginx/OSS (1.19.9), distributed under 2-clause BSD license. https://nginx.org/

Copyright © 2002-2021 Igor Sysoev

Copyright © 2011-2021 Nginx, Inc.

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

 Internal MD5 implementation (used only if no system MD5 support was found), based on Alexander Peslyak's public domain implementation:

This is an OpenSSL-compatible implementation of the RSA Data Security, Inc. MD5 Message-Digest Algorithm (RFC 1321).

Homepage:

http://openwall.info/wiki/people/solar/software/public-domain-source-code/md5

Author: Alexander Peslyak, better known as Solar Designer <solar at openwall.com>

This software was written by Alexander Peslyak in 2001. No copyright is claimed, and the software is hereby placed in the public domain. In case this attempt to disclaim copyright and place the software in the public domain is deemed null and void, then the software is Copyright © 2001 Alexander Peslyak and it is hereby released to the general public under the following terms:

- Redistribution and use in source and binary forms, with or without modification, are permitted.
- 2. There's ABSOLUTELY NO WARRANTY, express or implied.

(This is a heavily cut-down "BSD license".)

• MurmurHash algorithm (version 2), distributed under MIT license. https://sites.google.com/site/murmurhash/

Copyright © Austin Appleby

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Components used in status monitoring dashboard v2 only (dashboard.html in nginx-plus package) and distributed under MIT license:

• autoprefixer, a PostCSS plugin to parse CSS and add vendor prefixes to CSS rules (7.2.6).

https://github.com/postcss/autoprefixer

Copyright © 2013 Andrey Sitnik <andrey@sitnik.ru>

• babel-core, Babel compiler core (6.26.3).

https://github.com/babel/babel/tree/master/packages/babel-core

Copyright © 2014-present Sebastian McKenzie and other contributors

• babel-loader, allows transpiling JavaScript files using Babel and webpack (7.1.5). https://github.com/babel/babel-loader

Copyright © 2014-2019 Luís Couto < hello@luiscouto.pt>

• babel-plugin-transform-object-rest-spread, produces spec-compliant code by using Babel's objectSpread helper (6.26.0).

 $\label{lem:https://github.com/babel/babel/tree/master/packages/babel-plugin-transform-object-rest-spread$

• babel-plugin-transform-runtime, makes helpers reference the module babel-runtime to avoid duplication across your compiled output (6.23.0).

 ${\tt https://github.com/babel/babel/tree/master/packages/babel-plugin-transform-runtime}$

• babel-polyfill, provides polyfills necessary for a full ES2015+ environment (6.26.0). https://github.com/babel/babel/tree/master/packages/babel-polyfill Copyright © 2014-2017 Sebastian McKenzie <sebmck@gmail.com>

 css-loader, interprets @import and url() like import/require() and will resolve them (0.28.11).

https://github.com/webpack-contrib/css-loader

Copyright © JS Foundation and other contributors

Nginx, Inc. p.495 of 506

• cssnano, a modular minifier, built on top of the PostCSS ecosystem (3.10.0). https://github.com/cssnano/cssnano

Copyright © Ben Briggs

beneb.info@gmail.com>

• extract-text-webpack-plugin, a lightweight CSS extraction plugin (3.0.2). https://github.com/webpack-contrib/extract-text-webpack-plugin

Copyright © JS Foundation and other contributors

• history, manage session history with JavaScript (4.10.1).

https://github.com/ReactTraining/history

Copyright © React Training 2016-2018

• html-webpack-harddisk-plugin, writes html files to hard disk even when using the webpack dev server or middleware (0.1.0).

https://github.com/jantimon/html-webpack-harddisk-plugin

Copyright © 2016 Jan Nicklas

 html-webpack-inline-source-plugin, allows embedding javascript and css sources inline (0.0.9).

https://github.com/dustinjackson/html-webpack-inline-source-plugin

Copyright © 2016 Jan Nicklas

 html-webpack-plugin, simplifies creation of HTML files to serve your webpack bundles (2.30.1).

https://github.com/jantimon/html-webpack-plugin

Copyright © JS Foundation and other contributors

• postcss-import, PostCSS plugin to inline @import rules content (11.1.0). https://github.com/postcss/postcss-import

Copyright © 2014 Maxime Thirouin, Jason Campbell & Kevin Martensson

• postcss-inline-svg, PostCSS plugin to reference an SVG file and control its attributes with CSS syntax (3.1.1).

https://github.com/TrySound/postcss-inline-svg

Copyright © Bogdan Chadkin <trysound@yandex.ru>

• postcss-loader, PostCSS loader for webpack (2.1.6).

https://github.com/postcss/postcss-loader

Copyright © JS Foundation and other contributors

• postcss-svgo, a modular minifier, built on top of the PostCSS ecosystem (2.1.6). https://github.com/cssnano/cssnano

Copyright © Ben Briggs
 <beneb.info@gmail.com>

• postcss-url, PostCSS plugin to rebase url(), inline or copy asset (7.3.2).

https://github.com/postcss/postcss-url

Copyright © 2014 Maxime Thirouin

• preact, fast 3kb React alternative with the same ES6 API (8.5.3).

https://github.com/developit/preact

Copyright © 2015-present Jason Miller

• preact-compat, React compatibility layer for Preact (3.19.0).

https://github.com/preactjs/preact-compat

Copyright © 2016 Jason Miller

• style-loader, injects CSS into the DOM (0.18.2).

https://github.com/webpack-contrib/style-loader

Copyright © JS Foundation and other contributors

Nginx, Inc. p.496 of 506

- uglifyjs-webpack-plugin, UglifyJS Plugin (0.4.6). https://github.com/webpack-contrib/uglifyjs-webpack-plugin Copyright © JS Foundation and other contributors
- webpack, a bundler for javascript and friends (3.12.0). https://github.com/webpack/webpack Copyright © JS Foundation and other contributors
- whatwg-fetch, a window.fetch JavaScript polyfill (2.0.4). https://github.com/github/fetch Copyright © 2014-2016 GitHub, Inc.

The MIT License

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Components used in status monitoring dashboard v2 only (dashboard.html in nqinx-plus package) and distributed under 3-clause BSD license and Apache 2.0 license:

• babel-plugin-react-css-modules, transforms styleName to className using compile time CSS module resolution (3.4.2), distributed under 3-clause BSD license. https://github.com/gajus/babel-plugin-react-css-modules

Copyright © 2016, Gajus Kuizinas (http://gajus.com/) All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list
 of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the Gajus Kuizinas (http://gajus.com/) nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL ANUARY BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT

Nginx, Inc. p.497 of 506

LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

• npm-font-open-sans, Open Sans font family - incl. usage of CSS, SCSS, LESS (1.1.0), distributed under Apache 2.0 license.

https://github.com/dasrick/npm-font-open-sans

Copyright © Steve Matteson

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at: http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

The following component (Swagger UI) is distributed as a set of standalone files in the /usr/share/nginx/html/swagger-ui directory:

• Swagger UI (3.25.5), distributed under Apache 2.0 license.

https://github.com/swagger-api/swagger-ui

Copyright 2021 SmartBear Software

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

Optional add-on and third-party modules provided with NGINX Plus may include additional open-source components. The licenses for these components are included in the installation package for each module.

Nginx, Inc. p.498 of 506

Index

absolute_redirect, 21 accept_mutex, 7 accept_mutex_delay, 7 access_log, 200, 406 add_after_body, 61 add_before_body, 61 add_header, 173 add_trailer, 173 addition_types, 62 aio, 21 aio_write, 22 alias, 22 allow, 59, 391	charset_map, 123 charset_types, 124 chunked_transfer_encoding, 23 client_body_buffer_size, 24 client_body_in_file_only, 24 client_body_in_single_buffer, 24 client_body_temp_path, 24 client_body_timeout, 25 client_header_buffer_size, 25 client_header_timeout, 25 client_max_body_size, 25 connection_pool_size, 26 create_full_put_path, 125
ancient_browser, 121 ancient_browser_value, 121 api, 64 auth_basic, 110 auth_basic_user_file, 110 auth_delay, 23 auth_http, 463 auth_http_header, 463 auth_http_timeout, 463 auth_http_timeout, 463 auth_jwt, 113	daemon, 7 dav_access, 126 dav_methods, 126 debug_connection, 8 debug_points, 8 default_type, 26 deny, 59, 391 directio, 26 directio_alignment, 26 disable_symlinks, 27
auth_jwt_claim_set, 113 auth_jwt_header_set, 114 auth_jwt_key_file, 114 auth_jwt_key_request, 114 auth_jwt_leeway, 115 auth_jwt_type, 115 auth_request, 116 auth_request_set, 117	empty_gif, 128 env, 8 error_log, 9 error_page, 28 etag, 29 events, 10 expires, 174
autoindex, 118 autoindex_exact_size, 118 autoindex_format, 118 autoindex_localtime, 119 break, 257 charset, 122	f4f, 129 f4f_buffer_size, 129 fastcgi_bind, 131 fastcgi_buffer_size, 132 fastcgi_buffering, 132 fastcgi_buffers, 132 fastcgi_busy_buffers_size, 133

fastcgi_cache, 133	geo, 152, 392
$fastcgi_cache_background_update, 133$	geoip_city, 156, 395
fastcgi_cache_bypass, 133	geoip_country, 155, 394
fastcgi_cache_key, 134	geoip_org, 157, 396
fastcgi_cache_lock, 134	geoip_proxy, 157
fastcgi_cache_lock_age, 134	geoip_proxy_recursive, 157
fastcgi_cache_lock_timeout, 134	grpc_bind, 159
fastcgi_cache_max_range_offset, 135	grpc_buffer_size, 159
fastcgi_cache_methods, 135	grpc_connect_timeout, 159
fastcgi_cache_min_uses, 135	grpc_hide_header, 160
fastcgi_cache_path, 135	grpc_ignore_headers, 160
fastcgi_cache_purge, 137	grpc_intercept_errors, 160
fastcgi_cache_revalidate, 138	grpc_next_upstream, 160
fastcgi_cache_use_stale, 138	grpc_next_upstream_timeout, 161
fastcgi_cache_valid, 139	grpc_next_upstream_tries, 162
fastcgi_catch_stderr, 139	grpc_pass, 162
fastcgi_connect_timeout, 140	grpc_pass_header, 162
fastcgi_force_ranges, 140	grpc_read_timeout, 163
fastcgi_hide_header, 140	grpc_send_timeout, 163
fastcgi_ignore_client_abort, 140	grpc_set_header, 163
fastcgi_ignore_headers, 141	grpc_socket_keepalive, 163
fastcgi_index, 141	grpc_ssl_certificate, 164
fastcgi_intercept_errors, 141	grpc_ssl_certificate_key, 164
fastcgi_keep_conn, 142	grpc_ssl_ciphers, 164
fastcgi_limit_rate, 142	grpc_ssl_conf_command, 164
fastcgi_max_temp_file_size, 142	grpc_ssl_crl, 165
fastcgi_next_upstream, 142	grpc_ssl_name, 165
fastcgi_next_upstream_timeout, 143	grpc_ssl_password_file, 165
fastcgi_next_upstream_tries, 144	grpc_ssl_protocols, 165
fastcgi_no_cache, 144	grpc_ssl_server_name, 165
fastcgi_param, 144	grpc_ssl_session_reuse, 166
fastcgi_pass, 145	grpc_ssl_trusted_certificate, 166
fastcgi_pass_header, 145	grpc_ssl_verify, 166
fastcgi_pass_request_body, 145	grpc_ssl_verify_depth, 166
fastcgi_pass_request_headers, 146	gunzip, 167
fastcgi_read_timeout, 146	gunzip_buffers, 167
fastcgi_request_buffering, 146	gzip, 168
fastcgi_send_lowat, 146	gzip_buffers, 169
fastcgi_send_timeout, 147	gzip_comp_level, 169
fastcgi_socket_keepalive, 147	gzip_disable, 169
fastcgi_split_path_info, 147	gzip_http_version, 169
fastcgi_store, 147	gzip_min_length, 169
fastcgi_store_access, 148	gzip_proxied, 170
$fastcgi_temp_file_write_size, \ \underline{149}$	gzip_static, 172
fastcgi_temp_path, 149	gzip_types, 170
flv, 151	gzip_vary, 171

Nginx, Inc. p.500 of 506

hash, 328, 441	js_include, 188, 399
health_check, 345, 446	js_path, 188, 399
health_check_timeout, 447	js_path, 100, 555 js_preread, 400
hls, 177	js_set, 188, 400
hls_buffers, 177	js_var, 189, 400
hls_forward_args, 177	JS_va1, 109, 400
hls_fragment, 178	keepalive, 329
hls_mp4_buffer_size, 178	keepalive_disable, 30
hls_mp4_buffer_size, 179	keepalive_requests, 31, 330
http, 29	keepalive_time, 31, 331
http2_body_preread_size, 376	keepalive_timeout, 31, 331
http2_chunk_size, 376	keyval, 190, 401
http2_idle_timeout, 376	keyval_zone, 191, 402
http2_max_concurrent_pushes, 376	
http2_max_concurrent_streams, 377	large_client_header_buffers, 32
http2_max_field_size, 377	least_conn, 332, 442
http2_max_header_size, 377	least_time, 332, 442
http2_max_requests, 377	limit_conn, 192, 403
http2_push, 378	limit_conn_dry_run, 193, 404
http2_push_preload, 378	limit_conn_log_level, 193, 404
http2_recv_buffer_size, 378	limit_conn_status, 194
http2_recv_timeout, 378	limit_conn_zone, 194, 404
http2_recv_timeout, 570	limit_except, 32
if, 258	limit_rate, 32
if_modified_since, 29	limit_rate_after, 33
ignore_invalid_headers, 29	limit_req, 196
image_filter, 181	limit_req_dry_run, 197
image_filter_buffer, 182	limit_req_log_level, 197
image_filter_interlace, 182	limit_req_status, 198
image_filter_jpeg_quality, 182	limit_req_zone, 198
image_filter_sharpen, 182	limit_zone, 194
image_filter_transparency, 182	lingering_close, 33
image_filter_webp_quality, 183	lingering_time, 34
imap_auth, 478	lingering_timeout, 34
imap_capabilities, 478	listen, 35, 384, 458
imap_client_buffer, 478	load_module, 10
include, 10	location, 38
index, 184	lock_file, 10
internal, 30	log_format, 202, 407
ip_hash, 328	log_not_found, 39
-	log_subrequest, 40
js_access, 398	mail 460
js_body_filter, 186	mail, 460 map, 204, 409
js_content, 187	map_hash_bucket_size, 206, 410
js_filter, 399	map_hash_max_size, 206, 411
js_header_filter, 187	
js_import, 187, 399	master_process, 11

Nginx, Inc. p.501 of 506

match, 346, 447	pop3_capabilities, 480
max_ranges, 40	port_in_redirect, 42
memcached_bind, 207	postpone_output, 43
memcached_buffer_size, 208	preread_buffer_size, 386
memcached_connect_timeout, 208	preread_timeout, 386
memcached_force_ranges, 208	protocol, 460
memcached_gzip_flag, 209	proxy_bind, 225, 413
memcached_next_upstream, 209	proxy_buffer, 467
memcached_next_upstream_timeout,	proxy_buffer_size, 225, 413
209	proxy_buffering, 225
memcached_next_upstream_tries, 210	proxy_buffers, 226
memcached_pass, 210	proxy_busy_buffers_size, 226
memcached_read_timeout, 210	proxy_cache, 226
memcached_send_timeout, 210	proxy_cache_background_update, 226
memcached_socket_keepalive, 211	proxy_cache_bypass, 227
merge_slashes, 40	proxy_cache_convert_head, 227
min_delete_depth, 126	proxy_cache_key, 227
mirror, 212	proxy_cache_lock, 227
mirror_request_body, 212	proxy_cache_lock_age, 228
modern_browser, 121	proxy_cache_lock_timeout, 228
modern_browser_value, 121	proxy_cache_max_range_offset, 228
mp4, 215	proxy_cache_methods, 228
mp4_buffer_size, 215	proxy_cache_min_uses, 229
mp4_limit_rate, 216	proxy_cache_path, 229
mp4_limit_rate_after, 216	proxy_cache_purge, 231
mp4_max_buffer_size, 215	proxy_cache_revalidate, 231
msie_padding, 41	proxy_cache_use_stale, 232
msie_refresh, 41	proxy_cache_valid, 232
multi_accept, 11	proxy_connect_timeout, 233, 414
	proxy_cookie_domain, 233
ntlm, 331	proxy_cookie_flags, 234
open_file_cache, 41	proxy_cookie_path, 235
open_file_cache_errors, 42	proxy_download_rate, 414
open_file_cache_min_uses, 42	proxy_force_ranges, 235
open_file_cache_valid, 42	proxy_headers_hash_bucket_size, 236
open_log_file_cache, 203, 408	proxy_headers_hash_max_size, 236
output_buffers, 42	proxy_hide_header, 236
override_charset, 124	proxy_http_version, 236
override_charset, 124	proxy_ignore_client_abort, 236
pcre_jit, 11	proxy_ignore_headers, 237
perl, 218	proxy_intercept_errors, 237
perl_modules, 219	proxy_limit_rate, 237
perl_require, 219	proxy_max_temp_file_size, 238
perl_set, 219	proxy_method, 238
pid, 11	proxy_next_upstream, 238, 414
pop3_auth, 480	proxy_next_upstream_timeout, 239

Nginx, Inc. p.502 of 506

414	read_ahead, 43
proxy_next_upstream_tries, 239, 415	real_ip_header, 253
proxy_no_cache, 240	real_ip_recursive, 254
proxy_pass, 240, 415	recursive_error_pages, 43
proxy_pass_error_message, 467	referer_hash_bucket_size, 255
proxy_pass_header, 241	referer_hash_max_size, 255
proxy_pass_request_body, 242	request_pool_size, 43
proxy_pass_request_headers, 242	reset_timedout_connection, 43
proxy_protocol, 415, 467	resolver, 44, 333, 387, 443, 460
proxy_protocol_timeout, 387	resolver_timeout, 45, 334, 387, 444
proxy_read_timeout, 242	461
proxy_redirect, 242	return, 259, 422
proxy_request_buffering, 244	rewrite, 259
proxy_requests, 415	rewrite_log, 261
proxy_responses, 416	root, 45
proxy_send_lowat, 244	
proxy_send_timeout, 244	satisfy, 45
proxy_session_drop, 416	scgi_bind, 264
proxy_set_body, 245	scgi_buffer_size, 264
proxy_set_header, 245	scgi_buffering, 265
proxy_smtp_auth, 468	scgi_buffers, 265
proxy_socket_keepalive, 246, 416	scgi_busy_buffers_size, 265
proxy_ssl, 417	scgi_cache, 266
proxy_ssl_certificate, 246, 417	scgi_cache_background_update, 266
proxy_ssl_certificate_key, 246, 417	scgi_cache_bypass, 266
proxy_ssl_ciphers, 246, 417	scgi_cache_key, 266
proxy_ssl_conf_command, 246, 417	scgi_cache_lock, 266
proxy_ssl_crl, 247, 418	scgi_cache_lock_age, 267
proxy_ssl_name, 247, 418	scgi_cache_lock_timeout, 267
proxy_ssl_password_file, 247, 418	scgi_cache_max_range_offset, 267
proxy_ssl_protocols, 248, 418	scgi_cache_methods, 267
proxy_ssl_server_name, 248, 418	scgi_cache_min_uses, 268 scgi_cache_path, 268
proxy_ssl_session_reuse, 248, 419	scgi_cache_purge, 270
proxy_ssl_trusted_certificate, 248, 419	scgi_cache_revalidate, 270
proxy_ssl_verify, 248, 419	scgi_cache_use_stale, 270
proxy_ssl_verify_depth, 249, 419	scgi_cache_valid, 271
proxy_store, 249	scgi_connect_timeout, 272
proxy_store_access, 250	scgi_force_ranges, 272
proxy_temp_file_write_size, 250	scgi_hide_header, 272
proxy_temp_path, 250	scgi_ignore_client_abort, 273
proxy_timeout, 419, 468	scgi_ignore_headers, 273
proxy_upload_rate, 420	scgi_intercept_errors, 273
anono 333	scgi_limit_rate, 273
queue, 333	scgi_max_temp_file_size, 274
random, 333, 442	scgi_next_upstream, 274
random_index, 252	scgi_next_upstream_timeout, 275
,	beginneau_upatieam_timeout, 210

Nginx, Inc. p.503 of 506

scgi_next_upstream_tries, 275	ssl, 296, 471
scgi_no_cache, 276	ssLbuffer_size, 296
scgi_param, 276	ssl_certificate, 297, 426, 471
scgi_pass, 276	ssl_certificate_key, 298, 427, 472
scgi_pass_header, 277	ssl_ciphers, 298, 427, 472
scgi_pass_request_body, 277	ssl_client_certificate, 298, 427, 472
scgi_pass_request_headers, 277	ssl_conf_command, 298, 428, 473
scgi_read_timeout, 277	ssl_crl, 299, 428, 473
scgi_request_buffering, 278	ssl_dhparam, 299, 428, 473
scgi_send_timeout, 278	ssl_early_data, 299
scgi_socket_keepalive, 278	ssl_ecdh_curve, 300, 428, 473
scgi_store, 278	ssl_engine, 11
scgi_store_access, 279	ssl_handshake_timeout, 429
scgi_temp_file_write_size, 279	ssLocsp, 300
scgi_temp_path, 280	ssLocsp_cache, 301
secure_link, 281	ssl_ocsp_responder, 301
secure_link_md5, 282	ssl_password_file, 301, 429, 474
secure_link_secret, 282	ssl_prefer_server_ciphers, 302, 430, 474
send_lowat, 46	ssLpreread, 436
send_timeout, 46	ssLprotocols, 302, 430, 475
sendfile, 46	ssl_reject_handshake, 302
sendfile_max_chunk, 47	ssl_session_cache, 302, 430, 475
server, 47, 324, 388, 438, 461	ssl_session_ticket_key, 303, 431, 476
server_name, 47, 462	ssLsession_tickets, 304, 431, 476
server_name_in_redirect, 49	ssl_session_timeout, 304, 431, 476
server_names_hash_bucket_size, 49	ssLstapling, 304
server_names_hash_max_size, 49	ssl_stapling_file, 304
server_tokens, 50	ssl_stapling_responder, 305
session_log, 284	ssl_stapling_verify, 305
session_log_format, 284	ssl_trusted_certificate, 305, 432, 476
session_log_zone, 285	ssl_verify_client, 305, 432, 477
set, 261, 423	ssl_verify_depth, 306, 432, 477
set_real_ip_from, 253, 421, 469	starttls, 477
slice, 286	state, 327, 441
smtp_auth, 481	status, 310
smtp_capabilities, 481	status_format, 310
smtp_client_buffer, 482	status_zone, 65, 311
smtp_greeting_delay, 482	sticky, 334
source_charset, 124	sticky_cookie_insert, 337
split_clients, 288, 424	stream, 388
ssi, 289	stub_status, 319
ssi_last_modified, 289	sub_filter, 321
ssi_min_file_chunk, 290	sub_filter_last_modified, 321
ssi_silent_errors, 290	sub_filter_once, 322
ssi_types, 290	sub_filter_types, 322
ssi_value_length, 290	$subrequest_output_buffer_size, 50$

Nginx, Inc. p.504 of 506

tcp_nodelay, 50, 388	uwsgi_hide_header, 363
tcp_nopush, 50	uwsgi_ignore_client_abort, 363
thread_pool, 12	uwsgi_ignore_headers, 363
timeout, 462	uwsgi_intercept_errors, 364
timer_resolution, 12	uwsgi_limit_rate, 364
try_files, 51	uwsgi_max_temp_file_size, 364
types, 53	uwsgi_modifier1, 365
types_hash_bucket_size, 53	uwsgi_modifier2, 365
$types_hash_max_size, 53$	uwsgi_next_upstream, 365
underscores_in_headers, 54	uwsgi_next_upstream_timeout, 366
uninitialized_variable_warn, 261	uwsgi_next_upstream_tries, 366
upstream, 324, 438	uwsgi_no_cache, 366
	uwsgi_param, 367
upstream_conf, 340	uwsgi_pass, 367
use, 12	uwsgi_pass_header, 368
user, 13	uwsgi_pass_request_body, 368
userid, 349	uwsgi_pass_request_headers, 368
userid_domain, 350	uwsgi_read_timeout, 368
userid_expires, 350	uwsgi_request_buffering, 368
userid_flags, 350	uwsgi_send_timeout, 369
userid_mark, 350	uwsgi_socket_keepalive, 369
userid_name, 351	uwsgi_ssl_certificate, 369
userid_p3p, 351	uwsgi_ssl_certificate_key, 369
userid_path, 351	uwsgi_ssl_ciphers, 370
userid_service, 351	uwsgi_ssl_conf_command, 370
uwsgi_bind, 354	uwsgi_ssl_crl, 370
uwsgi_buffer_size, 355	uwsgi_ssl_name, 370
uwsgi_buffering, 355	uwsgi_ssl_password_file, 371
uwsgi_buffers, 356	uwsgi_ssl_protocols, 371
uwsgi_busy_buffers_size, 356	uwsgi_ssl_server_name, 371
uwsgi_cache, 356	uwsgi_ssl_session_reuse, 371
uwsgi_cache_background_update, 356	uwsgi_ssl_trusted_certificate, 371
uwsgi_cache_bypass, 356	uwsgi_ssl_verify, 372
uwsgi_cache_key, 357	uwsgi_ssl_verify_depth, 372
uwsgi_cache_lock, 357	uwsgi_store, 372
uwsgi_cache_lock_age, 357	uwsgi_store_access, 373
uwsgi_cache_lock_timeout, 357	uwsgi_temp_file_write_size, 373
uwsgi_cache_max_range_offset, 358	uwsgi_temp_path, 373
uwsgi_cache_methods, 358	
uwsgi_cache_min_uses, 358	valid_referers, 256
uwsgi_cache_path, 358	variables_hash_bucket_size, 54, 388
uwsgi_cache_purge, 360	variables_hash_max_size, 54, 388
uwsgi_cache_revalidate, 361	. 1
uwsgi_cache_use_stale, 361	worker_aio_requests, 13
uwsgi_cache_valid, 362	worker_connections, 13
uwsgi_connect_timeout, 362	worker_cpu_affinity, 13
uwsgi_force_ranges, 363	worker_priority, 14

Nginx, Inc. p.505 of 506

```
worker_processes, 14
worker_rlimit_core, 15
worker_rlimit_nofile, 15
worker_shutdown_timeout, 15
working_directory, 15
xclient, 468
xml_entities, 380
xslt_last_modified, 381
xslt_param, 381
xslt_string_param, 381
xslt_stylesheet, 381
xslt_types, 382
zone, 327, 440
zone_sync, 451
zone_sync_buffers, 451
zone_sync_connect_retry_interval, 451
zone_sync_connect_timeout, 451
zone_sync_interval, 451
zone_sync_recv_buffer_size, 452
zone_sync_server, 452
zone_sync_ssl, 452
zone_sync_ssl_certificate, 453
zone_sync_ssl_certificate_key, 453
zone_sync_ssl_ciphers, 453
zone_sync_ssl_conf_command, 453
zone_sync_ssl_crl, 454
zone_sync_ssl_name, 454
zone_sync_ssl_password_file, 454
zone_sync_ssl_protocols, 454
zone_sync_ssl_server_name, 454
zone_sync_ssl_trusted_certificate, 455
zone_sync_ssl_verify, 455
zone_sync_ssl_verify_depth, 455
zone_sync_timeout, 455
```

Nginx, Inc. p.506 of 506