TinkerCell

1.0

Generated by Doxygen 1.7.3

Fri May 20 2011 13:17:07

# **Contents**

1	Tink	kerCell	C API		1
2	<b>Mod</b> 2.1	<b>lule Ind</b> Modul			<b>3</b>
3	<b>Data</b> 3.1		tructures		<b>5</b> 5
4	<b>File</b> 4.1	<b>Index</b> File Li	st		<b>7</b> 7
5	Mod	lule Do	cumentati	on	9
	5.1	Basic	operations		9
		5.1.1		Description	11
		5.1.2		Documentation	11
			5.1.2.1	tc_appendColumns	11
			5.1.2.2	tc_appendRows	11
			5.1.2.3	tc_createItemsArray	12
			5.1.2.4	tc_createMatrix	12
			5.1.2.5	tc_createStringsArray	12
			5.1.2.6	tc_createTable	13
			5.1.2.7	tc_deleteItemsArray	13
			5.1.2.8	tc_deleteMatrix	13
			5.1.2.9	tc_deleteStringsArray	13
			5.1.2.10	tc_deleteTable	14
			5.1.2.11	tc_getColumnIndex	14
			5.1.2.12	tc_getColumnName	14
			5.1.2.13	tc_getItem	14
			5.1.2.14	tc_getMatrixValue	15
			5.1.2.15	tc_getRowIndex	15
			5.1.2.16	tc_getRowName	15
			5.1.2.17	tc_getString	16
			5.1.2.18	tc_getStringIndex	16
			5.1.2.19	tc_getTableValue	16
			5.1.2.20	tc_printMatrixToFile	17
			5.1.2.21	tc_printOutMatrix	17
			5.1.2.22	tc_printOutTable	17
			5.1.2.23	tc_printTableToFile	17
			5.1.2.24	tc setColumnName	17

ii CONTENTS

		5.1.2.25	tc_setItem
		5.1.2.26	tc_setMatrixValue
		5.1.2.27	tc_setRowName
		5.1.2.28	tc_setString
		5.1.2.29	tc_setTableValue
5.2	Appea	rance	
	5.2.1	Detailed	Description
	5.2.2		Documentation
		5.2.2.1	tc_changeArrowHead
		5.2.2.2	tc_changeNodeImage
		5.2.2.3	tc_getColor
		5.2.2.4	tc_getHeight
		5.2.2.5	tc_getPos
		5.2.2.6	tc_getWidth
		5.2.2.7	tc_getX
		5.2.2.8	tc_getY
		5.2.2.9	tc_moveSelected
		5.2.2.10	tc rotate
		5.2.2.11	tc_setColor
		5.2.2.12	tc_setPos
		5.2.2.13	tc_setPosMulti
		5.2.2.14	tc setSize
5.3	Get ite		
2.3	5.3.1		Description
	5.3.2		Documentation
	3.3.2	5.3.2.1	tc_alignParts
		5.3.2.2	tc_alignPartsOnPlasmid
		5.3.2.3	tc allItems
		5.3.2.4	tc deselect
		5.3.2.4	tc_find
		5.3.2.6	tc_findItems
		5.3.2.7	tc_getChildren
		5.3.2.8	tc getName
		5.3.2.9	<del>-</del>
		5.3.2.10	tc_getNames
			tc_getParent
		5.3.2.11 5.3.2.12	tc_getPos
		5.3.2.12	tc_getUniqueName
			tc_getUniqueNames
		5.3.2.14	tc_getX
		5.3.2.15	tc_getY
		5.3.2.16	tc_itemsOfFamily
		5.3.2.17	tc_itemsOfFamilyFrom
		5.3.2.18	tc_moveSelected
		5.3.2.19	tc_partsDownstream
		5.3.2.20	tc_partsIn
		5.3.2.21	tc_partsUpstream
		5.3.2.22	tc_rename
		5.3.2.23	tc_select
		5.3.2.24	tc_selectedItems
		5.3.2.25	tc_setPos

CONTENTS iii

			tc_setPosMulti
			tc_setSequence
5.4			
	5.4.1		Description
	5.4.2		Documentation
		5.4.2.1	tc_annotations
		5.4.2.2	tc_getAllTextNamed
		5.4.2.3	tc_getFamily
		5.4.2.4	tc_getName
		5.4.2.5	tc_getNames
		5.4.2.6	tc_getTextAttribute
		5.4.2.7	tc_getUniqueName
		5.4.2.8	tc_getUniqueNames
		5.4.2.9	tc_insertAnnotations
		5.4.2.10	tc_isA
		5.4.2.11	tc_rename
		5.4.2.12	tc_setSequence
		5.4.2.13	tc_setTextAttribute
		5.4.2.14	tc_setTextAttributeByName
		5.4.2.15	tc_setTextAttributes
5.5	Input a	and Output	
0.0	5.5.1		Description
	5.5.2		Documentation
	3.3.2	5.5.2.1	tc_addInputWindowCheckbox
		5.5.2.2	tc_addInputWindowOptions
		5.5.2.3	tc_askQuestion
		5.5.2.4	tc_burn
		5.5.2.5	tc_clear
		5.5.2.6	tc_createInputWindow
			_ 1
		5.5.2.7	= I
		5.5.2.8	<del></del>
		5.5.2.9	tc_displayNumber
		5.5.2.10	tc_displayText
		5.5.2.11	tc_errorReport
		5.5.2.12	tc_getFilename
		5.5.2.13	tc_getNumber
		5.5.2.14	tc_getNumbers
		5.5.2.15	tc_getStringDialog
		5.5.2.16	tc_getStringFromList
		5.5.2.17	tc_highlight
		5.5.2.18	tc_messageDialog
		5.5.2.19	tc_openFile
		5.5.2.20	tc_openNewWindow
		5.5.2.21	tc_openUrl
		5.5.2.22	tc_print
		5.5.2.23	tc_printFile
		5.5.2.24	tc_printMatrix
		5.5.2.25	tc_saveToFile
		5.5.2.26	tc_screenHeight
		5.5.2.27	tc_screenshot

iv CONTENTS

		5.5.2.28 tc_screenWidth	
		5.5.2.29 tc_screenX	
		5.5.2.30 tc_screenY	
			or
5.6	Syster	information	
0.0	5.6.1	Detailed Description	
	5.6.2	Function Documentation	
		- 11	
		5.6.2.3 tc_isLinux	
		5.6.2.4 tc_isMac	
		5.6.2.5 tc_isWindows	
5.7	Matrico		
		rk data	
5.8	Graph	_ =	
	5.8.1	Detailed Description	
	5.8.2	Function Documentation	
		•	
		5.8.2.5 tc_hist	
		5.8.2.6 tc_holdPlot	
		5.8.2.7 tc_multiplot	
		•	
5.9	Model		
).9	5.9.1	Detailed Description	
	5.9.1	*	
	3.9.2	Function Documentation	
			Assignments
			Names
		5.9.2.10 tc_getParameters	
		5.9.2.11 tc_getParametersAndFi	xedVariables
		5.9.2.12 tc_getParametersExcept	t
			1
		•	

CONTENTS v

	5.9.2.18 tc_setInitialValues 62
	5.9.2.19 tc_setParameter
	5.9.2.20 tc_setParameterByName 62
	5.9.2.21 tc_setParameters
	5.9.2.22 tc_setRate
	5.9.2.23 tc_setRates
	5.9.2.24 tc_setStoichiometry
	5.9.2.25 tc_setStoichiometryFor
	5.9.2.26 tc_StoichiometryTool_api
	5.9.2.27 tc_writeModel
5.10 Conne	ctions
5.10.1	
5.10.2	
	5.10.2.1 tc_getCenterPointX
	5.10.2.2 tc_getCenterPointY
	5.10.2.3 tc_getConnectedNodes
	5.10.2.4 tc_getConnectedNodesWithRole 67
	5.10.2.5 tc_getConnections
	5.10.2.6 tc_getConnectionsWithRole
	5.10.2.7 tc_getControlPointX
	5.10.2.8 tc_getControlPointY
	5.10.2.9 tc_insertConnection
	5.10.2.10 tc_setAllStraight
	5.10.2.11 tc setCenterPoint
	5.10.2.12 tc_setControlPoint
	5.10.2.13 tc_setLineWidth
	5.10.2.14 tc_setStraight
5.11 Import	/Export
	Detailed Description
	Function Documentation
3.11.2	5.11.2.1 tc_exportSBML
	5.11.2.2 tc_importSBML
5.12 Simula	ttion
	Detailed Description
	Function Documentation
3.12.2	5.12.2.1 tc_elementaryFluxModes
	5.12.2.2 tc_getEigenvalues       73         5.12.2.3 tc_getJacobian       73
	5.12.2.4 tc_getScaledConcentrationCC
	5.12.2.5 tc_getScaledElasticities
	5.12.2.6 tc_getScaledFluxCC
	<i>=</i> €
	<i>=</i> €
	5.12.2.11 tc_KMatrix
	5.12.2.12 tc_LMatrix
	5.12.2.13 tc_optimize
	5.12.2.14 tc_reducedStoichiometry
	5.12.2.15 tc_simulateDeterministic

vi CONTENTS

				6 tc_simulateHybrid
			5.12.2.17	7 tc_simulateStochastic
				8 tc_simulateTauLeap
				9 tc_steadyStateScan
			5.12.2.20	0 tc_steadyStateScan2D
				1 tc_updateParameters
6				mentation
	6.1			Reference
		6.1.1		Description
		6.1.2		ocumentation
			6.1.2.1	items
	_ د		6.1.2.2	length
	6.2			Reference
		6.2.1		Description
		6.2.2		ocumentation
			6.2.2.1	colnames
			6.2.2.2	cols
			6.2.2.3	rownames
			6.2.2.4	rows
			6.2.2.5	values
	6.3	tc_stri	ngs Struct	Reference
		6.3.1		Description
		6.3.2		ocumentation
			6.3.2.1	length
			6.3.2.2	strings
	6.4	tc_tabl	le Struct R	leference
		6.4.1		Description
		6.4.2		ocumentation
			6.4.2.1	colnames
			6.4.2.2	cols
			6.4.2.3	rownames
			6.4.2.4	rows
			6.4.2.5	strings
_		D.		
7			entation	inkarCall/trunk/ADI/main har Eila Dafaranaa
	7.1			inkerCell/trunk/API/main.hpp File Reference
	7.2			inkerCell/trunk/API/TC_api.h File Reference
	7.3			inkerCell/trunk/API/TC_AutoGeneRegulatoryTool_api.c
		7.3.1		Documentation
		7.00	7.3.1.1	tc_AutoGeneRegulatoryTool_api
		7.3.2		Documentation
			7.3.2.1	_tc_alignParts
			7.3.2.2	_tc_alignPartsOnPlasmid
			7.3.2.3	_tc_partsDownstream
			7.3.2.4	_tc_partsIn
			7.3.2.5	_tc_partsUpstream
	7.4		-	inkerCell/trunk/API/TC_AutoGeneRegulatoryTool_api.h
		File Re	eference.	

CONTENTS vii

	7.4.1	Function Documentation	86
		7.4.1.1 tc_AutoGeneRegulatoryTool_api	86
7.5	/home	/deepak/TinkerCell/trunk/API/TC_BasicInformationTool_api.c File	
			86
	7.5.1		88
			88
			89
	7.5.2		89
	1.3.2		89
		_ <i>−</i> υ	
		_ <i>−</i> υ	89
		_ <i>−</i> υ	89
		_ <i></i>	89
		_ <i>−</i> υ	89
		7.5.2.6 _tc_getParametersAndFixedVariables	89
		7.5.2.7 _tc_getParametersExcept	89
		7.5.2.8 _tc_getParametersNamed	89
			90
			90
			90
			90
7.6	/homa	/deepak/TinkerCell/trunk/API/TC_BasicInformationTool_api.h File	90
7.0			90
	7.6.1		92
			92
		1	92
7.7	/home	/deepak/TinkerCell/trunk/API/TC_ConnectionInsertion_api.c File	
	Refere		92
	7.7.1	Function Documentation	93
		7.7.1.1 tc_ConnectionInsertion_api	93
	7.7.2	Variable Documentation	93
			93
			93
			93
		= <i>=\begin{align*} \\ \\ \\ \\ \\ \\ \\ \\ \\ \\ \\ \\ \\</i>	93
			94
7.8	/homa	/deepak/TinkerCell/trunk/API/TC_ConnectionInsertion_api.h File	ノサ
7.0			94
	Refere		
	7.8.1		94
	_	— — — — — — — — — — — — — — — — — — —	94
7.9		/deepak/TinkerCell/trunk/API/TC_ConnectionSelection_api.c File	
			95
	7.9.1		96
		7.9.1.1 tc_ConnectionSelection_api	96
	7.9.2	Variable Documentation	96
		7.9.2.1 _tc_getCenterPointX	96
			96
		<u>~</u>	96
		· · · · · · · · · · · · · · · · · · ·	97
			97
		= = &	91 97
		1.7.2.0 _tt_SetCenterrount	11

viii CONTENTS

	7.9.2.7 _tc_setControlPoint	97
	7.9.2.8 _tc_setLineWidth	97
	7.9.2.9 _tc_setStraight	97
7.10 /home/	/deepak/TinkerCell/trunk/API/TC_ConnectionSelection_api.h File	
	ence	97
7.10.1		98
	7.10.1.1 tc_ConnectionSelection_api	98
7.11 /home	/deepak/TinkerCell/trunk/API/TC_COPASI_api.c File Reference	98
7.11.1		102
		102
7.11.2		102
		102
		102
		102
		102
		102
		103
		103
		103
		103
		103
		103
		103
		103
	7.11.2.14 _tc_reducedStoichiometry	103
		103
	7.11.2.16 _tc_simulateHybrid	104
		104
	7.11.2.18 _tc_simulateTauLeap	104
		104
		104
		104
7.12 /home		104
7.12.1	Function Documentation	107
		107
7.13 /home	/deepak/TinkerCell/trunk/API/TC_DynamicLibraryTool_api.c File	
Refere	ence	107
7.13.1	Function Documentation	109
		109
		109
	7.13.1.3 tc_addPythonPlugin	110
	7.13.1.4 tc_callFunction	110
	<b>–</b> 1	110
	7.13.1.6 tc_compileBuildLoad	110
		111
	_ , 1	111
	7.13.1.9 tc_LoadCLibraries_api	111
	7.13.1.10 tc_loadLibrary	111
	7.13.1.11 tc_OctaveTool_api	111
	7.13.1.12 tc_PythonTool_api	112

CONTENTS ix

	7.13.1.13 tc_runOctaveCode	112
	7.13.1.14 tc_runOctaveFile	112
	7.13.1.15 tc_runPythonCode	112
	7.13.1.16 tc_runPythonFile	112
	7.13.2 Variable Documentation	113
	7.13.2.1 _tc_addFunction	113
	7.13.2.2 _tc_addOctavePlugin	113
	7.13.2.3 _tc_addPythonPlugin	113
	7.13.2.4 _tc_callFunction	113
	7.13.2.5 _tc_compileAndRun	113
	7.13.2.6 _tc_compileBuildLoad	113
	7.13.2.7 _tc_compileBuildLoadSliders	113
	7.13.2.8 _tc_loadLibrary	113
	7.13.2.9 _tc_runOctaveCode	114
	7.13.2.10 _tc_runOctaveFile	114
	7.13.2.11 _tc_runPythonCode	114
	7.13.2.12 _tc_runPythonFile	114
7.14	/home/deepak/TinkerCell/trunk/API/TC_DynamicLibraryTool_api.h File	9
	Reference	114
	7.14.1 Function Documentation	116
	7.14.1.1 tc_addFunction	116
	7.14.1.2 tc_addOctavePlugin	116
	7.14.1.3 tc_addPythonPlugin	116
	7.14.1.4 tc_callFunction	116
	7.14.1.5 tc_compileAndRun	117
	7.14.1.6 tc_compileBuildLoad	117
	7.14.1.7 tc_compileBuildLoadSliders	117
	7.14.1.8 tc_DynamicLibraryMenu_api	117
	7.14.1.9 tc_LoadCLibraries_api	118
		118
	7.14.1.10 tc_loadLibrary	
	7.14.1.11 tc_OctaveTool_api	118
	7.14.1.12 tc_PythonTool_api	119
	7.14.1.13 tc_runOctaveCode	119
	7.14.1.14 tc_runOctaveFile	119
	7.14.1.15 tc_runPythonCode	119
	7.14.1.16 tc_runPythonFile	119
7.15	/home/deepak/TinkerCell/trunk/API/TC_EventsAssignments_api.c File	
	Reference	120
	7.15.1 Function Documentation	121
	7.15.1.1 tc_AssignmentFunctionsTool_api	121
	7.15.1.2 tc_SimulationEventsTool_api	121
	7.15.2 Variable Documentation	121
	7.15.2.1 _tc_addEvent	121
	7.15.2.2 _tc_addForcingFunction	121
	7.15.2.3 _tc_getEventResponses	121
	7.15.2.4 _tc_getEventTriggers	121
	7.15.2.5 _tc_getForcingFunctionAssignments	121
	7.15.2.6 _tc_getForcingFunctionNames	121
7 16		122
7.10	/home/deepak/TinkerCell/trunk/API/TC_EventsAssignments_api.h File	122
	Reference	122

X CONTENTS

	7.16.1	Function Documentation	123
		7.16.1.1 tc_AssignmentFunctionsTool_api	123
		7.16.1.2 tc_SimulationEventsTool_api	123
7.17	/home/	deepak/TinkerCell/trunk/API/TC_GroupHandlerTool_api.c File	
	Referen	nce	123
	7.17.1	Function Documentation	124
		7.17.1.1 tc_GroupHandlerTool_api	124
		7.17.1.2 tc_merge	124
		7.17.1.3 tc_separate	124
	7.17.2	Variable Documentation	124
		7.17.2.1 _tc_merge	124
		7.17.2.2 _tc_separate	124
7.18		deepak/TinkerCell/trunk/API/TC_GroupHandlerTool_api.h File	
		nce	124
	7.18.1	Function Documentation	125
		7.18.1.1 tc_GroupHandlerTool_api	125
		7.18.1.2 tc_merge	125
		7.18.1.3 tc_separate	125
7.19		deepak/TinkerCell/trunk/API/TC_Main_api.c File Reference .	125
	7.19.1	Function Documentation	135
		7.19.1.1 tc_callback	135
		7.19.1.2 tc_callWhenExiting	135
		7.19.1.3 tc_CThread_api_initialize	135
		7.19.1.4 tc_getNumericalData	135
		7.19.1.5 tc_getNumericalDataNames	135
		7.19.1.6 tc_getNumericalValue	136
		7.19.1.7 tc_getTextData	136
		7.19.1.8 tc_getTextDataNames	136
		7.19.1.9 tc_getTextValue	136
		7.19.1.10 tc_LabelingTool_api	136
		7.19.1.11 tc_Main_api_initialize	137
		7.19.1.12 tc_remove	137
		7.19.1.13 tc_setNumericalData	138
		7.19.1.14 tc_setNumericalValue	138
		7.19.1.15 tc_setNumericalValues	138
		7.19.1.16 tc_setTextData	138
		7.19.1.17 tc_setTextValue	138
		7.19.1.18 tc_setTextValues	139
	7.10.0	7.19.1.19 tc_thisThread	139
	7.19.2	Variable Documentation	139
		7.19.2.1 _tc_addInputWindowCheckbox	139
		7.19.2.2 _tc_addInputWindowOptions	139
		7.19.2.3 _tc_allItems	139
		7.19.2.4 _tc_annotations	139
		7.19.2.5 _tc_appDir	139
		7.19.2.6 _tc_askQuestion	139
		7.19.2.7 _tc_burn	140 140
		7.19.2.8 _tc_callback	140
		7.19.2.10 _tc_changeArrowHead	140
		1.19.2.10 _tc_changeAnownead	140

CONTENTS xi

7.19.2.11 _tc_changeNodeImage	140
7.19.2.12 _tc_clear	140
7.19.2.13 _tc_createInputWindow	140
7.19.2.14 _tc_createInputWindowForScript	140
7.19.2.15 _tc_createSliders	140
7.19.2.16 _tc_deselect	140
7.19.2.17 _tc_displayNumber	141
7.19.2.18 _tc_displayText	141
7.19.2.19 _tc_errorReport	141
7.19.2.20 _tc_find	141
7.19.2.21 _tc_findItems	141
7.19.2.22 _tc_getChildren	141
7.19.2.23 _tc_getColor	141
7.19.2.24 _tc_getFamily	141
7.19.2.25 _tc_getFilename	141
7.19.2.26 _tc_getHeight	141
7.19.2.27 _tc_getName	141
7.19.2.28 _tc_getNames	142
7.19.2.29 _tc_getNumber	142
7.19.2.30 _tc_getNumbers	142
7.19.2.31 _tc_getNumericalData	142
7.19.2.32 _tc_getNumericalDataNames	142
7.19.2.33 _tc_getNumericalValue	142
7.19.2.34 _tc_getParent	142
7.19.2.35 _tc_getPos	142
7.19.2.36 _tc_getStringDialog	142
7.19.2.37 _tc_getStringFromList	142
7.19.2.38 _tc_getTextData	143
7.19.2.39 _tc_getTextDataNames	143
7.19.2.40 _tc_getTextValue	143
7.19.2.41 _tc_getUniqueName	143
7.19.2.42 _tc_getUniqueNames	143
7.19.2.43 _tc_getWidth	143
7.19.2.44 _tc_getX	143
7.19.2.45 _tc_getY	143
7.19.2.46 _tc_highlight	143
7.19.2.47 _tc_homeDir	143
7.19.2.48 _tc_insertAnnotations	143
7.19.2.49 _tc_isA	144
7.19.2.50 _tc_isLinux	144
7.19.2.51 _tc_isMac	144
7.19.2.52 _tc_isWindows	144
7.19.2.53 _tc_itemsOfFamily	144
7.19.2.54 _tc_itemsOfFamilyFrom	144
7.19.2.55 _tc_messageDialog	144
7.19.2.55 _tc_moveSelected	144
7.19.2.57 _tc_openFile	144
7.19.2.58 _tc_openNewWindow	144
7.19.2.59 _tc_openUrl	144
	145
7.19.2.60 _tc_print	145

xii CONTENTS

	7.19.2.61 _tc_printFile	145
	7.19.2.62 _tc_printMatrix	145
	7.19.2.63 _tc_remove	145
	7.19.2.64 _tc_rename	145
	7.19.2.65 _tc_saveToFile	145
	7.19.2.66 _tc_screenHeight	145
	7.19.2.67 _tc_screenshot	145
	7.19.2.68 _tc_screenWidth	145
	7.19.2.69 _tc_screenX	145
	7.19.2.70 _tc_screenY	146
	7.19.2.70 _tc_select	146
	7.19.2.72 _tc_selectedItems	146
	7.19.2.73 _tc_setAngle	146
	7.19.2.74 _tc_setColor	146
		146
	7.19.2.75 _tc_setDisplayLabelColor	146
		146
	7.19.2.77 _tc_setNumericalValue	
	7.19.2.78 _tc_setNumericalValues	146
	7.19.2.79 _tc_setPos	146
	7.19.2.80 _tc_setPosMulti	146
	7.19.2.81 _tc_setSize	147
	7.19.2.82 _tc_setTextData	147
	7.19.2.83 _tc_setTextValue	147
	7.19.2.84 _tc_setTextValues	147
		147
	7.19.2.85 _tc_showProgress	
	7.19.2.86 _tc_zoom	147
	7.19.2.86 _tc_zoom	147 147
7.20 /home 7.20.1	7.19.2.86 _tc_zoom	147 147 154
	7.19.2.86 _tc_zoom	147 147 154 154
	7.19.2.86 _tc_zoom	147 147 154 154 155
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize	147 147 154 154 155 155
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData	147 147 154 154 155 155
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames	147 147 154 154 155 155 155
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData	147 147 154 154 155 155 155 156
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData	147 147 154 154 155 155 155 156 156
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames	147 147 154 155 155 155 156 156 156
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue	147 147 154 155 155 155 156 156 156
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames	147 147 154 155 155 155 156 156 156 156 156
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue	1477 1477 1544 1554 1555 1555 1556 1566 1566 1567 1577
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextData 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api	147 147 154 155 155 155 156 156 156 156 156
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize	1477 1477 1544 1554 1555 1555 1556 1566 1566 1567 1577
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextData 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove	147 147 154 154 155 155 155 156 156 156 157 157 157
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextData 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue	147 147 154 154 155 155 155 156 156 156 157 157 158 158
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextData 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalData 7.20.1.14 tc_setNumericalData 7.20.1.14 tc_setNumericalValue	147 147 154 154 155 155 155 156 156 156 157 157 158 158 158
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextData 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue	147 147 154 154 155 155 155 156 156 156 157 157 158 158 158
	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getTextData 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalData 7.20.1.15 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue 7.20.1.16 tc_setTextData	1477 1477 1544 1554 1555 1555 1556 1566 1566 1577 1577 1588 1588 1588 159
	7.19.2.86 _tc_zoom //deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getTextData 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue 7.20.1.16 tc_setTextData 7.20.1.16 tc_setTextData 7.20.1.17 tc_setTextData 7.20.1.17 tc_setTextValue	147 147 154 154 155 155 155 156 156 156 157 157 158 158 158 158 159
7.20.1	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue 7.20.1.16 tc_setTextData 7.20.1.17 tc_setTextValue 7.20.1.17 tc_setTextValue 7.20.1.18 tc_setTextValue 7.20.1.18 tc_setTextValue 7.20.1.18 tc_setTextValue	1477 1477 1544 1554 1555 1555 1556 1566 1567 1577 1588 1588 1559 1559 1559
7.20.1 7.21 /home	7.19.2.86 _tc_zoom /deepak/TinkerCell/trunk/API/TC_Main_api.h File Reference Function Documentation 7.20.1.1 tc_callback 7.20.1.2 tc_callWhenExiting 7.20.1.3 tc_CThread_api_initialize 7.20.1.4 tc_getNumericalData 7.20.1.5 tc_getNumericalDataNames 7.20.1.6 tc_getNumericalValue 7.20.1.7 tc_getTextData 7.20.1.8 tc_getTextDataNames 7.20.1.9 tc_getTextValue 7.20.1.10 tc_LabelingTool_api 7.20.1.11 tc_Main_api_initialize 7.20.1.12 tc_remove 7.20.1.13 tc_setNumericalData 7.20.1.14 tc_setNumericalValue 7.20.1.15 tc_setNumericalValue 7.20.1.16 tc_setTextData 7.20.1.17 tc_setTextValue 7.20.1.18 tc_setTextValue 7.20.1.19 tc_thisThread	1477 1477 1544 1554 1555 1555 1556 1566 1567 1577 1588 1588 1559 1559 1559

CONTENTS xiii

7.21.1.1 tc_ModelFileGenerator_api	160
7.21.2 Variable Documentation	160
	160
7.22 /home/deepak/TinkerCell/trunk/API/TC_ModelFileGenerator_api.h File	
	160
	161
	161
7.23 /home/deepak/TinkerCell/trunk/API/TC_ModuleTool_api.c File Refer-	
	161
	162
	162
	162
	162
_ 1,	162
	163
	163
	163
	163
7.24 /home/deepak/TinkerCell/trunk/API/TC_ModuleTool_api.h File Refer-	
ence	163
7.24.1 Function Documentation	164
7.24.1.1 tc_listOfPossibleModels	164
7.24.1.2 tc_ModuleTool_api	164
7.24.1.3 tc_substituteEmptyModel	164
	164
	165
7.25 /home/deepak/TinkerCell/trunk/API/TC_NodeInsertion_api.c File Ref-	. 00
	165
	165
	165
1	166
	166
	166
7.26 /home/deepak/TinkerCell/trunk/API/TC_NodeInsertion_api.h File Ref-	
	166
	166
	166
7.26.1.2 tc_NodeInsertion_api	167
7.27 /home/deepak/TinkerCell/trunk/API/TC_PlotTool_api.c File Reference 1	167
7.27.1 Function Documentation	169
7.27.1.1 tc_PlotTool_api	169
7.27.2 Variable Documentation	169
	169
	169
	169
= <del>-</del> c	169
<b>– –</b> U	169
— — — — — — — — — — — — — — — — — — —	169 169
— <u> </u>	169
7.27.2.8 _tc_plot	170

xiv CONTENTS

	7.27.2.9 _tc_savePlot	170
	7.27.2.10 _tc_scatterplot	170
	7.27.2.11 _tc_setLogScale	170
	7.27.2.12 _tc_surface	170
7.28	/home/deepak/TinkerCell/trunk/API/TC_PlotTool_api.h File Reference	170
	7.28.1 Function Documentation	171
	7.28.1.1 tc_PlotTool_api	171
7.29	/home/deepak/TinkerCell/trunk/API/TC_SBML_api.c File Reference	171
	7.29.1 Function Documentation	172
	7.29.1.1 tc_SBML_api	172
	7.29.2 Variable Documentation	172
	7.29.2.1 _tc_exportSBML	172
	7.29.2.2 _tc_importSBML	172
7.30	/home/deepak/TinkerCell/trunk/API/TC_SBML_api.h File Reference	172
	7.30.1 Function Documentation	173
	7.30.1.1 tc_SBML_api	173
7.31	/home/deepak/TinkerCell/trunk/API/TC_StoichiometryTool_api.c File	
	Reference	173
	7.31.1 Variable Documentation	174
	7.31.1.1 _tc_getRates	174
	7.31.1.2 _tc_getStoichiometry	174
	7.31.1.3 _tc_setRates	174
	7.31.1.4 _tc_setStoichiometry	174
7.32	/home/deepak/TinkerCell/trunk/API/TC_StoichiometryTool_api.h File	
	Reference	175
7.33	/home/deepak/TinkerCell/trunk/API/TC_structs.c File Reference	175
	/home/deepak/TinkerCell/trunk/API/TC_structs.h File Reference	178
	7.34.1 Define Documentation	180
	7.34.1.1 BEGIN_C_DECLS	180
	7.34.1.2 END_C_DECLS	180
	7.34.1.3 TCAPIEXPORT	180

# TinkerCell C API

The TinkerCell C API is a collection of functions that allow C programs to directly interact with TinkerCell's visual interface. SWIG is used to extend this API to other languages, such as Python, Perl, R, etc. The functions provided in this API are coverted to Signals, which are much slower than function calls. But they can be used to communicate between threads, which is the main reason why they are used in TinkerCell.The API uses **six main data structures**:

**item**: just a reference to a TinkerCell object. Items are represented as integers in Python and Octave and as long ints in C.

string: a string of characters used. Represented as const char\* in C.

tc\_items array of items

```
tc_items A = tc_allItems()
A.length
tc_getItem(A, 3)
long x = tc_find("x")
tc_setItem(A, 3, x)
tc_items A2 = tc_createItemsArray(10) //array of length 10
```

tc\_strings: array of strings

```
tc_items A = tc_allItems()
tc_strings S = tc_getNames( A )
S.length
tc_getString(S,3)
tc_setString(S,3,"hello")
tc_strings S2 = tc_createStringsArray(10) //array of length 10
```

**tc\_matrix**: Two dimensional array of reals with row and column names. The rownames and colnames fields are **tc\_strings** objects

```
long x = tc_find("x")
tc_matrix M = tc_getNumericalData( x, "Parameters" )
int r = M.rows
int c = M.cols
tc_getColumnName(M,2)
tc_setColumnName(M,2,"col2")
```

2 TinkerCell C API

```
tc_getRowName(M,1)
tc_setRowName(M,1,"row1")
tc_getMatrixValue(M,2,3)
tc_setMatrixValue(M,2,3,0.5)
tc_matrix M2 = tc_createMatrix(5,4)
```

**tc\_table**: Two dimensional array of Strings with row and column names. The rownames and colnames fields are tc\_strings objects

```
long x = tc_find("x")
tc_table S = tc_getTextData( x, "Text Attributes" )
S.rows
S.cols
tc_getString( S.rownames, 1)
tc_getString( S.colnames, 2)
tc_getTableValue(S,2,3)
tc_setTableValue(S,2,3,"hello")
tc_table S2 = tc_createTable(4,5)
```

# **Module Index**

# 2.1 Modules

Here	: .	. 1	: _4	_ C	11		11	
Here	19	ล เ	1ST	ΩŤ	ลบ	mod	1111	es.

Basic operations	
Appearance	
Get items	
Annotations	
Input and Output	
=	
Network data	
Graphing	
Modeling	
Connections	
Import/Export	
* *	

4 Module Index

# **Data Structure Index**

# 3.1 Data Structures

Here are the data structures with brief descriptions:

tc_items (An array of int objects with length information. Use tc_getItem(M,i)	
to get the i-th item )	<del>7</del> 9
tc_matrix (A 2D table of doubles with row and column names. Use tc	
getMatrixValue(M,i,j) to get the i,j-th value in tc_matrix M)	80
tc_strings (An array of strings with length information. Use tc_getString(M,i)	
to get the i-th string)	81
tc_table (A 2D table of strings with row and column names. Use tc_getTableValue	e(M,i,j)
to get the i,j-th value in tc_matrix M)	81

# File Index

# 4.1 File List

Here is a list of all files with brief descriptions:

/home/deepak/TinkerCell/trunk/API/main.hpp
/home/deepak/TinkerCell/trunk/API/TC_api.h
/home/deepak/TinkerCell/trunk/API/TC_AutoGeneRegulatoryTool_api.c 84
/home/deepak/TinkerCell/trunk/API/TC_AutoGeneRegulatoryTool_api.h 85
/home/deepak/TinkerCell/trunk/API/TC_BasicInformationTool_api.c 86
/home/deepak/TinkerCell/trunk/API/TC_BasicInformationTool_api.h 90
/home/deepak/TinkerCell/trunk/API/TC_ConnectionInsertion_api.c 92
/home/deepak/TinkerCell/trunk/API/TC_ConnectionInsertion_api.h 94
/home/deepak/TinkerCell/trunk/API/TC_ConnectionSelection_api.c 95
/home/deepak/TinkerCell/trunk/API/TC_ConnectionSelection_api.h 97
/home/deepak/TinkerCell/trunk/API/TC_COPASI_api.c
/home/deepak/TinkerCell/trunk/API/TC_COPASI_api.h
/home/deepak/TinkerCell/trunk/API/TC_DynamicLibraryTool_api.c 107
/home/deepak/TinkerCell/trunk/API/TC_DynamicLibraryTool_api.h 114
/home/deepak/TinkerCell/trunk/API/TC_EventsAssignments_api.c 120
/home/deepak/TinkerCell/trunk/API/TC_EventsAssignments_api.h 122
/home/deepak/TinkerCell/trunk/API/TC_GroupHandlerTool_api.c 123
/home/deepak/TinkerCell/trunk/API/TC_GroupHandlerTool_api.h 124
/home/deepak/TinkerCell/trunk/API/TC_Main_api.c
/home/deepak/TinkerCell/trunk/API/TC_Main_api.h
/home/deepak/TinkerCell/trunk/API/TC_ModelFileGenerator_api.c 160
/home/deepak/TinkerCell/trunk/API/TC_ModelFileGenerator_api.h 160
/home/deepak/TinkerCell/trunk/API/TC_ModuleTool_api.c 161
/home/deepak/TinkerCell/trunk/API/TC_ModuleTool_api.h 163
/home/deepak/TinkerCell/trunk/API/TC_NodeInsertion_api.c 165
/home/deepak/TinkerCell/trunk/API/TC_NodeInsertion_api.h 166
/home/deepak/TinkerCell/trunk/API/TC_PlotTool_api.c
/home/deepak/TinkerCell/trunk/API/TC_PlotTool_api.h
/home/deenak/TinkerCell/trunk/API/TC_SBMI_api_c 171

/home/deepak/TinkerCell/trunk/API/TC_SBML_api.h	172
/home/deepak/TinkerCell/trunk/API/TC_StoichiometryTool_api.c	173
/home/deepak/TinkerCell/trunk/API/TC_StoichiometryTool_api.h	175
/home/deepak/TinkerCell/trunk/API/TC_structs.c	175
/home/deepak/TinkerCell/trunk/API/TC_structs.h	178

# **Module Documentation**

# 5.1 Basic operations

basic functions for getting and setting matrices, arrays, tables, etc.

# **Functions**

- TCAPIEXPORT tc\_matrix tc\_createMatrix (int rows, int cols)

  Create a matrix with the given rows and columns.
- TCAPIEXPORT tc\_table tc\_createTable (int rows, int cols)

  Create a strings table with the given rows and columns.
- TCAPIEXPORT tc\_strings tc\_createStringsArray (int len) Create an array of strings.
- TCAPIEXPORT tc\_items tc\_createItemsArray (int len) Create an array of items.
- TCAPIEXPORT double tc\_getMatrixValue (tc\_matrix M, int i, int j) get i,jth value from a tc\_matrix
- TCAPIEXPORT void tc\_setMatrixValue (tc\_matrix M, int i, int j, double d) set i,jth value of a tc\_matrix
- TCAPIEXPORT const char \* tc\_getRowName (tc\_matrix M, int i) get ith row name from a tc\_matrix
- TCAPIEXPORT void tc\_setRowName (tc\_matrix M, int i, const char \*s) set ith row name for a tc\_matrix

- TCAPIEXPORT const char \* tc\_getColumnName (tc\_matrix M, int j) get jth column name of a tc\_matrix
- TCAPIEXPORT void tc\_setColumnName (tc\_matrix M, int j, const char \*s) set jth column name of a tc\_matrix
- TCAPIEXPORT const char \* tc\_getTableValue (tc\_table S, int i, int j) get i,j-th string in a table
- TCAPIEXPORT void tc\_setTableValue (tc\_table S, int i, int j, const char \*s) set i,jth string in a table
- TCAPIEXPORT const char \* tc\_getString (tc\_strings S, int i)

  get ith string in array of strings
- TCAPIEXPORT void tc\_setString (tc\_strings S, int i, const char \*c) set ith string in array of strings
- TCAPIEXPORT long tc\_getItem (tc\_items A, int i) get ith long item in array of items
- TCAPIEXPORT void tc\_setItem (tc\_items A, int i, long o) set ith long item in array of items
- TCAPIEXPORT int tc\_getStringIndex (tc\_strings A, const char \*s) get the index of a string in the array
- TCAPIEXPORT int tc\_getRowIndex (tc\_matrix, const char \*s) get the row number of a row name
- TCAPIEXPORT int tc\_getColumnIndex (tc\_matrix, const char \*s) get the column number of a column name
- TCAPIEXPORT void tc\_deleteMatrix (tc\_matrix M)
   delete a matrix
- TCAPIEXPORT void tc\_deleteTable (tc\_table M) delete a strings table
- TCAPIEXPORT void tc\_deleteItemsArray (tc\_items A) delete an array of items
- TCAPIEXPORT void tc\_deleteStringsArray (tc\_strings C) delete an array of strings
- TCAPIEXPORT tc\_matrix tc\_appendColumns (tc\_matrix A, tc\_matrix B)

combine two matrices by appending their columns. row size must be equal for both matrices

- TCAPIEXPORT tc\_matrix tc\_appendRows (tc\_matrix A, tc\_matrix B)
   combine two matrices by appending their row. column sizes must be equal for both matrices
- TCAPIEXPORT void tc\_printMatrixToFile (const char \*file, tc\_matrix M) print a matrix to file
- TCAPIEXPORT void tc\_printOutMatrix (tc\_matrix M)
   print a matrix to stdout
- TCAPIEXPORT void tc\_printTableToFile (const char \*file, tc\_table M)
   print a table to file
- TCAPIEXPORT void tc\_printOutTable (tc\_table M) print a table to stdout

# 5.1.1 Detailed Description

basic functions for getting and setting matrices, arrays, tables, etc.

# 5.1.2 Function Documentation

# 5.1.2.1 TCAPIEXPORT $tc_{matrix} tc_{append}Columns ( tc_{matrix} A, tc_{matrix} B)$

combine two matrices by appending their columns. row size must be equal for both matrices

#### **Parameters**

tc_matrix	first matrix
tc_matrix	fsecond matrix

#### Returns

tc\_matrix new combined matrix

Definition at line 221 of file TC structs.c.

# 5.1.2.2 TCAPIEXPORT tc\_matrix tc\_appendRows ( tc\_matrix A, tc\_matrix B)

combine two matrices by appending their row. column sizes must be equal for both matrices

# **Parameters**

tc_matrix	first matrix
tc_matrix	fsecond matrix

#### Returns

tc\_matrix new combined matrix

Definition at line 299 of file TC\_structs.c.

# 5.1.2.3 TCAPIEXPORT tc\_items tc\_createltemsArray ( int len )

Create an array of items.

# **Parameters**

int	number of items	]
-----	-----------------	---

#### **Returns**

tc\_items

Definition at line 67 of file TC\_structs.c.

# 5.1.2.4 TCAPIEXPORT tc\_matrix tc\_createMatrix ( int rows, int cols )

Create a matrix with the given rows and columns.

# **Parameters**

int	number of rows
int	number of columns

# Returns

tc\_matrix

Definition at line 8 of file TC\_structs.c.

# 5.1.2.5 TCAPIEXPORT tc\_strings tc\_createStringsArray ( int len )

Create an array of strings.

#### **Parameters**

24	1
1111	length
0100	14.18.11

# Returns

tc\_strings

Definition at line 48 of file TC\_structs.c.

# 5.1.2.6 TCAPIEXPORT $tc\_table\ tc\_createTable\ (int\ rows,\ int\ cols\ )$

Create a strings table with the given rows and columns.

# **Parameters**

int	number of rows
int	number of columns

#### Returns

tc\_table

Definition at line 28 of file TC\_structs.c.

# 5.1.2.7 TCAPIEXPORT void tc\_deleteltemsArray ( tc\_items A )

delete an array of items

#### **Parameters**

&tc_items	pointer to array

Definition at line 199 of file TC\_structs.c.

# 5.1.2.8 TCAPIEXPORT void tc\_deleteMatrix ( $tc_matrix M$ )

delete a matrix

# **Parameters**

&tc_matrix	pointer to matrix

Definition at line 179 of file TC\_structs.c.

# 5.1.2.9 TCAPIEXPORT void tc\_deleteStringsArray ( tc\_strings C )

delete an array of strings

#### **Parameters**

&tc_strings	pointer to array

Definition at line 207 of file TC\_structs.c.

# 5.1.2.10 TCAPIEXPORT void tc\_deleteTable ( tc\_table M )

delete a strings table

#### **Parameters**

&tc_table	pointer to table		

Definition at line 189 of file TC\_structs.c.

# 5.1.2.11 TCAPIEXPORT int tc\_getColumnIndex ( tc\_matrix , const char \* s )

get the column number of a column name

#### **Parameters**

tc_matrix	matrix
char*	a string in the matrix

#### Returns

int index of that string

Definition at line 511 of file TC\_structs.c.

# 5.1.2.12 TCAPIEXPORT const char\* tc\_getColumnName ( tc\_matrix M, int j )

get jth column name of a tc\_matrix

#### **Parameters**

tc_matrix	matrix
int	column

#### Returns

string column name

Definition at line 109 of file TC\_structs.c.

# 5.1.2.13 TCAPIEXPORT long tc\_getItem ( tc\_items A, int i )

get ith long item in array of items

# **Parameters**

tc_items	array
int	index

# Returns

long value

Definition at line 166 of file TC\_structs.c.

# 5.1.2.14 TCAPIEXPORT double tc\_getMatrixValue ( tc\_matrix M, int i, int j)

get i,jth value from a tc\_matrix

#### **Parameters**

tc_matrix	matrix
int	row
int	column

# Returns

double value at the given row, column

Definition at line 86 of file TC\_structs.c.

# 5.1.2.15 TCAPIEXPORT int tc\_getRowlndex ( $tc_matrix$ , const char \*s)

get the row number of a row name

# **Parameters**

tc_matrix	matrix
char*	a string in the matrix

# Returns

int index of that string

Definition at line 505 of file TC\_structs.c.

# 5.1.2.16 TCAPIEXPORT const char\* tc\_getRowName ( $tc_matrix M$ , int i)

get ith row name from a tc\_matrix

#### **Parameters**

tc_matrix	matrix
int	row

# Returns

string row name

Definition at line 99 of file TC\_structs.c.

# 5.1.2.17 TCAPIEXPORT const char\* tc\_getString ( tc\_strings S, int i )

get ith string in array of strings

# **Parameters**

tc_strings	array
int	index

#### **Returns**

string value

Definition at line 140 of file TC\_structs.c.

# 5.1.2.18 TCAPIEXPORT int tc\_getStringIndex ( tc\_strings A, const char \* s )

get the index of a string in the array

#### **Parameters**

tc_strings	array
char*	a string in the array

# Returns

int index of that string

Definition at line 493 of file TC\_structs.c.

# 5.1.2.19 TCAPIEXPORT const char\* tc\_getTableValue ( $tc_table S$ , int i, int j)

get i,j-th string in a table

# **Parameters**

tc_table	table
int	row
int	column

# Returns

string value at row, column

Definition at line 119 of file TC\_structs.c.

# 5.1.2.20 TCAPIEXPORT void tc\_printMatrixToFile ( const char \* file, tc\_matrix M )

print a matrix to file

#### **Parameters**

char*	file name
tc_matrix	

Definition at line 381 of file TC\_structs.c.

# 5.1.2.21 TCAPIEXPORT void tc\_printOutMatrix ( tc\_matrix M )

print a matrix to stdout

# **Parameters**

char*	file name
tc_matrix	

Definition at line 408 of file TC\_structs.c.

# 5.1.2.22 TCAPIEXPORT void tc\_printOutTable ( tc\_table M )

print a table to stdout

#### **Parameters**

```
tc_table
```

Definition at line 464 of file TC\_structs.c.

# 5.1.2.23 TCAPIEXPORT void tc\_printTableToFile ( const char \* file, tc\_table M )

print a table to file

#### **Parameters**

char*	file name
tc_table	

Definition at line 434 of file TC\_structs.c.

# 5.1.2.24 TCAPIEXPORT void tc\_setColumnName ( $tc_matrix M$ , int j, const char \*s)

set jth column name of a tc\_matrix

# **Parameters**

tc_matrix	matrix
int	column
string	column name

Definition at line 114 of file TC\_structs.c.

# 5.1.2.25 TCAPIEXPORT void tc\_setItem ( tc\_items A, int i, long o )

set ith long item in array of items

#### **Parameters**

tc_items	array
int	index
long	value

Definition at line 173 of file TC\_structs.c.

# 5.1.2.26 TCAPIEXPORT void tc\_setMatrixValue ( tc\_matrix M, int i, int j, double d)

set i,jth value of a tc\_matrix

# **Parameters**

tc_matrix	matrix
int	row
int	column
double	value at the given row, column

Definition at line 93 of file TC\_structs.c.

# 5.1.2.27 TCAPIEXPORT void tc\_setRowName ( $tc_matrix M$ , int i, const char \*s)

set ith row name for a tc\_matrix

# **Parameters**

tc_matrix	matrix
int	row
string	row name

Definition at line 104 of file TC\_structs.c.

5.2 Appearance 19

# 5.1.2.28 TCAPIEXPORT void tc\_setString ( $tc_strings S$ , int i, const char \* c )

set ith string in array of strings

#### **Parameters**

tc_strings	array
int	index
string	value

Definition at line 147 of file TC\_structs.c.

# 5.1.2.29 TCAPIEXPORT void tc\_setTableValue ( $tc_table S$ , int i, int j, const char \* s )

set i,jth string in a table

#### **Parameters**

tc_table	table
int	row
int	column
string	value at row,column

Definition at line 126 of file TC\_structs.c.

# 5.2 Appearance

get/set position, color, size, etc

# **Functions**

- TCAPIEXPORT double tc\_getY (long item) get the x location of an item
- TCAPIEXPORT double tc\_getX (long item) get the y location of an item
- TCAPIEXPORT tc\_matrix tc\_getPos (tc\_items items) get the y location of a list item. Output is a N x 2 matrix
- TCAPIEXPORT void tc\_setPos (long item, double x, double y) set the x and y location of an item
- TCAPIEXPORT void tc\_setPosMulti (tc\_items items, tc\_matrix positions) set the x and y location of a list of N items. Input a matrix of positions, with N rows and 2 columns (x,y)

- TCAPIEXPORT void tc\_moveSelected (double dx, double dy)
   move all the selected items by a given amount
- TCAPIEXPORT void tc\_setSize (long item, double width, double height)

  Change the size of an item.
- TCAPIEXPORT double tc\_getWidth (long item) get the width of an item
- TCAPIEXPORT double tc\_getHeight (long item) get the width of an item
- TCAPIEXPORT void tc\_rotate (long item, double t) get the width of an item
- TCAPIEXPORT const char \* tc\_getColor (long item) get the color of the item
- TCAPIEXPORT void tc\_setColor (long item, const char \*name, int permanent)

  set the color of the item and indicate whether or not the color is permanenet
- TCAPIEXPORT void tc\_changeNodeImage (long item, const char \*filename) change the graphics file for drawing one of the nodes
- TCAPIEXPORT void tc\_changeArrowHead (long connection, const char \*filename)

 $change \ the \ graphics \ file \ for \ drawing \ the \ arrowheads \ for \ the \ given \ connection$ 

# 5.2.1 Detailed Description

get/set position, color, size, etc

# 5.2.2 Function Documentation

#### 5.2.2.1 TCAPIEXPORT void tc\_changeArrowHead ( long connection, const char \* filename )

change the graphics file for drawing the arrowheads for the given connection

#### **Parameters**

int	address of connection, e.g. obtained using tc_find
string	file name of the new graphics file

5.2 Appearance 21

Definition at line 833 of file TC\_Main\_api.c.

# 5.2.2.2 TCAPIEXPORT void tc\_changeNodelmage ( long item, const char \* filename )

change the graphics file for drawing one of the nodes

### **Parameters**

int	address of item, e.g. obtained using tc_find
string	file name of the new graphics file

Definition at line 822 of file TC\_Main\_api.c.

# 5.2.2.3 TCAPIEXPORT const char \* tc\_getColor ( long item )

get the color of the item

#### **Parameters**

int	address of item, e.g. obtained using tc_find

### Returns

string Hex code for color

Definition at line 799 of file TC\_Main\_api.c.

# 5.2.2.4 TCAPIEXPORT double tc\_getHeight ( long item )

get the width of an item

### **Parameters**

int address of item, e.g. obtained using tc\_find

## Returns

double height

Definition at line 776 of file TC\_Main\_api.c.

# 5.2.2.5 TCAPIEXPORT tc\_matrix tc\_getPos ( tc\_items items )

get the y location of a list item. Output is a N x 2 matrix

### **Parameters**

tc_items   addresses of items
-------------------------------

### **Returns**

tc\_matrix x,y positions of items

Definition at line 290 of file TC\_Main\_api.c.

# 5.2.2.6 TCAPIEXPORT double tc\_getWidth ( long item )

get the width of an item

### **Parameters**

int address of item, e.g. obtained using tc\_find

### Returns

double width

Definition at line 764 of file TC\_Main\_api.c.

# 5.2.2.7 TCAPIEXPORT double tc\_getX ( long item )

get the y location of an item

# **Parameters**

int address of item

## Returns

double y position

Definition at line 278 of file TC\_Main\_api.c.

# 5.2.2.8 TCAPIEXPORT double tc\_getY ( long item )

get the x location of an item

# **Parameters**

int address of item

# Returns

double x position

Definition at line 266 of file TC\_Main\_api.c.

5.2 Appearance 23

### 5.2.2.9 TCAPIEXPORT void tc\_moveSelected ( double dx, double dy )

move all the selected items by a given amount

### **Parameters**

double	change in x
double	change in y

Definition at line 324 of file TC\_Main\_api.c.

# 5.2.2.10 TCAPIEXPORT void tc\_rotate ( long item, double t )

get the width of an item rotate and item by the given number of degrees

### **Parameters**

	int	address of item, e.g. obtained using tc_find
6	louble	angle in degrees

Definition at line 788 of file TC\_Main\_api.c.

# 5.2.2.11 TCAPIEXPORT void tc\_setColor ( long item, const char \* name, int permanent )

set the color of the item and indicate whether or not the color is permanenet set the rgb color of the item and indicate whether or not the color is permanenet

### **Parameters**

int	int address of item, e.g. obtained using tc_find	
string	Hex code for color	
int 0(temporary) or 1 (permenent color change)		

Definition at line 811 of file TC\_Main\_api.c.

# 5.2.2.12 TCAPIEXPORT void tc\_setPos ( long item, double x, double y )

set the x and y location of an item

#### **Parameters**

int	address of item
double	x position
double	y position

Definition at line 302 of file TC\_Main\_api.c.

# 5.2.2.13 TCAPIEXPORT void tc\_setPosMulti ( tc\_items items, tc\_matrix positions )

set the x and y location of a list of N items. Input a matrix of positions, with N rows and 2 columns (x,y)

#### **Parameters**

tc_items	addresses of items
tc_matrix	x,y positions

Definition at line 313 of file TC\_Main\_api.c.

### 5.2.2.14 TCAPIEXPORT void tc\_setSize ( long item, double width, double height )

Change the size of an item.

### **Parameters**

int	address of item, e.g. obtained using tc_find
double	width
double	height

Definition at line 753 of file TC\_Main\_api.c.

# 5.3 Get items

get selected items or items of a family

# **Functions**

- TCAPIEXPORT tc\_items tc\_partsIn (long o)

  Get all DNA parts inside the given container or module.
- TCAPIEXPORT tc\_items tc\_partsUpstream (long o)

  Get all DNA parts upstream of the given part.
- TCAPIEXPORT tc\_items tc\_partsDownstream (long o)

  Get all DNA parts downstream of the given part.
- TCAPIEXPORT void tc\_alignParts (tc\_items a)
   Align the given DNA parts in the order given.
- TCAPIEXPORT void tc\_alignPartsOnPlasmid (long o, tc\_items a)

  Align the given DNA parts in the order given.

5.3 Get items 25

```
• TCAPIEXPORT void tc_setSequence (long o, const char *s)
     Assign DNA sequence to a part.
• TCAPIEXPORT tc items tc allItems ()
     get all visible items
• TCAPIEXPORT tc_items tc_selectedItems ()
     get all selected items
• TCAPIEXPORT tc_items tc_itemsOfFamily (const char *family)
     get all items of the given family items
• TCAPIEXPORT tc_items tc_itemsOfFamilyFrom (const char *family, tc_items
  itemsToSelectFrom)
     get subset of items that belong to the given family
• TCAPIEXPORT long tc_find (const char *fullname)
     get the first item with the given name (full name)
• TCAPIEXPORT to items to findItems (to strings names)
     get all items with the given names (full names)
• TCAPIEXPORT void tc_select (long item)
     select an item
• TCAPIEXPORT void tc_deselect ()
     deselect all items
• TCAPIEXPORT tc_items tc_getChildren (long o)
     get child items of the given item
• TCAPIEXPORT long tc_getParent (long o)
     get parent item of the given item
• TCAPIEXPORT const char * tc_getName (long item)
     get the name of an item
• TCAPIEXPORT const char * tc_getUniqueName (long item)
     get the full name of an item
• TCAPIEXPORT void tc_rename (long item, const char *name)
     set the name of an item (not full name)
• TCAPIEXPORT tc_strings tc_getNames (tc_items items)
```

get the names of several items

- TCAPIEXPORT tc\_strings tc\_getUniqueNames (tc\_items items)
   get the full names of several items
- TCAPIEXPORT double tc\_getY (long item) get the x location of an item
- TCAPIEXPORT double tc\_getX (long item) get the y location of an item
- TCAPIEXPORT tc\_matrix tc\_getPos (tc\_items items) get the y location of a list item. Output is a N x 2 matrix
- TCAPIEXPORT void tc\_setPos (long item, double x, double y) set the x and y location of an item
- TCAPIEXPORT void tc\_setPosMulti (tc\_items items, tc\_matrix positions) set the x and y location of a list of N items. Input a matrix of positions, with N rows and 2 columns (x,y)
- TCAPIEXPORT void tc\_moveSelected (double dx, double dy)
   move all the selected items by a given amount

# 5.3.1 Detailed Description

get selected items or items of a family

#### 5.3.2 Function Documentation

# 5.3.2.1 TCAPIEXPORT void tc\_alignParts ( tc\_items a )

Align the given DNA parts in the order given.

### **Parameters**

tc\_items | a list of items

Definition at line 45 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.3.2.2 TCAPIEXPORT void tc\_alignPartsOnPlasmid ( long , $tc\_items$ )

Align the given DNA parts in the order given.

Align the given DNA parts in the order given on the given plasmid.

5.3 Get items 27

#### **Parameters**

long	plasmid
tc_items	a list of items

Definition at line 56 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.3.2.3 BEGIN\_C\_DECLS TCAPIEXPORT tc\_items tc\_allItems ( )

get all visible items

### Returns

tc\_items list of all items in the network

Definition at line 10 of file TC\_Main\_api.c.

# 5.3.2.4 TCAPIEXPORT void tc\_deselect ( )

deselect all items

Definition at line 93 of file TC\_Main\_api.c.

# 5.3.2.5 TCAPIEXPORT long tc\_find ( const char \* name )

get the first item with the given name (full name)

#### **Parameters**

string	name of an item.	use full name whenever possible	

### Returns

int address of item with the name

Definition at line 58 of file TC\_Main\_api.c.

# 5.3.2.6 TCAPIEXPORT $tc\_items$ $tc\_findItems$ ( $tc\_strings$ names )

get all items with the given names (full names)

# **Parameters**

tc_string names of one or more items
--------------------------------------

### Returns

 $tc\_items$  addresses of all the items. For nonexistent names, a 0 will be placed in the list

Definition at line 70 of file TC\_Main\_api.c.

# 5.3.2.7 TCAPIEXPORT $tc\_items\ tc\_getChildren\ (long\ o)$

get child items of the given item

# **Parameters**

int address of item

### Returns

tc\_items list of child items

Definition at line 450 of file TC\_Main\_api.c.

# 5.3.2.8 TCAPIEXPORT const char\* tc\_getName ( long item )

get the name of an item

#### **Parameters**

int	address of the item

## Returns

string name (not full name)

Definition at line 104 of file TC\_Main\_api.c.

# 5.3.2.9 TCAPIEXPORT $tc\_strings\ tc\_getNames\ (\ tc\_items\ items\ )$

get the names of several items

# **Parameters**

tc\_items | addresses of the items

# Returns

tc\_string list of names (not full names)

Definition at line 139 of file TC\_Main\_api.c.

# 5.3.2.10 TCAPIEXPORT long tc\_getParent ( long o )

get parent item of the given item

5.3 Get items 29

#### **Parameters**

int address of item

### Returns

int address of parent item (0 if no parent)

Definition at line 462 of file TC\_Main\_api.c.

# 5.3.2.11 TCAPIEXPORT tc\_matrix tc\_getPos ( tc\_items items )

get the y location of a list item. Output is a N x 2 matrix

#### **Parameters**

tc\_items addresses of items

### Returns

tc\_matrix x,y positions of items

Definition at line 290 of file TC\_Main\_api.c.

# 5.3.2.12 TCAPIEXPORT const char\* tc\_getUniqueName ( long item )

get the full name of an item

## **Parameters**

int address of the item

### Returns

string full name of the item (always unique)

Definition at line 116 of file TC\_Main\_api.c.

# 5.3.2.13 TCAPIEXPORT tc\_strings tc\_getUniqueNames ( tc\_items items )

get the full names of several items

### **Parameters**

tc\_items | addresses of the items

### Returns

tc\_string list of names (unique names)

Definition at line 151 of file TC\_Main\_api.c.

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

# 5.3.2.14 TCAPIEXPORT double tc\_getX ( long item )

get the y location of an item

#### **Parameters**

int	address of item

### **Returns**

double y position

Definition at line 278 of file TC\_Main\_api.c.

# 5.3.2.15 TCAPIEXPORT double tc\_getY ( long item )

get the x location of an item

### **Parameters**

int	address of item

### **Returns**

double x position

Definition at line 266 of file TC\_Main\_api.c.

# 5.3.2.16 TCAPIEXPORT $tc\_items$ $tc\_itemsOfFamily$ ( const char \* family )

get all items of the given family items

# **Parameters**

string	name of a type

# Returns

tc\_items list of all items in network belonging under the given type

Definition at line 34 of file TC\_Main\_api.c.

# 5.3.2.17 TCAPIEXPORT $tc\_items$ $tc\_items$ OfFamilyFrom ( const char \* family, $tc\_items$ itemsToSelectFrom )

get subset of items that belong to the given family

### **Parameters**

string	name of a type
tc_items	list of items to select from

**5.3 Get items 31** 

# Returns

tc\_items list of all items in the list belonging under the given type

Definition at line 46 of file TC\_Main\_api.c.

# 5.3.2.18 TCAPIEXPORT void tc\_moveSelected ( double dx, double dy )

move all the selected items by a given amount

### **Parameters**

double	change in x
double	change in y

Definition at line 324 of file TC\_Main\_api.c.

# 5.3.2.19 TCAPIEXPORT tc\_items tc\_partsDownstream ( long o )

Get all DNA parts downstream of the given part.

#### **Parameters**

int	address of an item in the network

Definition at line 33 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.3.2.20 BEGIN\_C\_DECLS TCAPIEXPORT tc\_items tc\_partsIn ( long o )

Get all DNA parts inside the given container or module.

### **Parameters**

int	address of an item in the network

Definition at line 9 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.3.2.21 TCAPIEXPORT tc\_items tc\_partsUpstream ( long o )

Get all DNA parts upstream of the given part.

### **Parameters**

int	address of an item in the network

Definition at line 21 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.3.2.22 TCAPIEXPORT void tc\_rename ( long item, const char \* name )

set the name of an item (not full name)

# **Parameters**

int	address of item

### **Returns**

string new name (not full name)

Definition at line 128 of file TC\_Main\_api.c.

# 5.3.2.23 TCAPIEXPORT void tc\_select ( long item )

select an item

#### **Parameters**

int	address of the item

Definition at line 82 of file TC\_Main\_api.c.

# 5.3.2.24 TCAPIEXPORT tc\_items tc\_selectedItems ( )

get all selected items

# Returns

tc\_items list of all items currently selected by user

Definition at line 22 of file TC\_Main\_api.c.

# 5.3.2.25 TCAPIEXPORT void tc\_setPos ( long item, double x, double y )

set the x and y location of an item

### **Parameters**

int	address of item
double	x position
double	y position

Definition at line 302 of file TC\_Main\_api.c.

5.4 Annotations 33

### 5.3.2.26 TCAPIEXPORT void tc\_setPosMulti ( tc\_items items, tc\_matrix positions )

set the x and y location of a list of N items. Input a matrix of positions, with N rows and 2 columns (x,y)

#### **Parameters**

tc_items	addresses of items
tc_matrix	x,y positions

Definition at line 313 of file TC\_Main\_api.c.

# 5.3.2.27 TCAPIEXPORT void tc\_setSequence ( long o, const char \*s)

Assign DNA sequence to a part.

Align the given DNA parts in the order given.

Definition at line 66 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.4 Annotations

get annotation information about items

### **Functions**

- TCAPIEXPORT void tc\_setSequence (long o, const char \*)

  Align the given DNA parts in the order given.
- TCAPIEXPORT const char \* tc\_getTextAttribute (long item, const char \*attribute)

get the text attribute with the given name for the given item

• TCAPIEXPORT tc\_strings tc\_getAllTextNamed (tc\_items a, tc\_strings attributes)

get all text Modeling with the given name for the given items

• TCAPIEXPORT void tc\_setTextAttribute (long item, const char \*attribute, const char \*value)

set text attribute for the given item

• TCAPIEXPORT void tc\_setTextAttributeByName (const char \*attribute, const char \*value)

set text attribute

• TCAPIEXPORT void tc\_setTextAttributes (tc\_table)

set text attributes for multiple items

- TCAPIEXPORT const char \* tc\_getName (long item) get the full name of an item
- TCAPIEXPORT const char \* tc\_getUniqueName (long item) get the full name of an item
- TCAPIEXPORT void tc\_rename (long item, const char \*name) set the name of an item (not full name)
- TCAPIEXPORT tc\_strings tc\_getNames (tc\_items items)

  get the full names of several items
- TCAPIEXPORT tc\_strings tc\_getUniqueNames (tc\_items items)
   get the full names of several items
- TCAPIEXPORT const char \* tc\_getFamily (long item) get the family name of an item
- TCAPIEXPORT int tc\_isA (long item, const char \*family)
   check is an item belongs in a family (or in a sub-family)
- TCAPIEXPORT const char \* tc\_annotations () get text displayed on the canvas
- TCAPIEXPORT void tc\_insertAnnotations (const char \*, double, double) show text displayed on the canvas at the given position

# 5.4.1 Detailed Description

get annotation information about items

# 5.4.2 Function Documentation

# 5.4.2.1 TCAPIEXPORT const char\* tc\_annotations ( )

get text displayed on the canvas

### Returns

const char \*

Definition at line 898 of file TC\_Main\_api.c.

5.4 Annotations 35

### 5.4.2.2 TCAPIEXPORT tc\_strings tc\_getAllTextNamed ( tc\_items a, tc\_strings attributes )

get all text Modeling with the given name for the given items

#### **Parameters**

tc_items	a list of items
tc_strings	a list of text attribute name that exists in each of the given items

### Returns

tc\_strings the set of all text attribute values, one for each item in the input

Definition at line 119 of file TC\_BasicInformationTool\_api.c.

# 5.4.2.3 TCAPIEXPORT const char \* tc\_getFamily ( long item )

get the family name of an item

#### **Parameters**

int	address of the item

# Returns

string type of the item

Definition at line 164 of file TC\_Main\_api.c.

# 5.4.2.4 TCAPIEXPORT const char\* tc\_getName ( long item )

get the full name of an item get the name of an item

Definition at line 104 of file TC\_Main\_api.c.

# 5.4.2.5 TCAPIEXPORT tc\_strings tc\_getNames ( tc\_items items )

get the full names of several items get the names of several items

Definition at line 139 of file TC\_Main\_api.c.

# 5.4.2.6 TCAPIEXPORT const char\* tc\_getTextAttribute ( long item, const char \* attribute )

get the text attribute with the given name for the given item

## **Parameters**

int	item in the model, e.g. something returned from tc_find
string	name of the attribute

### **Returns**

string attribute

Definition at line 71 of file TC\_BasicInformationTool\_api.c.

# 5.4.2.7 TCAPIEXPORT const char\* tc\_getUniqueName ( long item )

get the full name of an item

# **Parameters**

int	address of the item

### Returns

string full name of the item (always unique)

Definition at line 116 of file TC\_Main\_api.c.

# 5.4.2.8 TCAPIEXPORT tc\_strings tc\_getUniqueNames ( tc\_items items )

get the full names of several items

# **Parameters**

tc_items	addresses of the items

# Returns

tc\_string list of names (unique names)

Definition at line 151 of file TC\_Main\_api.c.

# 5.4.2.9 TCAPIEXPORT void $tc_i$ insertAnnotations ( const char \* , double , double )

show text displayed on the canvas at the given position

#### **Parameters**

double	X
double	y
const	char *

Definition at line 909 of file TC\_Main\_api.c.

5.4 Annotations 37

# 5.4.2.10 TCAPIEXPORT int tc\_isA ( long item, const char \* family )

check is an item belongs in a family (or in a sub-family)

### **Parameters**

int	address of the item
string	name of the family type

# Returns

int 0(no) or 1(yes)

Definition at line 176 of file TC\_Main\_api.c.

# 5.4.2.11 TCAPIEXPORT void tc\_rename ( long item, const char \* name )

set the name of an item (not full name)

### **Parameters**

int address of item
---------------------

#### Returns

string new name (not full name)

Definition at line 128 of file TC\_Main\_api.c.

# 5.4.2.12 TCAPIEXPORT void tc\_setSequence ( long $o_i$ const char \*s)

Align the given DNA parts in the order given.

# **Parameters**

tc_items	a list of items

Definition at line 66 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 5.4.2.13 TCAPIEXPORT void tc\_setTextAttribute ( long item, const char \* attribute, const char \* value )

set text attribute for the given item

### **Parameters**

int	item in model
string	name of text attribute

Definition at line 131 of file TC\_BasicInformationTool\_api.c.

# 5.4.2.14 TCAPIEXPORT void tc\_setTextAttributeByName ( const char \* attribute, const char \* value )

set text attribute

# **Parameters**

string	full name of text attribute, e.g. A.sequence or A_sequence
string	value

Definition at line 148 of file TC\_BasicInformationTool\_api.c.

### 5.4.2.15 TCAPIEXPORT void tc\_setTextAttributes ( tc\_table )

set text attributes for multiple items

### **Parameters**

tc_table	table with rownames as the attribute full names

Definition at line 158 of file TC\_BasicInformationTool\_api.c.

# 5.5 Input and Output

display dialogs or get user inputs

#### **Functions**

- TCAPIEXPORT void tc\_print (const char \*text) show text in the output window.
- TCAPIEXPORT void tc\_openUrl (const char \*s) show text in the output window.
- TCAPIEXPORT void tc\_errorReport (const char \*text) show error text in the output window.
- TCAPIEXPORT void tc\_printMatrix (tc\_matrix data) show table in the output window.
- TCAPIEXPORT void tc\_printFile (const char \*filename) show file contents in the output window.

TCAPIEXPORT void tc\_clear ()

cleat the contents in the output window.

• TCAPIEXPORT void tc\_createInputWindowForScript (tc\_matrix input, const char \*filename, const char \*functionname)

create an input window that can call a dynamic library

TCAPIEXPORT void tc\_createInputWindow (tc\_matrix input, const char \*title, void(\*f)(tc\_matrix))

create an input window that can call a dynamic library

• TCAPIEXPORT void tc\_addInputWindowOptions (const char \*title, int i, int j, tc\_strings options)

add options to an existing input window at the i,j-th cell. Options will appear in a list

TCAPIEXPORT void tc\_addInputWindowCheckbox (const char \*title, int i, int j)

add a yes or no type of option to an existing input window at the i,j-th cell

- TCAPIEXPORT void tc\_openNewWindow (const char \*title)
   open a new graphics window
- TCAPIEXPORT void tc\_zoom (double factor)
   zoom by the given factor (0 1)
- TCAPIEXPORT const char \* tc\_getStringDialog (const char \*title)

  get a text from the user (dialog)
- TCAPIEXPORT const char \* tc\_getFilename ()
   get a file from the user (dialog)
- TCAPIEXPORT int tc\_getStringFromList (const char \*title, tc\_strings list, const char \*selectedString)

get a text from the user (dialog) from a list of selections

- TCAPIEXPORT double tc\_getNumber (const char \*title)
   get a number from the user (dialog)
- TCAPIEXPORT void tc\_getNumbers (tc\_strings labels, double \*result) get a list of numbers from the user (dialog) into the argument array
- TCAPIEXPORT int tc\_askQuestion (const char \*message)
   display a dialog with a text and a yes and no button
- TCAPIEXPORT void tc\_messageDialog (const char \*message) display a dialog with a text message and a close button

- TCAPIEXPORT void tc\_openFile (const char \*message)
   open file
- TCAPIEXPORT void tc\_saveToFile (const char \*message)
   save to file
- TCAPIEXPORT void tc\_createSliders (tc\_matrix input, void(\*f)(tc\_matrix))

  create a window with several sliders. when the sliders change, the given function will be called with the values in the sliders
- TCAPIEXPORT void tc\_screenshot (const char \*filename, int width, int height)

  save screenshot in a file
- TCAPIEXPORT void tc\_showProgress (const char \*title, int progress)

  show progress of current operation
- TCAPIEXPORT void tc\_displayText (long item, const char \*text)

  displays the given text on the given item (the text is temporary)
- TCAPIEXPORT void tc\_displayNumber (long item, double number)

  displays the given number on the given item (the text is temporary)
- TCAPIEXPORT void tc\_setDisplayLabelColor (const char \*a, const char \*b)

  set the color for the number or text when using tc\_displayNumber and tc\_displayText
- TCAPIEXPORT void tc\_highlight (long item, const char \*color)

  highlights an item (the highlight is temporary) with the given color (hex)
- TCAPIEXPORT void tc\_burn (long item, double intensity) burn
- TCAPIEXPORT int tc\_screenWidth ()
   get width of current canvas
- TCAPIEXPORT int tc\_screenHeight ()
   get height of current canvas
- TCAPIEXPORT int tc\_screenX ()
   get x position of current canvas
- TCAPIEXPORT int tc\_screenY () get y position of current canvas

# 5.5.1 Detailed Description

display dialogs or get user inputs

# 5.5.2 Function Documentation

# 5.5.2.1 TCAPIEXPORT void tc\_addInputWindowCheckbox ( const char \* title, int i, int j)

add a yes or no type of option to an existing input window at the i,j-th cell

#### **Parameters**

int	row number
int	column number

Definition at line 428 of file TC\_Main\_api.c.

# 5.5.2.2 TCAPIEXPORT void tc\_addInputWindowOptions ( const char \* title, int i, int j, tc\_strings options )

add options to an existing input window at the i,j-th cell. Options will appear in a list

#### **Parameters**

string	name of an input window that was just created
int	row number
int	column number
tc_string	place these options (drop-down meny) at the (row,column) location of the
	table

Definition at line 417 of file TC\_Main\_api.c.

# 5.5.2.3 TCAPIEXPORT int tc\_askQuestion ( const char \* message )

display a dialog with a text and a yes and no button

### **Parameters**

const	char* displayed message or question
string	displayed message or question

Definition at line 684 of file TC\_Main\_api.c.

# 5.5.2.4 TCAPIEXPORT void tc\_burn ( long item, double intensity )

burn

shows a fire icon next to the item

#### **Parameters**

int	address of item in model, e.g. obtained from tc_find
double	intensity of the fire (0-1)

Definition at line 1225 of file TC\_Main\_api.c.

# 5.5.2.5 TCAPIEXPORT void tc\_clear ( )

cleat the contents in the output window.

cleat the contents in the output window

Definition at line 243 of file TC\_Main\_api.c.

# 5.5.2.6 TCAPIEXPORT void tc\_createInputWindow ( $tc_matrix input$ , const char \* title, void(\*)( $tc_matrix$ ) f)

create an input window that can call a dynamic library create an input window that will call a function

#### **Parameters**

tc_	_matrix	input window's arguments a default values
	string	name of this program
	void*	pointer to a 1-argument function that takes tc_matrix argument

Definition at line 406 of file TC\_Main\_api.c.

# 5.5.2.7 TCAPIEXPORT void tc\_createInputWindowForScript ( $tc_matrix input$ , const char \* title, const char \* functionname )

create an input window that can call a dynamic library

create an input window that will call a function in the console window with the arguments from the input matrix

# **Parameters**

tc_matrix	input window's arguments a default values
string	name of the program
string	name of function

Definition at line 395 of file TC\_Main\_api.c.

# 5.5.2.8 TCAPIEXPORT void tc\_createSliders ( tc\_matrix input, void(\*)(tc\_matrix) f)

create a window with several sliders. when the sliders change, the given function will be called with the values in the sliders

### **Parameters**

tc_matrix	names of variables and initial values for the sliders
void*	callback function with tc_matrix as the argument

Definition at line 742 of file TC\_Main\_api.c.

# 5.5.2.9 TCAPIEXPORT void tc\_displayNumber ( long item, double number )

displays the given number on the given item (the text is temporary)

#### **Parameters**

int	address of item in model, e.g. obtained from tc_find
double	number to display

Definition at line 1192 of file TC\_Main\_api.c.

# 5.5.2.10 TCAPIEXPORT void tc\_displayText ( long item, const char \* text )

displays the given text on the given item (the text is temporary)

### **Parameters**

int	address of item
string	text to display

Definition at line 1181 of file TC\_Main\_api.c.

# 5.5.2.11 TCAPIEXPORT void tc\_errorReport ( const char \* text )

show error text in the output window.

show error text in the output window

### **Parameters**

string	error message

Definition at line 210 of file TC\_Main\_api.c.

# 5.5.2.12 TCAPIEXPORT const char \* tc\_getFilename ( )

get a file from the user (dialog)
popup dialog asking user to select a file

#### Returns

string the filename selected by the user

Definition at line 636 of file TC\_Main\_api.c.

### 5.5.2.13 TCAPIEXPORT double tc\_getNumber ( const char \* title )

get a number from the user (dialog) popup dialog asking user for a number

# **Parameters**

string	text presented to the user
--------	----------------------------

## Returns

double user's response

Definition at line 660 of file TC\_Main\_api.c.

# 5.5.2.14 TCAPIEXPORT void tc\_getNumbers ( $tc\_strings$ labels, double \* result )

get a list of numbers from the user (dialog) into the argument array popup dialog asking user for several numbers (with labels)

### **Parameters**

tc_strings	labels for each number to get
double*	array that will store the results

Definition at line 672 of file TC\_Main\_api.c.

# 5.5.2.15 TCAPIEXPORT const char \* tc\_getStringDialog ( const char \* title )

get a text from the user (dialog)

Definition at line 624 of file TC\_Main\_api.c.

# 5.5.2.16 TCAPIEXPORT int tc\_getStringFromList ( const char \* title, tc\_strings list, const char \* selectedString )

get a text from the user (dialog) from a list of selections popup dialog asking user to select one item from a list

#### **Parameters**

stri	ng	title of dialog
tc_stri	ng	list of options
stri	ng	the option that is selected by default

#### Returns

int index of the user's selection, -1 if canceled

Definition at line 648 of file TC\_Main\_api.c.

# 5.5.2.17 TCAPIEXPORT void tc\_highlight ( long item, const char \* color )

highlights an item (the highlight is temporary) with the given color (hex) highlights an item (the highlight is temporary) with the given color

### **Parameters**

int	address of item in model, e.g. obtained from tc_find
string	HEX code for color

Definition at line 1214 of file TC\_Main\_api.c.

# 5.5.2.18 TCAPIEXPORT void tc\_messageDialog ( const char \* message )

display a dialog with a text message and a close button

# **Parameters**

const	char* displayed message
string	displayed message

Definition at line 697 of file TC\_Main\_api.c.

# 5.5.2.19 TCAPIEXPORT void tc\_openFile ( const char \* message )

open file

open a file

### **Parameters**

const	char* file
string	file name

Definition at line 709 of file TC\_Main\_api.c.

# 5.5.2.20 TCAPIEXPORT void tc\_openNewWindow ( const char \* title )

open a new graphics window

# **Parameters**

string title of the new windo	V
-------------------------------	---

Definition at line 439 of file TC\_Main\_api.c.

# 5.5.2.21 TCAPIEXPORT void tc\_openUrl ( const char \* url )

show text in the output window.

open any file or URL using the default app

### **Parameters**

string	file name

Definition at line 199 of file TC\_Main\_api.c.

# 5.5.2.22 TCAPIEXPORT void tc\_print ( const char \* text )

show text in the output window.

show text in the output window

# **Parameters**

string	text message

Definition at line 188 of file TC\_Main\_api.c.

# 5.5.2.23 TCAPIEXPORT void $tc_printFile$ ( const char \* filename )

show file contents in the output window.

show file contents in the output window

### **Parameters**

string	file name

Definition at line 232 of file TC\_Main\_api.c.

# 5.5.2.24 TCAPIEXPORT void tc\_printMatrix ( $tc_matrix data$ )

show table in the output window.

show table in the output window

#### **Parameters**

tc_matrix	table

Definition at line 221 of file TC\_Main\_api.c.

# 5.5.2.25 TCAPIEXPORT void tc\_saveToFile ( const char \* message )

save to file

save current network

### **Parameters**

const	char* file
string	filename

Definition at line 721 of file TC\_Main\_api.c.

# 5.5.2.26 TCAPIEXPORT int tc\_screenHeight ( )

get height of current canvas

### Returns

int height

Definition at line 865 of file TC\_Main\_api.c.

# 5.5.2.27 TCAPIEXPORT void tc\_screenshot ( const char \* filename, int width, int height )

save screenshot in a file

# **Parameters**

string	filename (PNG)
int	width of image
int	height of image

Definition at line 844 of file TC\_Main\_api.c.

### 5.5.2.28 TCAPIEXPORT int tc\_screenWidth ( )

get width of current canvas

### Returns

int width

Definition at line 854 of file TC\_Main\_api.c.

# 5.5.2.29 TCAPIEXPORT int tc\_screenX ( )

get x position of current canvas

### **Returns**

int x

Definition at line 876 of file TC\_Main\_api.c.

# 5.5.2.30 TCAPIEXPORT int tc\_screenY ( )

get y position of current canvas

### **Returns**

int y

Definition at line 887 of file TC\_Main\_api.c.

# 5.5.2.31 TCAPIEXPORT void tc\_setDisplayLabelColor ( const char \* color1, const char \* color2 )

set the color for the number or text when using tc\_displayNumber and tc\_displayText

### **Parameters**

string	HEX code for text color
string	HEX code for background color

Definition at line 1203 of file TC\_Main\_api.c.

# 5.5.2.32 TCAPIEXPORT void tc\_showProgress ( const char \* title, int progress )

show progress of current operation

# **Parameters**

string	label for the progress bar
int	progress in range 0-100

Definition at line 1129 of file TC\_Main\_api.c.

# 5.5.2.33 TCAPIEXPORT void tc\_zoom ( double factor )

zoom by the given factor (0 - 1)

### **Parameters**

double	zoom factor between 0 and 1
--------	-----------------------------

Definition at line 613 of file TC\_Main\_api.c.

# 5.6 System information

get information about the OS and program directory

# **Functions**

• TCAPIEXPORT int tc\_isWindows ()

 $is\ this\ running\ in\ MS\ windows?$ 

• TCAPIEXPORT int tc\_isMac ()

is this running in a Mac?

• TCAPIEXPORT int tc\_isLinux ()

 $is\ this\ running\ in\ Linux?$ 

• TCAPIEXPORT const char \* tc\_appDir ()

 ${\it Tinker Cell\ application\ folder}.$ 

• TCAPIEXPORT const char \* tc\_homeDir ()

TinkerCell home folder.

# 5.6.1 Detailed Description

get information about the OS and program directory

### 5.6.2 Function Documentation

# 5.6.2.1 TCAPIEXPORT const char \* tc\_appDir ( )

TinkerCell application folder.

### Returns

string application folder path

Definition at line 371 of file TC\_Main\_api.c.

# 5.6.2.2 TCAPIEXPORT const char \* tc\_homeDir ( )

TinkerCell home folder.

### Returns

string home folder path

Definition at line 383 of file TC\_Main\_api.c.

# 5.6.2.3 TCAPIEXPORT int tc\_isLinux ( )

is this running in Linux?

is this running in a Unix system (excluding Mac)?

## Returns

```
0 (not Linux) or 1 (is Linux)
```

Definition at line 359 of file TC\_Main\_api.c.

# 5.6.2.4 TCAPIEXPORT int tc\_isMac ( )

is this running in a Mac?

# Returns

```
0 (not Mac OS ) or 1 (is Mac OS)
```

Definition at line 347 of file TC\_Main\_api.c.

# 5.6.2.5 TCAPIEXPORT int tc\_isWindows ( )

is this running in MS windows?

5.7 Network data 51

#### Returns

0 (not windows OS) or 1 (is windows OS)

Definition at line 335 of file TC\_Main\_api.c.

# 5.7 Network data

get/set information about the individual items in the network get/set information about the individual items in the network

# 5.8 Graphing

display graphs, save graphs, get graph values

### **Functions**

- TCAPIEXPORT void tc\_surface (tc\_matrix z, const char \*title)

  plot 3D data. Input matrix has x,y on the first two columns and z on the third column
- TCAPIEXPORT void tc\_plot (tc\_matrix data, const char \*title)

  plot the data in the matrix (with headers) with the given x-axis and title
- TCAPIEXPORT void tc\_scatterplot (tc\_matrix data, const char \*title) plot the 2-columns in the matrix (with headers) as a scatter plot
- TCAPIEXPORT void tc\_errorBars (tc\_matrix data, const char \*title)

  plot the data in the matrix (with headers) with the given x-axis and title. For each column i, the i+1 and i+2 columns should contain the upper and lower bounds (errors).
- TCAPIEXPORT void tc\_hist (tc\_matrix data, const char \*title)

  plot histogram for each column of the given matrix with the given bin size.
- TCAPIEXPORT void tc\_multiplot (int rows, int cols)
   enable multi-plot, i.e. multiple plots on one screen. specify the number of rows and columns for the layout.
- TCAPIEXPORT void tc\_holdPlot (int z)

  enable hold
- TCAPIEXPORT void tc\_clusterPlots (int c) enable clustering
- TCAPIEXPORT tc\_matrix tc\_getPlotData (int whichPlot)

get the data that is currently in the plot window

- TCAPIEXPORT void tc\_gnuplot (const char \*s)
   gnuplot
- TCAPIEXPORT void tc\_savePlot (const char \*filename)

  save plot
- TCAPIEXPORT void tc\_setLogScale (int i)
   save plot

# 5.8.1 Detailed Description

display graphs, save graphs, get graph values

### 5.8.2 Function Documentation

# 5.8.2.1 TCAPIEXPORT void tc\_clusterPlots (int clusters)

enable clustering
perform clustering on plots

# **Parameters**

int	number of clusters (must be $> 1$ )

Definition at line 85 of file TC\_PlotTool\_api.c.

# 5.8.2.2 TCAPIEXPORT void tc\_errorBars ( $tc_matrix\ \textit{data}$ , const char \* title )

plot the data in the matrix (with headers) with the given x-axis and title. For each column i, the i+1 and i+2 columns should contain the upper and lower bounds (errors).

### **Parameters**

tc_matrix	data
string	title of plot

Definition at line 41 of file TC\_PlotTool\_api.c.

# $5.8.2.3 \quad \text{TCAPIEXPORT } tc\_matrix \; tc\_getPlotData \left( \right. int \; \textit{whichPlot} \; \right)$

get the data that is currently in the plot window get the data in the plot window

5.8 Graphing 53

#### **Parameters**

int index of the plot (if multiple plots are being displayed)

# Returns

tc matrix data

Definition at line 96 of file TC\_PlotTool\_api.c.

# 5.8.2.4 TCAPIEXPORT void tc\_gnuplot ( const char \* )

gnuplot

plot the specific script using gnuplot

#### **Parameters**

string	gnuplot commands

Definition at line 114 of file TC\_PlotTool\_api.c.

# 5.8.2.5 TCAPIEXPORT void tc\_hist ( tc\_matrix data, const char \* title )

plot histogram for each column of the given matrix with the given bin size.

# Parameters

tc_matrix	data
string	title of plot

Definition at line 52 of file TC\_PlotTool\_api.c.

# 5.8.2.6 TCAPIEXPORT void tc\_holdPlot ( int on )

enable hold

hold current plot and plot on top of it

### Parameters

```
int on(1) or off (0)
```

Definition at line 74 of file TC\_PlotTool\_api.c.

# 5.8.2.7 TCAPIEXPORT void tc\_multiplot (int rows, int cols)

enable multi-plot, i.e. multiple plots on one screen. specify the number of rows and columns for the layout.

#### **Parameters**

int	number of rows
int	number of columns

Definition at line 63 of file TC\_PlotTool\_api.c.

# 5.8.2.8 TCAPIEXPORT void tc\_plot ( tc\_matrix data, const char \* title )

plot the data in the matrix (with headers) with the given x-axis and title

# **Parameters**

tc	_matrix	data with first column being the x-axis
	string	title of plot

Definition at line 19 of file TC\_PlotTool\_api.c.

### 5.8.2.9 TCAPIEXPORT void tc\_savePlot ( const char \* filename )

save plot

save the current plot as a PDF file

# **Parameters**

string	filename (PDF suffix)

Definition at line 125 of file TC\_PlotTool\_api.c.

# 5.8.2.10 TCAPIEXPORT void tc\_scatterplot ( $tc_matrix\ data$ , const char \* title )

plot the 2-columns in the matrix (with headers) as a scatter plot plot the data in the matrix (with headers) as a scatter plot

# **Parameters**

tc_matrix	data with first column as x-axis
string	title of plot

Definition at line 30 of file TC\_PlotTool\_api.c.

# 5.8.2.11 TCAPIEXPORT void tc\_setLogScale (int)

save plot

set log scale for current plot; argument: 0=x-axis, 1=y-axis, 2=both

5.9 Modeling 55

#### **Parameters**

```
int 0=x-axis, 1=y-axis, 2=both
```

Definition at line 136 of file TC\_PlotTool\_api.c.

# 5.8.2.12 BEGIN\_C\_DECLS TCAPIEXPORT void tc\_surface ( tc\_matrix z, const char \* title )

plot 3D data. Input matrix has x,y on the first two columns and z on the third column

#### **Parameters**

tc_matrix	tree column matrix
string	title of plot

Definition at line 8 of file TC\_PlotTool\_api.c.

# 5.9 Modeling

get/set parameters, equations, and so on

### **Functions**

- BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_getParameters (tc\_items a) get all the parameters for the given items. use tc\_allItems() as argument to get all parameters
- TCAPIEXPORT tc\_matrix tc\_getInitialValues (tc\_items a) get initial values of the given items. Fixed varianbles are included. use tc\_allItems() for all items in the model.
- TCAPIEXPORT void tc\_setInitialValues (tc\_items items, tc\_matrix values) set initial values of the given items.
- TCAPIEXPORT tc\_matrix tc\_getFixedVariables (tc\_items a) get all fixed variables
- TCAPIEXPORT tc\_matrix tc\_getParametersAndFixedVariables (tc\_items a) get all the parameters and fixed variables
- TCAPIEXPORT double tc\_getParameter (long item, const char \*attribute) get the parameter with the given name for the given item
- TCAPIEXPORT tc\_matrix tc\_getParametersNamed (tc\_items a, tc\_strings attibutes)

get all numerical Modeling with the given names for the given items

TCAPIEXPORT tc\_matrix tc\_getParametersExcept (tc\_items a, tc\_strings attributes)

get all numerical Modeling EXCEPT the given names

TCAPIEXPORT void tc\_setParameter (long item, const char \*attribute, double value)

set a parameter value for the given item

• TCAPIEXPORT void tc\_setParameterByName (const char \*attribute, double value)

set a parameter value

- TCAPIEXPORT void tc\_setParameters (tc\_matrix, int)
   set parameter for multiple items
- BEGIN\_C\_DECLS TCAPIEXPORT tc\_strings tc\_getEventTriggers ()
   get the event triggers for a set of items
- TCAPIEXPORT tc\_strings tc\_getEventResponses ()
   get the event responses for a set of items
- TCAPIEXPORT void tc\_addEvent (const char \*trigger, const char \*event) set the event trigger and response
- TCAPIEXPORT tc\_strings tc\_getForcingFunctionNames (tc\_items a) get the forcing function names for a set of items
- TCAPIEXPORT tc\_strings tc\_getForcingFunctionAssignments (tc\_items a) get the forcing function definitions for a set of items
- TCAPIEXPORT void tc\_addForcingFunction (long item, const char \*variable, const char \*formula)

set the forcing function for an item

- TCAPIEXPORT int tc\_writeModel (const char \*file, tc\_items items) write the ODE, stoichiometry, and rates functions to a file
- BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_getStoichiometry (tc\_items A)

get Modeling for the given items

- TCAPIEXPORT void tc\_setStoichiometry (tc\_items A, tc\_matrix N) set Modeling for the given items (must be labeled)
- TCAPIEXPORT tc\_strings tc\_getRates (tc\_items A)

5.9 Modeling 57

get rates for the given items

• TCAPIEXPORT void tc\_setRates (tc\_items A, tc\_strings rates) set rates for the given items (same order as N)

• TCAPIEXPORT tc\_matrix tc\_getStoichiometryFor (long x) get Modeling for the given items

• TCAPIEXPORT const char \* tc\_getRate (long x) get rate for the given items

• TCAPIEXPORT void tc\_setRate (long x, const char \*r) set rate for the given items

• TCAPIEXPORT void tc\_setStoichiometryFor (long x, tc\_matrix N) set Modeling for the given items

TCAPIEXPORT void tc\_StoichiometryTool\_api (tc\_matrix(\*getStoichiometry)(tc\_items), void(\*setStoichiometry)(tc\_items, tc\_matrix), tc\_strings(\*getRates)(tc\_items), void(\*setRates)(tc\_items, tc\_strings))
 initialize stiochiometry plug-in

## 5.9.1 Detailed Description

get/set parameters, equations, and so on

#### 5.9.2 Function Documentation

5.9.2.1 TCAPIEXPORT void tc\_addEvent ( const char \* trigger, const char \* event )

set the event trigger and response

#### **Parameters**

string	trigger, e.g. $a > 2$
string	response to trigger, e.g. $x = 5$

Definition at line 32 of file TC\_EventsAssignments\_api.c.

## 5.9.2.2 TCAPIEXPORT void tc\_addForcingFunction ( long item, const char \* variable, const char \* formula )

set the forcing function for an item

#### **Parameters**

int	address of an item, e.g. obtained from tc_find
string	name of existing variable or new variable
string	formula for the variable

Definition at line 82 of file TC\_EventsAssignments\_api.c.

## 5.9.2.3 TCAPIEXPORT tc\_strings tc\_getEventResponses ( )

get the event responses for a set of items

#### Returns

tc\_strings all event trigger responses, e.g. A = 10; B = 2

Definition at line 20 of file TC\_EventsAssignments\_api.c.

#### 5.9.2.4 BEGIN\_C\_DECLS TCAPIEXPORT tc\_strings tc\_getEventTriggers ( )

get the event triggers for a set of items

#### Returns

tc\_strings all event trigger equations, e.g. A > 10

Definition at line 8 of file TC\_EventsAssignments\_api.c.

## 5.9.2.5 TCAPIEXPORT tc\_matrix tc\_getFixedVariables ( tc\_items a )

get all fixed variables

#### **Parameters**

tc_items	list of items for which fixed attribute are set
tc_matrix	matrix with 1 (fixed) or 0 (floating) in the same order as the list of items

Definition at line 47 of file TC\_BasicInformationTool\_api.c.

## 5.9.2.6 TCAPIEXPORT $tc\_strings\ tc\_getForcingFunctionAssignments\ (\ tc\_items\ a\ )$

get the forcing function definitions for a set of items

## **Parameters**

tc\_items list of items. use tc\_allItems() to get all forcing functions

5.9 Modeling 59

#### Returns

tc\_strings list of assignment equations

Definition at line 70 of file TC\_EventsAssignments\_api.c.

## 5.9.2.7 TCAPIEXPORT tc\_strings tc\_getForcingFunctionNames ( tc\_items a )

get the forcing function names for a set of items

#### **Parameters**

*tc\_items* list of items. use tc\_allItems() to get all forcing functions

#### Returns

tc\_strings list of variable names

Definition at line 58 of file TC\_EventsAssignments\_api.c.

#### 5.9.2.8 TCAPIEXPORT tc\_matrix tc\_getInitialValues (tc\_items a)

get initial values of the given items. Fixed varianbles are included. use tc\_allItems() for all items in the model.

#### **Parameters**

tc items	s list of items for which the initial values are returned	

#### Returns

tc\_matrix initial values in the same order as the input list

Definition at line 23 of file TC\_BasicInformationTool\_api.c.

## 5.9.2.9 TCAPIEXPORT double tc\_getParameter ( long item, const char \* attribute )

get the parameter with the given name for the given item

#### **Parameters**

int	item in the model, e.g. something returned from tc_find
string	name of the parameter

#### Returns

double value

Definition at line 83 of file TC\_BasicInformationTool\_api.c.

#### 5.9.2.10 BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_getParameters ( tc\_items a )

get all the parameters for the given items. use tc\_allItems() as argument to get all parameters

#### **Parameters**

tc\_items list of items for which the parameters are returned

#### Returns

tc\_matrix parameter values in the same order as the input list

Definition at line 10 of file TC\_BasicInformationTool\_api.c.

#### 5.9.2.11 TCAPIEXPORT tc\_matrix tc\_getParametersAndFixedVariables ( tc\_items a )

get all the parameters and fixed variables

#### **Parameters**

tc\_items list of items. use tc\_allItems() to get all items in the model

#### Returns

tc\_matrix list of parameters and fixed variables. order is not preserved from the input

Definition at line 59 of file TC\_BasicInformationTool\_api.c.

## 5.9.2.12 TCAPIEXPORT tc\_matrix tc\_getParametersExcept ( tc\_items a, tc\_strings attributes )

get all numerical Modeling EXCEPT the given names

## **Parameters**

tc_items	a list of items
tc_strings	a list of parameter names that exist in one or more of the given items

#### Returns

tc\_matrix the set of parameters with rownames as parameter names

Definition at line 107 of file TC\_BasicInformationTool\_api.c.

## 5.9.2.13 TCAPIEXPORT tc\_matrix tc\_getParametersNamed ( tc\_items a, tc\_strings attibutes )

get all numerical Modeling with the given names for the given items

5.9 Modeling 61

#### **Parameters**

tc_items	a list of items
tc_strings	a list of parameter names that exist in one or more of the given items

#### Returns

tc\_matrix the set of parameters with rownames as parameter names

Definition at line 95 of file TC\_BasicInformationTool\_api.c.

### 5.9.2.14 TCAPIEXPORT const char\* tc\_getRate ( long x )

get rate for the given items

#### **Parameters**

int	address of a connection item
-----	------------------------------

#### Returns

tc\_matrix reaction rate equations for given item

Definition at line 66 of file TC\_StoichiometryTool\_api.c.

## 5.9.2.15 TCAPIEXPORT tc\_strings tc\_getRates ( tc\_items A )

get rates for the given items

## **Parameters**

tc_items	list of items to get reaction rate equations from. use tc_allItems() for whole
	model.

## Returns

tc\_strings reaction rate equations for given items

Definition at line 32 of file TC\_StoichiometryTool\_api.c.

## 5.9.2.16 BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_getStoichiometry ( tc\_items A )

get Modeling for the given items

### **Parameters**

tc_items	list of items to get stoichiometry matrix from. use tc_allItems() for whole	1
	model.	

#### **Returns**

tc\_matrix stoichiometry matrix with rownames (molecules) and column names (reactions)

Definition at line 9 of file TC\_StoichiometryTool\_api.c.

#### 5.9.2.17 TCAPIEXPORT tc\_matrix tc\_getStoichiometryFor ( long x )

get Modeling for the given items

#### **Parameters**

int	address of a connection item

#### Returns

tc\_matrix stoichiometry matrix for the item

Definition at line 54 of file TC\_StoichiometryTool\_api.c.

#### 5.9.2.18 TCAPIEXPORT void tc\_setInitialValues ( tc\_items items, tc\_matrix values )

set initial values of the given items.

#### **Parameters**

tc_items	list of items for which initial values are set
tc_matrix	the initial values in the same order as the list of items

Definition at line 36 of file TC\_BasicInformationTool\_api.c.

## 5.9.2.19 TCAPIEXPORT void tc\_setParameter ( long item, const char \* attribute, double value )

set a parameter value for the given item

#### **Parameters**

int	item in model
string	name of parameter

Definition at line 142 of file TC\_BasicInformationTool\_api.c.

### 5.9.2.20 TCAPIEXPORT void tc\_setParameterByName ( const char \* attribute, double value )

set a parameter value

5.9 Modeling 63

#### **Parameters**

string	full name of parameter, e.g. A.k0 or A_k0
double	value

Definition at line 153 of file TC\_BasicInformationTool\_api.c.

#### 5.9.2.21 TCAPIEXPORT void tc\_setParameters ( tc\_matrix , int )

set parameter for multiple items

#### **Parameters**

tc_table	table with rownames as the parameter full names
int	0=temporarily (just for simulation, fast), 1 = permanent (slower)

Definition at line 163 of file TC\_BasicInformationTool\_api.c.

#### 5.9.2.22 TCAPIEXPORT void tc\_setRate ( long x, const char \* r )

set rate for the given items

#### **Parameters**

int	address of a connection item
tc_matrix	reaction rate equations for given item

Definition at line 80 of file TC\_StoichiometryTool\_api.c.

## 5.9.2.23 TCAPIEXPORT void tc\_setRates ( tc\_items A, tc\_strings rates )

set rates for the given items (same order as N)

## **Parameters**

tc_items	list of items to set reaction rate equations for. use tc_allItems() for whole
	model.

#### Returns

tc\_strings reaction rate equations for given items

Definition at line 44 of file TC\_StoichiometryTool\_api.c.

## 5.9.2.24 TCAPIEXPORT void tc\_setStoichiometry ( tc\_items A, tc\_matrix N )

set Modeling for the given items (must be labeled)

#### **Parameters**

tc_items	list of items to set stoichiometry matrix for. use tc_allItems() for whole
	model.
tc_matrix	new stoichiometry matrix with rownames (molecules) and column names
	(reactions) \

Definition at line 21 of file TC\_StoichiometryTool\_api.c.

### 5.9.2.25 TCAPIEXPORT void tc\_setStoichiometryFor ( long x, tc\_matrix N )

set Modeling for the given items

#### **Parameters**

int	address of a connection item
tc_matrix	stoichiometry matrix for given item

Definition at line 103 of file TC\_StoichiometryTool\_api.c.

5.9.2.26 TCAPIEXPORT void tc\_StoichiometryTool\_api ( tc\_matrix(\*)(tc\_items) getStoichiometry, void(\*)(tc\_items, tc\_matrix) setStoichiometry, tc\_strings(\*)(tc\_items) getRates, void(\*)(tc\_items, tc\_strings) setRates )

initialize stiochiometry plug-in

Definition at line 115 of file TC\_StoichiometryTool\_api.c.

#### 5.9.2.27 TCAPIEXPORT int tc\_writeModel ( const char \* file, tc\_items items )

write the ODE, stoichiometry, and rates functions to a file

#### **Parameters**

string	output filename
tc_items	items to include in the model. use tc_allItems for the whole model

Definition at line 8 of file TC\_ModelFileGenerator\_api.c.

## 5.10 Connections

change appearance of connection arcs

## **Functions**

• TCAPIEXPORT long tc\_insertConnection (tc\_items parts, const char \*name, const char \*family)

5.10 Connections 65

connect a set of parts (in) to another (out). give the connection name and family. returns the inserted connection

• TCAPIEXPORT tc\_items tc\_getConnectedNodes (long connection) get the connected parts for a connection

 TCAPIEXPORT tc\_items tc\_getConnectedNodesWithRole (long connection, const char \*role)

get the parts with a role in a connection, such as reactants

• TCAPIEXPORT tc\_items tc\_getConnections (long part) get connections for a part

• TCAPIEXPORT tc\_items tc\_getConnectionsWithRole (long part, const char \*role)

get connections where the given part has the given role, e.g. reactant

BEGIN\_C\_DECLS TCAPIEXPORT double tc\_getControlPointX (long connection, long part, int whichPoint)

get x position of a control point

• TCAPIEXPORT double tc\_getControlPointY (long connection, long part, int whichPoint)

get y position of a control point

• TCAPIEXPORT void tc\_setControlPoint (long connection, long part, int which-Point, double x, double y)

set x and y position of a control point

- TCAPIEXPORT void tc\_setCenterPoint (long connection, double y, double x) set x and y position of the central control point
- TCAPIEXPORT double tc\_getCenterPointX (long connection) get x position of the central control point
- TCAPIEXPORT double tc\_getCenterPointY (long connection) get y position of the central control point
- TCAPIEXPORT void tc\_setStraight (long item, int straight)

  switch between beziers and lines for drawing the connector, where 1 = line, 0 = bezier
- TCAPIEXPORT void tc\_setAllStraight (int straight)
   switch between beziers and lines for drawing ALL connectors
- TCAPIEXPORT void tc\_setLineWidth (long item, double width, int permanent)

set the line width. Indicate whether the change should be temporary or permanent.

#### 5.10.1 Detailed Description

change appearance of connection arcs

#### 5.10.2 Function Documentation

## 5.10.2.1 TCAPIEXPORT double tc\_getCenterPointX ( long connection )

get x position of the central control point

#### **Parameters**

int address of a connection, e.g. obtained using tc\_find

#### Returns

double x position

Definition at line 59 of file TC\_ConnectionSelection\_api.c.

#### 5.10.2.2 TCAPIEXPORT double tc\_getCenterPointY ( long connection )

get y position of the central control point

#### **Parameters**

int	address	of a	connection, e.s	z. obtained	l using tc	find
-----	---------	------	-----------------	-------------	------------	------

#### Returns

double y position

Definition at line 71 of file TC\_ConnectionSelection\_api.c.

#### 5.10.2.3 TCAPIEXPORT tc\_items tc\_getConnectedNodes ( long connection )

get the connected parts for a connection

#### **Parameters**

int address of a connection, e.g. obtained using tc\_find

#### Returns

tc\_items all nodes connection by the given connection

Definition at line 20 of file TC\_ConnectionInsertion\_api.c.

5.10 Connections 67

## 5.10.2.4 TCAPIEXPORT $tc\_items$ $tc\_getConnectedNodesWithRole$ ( long connection, const char \* role )

get the parts with a role in a connection, such as reactants get the parts with a specific role in the given connection, such as reactant

#### **Parameters**

int	address of a connection, e.g. obtained using tc_find
string	a role, e.g. Reactant

#### Returns

tc\_items all nodes in the given connection with the given role

Definition at line 32 of file TC\_ConnectionInsertion\_api.c.

#### 5.10.2.5 TCAPIEXPORT tc\_items tc\_getConnections ( long part )

get connections for a part

#### **Parameters**

int address of a node, e.g. obtained using tc_find	
----------------------------------------------------	--

#### Returns

tc\_items all connections linked to the given node

Definition at line 44 of file TC\_ConnectionInsertion\_api.c.

## 5.10.2.6 TCAPIEXPORT $tc\_items$ $tc\_getConnectionsWithRole$ ( long part, const char \* role )

get connections where the given part has the given role, e.g. reactant get connections where the given parts has a specific role, such as reactant

#### **Parameters**

int	address of a node, e.g. obtained using tc_find
string	a role, such as reactant

#### Returns

tc\_items connections linked to the given node with the given role

Definition at line 56 of file TC\_ConnectionInsertion\_api.c.

## 5.10.2.7 BEGIN\_C\_DECLS TCAPIEXPORT double tc\_getControlPointX ( long *connection*, long *part*, int *whichPoint* )

get x position of a control point

#### **Parameters**

int	address of a connection, e.g. obtained using tc_find
int	address of a node, e.g. obtained using tc_find
int	index of the control point related to the given connection and the given node

#### Returns

double x position

Definition at line 8 of file TC\_ConnectionSelection\_api.c.

## 5.10.2.8 TCAPIEXPORT double tc\_getControlPointY ( long *connection,* long *part,* int *whichPoint* )

get y position of a control point

#### **Parameters**

int	address of a connection, e.g. obtained using tc_find
int	address of a node, e.g. obtained using tc_find
int	index of the control point related to the given connection and the given node

### Returns

double y position

Definition at line 20 of file TC\_ConnectionSelection\_api.c.

## 5.10.2.9 BEGIN\_C\_DECLS TCAPIEXPORT long tc\_insertConnection ( tc\_items parts, const char \* name, const char \* family )

connect a set of parts (in) to another (out). give the connection name and family. returns the inserted connection

connect a set of parts. The role of each part is automatically determined by its type. Give the connection name and family. returns the inserted connection

## **Parameters**

tc_items	nodes to be connected
string	name of new connection
string	type of the new connection, i.e. one of the connection types in the catalog

Definition at line 8 of file TC\_ConnectionInsertion\_api.c.

5.10 Connections 69

### 5.10.2.10 TCAPIEXPORT void tc\_setAllStraight (int straight)

switch between beziers and lines for drawing ALL connectors

#### **Parameters**

int 0 (Bezier) or 1 (straight lines)
--------------------------------------

Definition at line 94 of file TC\_ConnectionSelection\_api.c.

## 5.10.2.11 TCAPIEXPORT void tc\_setCenterPoint ( long connection, double y, double x )

set x and y position of the central control point

#### **Parameters**

int	address of a connection, e.g. obtained using tc_find
double	x position
double	y position

Definition at line 48 of file TC\_ConnectionSelection\_api.c.

## 5.10.2.12 TCAPIEXPORT void tc\_setControlPoint ( long *connection*, long *part*, int *whichPoint*, double *y*, double *y*)

set x and y position of a control point

## Parameters

long	the connection
long	the node that is associated with the particular curve of interest
int	the index of the point on that curve of interest
double	x value
double	y value

Definition at line 37 of file TC\_ConnectionSelection\_api.c.

## 5.10.2.13 TCAPIEXPORT void tc\_setLineWidth ( long item, double width, int permanent )

set the line width. Indicate whether the change should be temporary or permanent.

## **Parameters**

int	address of a connection, e.g. obtained using tc_find
double	line width
int	0 (temporary change) or 1 (permanent change)

Definition at line 105 of file TC\_ConnectionSelection\_api.c.

#### 5.10.2.14 TCAPIEXPORT void tc\_setStraight ( long item, int straight )

switch between beziers and lines for drawing the connector, where 1 = line, 0 = bezier

#### **Parameters**

int	address of a connection, e.g. obtained using tc_find
int	0 (Bezier) or 1 (straight lines)

Definition at line 83 of file TC\_ConnectionSelection\_api.c.

## 5.11 Import/Export

Import/Export different file formats.

#### **Functions**

- TCAPIEXPORT void tc\_exportSBML (const char \*s) save sbml format to a file
- TCAPIEXPORT void tc\_importSBML (const char \*s) load sbml model as string

## 5.11.1 Detailed Description

Import/Export different file formats.

## 5.11.2 Function Documentation

## 5.11.2.1 BEGIN\_C\_DECLS TCAPIEXPORT void tc\_exportSBML ( const char \* s )

save sbml format to a file

#### **Parameters**

const	char* file name

Definition at line 9 of file TC\_SBML\_api.c.

#### 5.11.2.2 TCAPIEXPORT void tc\_importSBML ( const char \* s )

load sbml model as string

5.12 Simulation 71

#### **Parameters**

const | char\* sbml model file or string

Definition at line 21 of file TC SBML api.c.

## 5.12 Simulation

Simulations and other numerical analysis.

#### **Functions**

BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_simulateDeterministic (double startTime, double endTime, int numSteps)
 simulate using LSODA numerical integrator

• TCAPIEXPORT tc\_matrix tc\_simulateStochastic (double startTime, double end-Time, int numSteps)

simulate using exact stochastic algorithm

 TCAPIEXPORT tc\_matrix tc\_simulateHybrid (double startTime, double end-Time, int numSteps)

simulate using Hybrid algorithm/deterministic algorithmparam double start time

• TCAPIEXPORT tc\_matrix tc\_simulateTauLeap (double startTime, double end-Time, int numSteps)

simulate using Tau Leap stochastic algorithm

• TCAPIEXPORT tc\_matrix tc\_getSteadyState ()

bring the system to steady state

TCAPIEXPORT tc\_matrix tc\_steadyStateScan (const char \*param, double start, double end, int numSteps)

calculate steady state for each value of a parameter

• TCAPIEXPORT tc\_matrix tc\_steadyStateScan2D (const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2)

calculate steady state for each value of two parameters

• TCAPIEXPORT tc\_matrix tc\_getJacobian ()

get the Jacobian at the current state

• TCAPIEXPORT tc\_matrix tc\_getEigenvalues ()

get the eigenvalues of the Jacobian at the current state

TCAPIEXPORT tc\_matrix tc\_getUnscaledElasticities ()
 unscaled elasticities

TCAPIEXPORT tc\_matrix tc\_getUnscaledConcentrationCC ()
 unscaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getUnscaledFluxCC ()
unscaled flux control coefficients

TCAPIEXPORT tc\_matrix tc\_getScaledElasticities ()
 scaled elasticities

TCAPIEXPORT tc\_matrix tc\_getScaledConcentrationCC ()
 scaled concentration control coefficients

TCAPIEXPORT tc\_matrix tc\_getScaledFluxCC ()
 scaled flux control coefficients

TCAPIEXPORT tc\_matrix tc\_reducedStoichiometry ()
 reduced stoichiometry

TCAPIEXPORT tc\_matrix tc\_elementaryFluxModes ()
 elementary flux modes

TCAPIEXPORT tc\_matrix tc\_LMatrix ()
 left nullspace of the stoichiometry matrix

TCAPIEXPORT tc\_matrix tc\_KMatrix ()
 right nullspace of the stoichiometry matrix

TCAPIEXPORT void tc\_updateParameters (tc\_matrix params)
 update the model parameters just for simulation purposes, i.e. not the actual model itself this function will be much faster than using tc\_setParameters

• TCAPIEXPORT tc\_matrix tc\_optimize (const char \*formulaOrFile)

Maximize the given formula or fit the data is the given filename, depending on whether or not the input is a filename. The optimization is done using genetic algorithms, so a distribution of optimal parameters is generated. All parameters in the model will be used where the parameter's min and max values are different (i.e. parameter is variable)

## 5.12.1 Detailed Description

Simulations and other numerical analysis.

5.12 Simulation 73

#### 5.12.2 Function Documentation

#### 5.12.2.1 TCAPIEXPORT tc\_matrix tc\_elementaryFluxModes ( )

elementary flux modes

#### Returns

```
tc_matrix
```

Definition at line 162 of file TC\_COPASI\_api.c.

### 5.12.2.2 TCAPIEXPORT tc\_matrix tc\_getEigenvalues ( )

get the eigenvalues of the Jacobian at the current state

#### Returns

tc\_matrix matrix with 1 row and n columns, each containing an eigenvalue

Definition at line 81 of file TC\_COPASI\_api.c.

#### 5.12.2.3 TCAPIEXPORT tc\_matrix tc\_getJacobian ( )

get the Jacobian at the current state

#### Returns

tc\_matrix matrix with n rows and n columns, where n = number of species

Definition at line 73 of file TC\_COPASI\_api.c.

## 5.12.2.4 TCAPIEXPORT $tc\_matrix\ tc\_getScaledConcentrationCC\ (\ )$

scaled concentration control coefficients

### Returns

tc\_matrix

Definition at line 121 of file TC\_COPASI\_api.c.

#### 5.12.2.5 TCAPIEXPORT tc\_matrix tc\_getScaledElasticities ( )

scaled elasticities

#### Returns

tc\_matrix

Definition at line 113 of file TC\_COPASI\_api.c.

## 5.12.2.6 TCAPIEXPORT tc\_matrix tc\_getScaledFluxCC() scaled flux control coefficients **Returns** tc\_matrix Definition at line 129 of file TC\_COPASI\_api.c. 5.12.2.7 TCAPIEXPORT tc\_matrix tc\_getSteadyState ( ) bring the system to steady state Returns tc\_matrix matrix with 1 row and n columns, where n = number of species Definition at line 65 of file TC\_COPASI\_api.c. 5.12.2.8 TCAPIEXPORT tc\_matrix tc\_getUnscaledConcentrationCC ( ) unscaled elasticities unscaled concentration control coefficients Returns tc\_matrix Definition at line 97 of file TC\_COPASI\_api.c. 5.12.2.9 TCAPIEXPORT tc\_matrix tc\_getUnscaledElasticities ( ) unscaled elasticities Returns tc\_matrix Definition at line 89 of file TC\_COPASI\_api.c. 5.12.2.10 TCAPIEXPORT tc\_matrix tc\_getUnscaledFluxCC() unscaled flux control coefficients

Definition at line 105 of file TC\_COPASI\_api.c.

Returns

tc\_matrix

5.12 Simulation 75

#### 5.12.2.11 TCAPIEXPORT tc\_matrix tc\_KMatrix ( )

right nullspace of the stoichiometry matrix

#### Returns

```
tc_matrix
```

Definition at line 178 of file TC\_COPASI\_api.c.

```
5.12.2.12 TCAPIEXPORT tc_matrix tc_LMatrix ( )
```

left nullspace of the stoichiometry matrix

#### Returns

```
tc matrix
```

Definition at line 170 of file TC\_COPASI\_api.c.

### 5.12.2.13 TCAPIEXPORT tc\_matrix tc\_optimize ( const char \* formulaOrFile )

Maximize the given formula or fit the data is the given filename, depending on whether or not the input is a filename. The optimization is done using genetic algorithms, so a distribution of optimal parameters is generated. All parameters in the model will be used where the parameter's min and max values are different (i.e. parameter is variable)

## Parameters

const char \* formula to maximize or filename with data (csv or tab-delimited)

### Returns

tc\_matrix a population of parameters

Definition at line 187 of file TC\_COPASI\_api.c.

### 5.12.2.14 TCAPIEXPORT tc\_matrix tc\_reducedStoichiometry ( )

reduced stoichiometry

### Returns

tc matrix

Definition at line 154 of file TC\_COPASI\_api.c.

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

## 5.12.2.15 BEGIN\_C\_DECLS TCAPIEXPORT $tc\_matrix$ tc\_simulateDeterministic ( double startTime, double endTime, int numSteps )

simulate using LSODA numerical integrator

#### **Parameters**

double	start time
double	end time
int	number of steps in the output

#### Returns

tc\_matrix matrix of concentration or particles

Definition at line 33 of file TC\_COPASI\_api.c.

## 5.12.2.16 TCAPIEXPORT tc\_matrix tc\_simulateHybrid ( double *startTime*, double *endTime*, int *numSteps* )

simulate using Hybrid algorithm/deterministic algorithmparam double start time

#### **Parameters**

double	end time
int	number of steps in the output

#### Returns

tc\_matrix matrix of concentration or particles

Definition at line 49 of file TC\_COPASI\_api.c.

## 5.12.2.17 TCAPIEXPORT tc\_matrix tc\_simulateStochastic ( double *startTime*, double *endTime*, int *numSteps* )

simulate using exact stochastic algorithm

#### **Parameters**

double	start time
double	end time
int	number of steps in the output

#### Returns

tc\_matrix matrix of concentration or particles

Definition at line 41 of file TC\_COPASI\_api.c.

5.12 Simulation 77

## 5.12.2.18 TCAPIEXPORT $tc\_matrix$ $tc\_simulateTauLeap$ ( double startTime, double endTime, int numSteps )

simulate using Tau Leap stochastic algorithm

#### **Parameters**

double	start time
double	end time
int	number of steps in the output

#### Returns

tc\_matrix matrix of concentration or particles

Definition at line 57 of file TC\_COPASI\_api.c.

## 5.12.2.19 TCAPIEXPORT $tc\_matrix\ tc\_steadyStateScan\ (const\ char*param,\ double\ start,\ double\ end,\ int\ numSteps\ )$

calculate steady state for each value of a parameter

#### **Parameters**

char	* parameter name
double	start value
double	end value
int	number of steps in the output

#### Returns

tc\_matrix matrix of concentration or particles

Definition at line 137 of file TC\_COPASI\_api.c.

5.12.2.20 TCAPIEXPORT tc\_matrix tc\_steadyStateScan2D ( const char \* param1, double start1, double end1, int numSteps1, const char \* param2, double start2, double end2, int numSteps2)

calculate steady state for each value of two parameters

#### **Parameters**

char	* first parameter name
double	start value for parameter 1
double	end value for parameter 1
int	number of steps in parameter 1
char	* second parameter name
double	start value for parameter 2
double	end value for parameter 2
int	number of steps in parameter 2

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

#### Returns

tc\_matrix matrix of concentration or particles

Definition at line 145 of file TC\_COPASI\_api.c.

## 5.12.2.21 TCAPIEXPORT void tc\_updateParameters ( tc\_matrix params )

update the model parameters just for simulation purposes, i.e. not the actual model itself this function will be much faster than using tc\_setParameters

#### **Parameters**

const | char \* formula to maximize or filename with data (csv or tab-delimited)

#### Returns

tc\_matrix a population of parameters

Definition at line 195 of file TC\_COPASI\_api.c.

## **Chapter 6**

## **Data Structure Documentation**

## 6.1 tc\_items Struct Reference

An array of int objects with length information. Use  $tc\_getItem(M,i)$  to get the i-th item

```
#include <TC_structs.h>
```

#### **Data Fields**

- int length
- long \* items

## 6.1.1 Detailed Description

An array of int objects with length information. Use tc\_getItem(M,i) to get the i-th item

Definition at line 45 of file TC\_structs.h.

## 6.1.2 Field Documentation

#### **6.1.2.1** long\* items

Definition at line 48 of file TC\_structs.h.

## 6.1.2.2 int length

Definition at line 47 of file TC\_structs.h.

The documentation for this struct was generated from the following file:

• /home/deepak/TinkerCell/trunk/API/TC\_structs.h

## 6.2 tc\_matrix Struct Reference

A 2D table of doubles with row and column names. Use tc\_getMatrixValue(M,i,j) to get the i,j-th value in tc\_matrix M.

```
#include <TC_structs.h>
```

#### **Data Fields**

- int rows
- int cols
- double \* values
- tc\_strings rownames
- tc\_strings colnames

## 6.2.1 Detailed Description

A 2D table of doubles with row and column names. Use  $tc\_getMatrixValue(M,i,j)$  to get the i,j-th value in  $tc\_matrix\ M$ .

Definition at line 53 of file TC\_structs.h.

#### 6.2.2 Field Documentation

#### 6.2.2.1 tc\_strings colnames

Definition at line 58 of file TC\_structs.h.

#### 6.2.2.2 int cols

Definition at line 55 of file TC\_structs.h.

#### 6.2.2.3 tc\_strings rownames

Definition at line 57 of file TC\_structs.h.

## 6.2.2.4 int rows

Definition at line 55 of file TC\_structs.h.

#### 6.2.2.5 double\* values

Definition at line 56 of file TC\_structs.h.

The documentation for this struct was generated from the following file:

• /home/deepak/TinkerCell/trunk/API/TC\_structs.h

## 6.3 tc\_strings Struct Reference

An array of strings with length information. Use tc\_getString(M,i) to get the i-th string.

```
#include <TC_structs.h>
```

#### **Data Fields**

- int length
- char \*\* strings

## 6.3.1 Detailed Description

An array of strings with length information. Use tc\_getString(M,i) to get the i-th string. Definition at line 37 of file TC\_structs.h.

#### 6.3.2 Field Documentation

#### 6.3.2.1 int length

Definition at line 39 of file TC\_structs.h.

## 6.3.2.2 char\*\* strings

Definition at line 40 of file TC\_structs.h.

The documentation for this struct was generated from the following file:

 $\bullet \ /home/deepak/TinkerCell/trunk/API/TC\_structs.h$ 

## 6.4 tc\_table Struct Reference

A 2D table of strings with row and column names. Use  $tc\_getTableValue(M,i,j)$  to get the i,j-th value in  $tc\_matrix$  M.

```
#include <TC_structs.h>
```

## **Data Fields**

- int rows
- int cols
- char \*\* strings
- tc strings rownames
- tc\_strings colnames

## 6.4.1 Detailed Description

A 2D table of strings with row and column names. Use  $tc\_getTableValue(M,i,j)$  to get the i,j-th value in  $tc\_matrix\ M$ .

Definition at line 63 of file TC\_structs.h.

#### 6.4.2 Field Documentation

#### 6.4.2.1 tc\_strings colnames

Definition at line 68 of file TC\_structs.h.

#### 6.4.2.2 int cols

Definition at line 65 of file TC\_structs.h.

## 6.4.2.3 tc\_strings rownames

Definition at line 67 of file TC\_structs.h.

### 6.4.2.4 int rows

Definition at line 65 of file TC\_structs.h.

#### 6.4.2.5 char\*\* strings

Definition at line 66 of file TC\_structs.h.

The documentation for this struct was generated from the following file:

• /home/deepak/TinkerCell/trunk/API/TC\_structs.h

## **Chapter 7**

## **File Documentation**

## 7.1 /home/deepak/TinkerCell/trunk/API/main.hpp File Reference

## 7.2 /home/deepak/TinkerCell/trunk/API/TC\_api.h File Reference

```
#include "TC_structs.h"
#include "TC_Main_api.h"
#include "TC_BasicInformationTool_api.h"
#include "TC_ConnectionInsertion_api.h"
#include "TC_ConnectionSelection_api.h"
#include "TC_GroupHandlerTool_api.h"
#include "TC_NodeInsertion_api.h"
#include "TC_StoichiometryTool_api.h"
#include "TC_DynamicLibraryTool_api.h"
#include "TC_PlotTool_api.h"
#include "TC_ModelFileGenerator_api.h"
#include "TC_EventsAssignments_api.h"
#include "TC_AutoGeneRegulatoryTool_api.h"
#include "TC_SBML_api.h"
#include "TC_COPASI_api.h"
#include "TC_ModuleTool_api.h"
```

84 File Documentation

# 7.3 /home/deepak/TinkerCell/trunk/API/TC\_AutoGeneRegulatoryTool\_-api.c File Reference

```
#include "TC_AutoGeneRegulatoryTool_api.h"
#include "TC_BasicInformationTool_api.h"
```

#### **Functions**

• TCAPIEXPORT tc\_items tc\_partsIn (long o)

Get all DNA parts inside the given container or module.

• TCAPIEXPORT tc\_items tc\_partsUpstream (long o)

Get all DNA parts upstream of the given part.

• TCAPIEXPORT tc\_items tc\_partsDownstream (long o)

Get all DNA parts downstream of the given part.

• TCAPIEXPORT void tc\_alignParts (tc\_items a)

Align the given DNA parts in the order given.

• TCAPIEXPORT void tc\_alignPartsOnPlasmid (long o, tc\_items a)

Align the given DNA parts in the order given.

• TCAPIEXPORT void tc\_setSequence (long o, const char \*s)

Assign DNA sequence to a part.

• TCAPIEXPORT void tc\_AutoGeneRegulatoryTool\_api (tc\_items(\*f1)(long), tc\_items(\*f2)(long), tc\_items(\*f3)(long), void(\*f4)(tc\_items), void(\*f5)(long, tc\_items))

initialize grouping

#### Variables

- tc\_items(\* \_tc\_partsIn )(long)=0
- tc\_items(\* \_tc\_partsUpstream )(long)=0
- tc\_items(\* \_tc\_partsDownstream )(long)=0
- void(\* \_tc\_alignParts )(tc\_items)=0
- void(\* \_tc\_alignPartsOnPlasmid )(long, tc\_items)=0

## 7.3.1 Function Documentation

7.3.1.1 TCAPIEXPORT void tc\_AutoGeneRegulatoryTool\_api ( tc\_items(\*)(long) f1, tc\_items(\*)(long) f2, tc\_items(\*)(long) f3, void(\*)(tc\_items) f4, void(\*)(long, tc\_items) f5 )

initialize grouping

initialize auto-gene regulatory plugin C API

Definition at line 75 of file TC\_AutoGeneRegulatoryTool\_api.c.

## 7.3.2 Variable Documentation

#### 7.3.2.1 void(\* \_tc\_alignParts)(tc\_items)=0

Definition at line 40 of file TC\_AutoGeneRegulatoryTool\_api.c.

## 7.3.2.2 void(\* \_tc\_alignPartsOnPlasmid)(long, tc\_items)=0

Definition at line 51 of file TC\_AutoGeneRegulatoryTool\_api.c.

## 7.3.2.3 tc\_items(\* \_tc\_partsDownstream)(long)=0

Definition at line 28 of file TC\_AutoGeneRegulatoryTool\_api.c.

### 7.3.2.4 tc\_items(\* \_tc\_partsIn)(long)=0

Definition at line 4 of file TC\_AutoGeneRegulatoryTool\_api.c.

## 7.3.2.5 tc\_items(\* \_tc\_partsUpstream)(long)=0

Definition at line 16 of file TC\_AutoGeneRegulatoryTool\_api.c.

## 7.4 /home/deepak/TinkerCell/trunk/API/TC\_AutoGeneRegulatoryTool\_api.h File Reference

#include "TC\_structs.h"

#### **Functions**

• TCAPIEXPORT tc\_items tc\_partsIn (long o)

Get all DNA parts inside the given container or module.

86 File Documentation

```
• TCAPIEXPORT tc_items tc_partsUpstream (long o)

Get all DNA parts upstream of the given part.
```

• TCAPIEXPORT tc\_items tc\_partsDownstream (long o)

Get all DNA parts downstream of the given part.

TCAPIEXPORT void tc\_alignParts (tc\_items a)
 Align the given DNA parts in the order given.

• TCAPIEXPORT void tc\_alignPartsOnPlasmid (long o, tc\_items a)

Align the given DNA parts in the order given.

• TCAPIEXPORT void tc\_setSequence (long o, const char \*)

Align the given DNA parts in the order given.

• TCAPIEXPORT void tc\_AutoGeneRegulatoryTool\_api (tc\_items(\*f1)(long), tc\_items(\*f2)(long), tc\_items(\*f3)(long), void(\*f4)(tc\_items), void(\*f5)(long, tc\_items))

initialize auto-gene regulatory plugin C API

#### 7.4.1 Function Documentation

7.4.1.1 TCAPIEXPORT void tc\_AutoGeneRegulatoryTool\_api ( tc\_items(\*)(long) f1, tc\_items(\*)(long) f2, tc\_items(\*)(long) f3, void(\*)(tc\_items) f4, void(\*)(long, tc\_items) f5)

initialize auto-gene regulatory plugin C API

Definition at line 75 of file TC\_AutoGeneRegulatoryTool\_api.c.

# 7.5 /home/deepak/TinkerCell/trunk/API/TC\_BasicInformationTool\_api.c File Reference

```
#include "TC_BasicInformationTool_api.h"
#include "TC_Main_api.h"
#include "TC_COPASI_api.h"
```

#### **Functions**

- TCAPIEXPORT tc\_matrix tc\_getParameters (tc\_items a) get all the parameters
- TCAPIEXPORT tc\_matrix tc\_getInitialValues (tc\_items a)

get initial values of the given items. Fixed varianbles are included.

- TCAPIEXPORT void tc\_setInitialValues (tc\_items items, tc\_matrix values) set initial values of the given items.
- TCAPIEXPORT tc\_matrix tc\_getFixedVariables (tc\_items a) get all fixed variables
- TCAPIEXPORT tc\_matrix tc\_getParametersAndFixedVariables (tc\_items a) get all the parameters and fixed variables
- TCAPIEXPORT const char \* tc\_getTextAttribute (long item, const char \*attribute)

get the text attribute with the given name for the given item

- TCAPIEXPORT double tc\_getParameter (long item, const char \*attribute) get the numerical attribute with the given name for the given item
- TCAPIEXPORT tc\_matrix tc\_getParametersNamed (tc\_items a, tc\_strings attibutes)

get all numerical attributes with the given names for the given items

TCAPIEXPORT tc\_matrix tc\_getParametersExcept (tc\_items a, tc\_strings attributes)

get all numerical attributes EXCEPT the given names

• TCAPIEXPORT tc\_strings tc\_getAllTextNamed (tc\_items a, tc\_strings attributes)

get all text attributes with the given name for the given items

• TCAPIEXPORT void tc\_setTextAttribute (long item, const char \*attribute, const char \*value)

set text attribute for the given item

• TCAPIEXPORT void tc\_setParameter (long item, const char \*attribute, double value)

set numerical attribute for the given item

• TCAPIEXPORT void tc\_setTextAttributeByName (const char \*attribute, const char \*value)

set text attribute

• TCAPIEXPORT void tc\_setParameterByName (const char \*attribute, double value)

set a parameter value

• TCAPIEXPORT void tc\_setTextAttributes (tc\_table t)

set text attributes for multiple items

• TCAPIEXPORT void tc\_setParameters (tc\_matrix t, int permanent)

set parameter for multiple items

• TCAPIEXPORT void tc\_BasicInformationTool\_Text\_api (const char \*(\*getTextData)(long, const char \*), tc\_strings(\*getAllTextDataNamed)(tc\_items, tc\_strings), void(\*setTextData)(long, const char \*, const char \*))

initialize attribute functions

TCAPIEXPORT void tc\_BasicInformationTool\_Numeric\_api (tc\_matrix(\*getInitialValues)(tc\_items), void(\*setInitialValues)(tc\_items, tc\_matrix), tc\_matrix(\*getParameters)(tc\_items), tc\_matrix(\*getParameters)(tc\_items), tc\_matrix(\*getParametersAndFixedVariabes)(tc\_items), double(\*getNumericalData)(long, const char \*), tc\_matrix(\*getParametersNamed)(tc\_items, tc\_strings), tc\_matrix(\*getParametersExcept)(tc\_items, tc\_strings), void(\*setNumericalData)(long, const char \*, double))

#### **Variables**

- tc\_matrix(\* \_tc\_getParameters )(tc\_items)=0
- tc\_matrix(\* \_tc\_getInitialValues )(tc\_items)=0
- void(\* \_tc\_setInitialValues )(tc\_items items, tc\_matrix values)=0
- tc\_matrix(\* \_tc\_getFixedVariables )(tc\_items)=0
- tc\_matrix(\* \_tc\_getParametersAndFixedVariables )(tc\_items)=0
- const char \*(\* \_tc\_getTextAttribute )(long item, const char \*attribute)=0
- double(\* \_tc\_getParameter )(long item, const char \*attribute)=0
- tc\_matrix(\* \_tc\_getParametersNamed )(tc\_items, tc\_strings attibutes)=0
- tc\_matrix(\* \_tc\_getParametersExcept )(tc\_items, tc\_strings attributes)=0
- tc\_strings(\* \_tc\_getAllTextNamed )(tc\_items, tc\_strings attributes)=0
- void(\*\_tc\_setTextAttribute)(long item, const char \*attribute, const char \*value)=0
- void(\* \_tc\_setParameter )(long item, const char \*attribute, double value)=0

## 7.5.1 Function Documentation

7.5.1.1 TCAPIEXPORT void tc\_BasicInformationTool\_Numeric\_api ( tc\_matrix(\*)(tc\_items) getInitialValues, void(\*)(tc\_items, tc\_matrix) setInitialValues, tc\_matrix(\*)(tc\_items) getParameters, tc\_matrix(\*)(tc\_items) getFixedVariabes, tc\_matrix(\*)(tc\_items) getParametersAndFixedVariabes, double(\*)(long, const char \*) getNumericalData, tc\_matrix(\*)(tc\_items, tc\_strings) getParametersNamed, tc\_matrix(\*)(tc\_items, tc\_strings) getParametersExcept, void(\*)(long, const char \*, double) setNumericalData )

Definition at line 187 of file TC\_BasicInformationTool\_api.c.

7.5.1.2 TCAPIEXPORT void tc\_BasicInformationTool\_Text\_api ( const char \*(\*)(long, const char \*) getTextData, tc\_strings(\*)(tc\_items, tc\_strings) getAllTextDataNamed, void(\*)(long, const char \*, const char \*) setTextData )

initialize attribute functions

initialize the parameters and attributes plug-in

Definition at line 176 of file TC\_BasicInformationTool\_api.c.

#### 7.5.2 Variable Documentation

#### 7.5.2.1 tc\_strings(\* \_tc\_getAllTextNamed)(tc\_items, tc\_strings attributes)=0

Definition at line 114 of file TC\_BasicInformationTool\_api.c.

#### 7.5.2.2 tc\_matrix(\* \_tc\_getFixedVariables)(tc\_items)=0

Definition at line 42 of file TC\_BasicInformationTool\_api.c.

#### 7.5.2.3 tc\_matrix(\* \_tc\_getInitialValues)(tc\_items)=0

Definition at line 18 of file TC\_BasicInformationTool\_api.c.

#### 7.5.2.4 double(\* \_tc\_getParameter)(long item, const char \*attribute)=0

Definition at line 78 of file TC\_BasicInformationTool\_api.c.

## 7.5.2.5 tc\_matrix(\* \_tc\_getParameters)(tc\_items)=0

Definition at line 5 of file TC\_BasicInformationTool\_api.c.

## 7.5.2.6 tc\_matrix(\* \_tc\_getParametersAndFixedVariables)(tc\_items)=0

Definition at line 54 of file TC\_BasicInformationTool\_api.c.

### $7.5.2.7 \quad tc\_matrix(*\_tc\_getParametersExcept)(tc\_items, tc\_strings \ attributes) = 0$

Definition at line 102 of file TC\_BasicInformationTool\_api.c.

## 7.5.2.8 tc\_matrix(\* \_tc\_getParametersNamed)(tc\_items, tc\_strings attibutes)=0

Definition at line 90 of file TC\_BasicInformationTool\_api.c.

7.5.2.9 const char\*(\* \_tc\_getTextAttribute)(long item, const char \*attribute)=0

Definition at line 66 of file TC\_BasicInformationTool\_api.c.

7.5.2.10 void(\* \_tc\_setInitialValues)(tc\_items items, tc\_matrix values)=0

Definition at line 31 of file TC\_BasicInformationTool\_api.c.

7.5.2.11 void(\* \_tc\_setParameter)(long item, const char \*attribute, double value)=0

Definition at line 137 of file TC\_BasicInformationTool\_api.c.

7.5.2.12 void(\* \_tc\_setTextAttribute)(long item, const char \*attribute, const char \*value)=0

Definition at line 126 of file TC\_BasicInformationTool\_api.c.

# 7.6 /home/deepak/TinkerCell/trunk/API/TC\_BasicInformationTool\_api.h File Reference

#include "TC\_structs.h"

#### **Functions**

- BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_getParameters (tc\_items a) get all the parameters for the given items. use tc\_allItems() as argument to get all parameters
- TCAPIEXPORT tc\_matrix tc\_getInitialValues (tc\_items a)

  get initial values of the given items. Fixed varianbles are included. use tc\_allItems()

  for all items in the model.
- TCAPIEXPORT void tc\_setInitialValues (tc\_items items, tc\_matrix values) set initial values of the given items.
- TCAPIEXPORT tc\_matrix tc\_getFixedVariables (tc\_items a) get all fixed variables
- TCAPIEXPORT tc\_matrix tc\_getParametersAndFixedVariables (tc\_items a) get all the parameters and fixed variables
- TCAPIEXPORT const char \* tc\_getTextAttribute (long item, const char \*attribute)

get the text attribute with the given name for the given item

• TCAPIEXPORT tc\_matrix tc\_getParametersNamed (tc\_items a, tc\_strings attibutes)

get all numerical Modeling with the given names for the given items

TCAPIEXPORT tc\_matrix tc\_getParametersExcept (tc\_items a, tc\_strings attributes)

get all numerical Modeling EXCEPT the given names

• TCAPIEXPORT tc\_strings tc\_getAllTextNamed (tc\_items a, tc\_strings attributes)

get all text Modeling with the given name for the given items

• TCAPIEXPORT void tc\_setTextAttribute (long item, const char \*attribute, const char \*value)

set text attribute for the given item

• TCAPIEXPORT void tc\_setParameter (long item, const char \*attribute, double value)

set a parameter value for the given item

 TCAPIEXPORT void tc\_setTextAttributeByName (const char \*attribute, const char \*value)

set text attribute

TCAPIEXPORT void tc\_setParameterByName (const char \*attribute, double value)

set a parameter value

• TCAPIEXPORT void tc\_setTextAttributes (tc\_table)

set text attributes for multiple items

• TCAPIEXPORT void tc\_setParameters (tc\_matrix, int)

set parameter for multiple items

TCAPIEXPORT void tc\_BasicInformationTool\_Text\_api (const char \*(\*getTextData)(long, const char \*), tc\_strings(\*getAllTextDataNamed)(tc\_items, tc\_strings), void(\*setTextData)(long, const char \*, const char \*))

initialize the parameters and attributes plug-in

TCAPIEXPORT void tc\_BasicInformationTool\_Numeric\_api (tc\_matrix(\*getInitialValues)(tc\_items), void(\*setInitialValues)(tc\_items, tc\_matrix), tc\_matrix(\*getParameters)(tc\_items), tc\_matrix(\*getParameters)(tc\_items), tc\_matrix(\*getParametersAndFixedVariabes)(tc\_items), double(\*getNumericalData)(long, const char \*), tc\_matrix(\*getParametersNamed)(tc\_items, tc\_strings), tc\_matrix(\*getParametersExcept)(tc\_items, tc\_strings), void(\*setNumericalData)(long, const char \*, double))

#### 7.6.1 Function Documentation

7.6.1.1 TCAPIEXPORT void tc\_BasicInformationTool\_Numeric\_api ( tc\_matrix(\*)(tc\_items) getInitialValues, void(\*)(tc\_items, tc\_matrix) setInitialValues, tc\_matrix(\*)(tc\_items) getParameters, tc\_matrix(\*)(tc\_items) getFixedVariabes, tc\_matrix(\*)(tc\_items) getParametersAndFixedVariabes, double(\*)(long, const char \*) getNumericalData, tc\_matrix(\*)(tc\_items, tc\_strings) getParametersNamed, tc\_matrix(\*)(tc\_items, tc\_strings) getParametersExcept, void(\*)(long, const char \*, double) setNumericalData )

Definition at line 187 of file TC\_BasicInformationTool\_api.c.

7.6.1.2 TCAPIEXPORT void tc\_BasicInformationTool\_Text\_api ( const char \*(\*)(long, const char \*) getTextData, tc\_strings(\*)(tc\_items, tc\_strings) getAllTextDataNamed, void(\*)(long, const char \*, const char \*) setTextData )

initialize the parameters and attributes plug-in

Definition at line 176 of file TC\_BasicInformationTool\_api.c.

# 7.7 /home/deepak/TinkerCell/trunk/API/TC\_ConnectionInsertion\_api.c File Reference

#include "TC\_ConnectionInsertion\_api.h"

#### **Functions**

• TCAPIEXPORT long tc\_insertConnection (tc\_items parts, const char \*name, const char \*family)

connect a set of parts (in) to another (out). give the connection name and family. returns the inserted connection

- TCAPIEXPORT tc\_items tc\_getConnectedNodes (long connection) get the connected parts for a connection
- TCAPIEXPORT tc\_items tc\_getConnectedNodesWithRole (long connection, const char \*role)

get the parts with a role in a connection, such as reactants

- TCAPIEXPORT tc\_items tc\_getConnections (long part) get connections for a part
- TCAPIEXPORT tc\_items tc\_getConnectionsWithRole (long part, const char \*role)

get connections where the given part has the given role, e.g. reactant

TCAPIEXPORT void tc\_ConnectionInsertion\_api (long(\*insertConnection)(tc\_items, const char \*, const char \*), tc\_items(\*getConnectedParts)(long), tc\_items(\*getConnectedPartsWithRole)(long,
const char \*), tc\_items(\*getConnections)(long), tc\_items(\*getConnectionsWithRole)(long,
const char \*))

initialize connections

### **Variables**

- long(\* tc insertConnection)(tc items parts, const char \*name, const char \*family)=0
- tc\_items(\* \_tc\_getConnectedNodes )(long connection)=0
- tc\_items(\* \_tc\_getConnectedNodesWithRole)(long connection, const char \*role)=0
- tc\_items(\* \_tc\_getConnections)(long part)=0
- tc\_items(\* \_tc\_getConnectionsWithRole )(long part, const char \*role)=0

### 7.7.1 Function Documentation

7.7.1.1 TCAPIEXPORT void tc\_ConnectionInsertion\_api ( long(\*)(tc\_items, const char \*, const char \*, const char \*) insertConnection, tc\_items(\*)(long) getConnectedParts, tc\_items(\*)(long, const char \*) getConnectedPartsWithRole, tc\_items(\*)(long) getConnections, tc\_items(\*)(long, const char \*) getConnectionsWithRole )

initialize connections

initialize connections insertions plug-in

Definition at line 67 of file TC\_ConnectionInsertion\_api.c.

## 7.7.2 Variable Documentation

# 7.7.2.1 tc\_items(\* \_tc\_getConnectedNodes)(long connection)=0

Definition at line 15 of file  $TC\_ConnectionInsertion\_api.c.$ 

# 7.7.2.2 tc\_items(\* \_tc\_getConnectedNodesWithRole)(long connection, const char \*role)=0

Definition at line 27 of file TC\_ConnectionInsertion\_api.c.

# 7.7.2.3 tc\_items(\* \_tc\_getConnections)(long part)=0

Definition at line 39 of file TC\_ConnectionInsertion\_api.c.

# 7.7.2.4 tc\_items(\*\_tc\_getConnectionsWithRole)(long part, const char \*role)=0

Definition at line 51 of file TC\_ConnectionInsertion\_api.c.

7.7.2.5 long(\* \_tc\_insertConnection)(tc\_items parts, const char \*name, const char \*family)=0

Definition at line 3 of file TC\_ConnectionInsertion\_api.c.

# 7.8 /home/deepak/TinkerCell/trunk/API/TC\_ConnectionInsertion\_api.h File Reference

#include "TC\_structs.h"

### **Functions**

• TCAPIEXPORT long tc\_insertConnection (tc\_items parts, const char \*name, const char \*family)

connect a set of parts (in) to another (out). give the connection name and family. returns the inserted connection

- TCAPIEXPORT tc\_items tc\_getConnectedNodes (long connection) get the connected parts for a connection
- TCAPIEXPORT tc\_items tc\_getConnectedNodesWithRole (long connection, const char \*role)

get the parts with a role in a connection, such as reactants

- TCAPIEXPORT tc\_items tc\_getConnections (long part) get connections for a part
- TCAPIEXPORT tc\_items tc\_getConnectionsWithRole (long part, const char \*role)

get connections where the given part has the given role, e.g. reactant

TCAPIEXPORT void tc\_ConnectionInsertion\_api (long(\*insertConnection)(tc\_items, const char \*, const char \*), tc\_items(\*getConnectedParts)(long), tc\_items(\*getConnectedPartsWithl
const char \*), tc\_items(\*getConnections)(long), tc\_items(\*getConnectionsWithRole)(long,
const char \*))

initialize connections insertions plug-in

### 7.8.1 Function Documentation

7.8.1.1 TCAPIEXPORT void tc\_ConnectionInsertion\_api ( long(\*)(tc\_items, const char \*, const char \*) insertConnection, tc\_items(\*)(long) getConnectedParts, tc\_items(\*)(long, const char \*) getConnectedPartsWithRole, tc\_items(\*)(long) getConnections, tc\_items(\*)(long, const char \*) getConnectionsWithRole )

initialize connections insertions plug-in

Definition at line 67 of file TC\_ConnectionInsertion\_api.c.

# 7.9 /home/deepak/TinkerCell/trunk/API/TC\_ConnectionSelection\_api.c File Reference

#include "TC\_ConnectionSelection\_api.h"

#### **Functions**

• TCAPIEXPORT double tc\_getControlPointX (long connection, long part, int whichPoint)

get x position of a control point

• TCAPIEXPORT double tc\_getControlPointY (long connection, long part, int whichPoint)

get y position of a control point

• TCAPIEXPORT void tc\_setControlPoint (long connection, long part, int which-Point, double x, double y)

set x and y position of a control point

- TCAPIEXPORT void tc\_setCenterPoint (long connection, double y, double x) set x and y position of the central control point
- TCAPIEXPORT double tc\_getCenterPointX (long connection) get x position of the central control point
- TCAPIEXPORT double tc\_getCenterPointY (long connection) get y position of the central control point
- TCAPIEXPORT void tc\_setStraight (long item, int straight)

  switch between beziers and lines for drawing the connector, where 1 = line, 0 = bezier
- TCAPIEXPORT void tc\_setAllStraight (int straight)

  switch between beziers and lines for drawing the connector, where 1 = line, 0 = bezier
- TCAPIEXPORT void tc\_setLineWidth (long item, double width, int permanent)

set the line width. Indicate whether the change should be temporary or permanent.

TCAPIEXPORT void tc\_ConnectionSelection\_api (double(\*getControlPointX)(long, long, int), double(\*getControlPointY)(long, long, int), void(\*setControlPoint)(long, long, int, double, double), void(\*setCenterPoint)(long, double, double), double(\*getCenterPointX)(long), double(\*getCenterPointY)(long), void(\*setStraight)(long, int), void(\*setAllStraight)(int), void(\*setLineWidth)(long, double, int))

initialize control point functions

### **Variables**

- double(\* \_tc\_getControlPointX )(long connection, long part, int whichPoint)=0
- double(\* \_tc\_getControlPointY )(long connection, long part, int whichPoint)=0
- void(\* \_tc\_setControlPoint )(long connection, long part, int whichPoint, double x, double y)=0
- void(\* \_tc\_setCenterPoint )(long connection, double y, double x)=0
- double(\* <u>\_tc\_getCenterPointX</u>)(long connection)=0
- double(\* \_tc\_getCenterPointY )(long connection)=0
- void(\* \_tc\_setStraight)(long item, int straight)=0
- void(\* \_tc\_setAllStraight)(int straight)=0
- void(\* \_tc\_setLineWidth )(long item, double width, int permanent)=0

#### 7.9.1 Function Documentation

7.9.1.1 TCAPIEXPORT void tc\_ConnectionSelection\_api ( double(\*)(long, long, int) getControlPointX, double(\*)(long, long, int) getControlPointY, void(\*)(long, long, int, double, double) setControlPoint, void(\*)(long, double, double) setCenterPoint, double(\*)(long) getCenterPointX, double(\*)(long) getCenterPointY, void(\*)(long, int) setStraight, void(\*)(int) setAllStraight, void(\*)(long, double, int) setLineWidth)

initialize control point functions initialize control points plug-in

Definition at line 115 of file TC\_ConnectionSelection\_api.c.

### 7.9.2 Variable Documentation

### 7.9.2.1 double(\* \_tc\_getCenterPointX)(long connection)=0

Definition at line 54 of file TC\_ConnectionSelection\_api.c.

### 7.9.2.2 double(\* \_tc\_getCenterPointY)(long connection)=0

Definition at line 66 of file TC\_ConnectionSelection\_api.c.

# 7.9.2.3 double(\* \_tc\_getControlPointX)(long connection, long part, int whichPoint)=0

Definition at line 3 of file TC\_ConnectionSelection\_api.c.

7.9.2.4 double(\* \_tc\_getControlPointY)(long connection, long part, int whichPoint)=0

Definition at line 15 of file TC\_ConnectionSelection\_api.c.

7.9.2.5 void(\* \_tc\_setAllStraight)(int straight)=0

Definition at line 89 of file TC\_ConnectionSelection\_api.c.

7.9.2.6 void(\* tc setCenterPoint)(long connection, double y, double x)=0

Definition at line 43 of file TC\_ConnectionSelection\_api.c.

7.9.2.7 void(\* \_tc\_setControlPoint)(long connection, long part, int whichPoint, double x, double y)=0

Definition at line 27 of file TC\_ConnectionSelection\_api.c.

7.9.2.8 void(\* \_tc\_setLineWidth)(long item, double width, int permanent)=0

Definition at line 100 of file TC\_ConnectionSelection\_api.c.

7.9.2.9 void(\*  $\_tc\_setStraight$ )(long item, int straight)=0

Definition at line 78 of file TC\_ConnectionSelection\_api.c.

# 7.10 /home/deepak/TinkerCell/trunk/API/TC\_ConnectionSelection\_api.h File Reference

#include "TC structs.h"

# **Functions**

• BEGIN\_C\_DECLS TCAPIEXPORT double tc\_getControlPointX (long connection, long part, int whichPoint)

get x position of a control point

• TCAPIEXPORT double tc\_getControlPointY (long connection, long part, int whichPoint)

get y position of a control point

• TCAPIEXPORT void tc\_setControlPoint (long connection, long part, int which-Point, double x, double y)

set x and y position of a control point

- TCAPIEXPORT void tc\_setCenterPoint (long connection, double y, double x) set x and y position of the central control point
- TCAPIEXPORT double tc\_getCenterPointX (long connection) get x position of the central control point
- TCAPIEXPORT double tc\_getCenterPointY (long connection) get y position of the central control point
- TCAPIEXPORT void tc\_setStraight (long item, int straight)

  switch between beziers and lines for drawing the connector, where 1 = line, 0 = bezier
- TCAPIEXPORT void tc\_setAllStraight (int straight)
   switch between beziers and lines for drawing ALL connectors
- TCAPIEXPORT void tc\_setLineWidth (long item, double width, int permanent)

set the line width. Indicate whether the change should be temporary or permanent.

TCAPIEXPORT void tc\_ConnectionSelection\_api (double(\*getControlPointX)(long, long, int), double(\*getControlPointY)(long, long, int), void(\*setControlPoint)(long, long, int, double, double), void(\*setCenterPoint)(long, double, double), double(\*getCenterPointX)(long), double(\*getCenterPointY)(long), void(\*setStraight)(long, int), void(\*setAllStraight)(int), void(\*setLineWidth)(long, double, int))

initialize control points plug-in

### 7.10.1 Function Documentation

7.10.1.1 TCAPIEXPORT void tc\_ConnectionSelection\_api ( double(\*)(long, long, int) getControlPointX, double(\*)(long, long, int) getControlPointY, void(\*)(long, long, int, double, double) setControlPoint, void(\*)(long, double, double) setCenterPoint, double(\*)(long) getCenterPointX, double(\*)(long) getCenterPointY, void(\*)(long, int) setStraight, void(\*)(int) setAllStraight, void(\*)(long, double, int) setLineWidth)

initialize control points plug-in

Definition at line 115 of file TC\_ConnectionSelection\_api.c.

# 7.11 /home/deepak/TinkerCell/trunk/API/TC\_COPASI\_api.c File Reference

#include "TC\_COPASI\_api.h"

### **Functions**

 TCAPIEXPORT tc\_matrix tc\_simulateDeterministic (double startTime, double endTime, int numSteps)

simulate using LSODA numerical integrator

 TCAPIEXPORT tc\_matrix tc\_simulateStochastic (double startTime, double end-Time, int numSteps)

simulate using exact stochastic algorithm

• TCAPIEXPORT tc\_matrix tc\_simulateHybrid (double startTime, double end-Time, int numSteps)

simulate using Hybrid algorithm/deterministic algorithmparam double start time

• TCAPIEXPORT tc\_matrix tc\_simulateTauLeap (double startTime, double end-Time, int numSteps)

simulate using Tau Leap stochastic algorithm

• TCAPIEXPORT tc\_matrix tc\_getSteadyState ()

bring the system to steady state

• TCAPIEXPORT tc\_matrix tc\_getJacobian ()

get the Jacobian at the current state

• TCAPIEXPORT tc\_matrix tc\_getEigenvalues ()

get the eigenvalues of the Jacobian at the current state

• TCAPIEXPORT tc\_matrix tc\_getUnscaledElasticities ()

unscaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getUnscaledConcentrationCC ()

unscaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getUnscaledFluxCC ()

unscaled flux control coefficients

• TCAPIEXPORT tc\_matrix tc\_getScaledElasticities ()

scaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getScaledConcentrationCC ()

scaled concentration control coefficients

• TCAPIEXPORT tc\_matrix tc\_getScaledFluxCC ()

scaled flux control coefficients

• TCAPIEXPORT tc\_matrix tc\_steadyStateScan (const char \*param, double start, double end, int numSteps)

calculate steady state for each value of a parameter

• TCAPIEXPORT tc\_matrix tc\_steadyStateScan2D (const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2)

calculate steady state for each value of two parameters

- TCAPIEXPORT tc\_matrix tc\_reducedStoichiometry ()
   reduced stoichiometry
- TCAPIEXPORT tc\_matrix tc\_elementaryFluxModes ()
   elementary flux modes
- TCAPIEXPORT tc\_matrix tc\_LMatrix ()
   left nullspace of the stoichiometry matrix
- TCAPIEXPORT tc\_matrix tc\_KMatrix ()
   right nullspace of the stoichiometry matrix
- TCAPIEXPORT tc\_matrix tc\_optimize (const char \*s)

Maximize the given formula or fit the data is the given filename, depending on whether or not the input is a filename. The optimization is done using genetic algorithms, so a distribution of optimal parameters is generated. All parameters in the model will be used where the parameter's min and max values are different (i.e. parameter is variable)

• TCAPIEXPORT void tc\_updateParameters (tc\_matrix params)

update the model parameters just for simulation purposes, i.e. not the actual model itself this function will be much faster than using tc\_setParameters

• TCAPIEXPORT void tc\_COPASI\_api (tc\_matrix(\*simulateDeterministic)(double startTime, double endTime, int numSteps), tc\_matrix(\*simulateStochastic)(double startTime, double endTime, int numSteps), tc\_matrix(\*simulateHybrid)(double startTime, double endTime, int numSteps), tc\_matrix(\*simulateTauLeap)(double startTime, double endTime, int numSteps), tc\_matrix(\*getSteadyState)(), tc\_matrix(\*steadyStateScan)(const char \*param, double start, double end, int numSteps), tc\_matrix(\*steadyStateScan2D)(const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2), tc\_matrix(\*getJacobian)(), tc\_matrix(\*getEigenvalues)(), tc\_matrix(\*getUnscaledElasticities tc\_matrix(\*getUnscaledConcentrationCC)(), tc\_matrix(\*getUnscaledFluxCC)(), tc\_matrix(\*getScaledFluxCC)(), tc\_matrix(\*getScaledConcentrationCC)(), tc\_matrix(\*getScaledFluxCC)(), tc\_ma

initializing function

### **Variables**

- tc\_matrix(\* \_tc\_simulateDeterministic )(double startTime, double endTime, int numSteps)=0
- tc\_matrix(\*\_tc\_simulateStochastic )(double startTime, double endTime, int num-Steps)=0
- tc\_matrix(\* \_tc\_simulateHybrid )(double startTime, double endTime, int num-Steps)=0
- tc\_matrix(\* \_tc\_simulateTauLeap )(double startTime, double endTime, int num-Steps)=0
- tc\_matrix(\* \_tc\_getSteadyState )()=0
- tc\_matrix(\* \_tc\_steadyStateScan )(const char \*param, double start, double end, int numSteps)=0
- tc\_matrix(\* \_tc\_steadyStateScan2D )(const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2)=0
- tc\_matrix(\* \_tc\_getJacobian )()=0
- tc\_matrix(\* \_tc\_getEigenvalues )()=0
- tc\_matrix(\* \_tc\_getUnscaledElasticities )()=0
- tc\_matrix(\* \_tc\_getUnscaledConcentrationCC )()=0
- tc\_matrix(\* \_tc\_getUnscaledFluxCC )()=0
- tc\_matrix(\* \_tc\_getScaledElasticities )()=0
- tc\_matrix(\* \_tc\_getScaledConcentrationCC )()=0
- tc\_matrix(\* \_tc\_getScaledFluxCC )()=0
- tc\_matrix(\* \_tc\_reducedStoichiometry )()=0
- tc\_matrix(\* \_tc\_elementaryFluxModes )()=0
- tc\_matrix(\* \_tc\_LMatrix )()=0
- tc\_matrix(\* \_tc\_KMatrix )()=0
- tc\_matrix(\* \_tc\_optimize )(const char \*)=0
- void(\* \_tc\_updateParams )(tc\_matrix)=0

### 7.11.1 Function Documentation

7.11.1.1 TCAPIEXPORT void tc\_COPASI\_api ( tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateDeterministic, tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateStochastic, tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateHybrid, tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateTauLeap, tc\_matrix(\*)() getSteadyState, tc\_matrix(\*)(const char \*param, double start, double end, int numSteps) steadyStateScan, tc\_matrix(\*)(const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2) steadyStateScan2D, tc\_matrix(\*)() getJacobian, tc\_matrix(\*)() getEigenvalues, tc\_matrix(\*)() getUnscaledElasticities, tc\_matrix(\*)() getUnscaledFluxCC, tc\_matrix(\*)() getScaledFluxCC, tc\_matrix(\*)() getScaledConcentrationCC, tc\_matrix(\*)() getScaledFluxCC, tc\_matrix(\*)() getScaledFluxCC, tc\_matrix(\*)() reducedStoichiometry, tc\_matrix(\*)() emf, tc\_matrix(\*)() Lmat, tc\_matrix(\*)() Kmat, tc\_matrix(\*)(const char \*) gaoptim, void(\*)(tc\_matrix) update)

initializing function

Definition at line 202 of file TC COPASI api.c.

### 7.11.2 Variable Documentation

### 7.11.2.1 tc\_matrix(\* \_tc\_elementaryFluxModes)()=0

Definition at line 22 of file TC\_COPASI\_api.c.

# 7.11.2.2 tc\_matrix(\* \_tc\_getEigenvalues)()=0

Definition at line 14 of file TC\_COPASI\_api.c.

## 7.11.2.3 tc\_matrix(\* \_tc\_getJacobian)()=0

Definition at line 13 of file TC\_COPASI\_api.c.

## 7.11.2.4 tc\_matrix(\* \_tc\_getScaledConcentrationCC)()=0

Definition at line 19 of file TC\_COPASI\_api.c.

# 7.11.2.5 tc\_matrix(\*\_tc\_getScaledElasticities)()=0

Definition at line 18 of file TC\_COPASI\_api.c.

### 7.11 /home/deepak/TinkerCell/trunk/API/TC\_COPASI\_api.c File Reference 103

### 7.11.2.6 tc\_matrix(\*\_tc\_getScaledFluxCC)()=0

Definition at line 20 of file TC\_COPASI\_api.c.

## 7.11.2.7 tc\_matrix(\* \_tc\_getSteadyState)()=0

Definition at line 10 of file TC\_COPASI\_api.c.

## 7.11.2.8 tc\_matrix(\* \_tc\_getUnscaledConcentrationCC)()=0

Definition at line 16 of file TC\_COPASI\_api.c.

## 7.11.2.9 tc\_matrix(\* \_tc\_getUnscaledElasticities)()=0

Definition at line 15 of file TC\_COPASI\_api.c.

## 7.11.2.10 tc\_matrix(\* \_tc\_getUnscaledFluxCC)()=0

Definition at line 17 of file TC\_COPASI\_api.c.

# 7.11.2.11 tc\_matrix(\* \_tc\_KMatrix)()=0

Definition at line 24 of file TC\_COPASI\_api.c.

## 7.11.2.12 tc\_matrix(\* \_tc\_LMatrix)()=0

Definition at line 23 of file TC\_COPASI\_api.c.

### 7.11.2.13 tc\_matrix(\* \_tc\_optimize)(const char \*)=0

Definition at line 25 of file TC\_COPASI\_api.c.

# 7.11.2.14 tc\_matrix(\* \_tc\_reducedStoichiometry)()=0

Definition at line 21 of file TC\_COPASI\_api.c.

# 7.11.2.15 $tc_matrix(*\_tc\_simulateDeterministic)(double startTime, double endTime, int numSteps)=0$

Definition at line 6 of file TC\_COPASI\_api.c.

7.11.2.16 tc\_matrix(\* \_tc\_simulateHybrid)(double startTime, double endTime, int numSteps)=0

Definition at line 8 of file TC\_COPASI\_api.c.

7.11.2.17  $tc_matrix(*\_tc\_simulateStochastic)$ (double startTime, double endTime, int numSteps)=0

Definition at line 7 of file TC\_COPASI\_api.c.

7.11.2.18  $tc_matrix(*\_tc\_simulateTauLeap)$ (double startTime, double endTime, int numSteps)=0

Definition at line 9 of file TC\_COPASI\_api.c.

7.11.2.19  $tc_matrix(*\_tc\_steadyStateScan)(const char *param, double start, double end, int numSteps)=0$ 

Definition at line 11 of file TC\_COPASI\_api.c.

7.11.2.20 tc\_matrix(\* \_tc\_steadyStateScan2D)(const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2)=0

Definition at line 12 of file TC COPASI api.c.

7.11.2.21 void(\* \_tc\_updateParams)(tc\_matrix)=0

Definition at line 26 of file TC\_COPASI\_api.c.

# 7.12 /home/deepak/TinkerCell/trunk/API/TC\_COPASI\_api.h File Reference

#include "TC\_structs.h"

# **Functions**

- BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_simulateDeterministic (double startTime, double endTime, int numSteps)
  - simulate using LSODA numerical integrator
- TCAPIEXPORT tc\_matrix tc\_simulateStochastic (double startTime, double end-Time, int numSteps)

### 7.12 /home/deepak/TinkerCell/trunk/API/TC\_COPASI\_api.h File Reference 105

simulate using exact stochastic algorithm

 TCAPIEXPORT tc\_matrix tc\_simulateHybrid (double startTime, double end-Time, int numSteps)

simulate using Hybrid algorithm/deterministic algorithmparam double start time

• TCAPIEXPORT tc\_matrix tc\_simulateTauLeap (double startTime, double end-Time, int numSteps)

simulate using Tau Leap stochastic algorithm

• TCAPIEXPORT tc\_matrix tc\_getSteadyState ()

bring the system to steady state

TCAPIEXPORT tc\_matrix tc\_steadyStateScan (const char \*param, double start, double end, int numSteps)

calculate steady state for each value of a parameter

• TCAPIEXPORT tc\_matrix tc\_steadyStateScan2D (const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2)

calculate steady state for each value of two parameters

• TCAPIEXPORT tc\_matrix tc\_getJacobian ()

get the Jacobian at the current state

• TCAPIEXPORT tc\_matrix tc\_getEigenvalues ()

get the eigenvalues of the Jacobian at the current state

• TCAPIEXPORT tc\_matrix tc\_getUnscaledElasticities ()

unscaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getUnscaledConcentrationCC ()

unscaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getUnscaledFluxCC ()

unscaled flux control coefficients

• TCAPIEXPORT tc\_matrix tc\_getScaledElasticities ()

scaled elasticities

• TCAPIEXPORT tc\_matrix tc\_getScaledConcentrationCC ()

scaled concentration control coefficients

• TCAPIEXPORT tc\_matrix tc\_getScaledFluxCC ()

scaled flux control coefficients

• TCAPIEXPORT tc\_matrix tc\_reducedStoichiometry ()

reduced stoichiometry

• TCAPIEXPORT tc\_matrix tc\_elementaryFluxModes ()

elementary flux modes

• TCAPIEXPORT tc\_matrix tc\_LMatrix ()

left nullspace of the stoichiometry matrix

TCAPIEXPORT tc\_matrix tc\_KMatrix ()

right nullspace of the stoichiometry matrix

• TCAPIEXPORT void tc\_updateParameters (tc\_matrix params)

update the model parameters just for simulation purposes, i.e. not the actual model itself this function will be much faster than using tc\_setParameters

• TCAPIEXPORT tc\_matrix tc\_optimize (const char \*formulaOrFile)

Maximize the given formula or fit the data is the given filename, depending on whether or not the input is a filename. The optimization is done using genetic algorithms, so a distribution of optimal parameters is generated. All parameters in the model will be used where the parameter's min and max values are different (i.e. parameter is variable)

• TCAPIEXPORT void tc\_COPASI\_api (tc\_matrix(\*simulateDeterministic)(double startTime, double endTime, int numSteps), tc\_matrix(\*simulateStochastic)(double startTime, double endTime, int numSteps), tc\_matrix(\*simulateHybrid)(double startTime, double endTime, int numSteps), tc\_matrix(\*simulateTauLeap)(double startTime, double endTime, int numSteps), tc\_matrix(\*getSteadyState)(), tc\_matrix(\*steadyStateScan)(const char \*param, double start, double end, int numSteps), tc\_matrix(\*steadyStateScan2D)(const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2), tc\_matrix(\*getJacobian)(), tc\_matrix(\*getEigenvalues)(), tc\_matrix(\*getUnscaledElasticities tc\_matrix(\*getUnscaledConcentrationCC)(), tc\_matrix(\*getUnscaledFluxCC)(), tc\_matrix(\*getScaledFluxCC)(), tc\_matrix(\*getScaledFluxCC)(), tc\_matrix(\*getScaledFluxCC)(), tc\_matrix(\*tc\_reducedStoichiometry)(), tc\_matrix(\*tc\_emf)(), tc\_matrix(\*tc\_Lmat)(), tc\_matrix(\*tc\_Kmat)(), tc\_matrix(\*gaoptim)(const char \*), void(\*update)(tc\_matrix))

initializing function

#### 7.12.1 Function Documentation

7.12.1.1 TCAPIEXPORT void tc\_COPASI\_api ( tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateDeterministic, tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateStochastic, tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateHybrid, tc\_matrix(\*)(double startTime, double endTime, int numSteps) simulateTauLeap, tc\_matrix(\*)() getSteadyState, tc\_matrix(\*)(const char \*param, double start, double end, int numSteps) steadyStateScan, tc\_matrix(\*)(const char \*param1, double start1, double end1, int numSteps1, const char \*param2, double start2, double end2, int numSteps2) steadyStateScan2D, tc\_matrix(\*)() getJacobian, tc\_matrix(\*)() getEigenvalues, tc\_matrix(\*)() getUnscaledElasticities, tc\_matrix(\*)() getUnscaledFluxCC, tc\_matrix(\*)() getScaledFluxCC, tc\_matrix(\*)() getScaledFoncentrationCC, tc\_matrix(\*)() getScaledFluxCC, tc\_matrix(\*)() tc\_reducedStoichiometry, tc\_matrix(\*)() tc\_emf, tc\_matrix(\*)() tc\_Lmat, tc\_matrix(\*)() tc\_Kmat, tc\_matrix(\*)(const char \*) gaoptim, void(\*)(tc\_matrix) update)

initializing function

Definition at line 202 of file TC\_COPASI\_api.c.

# 7.13 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.c File Reference

#include "TC\_DynamicLibraryTool\_api.h"

# **Functions**

• TCAPIEXPORT int tc\_compileAndRun (const char \*command, const char \*args)

compile and run a c file

• TCAPIEXPORT int tc\_compileBuildLoad (const char \*filename, const char \*function, const char \*title)

compile a c file, generate the library, and load it

• TCAPIEXPORT int tc\_compileBuildLoadSliders (const char \*filename, const char \*function, const char \*title, tc\_matrix inputs)

compile a c file, generate the library, and load it

- TCAPIEXPORT void tc\_runPythonCode (const char \*code)
  - run the Python code given by the string
- TCAPIEXPORT void tc\_runPythonFile (const char \*filename)

run the Python code in the given file

TCAPIEXPORT void tc\_addPythonPlugin (const char \*file, const char \*name, const char \*description, const char \*category, const char \*icon)
 add a python script to the functions menu

- TCAPIEXPORT void tc\_runOctaveCode (const char \*code)
   run the Octave code given by the string
- TCAPIEXPORT void tc\_runOctaveFile (const char \*filename)
   run the Octave code in the given file
- TCAPIEXPORT void tc\_addOctavePlugin (const char \*file, const char \*name, const char \*description, const char \*category, const char \*icon)
   add a Octave script to the functions menu
- TCAPIEXPORT void tc\_callFunction (const char \*functionTitle)

  call a function listed in the functions menu, e.g. "Deterministic simulation"
- TCAPIEXPORT void tc\_loadLibrary (const char \*filename)
   run a dynamic C library that contains the function "tc\_main"
- TCAPIEXPORT void tc\_addFunction (void(\*f)(), const char \*title, const char \*description, const char \*category, const char \*iconFile, const char \*target\_family, int show\_menu, int in\_tool\_menu, int make\_default)
   add a function to the menu of functions
- TCAPIEXPORT void tc\_DynamicLibraryMenu\_api (void(\*callFunction)(const char \*))

initialize dialogs and c interface

• TCAPIEXPORT void tc\_LoadCLibraries\_api (int(\*compileAndRun)(const char \*, const char \*), int(\*compileBuildLoad)(const char \*, const char \*, const char \*), int(\*compileBuildLoadSliders)(const char \*, const char \*, const char \*, tc\_matrix), void(\*loadLibrary)(const char \*), void(\*addFunction)(void(\*f)(), const char \*, const char \*, const char \*, int, int, int))

initialize dialogs and c interface

• TCAPIEXPORT void tc\_PythonTool\_api (void(\*runPythonCode)(const char \*), void(\*runPythonFile)(const char \*), void(\*addPythonPlugin)(const char \*, const char \*, const char \*, const char \*))

initialize dialogs and c interface

• TCAPIEXPORT void tc\_OctaveTool\_api (void(\*runOctaveCode)(const char \*), void(\*runOctaveFile)(const char \*), void(\*addOctavePlugin)(const char \*, const char \*, const char \*, const char \*))

initialize dialogs and c interface

# 7.13 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.c File Reference 109

### **Variables**

- int(\* \_tc\_compileAndRun )(const char \*command, const char \*args)=0
- int(\* \_tc\_compileBuildLoad )(const char \*filename, const char \*function, const char \*title)=0
- int(\*\_tc\_compileBuildLoadSliders)(const char \*filename, const char \*function, const char \*title, tc\_matrix inputs)=0
- void(\* \_tc\_runPythonCode )(const char \*code)=0
- void(\* \_tc\_runPythonFile )(const char \*filename)=0
- void(\*\_tc\_addPythonPlugin )(const char \*, const char \*, const char \*, const char \*, const char \*)=0
- void(\* \_tc\_runOctaveCode )(const char \*code)=0
- void(\* \_tc\_runOctaveFile )(const char \*filename)=0
- void(\* \_tc\_addOctavePlugin )(const char \*, const char \*, const char \*, const char \*, const char \*)=0
- void(\* \_tc\_callFunction )(const char \*functionTitle)=0
- void(\* \_tc\_loadLibrary )(const char \*filename)=0
- void(\* \_tc\_addFunction )(void(\*f)(), const char \*title, const char \*description, const char \*category, const char \*iconFile, const char \*target\_family, int show\_menu, int in\_tool\_menu, int make\_default)=0

#### 7.13.1 Function Documentation

7.13.1.1 TCAPIEXPORT void tc\_addFunction ( void(\*)() f, const char \* title, const char \* description, const char \* category, const char \* iconFile, const char \* target\_family, int show\_menu, int in\_tool\_menu, int make\_default )

add a function to the menu of functions

Definition at line 132 of file TC\_DynamicLibraryTool\_api.c.

7.13.1.2 TCAPIEXPORT void tc\_addOctavePlugin ( const char \* file, const char \* name, const char \* description, const char \* category, const char \* icon )

add a Octave script to the functions menu

#### Parameters

string	octave script file
string	name of program
string	description of program
string	category where the program belongs (in the function menu)

Definition at line 99 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.1.3 TCAPIEXPORT void tc\_addPythonPlugin ( const char \* file, const char \* name, const char \* description, const char \* category, const char \* icon )

add a python script to the functions menu

### **Parameters**

string	python script file
string	name of program
string	description of program
string	category where the program belongs (in the function menu)

Definition at line 66 of file TC\_DynamicLibraryTool\_api.c.

## 7.13.1.4 TCAPIEXPORT void tc\_callFunction ( const char \* functionTitle )

call a function listed in the functions menu, e.g. "Deterministic simulation"

### **Parameters**

string	name of function

Definition at line 110 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.1.5 TCAPIEXPORT int tc\_compileAndRun ( const char \* command, const char \* args )

compile and run a c file

# **Parameters**

string	command
string	arguments

Definition at line 8 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.1.6 TCAPIEXPORT int tc\_compileBuildLoad ( const char \* filename, const char \* function, const char \* title )

compile a c file, generate the library, and load it

## **Parameters**

string	C code file name
string	main function inside C code
string	title of the program

Definition at line 20 of file TC\_DynamicLibraryTool\_api.c.

# 7.13 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.c File Reference 111

7.13.1.7 TCAPIEXPORT int tc\_compileBuildLoadSliders ( const char \* filename, const char \* function, const char \* title, tc\_matrix inputs )

compile a c file, generate the library, and load it compile a c file, generate the library, and load it as callback function for sliders Definition at line 32 of file TC\_DynamicLibraryTool\_api.c.

7.13.1.8 TCAPIEXPORT void tc\_DynamicLibraryMenu\_api (void(\*)(const char \*) callFunction)

initialize dialogs and c interface

Definition at line 142 of file TC\_DynamicLibraryTool\_api.c.

7.13.1.9 TCAPIEXPORT void tc\_LoadCLibraries\_api ( int(\*)(const char \*, const char \*)

compileAndRun, int(\*)(const char \*, const char \*, const char \*) compileBuildLoad,

int(\*)(const char \*, const char \*, tc\_matrix) compileBuildLoadSliders,

void(\*)(const char \*) loadLibrary, void(\*)(void(\*f)(), const char \*, const char \*, const

char \*, const char \*, const char \*, int, int, int) addFunction )

initialize dialogs and c interface

Definition at line 153 of file TC\_DynamicLibraryTool\_api.c.

7.13.1.10 TCAPIEXPORT void tc\_loadLibrary ( const char \* filename )

run a dynamic C library that contains the function "tc\_main"

### **Parameters**

string | name of C library

Definition at line 121 of file TC\_DynamicLibraryTool\_api.c.

7.13.1.11 TCAPIEXPORT void tc\_OctaveTool\_api ( void(\*)(const char \*) runOctaveCode, void(\*)(const char \*) runOctaveFile, void(\*)(const char \*, const char \*, const char \*, const char \*, addOctavePlugin )

initialize dialogs and c interface add a function to the menu of functions initialize octave plug-in

Definition at line 188 of file TC\_DynamicLibraryTool\_api.c.

7.13.1.12 TCAPIEXPORT void tc\_PythonTool\_api ( void(\*)(const char \*) runPythonCode, void(\*)(const char \*) runPythonFile, void(\*)(const char \*, const char \*, const char \*, const char \*, addPythonPlugin )

initialize dialogs and c interface

initialize python plug-in

Definition at line 172 of file TC\_DynamicLibraryTool\_api.c.

### 7.13.1.13 TCAPIEXPORT void tc\_runOctaveCode ( const char \* code )

run the Octave code given by the string

#### **Parameters**

string octave code

Definition at line 77 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.1.14 TCAPIEXPORT void tc\_runOctaveFile ( const char \* filename )

run the Octave code in the given file

### **Parameters**

string octave file

Definition at line 88 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.1.15 TCAPIEXPORT void tc\_runPythonCode ( const char \* code )

run the Python code given by the string

### **Parameters**

string python code

Definition at line 44 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.1.16 TCAPIEXPORT void tc\_runPythonFile ( const char \* filename )

run the Python code in the given file

# **Parameters**

string | python script file

# 7.13 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.c File Reference 113

Definition at line 55 of file TC\_DynamicLibraryTool\_api.c.

## 7.13.2 Variable Documentation

7.13.2.1 void(\* \_tc\_addFunction)(void(\*f)(), const char \*title, const char \*description, const char \*category, const char \*iconFile, const char \*target\_family, int show\_menu, int in\_tool\_menu, int make\_default)=0

Definition at line 127 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.2 void(\* \_tc\_addOctavePlugin)(const char \*, const char \*, const char \*, const char \*)=0

Definition at line 94 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.3 void(\* \_tc\_addPythonPlugin)(const char \*, const char \*, const char \*, const char \*, const char \*)=0

Definition at line 61 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.4 void(\* \_tc\_callFunction)(const char \*functionTitle)=0

Definition at line 105 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.5 int(\* \_tc\_compileAndRun)(const char \*command, const char \*args)=0

Definition at line 3 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.6 int(\* $\_$ tc $\_$ compileBuildLoad)(const char \*filename, const char \*function, const char \*title)=0

Definition at line 15 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.7 int(\* \_tc\_compileBuildLoadSliders)(const char \*filename, const char \*function, const char \*title, tc\_matrix inputs)=0

Definition at line 27 of file TC\_DynamicLibraryTool\_api.c.

7.13.2.8 void(\* \_tc\_loadLibrary)(const char \*filename)=0

Definition at line 116 of file TC\_DynamicLibraryTool\_api.c.

### 7.13.2.9 void(\* \_tc\_runOctaveCode)(const char \*code)=0

Definition at line 72 of file TC\_DynamicLibraryTool\_api.c.

## 7.13.2.10 void(\* \_tc\_runOctaveFile)(const char \*filename)=0

Definition at line 83 of file TC\_DynamicLibraryTool\_api.c.

## 7.13.2.11 void(\* \_tc\_runPythonCode)(const char \*code)=0

Definition at line 39 of file TC\_DynamicLibraryTool\_api.c.

# 7.13.2.12 void(\* \_tc\_runPythonFile)(const char \*filename)=0

Definition at line 50 of file TC\_DynamicLibraryTool\_api.c.

# 7.14 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.h File Reference

```
#include "TC_structs.h"
```

### **Functions**

- BEGIN\_C\_DECLS TCAPIEXPORT int tc\_compileAndRun (const char \*command, const char \*args)
  - compile and run a c file
- TCAPIEXPORT int tc\_compileBuildLoad (const char \*filename, const char \*function, const char \*title)
  - compile a c file, generate the library, and load it
- TCAPIEXPORT int tc\_compileBuildLoadSliders (const char \*filename, const char \*function, const char \*title, tc\_matrix inputs)
  - compile a c file, generate the library, and load it as callback function for sliders
- TCAPIEXPORT void tc\_runPythonCode (const char \*code)
   run the Python code given by the string
- TCAPIEXPORT void tc\_runPythonFile (const char \*filename)

  run the Python code in the given file
- TCAPIEXPORT void tc\_addPythonPlugin (const char \*file, const char \*name, const char \*description, const char \*category, const char \*icon)

add a python script to the functions menu

• TCAPIEXPORT void tc\_callFunction (const char \*functionTitle)

call a function listed in the functions menu, e.g. "Deterministic simulation"

• TCAPIEXPORT void tc\_loadLibrary (const char \*filename)

run a dynamic C library that contains the function "tc\_main"

• TCAPIEXPORT void tc\_OctaveTool\_api (void(\*runOctaveCode)(const char \*), void(\*runOctaveFile)(const char \*), void(\*addOctavePlugin)(const char \*, const char \*, const char \*))

add a function to the menu of functions

• TCAPIEXPORT void tc\_addFunction (void(\*f)(), const char \*title, const char \*description, const char \*category, const char \*iconFile, const char \*target\_family, int show\_menu, int in\_tool\_menu, int make\_default)

add a function to the menu of functions

• TCAPIEXPORT void tc\_runOctaveCode (const char \*code)

run the Octave code given by the string

• TCAPIEXPORT void tc\_runOctaveFile (const char \*filename)

run the Octave code in the given file

• TCAPIEXPORT void tc\_addOctavePlugin (const char \*file, const char \*name, const char \*description, const char \*category, const char \*icon)

add a Octave script to the functions menu

TCAPIEXPORT void tc\_DynamicLibraryMenu\_api (void(\*callFunction)(const char \*))

initialize dialogs and c interface

• TCAPIEXPORT void tc\_LoadCLibraries\_api (int(\*compileAndRun)(const char \*, const char \*), int(\*compileBuildLoad)(const char \*, const char \*, const char \*), int(\*compileBuildLoadSliders)(const char \*, const char \*, const char \*, tc\_matrix), void(\*loadLibrary)(const char \*), void(\*addFunction)(void(\*f)(), const char \*, const char \*, const char \*, int, int, int))

initialize dialogs and c interface

• TCAPIEXPORT void tc\_PythonTool\_api (void(\*runPythonCode)(const char \*), void(\*runPythonFile)(const char \*), void(\*addPythonPlugin)(const char \*, const char \*, const char \*, const char \*))

initialize python plug-in

### 7.14.1 Function Documentation

7.14.1.1 TCAPIEXPORT void tc\_addFunction ( void(\*)() f, const char \* title, const char \* description, const char \* category, const char \* iconFile, const char \* target\_family, int show\_menu, int in\_tool\_menu, int make\_default )

add a function to the menu of functions

Definition at line 132 of file TC\_DynamicLibraryTool\_api.c.

# 7.14.1.2 TCAPIEXPORT void tc\_addOctavePlugin ( const char \* *file*, const char \* *name*, const char \* *description*, const char \* *category*, const char \* *icon* )

add a Octave script to the functions menu

#### **Parameters**

string	octave script file
string	name of program
string	description of program
string	category where the program belongs (in the function menu)

Definition at line 99 of file TC\_DynamicLibraryTool\_api.c.

# 7.14.1.3 TCAPIEXPORT void tc\_addPythonPlugin ( const char \* file, const char \* name, const char \* description, const char \* category, const char \* icon )

add a python script to the functions menu

# **Parameters**

	string	python script file
	string	name of program
	string	description of program
	string	category where the program belongs (in the function menu)

Definition at line 66 of file TC\_DynamicLibraryTool\_api.c.

# 7.14.1.4 TCAPIEXPORT void tc\_callFunction ( const char \* functionTitle )

call a function listed in the functions menu, e.g. "Deterministic simulation"

# **Parameters**

string	name of function

Definition at line 110 of file TC\_DynamicLibraryTool\_api.c.

# 7.14 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.h File Reference 117

# 7.14.1.5 BEGIN\_C\_DECLS TCAPIEXPORT int tc\_compileAndRun ( const char \* command, const char \* args )

compile and run a c file

### **Parameters**

string	command
string	arguments

Definition at line 8 of file TC\_DynamicLibraryTool\_api.c.

# 7.14.1.6 TCAPIEXPORT int tc\_compileBuildLoad ( const char \* filename, const char \* function, const char \* title )

compile a c file, generate the library, and load it

### **Parameters**

string	C code file name
string	main function inside C code
string	title of the program

Definition at line 20 of file TC\_DynamicLibraryTool\_api.c.

# 7.14.1.7 TCAPIEXPORT int tc\_compileBuildLoadSliders ( const char \* function, const char \* title, tc\_matrix inputs )

compile a c file, generate the library, and load it as callback function for sliders

## **Parameters**

string	C code file name
string	callback function inside C code that will get called when slider values
	change
string	title of the program
tc_matrix	input of values for the sliders

Definition at line 32 of file TC\_DynamicLibraryTool\_api.c.

## 7.14.1.8 TCAPIEXPORT void tc\_DynamicLibraryMenu\_api (void(\*)(const char \*) callFunction)

initialize dialogs and c interface

Definition at line 142 of file TC\_DynamicLibraryTool\_api.c.

7.14.1.9 TCAPIEXPORT void tc\_LoadCLibraries\_api ( int(\*)(const char \*, const char \*)

compileAndRun, int(\*)(const char \*, const char \*, const char \*, const char \*)

int(\*)(const char \*, const char \*, const char \*, tc\_matrix) compileBuildLoadSliders,

void(\*)(const char \*) loadLibrary, void(\*)(void(\*f)(), const char \*, const char \*, const char \*, const char \*, int, int, int) addFunction )

initialize dialogs and c interface

Definition at line 153 of file TC\_DynamicLibraryTool\_api.c.

## 7.14.1.10 TCAPIEXPORT void tc\_loadLibrary ( const char \* filename )

run a dynamic C library that contains the function "tc\_main"

### **Parameters**

	C C 1'1
string	name of Clibrary
String	hame of Chorary
	· · · · · · · · · · · · · · · · · · ·

Definition at line 121 of file TC\_DynamicLibraryTool\_api.c.

7.14.1.11 TCAPIEXPORT void tc\_OctaveTool\_api ( void(\*)(const char \*) runOctaveCode, void(\*)(const char \*) runOctaveFile, void(\*)(const char \*, const char \*, const char \*, const char \*) addOctavePlugin )

add a function to the menu of functions initialize octave plug-in

### **Parameters**

void*	pointer to function
string	name of program
string	description of program
string	category of program (in the functions menu)
string	icon file (png file) use empty string for default
string	type of items in model that this function is specific for. use empty for no
	specifications
int	0 or 1 (show in tool's menu)
int	0 or 1 (make the default function when tinkercell loads)

initialize octave plug-in add a function to the menu of functions initialize octave plug-in Definition at line 188 of file TC\_DynamicLibraryTool\_api.c.

# 7.14 /home/deepak/TinkerCell/trunk/API/TC\_DynamicLibraryTool\_api.h File Reference 119

7.14.1.12 TCAPIEXPORT void tc\_PythonTool\_api ( void(\*)(const char \*) runPythonCode, void(\*)(const char \*) runPythonFile, void(\*)(const char \*, const char \*, const char \*, addPythonPlugin )

initialize python plug-in

Definition at line 172 of file TC\_DynamicLibraryTool\_api.c.

### 7.14.1.13 TCAPIEXPORT void tc\_runOctaveCode ( const char \* code )

run the Octave code given by the string

### **Parameters**

string octave code

Definition at line 77 of file TC\_DynamicLibraryTool\_api.c.

## 7.14.1.14 TCAPIEXPORT void tc\_runOctaveFile ( const char \* filename )

run the Octave code in the given file

#### **Parameters**

string octave file

Definition at line 88 of file TC\_DynamicLibraryTool\_api.c.

# 7.14.1.15 TCAPIEXPORT void tc\_runPythonCode ( const char \* code )

run the Python code given by the string

# Parameters

string python code

Definition at line 44 of file TC\_DynamicLibraryTool\_api.c.

## 7.14.1.16 TCAPIEXPORT void tc\_runPythonFile ( const char \* filename )

run the Python code in the given file

### **Parameters**

string | python script file

Definition at line 55 of file TC\_DynamicLibraryTool\_api.c.

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

# 7.15 /home/deepak/TinkerCell/trunk/API/TC\_EventsAssignments\_api.c File Reference

```
#include "TC_EventsAssignments_api.h"
```

#### **Functions**

- TCAPIEXPORT tc\_strings tc\_getEventTriggers ()
  get the event triggers for a set of items
- TCAPIEXPORT tc\_strings tc\_getEventResponses () get the event responses for a set of items
- TCAPIEXPORT void tc\_addEvent (const char \*trigger, const char \*event) set the event trigger and response
- TCAPIEXPORT void tc\_SimulationEventsTool\_api (tc\_strings(\*getEventTriggers)(), tc\_strings(\*getEventResponses)(), void(\*addEvent)(const char \*, const char \*))

initialize

- TCAPIEXPORT tc\_strings tc\_getForcingFunctionNames (tc\_items a) get the forcing function names for a set of items
- TCAPIEXPORT tc\_strings tc\_getForcingFunctionAssignments (tc\_items a) get the forcing function definitions for a set of items
- TCAPIEXPORT void tc\_addForcingFunction (long item, const char \*functionName, const char \*assignmentRule)
   set the forcing function for an item
- TCAPIEXPORT void tc\_AssignmentFunctionsTool\_api (tc\_strings(\*getForcingFunctionNames)(tc\_items), tc\_strings(\*getForcingFunctionAssignments)(tc\_items), void(\*addForcingFunction)(long, const char \*, const char \*))
   initialize

# **Variables**

- tc\_strings(\* \_tc\_getEventTriggers )()=0
- tc\_strings(\* \_tc\_getEventResponses )()=0
- void(\* \_tc\_addEvent )(const char \*trigger, const char \*event)=0
- tc\_strings(\* \_tc\_getForcingFunctionNames )(tc\_items)=0
- tc\_strings(\* \_tc\_getForcingFunctionAssignments )(tc\_items)=0
- void(\* \_tc\_addForcingFunction )(long item, const char \*functionName, const char \*assignmentRule)=0

### 7.15.1 Function Documentation

7.15.1.1 TCAPIEXPORT void tc\_AssignmentFunctionsTool\_api ( tc\_strings(\*)(tc\_items) getForcingFunctionNames, tc\_strings(\*)(tc\_items) getForcingFunctionAssignments, void(\*)(long, const char \*, const char \*) addForcingFunction )

initialize

initialize forcing functions plug-in

Definition at line 92 of file TC\_EventsAssignments\_api.c.

7.15.1.2 TCAPIEXPORT void tc\_SimulationEventsTool\_api ( tc\_strings(\*)() getEventTriggers, tc\_strings(\*)() getEventResponses, void(\*)(const char \*, const char \*) addEvent )

initialize

initialize events plug-in

Definition at line 42 of file TC\_EventsAssignments\_api.c.

### 7.15.2 Variable Documentation

7.15.2.1 void(\* \_tc\_addEvent)(const char \*trigger, const char \*event)=0

Definition at line 27 of file TC\_EventsAssignments\_api.c.

7.15.2.2 void(\*\_tc\_addForcingFunction)(long item, const char \*functionName, const char \*assignmentRule)=0

Definition at line 77 of file TC\_EventsAssignments\_api.c.

## 7.15.2.3 tc\_strings(\* \_tc\_getEventResponses)()=0

Definition at line 15 of file TC\_EventsAssignments\_api.c.

# 7.15.2.4 tc\_strings(\* \_tc\_getEventTriggers)()=0

Definition at line 3 of file TC\_EventsAssignments\_api.c.

# 7.15.2.5 tc\_strings(\* \_tc\_getForcingFunctionAssignments)(tc\_items)=0

Definition at line 65 of file TC\_EventsAssignments\_api.c.

### 7.15.2.6 tc\_strings(\* \_tc\_getForcingFunctionNames)(tc\_items)=0

Definition at line 53 of file TC\_EventsAssignments\_api.c.

# 7.16 /home/deepak/TinkerCell/trunk/API/TC\_EventsAssignments\_api.h

```
#include "TC structs.h"
```

### **Functions**

- BEGIN\_C\_DECLS TCAPIEXPORT tc\_strings tc\_getEventTriggers ()
   get the event triggers for a set of items
- TCAPIEXPORT tc\_strings tc\_getEventResponses ()
   get the event responses for a set of items
- TCAPIEXPORT void tc\_addEvent (const char \*trigger, const char \*event)
   set the event trigger and response
- TCAPIEXPORT void tc\_SimulationEventsTool\_api (tc\_strings(\*getEventTriggers)(), tc\_strings(\*getEventResponses)(), void(\*addEvent)(const char \*, const char \*))

initialize events plug-in

- TCAPIEXPORT tc\_strings tc\_getForcingFunctionNames (tc\_items a)
   get the forcing function names for a set of items
- TCAPIEXPORT tc\_strings tc\_getForcingFunctionAssignments (tc\_items a) get the forcing function definitions for a set of items
- TCAPIEXPORT void tc\_addForcingFunction (long item, const char \*variable, const char \*formula)

set the forcing function for an item

TCAPIEXPORT void tc\_AssignmentFunctionsTool\_api (tc\_strings(\*getForcingFunctionNames)(tc\_items), tc\_strings(\*getForcingFunctionAssignments)(tc\_items), void(\*addForcingFunction)(long, const char \*, const char \*))

initialize forcing functions plug-in

### 7.16.1 Function Documentation

7.16.1.1 TCAPIEXPORT void tc\_AssignmentFunctionsTool\_api ( tc\_strings(\*)(tc\_items) getForcingFunctionNames, tc\_strings(\*)(tc\_items) getForcingFunctionAssignments, void(\*)(long, const char \*, const char \*) addForcingFunction )

initialize forcing functions plug-in

Definition at line 92 of file TC\_EventsAssignments\_api.c.

7.16.1.2 TCAPIEXPORT void tc\_SimulationEventsTool\_api ( tc\_strings(\*)() getEventTriggers, tc\_strings(\*)() getEventResponses, void(\*)(const char \*, const char \*) addEvent )

initialize events plug-in

Definition at line 42 of file TC\_EventsAssignments\_api.c.

# 7.17 /home/deepak/TinkerCell/trunk/API/TC\_GroupHandlerTool\_api.c File Reference

#include "TC\_GroupHandlerTool\_api.h"

### **Functions**

- TCAPIEXPORT void tc\_merge (tc\_items parts)
  - merge an array of items
- TCAPIEXPORT void tc\_separate (long part)

separate all the graphical items in the handle

• TCAPIEXPORT void tc\_GroupHandlerTool\_api (void(\*merge)(tc\_items), void(\*separate)(long))

initialize grouping

# **Variables**

- void(\* \_tc\_merge )(tc\_items parts)=0
- void(\* \_tc\_separate )(long part)=0

### 7.17.1 Function Documentation

# 7.17.1.1 TCAPIEXPORT void tc\_GroupHandlerTool\_api ( void(\*)(tc\_items) merge, void(\*)(long) separate )

initialize grouping

initialize grouping plug-in

Definition at line 28 of file TC\_GroupHandlerTool\_api.c.

# 7.17.1.2 TCAPIEXPORT void tc\_merge ( tc\_items parts )

merge an array of items

### **Parameters**

*tc\_items* list of items

Definition at line 8 of file TC\_GroupHandlerTool\_api.c.

## 7.17.1.3 TCAPIEXPORT void tc\_separate ( long part )

separate all the graphical items in the handle

#### **Parameters**

int address of item

Definition at line 19 of file TC\_GroupHandlerTool\_api.c.

## 7.17.2 Variable Documentation

# 7.17.2.1 void(\* \_tc\_merge)(tc\_items parts)=0

Definition at line 3 of file TC\_GroupHandlerTool\_api.c.

## 7.17.2.2 void(\* \_tc\_separate)(long part)=0

Definition at line 14 of file TC\_GroupHandlerTool\_api.c.

# 7.18 /home/deepak/TinkerCell/trunk/API/TC\_GroupHandlerTool\_api.h File Reference

#include "TC\_structs.h"

### **Functions**

- BEGIN\_C\_DECLS TCAPIEXPORT void tc\_merge (tc\_items parts)

  merge an array of items
- TCAPIEXPORT void tc\_separate (long part) separate all the graphical items in the handle
- TCAPIEXPORT void tc\_GroupHandlerTool\_api (void(\*merge)(tc\_items), void(\*separate)(long))

initialize grouping plug-in

### 7.18.1 Function Documentation

# 7.18.1.1 TCAPIEXPORT void tc\_GroupHandlerTool\_api ( void(\*)(tc\_items) merge, void(\*)(long) separate )

initialize grouping plug-in

Definition at line 28 of file TC\_GroupHandlerTool\_api.c.

## 7.18.1.2 BEGIN\_C\_DECLS TCAPIEXPORT void tc\_merge ( tc\_items parts )

merge an array of items

## **Parameters**

tc\_items list of items

Definition at line 8 of file TC\_GroupHandlerTool\_api.c.

# 7.18.1.3 TCAPIEXPORT void tc\_separate ( long part )

separate all the graphical items in the handle

### **Parameters**

int address of item

Definition at line 19 of file TC\_GroupHandlerTool\_api.c.

# 7.19 /home/deepak/TinkerCell/trunk/API/TC\_Main\_api.c File Reference

#include "TC\_Main\_api.h"

### **Functions**

```
• TCAPIEXPORT tc_items tc_allItems ()
```

get all visible items

• TCAPIEXPORT to items to selectedItems ()

get all selected items

• TCAPIEXPORT tc\_items tc\_itemsOfFamily (const char \*family)

get all items of the given family items

TCAPIEXPORT tc\_items tc\_itemsOfFamilyFrom (const char \*family, tc\_items itemsToSelectFrom)

get subset of items that belong to the given family

• TCAPIEXPORT long tc\_find (const char \*fullname)

get the first item with the given name (full name)

• TCAPIEXPORT tc\_items tc\_findItems (tc\_strings names)

get all items with the given names (full names)

• TCAPIEXPORT void tc\_select (long item)

select an item

• TCAPIEXPORT void tc\_deselect ()

deselect all items

• TCAPIEXPORT const char \* tc\_getName (long item)

get the full name of an item

• TCAPIEXPORT const char \* tc\_getUniqueName (long item)

get the full name of an item

• TCAPIEXPORT void tc\_rename (long item, const char \*name)

set the name of an item (not full name)

• TCAPIEXPORT tc\_strings tc\_getNames (tc\_items items)

get the full names of several items

• TCAPIEXPORT tc\_strings tc\_getUniqueNames (tc\_items items)

get the full names of several items

• TCAPIEXPORT const char \* tc\_getFamily (long item)

get the family name of an item

• TCAPIEXPORT int tc\_isA (long item, const char \*family)

check is an item belongs in a family (or in a sub-family)

- TCAPIEXPORT void tc\_print (const char \*text) show text in the output window.
- TCAPIEXPORT void tc\_openUrl (const char \*s) show text in the output window.
- TCAPIEXPORT void tc\_errorReport (const char \*text) show error text in the output window.
- TCAPIEXPORT void tc\_printMatrix (tc\_matrix data) show table in the output window.
- TCAPIEXPORT void tc\_printFile (const char \*filename) show file contents in the output window.
- TCAPIEXPORT void tc\_clear () cleat the contents in the output window.
- TCAPIEXPORT void tc\_remove (long item)

  delete an item
- TCAPIEXPORT double tc\_getY (long item) get the x location of an item
- TCAPIEXPORT double tc\_getX (long item) get the y location of an item
- TCAPIEXPORT tc\_matrix tc\_getPos (tc\_items items) get the y location of a list item. Output is a N x 2 matrix
- TCAPIEXPORT void tc\_setPos (long item, double x, double y) set the x and y location of an item
- TCAPIEXPORT void tc\_setPosMulti (tc\_items items, tc\_matrix positions) set the x and y location of a list of N items. Input a matrix of positions, with N rows and 2 columns (x,y)
- TCAPIEXPORT void tc\_moveSelected (double dx, double dy)

  move all the selected items by a given amount
- TCAPIEXPORT int tc\_isWindows () is this running in MS windows?
- TCAPIEXPORT int tc\_isMac ()

is this running in a Mac?

• TCAPIEXPORT int tc\_isLinux ()

is this running in Linux?

• TCAPIEXPORT const char \* tc\_appDir ()

TinkerCell application folder.

TCAPIEXPORT const char \* tc\_homeDir ()

TinkerCell home folder.

• TCAPIEXPORT void tc\_createInputWindowForScript (tc\_matrix input, const char \*filename, const char \*functionname)

create an input window that can call a dynamic library

TCAPIEXPORT void tc\_createInputWindow (tc\_matrix input, const char \*title, void(\*f)(tc\_matrix))

create an input window that can call a dynamic library

TCAPIEXPORT void tc\_addInputWindowOptions (const char \*title, int i, int j, tc\_strings options)

add options to an existing input window at the i,j-th cell. Options will appear in a list

• TCAPIEXPORT void tc\_addInputWindowCheckbox (const char \*title, int i, int j)

add a yes or no type of option to an existing input window at the i,j-th cell

- TCAPIEXPORT void tc\_openNewWindow (const char \*title)
   open a new graphics window
- TCAPIEXPORT tc\_items tc\_getChildren (long o) get child items of the given item
- TCAPIEXPORT long tc\_getParent (long o) get parent item of the given item
- TCAPIEXPORT tc\_matrix tc\_getNumericalData (long item, const char \*data) get the entire data matrix for the given numerical data table of the given item
- TCAPIEXPORT double tc\_getNumericalValue (const char \*name) get a value from its full name
- TCAPIEXPORT const char \* tc\_getTextValue (const char \*name)
   get a text value from its full name
- TCAPIEXPORT void tc\_setNumericalData (long o, const char \*title, tc\_matrix data)

set a new data matrix for an item. Use 0 for the global model item.

- TCAPIEXPORT void tc\_setNumericalValues (tc\_matrix data)
   set multiple values in a model. The input matrix row names correspond to data names.
- TCAPIEXPORT void tc\_setNumericalValue (const char \*name, double value) set a single value in a model
- TCAPIEXPORT tc\_table tc\_getTextData (long item, const char \*data) get the entire data matrix for the given strings data table of the given item
- TCAPIEXPORT void tc\_setTextData (long o, const char \*title, tc\_table data) set the entire data matrix for the given strings data table of the given item
- TCAPIEXPORT void tc\_setTextValues (tc\_table data)
   set multiple values in a model. The input matrix row names correspond to data names.
- TCAPIEXPORT void tc\_setTextValue (const char \*name, const char \*value) set a single value in a model
- TCAPIEXPORT tc\_strings tc\_getNumericalDataNames (long o) get all the numeric data table names for the given item. Use 0 for the global tables.
- TCAPIEXPORT tc\_strings tc\_getTextDataNames (long o)
   get all the text data table names for the given item. Use 0 for the global tables.
- TCAPIEXPORT void tc\_zoom (double factor)

  zoom by the given factor (0 1)
- TCAPIEXPORT const char \* tc\_getStringDialog (const char \*title)

  get a text from the user (dialog)
- TCAPIEXPORT const char \* tc\_getFilename ()
   get a file from the user (dialog)
- TCAPIEXPORT int tc\_getStringFromList (const char \*title, tc\_strings list, const char \*selectedString)

get a text from the user (dialog) from a list of selections

- TCAPIEXPORT double tc\_getNumber (const char \*title) get a number from the user (dialog)
- TCAPIEXPORT void tc\_getNumbers (tc\_strings labels, double \*result) get a list of numbers from the user (dialog) into the argument array
- TCAPIEXPORT int tc\_askQuestion (const char \*message)

display a dialog with a text and a yes and no button

TCAPIEXPORT void tc\_messageDialog (const char \*message)
 display a dialog with a text message and a close button

- TCAPIEXPORT void tc\_openFile (const char \*message)
   open file
- TCAPIEXPORT void tc\_saveToFile (const char \*message)
   save to file
- TCAPIEXPORT long tc\_thisThread ()
   get pointer to the current thread
- TCAPIEXPORT void tc\_createSliders (tc\_matrix input, void(\*f)(tc\_matrix))

  create a window with several sliders. when the sliders change, the given function will
  be called with the values in the sliders
- TCAPIEXPORT void tc\_setSize (long item, double width, double height) Change the size of an item.
- TCAPIEXPORT double tc\_getWidth (long item) get the width of an item
- TCAPIEXPORT double tc\_getHeight (long item) get the width of an item
- TCAPIEXPORT void tc\_rotate (long item, double t) get the width of an item
- TCAPIEXPORT const char \* tc\_getColor (long item) get the color of the item
- TCAPIEXPORT void tc\_setColor (long item, const char \*name, int permanent)
- TCAPIEXPORT void tc\_changeNodeImage (long item, const char \*filename) change the graphics file for drawing one of the nodes

set the color of the item and indicate whether or not the color is permanenet

- TCAPIEXPORT void tc\_changeArrowHead (long connection, const char \*filename)

  change the graphics file for drawing the arrowheads for the given connection
- TCAPIEXPORT void tc\_screenshot (const char \*filename, int width, int height)

  save screenshot in a file

- TCAPIEXPORT int tc\_screenWidth ()
   get width of current canvas
- TCAPIEXPORT int tc\_screenHeight () get height of current canvas
- TCAPIEXPORT int tc\_screenX () get x of current canvas
- TCAPIEXPORT int tc\_screenY () get y of current canvas
- TCAPIEXPORT const char \* tc\_annotations ()
   get text displayed on the canvas
- TCAPIEXPORT void tc\_insertAnnotations (const char \*s, double x, double y) show text displayed on the canvas at the given position
- TCAPIEXPORT void tc\_Main\_api\_initialize (tc\_items(\*tc\_allItems0)(), tc\_items(\*tc\_selectedItems0)(), tc\_items(\*tc\_itemsOfFamily0)(const char \*), tc\_items(\*tc\_itemsOfFamily1)(const char \*, tc\_items), long(\*tc\_find0)(const char \*), tc\_items(\*tc\_findItems0)(tc\_strings), void(\*tc\_select0)(long), void(\*tc\_deselect0)(), const char \*(\*tc\_getName0)(long), const char \*(\*tc\_getUniqueName0)(long), void(\*tc\_setName0)(long item, const char \*name), tc\_strings(\*tc\_getNames0)(tc\_items), tc\_strings(\*tc\_getUniqueNames0)(tc\_items), const char \*(\*tc\_getFamily0)(long), int(\*tc\_isA0)(long, const char \*), void(\*tc\_clearText)(), void(\*tc\_outputText0)(const char \*), void(\*tc\_errorReport0)(const char \*), void(\*tc\_outputTable0)(tc\_matrix), void(\*tc\_printFile0)(const char \*), void(\*tc\_removeItem0)(long), double(\*tc\_getY0)(long), double(\*tc getX0)(long), tc matrix(\*tc getPos0)(tc items), void(\*tc setPos0)(long, double, double), void(\*tc\_setPos1)(tc\_items, tc\_matrix), void(\*tc\_moveSelected0)(double, double), int(\*tc\_isWindows0)(), int(\*tc\_isMac0)(), int(\*tc\_isLinux0)(), const char \*(\*tc\_appDir0)(), const char \*(\*tc\_homeDir0)(), void(\*tc\_createInputWindow0)(tc matrix, const char \*, const char \*), void(\*tc createInputWindow1)(long ptr, tc\_matrix, const char \*, void(\*f)(tc\_matrix)), void(\*createSliders0)(long, tc\_matrix, void(\*f)(tc\_matrix)), void(\*tc\_addInputWindowOptions0)(const char \*, int i, int j, tc strings), void(\*tc addInputWindowCheckbox0)(const char \*, int i, int j), void(\*tc openNewWindow0)(const const char \*title), tc items(\*tc getChildren0)(long), long(\*tc\_getParent0)(long), tc\_matrix(\*tc\_getNumericalData0)(long, const char \*), void(\*tc\_setNumericalData0)(long, const char \*, tc\_matrix), tc\_table(\*tc\_getTextData0)(long, const char \*), void(\*tc\_setTextData0)(long, const char \*, tc\_table), tc\_strings(\*tc\_getNumericalDataNames0)(long), tc\_strings(\*tc\_getTextDataNames0)(long), void(\*tc\_zoom0)(double factor), const char \*(\*tc\_getString0)(const char \*), int(\*getSelectedString0)(const char \*, tc\_strings, const char \*), double(\*getNumber0)(const char \*), void(\*getNumbers0)(tc\_strings, double \*), const char \*(\*getFilename0)(), int(\*askQuestion0)(const char \*), void(\*messageDialog0)(const char \*), void(\*openFile0)(const char \*), void(\*saveToFile0)(const char \*), void(\*setSize0)(long, double, double, int), double(\*getWidth0)(long), double(\*getHeight0)(long), void(\*setAngle0)(long,

double, int), const char \*(\*getColor0)(long), void(\*setColor0)(long, const char \*, int), void(\*changeGraphics0)(long, const char \*), void(\*changeArrowHead0)(long, const char \*), void(\*screenStot)(const char \*, int, int), int(\*screenWidth)(), int(\*screenHeight)(), int(\*screenX)(), int(\*screenY)(), const char \*(\*annotations)(), void(\*insertAnnotations)(const char \*, double, double), void(\*setNumericalValues)(tc\_matrix), void(\*setNumericalValue)(const char \*, double), void(\*setTextValues)(tc\_table), void(\*setTextValue)(const char \*, const char \*), double(\*getNumericalValue)(const char \*), const char \*(\*getTextValue)(const char \*), void(\*openUrl)())

initialize main

- TCAPIEXPORT void tc\_showProgress (const char \*title, int progress)
   show progress of current operation
- TCAPIEXPORT void tc\_callback (void(\*f)(void))
   this function will be called whenever the model is changed
- TCAPIEXPORT void tc\_callWhenExiting (void(\*f)(void))
   this function will be called whenever Tinkercell exits. Use it to free memory.
- TCAPIEXPORT void tc\_CThread\_api\_initialize (long cthread, void(\*callback)(long, void(\*f)(void)), void(\*callWhenExiting)(long, void(\*f)(void)), void(\*showProgress)(long, const char \*, int))

initialize main

- TCAPIEXPORT void tc\_displayText (long item, const char \*text)

  displays the given text on the given item (the text is temporary)
- TCAPIEXPORT void tc\_displayNumber (long item, double number)

  displays the given number on the given item (the text is temporary)
- TCAPIEXPORT void tc\_setDisplayLabelColor (const char \*a, const char \*b)
   set the color for the number or text when using tc\_displayNumber and tc\_displayText
- TCAPIEXPORT void tc\_highlight (long item, const char \*color)
   highlights an item (the highlight is temporary) with the given color (hex)
- TCAPIEXPORT void tc\_burn (long item, double intensity)
   burn
- TCAPIEXPORT void tc\_LabelingTool\_api (void(\*displayText)(long item, const char \*), void(\*displayNumber)(long item, double), void(\*setDisplayLabelColor)(const char \*, const char \*), void(\*highlight)(long, const char \*), void(\*burn)(long, double))

initialize

#### **Variables**

```
• tc items(* tc allItems)()=0
• tc_items(* _tc_selectedItems )()=0
• tc_items(* _tc_itemsOfFamily )(const char *family)=0
• tc_items(* _tc_itemsOfFamilyFrom )(const char *family, tc_items itemsToSe-
  lectFrom)=0
• long(* _tc_find )(const char *fullname)=0
• tc_items(* _tc_findItems )(tc_strings names)=0
• void(* <u>tc_select</u>)(long item)=0
• void(* _tc_deselect )()=0
• const char *(* tc getName )(long item)=0
• const char *(* _tc_getUniqueName )(long item)=0
• void(* _tc_rename )(long item, const char *name)=0
• tc_strings(* _tc_getNames )(tc_items items)=0
• tc_strings(* _tc_getUniqueNames )(tc_items items)=0
• const char *(* _tc_getFamily )(long item)=0
• int(* _tc_isA )(long item, const char *family)=0
• void(* _tc_print )(const char *text)=0
• void(* _tc_openUrl )(const char *file)=0
• void(* _tc_errorReport )(const char *text)=0
• void(* _tc_printMatrix )(tc_matrix data)=0
• void(* _tc_printFile )(const char *filename)=0
• void(* tc clear)()=0
• void(* _tc_remove )(long item)=0
• double(* _tc_getY )(long item)=0
• double(* <u>tc_getX</u>)(long item)=0
• tc_matrix(* _tc_getPos )(tc_items items)=0
• void(* tc setPos)(long item, double x, double y)=0
• void(* _tc_setPosMulti )(tc_items items, tc_matrix positions)=0
• void(* tc moveSelected)(double dx, double dy)=0
• int(* _tc_isWindows )()=0
• int(* _tc_isMac )()=0
• int(* _tc_isLinux )()=0
• const char *(* _tc_appDir )()=0
• const char *(* tc homeDir)()=0
• void(*_tc_createInputWindowForScript)(tc_matrix input, const char *title, const
  char *functionname)=0
• void(*_tc_createInputWindow)(long ptr, tc_matrix, const char *title, void(*f)(tc_-
  matrix) = 0
• void(* _tc_addInputWindowOptions )(const char *, int i, int j, tc_strings)=0
• void(* _tc_addInputWindowCheckbox )(const char *, int i, int j)=0
• void(* _tc_openNewWindow )(const char *title)=0
• tc_items(* _tc_getChildren )(long)=0
```

• double(\* \_tc\_getNumericalValue )(const char \*)=0

• tc\_matrix(\* \_tc\_getNumericalData )(long item, const char \*data)=0

• long(\* \_tc\_getParent )(long)=0

```
• const char *(* tc getTextValue )(const char *name)=0
• void(* _tc_setNumericalData )(long, const char *, tc_matrix)=0
• void(* _tc_setNumericalValues )(tc_matrix)=0
• void(* tc setNumericalValue)(const char *, double)=0
• tc_table(* _tc_getTextData )(long item, const char *data)=0
• void(* _tc_setTextData )(long, const char *, tc_table)=0
• void(* _tc_setTextValues )(tc_table)=0
• void(* tc setTextValue)(const char *, const char *)=0
• tc_strings(* _tc_getNumericalDataNames )(long)=0
• tc_strings(* _tc_getTextDataNames )(long)=0
• void(* _tc_zoom )(double factor)=0
• const char *(* tc getStringDialog )(const char *title)=0
• const char *(* tc getFilename)()=0
• int(*_tc_getStringFromList)(const char *title, tc_strings list, const char *selectedString)=0
• double(* _tc_getNumber )(const char *title)=0
• void(* _tc_getNumbers )(tc_strings labels, double *result)=0
• int(* _tc_askQuestion )(const char *)=0
• void(* _tc_messageDialog )(const char *)=0
• void(* _tc_openFile )(const char *)=0
• void(* tc saveToFile)(const char *)=0
• void(* tc createSliders)(long, tc matrix, void(*f)(tc matrix))=0
• void(* _tc_setSize )(long, double, double, int)=0
• double(* _tc_getWidth )(long)=0
• double(* _tc_getHeight )(long)=0
• void(* tc setAngle)(long, double, int)=0
• const char *(* _tc_getColor )(long item)=0
• void(* <u>tc_setColor</u>)(long item, const char *name, int permanent)=0
• void(* _tc_changeNodeImage)(long, const char *)=0
• void(* tc changeArrowHead)(long, const char *)=0
• void(* tc screenshot)(const char *filename, int width, int height)=0
• int(* tc screenWidth)(void)=0
• int(* _tc_screenHeight)(void)=0
• int(* tc screenX)(void)=0
• int(* _tc_screenY )(void)=0
• const char *(* _tc_annotations )()=0
• void(* _tc_insertAnnotations )(const char *, double, double)=0
• void(* tc showProgress)(long thread, const char *title, int progress)=0
• void(* _tc_callback )(long, void(*f)(void))=0
• void(* _tc_callWhenExiting)(long, void(*f)(void))=0
• void(* _tc_displayText )(long item, const char *text)=0
• void(* tc displayNumber)(long item, double number)=0
• void(* tc setDisplayLabelColor)(const char *, const char *)=0
• void(* _tc_highlight)(long item, const char *)=0
```

• void(\* <u>tc\_burn</u>)(long item, double intensity)=0

#### 7.19.1 Function Documentation

# 7.19.1.1 TCAPIEXPORT void tc\_callback ( void(\*)(void) f )

this function will be called whenever the model is changed

#### **Parameters**

void*	callback function pointer
-------	---------------------------

Definition at line 1141 of file TC\_Main\_api.c.

# 7.19.1.2 TCAPIEXPORT void tc\_callWhenExiting (void(\*)(void) f)

this function will be called whenever Tinkercell exits. Use it to free memory.

#### **Parameters**

void*	callback function pointer

Definition at line 1153 of file TC\_Main\_api.c.

7.19.1.3 TCAPIEXPORT void tc\_CThread\_api\_initialize ( long cthread, void(\*)(long, void(\*f)(void)) callback, void(\*)(long, void(\*f)(void)) callWhenExiting, void(\*)(long, const char \*, int) showProgress )

initialize main

Definition at line 1163 of file TC\_Main\_api.c.

# 7.19.1.4 TCAPIEXPORT tc\_matrix tc\_getNumericalData ( long item, const char \* data )

get the entire data matrix for the given numerical data table of the given item

#### **Parameters**

int	address of item. use 0 for the model item
string	name of numerical data table

# Returns

tc\_matrix the numerical data table for the given item

Definition at line 474 of file TC\_Main\_api.c.

# 7.19.1.5 TCAPIEXPORT tc\_strings tc\_getNumericalDataNames ( long o )

get all the numeric data table names for the given item. Use 0 for the global tables.

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

get all the numeric data table names for the given item Definition at line 589 of file TC\_Main\_api.c.

#### 7.19.1.6 TCAPIEXPORT double tc\_getNumericalValue ( const char \* name )

get a value from its full name
get a numerical value from its full name
Definition at line 487 of file TC\_Main\_api.c.

# 7.19.1.7 TCAPIEXPORT tc\_table tc\_getTextData ( long item, const char \* data )

get the entire data matrix for the given strings data table of the given item get the entire data table for the given strings data table of the given item Definition at line 544 of file TC\_Main\_api.c.

#### 7.19.1.8 TCAPIEXPORT tc\_strings tc\_getTextDataNames ( long o )

get all the text data table names for the given item. Use 0 for the global tables. get all the text data table names for the given item

Definition at line 601 of file TC\_Main\_api.c.

### 7.19.1.9 TCAPIEXPORT const char\* tc\_getTextValue ( const char\* name )

get a text value from its full name

#### **Parameters**

string full name

Definition at line 499 of file TC\_Main\_api.c.

7.19.1.10 TCAPIEXPORT void tc\_LabelingTool\_api ( void(\*)(long item, const char \*) displayText, void(\*)(long item, double) displayNumber, void(\*)(const char \*, const char \*) setDisplayLabelColor, void(\*)(long, const char \*) highlight, void(\*)(long, double) burn )

initialize

Definition at line 1235 of file TC\_Main\_api.c.

7.19.1.11 TCAPIEXPORT void tc\_Main\_api\_initialize ( tc items(\*)() tc\_allItems0, tc items(\*)() tc\_selectedItems0, tc items(\*)(const char \*) tc\_itemsOfFamily0, tc\_items(\*)(const char \*, tc\_items) tc\_itemsOfFamily1, long(\*)(const char \*) tc\_find0, tc\_items(\*)(tc\_strings) tc\_findItems0, void(\*)(long) tc\_select0, void(\*)() tc\_deselect0, const char \*(\*)(long) tc\_getName0, const char \*(\*)(long) tc\_getUniqueName0, void(\*)(long item, const char \*name) tc\_setName0, tc\_strings(\*)(tc\_items) tc\_getNames0, tc\_strings(\*)(tc\_items) tc\_getUniqueNames0, const char \*(\*)(long) tc\_getFamily0, int(\*)(long, const char \*) tc\_isA0, void(\*)() tc\_clearText, void(\*)(const char \*) tc\_outputText0, void(\*)(const char \*) tc\_errorReport0, void(\*)(tc\_matrix) tc\_outputTable0, void(\*)(const char \*) tc\_printFile0, void(\*)(long) tc\_removeItem0, double(\*)(long) tc\_getY0, double(\*)(long) tc\_getX0, tc\_matrix(\*)(tc\_items) tc\_getPos0, void(\*)(long, double, double) tc\_setPos0, void(\*)(tc\_items, tc\_matrix) tc\_setPos1, void(\*)(double, double) tc\_moveSelected0, int(\*)() tc\_isWindows0, int(\*)() tc\_isMac0, int(\*)() tc\_isLinux0, const char \*(\*)() tc\_appDir0, const char \*(\*)() tc\_homeDir0, void(\*)(tc\_matrix, const char \*, const char \*) tc\_createInputWindow0, void(\*)(long ptr, tc\_matrix, const char \*, void(\*f)(tc\_matrix)) tc\_createInputWindow1, void(\*)(long, tc\_matrix, void(\*f)(tc\_matrix)) createSliders0, void(\*)(const char \*, int i, int j, tc strings) tc\_addInputWindowOptions0, void(\*)(const char \*, int i, int j) tc\_addInputWindowCheckbox0, void(\*)(const const char \*title) tc\_openNewWindow0, tc items(\*)(long) tc\_getChildren0, long(\*)(long) tc\_getParent0, tc\_matrix(\*)(long, const char \*) tc\_getNumericalData0, void(\*)(long, const char \*, tc\_matrix) tc\_setNumericalData0, tc\_table(\*)(long, const char \*) tc\_getTextData0, void(\*)(long, const char \*, tc\_table) tc\_setTextData0, tc\_strings(\*)(long) tc\_getNumericalDataNames0, tc\_strings(\*)(long) tc\_getTextDataNames0, void(\*)(double factor) tc\_zoom0, const char \*(\*)(const char \*) tc\_getString0, int(\*)(const char \*, tc\_strings, const char \*) getSelectedString0, double(\*)(const char \*) getNumber0, void(\*)(tc\_strings, double \*) getNumbers0, const char \*(\*)() getFilename0, int(\*)(const char \*) askQuestion0, void(\*)(const char \*) messageDialog0, void(\*)(const char \*) openFile0, void(\*)(const char \*) saveToFile0, void(\*)(long, double, double, int) setSize0, double(\*)(long) getWidth0, double(\*)(long) getHeight0, void(\*)(long, double, int) setAngle0, const char \*(\*)(long) getColor0, void(\*)(long, const char \*, int) setColor0, void(\*)(long, const char \*) changeGraphics0, void(\*)(long, const char \*) changeArrowHead0, void(\*)(const char \*, int, int) screenshot, int(\*)() screenWidth, int(\*)() screenHeight, int(\*)() screenX, int(\*)() screen Y, const char \*(\*)() annotations, void(\*)(const char \*, double, double)insertAnnotations, void(\*)(tc\_matrix) setNumericalValues, void(\*)(const char \*, double) setNumericalValue, void(\*)(tc\_table) setTextValues, void(\*)(const char \*, const char \*) setTextValue, double(\*)(const char \*) getNumericalValue, const char \*(\*)(const char \*) getTextValue, void(\*)() openUrl )

initialize main

Definition at line 919 of file TC Main api.c.

7.19.1.12 TCAPIEXPORT void tc\_remove ( long item )

delete an item

#### **Parameters**

int	address of item

Definition at line 254 of file TC\_Main\_api.c.

# 7.19.1.13 TCAPIEXPORT void tc\_setNumericalData ( long o, const char \* title, tc\_matrix data )

set a new data matrix for an item. Use 0 for the global model item. set a new data matrix for an item or replace an existing one Definition at line 511 of file TC\_Main\_api.c.

# 7.19.1.14 TCAPIEXPORT void tc\_setNumericalValue ( const char \* name, double value )

set a single value in a model

#### **Parameters**

string	name of variable
double	new value of variable

Definition at line 533 of file TC\_Main\_api.c.

# 7.19.1.15 TCAPIEXPORT void tc\_setNumericalValues ( tc\_matrix data )

set multiple values in a model. The input matrix row names correspond to data names.

### **Parameters**

to	c_matrix	matrix wi	th rownames	with the	names	of the	variables	and	columns	with
		values								

Definition at line 522 of file TC Main api.c.

# 7.19.1.16 TCAPIEXPORT void tc\_setTextData ( long o, const char \* title, tc\_table data )

set the entire data matrix for the given strings data table of the given item set or replace the entire data matrix for the given strings data table of the given item Definition at line 556 of file TC\_Main\_api.c.

### 7.19.1.17 TCAPIEXPORT void tc\_setTextValue ( const char \* name, const char \* value )

set a single value in a model set a single text value in a model

Definition at line 578 of file TC\_Main\_api.c.

# 7.19.1.18 TCAPIEXPORT void tc\_setTextValues ( tc\_table data )

set multiple values in a model. The input matrix row names correspond to data names.

#### **Parameters**

tc_table	table	with	rownames	with	the	names	of	the	variables	and	columns	with
	value	S										

Definition at line 567 of file TC\_Main\_api.c.

#### 7.19.1.19 TCAPIEXPORT long tc\_thisThread ( )

get pointer to the current thread get pointer to the current thread. used for passing this thread as some argument Definition at line 731 of file TC\_Main\_api.c.

#### 7.19.2 Variable Documentation

#### 7.19.2.1 void(\* \_tc\_addInputWindowCheckbox)(const char \*, int i, int j)=0

Definition at line 423 of file TC\_Main\_api.c.

# 7.19.2.2 void(\* \_tc\_addInputWindowOptions)(const char \*, int i, int j, tc\_strings)=0

Definition at line 412 of file TC\_Main\_api.c.

# 7.19.2.3 tc\_items(\* \_tc\_allItems)()=0

Definition at line 5 of file TC\_Main\_api.c.

#### 7.19.2.4 const char\*(\* \_tc\_annotations)()=0

Definition at line 894 of file TC\_Main\_api.c.

# 7.19.2.5 const char\*(\* \_tc\_appDir)()=0

Definition at line 366 of file TC\_Main\_api.c.

# 7.19.2.6 int(\* \_tc\_askQuestion)(const char \*)=0

Definition at line 678 of file TC\_Main\_api.c.

7.19.2.7 void(\* \_tc\_burn)(long item, double intensity)=0

Definition at line 1220 of file TC\_Main\_api.c.

7.19.2.8 void(\* \_tc\_callback)(long, void(\*f)(void))=0

Definition at line 1135 of file TC\_Main\_api.c.

7.19.2.9 void(\* \_tc\_callWhenExiting)(long, void(\*f)(void))=0

Definition at line 1147 of file TC\_Main\_api.c.

7.19.2.10 void(\* \_tc\_changeArrowHead)(long, const char \*)=0

Definition at line 828 of file TC\_Main\_api.c.

7.19.2.11 void(\* \_tc\_changeNodeImage)(long, const char \*)=0

Definition at line 817 of file TC\_Main\_api.c.

7.19.2.12 void(\* \_tc\_clear)()=0

Definition at line 238 of file TC Main api.c.

7.19.2.13 void(\*  $\_tc\_createInputWindow$ )(long ptr,  $tc\_matrix$ , const char \*title, void(\*f)(tc $\_matrix$ ))=0

Definition at line 401 of file TC\_Main\_api.c.

7.19.2.14 void(\* $\_$ tc $\_$ createInputWindowForScript)(tc $\_$ matrix input, const char \*title, const char \*functionname)=0

Definition at line 390 of file TC\_Main\_api.c.

 $7.19.2.15 \quad \text{void}(*\_tc\_createSliders)(\text{long, } tc\_matrix, \text{void}(*f)(tc\_matrix)) = 0$ 

Definition at line 737 of file TC\_Main\_api.c.

7.19.2.16 void(\* \_tc\_deselect)()=0

Definition at line 88 of file TC\_Main\_api.c.

7.19.2.17 void(\* \_tc\_displayNumber)(long item, double number)=0

Definition at line 1187 of file TC\_Main\_api.c.

7.19.2.18 void(\* \_tc\_displayText)(long item, const char \*text)=0

Definition at line 1176 of file TC\_Main\_api.c.

7.19.2.19 void(\* \_tc\_errorReport)(const char \*text)=0

Definition at line 205 of file TC\_Main\_api.c.

7.19.2.20 long(\* \_tc\_find)(const char \*fullname)=0

Definition at line 53 of file TC\_Main\_api.c.

7.19.2.21 tc\_items(\* \_tc\_findItems)(tc\_strings names)=0

Definition at line 65 of file TC\_Main\_api.c.

7.19.2.22 tc\_items(\* \_tc\_getChildren)(long)=0

Definition at line 445 of file TC\_Main\_api.c.

7.19.2.23 const char\*(\* \_tc\_getColor)(long item)=0

Definition at line 794 of file TC\_Main\_api.c.

7.19.2.24 const char\*(\* \_tc\_getFamily)(long item)=0

Definition at line 159 of file TC\_Main\_api.c.

7.19.2.25 const char\*(\* \_tc\_getFilename)()=0

Definition at line 631 of file TC\_Main\_api.c.

7.19.2.26 double(\* \_tc\_getHeight)(long)=0

Definition at line 771 of file TC\_Main\_api.c.

7.19.2.27 const char\*(\*  $_{tc\_getName}$ )(long item)=0

Definition at line 99 of file TC\_Main\_api.c.

7.19.2.28 tc\_strings(\* \_tc\_getNames)(tc\_items items)=0

Definition at line 134 of file TC\_Main\_api.c.

7.19.2.29 double(\* \_tc\_getNumber)(const char \*title)=0

Definition at line 655 of file TC\_Main\_api.c.

7.19.2.30 void(\* \_tc\_getNumbers)(tc\_strings labels, double \*result)=0

Definition at line 667 of file TC\_Main\_api.c.

7.19.2.31 tc\_matrix(\* \_tc\_getNumericalData)(long item, const char \*data)=0

Definition at line 469 of file TC\_Main\_api.c.

7.19.2.32 tc\_strings(\* \_tc\_getNumericalDataNames)(long)=0

Definition at line 584 of file TC\_Main\_api.c.

7.19.2.33 double(\*  $\_tc\_getNumericalValue$ )(const char \*)=0

Definition at line 481 of file TC\_Main\_api.c.

7.19.2.34 long(\* \_tc\_getParent)(long)=0

Definition at line 457 of file TC\_Main\_api.c.

7.19.2.35 tc\_matrix(\* \_tc\_getPos)(tc\_items items)=0

Definition at line 285 of file TC\_Main\_api.c.

7.19.2.36 const char\*(\* \_tc\_getStringDialog)(const char \*title)=0

Definition at line 619 of file TC\_Main\_api.c.

7.19.2.37 int(\* \_tc\_getStringFromList)(const char \*title, tc\_strings list, const char \*selectedString)=0

Definition at line 643 of file TC\_Main\_api.c.

7.19.2.38 tc\_table(\* \_tc\_getTextData)(long item, const char \*data)=0

Definition at line 539 of file TC\_Main\_api.c.

7.19.2.39 tc\_strings(\* \_tc\_getTextDataNames)(long)=0

Definition at line 596 of file TC\_Main\_api.c.

7.19.2.40 const char\*(\* \_tc\_getTextValue)(const char \*name)=0

Definition at line 494 of file TC\_Main\_api.c.

7.19.2.41 const char\*(\* \_tc\_getUniqueName)(long item)=0

Definition at line 111 of file TC\_Main\_api.c.

7.19.2.42 tc\_strings(\* \_tc\_getUniqueNames)(tc\_items items)=0

Definition at line 146 of file TC\_Main\_api.c.

7.19.2.43 double(\* \_tc\_getWidth)(long)=0

Definition at line 759 of file TC\_Main\_api.c.

7.19.2.44 double(\*  $_{tc\_getX}$ )(long item)=0

Definition at line 273 of file TC\_Main\_api.c.

7.19.2.45 double(\*  $\_tc\_getY$ )(long item)=0

Definition at line 260 of file TC\_Main\_api.c.

7.19.2.46 void(\* \_tc\_highlight)(long item, const char \*)=0

Definition at line 1209 of file TC\_Main\_api.c.

7.19.2.47 const char\*(\* \_tc\_homeDir)()=0

Definition at line 378 of file TC\_Main\_api.c.

7.19.2.48 void(\* \_tc\_insertAnnotations)(const char \*, double, double)=0

Definition at line 905 of file TC\_Main\_api.c.

7.19.2.49  $int(*\_tc\_isA)(long item, const char *family)=0$ 

Definition at line 171 of file TC\_Main\_api.c.

7.19.2.50 int(\* \_tc\_isLinux)()=0

Definition at line 354 of file TC\_Main\_api.c.

7.19.2.51 int(\* \_tc\_isMac)()=0

Definition at line 342 of file TC\_Main\_api.c.

7.19.2.52 int(\* \_tc\_isWindows)()=0

Definition at line 330 of file TC\_Main\_api.c.

7.19.2.53 tc\_items(\* \_tc\_itemsOfFamily)(const char \*family)=0

Definition at line 29 of file TC\_Main\_api.c.

7.19.2.54  $tc\_items(*\_tc\_itemsOfFamilyFrom)(const char *family, tc\_items itemsToSelectFrom)=0$ 

Definition at line 41 of file TC\_Main\_api.c.

7.19.2.55 void(\* \_tc\_messageDialog)(const char \*)=0

Definition at line 691 of file TC\_Main\_api.c.

7.19.2.56 void(\* \_tc\_moveSelected)(double dx, double dy)=0

Definition at line 319 of file TC\_Main\_api.c.

7.19.2.57 void(\* \_tc\_openFile)(const char \*)=0

Definition at line 703 of file TC\_Main\_api.c.

7.19.2.58 void(\* \_tc\_openNewWindow)(const char \*title)=0

Definition at line 434 of file TC\_Main\_api.c.

7.19.2.59 void(\* \_tc\_openUrl)(const char \*file)=0

Definition at line 194 of file TC\_Main\_api.c.

7.19.2.60 void(\* \_tc\_print)(const char \*text)=0

Definition at line 183 of file TC\_Main\_api.c.

7.19.2.61 void(\* \_tc\_printFile)(const char \*filename)=0

Definition at line 227 of file TC\_Main\_api.c.

7.19.2.62 void(\* \_tc\_printMatrix)(tc\_matrix data)=0

Definition at line 216 of file TC\_Main\_api.c.

7.19.2.63 void(\* \_tc\_remove)(long item)=0

Definition at line 249 of file TC\_Main\_api.c.

7.19.2.64 void(\* \_tc\_rename)(long item, const char \*name)=0

Definition at line 123 of file TC\_Main\_api.c.

7.19.2.65 void(\* tc saveToFile)(const char \*)=0

Definition at line 715 of file TC\_Main\_api.c.

7.19.2.66 int(\* \_tc\_screenHeight)(void)=0

Definition at line 861 of file TC\_Main\_api.c.

7.19.2.67 void(\* \_tc\_screenshot)(const char \*filename, int width, int height)=0

Definition at line 839 of file TC\_Main\_api.c.

7.19.2.68 int(\* \_tc\_screenWidth)(void)=0

Definition at line 850 of file TC\_Main\_api.c.

7.19.2.69 int(\* \_tc\_screenX)(void)=0

Definition at line 872 of file TC\_Main\_api.c.

7.19.2.70 int(\* \_tc\_screenY)(void)=0

Definition at line 883 of file TC\_Main\_api.c.

7.19.2.71 void(\* \_tc\_select)(long item)=0

Definition at line 77 of file TC\_Main\_api.c.

7.19.2.72 tc\_items(\* \_tc\_selectedItems)()=0

Definition at line 17 of file TC\_Main\_api.c.

7.19.2.73 void(\* \_tc\_setAngle)(long, double, int)=0

Definition at line 783 of file TC\_Main\_api.c.

7.19.2.74 void(\* \_tc\_setColor)(long item, const char \*name, int permanent)=0

Definition at line 806 of file TC\_Main\_api.c.

7.19.2.75 void(\* \_tc\_setDisplayLabelColor)(const char \*, const char \*)=0

Definition at line 1198 of file TC\_Main\_api.c.

7.19.2.76 void(\* tc setNumericalData)(long, const char \*, tc matrix)=0

Definition at line 506 of file TC\_Main\_api.c.

7.19.2.77 void(\* \_tc\_setNumericalValue)(const char \*, double)=0

Definition at line 528 of file TC\_Main\_api.c.

7.19.2.78 void(\* \_tc\_setNumericalValues)(tc\_matrix)=0

Definition at line 517 of file TC\_Main\_api.c.

7.19.2.79 void(\* \_tc\_setPos)(long item, double x, double y)=0

Definition at line 297 of file TC\_Main\_api.c.

7.19.2.80 void(\* \_tc\_setPosMulti)(tc\_items items, tc\_matrix positions)=0

Definition at line 308 of file TC\_Main\_api.c.

7.19.2.81 void(\* \_tc\_setSize)(long, double, double, int)=0

Definition at line 748 of file TC\_Main\_api.c.

7.19.2.82 void(\* \_tc\_setTextData)(long, const char \*, tc\_table)=0

Definition at line 551 of file TC\_Main\_api.c.

7.19.2.83 void(\* \_tc\_setTextValue)(const char \*, const char \*)=0

Definition at line 573 of file TC Main api.c.

7.19.2.84 void(\* \_tc\_setTextValues)(tc\_table)=0

Definition at line 562 of file TC\_Main\_api.c.

7.19.2.85 void(\* \_tc\_showProgress)(long thread, const char \*title, int progress)=0

Definition at line 1124 of file TC\_Main\_api.c.

7.19.2.86 void(\* \_tc\_zoom)(double factor)=0

Definition at line 608 of file TC\_Main\_api.c.

# 7.20 /home/deepak/TinkerCell/trunk/API/TC\_Main\_api.h File Reference

```
#include "TC_structs.h"
```

#### **Functions**

• TCAPIEXPORT tc\_items tc\_allItems ()

get all visible items

• TCAPIEXPORT tc\_items tc\_selectedItems ()

get all selected items

• TCAPIEXPORT tc\_items tc\_itemsOfFamily (const char \*family)

get all items of the given family items

• TCAPIEXPORT tc\_items tc\_itemsOfFamilyFrom (const char \*family, tc\_items itemsToSelectFrom)

get subset of items that belong to the given family

```
• TCAPIEXPORT long tc_find (const char *fullname)

get the first item with the given name (full name)
```

- TCAPIEXPORT tc\_items tc\_findItems (tc\_strings names) get all items with the given names (full names)
- TCAPIEXPORT void tc\_select (long item) select an item
- TCAPIEXPORT void tc\_deselect ()
   deselect all items
- TCAPIEXPORT const char \* tc\_getName (long item)
   get the name of an item
- TCAPIEXPORT const char \* tc\_getUniqueName (long item) get the full name of an item
- TCAPIEXPORT void tc\_rename (long item, const char \*name) set the name of an item (not full name)
- TCAPIEXPORT tc\_strings tc\_getNames (tc\_items items) get the names of several items
- TCAPIEXPORT tc\_strings tc\_getUniqueNames (tc\_items items)
   get the full names of several items
- TCAPIEXPORT const char \* tc\_getFamily (long item) get the family name of an item
- TCAPIEXPORT int tc\_isA (long item, const char \*family) check is an item belongs in a family (or in a sub-family)
- TCAPIEXPORT void tc\_print (const char \*text) show text in the output window.
- TCAPIEXPORT void tc\_openUrl (const char \*s) show text in the output window.
- TCAPIEXPORT void tc\_errorReport (const char \*text) show error text in the output window.
- TCAPIEXPORT void tc\_printMatrix (tc\_matrix data) show table in the output window.
- TCAPIEXPORT void tc\_printFile (const char \*filename)

show file contents in the output window.

• TCAPIEXPORT void tc\_clear ()

cleat the contents in the output window.

• TCAPIEXPORT void tc\_remove (long item)

delete an item

• TCAPIEXPORT double tc\_getY (long item)

get the x location of an item

• TCAPIEXPORT double tc\_getX (long item)

get the y location of an item

• TCAPIEXPORT tc\_matrix tc\_getPos (tc\_items items)

get the y location of a list item. Output is a N x 2 matrix

• TCAPIEXPORT void tc\_setPos (long item, double x, double y)

set the x and y location of an item

• TCAPIEXPORT void tc\_setPosMulti (tc\_items items, tc\_matrix positions)

set the x and y location of a list of N items. Input a matrix of positions, with N rows and 2 columns (x,y)

• TCAPIEXPORT void tc\_moveSelected (double dx, double dy)

move all the selected items by a given amount

• TCAPIEXPORT int tc\_isWindows ()

is this running in MS windows?

• TCAPIEXPORT int tc\_isMac ()

is this running in a Mac?

• TCAPIEXPORT int tc\_isLinux ()

is this running in Linux?

• TCAPIEXPORT const char \* tc\_appDir ()

 ${\it Tinker Cell\ application\ folder}.$ 

• TCAPIEXPORT const char \* tc\_homeDir ()

TinkerCell home folder.

• TCAPIEXPORT void tc\_createInputWindowForScript (tc\_matrix input, const char \*filename, const char \*functionname)

create an input window that can call a dynamic library

TCAPIEXPORT void tc\_createInputWindow (tc\_matrix input, const char \*title, void(\*f)(tc\_matrix))

create an input window that can call a dynamic library

TCAPIEXPORT void tc\_addInputWindowOptions (const char \*title, int i, int j, tc\_strings options)

add options to an existing input window at the i,j-th cell. Options will appear in a list

TCAPIEXPORT void tc\_addInputWindowCheckbox (const char \*title, int i, int j)

add a yes or no type of option to an existing input window at the i,j-th cell

- TCAPIEXPORT void tc\_openNewWindow (const char \*title) open a new graphics window
- TCAPIEXPORT tc\_items tc\_getChildren (long o) get child items of the given item
- TCAPIEXPORT long tc\_getParent (long o) get parent item of the given item
- TCAPIEXPORT tc\_matrix tc\_getNumericalData (long item, const char \*data) get the entire data matrix for the given numerical data table of the given item
- TCAPIEXPORT void tc\_setNumericalData (long o, const char \*title, tc\_matrix data)

set a new data matrix for an item or replace an existing one

- TCAPIEXPORT void tc\_setNumericalValues (tc\_matrix data)
   set multiple values in a model. The input matrix row names correspond to data names.
- TCAPIEXPORT void tc\_setNumericalValue (const char \*name, double value) set a single value in a model
- TCAPIEXPORT tc\_table tc\_getTextData (long item, const char \*data) get the entire data table for the given strings data table of the given item
- TCAPIEXPORT void tc\_setTextData (long o, const char \*title, tc\_table data)

  set or replace the entire data matrix for the given strings data table of the given item
- TCAPIEXPORT void tc\_setTextValues (tc\_table data)
   set multiple values in a model. The input matrix row names correspond to data names.
- TCAPIEXPORT double tc\_getNumericalValue (const char \*name) get a numerical value from its full name

- TCAPIEXPORT const char \* tc\_getTextValue (const char \*name) get a text value from its full name
- TCAPIEXPORT void tc\_setTextValue (const char \*name, const char \*value) set a single text value in a model
- TCAPIEXPORT tc\_strings tc\_getNumericalDataNames (long o) get all the numeric data table names for the given item
- TCAPIEXPORT tc\_strings tc\_getTextDataNames (long o) get all the text data table names for the given item
- TCAPIEXPORT void tc\_zoom (double factor)

  zoom by the given factor (0 1)
- TCAPIEXPORT const char \* tc\_getStringDialog (const char \*title)

  get a text from the user (dialog)
- TCAPIEXPORT const char \* tc\_getFilename ()
   get a file from the user (dialog)
- TCAPIEXPORT int tc\_getStringFromList (const char \*title, tc\_strings list, const char \*selectedString)

get a text from the user (dialog) from a list of selections

- TCAPIEXPORT double tc\_getNumber (const char \*title) get a number from the user (dialog)
- TCAPIEXPORT void tc\_getNumbers (tc\_strings labels, double \*result) get a list of numbers from the user (dialog) into the argument array
- TCAPIEXPORT int tc\_askQuestion (const char \*message)
   display a dialog with a text and a yes and no button
- TCAPIEXPORT void tc\_messageDialog (const char \*message) display a dialog with a text message and a close button
- TCAPIEXPORT void tc\_openFile (const char \*message)
   open file
- TCAPIEXPORT void tc\_saveToFile (const char \*message) save to file
- TCAPIEXPORT long tc\_thisThread ()
  get pointer to the current thread. used for passing this thread as some argument

• TCAPIEXPORT void tc\_createSliders (tc\_matrix input, void(\*f)(tc\_matrix))

create a window with several sliders. when the sliders change, the given function will
be called with the values in the sliders

- TCAPIEXPORT const char \* tc\_getColor (long item) get the color of the item
- TCAPIEXPORT void tc\_setColor (long item, const char \*name, int permanent)

set the color of the item and indicate whether or not the color is permanenet

- TCAPIEXPORT void tc\_changeNodeImage (long item, const char \*filename) change the graphics file for drawing one of the nodes
- TCAPIEXPORT void tc\_changeArrowHead (long connection, const char \*filename)

change the graphics file for drawing the arrowheads for the given connection

- TCAPIEXPORT void tc\_setSize (long item, double width, double height)

  Change the size of an item.
- TCAPIEXPORT double tc\_getWidth (long item) get the width of an item
- TCAPIEXPORT double tc\_getHeight (long item) get the width of an item
- TCAPIEXPORT void tc\_rotate (long item, double t) get the width of an item
- TCAPIEXPORT void tc\_screenshot (const char \*filename, int width, int height)

  save screenshot in a file
- TCAPIEXPORT int tc\_screenWidth ()
   get width of current canvas
- TCAPIEXPORT int tc\_screenHeight () get height of current canvas
- TCAPIEXPORT int tc\_screenX () get x position of current canvas
- TCAPIEXPORT int tc\_screenY () get y position of current canvas

- TCAPIEXPORT const char \* tc\_annotations ()
   get text displayed on the canvas
- TCAPIEXPORT void tc\_insertAnnotations (const char \*, double, double) show text displayed on the canvas at the given position
- TCAPIEXPORT void tc\_Main\_api\_initialize (tc\_items(\*tc\_allItems0)(), tc\_items(\*tc\_selectedItems0)(), tc\_items(\*tc\_itemsOfFamily0)(const char \*), tc\_items(\*tc\_itemsOfFamily1)(const char \*, tc\_items), long(\*tc\_find0)(const char \*), tc\_items(\*tc\_findItems0)(tc\_strings), void(\*tc\_select0)(long), void(\*tc\_deselect0)(), const char \*(\*tc\_getName0)(long), const char \*(\*tc\_getUniqueName0)(long), void(\*tc setName0)(long item, const char \*name), tc strings(\*tc getNames0)(tc items), tc strings(\*tc getUniqueNames0)(tc items), const char \*(\*tc getFamily0)(long), int(\*tc\_isA0)(long, const char \*), void(\*tc\_clearText)(), void(\*tc\_outputText0)(const char \*), void(\*tc errorReport0)(const char \*), void(\*tc outputTable0)(tc matrix), void(\*tc printFile0)(const char \*), void(\*tc removeItem0)(long), double(\*tc getY0)(long), double(\*tc\_getX0)(long), tc\_matrix(\*tc\_getPos0)(tc\_items), void(\*tc\_setPos0)(long, double, double), void(\*tc\_setPos1)(tc\_items, tc\_matrix), void(\*tc\_moveSelected0)(double, double), int(\*tc\_isWindows0)(), int(\*tc\_isMac0)(), int(\*tc\_isLinux0)(), const char \*(\*tc appDir0)(), const char \*(\*tc homeDir0)(), void(\*tc createInputWindow0)(tc\_matrix, const char \*, const char \*), void(\*tc\_createInputWindow1)(long, tc\_matrix, const char \*, void(\*f)(tc\_matrix)), void(\*createSliders)(long, tc\_matrix, void(\*f)(tc\_matrix)), void(\*tc\_addInputWindowOptions0)(const char \*, int i, int i, tc strings), void(\*tc addInputWindowCheckbox0)(const char \*, int i, int i), void(\*tc\_openNewWindow0)(const char \*title), tc\_items(\*tc\_getChildren0)(long), long(\*tc\_getParent0)(long), tc\_matrix(\*tc\_getNumericalData0)(long, const char \*), void(\*tc\_setNumericalData0)(long, const char \*, tc\_matrix), tc\_table(\*tc\_getTextData0)(long, const char \*), void(\*tc\_setTextData0)(long, const char \*, tc\_table), tc\_strings(\*tc\_getNumericalDataNames0)(long), tc\_strings(\*tc\_getTextDataNames0)(long), void(\*tc\_zoom0)(double factor), const char \*(\*tc\_getStringDialog0)(const char \*), int(\*getSelectedString)(const char \*, tc\_strings, const char \*), double(\*getNumber)(const char \*), void(\*getNumbers)(tc\_strings, double \*), const char \*(\*getFilename)(), int(\*askQuestion)(const char \*), void(\*messageDialog)(const char \*), void(\*openFile)(const char \*), void(\*saveToFile)(const char \*), void(\*setSize0)(long, double, double, int), double(\*getWidth0)(long), double(\*getHeight0)(long), void(\*setAngle0)(long, double, int), const char \*(\*getColor)(long), void(\*setColor0)(long, const char \*, int), void(\*changeGraphics0)(long, const char \*), void(\*changeArrowHead0)(long, const char \*), void(\*screenshot)(const char \*, int, int), int(\*screenHeight)(), int(\*screenWidth)(), int(\*screenX)(), int(\*screenY)(), const char \*(\*annotations)(), void(\*insertAnnotations)(const char \*, double, double), void(\*setNumericalValues)(tc matrix), void(\*setNumericalValue)(const char \*, double), void(\*setTextValues)(tc\_table), void(\*setTextValue)(const char \*, const char \*), double(\*getNumericalValue)(const char \*), const char \*(\*getTextValue)(const char \*), void(\*openUrl)())
- TCAPIEXPORT void tc\_showProgress (const char \*title, int progress)

  show progress of current operation
- TCAPIEXPORT void tc\_callback (void(\*f)(void))

initialize core C api

this function will be called whenever the model is changed

TCAPIEXPORT void tc\_callWhenExiting (void(\*f)(void))
 this function will be called whenever Tinkercell exits. Use it to free memory.

• TCAPIEXPORT void tc\_CThread\_api\_initialize (long cthread, void(\*callback)(long, void(\*f)(void)), void(\*callWhenExiting)(long, void(\*f)(void)), void(\*showProgress)(long, const char \*, int))

initialize main

- TCAPIEXPORT void tc\_displayText (long item, const char \*text)

  displays the given text on the given item (the text is temporary)
- TCAPIEXPORT void tc\_displayNumber (long item, double number)

  displays the given number on the given item (the text is temporary)
- TCAPIEXPORT void tc\_setDisplayLabelColor (const char \*a, const char \*b)
   set the color for the number or text when using tc\_displayNumber and tc\_displayText
- TCAPIEXPORT void tc\_highlight (long item, const char \*color)
   highlights an item (the highlight is temporary) with the given color (hex)
- TCAPIEXPORT void tc\_burn (long item, double intensity)
   burn
- TCAPIEXPORT void tc\_LabelingTool\_api (void(\*displayText)(long item, const char \*), void(\*displayNumber)(long item, double), void(\*setDisplayLabelColor)(const char \*color1, const char \*color2), void(\*highlight)(long, const char \*color), void(\*burn)(long, double))

initialize highlighting plug-in

#### 7.20.1 Function Documentation

#### 7.20.1.1 TCAPIEXPORT void tc\_callback ( void(\*)(void) f )

this function will be called whenever the model is changed

#### **Parameters**

void*	callback function pointer

Definition at line 1141 of file TC\_Main\_api.c.

# 7.20.1.2 TCAPIEXPORT void tc\_callWhenExiting (void(\*)(void) f)

this function will be called whenever Tinkercell exits. Use it to free memory.

#### **Parameters**

void*	callback function pointer

Definition at line 1153 of file TC\_Main\_api.c.

7.20.1.3 TCAPIEXPORT void tc\_CThread\_api\_initialize ( long cthread, void(\*)(long, void(\*f)(void)) callback, void(\*)(long, void(\*f)(void)) callWhenExiting, void(\*)(long, const char \*, int) showProgress )

initialize main

Definition at line 1163 of file TC\_Main\_api.c.

# 7.20.1.4 TCAPIEXPORT tc\_matrix tc\_getNumericalData ( long item, const char \* data )

get the entire data matrix for the given numerical data table of the given item

#### **Parameters**

	int	address of item. use 0 for the model item
stri	ing	name of numerical data table

#### Returns

tc\_matrix the numerical data table for the given item

Definition at line 474 of file TC\_Main\_api.c.

#### 7.20.1.5 TCAPIEXPORT tc\_strings tc\_getNumericalDataNames ( long o )

get all the numeric data table names for the given item

#### **Parameters**

int	address of item. use 0 for the model item

### Returns

tc\_string list of names of all numerical tables inside this item

Definition at line 589 of file TC\_Main\_api.c.

#### 7.20.1.6 TCAPIEXPORT double tc\_getNumericalValue ( const char \* name )

get a numerical value from its full name

#### **Parameters**

string	full name

Definition at line 487 of file TC\_Main\_api.c.

# 7.20.1.7 TCAPIEXPORT tc\_table tc\_getTextData ( long item, const char \* data )

get the entire data table for the given strings data table of the given item

#### **Parameters**

int	address of item. use 0 for the model item
string	name of text data table

#### Returns

tc\_table the text data table for the given item

Definition at line 544 of file TC\_Main\_api.c.

#### 7.20.1.8 TCAPIEXPORT tc\_strings tc\_getTextDataNames ( long o )

get all the text data table names for the given item

#### **Parameters**

int	address of item. use 0 for the model item

# Returns

tc\_string list of names of all text tables inside this item

Definition at line 601 of file TC\_Main\_api.c.

# 7.20.1.9 TCAPIEXPORT const char\* tc\_getTextValue ( const char\* name )

get a text value from its full name

### **Parameters**

|--|

Definition at line 499 of file TC\_Main\_api.c.

7.20.1.10 TCAPIEXPORT void tc\_LabelingTool\_api ( void(\*)(long item, const char \*) displayText, void(\*)(long item, double) displayNumber, void(\*)(const char \*color1, const char \*color2) setDisplayLabelColor, void(\*)(long, const char \*color) highlight, void(\*)(long, double) burn )

initialize highlighting plug-in

7.20.1.11 TCAPIEXPORT void tc\_Main\_api\_initialize ( tc\_items(\*)() tc\_allItems0, tc items(\*)() tc\_selectedItems0, tc items(\*)(const char \*) tc\_itemsOfFamily0, tc items(\*)(const char \*, tc items) tc\_itemsOfFamily1, long(\*)(const char \*) tc\_find0, tc\_items(\*)(tc\_strings) tc\_findItems0, void(\*)(long) tc\_select0, void(\*)() tc\_deselect0, const char \*(\*)(long) tc\_getName0, const char \*(\*)(long) tc\_getUniqueName0, void(\*)(long item, const char \*name) tc\_setName0, tc\_strings(\*)(tc\_items) tc\_getNames0, tc\_strings(\*)(tc\_items) tc\_getUniqueNames0, const char \*(\*)(long) tc\_getFamily0, int(\*)(long, const char \*) tc\_isA0, void(\*)() tc\_clearText, void(\*)(const char \*) tc\_outputText0, void(\*)(const char \*) tc\_errorReport0, void(\*)(tc matrix) tc\_outputTable0, void(\*)(const char \*) tc\_printFile0, void(\*)(long) tc\_removeItem0, double(\*)(long) tc\_getY0, double(\*)(long) tc\_getX0, tc\_matrix(\*)(tc\_items) tc\_getPos0, void(\*)(long, double, double) tc\_setPos0, void(\*)(tc\_items, tc\_matrix) tc\_setPos1, void(\*)(double, double) tc\_moveSelected0, int(\*)() tc\_isWindows0, int(\*)() tc\_isMac0, int(\*)() tc\_isLinux0, const char \*(\*)() tc\_appDir0, const char \*(\*)() tc\_homeDir0, void(\*)(tc\_matrix, const char \*, const char \*) tc\_createInputWindow0, void(\*)(long, tc\_matrix, const char \*, void(\*f)(tc\_matrix)) tc\_createInputWindow1, void(\*)(long, tc\_matrix, void(\*f)(tc\_matrix)) createSliders, void(\*)(const char \*, int i, int j, tc\_strings) tc\_addInputWindowOptions0, void(\*)(const char \*, int i, int j) tc\_addInputWindowCheckbox0, void(\*)(const char \*title) tc\_openNewWindow0, tc\_items(\*)(long) tc\_getChildren0, long(\*)(long) tc\_getParent0, tc\_matrix(\*)(long, const char \*) tc\_getNumericalData0, void(\*)(long, const char \*, tc matrix) tc\_setNumericalData0, tc\_table(\*)(long, const char \*) tc\_getTextData0, void(\*)(long, const char \*, tc\_table) tc\_setTextData0, tc\_strings(\*)(long) tc\_getNumericalDataNames0, tc strings(\*)(long) tc\_getTextDataNames0, void(\*)(double factor) tc\_zoom0, const char \*(\*)(const char \*) tc\_getStringDialog0, int(\*)(const char \*, tc\_strings, const char \*) getSelectedString, double(\*)(const char \*) getNumber, void(\*)(tc\_strings, double \*) getNumbers, const char \*(\*)() getFilename, int(\*)(const char \*) askQuestion, void(\*)(const char \*) messageDialog, void(\*)(const char \*) openFile, void(\*)(const char \*) saveToFile, void(\*)(long, double, double, int) setSize0, double(\*)(long) getWidth0, double(\*)(long) getHeight0, void(\*)(long, double, int) setAngle0, const char \*(\*)(long) getColor, void(\*)(long, const char \*, int) setColor0, void(\*)(long, const char \*) changeGraphics0, void(\*)(long, const char \*) changeArrowHead0, void(\*)(const char \*, int, int) screenshot, int(\*)() screenHeight, int(\*)() screenWidth, int(\*)() screenX, int(\*)() screenY, const char \*(\*)() annotations, void(\*)(const char \*, double, double) insertAnnotations, void(\*)(tc matrix) setNumericalValues, void(\*)(const char \*, double) setNumericalValue, void(\*)(tc\_table) setTextValues, void(\*)(const char \*, const char \*) setTextValue, double(\*)(const char \*) getNumericalValue, const char \*(\*)(const char \*) getTextValue, void(\*)() openUrl )

initialize core C api

# 7.20.1.12 TCAPIEXPORT void tc\_remove ( long item )

delete an item

#### **Parameters**

int	address of item

Definition at line 254 of file TC\_Main\_api.c.

# 7.20.1.13 TCAPIEXPORT void tc\_setNumericalData ( long o, const char \* title, tc\_matrix data )

set a new data matrix for an item or replace an existing one

#### **Parameters**

int	address of item. use 0 for the model item
string	name of numerical data table
tc_matrix	the new numerical data table for the given item

Definition at line 511 of file TC\_Main\_api.c.

# 7.20.1.14 TCAPIEXPORT void tc\_setNumericalValue ( const char \* name, double value )

set a single value in a model

#### **Parameters**

string	name of variable
double	new value of variable

Definition at line 533 of file TC\_Main\_api.c.

# 7.20.1.15 TCAPIEXPORT void tc\_setNumericalValues ( tc\_matrix data )

set multiple values in a model. The input matrix row names correspond to data names.

# **Parameters**

tc_matrix	matrix with rownames with the names of the variables and columns with	
	values	

Definition at line 522 of file TC\_Main\_api.c.

# 7.20.1.16 TCAPIEXPORT void tc\_setTextData ( long o, const char \* title, tc\_table data )

set or replace the entire data matrix for the given strings data table of the given item

#### **Parameters**

int	address of item. use 0 for the model item
string	name of text data table

#### Returns

tc\_table the new text data table for the given item

Definition at line 556 of file TC\_Main\_api.c.

# 7.20.1.17 TCAPIEXPORT void tc\_setTextValue ( const char \* name, const char \* value )

set a single text value in a model

#### **Parameters**

string	name of variable
string	new value of variable

Definition at line 578 of file TC\_Main\_api.c.

# 7.20.1.18 TCAPIEXPORT void tc\_setTextValues ( tc\_table data )

set multiple values in a model. The input matrix row names correspond to data names.

# **Parameters**

tc_t	table	table with	rownames	with	the	names	of	the	variables	and	columns	with
		values										

Definition at line 567 of file TC\_Main\_api.c.

# 7.20.1.19 TCAPIEXPORT long tc\_thisThread ( )

get pointer to the current thread. used for passing this thread as some argument

#### Returns

int pointer

Definition at line 731 of file TC\_Main\_api.c.

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

# 7.21 /home/deepak/TinkerCell/trunk/API/TC\_ModelFileGenerator\_api.c File Reference

```
#include "TC_ModelFileGenerator_api.h"
```

# **Functions**

- TCAPIEXPORT int tc\_writeModel (const char \*file, tc\_items items)

  write the ODE, stoichiometry, and rates functions to a file
- TCAPIEXPORT void tc\_ModelFileGenerator\_api (int(\*modelgen)(const char \*, tc\_items))

initialize model generator functions

# **Variables**

• int(\* \_tc\_writeModel )(const char \*file, tc\_items items)=0

#### 7.21.1 Function Documentation

# 7.21.1.1 TCAPIEXPORT void tc\_ModelFileGenerator\_api ( int(\*)(const char \*, tc\_items) modelgen )

initialize model generator functions

initialize model generator plug-in

Definition at line 19 of file TC\_ModelFileGenerator\_api.c.

# 7.21.2 Variable Documentation

### 7.21.2.1 int(\* \_tc\_writeModel)(const char \*file, tc\_items items)=0

Definition at line 3 of file TC\_ModelFileGenerator\_api.c.

# 7.22 /home/deepak/TinkerCell/trunk/API/TC\_ModelFileGenerator\_api.h File Reference

#include "TC\_structs.h"

#### 7.23 /home/deepak/TinkerCell/trunk/API/TC\_ModuleTool\_api.c File Referend61

#### **Functions**

BEGIN\_C\_DECLS TCAPIEXPORT int tc\_writeModel (const char \*file, tc\_items items)

write the ODE, stoichiometry, and rates functions to a file

TCAPIEXPORT void tc\_ModelFileGenerator\_api (int(\*modelgen)(const char \*, tc\_items))

initialize model generator plug-in

# 7.22.1 Function Documentation

7.22.1.1 TCAPIEXPORT void tc\_ModelFileGenerator\_api ( int(\*)(const char \*, tc\_items) modelgen )

initialize model generator plug-in

Definition at line 19 of file TC\_ModelFileGenerator\_api.c.

# 7.23 /home/deepak/TinkerCell/trunk/API/TC\_ModuleTool\_api.c File Reference

```
#include "TC_ModuleTool_api.h"
```

#### **Functions**

- TCAPIEXPORT void tc\_substituteModel (long item, const char \*filename)

  load a sub-model to represent the processes inside an existing connection. use an
  empty string to substitude the empty model.
- TCAPIEXPORT void tc\_substituteEmptyModel (long item)

  load an empty sub-model to represent the processes inside an existing connection, i.e

  removed that process from the model
- TCAPIEXPORT void tc\_substituteOriginalModel (long item)
   load the original sub-model for the processes inside an existing connection
- TCAPIEXPORT tc\_strings tc\_listOfPossibleModels (long item)
  get the list of possible model files that can be used as a sub-model to represent the
  processes inside an existing connection
- TCAPIEXPORT void tc\_ModuleTool\_api (void(\*substituteModel)(long, const char \*), tc\_strings(\*listOfModels)(long))

initializing function

#### **Variables**

- void(\* \_tc\_substituteModel )(long, const char \*)=0
- tc\_strings(\* \_tc\_listOfPossibleModels )(long)=0

#### 7.23.1 Function Documentation

# 7.23.1.1 TCAPIEXPORT tc\_strings tc\_listOfPossibleModels ( long item )

get the list of possible model files that can be used as a sub-model to represent the processes inside an existing connection

#### **Parameters**

long	connection that will be the parent of the new model
0	1

#### Returns

tc\_list list of file names

Definition at line 27 of file TC\_ModuleTool\_api.c.

# 7.23.1.2 TCAPIEXPORT void tc\_ModuleTool\_api ( void(\*)(long, const char \*) substituteModel, tc\_strings(\*)(long) listOfModels )

initializing function

Definition at line 38 of file TC\_ModuleTool\_api.c.

#### 7.23.1.3 TCAPIEXPORT void tc\_substituteEmptyModel ( long item )

load an empty sub-model to represent the processes inside an existing connection, i.e removed that process from the model

# **Parameters**

long   connection that will be the parent of the new model	
------------------------------------------------------------	--

Definition at line 12 of file TC\_ModuleTool\_api.c.

# 7.23.1.4 TCAPIEXPORT void tc\_substituteModel ( long item, const char \* filename )

load a sub-model to represent the processes inside an existing connection. use an empty string to substitude the empty model.

#### **Parameters**

long	connection that will be the parent of the new model
const	char* file name of new model

#### 7.24 /home/deepak/TinkerCell/trunk/API/TC\_ModuleTool\_api.h File Referen**46**3

Definition at line 6 of file TC\_ModuleTool\_api.c.

# 7.23.1.5 TCAPIEXPORT void tc\_substituteOriginalModel ( long item )

load the original sub-model for the processes inside an existing connection

#### **Parameters**

long | connection that will be the parent of the new model

Definition at line 18 of file TC\_ModuleTool\_api.c.

#### 7.23.2 Variable Documentation

# 7.23.2.1 tc\_strings(\* \_tc\_listOfPossibleModels)(long)=0

Definition at line 24 of file TC\_ModuleTool\_api.c.

# 7.23.2.2 void(\* \_tc\_substituteModel)(long, const char \*)=0

Definition at line 3 of file TC\_ModuleTool\_api.c.

# 7.24 /home/deepak/TinkerCell/trunk/API/TC\_ModuleTool\_api.h File Reference

#include "TC\_structs.h"

#### **Functions**

• BEGIN\_C\_DECLS TCAPIEXPORT void tc\_substituteModel (long item, const char \*filename)

load a sub-model to represent the processes inside an existing connection. use an empty string to substitude the empty model.

• TCAPIEXPORT void tc\_substituteEmptyModel (long item)

load an empty sub-model to represent the processes inside an existing connection, i.e removed that process from the model

- TCAPIEXPORT void tc\_substituteOriginalModel (long item)
  - load the original sub-model for the processes inside an existing connection
- TCAPIEXPORT tc\_strings tc\_listOfPossibleModels (long item)

get the list of possible model files that can be used as a sub-model to represent the processes inside an existing connection

• TCAPIEXPORT void tc\_ModuleTool\_api (void(\*substituteModel)(long, const char \*), tc\_strings(\*listOfModels)(long))

initializing function

#### 7.24.1 Function Documentation

# 7.24.1.1 TCAPIEXPORT tc\_strings tc\_listOfPossibleModels ( long item )

get the list of possible model files that can be used as a sub-model to represent the processes inside an existing connection

#### **Parameters**

long | connection that will be the parent of the new model

#### Returns

tc\_list list of file names

Definition at line 27 of file TC\_ModuleTool\_api.c.

# 7.24.1.2 TCAPIEXPORT void tc\_ModuleTool\_api ( void(\*)(long, const char \*) substituteModel, tc\_strings(\*)(long) listOfModels )

initializing function

Definition at line 38 of file TC\_ModuleTool\_api.c.

# 7.24.1.3 TCAPIEXPORT void tc\_substituteEmptyModel ( long item )

load an empty sub-model to represent the processes inside an existing connection, i.e removed that process from the model

#### **Parameters**

long | connection that will be the parent of the new model

Definition at line 12 of file TC\_ModuleTool\_api.c.

# 7.24.1.4 BEGIN\_C\_DECLS TCAPIEXPORT void tc\_substituteModel ( long *item*, const char \* *filename* )

load a sub-model to represent the processes inside an existing connection. use an empty string to substitude the empty model.

### $7.25\ /home/deepak/TinkerCell/trunk/API/TC\_NodeInsertion\_api.c\ File\ Reference$

165

#### **Parameters**

long	connection that will be the parent of the new model
const	char* file name of new model

Definition at line 6 of file TC\_ModuleTool\_api.c.

#### 7.24.1.5 TCAPIEXPORT void tc\_substituteOriginalModel ( long item )

load the original sub-model for the processes inside an existing connection

#### **Parameters**

long	connection that will be the parent of the new model
------	-----------------------------------------------------

Definition at line 18 of file TC\_ModuleTool\_api.c.

## 7.25 /home/deepak/TinkerCell/trunk/API/TC\_NodeInsertion\_api.c File Reference

#include "TC\_NodeInsertion\_api.h"

#### **Functions**

- TCAPIEXPORT long tc\_insert (const char \*name, const char \*family)

  insert an item with the given name and family. returns the inserted connection
- TCAPIEXPORT void tc\_NodeInsertion\_api (long(\*insertItem)(const char \*, const char \*))

initializing function

#### **Variables**

• long(\* \_tc\_insert )(const char \*name, const char \*family)=0

#### 7.25.1 Function Documentation

#### 7.25.1.1 TCAPIEXPORT long tc\_insert ( const char \* name, const char \* family )

insert an item with the given name and family. returns the inserted connection

#### **Parameters**

string	name of new item
string	family name (type) of new item

Generated on Fri May 20 2011 13:17:07 for TinkerCell by Doxygen

#### Returns

int address of new item, 0 if insertion failed

Definition at line 8 of file TC\_NodeInsertion\_api.c.

### 7.25.1.2 TCAPIEXPORT void tc\_NodeInsertion\_api ( long(\*)(const char \*, const char \*) insertItem )

initializing function

initialize for node insertion plug-in

Definition at line 19 of file TC\_NodeInsertion\_api.c.

#### 7.25.2 Variable Documentation

7.25.2.1 long(\* tc insert)(const char \*name, const char \*family)=0

Definition at line 3 of file TC\_NodeInsertion\_api.c.

## 7.26 /home/deepak/TinkerCell/trunk/API/TC\_NodeInsertion\_api.h File Reference

```
#include "TC_structs.h"
```

#### **Functions**

• BEGIN\_C\_DECLS TCAPIEXPORT long tc\_insert (const char \*name, const char \*family)

insert an item with the given name and family. returns the inserted connection

• TCAPIEXPORT void tc\_NodeInsertion\_api (long(\*insertItem)(const char \*, const char \*))

initialize for node insertion plug-in

#### 7.26.1 Function Documentation

### 7.26.1.1 BEGIN\_C\_DECLS TCAPIEXPORT long tc\_insert ( const char \* name, const char \* family )

insert an item with the given name and family. returns the inserted connection

#### **Parameters**

string	name of new item
string	family name (type) of new item

#### Returns

int address of new item, 0 if insertion failed

Definition at line 8 of file TC\_NodeInsertion\_api.c.

### 7.26.1.2 TCAPIEXPORT void tc\_NodeInsertion\_api ( long(\*)(const char \*, const char \*) insertItem )

initialize for node insertion plug-in

Definition at line 19 of file TC\_NodeInsertion\_api.c.

# 7.27 /home/deepak/TinkerCell/trunk/API/TC\_PlotTool\_api.c File Reference

```
#include "TC_PlotTool_api.h"
```

#### **Functions**

- TCAPIEXPORT void tc\_surface (tc\_matrix z, const char \*title)

  plot 3D data. Input matrix has x,y on the first two columns and z on the third column
- TCAPIEXPORT void tc\_plot (tc\_matrix data, const char \*title)

  plot the data in the matrix (with headers) with the given x-axis and title
- TCAPIEXPORT void tc\_scatterplot (tc\_matrix data, const char \*title) plot the 2-columns in the matrix (with headers) as a scatter plot
- TCAPIEXPORT void tc\_errorBars (tc\_matrix data, const char \*title)
   plot the data in the matrix (with headers) with the given x-axis and title. For each column i, the i+1 and i+2 columns should contain the upper and lower bounds (errors).
- TCAPIEXPORT void tc\_hist (tc\_matrix data, const char \*title)

  plot histogram for each column of the given matrix with the given bin size.
- TCAPIEXPORT void tc\_multiplot (int rows, int cols)

  enable multi-plot, i.e. multiple plots on one screen. specify the number of rows and columns for the layout.
- TCAPIEXPORT void tc\_holdPlot (int z)

  enable hold

• TCAPIEXPORT void tc\_clusterPlots (int c)

enable clustering

• TCAPIEXPORT tc\_matrix tc\_getPlotData (int whichPlot)

get the data that is currently in the plot window

• TCAPIEXPORT void tc\_gnuplot (const char \*s)

gnuplot

• TCAPIEXPORT void tc\_savePlot (const char \*filename)

save plot

• TCAPIEXPORT void tc\_setLogScale (int i)

save plot

• TCAPIEXPORT void tc\_PlotTool\_api (void(\*plot)(tc\_matrix, const char \*), void(\*surface)(tc\_matrix M, const char \*), void(\*hist)(tc\_matrix data, const char \*title), void(\*errorBars)(tc\_matrix data, const char \*title), void(\*scatterplot)(tc\_matrix data, const char \*title), void(\*multiplot)(int r, int c), void(\*hold)(int b), void(\*enableClustering)(int c), tc\_matrix(\*plotData)(int), void(\*gnuplot)(const char \*), void(\*savePlotImage)(const char \*), void(\*logscale)(int))

initializing function

#### **Variables**

- void(\* \_tc\_surface)(tc\_matrix z, const char \*title)=0
- void(\* \_tc\_plot )(tc\_matrix data, const char \*title)=0
- void(\* \_tc\_scatterplot )(tc\_matrix data, const char \*title)=0
- void(\* \_tc\_errorBars )(tc\_matrix data, const char \*title)=0
- void(\* \_tc\_hist )(tc\_matrix data, const char \*title)=0
- void(\* \_tc\_multiplot )(int r, int c)=0
- void(\* \_tc\_holdPlot )(int)=0
- void(\* \_tc\_clusterPlots )(int c)=0
- tc\_matrix(\* \_tc\_getPlotData )(int whichPlot)=0
- void(\* \_tc\_gnuplot )(const char \*)=0
- void(\* \_tc\_savePlot )(const char \*)=0
- void(\* \_tc\_setLogScale )(int)=0

#### 7.27.1 **Function Documentation**

7.27.1.1 TCAPIEXPORT void tc\_PlotTool\_api ( void(\*)(tc\_matrix, const char \*) plot, void(\*)(tc\_matrix M, const char \*) surface, void(\*)(tc\_matrix data, const char \*title) hist, void(\*)(tc\_matrix data, const char \*title) errorBars, void(\*)(tc\_matrix data, const char \*title) scatterplot, void(\*)(int r, int c) multiplot, void(\*)(int b) hold, void(\*)(int c) enableClustering, tc\_matrix(\*)(int) plotData, void(\*)(const char \*) gnuplot, void(\*)(const char \*) savePlotImage, void(\*)(int) logscale )

initializing function

Definition at line 146 of file TC\_PlotTool\_api.c.

#### 7.27.2 Variable Documentation

7.27.2.1 void(\* \_tc\_clusterPlots)(int c)=0

Definition at line 80 of file TC\_PlotTool\_api.c.

7.27.2.2 void(\* \_tc\_errorBars)(tc\_matrix data, const char \*title)=0

Definition at line 36 of file TC\_PlotTool\_api.c.

7.27.2.3 tc\_matrix(\* \_tc\_getPlotData)(int whichPlot)=0

Definition at line 91 of file TC\_PlotTool\_api.c.

7.27.2.4 void(\* \_tc\_gnuplot)(const char \*)=0

Definition at line 109 of file TC PlotTool api.c.

7.27.2.5 void(\* \_tc\_hist)(tc\_matrix data, const char \*title)=0

Definition at line 47 of file TC\_PlotTool\_api.c.

7.27.2.6 void(\* \_tc\_holdPlot)(int)=0

Definition at line 69 of file TC\_PlotTool\_api.c.

7.27.2.7 void(\* \_tc\_multiplot)(int r, int c)=0

Definition at line 58 of file TC\_PlotTool\_api.c.

170 File Documentation

7.27.2.8 void(\* \_tc\_plot)(tc\_matrix data, const char \*title)=0

Definition at line 14 of file TC\_PlotTool\_api.c.

7.27.2.9 void(\* \_tc\_savePlot)(const char \*)=0

Definition at line 120 of file TC\_PlotTool\_api.c.

7.27.2.10 void(\* \_tc\_scatterplot)(tc\_matrix data, const char \*title)=0

Definition at line 25 of file TC\_PlotTool\_api.c.

7.27.2.11  $void(*\_tc\_setLogScale)(int)=0$ 

Definition at line 131 of file TC PlotTool api.c.

7.27.2.12 void(\* \_tc\_surface)(tc\_matrix z, const char \*title)=0

Definition at line 3 of file TC\_PlotTool\_api.c.

# 7.28 /home/deepak/TinkerCell/trunk/API/TC\_PlotTool\_api.h File Reference

#include "TC\_structs.h"

#### **Functions**

- TCAPIEXPORT void tc\_surface (tc\_matrix z, const char \*title)

  plot 3D data. Input matrix has x,y on the first two columns and z on the third column
- TCAPIEXPORT void tc\_plot (tc\_matrix data, const char \*title)

  plot the data in the matrix (with headers) with the given x-axis and title
- TCAPIEXPORT void tc\_scatterplot (tc\_matrix data, const char \*title) plot the 2-columns in the matrix (with headers) as a scatter plot
- TCAPIEXPORT void tc\_errorBars (tc\_matrix data, const char \*title)
   plot the data in the matrix (with headers) with the given x-axis and title. For each column i, the i+1 and i+2 columns should contain the upper and lower bounds (errors).
- TCAPIEXPORT void tc\_hist (tc\_matrix data, const char \*title)

  plot histogram for each column of the given matrix with the given bin size.

• TCAPIEXPORT void tc\_multiplot (int rows, int cols)

enable multi-plot, i.e. multiple plots on one screen. specify the number of rows and columns for the layout.

• TCAPIEXPORT void tc\_holdPlot (int z)

enable hold

• TCAPIEXPORT void tc\_clusterPlots (int c)

enable clustering

• TCAPIEXPORT tc\_matrix tc\_getPlotData (int whichPlot)

get the data that is currently in the plot window

• TCAPIEXPORT void tc\_gnuplot (const char \*s)

gnuplot

• TCAPIEXPORT void tc\_savePlot (const char \*filename)

save plot

• TCAPIEXPORT void tc\_setLogScale (int i)

save plot

• TCAPIEXPORT void tc\_PlotTool\_api (void(\*plot)(tc\_matrix, const char \*), void(\*surface)(tc\_matrix, const char \*), void(\*hist)(tc\_matrix, const char \*), void(\*errorBars)(tc\_matrix, const char \*), void(\*scatterplot)(tc\_matrix, const char \*), void(\*multiplot)(int, int), void(\*hold)(int), void(\*enableClustering)(int), tc\_matrix(\*plotData)(int), void(\*gnuplot)(const char \*), void(\*savePlotImage)(const char \*), void(\*logscale)(int))

initialize plot plug-in

#### 7.28.1 Function Documentation

7.28.1.1 TCAPIEXPORT void tc\_PlotTool\_api ( void(\*)(tc\_matrix, const char \*) plot, void(\*)(tc\_matrix, const char \*) surface, void(\*)(tc\_matrix, const char \*) hist, void(\*)(tc\_matrix, const char \*) errorBars, void(\*)(tc\_matrix, const char \*) scatterplot, void(\*)(int, int) multiplot, void(\*)(int) hold, void(\*)(int) enableClustering, tc\_matrix(\*)(int) plotData, void(\*)(const char \*) gnuplot, void(\*)(const char \*) savePlotImage, void(\*)(int) logscale )

initialize plot plug-in

# 7.29 /home/deepak/TinkerCell/trunk/API/TC\_SBML\_api.c File Reference

#include "TC\_SBML\_api.h"

172 File Documentation

#### **Functions**

TCAPIEXPORT void tc\_exportSBML (const char \*s)
 save sbml format to a file

• TCAPIEXPORT void tc\_importSBML (const char \*s)

load sbml model as string

TCAPIEXPORT void tc\_SBML\_api (void(\*exportSBML)(const char \*), void(\*importSBML)(const char \*))

initializing function

#### **Variables**

- void(\* \_tc\_exportSBML )(const char \*)=0
- void(\* \_tc\_importSBML )(const char \*)=0

#### 7.29.1 Function Documentation

7.29.1.1 TCAPIEXPORT void tc\_SBML\_api ( void(\*)(const char \*) exportSBML, void(\*)(const char \*) importSBML )

initializing function

Definition at line 30 of file TC\_SBML\_api.c.

#### 7.29.2 Variable Documentation

7.29.2.1  $void(*\_tc\_exportSBML)(const char *)=0$ 

Definition at line 3 of file TC\_SBML\_api.c.

7.29.2.2 void(\* \_tc\_importSBML)(const char \*)=0

Definition at line 15 of file TC\_SBML\_api.c.

# 7.30 /home/deepak/TinkerCell/trunk/API/TC\_SBML\_api.h File Reference

#include "TC\_structs.h"

#### **Functions**

- TCAPIEXPORT void tc\_exportSBML (const char \*s) save sbml format to a file
- TCAPIEXPORT void tc\_importSBML (const char \*s)
   load sbml model as string
- TCAPIEXPORT void tc\_SBML\_api (void(\*exportSBML)(const char \*), void(\*importSBML)(const char \*))

initializing function

#### 7.30.1 Function Documentation

7.30.1.1 TCAPIEXPORT void tc\_SBML\_api ( void(\*)(const char \*) exportSBML, void(\*)(const char \*) importSBML )

initializing function

Definition at line 30 of file TC\_SBML\_api.c.

## 7.31 /home/deepak/TinkerCell/trunk/API/TC\_StoichiometryTool\_api.c File Reference

```
#include <stdlib.h>
#include "TC_StoichiometryTool_api.h"
```

#### **Functions**

- TCAPIEXPORT tc\_matrix tc\_getStoichiometry (tc\_items A) get stoichiometry for the given items
- TCAPIEXPORT void tc\_setStoichiometry (tc\_items A, tc\_matrix N) set stoichiometry for the given items (must be labeled)
- TCAPIEXPORT tc\_strings tc\_getRates (tc\_items A) get rates for the given items
- TCAPIEXPORT void tc\_setRates (tc\_items A, tc\_strings rates) set rates for the given items (same order as N)
- TCAPIEXPORT tc\_matrix tc\_getStoichiometryFor (long x) get stoichiometry for the given items

174 File Documentation

```
• TCAPIEXPORT const char * tc_getRate (long x) get rate for the given items
```

- TCAPIEXPORT void tc\_setRate (long x, const char \*r) set rate for the given items
- TCAPIEXPORT void tc\_setStoichiometryFor (long x, tc\_matrix N) set stoichiometry for the given items
- TCAPIEXPORT void tc\_StoichiometryTool\_api (tc\_matrix(\*getStoichiometry)(tc\_items), void(\*setStoichiometry)(tc\_items, tc\_matrix), tc\_strings(\*getRates)(tc\_items), void(\*setRates)(tc\_items, tc\_strings))

initialize stiochiometry functions

#### **Variables**

- tc\_matrix(\* \_tc\_getStoichiometry )(tc\_items)=0
- void(\* \_tc\_setStoichiometry )(tc\_items, tc\_matrix N)=0
- tc\_strings(\* \_tc\_getRates )(tc\_items A)=0
- void(\* \_tc\_setRates )(tc\_items, tc\_strings rates)=0

#### 7.31.1 Variable Documentation

#### 7.31.1.1 tc\_strings(\* \_tc\_getRates)(tc\_items A)=0

Definition at line 27 of file TC\_StoichiometryTool\_api.c.

#### 7.31.1.2 tc\_matrix(\* \_tc\_getStoichiometry)(tc\_items)=0

Definition at line 4 of file TC\_StoichiometryTool\_api.c.

#### 7.31.1.3 void(\* \_tc\_setRates)(tc\_items,tc\_strings rates)=0

Definition at line 39 of file TC\_StoichiometryTool\_api.c.

#### 7.31.1.4 void(\* \_tc\_setStoichiometry)(tc\_items,tc\_matrix N)=0

Definition at line 16 of file TC\_StoichiometryTool\_api.c.

## 7.32 /home/deepak/TinkerCell/trunk/API/TC\_StoichiometryTool\_api.h File Reference

```
#include "TC_structs.h"
```

#### **Functions**

• BEGIN\_C\_DECLS TCAPIEXPORT tc\_matrix tc\_getStoichiometry (tc\_items A)

get Modeling for the given items

- TCAPIEXPORT void tc\_setStoichiometry (tc\_items A, tc\_matrix N) set Modeling for the given items (must be labeled)
- TCAPIEXPORT tc\_strings tc\_getRates (tc\_items A) get rates for the given items
- TCAPIEXPORT void tc\_setRates (tc\_items A, tc\_strings rates) set rates for the given items (same order as N)
- TCAPIEXPORT tc\_matrix tc\_getStoichiometryFor (long x) get Modeling for the given items
- TCAPIEXPORT const char \* tc\_getRate (long x) get rate for the given items
- TCAPIEXPORT void tc\_setRate (long x, const char \*r)
   set rate for the given items
- TCAPIEXPORT void tc\_setStoichiometryFor (long x, tc\_matrix N) set Modeling for the given items
- TCAPIEXPORT void tc\_StoichiometryTool\_api (tc\_matrix(\*getStoichiometry)(tc\_items), void(\*setStoichiometry)(tc\_items, tc\_matrix), tc\_strings(\*getRates)(tc\_items), void(\*setRates)(tc\_items, tc\_strings))

initialize stiochiometry plug-in

### 7.33 /home/deepak/TinkerCell/trunk/API/TC\_structs.c File Reference

```
#include <stdlib.h>
#include <stdio.h>
#include <math.h>
```

176 File Documentation

```
#include <string.h>
#include "TC_structs.h"
```

#### **Functions**

- TCAPIEXPORT tc\_matrix tc\_createMatrix (int rows, int cols)

  Create a matrix with the given rows and columns.
- TCAPIEXPORT tc\_table tc\_createTable (int rows, int cols)

  Create a strings table with the given rows and columns.
- TCAPIEXPORT tc\_strings tc\_createStringsArray (int len)

  Create an array of strings.
- TCAPIEXPORT tc\_items tc\_createItemsArray (int len) Create an array of items.
- TCAPIEXPORT double tc\_getMatrixValue (tc\_matrix M, int i, int j) get i,jth value from a tc\_matrix
- TCAPIEXPORT void tc\_setMatrixValue (tc\_matrix M, int i, int j, double d) set i,jth value of a tc\_matrix
- TCAPIEXPORT const char \* tc\_getRowName (tc\_matrix M, int i) get ith row name from a tc\_matrix
- TCAPIEXPORT void tc\_setRowName (tc\_matrix M, int i, const char \*s) set ith row name for a tc\_matrix
- TCAPIEXPORT const char \* tc\_getColumnName (tc\_matrix M, int i) get jth column name of a tc\_matrix
- TCAPIEXPORT void tc\_setColumnName (tc\_matrix M, int i, const char \*s) set jth column name of a tc\_matrix
- TCAPIEXPORT const char \* tc\_getTableValue (tc\_table S, int i, int j) get i,j-th string in a table
- TCAPIEXPORT void tc\_setTableValue (tc\_table S, int i, int j, const char \*s) set i,jth string in a table
- TCAPIEXPORT const char \* tc\_getString (tc\_strings S, int i) get ith string in array of strings
- TCAPIEXPORT void tc\_setString (tc\_strings S, int i, const char \*s)

set ith string in array of strings

- TCAPIEXPORT long tc\_getItem (tc\_items A, int i) get ith long item in array of items
- TCAPIEXPORT void tc\_setItem (tc\_items A, int i, long o) set ith long item in array of items
- TCAPIEXPORT void tc\_deleteMatrix (tc\_matrix M) delete a matrix
- TCAPIEXPORT void tc\_deleteTable (tc\_table M) delete a strings table
- TCAPIEXPORT void tc\_deleteItemsArray (tc\_items A) delete an array of items
- TCAPIEXPORT void tc\_deleteStringsArray (tc\_strings C) delete an array of strings
- TCAPIEXPORT tc\_matrix tc\_appendColumns (tc\_matrix A, tc\_matrix B)
   combine two matrices by appending their columns. row size must be equal for both
   matrices
- TCAPIEXPORT tc\_matrix tc\_appendRows (tc\_matrix A, tc\_matrix B)
   combine two matrices by appending their row. column sizes must be equal for both
   matrices
- TCAPIEXPORT void tc\_printMatrixToFile (const char \*s, tc\_matrix output)
   print a matrix to file
- TCAPIEXPORT void tc\_printOutMatrix (tc\_matrix output)

  print a matrix to stdout
- TCAPIEXPORT void tc\_printTableToFile (const char \*s, tc\_table output) print a table to file
- TCAPIEXPORT void tc\_printOutTable (tc\_table output)
   print a table to stdout
- TCAPIEXPORT int tc\_getStringIndex (tc\_strings A, const char \*s) get the index of a string in the array
- TCAPIEXPORT int tc\_getRowIndex (tc\_matrix m, const char \*s) get the row number of a row name
- TCAPIEXPORT int tc\_getColumnIndex (tc\_matrix m, const char \*s) get the column number of a column name

178 File Documentation

### 7.34 /home/deepak/TinkerCell/trunk/API/TC\_structs.h File Reference

#### **Data Structures**

• struct tc\_strings

An array of strings with length information. Use  $tc\_getString(M,i)$  to get the i-th string.

• struct tc\_items

An array of int objects with length information. Use tc\_getItem(M,i) to get the i-th item

• struct tc\_matrix

A 2D table of doubles with row and column names. Use  $tc\_getMatrixValue(M,i,j)$  to get the i,j-th value in  $tc\_matrix$  M.

• struct tc\_table

A 2D table of strings with row and column names. Use tc\_getTableValue(M,i,j) to get the i,j-th value in tc\_matrix M.

#### **Defines**

- #define BEGIN\_C\_DECLS
- #define END\_C\_DECLS
- #define TCAPIEXPORT

#### **Functions**

• TCAPIEXPORT tc\_matrix tc\_createMatrix (int rows, int cols)

Create a matrix with the given rows and columns.

• TCAPIEXPORT tc\_table tc\_createTable (int rows, int cols)

Create a strings table with the given rows and columns.

• TCAPIEXPORT tc\_strings tc\_createStringsArray (int len)

Create an array of strings.

• TCAPIEXPORT tc\_items tc\_createItemsArray (int len) Create an array of items.

- TCAPIEXPORT double tc\_getMatrixValue (tc\_matrix M, int i, int j) get i,jth value from a tc\_matrix
- TCAPIEXPORT void tc\_setMatrixValue (tc\_matrix M, int i, int j, double d) set i,jth value of a tc\_matrix

- TCAPIEXPORT const char \* tc\_getRowName (tc\_matrix M, int i) get ith row name from a tc\_matrix
- TCAPIEXPORT void tc\_setRowName (tc\_matrix M, int i, const char \*s) set ith row name for a tc\_matrix
- TCAPIEXPORT const char \* tc\_getColumnName (tc\_matrix M, int j) get jth column name of a tc\_matrix
- TCAPIEXPORT void tc\_setColumnName (tc\_matrix M, int j, const char \*s) set jth column name of a tc\_matrix
- TCAPIEXPORT const char \* tc\_getTableValue (tc\_table S, int i, int j) get i,j-th string in a table
- TCAPIEXPORT void tc\_setTableValue (tc\_table S, int i, int j, const char \*s) set i,jth string in a table
- TCAPIEXPORT const char \* tc\_getString (tc\_strings S, int i) get ith string in array of strings
- TCAPIEXPORT void tc\_setString (tc\_strings S, int i, const char \*c) set ith string in array of strings
- TCAPIEXPORT long tc\_getItem (tc\_items A, int i) get ith long item in array of items
- TCAPIEXPORT void tc\_setItem (tc\_items A, int i, long o) set ith long item in array of items
- TCAPIEXPORT int tc\_getStringIndex (tc\_strings A, const char \*s) get the index of a string in the array
- TCAPIEXPORT int tc\_getRowIndex (tc\_matrix, const char \*s) get the row number of a row name
- TCAPIEXPORT int tc\_getColumnIndex (tc\_matrix, const char \*s) get the column number of a column name
- TCAPIEXPORT void tc\_deleteMatrix (tc\_matrix M) delete a matrix
- TCAPIEXPORT void tc\_deleteTable (tc\_table M) delete a strings table

180 File Documentation

• TCAPIEXPORT void tc\_deleteItemsArray (tc\_items A) delete an array of items

- TCAPIEXPORT void tc\_deleteStringsArray (tc\_strings C)
   delete an array of strings
- TCAPIEXPORT tc\_matrix tc\_appendColumns (tc\_matrix A, tc\_matrix B)
   combine two matrices by appending their columns. row size must be equal for both
   matrices
- TCAPIEXPORT tc\_matrix tc\_appendRows (tc\_matrix A, tc\_matrix B)

  combine two matrices by appending their row. column sizes must be equal for both
  matrices
- TCAPIEXPORT void tc\_printMatrixToFile (const char \*file, tc\_matrix M) print a matrix to file
- TCAPIEXPORT void tc\_printOutMatrix (tc\_matrix M)
   print a matrix to stdout
- TCAPIEXPORT void tc\_printTableToFile (const char \*file, tc\_table M) print a table to file
- TCAPIEXPORT void tc\_printOutTable (tc\_table M)
   print a table to stdout

#### 7.34.1 Define Documentation

#### 7.34.1.1 #define BEGIN\_C\_DECLS

Definition at line 9 of file TC\_structs.h.

#### 7.34.1.2 #define END\_C\_DECLS

Definition at line 10 of file TC\_structs.h.

#### 7.34.1.3 #define TCAPIEXPORT

Definition at line 29 of file TC\_structs.h.

### Index

/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
AutoGeneRegulatoryTool_api.c,	ModelFileGenerator_api.h, 160
84	/home/deepak/TinkerCell/trunk/API/TC
/home/deepak/TinkerCell/trunk/API/TC	ModuleTool_api.c, 161
AutoGeneRegulatoryTool_api.h,	/home/deepak/TinkerCell/trunk/API/TC
85	ModuleTool_api.h, 163
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
BasicInformationTool_api.c, 86	NodeInsertion_api.c, 165
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
BasicInformationTool_api.h, 90	NodeInsertion_api.h, 166
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
COPASI_api.c, 98	PlotTool_api.c, 167
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
COPASI_api.h, 104	PlotTool_api.h, 170
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
ConnectionInsertion_api.c, 92	SBML_api.c, 171
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
ConnectionInsertion_api.h, 94	SBML_api.h, 172
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
ConnectionSelection_api.c, 95	StoichiometryTool_api.c, 173
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
ConnectionSelection_api.h, 97	StoichiometryTool_api.h, 175
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
DynamicLibraryTool_api.c, 107	api.h, 83
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
DynamicLibraryTool_api.h, 114	structs.c, 175
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/TC
EventsAssignments_api.c, 120	structs.h, 178
/home/deepak/TinkerCell/trunk/API/TC	/home/deepak/TinkerCell/trunk/API/main.hpp,
EventsAssignments_api.h, 122	83 tc KMatrix
/home/deepak/TinkerCell/trunk/API/TC	<del></del>
GroupHandlerTool_api.c, 123	TC_COPASI_api.c, 103 tc LMatrix
/home/deepak/TinkerCell/trunk/API/TC	TC_COPASI_api.c, 103
GroupHandlerTool_api.h, 124	_tc_addEvent
/home/deepak/TinkerCell/trunk/API/TC	TC_EventsAssignments_api.c, 121
Main_api.c, 125	_tc_addForcingFunction
/home/deepak/TinkerCell/trunk/API/TC	TC_EventsAssignments_api.c, 121
Main_api.h, 147	_tc_addFunction
/home/deepak/TinkerCell/trunk/API/TC	TC_DynamicLibraryTool_api.c, 113
÷	_tc_addInputWindowCheckbox
ModelFileGenerator_api.c, 160	_ic_addinput windowCheckbox

TC_Main_api.c, 139	TC_Main_api.c, 140
_tc_addInputWindowOptions	_tc_displayNumber
TC_Main_api.c, 139	TC_Main_api.c, 140
_tc_addOctavePlugin	_tc_displayText
TC_DynamicLibraryTool_api.c, 113	TC_Main_api.c, 141
_tc_addPythonPlugin	_tc_elementaryFluxModes
TC_DynamicLibraryTool_api.c, 113	TC_COPASI_api.c, 102
_tc_alignParts	_tc_errorBars
TC_AutoGeneRegulatoryTool_api.c,	TC_PlotTool_api.c, 169
85	_tc_errorReport
_tc_alignPartsOnPlasmid	TC_Main_api.c, 141
TC_AutoGeneRegulatoryTool_api.c,	_tc_exportSBML
85	TC_SBML_api.c, 172
_tc_allItems	_tc_find
TC_Main_api.c, 139	TC_Main_api.c, 141
_tc_annotations	_tc_findItems
TC_Main_api.c, 139	TC_Main_api.c, 141
_tc_appDir	_tc_getAllTextNamed
TC_Main_api.c, 139	TC_BasicInformationTool_api.c, 89
_tc_askQuestion	_tc_getCenterPointX
TC_Main_api.c, 139	TC_ConnectionSelection_api.c, 96
_tc_burn	_tc_getCenterPointY
TC_Main_api.c, 139	TC_ConnectionSelection_api.c, 96
_tc_callFunction	_tc_getChildren
TC_DynamicLibraryTool_api.c, 113	TC_Main_api.c, 141
_tc_callWhenExiting	_tc_getColor
TC_Main_api.c, 140	TC_Main_api.c, 141
_tc_callback	_tc_getConnectedNodes
TC_Main_api.c, 140	TC_ConnectionInsertion_api.c, 93
_tc_changeArrowHead	_tc_getConnectedNodesWithRole
TC_Main_api.c, 140	TC_ConnectionInsertion_api.c, 93
_tc_changeNodeImage	_tc_getConnections
TC_Main_api.c, 140	TC_ConnectionInsertion_api.c, 93
_tc_clear	_tc_getConnectionsWithRole
TC_Main_api.c, 140	TC_ConnectionInsertion_api.c, 93
_tc_clusterPlots	_tc_getControlPointX
TC_PlotTool_api.c, 169	TC_ConnectionSelection_api.c, 96
_tc_compileAndRun	_tc_getControlPointY
TC_DynamicLibraryTool_api.c, 113	TC_ConnectionSelection_api.c, 96
_tc_compileBuildLoad	_tc_getEigenvalues
TC_DynamicLibraryTool_api.c, 113	TC_COPASI_api.c, 102
_tc_compileBuildLoadSliders	_tc_getEventResponses
TC_DynamicLibraryTool_api.c, 113	TC_EventsAssignments_api.c, 121
_tc_createInputWindow	_tc_getEventTriggers
TC_Main_api.c, 140	TC_EventsAssignments_api.c, 121
_tc_createInputWindowForScript	_tc_getFamily
TC_Main_api.c, 140	TC_Main_api.c, 141
_tc_createSliders	_tc_getFilename
TC_Main_api.c, 140	TC_Main_api.c, 141
_tc_deselect	_tc_getFixedVariables
	=

TC_BasicInformationTool_api.c, 89	TC_COPASI_api.c, 103
_tc_getForcingFunctionAssignments	_tc_getStoichiometry
TC_EventsAssignments_api.c, 121	TC_StoichiometryTool_api.c, 174
_tc_getForcingFunctionNames	_tc_getStringDialog
TC_EventsAssignments_api.c, 121	TC_Main_api.c, 142
_tc_getHeight	_tc_getStringFromList
TC_Main_api.c, 141	TC_Main_api.c, 142
_tc_getInitialValues	_tc_getTextAttribute
TC_BasicInformationTool_api.c, 89	TC_BasicInformationTool_api.c, 89
_tc_getJacobian	_tc_getTextData
TC_COPASI_api.c, 102	TC_Main_api.c, 142
_tc_getName	_tc_getTextDataNames
TC_Main_api.c, 141	TC_Main_api.c, 143
_tc_getNames	_tc_getTextValue
TC_Main_api.c, 141	TC_Main_api.c, 143
_tc_getNumber	_tc_getUniqueName
TC_Main_api.c, 142	TC_Main_api.c, 143
_tc_getNumbers	_tc_getUniqueNames
TC_Main_api.c, 142	TC_Main_api.c, 143
_tc_getNumericalData	_tc_getUnscaledConcentrationCC
TC_Main_api.c, 142	TC_COPASI_api.c, 103
_tc_getNumericalDataNames	_tc_getUnscaledElasticities
TC_Main_api.c, 142	TC_COPASI_api.c, 103
_tc_getNumericalValue	_tc_getUnscaledFluxCC
•	=
TC_Main_api.c, 142	TC_COPASI_api.c, 103
_tc_getParameter	_tc_getWidth
TC_BasicInformationTool_api.c, 89	TC_Main_api.c, 143
_tc_getParameters	_tc_getX
TC_BasicInformationTool_api.c, 89	TC_Main_api.c, 143
_tc_getParametersAndFixedVariables	_tc_getY
TC_BasicInformationTool_api.c, 89	TC_Main_api.c, 143
_tc_getParametersExcept	_tc_gnuplot
TC_BasicInformationTool_api.c, 89	TC_PlotTool_api.c, 169
_tc_getParametersNamed	_tc_highlight
TC_BasicInformationTool_api.c, 89	TC_Main_api.c, 143
_tc_getParent	_tc_hist
TC_Main_api.c, 142	TC_PlotTool_api.c, 169
_tc_getPlotData	_tc_holdPlot
TC_PlotTool_api.c, 169	TC_PlotTool_api.c, 169
_tc_getPos	_tc_homeDir
TC_Main_api.c, 142	TC_Main_api.c, 143
_tc_getRates	_tc_importSBML
TC_StoichiometryTool_api.c, 174	TC_SBML_api.c, 172
_tc_getScaledConcentrationCC	_tc_insert
TC_COPASI_api.c, 102	TC_NodeInsertion_api.c, 166
_tc_getScaledElasticities	_tc_insertAnnotations
TC_COPASI_api.c, 102	TC_Main_api.c, 143
_tc_getScaledFluxCC	_tc_insertConnection
TC_COPASI_api.c, 102	TC_ConnectionInsertion_api.c, 93
_tc_getSteadyState	_tc_isA

TC_Main_api.c, 143	_tc_remove
_tc_isLinux	TC_Main_api.c, 145
TC_Main_api.c, 144	_tc_rename
_tc_isMac	TC_Main_api.c, 145
TC_Main_api.c, 144	_tc_runOctaveCode
_tc_isWindows	TC_DynamicLibraryTool_api.c, 113
TC_Main_api.c, 144	_tc_runOctaveFile
_tc_itemsOfFamily	TC_DynamicLibraryTool_api.c, 114
TC_Main_api.c, 144	_tc_runPythonCode
_tc_itemsOfFamilyFrom	TC_DynamicLibraryTool_api.c, 114
TC_Main_api.c, 144	_tc_runPythonFile
tc listOfPossibleModels	TC_DynamicLibraryTool_api.c, 114
TC_ModuleTool_api.c, 163	_tc_savePlot
_tc_loadLibrary	TC_PlotTool_api.c, 170
TC_DynamicLibraryTool_api.c, 113	_tc_saveToFile
_tc_merge	TC_Main_api.c, 145
TC_GroupHandlerTool_api.c, 124	_tc_scatterplot
	_
_tc_messageDialog	TC_PlotTool_api.c, 170
TC_Main_api.c, 144	_tc_screenHeight
_tc_moveSelected	TC_Main_api.c, 145
TC_Main_api.c, 144	_tc_screenWidth
_tc_multiplot	TC_Main_api.c, 145
TC_PlotTool_api.c, 169	_tc_screenX
_tc_openFile	TC_Main_api.c, 145
TC_Main_api.c, 144	_tc_screenY
_tc_openNewWindow	TC_Main_api.c, 145
TC_Main_api.c, 144	_tc_screenshot
_tc_openUrl	TC_Main_api.c, 145
TC_Main_api.c, 144	_tc_select
_tc_optimize	TC_Main_api.c, 146
TC_COPASI_api.c, 103	_tc_selectedItems
_tc_partsDownstream	TC_Main_api.c, 146
TC_AutoGeneRegulatoryTool_api.c,	_tc_separate
85	TC_GroupHandlerTool_api.c, 124
_tc_partsIn	_tc_setAllStraight
TC_AutoGeneRegulatoryTool_api.c,	TC_ConnectionSelection_api.c, 97
85	_tc_setAngle
_tc_partsUpstream	TC_Main_api.c, 146
TC_AutoGeneRegulatoryTool_api.c,	_tc_setCenterPoint
85	TC_ConnectionSelection_api.c, 97
	_
_tc_plot	_tc_setColor
TC_PlotTool_api.c, 169	TC_Main_api.c, 146
_tc_print	_tc_setControlPoint
TC_Main_api.c, 145	TC_ConnectionSelection_api.c, 97
_tc_printFile	_tc_setDisplayLabelColor
TC_Main_api.c, 145	TC_Main_api.c, 146
_tc_printMatrix	_tc_setInitialValues
TC_Main_api.c, 145	TC_BasicInformationTool_api.c, 90
_tc_reducedStoichiometry	_tc_setLineWidth
TC_COPASI_api.c, 103	TC_ConnectionSelection_api.c, 97

_tc_setLogScale	_tc_writeModel
TC_PlotTool_api.c, 170	TC_ModelFileGenerator_api.c, 160
_tc_setNumericalData	_tc_zoom
TC_Main_api.c, 146	TC_Main_api.c, 147
_tc_setNumericalValue	
TC_Main_api.c, 146	Annotation
_tc_setNumericalValues	tc_annotations, 34
TC_Main_api.c, 146	tc_getAllTextNamed, 34
_tc_setParameter	tc_getFamily, 35
TC_BasicInformationTool_api.c, 90	tc_getName, 35
_tc_setPos	tc_getNames, 35
TC_Main_api.c, 146	tc_getTextAttribute, 35
_tc_setPosMulti	tc_getUniqueName, 36
TC_Main_api.c, 146	tc_getUniqueNames, 36
_tc_setRates	tc_insertAnnotations, 36
TC_StoichiometryTool_api.c, 174	tc_isA, 36
_tc_setSize	tc_rename, 37
TC_Main_api.c, 146	tc_setSequence, 37
_tc_setStoichiometry	tc_setTextAttribute, 37
TC_StoichiometryTool_api.c, 174	tc_setTextAttributeByName, 38
_tc_setStraight	tc_setTextAttributes, 38
TC_ConnectionSelection_api.c, 97	Annotations, 33
_tc_setTextAttribute	Appearance, 19
TC_BasicInformationTool_api.c, 90	tc_changeArrowHead, 20
_tc_setTextData	tc_changeNodeImage, 21
TC_Main_api.c, 147	tc_getColor, 21
_tc_setTextValue	tc_getHeight, 21
TC_Main_api.c, 147	tc_getPos, 21
_tc_setTextValues	tc_getWidth, 22
TC_Main_api.c, 147	tc_getX, 22
_tc_showProgress	tc_getY, 22
TC_Main_api.c, 147	tc_moveSelected, 22
_tc_simulateDeterministic	tc_rotate, 23
TC_COPASI_api.c, 103	tc_setColor, 23
_tc_simulateHybrid	tc_setPos, 23
TC_COPASI_api.c, 103	tc_setPosMulti, 23
_tc_simulateStochastic	tc_setSize, 24
TC_COPASI_api.c, 104	_ ,
_tc_simulateTauLeap	Basic
TC_COPASI_api.c, 104	tc_appendColumns, 11
_tc_steadyStateScan	tc_appendRows, 11
TC_COPASI_api.c, 104	tc_createItemsArray, 12
_tc_steadyStateScan2D	tc_createMatrix, 12
TC_COPASI_api.c, 104	tc_createStringsArray, 12
_tc_substituteModel	tc_createTable, 13
TC_ModuleTool_api.c, 163	tc_deleteItemsArray, 13
_tc_surface	tc_deleteMatrix, 13
TC_PlotTool_api.c, 170	tc_deleteStringsArray, 13
_tc_updateParams	tc_deleteTable, 13
TC_COPASI_api.c, 104	tc_getColumnIndex, 14
	-G,

tc_getColumnName, 14	tc_alignParts, 26
tc_getItem, 14	tc_alignPartsOnPlasmid, 26
tc_getMatrixValue, 15	tc_allItems, 27
tc_getRowIndex, 15	tc_deselect, 27
tc_getRowName, 15	tc_find, 27
tc_getString, 16	tc_findItems, 27
tc_getStringIndex, 16	tc_getChildren, 28
tc_getTableValue, 16	tc_getName, 28
tc_printMatrixToFile, 16	tc_getNames, 28
tc_printOutMatrix, 17	tc_getParent, 28
tc_printOutTable, 17	tc_getPos, 29
tc_printTableToFile, 17	tc_getUniqueName, 29
tc_setColumnName, 17	tc_getUniqueNames, 29
tc_setItem, 18 tc_setMatrixValue, 18	tc_getX, 29
tc_setNatrix value, 18 tc_setRowName, 18	tc_getY, 30 tc_itemsOfFamily, 30
tc_setString, 18	tc_itemsOfFamilyFrom, 30
tc_setStillig, 18 tc_setTableValue, 19	tc_moveSelected, 31
Basic operations, 9	tc_noveselected, 31 tc_partsDownstream, 31
BEGIN_C_DECLS	tc_partsIownstream, 31
TC_structs.h, 180	tc_partsH, 31 tc_partsUpstream, 31
TC_structs.ii, 100	tc_rename, 31
colnames	tc_select, 32
tc_matrix, 80	tc_selectedItems, 32
tc_table, 82	tc_setPos, 32
cols	tc_setPosMulti, 32
tc_matrix, 80	tc_setSequence, 33
tc_table, 82	Get items, 24
Connections, 64	Graphing, 51
tc_getCenterPointX, 66	Graphing, 61
tc_getCenterPointY, 66	Import/Export, 70
tc_getConnectedNodes, 66	Input
tc_getConnectedNodesWithRole, 66	tc_addInputWindowCheckbox, 41
tc_getConnections, 67	tc_addInputWindowOptions, 41
tc_getConnectionsWithRole, 67	tc_askQuestion, 41
tc_getControlPointX, 67	tc_burn, 41
tc_getControlPointY, 68	tc_clear, 42
tc_insertConnection, 68	tc_createInputWindow, 42
tc_setAllStraight, 68	tc_createInputWindowForScript, 42
tc_setCenterPoint, 69	tc_createSliders, 42
tc_setControlPoint, 69	tc_displayNumber, 43
tc_setLineWidth, 69	tc_displayText, 43
tc_setStraight, 69	tc_errorReport, 43
END_C_DECLS	tc_getFilename, 43
TC_structs.h, 180	tc_getNumber, 44
Export	tc_getNumbers, 44
tc_exportSBML, 70	tc_getStringDialog, 44
tc_importSBML, 70	tc_getStringFromList, 44
r	tc_highlight, 45
Get	tc_messageDialog, 45

tc_openFile, 45	tc_StoichiometryTool_api, 64
tc_openNewWindow, 46	tc_writeModel, 64
tc_openUrl, 46	
tc_print, 46	Network data, 51
tc_printFile, 46	
tc_printMatrix, 47	Plotting
tc_saveToFile, 47	tc_clusterPlots, 52
tc_screenHeight, 47	tc_errorBars, 52
tc_screenshot, 47	tc_getPlotData, 52
tc_screenWidth, 47	tc_gnuplot, 53
tc_screenX, 48	tc_hist, 53
tc_screenY, 48	tc_holdPlot, 53
tc_setDisplayLabelColor, 48	tc_multiplot, 53
tc_showProgress, 48	tc_plot, 54
tc_zoom, 49	tc_savePlot, 54
Input and Output, 38	tc_scatterplot, 54
items	tc_setLogScale, 54
tc_items, 79	tc_surface, 55
length	rownames
tc_items, 79	tc_matrix, 80
tc_strings, 81	tc_table, 82
to_sumgs, 01	rows
Modeling, 55	tc_matrix, 80
tc_addEvent, 57	tc_table, 82
tc_addForcingFunction, 57	
tc_getEventResponses, 58	Simulation, 71
tc_getEventTriggers, 58	tc_elementaryFluxModes, 73
tc_getFixedVariables, 58	tc_getEigenvalues, 73
tc_getForcingFunctionAssignments, 58	tc_getJacobian, 73
tc_getForcingFunctionNames, 59	tc_getScaledConcentrationCC, 73
tc_getInitialValues, 59	tc_getScaledElasticities, 73
tc_getParameter, 59	tc_getScaledFluxCC, 73
tc_getParameters, 59	tc_getSteadyState, 74
tc_getParametersAndFixedVariables,	tc_getUnscaledConcentrationCC, 74
60	tc_getUnscaledElasticities, 74
tc_getParametersExcept, 60	tc_getUnscaledFluxCC, 74
tc_getParametersNamed, 60	tc_KMatrix, 74
tc_getRate, 61	tc_LMatrix, 75
tc_getRates, 61	tc_optimize, 75
tc_getStoichiometry, 61	tc_reducedStoichiometry, 75
tc_getStoichiometryFor, 62	tc_simulateDeterministic, 75
tc_setInitialValues, 62	tc_simulateHybrid, 76
tc_setParameter, 62	tc_simulateStochastic, 76
tc_setParameterByName, 62	tc_simulateTauLeap, 76
tc_setParameters, 63	tc_steadyStateScan, 77
tc_setRate, 63	tc_steadyStateScan2D, 77
tc_setRates, 63	tc_updateParameters, 78
tc_setStoichiometry, 63	strings
tc_setStoichiometryFor, 64	tc_strings, 81

tc_table, 82	TC_AutoGeneRegulatoryTool_api.c
System	_tc_alignParts, 85
tc_appDir, 50	_tc_alignPartsOnPlasmid, 85
tc_homeDir, 50	_tc_partsDownstream, 85
tc_isLinux, 50	_tc_partsIn, 85
tc_isMac, 50	_tc_partsUpstream, 85
tc_isWindows, 50	tc_AutoGeneRegulatoryTool_api, 85
System information, 49	TC_AutoGeneRegulatoryTool_api.h
40 addE4	tc_AutoGeneRegulatoryTool_api, 86
tc_addEvent	TC_BasicInformationTool_api.c
Modeling, 57	_tc_getAllTextNamed, 89
tc_addForcingFunction	_tc_getFixedVariables, 89
Modeling, 57	_tc_getInitialValues, 89
tc_addFunction	_tc_getParameter, 89
TC_DynamicLibraryTool_api.c, 109	_tc_getParameters, 89
TC_DynamicLibraryTool_api.h, 116	_tc_getParametersAndFixedVariables,
tc_addInputWindowCheckbox	89
Input, 41	_tc_getParametersExcept, 89
tc_addInputWindowOptions	_tc_getParametersNamed, 89
Input, 41	_tc_getTextAttribute, 89
tc_addOctavePlugin	_tc_setInitialValues, 90
TC_DynamicLibraryTool_api.c, 109	_tc_setParameter, 90
TC_DynamicLibraryTool_api.h, 116	_tc_setTextAttribute, 90
tc_addPythonPlugin	tc_BasicInformationTool_Numeric
TC_DynamicLibraryTool_api.c, 109	api, 88
TC_DynamicLibraryTool_api.h, 116	tc_BasicInformationTool_Text_api, 88
tc_alignParts	TC_BasicInformationTool_api.h
Get, 26	tc_BasicInformationTool_Numeric
tc_alignPartsOnPlasmid	api, 92
Get, 26	tc_BasicInformationTool_Text_api, 92
tc_allItems	tc_BasicInformationTool_Numeric_api
Get, 27	TC_BasicInformationTool_api.c, 88
tc_annotations	TC_BasicInformationTool_api.h, 92
Annotation, 34	tc_BasicInformationTool_Text_api
tc_appDir	TC_BasicInformationTool_api.c, 88
System, 50	TC_BasicInformationTool_api.h, 92
tc_appendColumns	tc_burn
Basic, 11	Input, 41
tc_appendRows	tc_callback
Basic, 11	TC_Main_api.c, 135
tc_askQuestion	TC_Main_api.h, 154
Input, 41	tc_callFunction
tc_AssignmentFunctionsTool_api	TC_DynamicLibraryTool_api.c, 110
TC_EventsAssignments_api.c, 121	TC_DynamicLibraryTool_api.h, 116
TC_EventsAssignments_api.h, 123	tc_callWhenExiting
tc_AutoGeneRegulatoryTool_api	TC_Main_api.c, 135
TC_AutoGeneRegulatoryTool_api.c,	TC_Main_api.h, 154
85	tc_changeArrowHead
TC_AutoGeneRegulatoryTool_api.h,	Appearance, 20
86	tc_changeNodeImage
**	

Appearance, 21	_tc_getJacobian, 102
tc_clear	_tc_getScaledConcentrationCC, 102
Input, 42	_tc_getScaledElasticities, 102
tc_clusterPlots	_tc_getScaledFluxCC, 102
Plotting, 52	_tc_getSteadyState, 103
tc_compileAndRun	_tc_getUnscaledConcentrationCC, 103
TC_DynamicLibraryTool_api.c, 110	_tc_getUnscaledElasticities, 103
TC_DynamicLibraryTool_api.h, 116	_tc_getUnscaledFluxCC, 103
tc_compileBuildLoad	_tc_optimize, 103
TC_DynamicLibraryTool_api.c, 110	_tc_reducedStoichiometry, 103
TC_DynamicLibraryTool_api.h, 117	_tc_simulateDeterministic, 103
tc_compileBuildLoadSliders	_tc_simulateHybrid, 103
TC_DynamicLibraryTool_api.c, 110	_tc_simulateStochastic, 104
TC_DynamicLibraryTool_api.h, 117	_tc_simulateTauLeap, 104
tc_ConnectionInsertion_api	_tc_steadyStateScan, 104
TC_ConnectionInsertion_api.c, 93	_tc_steadyStateScan2D, 104
TC_ConnectionInsertion_api.h, 94	_tc_updateParams, 104
TC_ConnectionInsertion_api.c	tc_COPASI_api, 102
_tc_getConnectedNodes, 93	TC_COPASI_api.h
_tc_getConnectedNodesWithRole, 93	tc_COPASI_api, 107
_tc_getConnections, 93	tc_createInputWindow
_tc_getConnectionsWithRole, 93	Input, 42
_tc_insertConnection, 93	tc_createInputWindowForScript
	<u> </u>
tc_ConnectionInsertion_api, 93	Input, 42
TC_ConnectionInsertion_api.h	tc_createItemsArray
tc_ConnectionInsertion_api, 94	Basic, 12
tc_ConnectionSelection_api	tc_createMatrix
TC_ConnectionSelection_api.c, 96	Basic, 12
TC_ConnectionSelection_api.h, 98	tc_createSliders
TC_ConnectionSelection_api.c	Input, 42
_tc_getCenterPointX, 96	tc_createStringsArray
_tc_getCenterPointY, 96	Basic, 12
_tc_getControlPointX, 96	tc_createTable
_tc_getControlPointY, 96	Basic, 13
_tc_setAllStraight, 97	tc_CThread_api_initialize
_tc_setCenterPoint, 97	TC_Main_api.c, 135
_tc_setControlPoint, 97	TC_Main_api.h, 155
_tc_setLineWidth, 97	tc_deleteItemsArray
_tc_setStraight, 97	Basic, 13
tc_ConnectionSelection_api, 96	tc_deleteMatrix
TC_ConnectionSelection_api.h	Basic, 13
tc_ConnectionSelection_api, 98	tc_deleteStringsArray
tc_COPASI_api	Basic, 13
TC_COPASI_api.c, 102	tc_deleteTable
TC_COPASI_api.h, 107	Basic, 13
TC_COPASI_api.c	tc_deselect
_tc_KMatrix, 103	Get, 27
_tc_LMatrix, 103	tc_displayNumber
_tc_elementaryFluxModes, 102	Input, 43
_tc_getEigenvalues, 102	tc_displayText
_ ,	* *

Input, 43	tc_elementaryFluxModes
tc_DynamicLibraryMenu_api	Simulation, 73
TC_DynamicLibraryTool_api.c, 111	tc_errorBars
TC_DynamicLibraryTool_api.h, 117	Plotting, 52
ΓC_DynamicLibraryTool_api.c	tc_errorReport
_tc_addFunction, 113	Input, 43
_tc_addOctavePlugin, 113	TC_EventsAssignments_api.c
_tc_addPythonPlugin, 113	_tc_addEvent, 121
_tc_callFunction, 113	_tc_addForcingFunction, 121
_tc_compileAndRun, 113	_tc_getEventResponses, 121
_tc_compileBuildLoad, 113	_tc_getEventTriggers, 121
_tc_compileBuildLoadSliders, 113	_tc_getForcingFunctionAssignments,
_tc_loadLibrary, 113	121
_tc_runOctaveCode, 113	_tc_getForcingFunctionNames, 121
_tc_runOctaveFile, 114	tc_AssignmentFunctionsTool_api, 121
_tc_runPythonCode, 114	tc_SimulationEventsTool_api, 121
_tc_runPythonFile, 114	TC_EventsAssignments_api.h
tc_addFunction, 109	tc_AssignmentFunctionsTool_api, 123
tc_addOctavePlugin, 109	tc_SimulationEventsTool_api, 123
tc_addPythonPlugin, 109	tc_exportSBML
tc_callFunction, 110	Export, 70
tc_compileAndRun, 110	tc_find
tc_compileBuildLoad, 110	Get, 27
tc_compileBuildLoadSliders, 110	tc_findItems
tc_DynamicLibraryMenu_api, 111	Get, 27
tc_LoadCLibraries_api, 111	tc_getAllTextNamed
tc_loadLibrary, 111	Annotation, 34
tc_OctaveTool_api, 111	tc_getCenterPointX
tc_PythonTool_api, 111	Connections, 66
tc_runOctaveCode, 112	tc_getCenterPointY
tc_runOctaveFile, 112	Connections, 66
tc_runPythonCode, 112	tc_getChildren
tc_runPythonFile, 112	Get, 28
ΓC_DynamicLibraryTool_api.h	tc_getColor
tc_addFunction, 116	Appearance, 21
tc_addOctavePlugin, 116	tc_getColumnIndex
tc_addPythonPlugin, 116	Basic, 14
tc_callFunction, 116	tc_getColumnName
tc_compileAndRun, 116	Basic, 14
tc_compileBuildLoad, 117	tc_getConnectedNodes
tc_compileBuildLoadSliders, 117	Connections, 66
tc_DynamicLibraryMenu_api, 117	tc_getConnectedNodesWithRole
tc_LoadCLibraries_api, 117	Connections, 66
tc_loadLibrary, 118	tc_getConnections
tc_OctaveTool_api, 118	Connections, 67
tc_PythonTool_api, 118	tc_getConnectionsWithRole
tc_runOctaveCode, 119	Connections, 67
tc_runOctaveFile, 119	tc_getControlPointX
tc_runPythonCode, 119	Connections, 67
tc_runPythonFile, 119	tc_getControlPointY
w_rum ymom ne, 11)	ic_5cicondon oniti

Connections, 68	tc_getParametersAndFixedVariables
tc_getEigenvalues	Modeling, 60
Simulation, 73	tc_getParametersExcept
tc_getEventResponses	Modeling, 60
Modeling, 58	tc_getParametersNamed
tc_getEventTriggers	Modeling, 60
Modeling, 58	tc_getParent
tc_getFamily	Get, 28
Annotation, 35	tc_getPlotData
tc_getFilename	Plotting, 52
Input, 43	tc_getPos
tc_getFixedVariables	Appearance, 21
Modeling, 58	Get, 29
tc_getForcingFunctionAssignments	tc_getRate
Modeling, 58	Modeling, 61
tc_getForcingFunctionNames	tc_getRates
Modeling, 59	Modeling, 61
tc_getHeight	tc_getRowIndex
Appearance, 21	Basic, 15
tc_getInitialValues	tc_getRowName
Modeling, 59	Basic, 15
tc_getItem	tc_getScaledConcentrationCC
Basic, 14	Simulation, 73
tc_getJacobian	tc_getScaledElasticities
Simulation, 73	Simulation, 73
tc_getMatrixValue	tc_getScaledFluxCC
Basic, 15	Simulation, 73
tc_getName	tc_getSteadyState
Annotation, 35	Simulation, 74
Get, 28	tc_getStoichiometry
tc_getNames	Modeling, 61
Annotation, 35	tc_getStoichiometryFor
Get, 28	Modeling, 62
tc_getNumber	tc_getString
Input, 44	Basic, 16
tc_getNumbers	tc_getStringDialog
Input, 44	Input, 44
tc_getNumericalData	tc_getStringFromList
TC_Main_api.c, 135	Input, 44
TC_Main_api.h, 155	tc_getStringIndex
tc_getNumericalDataNames	Basic, 16
TC_Main_api.c, 135	tc_getTableValue
TC_Main_api.h, 155	Basic, 16
tc_getNumericalValue	tc_getTextAttribute
TC_Main_api.c, 136	Annotation, 35
TC_Main_api.h, 155	tc_getTextData
tc_getParameter	TC_Main_api.c, 136
Modeling, 59	TC_Main_api.h, 156
tc_getParameters	tc_getTextDataNames
Modeling, 59	TC_Main_api.c, 136
,	,,,

TC_Main_api.h, 156	TC_NodeInsertion_api.c, 165
tc_getTextValue	TC_NodeInsertion_api.h, 166
TC_Main_api.c, 136	tc_insertAnnotations
TC_Main_api.h, 156	Annotation, 36
tc_getUniqueName	tc_insertConnection
Annotation, 36	Connections, 68
Get, 29	
	tc_isA
tc_getUniqueNames Annotation, 36	Annotation, 36
	tc_isLinux
Get, 29	System, 50 tc isMac
tc_getUnscaledConcentrationCC	<del>_</del>
Simulation, 74	System, 50
tc_getUnscaledElasticities	tc_isWindows
Simulation, 74	System, 50
tc_getUnscaledFluxCC	tc_items, 79
Simulation, 74	items, 79
tc_getWidth	length, 79
Appearance, 22	tc_itemsOfFamily
tc_getX	Get, 30
Appearance, 22	tc_itemsOfFamilyFrom
Get, 29	Get, 30
tc_getY	tc_KMatrix
Appearance, 22	Simulation, 74
Get, 30	tc_LabelingTool_api
tc_gnuplot	TC_Main_api.c, 136
Plotting, 53	TC_Main_api.h, 156
tc_GroupHandlerTool_api	tc_listOfPossibleModels
TC_GroupHandlerTool_api.c, 124	TC_ModuleTool_api.c, 162
TC_GroupHandlerTool_api.h, 125	TC_ModuleTool_api.h, 164
TC_GroupHandlerTool_api.c	tc_LMatrix
_tc_merge, 124	Simulation, 75
_tc_separate, 124	tc_LoadCLibraries_api
tc_GroupHandlerTool_api, 124	TC_DynamicLibraryTool_api.c, 111
tc_merge, 124	TC_DynamicLibraryTool_api.h, 117
tc_separate, 124	tc_loadLibrary
TC_GroupHandlerTool_api.h	TC_DynamicLibraryTool_api.c, 111
tc_GroupHandlerTool_api, 125	TC_DynamicLibraryTool_api.h, 118
tc_merge, 125	TC_Main_api.c
tc_separate, 125	_tc_addInputWindowCheckbox, 139
tc_highlight	_tc_addInputWindowOptions, 139
Input, 45	_tc_allItems, 139
tc_hist	_tc_annotations, 139
Plotting, 53	_tc_appDir, 139
tc_holdPlot	_tc_askQuestion, 139
Plotting, 53	_tc_burn, 139
tc_homeDir	_tc_callWhenExiting, 140
System, 50	_tc_callback, 140
tc_importSBML	_tc_changeArrowHead, 140
Export, 70	_tc_changeNodeImage, 140
tc_insert	_tc_clear, 140

to anatalmentWindow 140	4 145
_tc_createInputWindow, 140	_tc_remove, 145
_tc_createInputWindowForScript, 140	
_tc_createSliders, 140	_tc_saveToFile, 145
_tc_deselect, 140	_tc_screenHeight, 145
_tc_displayNumber, 140	_tc_screenWidth, 145
_tc_displayText, 141	_tc_screenX, 145
_tc_errorReport, 141	_tc_screenY, 145
_tc_find, 141	_tc_screenshot, 145
_tc_findItems, 141	_tc_select, 146
_tc_getChildren, 141	_tc_selectedItems, 146
_tc_getColor, 141	_tc_setAngle, 146
_tc_getFamily, 141	_tc_setColor, 146
_tc_getFilename, 141	_tc_setDisplayLabelColor, 146
_tc_getHeight, 141	_tc_setNumericalData, 146
_tc_getName, 141	_tc_setNumericalValue, 146
_tc_getNames, 141	_tc_setNumericalValues, 146
_tc_getNumber, 142	_tc_setPos, 146
_tc_getNumbers, 142	_tc_setPosMulti, 146
_tc_getNumericalData, 142	_tc_setSize, 146
•	
_tc_getNumericalDataNames, 142	_tc_setTextData, 147
_tc_getNumericalValue, 142	_tc_setTextValue, 147
_tc_getParent, 142	_tc_setTextValues, 147
_tc_getPos, 142	_tc_showProgress, 147
_tc_getStringDialog, 142	_tc_zoom, 147
_tc_getStringFromList, 142	tc_callback, 135
_tc_getTextData, 142	tc_callWhenExiting, 135
_tc_getTextDataNames, 143	tc_CThread_api_initialize, 135
_tc_getTextValue, 143	tc_getNumericalData, 135
_tc_getUniqueName, 143	tc_getNumericalDataNames, 135
_tc_getUniqueNames, 143	tc_getNumericalValue, 136
_tc_getWidth, 143	tc_getTextData, 136
_tc_getX, 143	tc_getTextDataNames, 136
_tc_getY, 143	tc_getTextValue, 136
_tc_highlight, 143	tc_LabelingTool_api, 136
_tc_homeDir, 143	tc_Main_api_initialize, 136
_tc_insertAnnotations, 143	tc_remove, 137
_tc_isA, 143	tc_setNumericalData, 138
_tc_isLinux, 144	tc_setNumericalValue, 138
_tc_isMac, 144	tc_setNumericalValues, 138
_tc_isWindows, 144	tc_setTextData, 138
_tc_itemsOfFamily, 144	tc_setTextValue, 138
_tc_itemsOfFamilyFrom, 144	tc_setTextValues, 139
_tc_messageDialog, 144	tc_thisThread, 139
_tc_moveSelected, 144	TC_Main_api.h
_tc_openFile, 144	tc_callback, 154
_tc_openNewWindow, 144	tc_callWhenExiting, 154
_tc_openUrl, 144	tc_CThread_api_initialize, 155
_tc_print, 145	tc_getNumericalData, 155
_tc_printFile, 145	tc_getNumericalDataNames, 155
_tc_printMatrix, 145	tc_getNumericalValue, 155

tc_getTextData, 156	tc_substituteModel, 164
tc_getTextDataNames, 156	tc_substituteOriginalModel, 165
tc_getTextValue, 156	tc_moveSelected
tc_LabelingTool_api, 156	Appearance, 22
tc_Main_api_initialize, 157	Get, 31
tc_remove, 157	tc_multiplot
tc_setNumericalData, 158	Plotting, 53
tc_setNumericalValue, 158	tc_NodeInsertion_api
tc_setNumericalValues, 158	TC_NodeInsertion_api.c, 166
tc_setTextData, 158	TC_NodeInsertion_api.h, 167
tc_setTextValue, 159	TC_NodeInsertion_api.c
tc_setTextValues, 159	_tc_insert, 166
tc_thisThread, 159	tc_insert, 165
tc_Main_api_initialize	tc_NodeInsertion_api, 166
TC_Main_api.c, 136	TC_NodeInsertion_api.h
TC_Main_api.h, 157	tc_insert, 166
tc_matrix, 80	tc_NodeInsertion_api, 167
colnames, 80	tc_OctaveTool_api
cols, 80	TC_DynamicLibraryTool_api.c, 111
rownames, 80	TC_DynamicLibraryTool_api.h, 118
rows, 80	tc_openFile
values, 80	Input, 45
tc_merge	tc_openNewWindow
TC_GroupHandlerTool_api.c, 124	Input, 46
TC_GroupHandlerTool_api.h, 125	tc_openUrl
tc_messageDialog	Input, 46
Input, 45	tc_optimize
tc_ModelFileGenerator_api	Simulation, 75
TC_ModelFileGenerator_api.c, 160	tc_partsDownstream
TC_ModelFileGenerator_api.h, 161	Get, 31
ΓC_ModelFileGenerator_api.c	tc_partsIn
_tc_writeModel, 160	Get, 31
tc_ModelFileGenerator_api, 160	tc_partsUpstream
ΓC_ModelFileGenerator_api.h	Get, 31
tc_ModelFileGenerator_api, 161	tc_plot
tc_ModuleTool_api	Plotting, 54
TC_ModuleTool_api.c, 162	tc_PlotTool_api
TC_ModuleTool_api.h, 164	TC_PlotTool_api.c, 169
ΓC_ModuleTool_api.c	TC_PlotTool_api.h, 171
_tc_listOfPossibleModels, 163	TC_PlotTool_api.c
_tc_substituteModel, 163	_tc_clusterPlots, 169
tc_listOfPossibleModels, 162	_tc_errorBars, 169
tc_ModuleTool_api, 162	_tc_getPlotData, 169
tc_substituteEmptyModel, 162	_tc_gnuplot, 169
tc_substituteModel, 162	_tc_hist, 169
tc_substituteOriginalModel, 163	_tc_holdPlot, 169
ГС_ModuleTool_api.h	_tc_multiplot, 169
tc_listOfPossibleModels, 164	_tc_plot, 169
tc_ModuleTool_api, 164	_tc_savePlot, 170
tc_substituteEmptyModel, 164	_tc_scatterplot, 170

_tc_setLogScale, 170	TC_SBML_api.h, 173
_tc_surface, 170	TC_SBML_api.c
tc_PlotTool_api, 169	_tc_exportSBML, 172
TC_PlotTool_api.h	_tc_importSBML, 172
tc_PlotTool_api, 171	tc_SBML_api, 172
tc_print	TC_SBML_api.h
Input, 46	tc_SBML_api, 173
tc_printFile	tc_scatterplot
Input, 46	Plotting, 54
tc_printMatrix	tc_screenHeight
Input, 47	Input, 47
tc_printMatrixToFile	tc_screenshot
Basic, 16	Input, 47
tc_printOutMatrix	tc_screenWidth
Basic, 17	Input, 47
tc_printOutTable	tc_screenX
Basic, 17	Input, 48
tc_printTableToFile	tc_screenY
Basic, 17	Input, 48
tc_PythonTool_api	tc_select
TC_DynamicLibraryTool_api.c, 111	Get, 32
TC_DynamicLibraryTool_api.h, 118	tc_selectedItems
tc_reducedStoichiometry	Get, 32
Simulation, 75	tc_separate
tc_remove	TC_GroupHandlerTool_api.c, 124
TC_Main_api.c, 137	TC_GroupHandlerTool_api.h, 125
TC_Main_api.h, 157	tc_setAllStraight
tc_rename	Connections, 68
Annotation, 37	tc_setCenterPoint
Get, 31	Connections, 69
tc_rotate	tc_setColor
Appearance, 23	Appearance, 23
tc_runOctaveCode	tc_setColumnName
TC_DynamicLibraryTool_api.c, 112	Basic, 17
TC_DynamicLibraryTool_api.h, 119	tc_setControlPoint
tc_runOctaveFile	Connections, 69
TC_DynamicLibraryTool_api.c, 112	tc setDisplayLabelColor
TC_DynamicLibraryTool_api.h, 119	Input, 48
tc_runPythonCode	tc setInitialValues
TC_DynamicLibraryTool_api.c, 112	Modeling, 62
TC_DynamicLibraryTool_api.h, 119	tc_setItem
tc_runPythonFile	Basic, 18
TC_DynamicLibraryTool_api.c, 112	tc_setLineWidth
TC_DynamicLibraryTool_api.h, 119	Connections, 69
tc_savePlot	tc_setLogScale
Plotting, 54	Plotting, 54
tc_saveToFile	tc_setMatrixValue
Input, 47	Basic, 18
tc_SBML_api	tc_setNumericalData
TC_SBML_api.c, 172	TC_Main_api.c, 138

TC_Main_api.h, 158	TC_Main_api.c, 138
tc_setNumericalValue	TC_Main_api.h, 159
TC_Main_api.c, 138	tc_setTextValues
TC_Main_api.h, 158	TC_Main_api.c, 139
tc_setNumericalValues	TC_Main_api.h, 159
TC_Main_api.c, 138	tc_showProgress
TC_Main_api.h, 158	Input, 48
tc_setParameter	tc_simulateDeterministic
Modeling, 62	Simulation, 75
tc_setParameterByName	tc_simulateHybrid
Modeling, 62	Simulation, 76
tc_setParameters	tc simulateStochastic
Modeling, 63	Simulation, 76
tc_setPos	tc_simulateTauLeap
Appearance, 23	Simulation, 76
Get, 32	tc_SimulationEventsTool_api
tc setPosMulti	TC_EventsAssignments_api.c, 121
Appearance, 23	TC_EventsAssignments_api.h, 123
Get, 32	tc_steadyStateScan
tc_setRate	Simulation, 77
Modeling, 63	tc_steadyStateScan2D
tc setRates	Simulation, 77
Modeling, 63	tc_StoichiometryTool_api
tc_setRowName	Modeling, 64
Basic, 18	TC_StoichiometryTool_api.c
tc_setSequence	_tc_getRates, 174
Annotation, 37	_tc_getStoichiometry, 174
Get, 33	_tc_setRates, 174
tc_setSize	_tc_setStoichiometry, 174
Appearance, 24	tc_strings, 81
tc_setStoichiometry	length, 81
Modeling, 63	strings, 81
tc_setStoichiometryFor	TC_structs.h
Modeling, 64	BEGIN_C_DECLS, 180
tc_setStraight	END_C_DECLS, 180
Connections, 69	TCAPIEXPORT, 180
tc_setString	tc_substituteEmptyModel
Basic, 18	TC_ModuleTool_api.c, 162
tc_setTableValue	TC_ModuleTool_api.e, 102 TC_ModuleTool_api.h, 164
Basic, 19	tc_wodule1001_apr.n, 104
tc setTextAttribute	TC_ModuleTool_api.c, 162
Annotation, 37	TC_ModuleTool_api.b, 164
tc_setTextAttributeByName	tc_substituteOriginalModel
Annotation, 38	TC_ModuleTool_api.c, 163
tc_setTextAttributes	TC_ModuleTool_api.b, 165
	-
Annotation, 38 tc_setTextData	tc_surface
	Plotting, 55
TC_Main_api.c, 138	tc_table, 81
TC_Main_api.h, 158	colnames, 82
tc_setTextValue	cols, 82

```
rownames, 82
    rows, 82
    strings, 82
tc_thisThread
    TC_Main_api.c, 139
    TC_Main_api.h, 159
tc_updateParameters
    Simulation, 78
tc\_writeModel
    Modeling, 64
tc_zoom
    Input, 49
TCAPIEXPORT
    TC_structs.h, 180
values
    tc_matrix, 80
```