# 1 Ideal gas mixer

## 1.1 Utility functions

For emptying the input pipe I into the furnace

fillFurnace:
yield
s Furnace SettingInput 100
l x IAnalyzer TotalMoles
brgtz -3

s Furnace SettingInput 0

j ra

And for emptying the furnace into the filtration system, which filters all  $CO_2$  back into the input pipe.

emptyFurnace:
yield
s Furnace SettingOutput 100

1 x Furnace TotalMoles
brgtz -3

brgtz -3

s Furnace SettingOutput 0

j ra

### 1.2 Mixing algorithm

Let  $n_R=0$  be the moles to remove, and calculate constant terms.

constant terms.  $e_T = t_T n_T$   $n_{T-F} = n_T - n_F$ 

move nR 0 mul eT tT nT sub dn nT nF sub dt tH tC

### 1.3 Calculate input moles $n_I = n_H + n_C$ given $n_R$

Calculate total moles input

 $n_I = n_{T-F} + n_R$ 

 $t_{H-C} = t_H - t_C$ 

calculateInputMoles:
add nI dn nR

Calculate temperature input:

$$t_I = \frac{e_T - t_F(n_F - n_R)}{n_I}$$

Calculate moles from hot/cold source:

$$n_H = \frac{n_I(t_I - t_C)}{t_{H-C}}, \quad n_C = n_I - n_H$$

sub nH tI tC mul nH nI nH div nH nH dt sub nC nI nH j ra

sub x nF nR
mul x tF x

sub tI eT x
div tI tI nI

### 1.4 Searching for $n_R$

For  $n_R$  to be valid,  $n_H$  and  $n_C$  must both be positive.

checkInputMoles:
min x nH nC
sgtz x x # x = nH > 0 and nC > 0
j ra

For  $n_R = 0$ , if this is the case we are done.

move nR 0
jal calculateInputMoles
jal checkInputMoles
beq x 1 compose # nR=0, nH>0, nC>0: skip

Else, we begin a binary search of the domain  $[0, n_F]$  for a satisfactory value of  $n_R$ , each time recalculating and rechecking the input moles via 1.3. Beginning with  $n_R = n_F/2$ , we bisect i times.

```
define BisectionIterations 20
# ...
move i BisectionIterations
div nR nF 2
div step nF 4
jal calculateInputMoles
jal checkInputMoles
select x x 1 -1
mul x x step
add nR nR x # nR += (nH>0 && nC>0) ? step : -step
div step step 2
sub i i 1
brgtz i -7
```

#### 1.5 Removing $n_R$ and composing I

Having found satisfactory  $n_R$ ,  $n_H$  and  $n_C$ , we first remove  $n_R$  moles from the furnace (or remove none when  $n_R$  is zero). The furnace, containing only  $CO_2$ , is emptied into the input pipe I. Moles are removed, via a volume pump, until the total moles in the pipe  $n_I$  is less-than or equal to the initial number of moles  $n_F$  minus the number of moles to remove  $n_R$ . Then this potentially reduced amount is reinserted into the furnace.

We then compose the I mixture by first adding H moles via a volume pump while the moles in I is less-than to  $n_H$ , then doing the same for C until moles in I is less-than to  $n_I$ .

jal emptyFurnace
sub nF nF nR
yield
s InputDumpPump On 1
l x IAnalyzer TotalMoles
brgt x nF -3
s InputDumpPump On 0
jal fillFurnace

alias HPump d0 alias CPump d1 alias HAnalyzer d2 alias CAnalyzer d3

alias nH r0 alias hC r1 alias i r2

 ${\tt move~i~0}$ 

fillUntil:
yield
s dr2 On 1
add i i 2
l x dr3 TotalMoles
sub i i 2
brlt x rr2 - 3
s dr0 On 0
add i i 1