
Multi-Layer Switching

Lab Summary

Configure Layer 2 and Layer 3 switch for connectivity of hosts to both servers.

Figure 1 Lab Topology



Lab Configuration

Start Packet Tracer File: Multilayer Switching

Click on the *L2-Switch* icon and select the *CLI* folder. Hit <enter> key for user mode prompt .

Step 1: Enter global configuration mode

L2-Switch> enable
Password: cisconet

L2-Switch# configure terminal

Configure VLANs on Layer 2 Switch

Step 2: Configure interface Fa0/1 as an access port and assign it to VLAN 10.

- L2-Switch(config)# interface fastethernet 0/1
- L2-Switch(config-if)# switchport mode access
- L2-Switch(config-if)# switchport access vlan 10

Step 3: Configure interface Fa1/1 as an access port and assign it to VLAN 11.

- L2-Switch(config)# interface fastethernet 1/1
- L2-Switch(config-if)# switchport mode access
- L2-Switch(config-if)# switchport access vlan 11

- Step 4: Configure interface Fa2/1 as an access port and assign it to VLAN 12.
 - L2-Switch(config)# interface fastethernet 2/1
 - L2-Switch(config-if)# switchport mode access
 - L2-Switch(config-if)# switchport access vlan 12
 - L2-Switch(config-if)# exit
- Step 5: Configure trunk interface on Layer 2 switch to Layer 3 switch.
 - L2-Switch(config)# interface fastethernet 3/1
 - L2-Switch(config-if)# switchport mode trunk
 - L2-Switch(config-if)# switchport trunk allowed vlan 10-12
 - L2-Switch(config-if)# end
 - L2-Switch# copy run start
- Step 6: Configure trunk interface on Layer 3 switch to Layer 2 switch.
 - L3-Switch> enable
 - L3-Switch# configure terminal
 - L3-Switch(config)# interface fastethernet 0/1
 - L3-Switch(config-if)# switchport mode trunk
 - L3-Switch(config-if)# switchport trunk allowed vlan 10-12
 - L3-Switch(config-if)# exit
- Step 7: Enable IP routing on Layer 3 switch.
 - L3-Switch(config)# ip routing
- Step 8: Configure an SVI for each host VLAN on Layer 3 switch.
 - L3-Switch(config)# interface vlan 10
 - L3-Switch(config-if)# ip address 172.16.10.254 255.255.255.0
 - L3-Switch(config-if)# no shut
 - L3-Switch(config-if)# interface vlan 11
 - L3-Switch(config-if)# ip address 172.16.11.254 255.255.255.0
 - L3-Switch(config-if)# no shut
 - L3-Switch(config)# interface vlan 12
 - L3-Switch(config-if)# ip address 172.16.12.254 255.255.255.0
 - L3-Switch(config-if)# no shut
 - L3-Switch(config-if)# exit
- Step 9: Configure default gateway on hosts.
 - host-1:Config Folder
 - host-1: Gateway/DNS IPv4

host-1: 172.16.10.254

host-2:Config Folder

host-2: Gateway/DNS IPv4

host-2: 172.16.11.254

server-1: Config Folder

server-1: Gateway/DNS IPv4

server-1: 172.16.12.254

Step 10: Configure uplink interface on Layer 3 switch to router-1

L3-Switch(config)# interface fastethernet0/4

L3-Switch(config-if)# no switchport

L3-Switch(config-if)# ip address 172.16.1.1 255.255.255.0

L3-Switch(config-if)# no shut

L3-Switch(config-if)# exit

Step 11: Configure default route on Layer 3 switch to router-1

L3-Switch(config)# ip route 0.0.0.0 0.0.0.0 172.16.1.2

L3-Switch(config)# end

L3-Switch# copy run start

Step 12: Verify Lab

Ping server-1 and server-2 from host-1 and host-2 command prompt to verify network connectivity.

host-1: ping 172.16.12.1

host-1: ping 172.16.3.1

host-2: ping 172.16.12.1

host-2: ping 172.16.3.1