BLM2041 Signals and Systems

Syllabus

The Instructors:

Doç. Dr. Ali Can Karaca


ackaraca@yildiz.edu.tr

Dr. Ahmet Elbir

aelbir@yildiz.edu.tr

Where are we now?

The arrows here show conceptual flow between ideas. Note the parallel structure between the pink blocks (C-T Freq. Analysis) and the blue blocks (D-T Freq. Analysis).



Recall: Fourier Series represents a periodic signal as a sum of sinusoids

or complex sinusoids $e^{jk\omega_0 t}$

Note: Because the FS uses "harmonically related" frequencies $k\omega_0$, it can only create periodic signals

Q: Can we modify the FS idea to handle <u>non</u>-periodic signals?

<u>A:</u> Yes!!

What about $x(t) = \sum_{k=-\infty}^{\infty} c_k e^{j\omega_k t}$?


With <u>arbitrary</u> <u>discrete</u> frequencies... <u>NOT</u> harmonically related


This will give <u>some</u> non-periodic signals but not all signals of interest!!

The problem with this is that it cannot include <u>all</u> possible frequencies!

No matter how close we try to choose the discrete frequencies ω_k there are always some left out of the sum!!!

We need some way to include ALL frequencies!!





Yes... this will work for any practical non-periodic signal!!

Called the "Fourier Integral" also, more commonly, called the "Inverse Fourier Transform"

Plays the role of c_k

Plays the role of $e^{jk\omega_0t}$

Integral replaces sum because it can "add up over the *continuum* of frequencies"!

Okay... given x(t) how do we get $X(\omega)$?

$$X(\omega) = \int_{-\infty}^{\infty} x(t)e^{-j\omega t}dt$$

Called the "Fourier Transform" of x(t)

Note: $X(\omega)$ is complex-valued function of $\omega \in (-\infty, \infty)$



Comparison of FT and FS

Fourier Series: Used for periodic signals

Fourier Transform: Used for <u>non-periodic</u> signals (although we will see later that it can also be used for periodic signals)

	Synthesis	Analysis
Fourier Series	$x(t) = \sum_{n = -\infty}^{\infty} c_k e^{jk\omega_0 t}$	$c_k = \frac{1}{T} \int_{t_0}^{t_0+T} x(t) e^{-jk\omega_0 t} dt$
	Fourier Series	Fourier Coefficients
Fourier Transform	$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega) e^{j\omega t} d\omega$	$X(\omega) = \int_{-\infty}^{\infty} x(t)e^{-j\omega t}dt$
	<u>Inverse</u> Fourier Transform	Fourier Transform

FS coefficients c_k are a <u>complex-valued</u> function of integer k

FT $X(\omega)$ is a complex-valued function of the variable $\omega \in (-\infty, \infty)$

Fourier Transform Defined

For non-periodic signals

$$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(j\omega) e^{j\omega t} d\omega$$

Fourier Synthesis (Inverse Transform)

$$X(j\omega) = \int_{-\infty}^{\infty} x(t)e^{-j\omega t}dt$$

Fourier Analysis (Forward Transform)

Time - Domain \Leftrightarrow Frequency - Domain $x(t) \Leftrightarrow X(j\omega)$

Synthesis Viewpoints:

$$\mathbf{\underline{FS:}} \qquad x(t) = \sum_{n = -\infty}^{\infty} c_k e^{jk\omega_0 t}$$

 $|c_k|$ shows how much there is of the signal at frequency $k\omega_0$

 $\angle c_k$ shows how much phase shift is needed at frequency $k\omega_0$

We need two plots to show these

FT:
$$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega) e^{j\omega t} d\omega$$


 $|X(\omega)|$ shows how much there is in the signal at frequency ω

 $\angle X(\omega)$ shows how much phase shift is needed at frequency ω

We need two plots to show these

Fourier Transform Viewpoint

View FT as a transformation into a new "domain"



x(t) is the "time domain" description of the signal $X(\omega)$ is the "frequency domain" description of the signal

Alternate Notations

1.
$$x(t) \leftrightarrow X(\omega)$$

$$2. X(\omega) = \mathcal{F}\left\{x(t)\right\}$$

$$\Rightarrow \mathcal{F}\{\}$$
 is an "operator on" $x(t)$ to give $X(\omega)$

$$3. x(t) = \mathcal{F}^{-1} \left\{ X(\omega) \right\}$$

$$\Rightarrow \mathcal{F}^{-1}$$
{}is an "operator on"

$$X(\omega)$$
 to give $x(t)$

Analogy: Looking at $X(\omega)$ is "like" looking at an x-ray of the signal- in the sense that an x-ray lets you see what is inside the object... shows what stuff it is made from.

In this sense: $X(\omega)$ shows what is "inside" the signal – it shows how much of each complex sinusoid is "inside" the signal

Note: x(t) completely determines $X(\omega)$


 $X(\omega)$ completely determines x(t)

There are some advanced mathematical issues that can be hurled at these comments... we'll not worry about them

Example: FT of a Rectangular pulse

 τ = pulse width

Given: a rectangular pulse signal $p_{\tau}(t)$



Find: $P_t(\omega)$... the FT of $p_t(t)$

Note the Notational Convention: lowercase for time signal and corresponding upper-case for its FT Recall: we use this symbol to indicate a rectangular pulse with width τ

Solution: (Here we'll directly do the integral... but later we'll use the "FT Table")

Note that

$$p_{\tau}(t) = \begin{cases} 1, & -\frac{\tau}{2} \le t \le \frac{\tau}{2} \\ 0, & otherwise \end{cases}$$

Now apply the definition of the FT:

$$P_{\tau}(\omega) = \int_{-\infty}^{\infty} p_{\tau}(t)e^{-j\omega t}dt = \int_{-\tau/2}^{\tau/2} e^{-j\omega t}dt$$


Limit integral to where $p_{\tau}(t)$ is non-zero... and use the fact that it is 1 over that region

$$= \frac{-1}{j\omega} \left[e^{-j\omega t} \right]_{\frac{-\tau}{2}}^{\frac{\tau}{2}} = \frac{2}{\omega} \left[\frac{e^{j\frac{\omega\tau}{2}} - e^{-j\frac{\omega\tau}{2}}}{j2} \right]$$

Artificially inserted 2 in numerator and denominator

$$= \sin\left(\frac{\omega\tau}{2}\right)$$

Use Euler's Formula




$$P_{\tau}(\omega) = \frac{2\sin\left(\frac{\omega\tau}{2}\right)}{\omega}$$

sin goes up and down between -1 and 1

1/ω decays down as |ω| gets big... this causes the overall function to decay down


For <u>this</u> case the FT is real valued so we can plot it using a single plot (shown in solid blue here):




Now... let's think about how to make a magnitude/phase plot...


Even though this FT is real-valued we can still plot it using magnitude and phase plots:

We can view any real number as a complex number that has zero as its imaginary part





Applying these Ideas to the Real-valued FT $P_{\tau}(\omega)$



Here I have chosen $-\pi$ to <u>display</u> odd symmetry


Definition of "Sinc" Function

The result we just found had this mathematical form:


$$P_{\tau}(\omega) = \frac{2\sin\left(\frac{\omega\tau}{2}\right)}{\omega}$$

This structure shows up enough that we define a special function to capture it:

Define:
$$\operatorname{sinc}(x) = \frac{\sin(\pi x)}{\pi x}$$




With a little manipulation we can re-write the FT result for a pulse in terms of the sinc function:



$$P_{\tau}(\omega) = \tau \operatorname{sinc}\left(\frac{\omega\tau}{2\pi}\right)$$

FT of Rect. Pulse = Sinc Function



$$x(t) = e^{-at}u(t)$$

$$X(j\omega) = \int_{0}^{\infty} e^{-at} e^{-j\omega t} dt = \int_{0}^{\infty} e^{-(a+j\omega)t} dt$$

$$e^{-at} e^{-j\omega t} \Big|_{\infty}^{\infty}$$
1

$$X(j\omega) = -\frac{e^{-at}e^{-j\omega t}}{a+j\omega}\bigg|_{0}^{\infty} = \frac{1}{a+j\omega}$$

$$X(j\omega) = \frac{1}{a + j\omega}$$

Example 1 - Frequency Response


- Fourier Transform of h(t) is
 - the Frequency Response

$$h(t) = e^{-t}u(t)$$

$$e^{-1}$$

$$h(t) = e^{-t}u(t) \Leftrightarrow H(j\omega) = \frac{1}{1+j\omega}$$

Example 1 - Magnitude and Phase Plots




$$x(t) = \begin{cases} 1 & |t| < T/2 \\ 0 & |t| > T/2 \end{cases}$$

$$X(j\omega) = \int_{-T/2}^{T/2} (1)e^{-j\omega t}dt = \int_{-T/2}^{T/2} e^{-j\omega t}dt$$

$$X(j\omega) = \frac{e^{-j\omega t}}{-j\omega}\bigg|_{-T/2}^{T/2} = \frac{e^{-j\omega T/2} - e^{j\omega T/2}}{-j\omega}$$

$$X(j\omega) = \frac{\sin(\omega T/2)}{(\omega/2)}$$

$$x(t) = \begin{cases} 1 & |t| < T/2 \\ 0 & |t| > T/2 \end{cases} \Leftrightarrow X(j\omega) = \frac{\sin(\omega T/2)}{(\omega/2)}$$




$$X(j\omega) = \begin{cases} 1 & |\omega| < \omega_b \\ 0 & |\omega| > \omega_b \end{cases}$$

$$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(j\omega) e^{j\omega t} d\omega = \frac{1}{2\pi} \int_{-\omega_b}^{\omega_b} 1 e^{j\omega t} d\omega$$
$$x(t) = \frac{1}{2\pi} \frac{e^{j\omega t}}{jt} \Big|_{-\omega_b}^{\omega_b} = \frac{1}{2\pi} \frac{e^{j\omega_b t} - e^{-j\omega_b t}}{jt}$$

$$x(t) = \frac{1}{2\pi} \frac{e^{j\omega t}}{jt} \Big|_{-\infty}^{\omega_b} = \frac{1}{2\pi} \frac{e^{j\omega_b t} - e^{-j\omega_b t}}{jt}$$

$$x(t) = \frac{\sin(\omega_b t)}{\pi t}$$

$$x(t) = \frac{\sin(\omega_b t)}{\pi t} \quad \Leftrightarrow \quad X(j\omega) = \begin{cases} 1 & |\omega| < \omega_b \\ 0 & |\omega| > \omega_b \end{cases}$$



$$x(t) = \delta(t - t_0)$$


$$X(j\omega) = \int_{-\infty}^{\infty} \delta(t)e^{-j\omega t}dt = 1$$

$$X(j\omega) = \int_{-\infty}^{\infty} \delta(t - t_0)e^{-j\omega t}dt = e^{-j\omega t_0}$$

Shifting Property of the Impulse

Impulse function – Time and Frequency domains

$$x(t) = \delta(t) \Leftrightarrow X(j\omega) = 1$$



$$X(j\omega) = 2\pi\delta(\omega - \omega_0)$$

$$x(t) = \frac{1}{2\pi} \int_{-\infty}^{\infty} 2\pi \delta(\omega - \omega_0) e^{j\omega t} d\omega = e^{j\omega_0 t}$$


$$x(t) = e^{j\omega_0 t} \Leftrightarrow X(j\omega) = 2\pi\delta(\omega - \omega_0)$$

$$x(t) = 1 \Leftrightarrow X(j\omega) = 2\pi\delta(\omega)$$

$$x(t) = \cos(\omega_0 t) \Leftrightarrow$$

$$X(j\omega) = \pi \delta(\omega - \omega_0) + \pi \delta(\omega + \omega_0)$$

$$x(t) = \cos(\omega_c t) \Leftrightarrow X(j\omega) = \pi \delta(\omega - \omega_c) + \pi \delta(\omega + \omega_c)$$



We have just found the FT for a common signal...

$$p_{\tau}(t) = \begin{cases} 1, & -\frac{\tau}{2} \le t \le \frac{\tau}{2} \\ 0, & otherwise \end{cases} \qquad P_{\tau}(\omega) = \tau \operatorname{sinc}\left(\frac{\omega \tau}{2\pi}\right)$$

We derived that result by directly applying the integral form of the FT to the given signal equation.

For the common "textbook" signals this has already been done... and the results are available in tables published in books and on-line

You should study the table provided...


- If you encounter a time signal or FT that is on this table you should recognize that it is on the table without being told that it is there.
- You should be able to recognize entries in graphical form as well as in equation form.
- Later we'll learn about some "FT properties" that will expand your ability to apply these entries on the FT Table

In the real-world, engineers use these table results to understand basic ideas and concepts and to think through how things work in principle!

So... next we'll look at some of the more important entries in the table provided...

Decaying Exponential

As we'll see later... this signal naturally occurs in lots of real-world places!




 ω



-20

Frequency ω (rad/sec)



True for <u>every</u> real-valued signal

MATLAB Commands to Compute FT

w=-100:0.2:100;

-80

b=10:

-2└ -100

X=1./(b+j*w);

Plotting Commands

80

60


subplot(2,1,1); plot(w,abs(X))
xlabel('Frequency \omega (rad/sec)')
ylabel('|X(\omega|) (volts)'); grid
subplot(2,1,2); plot(w,angle(X))
xlabel('Frequency \omega (rad/sec)')
ylabel('<X(\omega) (rad)'); grid

100


Effect of Exp. Decay Rate b on FT Magnitude

Time Signal

$x(t) = e^{-bt}u(t)$



FT Magnitude



Note: As b increases...

1. Decay rate in time signal increases

Short Signals have FTs that spread more into High Frequencies!!!

2. High frequencies in Fourier transform are more prominent.

Some Important Signals & Their FTs (see Table for More!)

$$1, \quad -\infty < t < \infty \Longrightarrow 2\pi\delta(\omega)$$

$$u(t) \Longrightarrow \pi\delta(\omega) + 1/j\omega$$

$$-0.5 + u(t) \Longrightarrow 1/j\omega$$

$$\delta(t) \Longrightarrow 1, \quad -\infty < \omega < \infty$$

$$\cos(\omega_o t) \Longrightarrow \pi[\delta(\omega + \omega_o) + \delta(\omega - \omega_o)]$$

$$\sin(\omega_o t) \Longrightarrow j\pi[\delta(\omega + \omega_o) - \delta(\omega - \omega_o)]$$

$$e^{j\omega_o t} \Longrightarrow 2\pi\delta(\omega - \omega_o), \quad \omega_o \text{ real}$$

Time Signal	Fourier Transform
$1, -\infty < t < \infty$	$2\pi\delta(\omega)$
-0.5 + u(t)	$1/j\omega$
u(t)	$\pi\delta(\omega) + 1/j\omega$
$\delta(t)$	$1, -\infty < \omega < \infty$
$\delta(t-c)$, c real	$e^{-j\alpha c}$, c real
$e^{-bt}u(t), b>0$	$\frac{1}{j\omega+b}$, $b>0$
$e^{j\omega_o t}$, ω_o real	$2\pi\delta(\omega-\omega_o)$, ω_o real
$p_{\tau}(t)$	$\tau \operatorname{sinc}[\tau \omega / 2\pi]$
$\tau \operatorname{sinc}[\tau t/2\pi]$	$2\pi p_{\tau}(\omega)$
$\left[1-\frac{2 t }{\tau}\right]p_{\tau}(t)$	$\frac{\tau}{2} \operatorname{sinc}^2 \left[\tau \omega / 4\pi \right]$
$\frac{\tau}{2}\mathrm{sinc}^2\big[\taut/4\pi\big]$	$2\pi \left[1-\frac{2 \omega }{\tau}\right]p_{\tau}(\omega)$
$\cos(\omega_o t)$	$\pi \left[\mathcal{S}(\omega + \omega_o) + \mathcal{S}(\omega - \omega_o) \right]$
$\cos(\omega_o t + \theta)$	$\pi \Big[e^{-j\theta} \mathcal{S}(\omega + \omega_o) + e^{j\theta} \mathcal{S}(\omega - \omega_o) \Big]$
$\sin(\omega_o t)$	$j\pi[\delta(\omega+\omega_o)-\delta(\omega-\omega_o)]$
$\sin(\omega_o t + \theta)$	$j\pi \Big[e^{-j\theta} \delta(\omega + \omega_o) - e^{j\theta} \delta(\omega - \omega_o) \Big]$

Property Name	Pı	roperty	
Linearity	ax(t) + bv(t)	$aX(\omega) + bV(\omega)$	
Time Shift	x(t-c)	$e^{-j\omega}X(\omega)$	
Time Scaling	$x(at), a \neq 0$	$\frac{1}{a}X(\omega/a), a \neq 0$	
Time Reversal	x(-t)	$X(-\omega)$	
		$\overline{X(\omega)}$ if $x(t)$ is real	
Multiply by t ⁿ	$t^n x(t), n = 1, 2, 3, \dots$	$j^n \frac{d^n}{d\omega^n} X(\omega), n = 1, 2, 3, \dots$	
Multiply by Complex Exponential	$e^{j\omega_o t}x(t)$, ω_o real	$X(\omega - \omega_o)$, ω_o real	
Multiply by Sine	$\sin(\omega_o t)x(t)$	$\frac{j}{2} [X(\omega + \omega_o) - X(\omega - \omega_o)]$	
Multiply by Cosine	$\cos(\omega_o t)x(t)$	$\frac{1}{2} \left[X(\omega + \omega_o) + X(\omega - \omega_o) \right]$	
Time Differentiation	$\frac{d^n}{dt^n}x(t), n=1, 2, 3, \dots$	$(j\omega)^n X(\omega), n=1,2,3,\ldots$	
Time Integration	$\int_{-\infty}^{t} x(\lambda) d\lambda$	$\frac{1}{j\omega}X(\omega) + \pi X(0)S(\omega)$	
Convolution in Time	x(t) * h(t)	$X(\omega)H(\omega)$	
Multiplication in Time	x(t)w(t)	$\frac{1}{2\pi}X(\omega)^*W(\omega)$	
Parseval's Theorem (General)	$\int_{-\infty}^{\infty} x(t)\overline{v(t)}dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega)\overline{V(\omega)}d\omega$		
Parseval's Theorem (Energy)	$\int_{-\infty}^{\infty} x^{2}(t)dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega) ^{2} d\omega \text{if } x(t) \text{ is real}$		
	$\int_{-\infty}^{\infty} x(t) ^2 dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega) ^2 d\omega$		
Duality: If $x(t) \leftrightarrow X(\omega)$	X(t) 2	$2\pi x(-\omega)$	

FT of Periodic Signal

Note that we have now used the FT to analyze cosine and sine... which are <u>PERIODIC</u> signals!!! Before we used the Fourier <u>Series</u> to analyze <u>periodic</u> signals... Now we see that we can also use the Fourier <u>Transform</u>!

If x(t) is periodic then we can write the FS of it as: $x(t) = \sum_{k=-\infty}^{\infty} c_k e^{jk\omega_0 t}$

Now we can take the FT of both sides of this: $\Im\{x(t)\} = \Im\{\sum_{k=-\infty}^{\infty} c_k e^{jk\omega_0 t}\}$


FT of a Periodic Signal

$$X(\omega) = \sum_{k=-\infty}^{\infty} 2\pi c_k \delta(\omega - k\omega_0)$$

Note: the FT is a bunch of delta functions with "weights" given by the FS coefficients!

$$=\sum_{k=-\infty}^{\infty}c_{k}\mathcal{F}\left\{ e^{jk\omega_{0}t}\right\}$$

$$2\pi\delta(\omega-k\omega_{0})$$



So the FT of a periodic signal is zero except at multiples of the fundamental frequency ω_0 , where you get impulses.

We call these spikes "Spectral Lines"

Note that if we start with the Amplitude-Phase Trig form we end up with the same result for the FT

$$x(t) = A_0 + \sum_{k=1}^{\infty} A_k \cos(k\omega_0 t + \theta_k)$$

For each cosine term we get two deltas (a positive frequency & negative frequency): $\cos(\omega_o t + \theta) \iff \pi \left[e^{-j\theta} \delta(\omega + \omega_o) + e^{j\theta} \delta(\omega - \omega_o) \right]$

These properties are useful for two main things:

- 1. They help you apply the table to a wider class of signals
- 2. They are often the key to understanding how the FT can be used in a given application.

So... even though these results may at first seem like "just boring math" they are important tools that let signal processing engineers understand how to build things like cell phones, radars, mp3 processing, etc.

Here... we will only cover the most important properties.

See the available table for the complete list of properties!

In this note set we simply learn these most-important properties... in the next note set we'll see how to use them.

1. Linearity (Supremely Important)

Gets used virtually all the time!!

If
$$x(t) \leftrightarrow X(\omega)$$
 & $y(t) \leftrightarrow Y(\omega)$
then $[ax(t) + by(t)] \leftrightarrow [aX(\omega) + bY(\omega)]$

Another way to write this property:

$$\mathcal{F}\left\{ax(t) + by(t)\right\} = a\mathcal{F}\left\{x(t)\right\} + b\mathcal{F}\left\{y(t)\right\}$$

To see why:
$$\Im\{ax(t) + by(t)\} = \int_{-\infty}^{\infty} [ax(t) + by(t)]e^{-j\omega t} dt$$
 Use Defin of FT

By standard Property of Integral of sum of functions
$$= a \int_{-\infty}^{\infty} x(t)e^{-j\omega t}dt + b \int_{-\infty}^{\infty} y(t)e^{-j\omega t}dt$$

$$= X(\omega) = Y(\omega)$$
By Defin of FT

2. Time Shift (Really Important!)

Used often to understand <u>practical</u> issues that arise in <u>audio</u>, <u>communications</u>, <u>radar</u>, etc.

If
$$x(t) \leftrightarrow X(\omega)$$
 then $x(t-c) \leftrightarrow X(\omega)e^{-jc\omega}$

Note: If c > 0 then x(t - c) is a <u>delay</u> of x(t)

So... what does this *mean*??

<u>First</u>... it does nothing to the magnitude of the FT: $X(\omega)e^{-j\omega} = |X(\omega)|$

That means that a shift doesn't change "how much" we need of each of the sinusoids we build with

Second... it does change the phase of the FT: $\angle \{X(\omega)e^{-jc\omega}\} = \angle X(\omega) + \angle e^{-jc\omega}$

$$= \angle X(\omega) + c\omega$$


Line of slope -c

Phase shift increases linearly as the frequency increases

This gets added to original phase


3. Time Scaling (Important)

Q: If $x(t) \leftrightarrow X(\omega)$, then $x(at) \leftrightarrow ???$ for $a \neq 0$



An interesting "duality"!!!


To explore this FT property...first, what does x(at) look like?





|a| > 1 makes it "wiggle" faster \Rightarrow need <u>more</u> high frequencies |a| < 1 makes it "wiggle" slower \Rightarrow need <u>less</u> high frequencies

When
$$|a| > 1 \Rightarrow |1/a| < 1$$

Time Signal is Squished
$$x(at) \leftrightarrow \frac{1}{|a|} X \left(\frac{\omega}{a}\right)$$
FT is Stretched Horizontally and Reduced Vertically








Rough Rule of Thumb we can extract from this property:

Very Short Signals tend to take up Wide Bandwidth

Scaling Property



4. Time Reversal (Special case of time scaling: a = -1)

$$x(-t) \leftrightarrow X(-\omega)$$

Note:
$$X(-\omega) = \int_{-\infty}^{\infty} x(t)e^{-j(-\omega)t}dt = \int_{-\infty}^{\infty} x(t)e^{+j\omega t}dt$$
 = "No Change"

$$= \int_{-\infty}^{\infty} \overline{x(t)} e^{\frac{-j}{+j \cot t}} dt$$
 Conjugate changes to $-j$
$$= x(t) \text{ if } x(t) \text{ is real}$$

$$= \overline{\int_{-\infty}^{\infty} x(t) e^{-j\omega t} dt} = \overline{X(\omega)}$$

So if x(t) is <u>real</u>, then we get the <u>special case</u>:

$$x(-t) \leftrightarrow \overline{X(\omega)}$$

Recall: conjugation doesn't change abs. value but negates the angle

$$|\overline{X(\omega)}| = |X(\omega)|$$

$$\angle X(\omega) = -\angle X(\omega)$$

5. Modulation Property

Super important!!!

Essential for understanding practical issues that arise in communications, radar, etc.

There are two forms of the modulation property...

- 1. Complex Exponential Modulation ... simpler mathematics, doesn't directly describe real-world cases
- 2. Real Sinusoid Modulation... mathematics a bit more complicated, directly describes real-world cases


Euler's formula connects the two... so you often can use the Complex Exponential form to analyze real-world cases


Complex Exponential Modulation Property: $x(t)e^{j\omega_0 t} \leftrightarrow X(\omega-\omega_0)$

$$x(t)e^{j\omega_0t} \longleftrightarrow X(\omega-\omega_0)$$

Multiply signal by a complex sinusoid

Shift the FT in frequency





Real Sinusoid Modulation

Based on Euler, Linearity property, & the Complex Exp. Modulation Property

$$\mathcal{F}\left\{x(t)\cos(\omega_{0}t)\right\} = \mathcal{F}\left\{\frac{1}{2}\left[x(t)e^{j\omega_{0}t} + x(t)e^{-j\omega_{0}t}\right]\right\}$$

$$= \frac{1}{2}\left[\mathcal{F}\left\{x(t)e^{j\omega_{0}t}\right\} + \mathcal{F}\left\{x(t)e^{-j\omega_{0}t}\right\}\right]$$


$$= \frac{1}{2}\left[X(\omega - \omega_{o}) + X(\omega + \omega_{o})\right]$$
Comp. Exp. Mod.

$$x(t)\cos(\omega_0 t) \leftrightarrow \frac{1}{2} [X(\omega + \omega_0) + X(\omega - \omega_0)]$$
Shift Down Shift Up

$$x(t)\sin(\omega_0 t) \leftrightarrow \frac{j}{2}[X(\omega + \omega_0) - X(\omega - \omega_0)]$$

Visualizing the Result

$$x(t)\cos(\omega_0 t) \leftrightarrow \frac{1}{2} \left[X(\omega - \omega_0) + X(\omega + \omega_0) \right]$$
Shift up Shift down



Interesting... This tells us how to move a signal's spectrum up to higher frequencies without changing the shape of the spectrum!!!

What is that good for??? Well... only <u>high</u> frequencies will radiate from an antenna and propagate as electromagnetic waves and then induce a signal in a receiving antenna....

6. Convolution Property (The Most Important FT Property!!!)

$$y(t) = \int_{-\infty}^{\infty} x(\tau)h(t-\tau)d\tau \quad \Longleftrightarrow \quad Y(\omega) = X(\omega)H(\omega)$$

In the next Note Set we will explore the real-world use of the right side of this result!

7. Parseval's Theorem (Recall Parseval's Theorem for FS!)

$$\int_{-\infty}^{\infty} |x(t)|^2 dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} |X(\omega)|^2 d\omega$$


Energy computed in time domain

Energy computed in frequency domain

$$|x(t)|^2 dt$$
= energy at time t

$$\left| X(\omega) \right|^2 \frac{d\omega}{2\pi}$$
= energy at freq. ω

Convolution Property



Convolution in the time-domain

$$y(t) = h(t) * x(t) = \int_{-\infty}^{\infty} h(\tau)x(t-\tau)d\tau$$

corresponds to **MULTIPLICATION** in the frequency-domain

$$Y(j\omega) = H(j\omega)X(j\omega)$$


Convolution Example

- Bandlimited Input Signal
 - "sinc" function

- Ideal LPF (Lowpass Filter)
 - -h(t) is a "sinc"
- Output is Bandlimited
 - Convolve "sincs"

Ideally Bandlimited Signal


$$x(t) = \frac{\sin(100\pi t)}{\pi t} \quad \Leftrightarrow \quad X(j\omega) = \begin{cases} 1 & |\omega| < 100\pi \\ 0 & |\omega| > 100\pi \end{cases}$$



Convolution Example 1

$$x(t)*h(t) \Leftrightarrow H(j\omega)X(j\omega)$$

$$\frac{\sin(100\pi t)}{\pi t} * \frac{\sin(200\pi t)}{\pi t} = \frac{\sin(100\pi t)}{\pi t}$$



Cosine Input to LTI System

$$Y(j\omega) = H(j\omega)X(j\omega)$$

$$= H(j\omega)[\pi\delta(\omega - \omega_0) + \pi\delta(\omega + \omega_0)]$$


$$= H(j\omega_0)\pi\delta(\omega - \omega_0) + H(-j\omega_0)\pi\delta(\omega + \omega_0)$$

$$y(t) = H(j\omega_0)\frac{1}{2}e^{j\omega_0t} + H(-j\omega_0)\frac{1}{2}e^{-j\omega_0t}$$


$$= H(j\omega_0)\frac{1}{2}e^{j\omega_0t} + H^*(j\omega_0)\frac{1}{2}e^{-j\omega_0t}$$

$$= |H(j\omega_0)|\cos(\omega_0t + \angle H(j\omega_0))$$


Ideal Lowpass Filter



Ideal Lowpass Filter




8. Duality:



Both FT & IFT are pretty much the "same machine": $c \int_{-\infty}^{\infty} f(\lambda) e^{\pm j\lambda \xi} d\lambda$

So if there is a "time-to-frequency" property we would expect a virtually similar "frequency-to-time" property

<u>Illustration:</u> Delay Property:



Other Dual Properties: (Multiply by t^n) vs. (Diff. in time domain)


(Convolution) vs. (Mult. of signals)

Also, this duality structure gives FT pairs that show duality.

Suppose we have a FT table that a FT Pair A... we can get the dual Pair B using the general Duality Property:

- 1. Take the FT side of (known) Pair A and replace ω by t and move it to the time-domain side of the table of the (unknown) Pair B.
- 2. Take the time-domain side of the (known) Pair A and replace t by $-\omega$, multiply by 2π , and then move it to the FT side of the table of the (unknown) Pair B.

Here is an example... We found the FT pair for the pulse signal:



Differentiation in the Time Domain:

$$\frac{dx(t)}{dt} \longleftrightarrow j\omega X(\omega) \tag{5.55}$$

Equation (5.55) shows that the effect of differentiation in the time domain is the multiplication of $X(\omega)$ by $j\omega$ in the frequency domain (Prob. 5.28).

Differentiation in the Frequency Domain:

$$(-jt)x(t) \longleftrightarrow \frac{dX(\omega)}{d\omega}$$
 (5.56)

Equation (5.56) is the dual property of Eq. (5.55).

Alternatively, we can apply the Fourier transform directly to the differential equation [use the differentiation property: $\frac{d^n y}{dt^n} \leftrightarrow (j\omega)^n Y(\omega)$]

Using the Fourier transform, redo Prob. 2.25.

The system is described by

$$y'(t) + 2y(t) = x(t) + x'(t)$$

Taking the Fourier transforms of the above equation, we get

$$j\omega Y(\omega) + 2Y(\omega) = X(\omega) + j\omega X(\omega)$$

$$(j\omega + 2)Y(\omega) = (1 + j\omega)X(\omega)$$

Hence, by Eq. (5.67) the frequency response $H(\omega)$ is

$$H(\omega) = \frac{Y(\omega)}{X(\omega)} = \frac{1+j\omega}{2+j\omega} = \frac{2+j\omega-1}{2+j\omega} = 1 - \frac{1}{2+j\omega}$$

Taking the inverse Fourier transform of $H(\omega)$, the impulse response h(t) is

$$h(t) = \delta(t) - e^{-2t}u(t)$$

Example. Determine the *frequency response function*, $H(\omega)$, for the following <u>stable</u> linear system,

$$\ddot{y}(t) + 3\dot{y}(t) + 2y(t) = f(t)$$

Alternatively, we can apply the Fourier transform directly to the differential equation [use the differentiation property: $\frac{d^n y}{dt^n} \leftrightarrow (j\omega)^n Y(\omega)$] and obtain,

$$[(j\omega)^2 + 3(j\omega) + 2]Y(\omega) = F(\omega)$$

or,

$$H(\omega) = \frac{Y(\omega)}{F(\omega)} = \frac{1}{-\omega^2 + 3j\omega + 2}$$

Example. Determine the zero-state response for the following stable system.


$$f(t) = e^{-t}u(t)$$

$$F(\omega) = \frac{1}{1+j\omega} \longrightarrow \frac{1}{2+j\omega} \longrightarrow y_{z,s}(t)$$

$$y_{zs}(t) = F^{-1} \left\{ \frac{1}{2 + j\omega} \cdot \frac{1}{1 + j\omega} \right\} = F^{-1} \left\{ \frac{1}{1 + j\omega} - \frac{1}{2 + j\omega} \right\}$$
$$y_{zs}(t) = e^{-t}u(t) - e^{-2t}u(t)$$

Application of Modulation Property to Radio Communication

FT theory tells us what we need to do to make a <u>simple</u> radio system... <u>then</u> electronics can be built to perform the operations that the FT theory calls for:





Choose $f_0 > 10$ kHz to enable efficient radiation (with $\omega_0 = 2\pi f_0$)


AM Radio: around 1 MHz FM Radio: around 100 MHz

Cell Phones: around 900 MHz, around 1.8 GHz, around 1.9 GHz etc.

The next several slides show how these ideas are used to make a receiver:







So... what have we seen in this example:

Using the Modulation property of the FT we saw...

- 1. Key Operation at Transmitter is up-shifting the message spectrum:
 - a) FT Modulation Property tells the theory then we can build...
 - b) "modulator" = oscillator and a multiplier circuit
- 2. Key Operation at Recevier—is down-shifting the received spectrum
 - a) FT Modulation Property tells the theory then we can build...
 - b) "de-modulator" = oscillator and a multiplier circuit
 - c) But... the FT modulation property theory also shows that we need filters to get rid of "extra spectrum" stuff
 - i. So... one thing we still need to figure out is how to deal with these filters...
 - ii. Filters are a specific "system" and we still have a lot to learn about Systems...
 - iii. That is the subject of much of the rest of this course!!!