Mathematics and Problem Solving

Lecture 2


Numerical Systems

"He is the master who, after reaching the furthest shores and plumbing the inmost depths of the sea of ultimate knowledge of mathematics, kinematics and spherics, handed over the three sciences to the learned world."

Bhaskara I, of Aryabhata

Overview

- Positional Notation
- Conversion Between Bases
- Binary Arithmetic
- Negative Numbers in Binary



Positional Notation

- Positional notation is a way of writing numbers in some numerical systems
 - Decimal (base 10)
 - Binary (base 2)
 - Octal (base 8)
 - Hexadecimal (base 16)
- A digit's value is dependant on its position
- Numbers are represented as a sequence of digits

Positional Notiation

- Rightmost digit is smallest
 - Units = 1s
- Digits increase in significance to the left

 - Hundreds
 - Thousands
- 4 thousands = $4 \times 1000 = 4 \times 10^3$

| 4 | 3 | 2 | 1 |
|-----------------|-----------------|-----------------|-----|
| 10 ³ | 10 ² | 10 ¹ | 100 |
| 1000 | 100 | 10 | 1 |

Why use diferent bases?

- Decimal (base 10) is the most common human number system
 - A few exceptions:
 - Babylonian
 - Maya
 - Aztec
 - Kaktovik Inupiaq
- Data in a computer is stored and manipulated in binary (base 2)
- If encoding numbers as text, only using 10 symbols is inefficient. Higher bases can be used

Decimal

- Uses ten symbols
 - 0123456789

| 7 | 0 | 6 | 1 |
|------------------------|------------------------|-----------------|-----|
| 10 ³ | 10 ² | 10 ¹ | 10° |
| 1000 | 100 | 10 | 1 |

$$7061$$
= $7x10^3 + 0x10^2 + 6x10^1 + 1x10^0$
= 7061

Binary

- Binary is a numerical system with 2 digits
 - 01

| 0 | 1 | 0 | 0 | 1 | 1 | 0 | 1 |
|-----------------------|-----------------------|-----------------------|----|-----------------------|-----------------------|----------------|------------|
| 2 ⁷ | 2 ⁶ | 2 ⁵ | 24 | 2 ³ | 2 ² | 2 ¹ | 2 ° |
| 128 | 64 | 32 | 16 | 8 | 4 | 2 | 1 |

Binary Numbers

- $00000000_2 = 0$
- $0000001_2 = 1$
- $0000010_2 = 2$
- $00000011_2 = 3$
- $00000100_2 = 4$
- $00000101_2 = 5$

-
- $11111011_2 = 251$
- $11111100_2 = 252$
- $11111101_2 = 253$
- $11111110_2 = 254$
- $11111111_2 = 255$

You can have binary numbers with >8 digits, but 1 byte stores only 8 binary digits

Hexadecimal

| Decimal | Hexadeci mal | Decimal | Hexadeci mal |
|---------|-----------------|---------|-----------------|
| 0 | 0 | 8 | 8 |
| 1 | 1 | 9 | 9 |
| 2 | 2 | 10 | Α |
| 3 | 3 | 11 | В |
| 4 | 4 | 12 | С |
| 5 | 5 | 13 | D |
| 6 | 6 | 14 | Е |
| 7 | 7 | 15 | F |

- Binary uses only 2 different symbols, so it's very long to write out
- Hexadecimal uses the numbers 0-9 and then the letters A-F
- It is also called base 16

Hexadecimal

- We often represent data using hexadecimal to save space
 - 1 byte = 2 x 4 bits
 - 4 bits can store 2⁴ = 16 different symbols
 - 1 byte can be represented by a 2digit hex number

| 4 | E | 0 | 2 |
|-----------------|-----------------|-----------------|-----|
| 16 ³ | 16 ² | 16 ¹ | 16° |
| 4096 | 256 | 16 | 1 |

$$= 4*4096 + 14*256 + 2*1$$

= 19970

Example Hexadecimal Numbers

•
$$0000_{16} = 0$$

• ...

•
$$000A_{16} = 10$$

• ...

• 0010₁₆ = 16

•
$$001F_{16} = 31$$

•

• ...

ASCII

- What if we represented a byte with one character?
- 1 byte = 8 bits = 2^8 = 256 different symbols
 - Base 256
- ASCII
 - 0-31 Control characters
 - 32-126 Printable characters
 - 127-255 Extension to original 7-bit ASCII standard

Logs

- Log is the inverse of exponentiation
 - If $a^{10} = n$, then
 - $\log_{10} n = a$
- Gives the number of digits in a base *b* number *n* (round up)
 - log₅ n
 - $-\log_2 18 = 4.1699...$
 - You'd need 5 binary digits to write 18

Summary


- Data is stored in binary
 - 1 byte = 8 bits \rightarrow 2⁸ = 256 possible values
- Binary is a number system (base 2)
 - A way of representing numbers just like decimal (base 10)
 - Hexadecimal (base 16) is commonly used as well
 - While bytes only store numbers 0-255, number systems can represent any number

Mayan Numbers

Exercise 1:

Translate the following numbers. One is done for you.









Conversion between bases

- To use different bases, we need to be able to convert between them
- Easiest conversions are:
 - Those involving decimal
 - Between bases that are powers of two






Binary to Decimal conversion

Technique

- Multiply each bit by 2ⁿ, where n is the "weight" of the bit
- The weight is the position of the bit, starting from 0 on the right
- Add the results

Binary to Decimal Conversion



Octal to Decimal conversion

- Technique
 - Multiply each bit by 8ⁿ, where n is the "weight" of the bit
 - The weight is the position of the bit, starting from 0 on the right
 - Add the results

Base n to Decimal

Exercise 2:

Convert the following numbers from their bases into decimal

- 1. (1010)2
- 2. (351)8
- 3. (4E)₁₆

Hint:

- Multiply each bit by b^n ,
 - b is the base
 - n is the position of the bit, starting from 0 on the right
- Add the results



Decimal to Binary

- To convert from decimal to binary, we repeatedly divide by 2.
 - Each time, the remainder becomes the next least significant binary digit.
- We divide by 2 because we converting into base 2 (binary).
- In the example, we convert 140 from decimal into binary, getting the answer 10001100.

```
140/2 = 70 r 0
70/2 = 35 r 0
35/2 = 17r1
17/2 = 8 r 1
8/2 = 4 r0
4/2 = 2 r0
2/2 = 1 r0
1/2 = 0 r 1
10001100
```

Decimal to Octal

- To convert from decimal to octal, we repeatedly divide by 8.
 - Each time, the remainder becomes the next least significant binary digit.
- We divide by 8 because we converting into base 8 (octal).

$$17/8 = 2 r 1$$

$$2/8 = 0r2$$

214

Decimal to Hexadecimal

- To convert from decimal to hexadecimal, we repeatedly divide by 16.
 - Each time, the remainder becomes the next least significant binary digit.
- We divide by 16 because we converting into base 16 (hexadecimal).

```
140/16=8r12 (r=C)
8/16=0r8
-----
```

Decimal to base n


Exercise 3:

Convert the following decimal numbers into the given base

- 1. $14 \rightarrow base 2$
- 2. $19 \rightarrow base 6$
- $3. 43 \rightarrow base 12$

• HintL

- To convert from decimal to base n, we repeatedly divide by n
- Each time, add the remainder to the left of the result



Binary to Octal

- Because each octal digit can be 8
 different values, we need 3 binary
 bits to store one octal digit
 - 2³ = 8 (and $\log_2 8 = 4$).
- So to convert binary to octal, we
 - group our bits into triplets
 (threes), starting on the right
 - convert each triplet to its value in hexadecimal.

- Binary: 10 001 100
- Decimal: 2 1 4
- Octal: 214

Binary to Hexadecimal

- Because each hexadecimal digit can be 16 different values, we need 4 binary bits to store it
 - $-2^4 = 16$ (and $\log_2 16 = 4$).
- So to convert binary to hexadecimal
 - we group our bits into quartets (fours)
 - convert each quartet to its value in hexadecimal.

- Binary: 1000 1100
- Decimal: 8 12
- Hexadecimal: 8 C

Convertion to other power of 2 bases

- If we wanted to convert binary to another numerical base that is a power of 2, e.g. 8 or 32, we can group the bits differently, e.g. into 3s or 5s.
- We can reverse the steps to convert from a power of 2 base back to binary

Binary and Power of 2 Bases

Exercise 4:

Convert the following numbers between the given bases

- (0111)₂ → base 8
- $(1001)_2$ → base 16
- (722)₈ → base 2
- $(EFO)_{16} \rightarrow base 2$

Hint:

- Work out how many bits, d, store a single digit of base b
- $-\log_2 b = d$
- $2^{d} = b$



Other conversions

Exercise 5:

Convert the following

- $(E2)_{16} \rightarrow base 8$
- $(72)_8$ → base 16

Hint:

Use binary or decimal as an intermediary



Adding 1 digit binary numbers


- Adding 1 digit binary numbers together is straight forward
 - As easy as 1+1 = 10
- But digital circuits work with 0 and 1, how do we they store the output of 1 + 1?

| A | В | A + B |
|---|---|-----------------|
| 0 | 0 | 0 |
| 0 | 1 | 1 |
| 1 | 0 | 1 |
| 1 | 1 | <mark>10</mark> |

Half Adder

- Store output of 1-bit addition as two bits
 - Sum bit
 - Carry bit
- Allows us to do addition for one position at a time
 - 1 + 1 = 0 (carry 1_2)
- This is the same thing that a half adder does
 - A half adder is a circuit used to add two bits of data together

| A | В | Sum | Carry |
|---|---|-----|-------|
| 0 | 0 | 0 | 0 |
| 0 | 1 | 1 | 0 |
| 1 | 0 | 1 | 0 |
| 1 | 1 | 0 | 1 |




Full Adder

- So really we need to be add three bits together
 - a, b and a carry bit (c_{in})
- A full adder is a circuit used to add two bits of data together
 - Takes in two bits and a carry bit
 - Returns the sum and a carry bit

| A | В | C _{in} | Sum | C _{out} |
|---|---|-----------------|-----|------------------|
| 0 | 0 | 0 | 0 | 0 |
| 1 | 0 | 0 | 1 | 0 |
| 0 | 1 | 0 | 1 | 0 |
| 1 | 1 | 0 | 0 | 1 |
| 0 | 0 | 1 | 1 | 0 |
| 1 | 0 | 1 | 0 | 1 |
| 0 | 1 | 1 | 0 | 1 |
| 1 | 1 | 1 | 1 | 1 |


Full Adder

- To add two 8 bit numbers we need
 - 1 half adder (first bit)
 - 7 full adders (remaining bits)
- Or, if doing it manually
 - Add lowest pair of bits
 - Determine sum and carry
 - From then on, add each pair of bits with previous carry
 - Final carry is overflow



Manual Binary Addition

- Write the two numbers above each other.
- Working from right to left, add the columns of digits, carrying numbers to the next column as required.



Exercise 6:

Add the following binary numbers

- 1. 101 + 111
- 2. 010101 + 01101

• Hint:

- Write the two numbers above each other.
- Working from right to left, add the columns of digits, carrying numbers to the next column as required.



Representing Negative Numbers

- 8 bits can represent 256 positive numbers
 - -0-255
- How do we encode negative numbers?
 - There are no "negative bits" so we cannot store negative values
 - We can treat some range of values as if they are negative values
 - Three common representations in microprocessors
 - Sign and Magnitude
 - One's Compliment
 - Two's Complement ← most modern microprocessors

Representing Negative Numbers

- We need to decide on how to map some range of positive numbers onto the negative numbers
 - i.e. we need a transformation that takes a positive number e.g. 1 and returns the number that represents its additive inverse, i.e. -1
 - For example 1 might map to 255 (which represents -1)
- We want it to
 - Represent as many numbers as possible with the bits available (be efficient)
 - Be able to use the same algorithm/hardware for addition for positive and negative numbers

Sign and Magnitude

- Use the largest bit to represent the sign (+/-), store number with remaining bits
 - if working with n bits, the additive inverse of a number k is
 - $(k + 2^{n-1}) \mod 2^n$
- Equivalent to mapping second half of range to negative numbers
 - 0-127 \rightarrow 0 127
 - $-128-256 \rightarrow -0-127$

$$1000 = -0$$

Red values map to

Sign and Magnitude

- With 8 bits
 - 1 bit sign, 7 bit number
 - -127 → 127 only 255 numbers!
- Inefficient
 - Represents both +0 and -0
- Requires different addition and subtraction algorithm than for unsigned binary

Exercise 7:

What is the value of the following 4-bit signed numbers, stored using sign-and-magnitude

- 1. 1001
- 2. 0011
- 3. 1111
- 4. 1000

Hint:

- Leftmost bit stores sign
- 0 = positive
- 1 = negative

One's Complement

- Here's another idea, instead of inverting a sign bit, invert every bit
- One's complement of
 - 0 is 1
 - 1 is 0
- To get the 1s complement of a binary number, invert every bit
 - 0000 → 1111

One's Complement

- Stores negative numbers as the inverse of the corresponding positive number
 - First digit still gives sign
- Still two Os, only 255 unique numbers
- But notice that values are stored symmetrically

0, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15

Red values map to

Exercise 8:

What is the value of the following 4-bit signed numbers stored using one's complement?

- 1. 1101
- 2. 0010

• Hint:

- One's Complement stores
 negative numbers as the inverse of
 the corresponding positive
 number
- First digit still gives sign



Method of Complements

- A Method of Complements is a way to encode a symmetric range of numbers
 - Make it easy to perform arithmetic
- Examples of Complements
 - Ones Complement
 - Tens Complement
 - Twos Complement
- A number and its **additive inverse** make a compliment
 - e.g. Ten's Complement is the number you add to a digit to make 10

Ten's Complement

- Imagine we used ten's complement to encode a symmetric range of positive and negative numbers
 - 0, 1, 2, 3, 4, 5, 6, 7, 8, 9
 - 0, 1, 2, 3, 4, 5, -4, -3, -2, -1
- Addition works, observe:
 - -3+6=9
 - $-3+\overline{-4}=-1$

- Ten's compliment of
 - 0 is 0 (*overflow)
 - 1 is 9
 - 2 is 8
 - 3 is 7
 - 4 is 6
 - 5 is 5

Ten's Complement

- The ten's complement of y with n decimal digits is
 - $10^{n} y$
- Again observe, with 2 decimal digits
 - 72 + 33 \equiv 105 \equiv 5 (mod 10²)
 - $-72 \equiv -(10^2 72) \equiv -28 \pmod{10^2}$
 - $-28 + 33 \equiv 5$

- For example,
 - with 1 decimal digits, the tens complement of 8 is
 - 10 8 = 2
 - with 2 decimal digits, the tens complement of 64 is
 - 100 64 = 36
 - with 3 decimal digits, the tens compliment of 268 is
 - 1000 268 = 732

Exercise 9:

What is the ten's complement of the following (using number of digits shown?

- 1. 2
- 2. 57
- 3. 9999

Which of the above represent negative numbers?

• Hint:

 Tens complement of an n digit number y is 10ⁿ - y

Radix Complement

• In general, the radix compliment* of an n digit number y, in radix b, is

$$b^n - y$$

 So to calculate the radix compliment of the base 8 number 274 using 4 digits (i.e. the Eight's Compliment)

```
8^4 - 274
```

$$=4096 - 274$$

$$= 3822$$

Twos Compliment

- Binary has a radix of 2, so it's the Two's Compliment
- For *n* bits, the Two's Compliment of a number *y* is

$$2^n - y$$

or in other words the number you add to get 2ⁿ

- Using 1 bit (2¹)
 - 0 is 0 (*overflow)
 - 1 is 1
- Using 2 bits (2²)
 - 0 is 0 [0/0] (*overflow)
 - -1 is 3[1/-1]
 - 2 is 2 [2 / 2]
 - -3 is 1[-1/1]

Twos Complement Example

- We're working with 8 binary bits (radix 2). We can store numbers 0-255
- Our formula for radix compliment was

$$b^n$$
 -y

To store -25, we find

$$2^8 - 25$$

So we can encode the additive inverse of 25 as 231

Twos Complement in Binary

- With 8 bits, the Twos Compliment of 25 is 231
- With the same numbers in binary, the Twos Compliment of
 - (00011001)₁₀ is
 - **(11100111)**₁₀
- Note how similar it looks to the One's Compliment
 - Flip every bit (= One's Compliment)
 - Add 1

Diminished Radix Complement

 One's compliment is a diminished radix complement, which is the same as the radix compliment minus 1

$$(b^n - 1) - y$$

- Observe that $b^n 1$ is the largest digit repeated n times, e.g.
 - $-10^3 1 = (999)_{10}$
 - $-2^8-1=(111111111)_2$
- One's compliment in binary is like 9's complement in decimal
 - Find the complement of each digit with b 1

Finding the Twos Complement

- So, an easy way to find the Twos Complement of a binary number is to
 - Replace each bit with its one's complement
 - i.e. its complement with b-1, where b=2
 - i.e. the diminished radix complement, $(b^n 1) y$
 - i.e. flip each bit
 - Add 1
 - To get the radix complement (bⁿ y)

Finding the Twos Complement

Exercise 10:

Find the twos complement of the following 4-bit numbers.

- 1. 0101
- 2. 1101
- 3. 0001


Which of the above represent negative numbers?

• Hint:

- Replace each bit with its one's complement (i.e. flip each bit)
 - = diminished radix complement $(b^n 1) y$
- Add 1
 - = radix complement bⁿ -y

Negative Numbers, Summary

- By representing negative numbers symmetrically using the Method of Complements, we get nice arithmetic properties
- Using Twos complement we can:
 - Store 256 different values (with 8 bit numbers)
 - Don't have two 0s
 - Add/Subtract signed and unsigned values using the same algorithm/hardware



Binary Subtraction

- We've already covered the complexity of binary subtraction
- By encoding negative values using Two's Complement, we can perform sutraction with the same method as addition
 - Recognise that instead of subtracting a positive number, we can add its additive inverse

$$A - B = A + (-B)$$

- So a subtraction (A B) is a two stage process
 - Find the twos complement of B
 - Add the two's complement of B to A

Manual Binary Subtraction

- 0101 0101 (storing numbers as 4 bits),
 - find the twos compliment of 0101
 - \bullet = 1010 + 1 = 0011
 - Add 0101 to this value
 - 0101 + 0101 = 10000
 - As we're only storing 4 bits, we dispose of the overflow, leaving
 - 0000 = 0

Exercise 11:

Solve the following binary subtraction

1. 0101 - 1100

Hint:

- A B = A + (-B)
- Find the twos complement of the second number (flip each bit and add 1)
- Add the first and second numbers together



Binary Multiplication

- To explain multiplication, we need to know 3 things
 - Multiplication of 1 bit values
 - Super simple!
 - Multiplication by 2ⁿ
 - Like multiplying by powers of 10 in decimal
 - That multiplication distributes over addition
 - a(b + c) = ab + ac
 - i.e. we can break a number into parts, multiply each part, then add it together at the end

Multiplication of 1 Bit Values

| А | В | АхВ |
|---|---|-----|
| 0 | 0 | 0 |
| 0 | 1 | 0 |
| 1 | 0 | 0 |
| 1 | 1 | 1 |

 Multiplying 1-bit binary numbers is easy, as shown in the table

Multiplication by 2ⁿ

- Multiplying any number by 1 is straightforward
 - -1k=k
- Multiplying any number by 2ⁿ is the same as above, with a left shift of n
 - $2^n k = k << n$

| 10 1 | X | 101 1 | X |
|----------|---|-------------------|---|
| 10 | | 101 | |
| 11 10 | X | 11 100 | X |
| 110 | | $\overline{1100}$ | |

Multiplication distributes over addition

- A number *k* can be expressed as a sum of powers of 2, e.g. (in binary)
 - -11 = 10 + 1
 - 1011 = 1000 + 10 + 1
 - k = a + b + ...
 - Express second operand like this
 - 11 = 10 + 1
- Multiplication distributes over addition
 - nxk = n(a+b+...) = na + nb + ...
 - 10 x 11 = 10 (10+1) = 10 x 10 + 10 x 1 = 110

Multiplication in Computers

- Multiplication by 2ⁿ can be implemented as a bit shift
- Multiplication by all other numbers can be implemented as a series of shifts followed by addition

```
1110

x 1011

1110

11100

00000

1110000
```

10011010

Exercise 12:

Following the example of 1110 x 1011 (right), solve the following binary multiplication

1. 10101 x 10110

10011010

1110000



Division Terminology

- Dividend ÷ Divisor = Quotient r. Remainder
- For example,
 - $-7 \div 3 = 2 \text{ r. } 1$
 - Dividend = 7, Divisor = 3, Quotient = 2, Remainder = 1
 - $-18 \div 4 = 4 \text{ r. } 2$
 - Dividend = 18, Divisor = 4, Quotient = 4, Remainder = 2

Long Division in Decimal


- Arrange numbers, e.g. for 144 ÷ 2
- Work from left of dividend
 - Do 12s go into 1? No.
 - Do 12s go into 14? Yes, once, remainder 2 (=20)
- What's left? We've still got that 4, so bring it down. Continue working across 24
 - Do 12s go into 24? Yes, twice
- No remainder (or remainder < 12), so stop.

Long Division in Decimal

- Align the divisor, D, with the most significant end of the dividend (= left)
- Let the "aligned" part of the dividend be X
- If X > D
 - The quotient digit becomes $X \div D$
 - Subtract D from X
- Else quotient digit is 0
- Repeat with D shifted one digit to the right

Division in Binary


- Align the divisor with the most significant end of the dividend (=left)
- Let the portion of the dividend from its MSB to its bit aligned with the LSB of the divisor be denoted X
- Compare X and Y.
 - a) If X >= Y, the quotient bit is 1 and perform the subtraction X-Y.
 - b) If X < Y, the quotient bit is 0 and do not perform any subtractions.
- Shift Y one bit to the right and go to step 2.



Exercise 13:

Following the example of 110101 ÷ 111 (right), solve the following binary division:

1. 10101 ÷ 10





Summary

- Number Systems, using Positional Notation
 - Decimal (base 10)
 - Binary (base 2)
 - Octal (base 8)
 - Hexadecimal (base 16)
- Method of Complements to symmetrically encode negative numbers
- Binary Arithmetic
 - Addition (+ Subtraction with Twos Complement)
 - Multiplication
 - Division