cinoptions - VIM Documentation

Bruce Dearing 100036623 Acadia University 036623d@acadiau.ca

November 21, 2013

cinoptions-values The 'cinoptions' option sets how Vim performs indentation. In the list below, N represents a number of your choice (the number can be negative). When there is an 's' after the number, Vim multiplies the number by 'shiftwidth': 1s is 'shiftwidth' 2s is two times 'shiftwidth', etc. You can use a decimal point, too: "-0.5s" is minus half a 'shiftwidth'. The examples below assume a 'shiftwidth' of 4.

>N Amount added for "normal" indent. Used after a line that should increase the indent (lines starting with "if", an opening brace, etc.). (default 'shiftwidth').

cino=	cino=>2	cino=>2s
if (cond)	if (cond)	if (cond)
{	{	{
foo;	foo;	foo;
}	}	}

eN Add N to the prevailing indent inside a set of braces if the opening brace at the End of the line (more precise: is not the first character in a line). This is useful if you want a different indent when the '{' is at the start of the line from when '{' is at the end of the line. (default 0).

```
cino=
                   cino=e2
                                    cino=e-2
  if (cond) {
                     if (cond) {
                                      if (cond) {
                            foo;
      foo;
                                         foo;
  }
                                      }
                     }
  else
                     else
                                      else
                     {
  {
                                       {
      bar;
                          bar;
                                           bar;
  }
```

nN Add N to the prevailing indent for a statement after an "if", "while", etc., if it is NOT inside a set of braces. This is useful if you want a different indent when there is no '{' before the statement from when there is a '{' before it. (default 0).

```
cino= cino=n2 cino=n-2
if (cond) if (cond) if (cond)
  foo; foo; foo;
else else else
{
```

bar; bar; bar;
}

fN Place the first opening brace of a function or other block in column N. This applies only for an opening brace that is not inside other braces and is at the start of the line. What comes after the brace is put relative to this brace. (default 0).

 $\{{f N}\ \ {
m Place}\ {
m opening}\ {
m braces}\ {
m N}\ {
m characters}\ {
m from}\ {
m the}\ {
m prevailing}\ {
m indent.}\ {
m This}\ {
m applies}\ {
m only}\ {
m for}\ {
m opening}\ {
m braces}\ {
m that}\ {
m are}\ {
m inside}\ {
m other}\ {
m braces}.\ ({
m default}\ 0).$

N Place closing braces N characters from the matching opening brace. (default 0).

^N Add N to the prevailing indent inside a set of braces if the opening brace is in column 0. This can specify a different indent for whole of a function (some may like to set it to a negative number). (default 0).

```
cino=^-2
                                          cino=^-s
cino=
  func()
                       func()
                                            func()
                        {
                                            {
  {
      if (cond)
                          if (cond)
                                            if (cond)
      {
                          {
                                            {
                              a = b;
                                                 a = b;
                          }
  }
                       }
                                            }
```

LN Controls placement of jump labels. If N is negative, the label will be placed at column 1. If N is non-negative, the indent of the label will be the prevailing indent minus N. (default -1).

```
cino=
                      cino=L2
                                             cino=Ls
  func()
                         func()
                                                func()
  {
                         {
                                                {
                              {
                                                         stmt;
           stmt;
                                  stmt;
  LABEL:
                               LABEL:
                                                    LABEL:
                             }
                                                    }
  }
                                                }
                         }
```

:N Place case labels N characters from the indent of the switch(). (default 'shiftwidth').

=N Place statements occurring after a case label N characters from the indent of the label. (default 'shiftwidth').

1N If N != 0 Vim will align with a case label instead of the statement after it in the same line.

bN If N != 0 Vim will align a final "break" with the case label, so that case..break looks like a sort of block. (default: 0). When using 1, consider adding "0=break" to cinkeys.

```
cino=b1
cino=
  switch (x)
                       switch(x)
  {
                       {
      case 1:
                           case 1:
           a = b;
                               a = b;
           break;
                           break;
      default:
                           default:
          a = 0;
                               a = 0;
           break;
                           break;
  }
                       }
```

gN Place C++ scope declarations N characters from the indent of the block they are in. (default 'shiftwidth'). A scope declaration can be "public:", "protected:" or "private:".

hN Place statements occurring after a C++ scope declaration N characters from the indent of the label. (default 'shiftwidth').

 \mathbf{pN} Parameter declarations for K&R-style function declarations will be indented N characters from the margin. (default 'shiftwidth').

```
cino= cino=p0 cino=p2s
func(a, b) func(a, b) func(a, b)
int a; int a; int a;
char b; char b; char b;
```

tN Indent a function return type declaration N characters from the margin. (default 'shiftwidth').

iN Indent C++ base class declarations and constructor initializations, if they start in a new line (otherwise they are aligned at the right side of the ':'). (default 'shiftwidth').

 $+{\bf N}$ Indent a continuation line (a line that spills onto the next) inside a function N additional characters. (default 'shiftwidth'). Outside of a function, when the previous line ended in a backslash, the 2 * N is used.

cN Indent comment lines after the comment opener, when there is no other text with which to align, N characters from the comment opener. (default 3).

CN When N is non-zero, indent comment lines by the amount specified with the c flag above even if there is other text behind the comment opener. (default 0).

/N Indent comment lines N characters extra. (default 0).

(N When in unclosed parentheses, indent N characters from the line with the unclosed parentheses. Add a 'shiftwidth' for every unclosed parentheses. When N is 0 or the unclosed parentheses is the first non-white character in its line, line up with the next non-white character after the unclosed parentheses. (default 'shiftwidth' * 2).

uN Same as (N, but for one level deeper. (default 'shiftwidth').

UN When N is non-zero, do not ignore the indenting specified by (or u in case that the unclosed parentheses is the first non-white character in its line. (default 0).

wN When in unclosed parentheses and N is non-zero and either using "(0" or "u0", respectively, or using "U0" and the unclosed parentheses is the first non-white character in its line, line up with the character immediately after the unclosed parentheses rather than the first non-white character. (default 0).

WN When in unclosed parentheses and N is non-zero and either using "(0" or "u0", respectively and the unclosed parentheses is the last non-white character in its line and it is not the closing parentheses, indent the following line N characters relative to the outer context (i.e. start of the line or the next unclosed parentheses). (default: 0).

mN When N is non-zero, line up a line starting with a closing parentheses with the first character of the line with the matching opening parentheses. (default 0).

```
cino=(s
                       cino=(s,m1)
  c = c1 && (
                         c = c1 && (
                             c2 ||
      c2 ||
      сЗ
                             с3
      ) && c4;
                         ) && c4;
  if (
                         if (
      c1 && c2
                             c1 && c2
     )
                         )
      foo;
                             foo;
```

MN When N is non-zero, line up a line starting with a closing parentheses with the first character of the previous line. (default 0).

)N Vim searches for unclosed parentheses at most N lines away. This limits the time needed to search for parentheses. (default 20 lines).

- *N Vim searches for unclosed comments at most N lines away. This limits the time needed to search for the start of a comment. (default 70 lines).
- **#N** When N is non-zero recognize shell/Perl comments, starting with '#'. Default N is zero: don't recognizes '#' comments. Note that lines starting with # will still be seen as preprocessor lines.

The defaults, spelled out in full, are:

```
cinoptions=>s,e0,n0,f0,\{0,\}0,^0,L-1,:s,=s,10,b0,gs,hs,ps,ts,is,+s,c3,C0,/0,(2s,us,U0,w0,W0,m0,j0,J0,)20,*70,#0
```

Vim puts a line in column 1 if: - It starts with '#' (preprocessor directives), if cinkeys contains '#'. - It starts with a label (a keyword followed by ':', other than "case" and "default") and 'cinoptions' does not contain an 'L' entry with a positive value. - Any combination of indentations causes the line to have less than 0 indentation.