Key Commands

- Key Commands
 - General
 - Process management
 - Resource management
 - Scheduling tasks
 - Shared libraries
 - Logging
 - Configure a logging server
 - Configure the client
 - Users and Groups
 - Primary files
 - Commands
 - Shell and login scripts
 - PAM
 - Package management
 - Source packages
 - Date and time
 - Chrony
 - Systemd management
 - Services
 - Run levels/targets
 - Networking
 - Networking config
 - IP Forwarding
 - Firewall
 - IP Masquerading
 - Port forwarding

- Tunnels
- o DHCP
 - Client
 - Server
- o DNS
 - Client
 - Server
 - Options
 - Create a forward lookup zone
- o LDAP
 - Client
- Kerberos
 - Server
 - Client
 - Enable in SSH
- Filesystem management
 - ACLs
- SELinux
 - Manage policies and contexts
 - Example of configuring SELinux for Squid
- Storage management
 - Mounting a filesystem
 - fstab
 - Storage devices
 - Partitioning
 - XFS
 - System Storage manager
 - RAID
 - iSCSI block storage server
 - Server

- Client
- NFS
- AutoFS
- CIFS
- o GRUB
- o PXE Boot
 - DHCP
 - PXE Boot menu
- Services
 - FTP
 - MariaDB
 - HTTP
 - SSL
 - PHP
 - Mail
 - SMTP Relay
 - IMAP

General

Command	Description
man -k iscsi	Searches short descriptions
man -K iscsi	Full search
<pre>find /usr/share/doc -type f -name *.html</pre>	Find all HTML files in the dir
grep volume README	Searches for the word "volume" in the README file
grep -i volume README	Case-insensitive search for the word "volume" in the README file
diff README README.2	Diff two files
wdiff README README.2	Diff two files

Process management

Command	Description
kill -l	Lists all kill signals
ps -F -p \$(pgrep sshd)	Process details for sshd
pmap 1404	Memory map of the requested process
pgrep fail2ban	Get process ID for specified term
pkill sleep	Kill all sleep processes
nice	Current process's priority
ps -1	Lists processes and their priority
nice -n 19 sleep 1000	Starts a low-priority process
renice -n 0 1393	Changes the priority of an existing process
renice -n 10 \$(pgrep sleep)	Changes the priority of an existing process

Notes:

- Nice value range: -20 (high) to +19 (low)
- Regular users can only use nice values >=0
- Default priority set in /etc/security/limits.conf
 - Set in /etc/security/limits.d/

Resource management

Command	Description
top	Activity monitor
free	Memory resources
pwdx \$(pgrep squid)	Working directory for the process (from /proc/ <id>/cwd)</id>
uptime	System uptime
cat /proc/loadavg	Load average
lscpu	Lists the CPUs in the system
vmstat	Virtual memory stats
iostat -m 5 3	CPU and IO stats
pidstat -p 1614 5 3	Stats for a specific process
mpstat 5 3	Per-CPU stats

sysstat

Package: sysstat Configuration: /etc/sysconfig/sysstat

Command	Description
sar	sysstat reporting tool
sar -A	All stats
sar -n ALL	All networking stats
sar -s 14:50:00 -e 15:10:00	Limit to a time period

Notes:

• /etc/cron.d/sysstat is created to compile reports

Scheduling tasks

- cron: Schedules jobs
 - Configuration: /etc/crontab
- anacron: Handles systems not running 24x7
 - o Configuration: /etc/anacrontab
- at: Used for one-off jobs and batches
 - o atq lists queued jobs
 - o atrm removes a job

Shared libraries

Command	Description	
ldd /usr/bin/ls	Lists the shared libraries used by the ls command	
ldconfig -p	Display the linker cache	

Add new library locations to a file in /etc/ld.so.conf.d or add to \$LD_LIBRARY_PATH

Logging

Configuration:

- /etc/rsyslog.conf
- /etc/rsyslog.d

Configure a logging server

Enable SELinux and the firewall for syslog to listen on port 10514:

```
semanage port -a -t syslogd_port_t -p tcp 10514
semanage port -l|grep syslogd
firewall-cmd --zone=lab-internal --add-port=10514/tcp --permanent
firewall-cmd --reload
```

Configure the port in /etc/rsyslog.conf by including the following line:

```
$template TmplAuthpriv, "/var/log/remote/auth/%HOSTNAME%
/%PROGRAMNAME:::secpath-replace%.log"
$template TmplMsg, "/var/log/remote/msg/%HOSTNAME%/%PROGRAMNAME:::secpath-replace%.log"

$ModLoad imtcp

# Adding this ruleset to process remote messages
$RuleSet remote1
authpriv.* ?TmplAuthpriv
*.info;mail.none;authpriv.none;cron.none ?TmplMsg
$RuleSet RSYSLOG_DefaultRuleset #End the rule set by switching back to
the default rule set
$InputTCPServerBindRuleset remote1 #Define a new input and bind it to the
"remote1" rule set
$InputTCPServerRun 10514
```

Restart rsyslog

Configure the client

Configure the logserver in /etc/rsyslog.conf by including the following line:

```
*.* @@172.16.1.1:10514
```

Users and Groups Primary files

- /etc/passwd local users
- /etc/shadow local user passwords
- /etc/group local groups
- /etc/gshadow local group passwords
- /etc/nsswitch.conf Name Service Switch config file
- /etc/profile.d/ profile scripts
- /etc/skel Home directory template
- /etc/login.defs
 Login defaults such as password config
- /etc/default/useradd Defaults for new users

Commands

Command	Description
getent	Gets entries from the administrative database
getent passwd penguin	passwd entry for the requested user
id	Info about current user
id penguin	Info about specified user
useradd	Create a user
usermod	Modify a user
userdel	Delete a user
groupadd	Create a group
chsh	Change user shell
chmod g+s <file dir=""></file>	Set the Group ID (SGID)

Shell and login scripts

- profile scripts are used at login and should include environment settings.
 - O /etc/profile
 - O /etc/profile.d
 - 0 ~/.bash_profile

- bashrc scripts are executed for interactive non-login shells. The profile scripts will generally call bashrc scripts.
 - O /etc/bashrc
 - O ~/.bashrc
- logout scripts are executed at logout
 - O ~/.bash_logout

PAM

Configuration:

- /etc/pam.d/
- /etc/security/
 - o Password quality: /etc/security/pwquality.conf
 - Limit resource access (ulimit): /etc/security/limits.conf

Various PAM modules are available in /lib64/security

Can use authconfig:

```
authconfig --savebackup=/backups/authconfigbackup20170701

authconfig --passminlen=9 --passminclass=3 --passmaxrepeat=2

--passmaxclassrepeat=2 --enablerequpper --enablereqother --update
```

Package management

- Yum repositories: /etc/yum.repos.d
- Cache: /var/cache/yum/

Command	Description
rpm -V nmap	Verify a package
rpm -qf /etc/hosts	Query the package that installed a resource
yum repolist	List Yum repos
yum list installed	List all installed packages
yum whatprovides lsof	Lists the package providing a file/app (e.g. lsof)
yum update kernel	Update the kernel

Source packages

Download and compile from source:

```
yum install yum-utils ncurses-devel bzip2 gcc
yumdownloader --source zsh
cd rpmbuild/SOURCES/
tar -xjf zsh-5.0.2.tar.bz2
cd zsh-5.0.2/
./configure
make
make install
```

Date and time

Command	Description
timedatectl	Get current date/time info
timedatectl list-timezones	List all timezones
timedatectl set-timezone time_zone	Set the timezone

Chrony

• Package: chrony

• Service: chronyd

• Configuration: /etc/chrony.conf

• Sample time server entry: server 0.centos.pool.ntp.org iburst

Command	Description
chronyc	CLI for Chrony config
chronyc tracking	Current time tracking stats
chronyc sources	Details of time sources

Systemd management Services

Command	Description
systemctl start httpd	Start the service
systemctl stop httpd	Stop the service
systemctl enable httpd	Enable the service to start at boot

Run levels/targets

Now called targets in Systemd

Command	Description
runlevel	Get the current run level
systemctl get-default	Gets the default target
systemctl set-default multi-user.target	Sets the default target
systemctl isolate rescue.target	Changes the current run level

To change at boot time:

- 1. In the Grub menu, press e to edit
- 2. At the end of the Linux16 line, append systemd.unit=rescue.target
- 3. Login as root
- 4. If you need to edit anything: mount -o remount, rw /

Networking

Configuration:

- /etc/sysconfig/network-scripts/
- /etc/hosts local static lookups
- /etc/hostname the hostname
- /etc/nsswitch.conf name service switching
- /etc/resolv.conf resolver config

Command	Description
hostnamectl	Current hostname
hostnamectl set-hostname router.lab.example.com	Set hostname
ip a s	IP details for all network devices
ip a s enp0s3	IP details for the specified network device
ip link show enp0s3	Device info
ethtool enp0s3	Network driver info
ls /sys/class/net/	Lists all networking devices
netstat -t	All active connections
netstat -tulpn	Lists all ports and backing processes
watch -n 5 -x netstatinterfaces	Handy network activity monitor
nmap router.lab.example.com	Port scanner
iptableslist	Lists all rules for all chains

Networking config

Command	Description
ip addr add 172.17.67.3/16 dev enp0s8	Temporarily add the IP address

IP Forwarding

To enable IP Forwarding edit [/etc/sysctl.conf] to feature:

```
net.ipv4.ip_forward = 1
```

Load the changes with:

sysctl -p

Firewall

Command	Description
firewall-cmdstate	Current firewall state
firewall-cmdreload	Sets config and reloads
firewall-cmdget-services	Lists all pre- canned services known to the firewall
firewall-cmdget-zones	Lists all defined zones
firewall-cmdlist-allzone=lab-internal	Get details on a zone
firewall-cmdadd-service=sshpermanentzone=lab-internal	Adds the ssh service to the firewall

Advanced language help: man 5 firewalld.richlanguage

IP Masquerading

```
firewall-cmd --zone=external --add-masquerade --permanent --zone=lab-dmz
firewall-cmd --reload

#Check:
firewall-cmd --permanent --query-masquerade --zone=lab-dmz
```

Note: This will also configure IP Forwarding

Port forwarding

```
firewall-cmd --permanent --zone=lab-dmz --add-forward-
port=port=80:proto=tcp:toaddr=172.16.100.50:toport=8080
```

Tunnels

Listen locally on 2222 and tunnels to 172.16.1.50, then calling into port 22:

```
ssh -f -L 2222:localhost:22 ansible@172.16.1.50 -N
```

DHCP

Client

• Package: dhclient

Configure the appropriate /etc/sysconfig/network-scripts/ifcfg- file with:

```
BOOTPROTO="dhcp"
```

Server

- Package: dhcp
- Configuration: /etc/dhcp/dhcpd.conf
- Leases: /var/lib/dhcpd/dhcpd.leases

Example config:

```
option domain-name "lab.example.com";
option domain-name-servers ns.lab.example.org;
shared-network lab {
 option subnet-mask 255.255.255.0;
 option domain-search "lab.example.com";
 option domain-name-servers 172.16.1.1;
 option time-servers 172.16.1.1;
 next-server 172.16.1.1;
  filename "pxelinux.0";
# The Internal subnet
  subnet 172.16.1.0 netmask 255.255.255.0 {
    option routers 172.16.1.1;
    range 172.16.1.100 172.16.1.199;
    #option auto-proxy-config " http://proxy.lab.example.com/proxy
/proxy.pac";
    host canary {
     option host-name "canaryinternal.lab.example.com";
     hardware ethernet 08:00:27:c7:13:9e;
     fixed-address 172.16.1.50;
    }
  }
}
```

Check the configuration: dhcpd -t -cf /etc/dhcp/dhcpd.conf

DNS

Client

• Configuration:

O /etc/resolv.conf

Configure the appropriate /etc/sysconfig/network-scripts/ifcfg- file with:

```
PEERDNS=no
DNS1=
DNS2=
```

Or via DHCP.

Server

- Packages: bind bind-utils
- Configuration:
 - /etc/named.conf primary configuration
 - o /var/named configuration items
- Log: /var/named/data/named.run
- Samples: /usr/share/doc/bind-9.9.4/sample/

Options

Command	Description
listen-on port 53 { 172.16.1.1; 127.0.0.1; };	Sets port and host address
allow-query { 172.16.0.0/16; 127.0.0.1; };	The hosts the server will respond to
recursion yes;	Provides a caching server
forwarders {8.8.8.8; 8.8.4.4}; forward only;	Configure forwarding

Create a forward lookup zone

Add to /etc/named.conf:

```
zone "lab.example.com." {
   type master;
   file "named.lab";
   allow-update { none; };
};
```

Then in /var/named/named.lab:

```
$TTL 3H
$ORIGIN lab.example.com.
lab.example.com. IN SOA router.lab.example.com. root.lab.example.com. (
    1 ; serial - increment this on changes
    1D; refresh
    1H ; retry
    1W; expire
    3H); minimum
lab.example.com. NS router.lab.example.com.
router A 172.16.1.1
time CNAME router
centos-mirror CNAME router
mirror CNAME router
proxy CNAME router
mail CNAME router
lab.example.com. MX 10 mail.lab.example.com
canaryinternal A 172.16.1.50
canarydmz A 172.16.100.50
```

Validate:

- named-checkzone lab.example.com named.lab
- named-checkconf

LDAP

Client

- Packages: openIdap-clients nss-pam-ldapd
- Configuration: etc/nsswitch.conf

Configuration:

```
# Enable a user's home dir to be created ad-hoc:
authconfig --enablemkhomedir --update

# Configure LDAP for use User Information and/or Authentication
authconfig-tui
```

Command	Description
<pre>ldapsearch -x -b 'dc=lab,dc=example,dc=com' '(uid=penguin)'</pre>	Search for a
Tuapsearen -x -b uc-rab, uc-example, uc-com (uru-pengurn)	user

Kerberos

Make sure time services are correctly configured.

Server

Configure a Kerberos server via kadmin and kadmin.local

Command	Description
listprincs	List principals
addprinc root/admin	Add the root principal with admin rights
addprinc penguin	Add a normal user
addprinc -randkey host/server2.lab.example.com ktadd host/server2.lab.example.com	Add a server prinipal

Client

- Packages: krb5-workstation pam_krb5
- Configuration:
 - O /etc/krb5.conf
 - O Use authconfig-tui to setup Authentication

In order to get keys and access systems:

Command	Description
kinit	Get a ticket
klist	List current tickets
kdestroy	Removes the ticket

Enable in SSH

Set the following to yes and systemeth reload sshd:

- GSSAPIAuthentication
- GSSAPIDelegateCredentials

Then:

authconfig --enablekrb5 --update

Filesystem management ACLs

Command	Description
getfacl test.txt	List ACLs
setfacl -m u:puffin:r test.txt	Grant read to the puffin user
setfacl -m g:birds:rw test.txt	Grant read/write to the birds group
setfacl -x g:birds test.txt	Removes access from the birds group
setfacl -b test.txt	Removes all ACLs

SELinux

Configuration:

- /etc/selinux/config
- /etc/selinux/targeted/contexts/

Packages:

- setools
- setools-console
- policycoreutils-python
- setroubleshoot
- selinux-policy-doc

Command	Description
ls -Z	List files with their SELinux context
ls -dZ /var/spool/squid	Directory context
ps axZ	List processes with their SELinux context
id -Z	User context
sestatus	SELinux status
getenforce	SELinux mode
setenforce 0	Set to permissive
seinfo	Policy query
ausearch -m avc	SELinux alerts in the audit log

Manage policies and contexts

Command	Description
chcon	Changes a file's security context - only lasts until next restore
restorecon	Restores a file's context to the default
getsebool -a	Lists all boolean config
setsebool -P samba_export_all_rw 1	Enables Samba to read/write all files
semanage port -1	Port mappings
semanage permissive -a smbd_t	Sets the smbd_t process type to be permissive

Example of configuring SELinux for Squid

Audit log revealed an issue in permissive mode:

```
time->Sat Mar 24 14:18:27 2018

type=PROCTITLE msg=audit(1521865107.759:118):

proctitle=2873717569642D3129002D66002F6574632F73717569642F73717569642E636F6E6

type=SYSCALL msg=audit(1521865107.759:118): arch=c000003e syscall=2

success=yes exit=18 a0=55c2f9f7ce40 a1=641 a2=1a4 a3=64697571732f6c6f

items=0 ppid=1603 pid=1605 auid=4294967295 uid=23 gid=23 euid=23 suid=0

fsuid=23 egid=23 sgid=23 fsgid=23 tty=(none) ses=4294967295 comm="squid"

exe="/usr/sbin/squid" subj=system_u:system_r:squid_t:s0 key=(null)

type=AVC msg=audit(1521865107.759:118): avc: denied { append open } for

pid=1605 comm="squid" path="/var/spool/squid/00/00/000000E5" dev="dm-1"

ino=8766949 scontext=system_u:system_r:squid_t:s0

tcontext=system_u:object_r:unlabeled_t:s0 tclass=file

type=AVC msg=audit(1521865107.759:118): avc: denied { create } for

pid=1605 comm="squid" name="000000E5" scontext=system_u:system_r:squid_t:s0

tcontext=system_u:object_r:unlabeled_t:s0 tclass=file
```

Note that the service context (scontext=system_u:system_r:squid_t:s0) was trying to access the type context (tcontext=system_u:object_r:unlabeled_t:s0 tclass=file).

Some checks:

- Check the squid process with axz | grep squid
- The getsebool squid_connect_any command indicates squid can connect to any port.
- Check the cache dir with 1s -dZ /var/spool/squid
- Look at the file contexts for squid: semanage fcontext --list|grep squid
- man squid_selinux indicated that squid_cache_t is used for cache files

Configure the context:

```
semanage fcontext -a -t squid_cache_t "/var/spool/squid(/.*)?"
restorecon -R -v /var/spool/squid
systemctl restart squid
```

The new entry is in cat /etc/selinux/targeted/contexts/files/file_contexts.local

I could have used semanage permissive -a squid_t but I wanted to be specific.

Storage management

Handy commands:

• lsof: lists open files

Mounting a filesystem

- /mnt is used for temporarily mounting
- /mnt/cdrom is usually a symbolic link

Command	Description
mount	List all currently mounted filesystems
mount /dev/cdrom /mnt/	Mount the CD/DVD to /mnt
umount /mnt	Unmounts the filesystem
eject /dev/cdrom	Ejects (and unmounts) the CD/DVD

fstab

XFS example:

UUID=be9df528-6544-4592-99a8-b3a6d223ed3e /var/ftp/pub/distro xfs defaults 0 0

Storage devices

Command	Description
lsblk	Lists block devices
parted /dev/sdb print	Get the partition details for a device
blkid -o list	Prints block device info, inc fs type and UUID
shred -v /dev/sdb	Deletes the device

Partitioning

Command	Description
parted /dev/sdb	Starts the parted cli for the nominated device
cli: print	Info about the device
cli: mklabel gtp	Sets the disk to use the GUID partition table
cli:	Creates a primary partition with the xfs
mkpart primary xfs 0% 25%	filesystem
cli: rm 1	Removes partition 1
cli: quit	Exits the parted cli

XFS



System Storage manager

Install:

yum install system-storage-manager lvm2

Command	Description
ssm list	Lists info about detected devices, pools, volumes
ssm createfs xfs -s 5G -n centos-distro /dev/sdc1 /dev/sdc2	Creates a new 5Gig logical volume in the default pool (lvm_pool). The pool has 2 physical volumes (/dev/sdc1, /dev/sdc2)
ssm createfs xfs -s 10G -n squid-cache	Creates a new logical volume in the default pool
ssm mount /dev/lvm-pool/centos-distro /mnt	Temporary mount of a logical volume

Example /etc/fstab entry:

/dev/lvm_pool/centos-distro /var/ftp/pub/distro xfs defaults 0 0

RAID

Levels:

- linear spans storage over different sized disks
- Raid 0 same as linear but same size disks
- Raid 1 mirror over 2 disks
- Raid 4-6 data is striped with parity over 3 or more disks

Packages: mdadm

```
Command

mdadm --create /dev/md0 --verbose --level=mirror --raid-devices=2 /dev/sdb13 /
mkfs.xfs /dev/md0

mdadm --create /dev/md1 --level 5 --raid-devices=3 /dev/sdb10 /dev/sdb9 /dev/s
mkfs.xfs /dev/md1

mdadm --detail --scan >> /etc/mdadm.conf

mdadm --stop /dev/md0

mdadm --assemble --scan
```

To add/replace devices:

Command	Description	
<pre>mdadmmanage /dev/md1add-spare /dev/sdb7</pre> mdadmdetail /dev/md1	Adds a spare device	
mdadmmanage /dev/md1replace /dev/sdb9	Drops a disk out	
mdadmdetail /dev/md1	Checks device status in array	
mdadmmanage /dev/md1re-add /dev/sdb9	Adds device back as spare	

Sample fstab entry:

/dev/md1 /data xfs defaults 0 0

iSCSI block storage server

- iSCSI targets are servers that share out block devices
- iSCSI initiators are clients

Server

Packages: targetd targetcli

Run targetcli and configure a target:

backstores/block create mediashare /dev/lvm_pool/mediashare
iscsi/ create iqn.2018-03.com.example.lab.router:media
cd iscsi/iqn.2018-03.com.example.lab.router:media/tpg1/
luns/ create /backstores/block/mediashare
acls/ create iqn.2018-03.com.example.lab.canaryinternal:media
cd /
ls
saveconfig
exit

Client

Packages: iscsi-initiator-utils

Configure the initiator name: /etc/iscsi/initiatorname.iscsi

InitiatorName=iqn.2018-03.com.example.lab.canaryinternal:media

Then access the portal:

```
iscsiadm -m discovery -t st -p 172.16.1.1
```

and connect:

```
iscsiadm -m node -T iqn.2018-03.com.example.lab.router:media -l
iscsiadm --mode node --targetname iqn.2018-03.com.example.lab.router:media -l

# Create a filesystem
mkfs.xfs /dev/sdc
```

To disconnect:

```
iscsiadm -m node -T iqn.2018-03.com.example.lab.router:media -u
```

NFS

```
Packages: nfs-utils Configuration: /etc/exports/ Services: - nfs-server -
```

Sample /etc/exports/ entry:

```
/share/nfs *(ro)
```

Export shares using:

```
exportfs -r
```

Mount the share:

mount -t nfs server2.lab.example.com:/share/nfs /mnt

AutoFS

Package: autofs

Configuration: /etc/auto.misc

Add an automount to /etc/auto.misc:

nfsshare -ro,soft,intr server1.lab.example.com:/share/nfs

This will appear in /misc/nfsshare

CIFS

Package: samba

Prepare a share directory:

mkdir -m 1777 /share

Setup the share in /etc/samba/smb.conf:

[share]

path=/share
writable=yes

Prep the password with smbpasswd -a root

SELinux config:

```
semanage fcontext -a -t samba_share_t '/share(/.*)?'
restorecon -R /share
```

Firewall:

```
firewall-cmd --add-service=samba --permanent
firewall-cmd --reload
```

Connect: smbclient //localhost/share

Mount the share:

```
yum install cifs-utils
mount.cifs //172.16.1.50/share /mnt
```

Or use autofs with an /etc/auto.misc entry:

```
samba -fstype=cifs,rw,noperm,user=root,password=PASSWORD ://172.16.1.50
/share
```

GRUB

- Configuration:
 - O /etc/default/grub
 - O /boot/grub2/grub.cfg
 - O /etc/grub.d/

Command	Description
grubbydefault-kernel	Displays the default kernel
grubbyset-default /boot/ <kernel></kernel>	Change the default
grubbyinfo=ALL	Info for all known kernels
<pre>grubbyinfo /boot/<kernel></kernel></pre>	get info about a specific kernel
<pre>grubbyremove-args="rhgb quiet" -update-kernel /boot/<kernel></kernel></pre>	Change a kernel arg
<pre>grub2-mkconfig -o /boot/grub2/grub.cfg</pre>	Used when changing config files outside

PXE Boot

Packages: syslinux tftp tftp-server

Copy across files:

cp /usr/share/syslinux/pxelinux.0 /var/lib/tftpboot/

cp /usr/share/syslinux/menu.c32 /var/lib/tftpboot/

From, the ISO, also copy vmlinuz and initrd.img

Start the tftp server

```
systemctl start tftp.socket
systemctl enable tftp.socket
```

DHCP

Edit /etc/dhcp/dhcp.conf and in the subnet config, add:

```
next-server <ip of pxe server>;
filename "pxelinux.0";
```

Test the config and restart:

```
dhcpd -t -cf /etc/dhcp/dhcp.conf
systemctl restart dhcpd
```

PXE Boot menu

Configuration file: /var/lib/tftpboot/pxelinux.cfg/default

Example:

```
default menu.32
prompt 0
timeout 1000
ontimeout local

menu title Boot menu

label local
menu Boot from local disk
LOCALBOOT 0
```

Services FTP

Package: vsftpd

Configuration: /etc/vsftpd/vsftpd.conf

Maria DB

Package: mariadb-server

HTTP

Packages: httpd

Firewall:

firewall-cmd --add-service={http,https} --permanent

SSL

Package: httpd

Configuration: /etc/httpd/conf.d/ssl.conf

Create a key and add it:

```
openssl req -new -nodes -x509 -keyout canary.key -out canary.crt
chmod 400 canary.key canary.crt
cp canary.crt /etc/pki/tls/certs/
cp canary.key /etc/pki/tls/private/
```

PHP

Package: httpd mod_php

Configuration: /etc/httpd/conf.d/php.conf

Mail

Package: postfix

Configuration: /etc/postfix/main.cf

Sample MX entry:

```
lab.example.com. MX 10 mail.lab.example.com
```

Aliases in /etc/aliases - run newaliases after edits.

SMTP Relay

On the host mail server:

```
postconf -e inet_protocols=ipv4
postconf -e inet_interfaces=all
postconf -e mydestination=localhost,lab.example.com,router.lab.example.com
systemctl restart postfix

firewall-cmd --add-service=smtp --permanent
firewall-cmd --reload

postconf mynetworks
```

On the client:

```
postconf -e inet_protocols=ipv4
postconf -e inet_interfaces=all
postconf -e relayhost=mail.lab.example.com
postfix check
systemctl restart postfix
```

IMAP

Package: dovecot

Configuration: - /etc/dovecot/conf - /etc/dovecot/conf.d

Firewall:

```
firewall-cmd --add-service={imap,imaps} --permanent --zone=lab-internal
firewall-cmd --reload
```

In /etc/dovecot/dovecot.conf:

```
protocols = imap pop3 lmtp
listen = *
```

In /etc/dovecot/conf.d/10-mail.conf:

```
mail_location = mbox:~/mail:INBOX=/var/mail/%u
```

Add appropriate users to the mail group:

```
usermod -a -G mail puffin
```

Check with mutt:

```
mutt -f imaps://user@hostname/
```