# CS528 SCO and Tuning


A Sahu Dept of CSE, IIT Guwahati

# **Outline**

- Intro to Code Optimization
- Machine independent/dependent optimization
- Common sense of Optimization
  - Do less work, avoid expensive Ops, shrink working set
- Simple measure Large impact : simd, branch, comm sub expre
- C++ Optimization
- Scalar Profiling
  - Manual Instrumentation (get\_wall\_time, clock\_t)
  - Function and line based profiling (gprof, gcov)
  - Memory Profiling (valgrind, callgraph)
  - Hardware Performance Counter (oprofile, likwid)

#### **CSO:** Loop Jamming

```
for(i=0;i<10000;i++) {
    Dostuff(i);//Small Independent work
}
for(i=0;i<10000;i++) {
    DoMorestuff(i); //Small Independent work
}</pre>
```




```
for(i=0;i<10000;i++) {
    Dostuff(i);
    DoMorestuff(i);
}</pre>
```

#### **CSO:** Function Looping

```
for(i=0;i<10000;i++) {
    Func(t,i);
}
Fun (int w, d) {//do lots of stuff}</pre>
```

```
funn(t);
void funn(w) {
  for(i=0;i<10000;i++) {//do lots stuffs}
  }
}</pre>
```

# **CSO: Example: Vector ADT**



vec\_ptr new\_vec(int len)

Create vector of specified length

```
int get_vec_element(vec_ptr v, int
  index, int *dest)
```

- Retrieve vector element, store at \*dest
- Return 0 if out of bounds, 1 if successful

```
int *get_vec_start(vec_ptr v)
```

Return pointer to start of vector data

# **Optimization Example**

- Procedure
  - -Compute sum of all elements of vector
  - -Store result at destination location
  - -What's the Big-O of this code?

```
void combine1(vec ptr v, int *dest) {
  int i;
  *dest = 0;
  for (i=0; i<vec length(v); i++) {</pre>
    int val;
    get vec element(v, i, &val);
    *dest += val;
```

# Move vec length Call Out of Loop

- Value does not change from one iteration to next
- •Code motion, vec\_length requires only constant time, but significant overhead

```
void combine2(vec ptr v, int *dest) {
  int i;
  int length = vec length(v);
  *dest = 0;
  for (i = 0; i < length; i++) {
    int val;
    get vec element(v, i, &val);
    *dest += val;
```

#### **Reduction in Strength**

```
void combine2(vec ptr v, int *dest) {
 int length = vec length(v);
 *dest = 0;
  for (i = 0; i < length; i++) {
    int val;
    get vec element(v, i, &val);
    *dest += val;
```

#### **Reduction in Strength**

```
void combine3(vec_ptr v, int *dest){
  int i;
  int length = vec_length(v);
  int *data = get_vec_start(v);
  *dest = 0;
  for (i = 0; i < length; i++) {
    *dest += data[i];
}</pre>
```

#### **Eliminate Unneeded Memory Refs**

```
void combine4(vec ptr v, int *dest) {
  int i;
  int length = vec length(v);
  int *data = get vec start(v);
  int sum = 0;
  for (i = 0; i < length; i++)
    sum += data[i];
  *dest = sum;
```

# **Code Motion Example #2**

- Procedure to Convert String to Lowercase
  - Extracted from many beginners' C programs
  - (Note: only works for ASCII, not extended characters)

```
void toLower(char *s) {
  int i;
  for (i = 0; i < strlen(s); i++)
    if (s[i]>='A' && s[i]<='Z')
        s[i] -= ('A' - 'a');
}</pre>
```

#### **Optimization Blocker: Procedure Calls**

- Why couldn't the compiler move vec\_len or strlen out of the inner loop?
  - Procedure might have side effects
    - Alters global state each time called
  - Function might not return same value for given arguments
    - Depends on other parts of global state
    - Procedure lower could interact with strlen

#### **Optimization Blocker: Procedure Calls**

- Why doesn't compiler look at code for vec\_len or strlen?
  - Linker may overload with different version
    - Unless declared static
  - Interprocedural optimization is not extensively used, due to cost

#### Warning:

- Compiler treats procedure call as a black box
- Weak optimizations in and around them

# **Profiling for Serial Code**

#### **Profiling for Serial Code**

- Manual Instrumentation (get\_wall\_time, clock\_t)
- Function and line based profiling (gprof, gcov)
- Memory Profiling (valgrind, callgraph)
- Hardware Performance Counter (oprofile,likwid)

#### **Manual Instrumentation**

- System Status
  - \$uptime, \$top , \$vmstat
  - \$systemmonitor, \$gnome-system-monitor
- \$time ./a.out
  - real time/wall clock time
  - cpu time and system time
  - cputime=sys time+usr time
- Using get\_wall\_time, clock\_t

#### **Manual Instrumentation**

\$time command and Using get\_wall\_time,

```
#include <time.h>
int main(){
clock t t; double Etime;
t = clock();
//Do some Work
t = clock() - t;
Etime=((double)t)/CLOCKS PER SEC;
printf("ETime =%f seconds", Etime)
return 0;
```

# **Profiler: Hotspot Analyzer**

- Given a program
- Finding out part of the program which takes maximum amount of time
- Optimizing hot-spot area reduce the execution time significantly
- Suppose a program spend 99% of time in a small function/code
  - Optimizing that code will result better performance

#### Function and line based profiling

- GNU profile (gprof)
  - \$gcc –p test.c
  - \$./a.out
  - \$gprof ./a.out
  - \$gprof ./a.out >FPprofile.txt
- GNU coverage (gcov)

# **Gprof Example**

```
#include <stdio.h>
void FunA() {
  int i=0, q=0;
  while (i++<100000)
   \{ q+=i; \}
void FunB() {
  int i=0, q=0;
  while (i++<400000)
   { q+=i; }
```

```
int main() {
   int iter=5000;
   while (iter--) {
      FunA();
      FunB();
   return 0;
```

# **Gprof Example: Flat Profile**

Flat profile:

```
Each sample counts as 0.01 seconds.
```

```
% cumulative self self total
time seconds seconds calls ms/call ms/call name
80.26 5.55 5.55 5000 1.11 1.11 FunB
20.94 6.99 1.45 5000 0.29 0.29 FunA
```

# **Gprof Example: Call Graph**

```
Call graph
index % time self children called
                        <spontaneous>
[1]
          0.00 6.99
    100.0
                             main [1]
             0.00 5000/5000
                                 FunB [2]
        5.55
        1.45 0.00 5000/5000 FunA [3]
       5.55 0.00 5000/5000
                                 main [1]
[2]
    79.3 5.55 0.00 5000
                               FunB [2]
        1.45 0.00 5000/5000
                                 main [1]
[3]
          1.45 0.00
                      5000
                               FunA [3]
    20.7
```

#### Function and line based profiling

- GNU profile (gprof)
- GNU coverage (gcov)
  - –\$gcc -fprofile-arcs -ftest-coverage tmp.c
  - -\$./a.out
  - -\$gcov tmp.c

File 'tmp.c'

Lines executed:87.50% of 8

Creating 'tmp.c.gcov'

#### **Gcov output**

```
#include <stdio.h>
int main (){
  int i, total;
  total = 0;
  for (i = 0; i < 10; i++)
        total += i;
  if (total != 45)
        printf ("Failure\n");
  else printf ("Success\n");
  return 0;
```

```
-: 1:#include <stdio.h>
  1: 2:int main (){
  -: 3: int i, total;
  1: 4: total = 0;
 11: 5: for (i = 0; i < 10; i++)
 10: 6: total += i;
  1: 7: if (total != 45)
#####:8: printf ("Failure\n");
  1: 9: else printf ("Success\n");
  1: 10: return 0;
  -: 11:}
```

# **Valgrind**

- Free tools: \$sudo apt-get install valgrind
- CallGraph, Profiler, Memory Check...
  - Many more
  - From C code, one can use API of valgrind
- Program analysis tools are useful
  - Bug detectors, Profilers, Visualizers
- Dynamic binary analysis (DBA) tools
  - Analyse a program's machine code at run-time
  - Augment original code with analysis code

#### **Valgrind**

```
void Work1(int n) {
   int i=0, j=0, k=0;
   while(i++<n) {
       while (j++< n) { while (k++< n) ; }
void Work2(int n) { int i=0; while(i++<n);}</pre>
void Maneger(int n1, int n2) {
     Work1(n1); Work2(n2);
void Projects1() { Maneger(1000000, 1000);}
void Projects2() { Maneger(100, 1000000);}
int main() {
  Projects1(); Projects2(); return 0;
```


#### Valgrind: How to use

- \$gcc -pg -o Valgrindtest Valgrindtest.c
- \$valgrind --tool=callgrind ./Valgrindtest
- \$Is

Valgrindtest Valgrindtest.c callgrind.out.11233
\$kcachegrind `ls -tr callgrind.out.\* | tail -1`

pid

# Valgrind: Call Graph



#### **Further Optimizations for Serial Code**

- Simple measure Large impact : simd, branch, comm sub expre
- C++ Optimization

#### Simple measures, large impact

- Elimination of Common Sub-expressions
- Avoid Branches:
  - Code Can be SIMdized by compiler/gcc
  - Effective use of pipeline for loop code
- Use of SIMD Instruction sets
  - 512 bit AVX SIMD in modern processor
  - ML/AI app use 8 bit Ops, can be speed up
     512/8=64 time by simply SIMD-AVX

# Elimination of Common Subexpressions

```
//value of s, r, x don't change in this loop
for (i=0; i<ALargeN; i++) {
    A[i]=A[i]+s+r+sinx(x);
}</pre>
```

```
//value of s, r, x don't change in this loop
Tmp=s+r+sinx(x);
for (i=0; i<ALargeN; i++) {
    A[i]=A[i]+Tmp;
}</pre>
```

#### **Avoid Branches**

```
for (i=0; i<N; i++)
  for(j=0; j<N; j++) {
    if(i<j) S=1; else S=-1;
    C[i] =C[i]+S*A[i][j]*B[i];
}</pre>
```

```
for (i=0; i<N; i++) {
    for (j=0; j<i; j++)
        C[i] =C[i] -A[i][j]*B[i];
    for (j=i; j<N; j++)
        C[i] =C[i] +A[i][j]*B[i];
}</pre>
```