DBMS_STAT_FUNCS

The DBMS STAT FUNCS package provides statistical functions.

This chapter contains the following topic:

Summary of DBMS_STAT_FUNCS Subprograms

Summary of DBMS_STAT_FUNCS Subprograms

This table lists and briefly describes the DBMS_STAT_FUNCS subprograms.

Table 196-1 DBMS_STAT_FUNCS Package Subprograms

Subprogram	Description
EXPONENTIAL_DIST_FIT Procedure	Tests how well a sample of values fits an exponential distribution
NORMAL_DIST_FIT Procedure	Tests how well a sample of values fits a normal distribution
POISSON_DIST_FIT Procedure	Tests how well a sample of values fits a Poisson distribution
SUMMARY Procedure	Summarizes a numerical column of a table
UNIFORM_DIST_FIT Procedure	Tests how well a sample of values fits a uniform distribution
WEIBULL_DIST_FIT Procedure	Tests how well a sample of values fits a Weibull distribution

EXPONENTIAL_DIST_FIT Procedure

This procedure tests how well a sample of values fits an exponential distribution.

Syntax

Parameters

Table 196-2 EXPONENTIAL_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.

Table 196-2 (Cont.) EXPONENTIAL_DIST_FIT Procedure Parameters

Parameter	Description
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
lambda	The scale parameter.
mu	The location parameter.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the exponential distribution. A number close to 1 indicates a close match.

NORMAL_DIST_FIT Procedure

This procedure tests how well a sample of values fits a normal distribution.

Syntax

Parameters

Table 196-3 NORMAL_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV', 'ANDERSON_DARLING' or 'SHAPIRO_WILKS'.
mean	The mean of the distribution against which to compare.
stdev	The standard deviation of the distribution against which to compare.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the normal distribution. A number close to 1 indicates a close match.

POISSON_DIST_FIT Procedure

This procedure tests how well a sample of values fits a Poisson distribution.

Syntax

```
DBMS_STAT_FUNCS.POISSON_DIST_FIT (
    ownername IN VARCHAR2,
```



Parameters

Table 196-4 POISSON DIST FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
lambda	The lambda parameter is the shape parameter.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the Poisson distribution. A number close to 1 indicates a close match.

SUMMARY Procedure

This procedure summarizes the numerical column specified in the columnname of tablename.

The summary is returned as a Summary Type. Note that most of the output of SUMMARY can be obtained with currently available SQL.

Syntax

```
DBMS_STAT_FUNCS.SUMMARY (
ownername IN VARCHAR2,
tablename IN VARCHAR2,
columnname IN VARCHAR2,
sigma_value IN NUMBER DEFAULT 3,
s OUT SummaryType);
```

Parameters

Table 196-5 SUMMARY Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table to be summarized.
sigma_value	The number of sigmas for the set of extreme values, defaults to 3.
S	The Record containing summary information about given column.

Definition of SummaryType

```
TYPE n_arr IS VARRAY(5) of NUMBER;
TYPE num table IS TABLE of NUMBER;
```

```
TYPE summaryType IS RECORD (
count NUMBER,
min NUMBER,
max NUMBER,
range NUMBER,
mean NUMBER,
cmode num_table,
variance NUMBER,
guantile_5 NUMBER,
quantile_5 NUMBER,
quantile_5 NUMBER,
median NUMBER,
quantile_75 NUMBER,
quantile_95 NUMBER,
quantile_95 NUMBER,
quantile_95 NUMBER,
plus_x_sigma NUMBER,
minus_x_sigma NUMBER,
minus_x_sigma NUMBER,
minus_x_sigma NUMBER,
minus_table,
top_5_values n_arr,
bottom 5 values n arr);
```

UNIFORM_DIST_FIT Procedure

This procedure tests well a sample of values fits a uniform distribution.

Syntax

Parameters

Table 196-6 UNIFORM_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
var_type	The type of distribution: 'CONTINUOUS' (the default) or 'DISCRETE'
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
paramA	Parameter A estimated from the sample (the location parameter).
paramB	Parameter B estimated from the sample (the scale parameter).
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the uniform distribution. A number close to 1 indicates a close match.



WEIBULL_DIST_FIT Procedure

This procedure tests how well a sample of values fits a Weibull distribution.

Syntax

Parameters

Table 196-7 WEIBULL_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
alpha	The scale parameter.
mu	The location parameter.
beta	The slope/shape parameter.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the Weibull distribution. A number close to 1 indicates a close match.

