



Γ<sup>†</sup> Subscribe

## How to Configure the Linux Firewall for Docker Swarm on Ubuntu 16.04



Posted January 9, 2017 43k FIREWALL DOCKER SECURITY UBUNTU 16.04

By: finid

#### Introduction

<u>Docker Swarm</u> is a feature of Docker that makes it easy to run Docker hosts and containers at scale. A Docker Swarm, or Docker cluster, is made up of one or more Dockerized hosts that function as *manager* nodes, and any number of *worker* nodes. Setting up such a system requires careful manipulation of the Linux firewall.

The network ports required for a Docker Swarm to function correctly are:

- TCP port 2376 for secure Docker client communication. This port is required for Docker Machine to work. Docker Machine is used to orchestrate Docker hosts.
- TCP port 2377. This port is used for communication between the nodes of a Docker Swarm or cluster. It only needs to be opened on manager nodes.
- TCP and UDP port 7946 for communication among nodes (container network discovery).
- UDP port 4789 for overlay network traffic (container ingress networking).

**Note:** Aside from those ports, port **22** (for SSH traffic) and any other ports needed for specific services to run on the cluster have to be open.

In this article, you'll learn how to configure the Linux firewall on Ubuntu 16.04 using the different firewall management applications available on all Linux distributions. Those firewall management applications are FirewallD, IPTables Tools, and UFW, the Uncomplicated Firewall. UFW is the default firewall application on Ubuntu distributions, including Ubuntu 16.04. While this tutorial

covers three methods, each one delivers the same outcome, so you can choose the one you are most familiar with.

#### Prerequisites

Before proceeding with this article, you should:

 Set up the hosts that make up your cluster, including at least one swarm manager and one swarm worker. You can follow the tutorial <u>How To Provision and Manage Remote Docker Hosts</u> with Docker Machine on Ubuntu 16.04 to set these up.

**Note:** You'll notice that the commands (and all the commands in this article) are not prefixed with **sudo**. That's because it's assumed that you're logged into the server using the **docker-machine ssh** command after provisioning it using Docker Machine.

### Method 1 — Opening Docker Swarm Ports Using UFW

If you just set up your Docker hosts, UFW is already installed. You just need to enable and configure it. Follow this guide to learn more about using UFW on Ubuntu 16.04.

Execute the following commands on the nodes that will function as Swarm managers:

```
$ ufw allow 22/tcp
$ ufw allow 2376/tcp
$ ufw allow 2377/tcp
$ ufw allow 7946/tcp
$ ufw allow 7946/udp
$ ufw allow 4789/udp
```

Afterwards, reload UFW:

#### \$ ufw reload

If UFW isn't enabled, do so with the following command:

#### \$ ufw enable

This might not be necessary, but it never hurts to restart the Docker daemon anytime you make changes to and restart the firewall:

#### systemctl restart docker

Then on each node that will function as a worker, execute the following commands:

```
$ ufw allow 22/tcp
$ ufw allow 2376/tcp
$ ufw allow 7946/tcp
$ ufw allow 7946/udp
$ ufw allow 4789/udp
```

Afterwards, reload UFW:

\$ ufw reload

If UFW isn't enabled, enable it:

\$ ufw enable

Then restart the Docker daemon:

systemctl restart docker

That's all you need to do to open the necessary ports for Docker Swarm using UFW.

# Method 2 — Opening Docker Swarm Ports Using FirewallD

FirewallD is the default firewall application on Fedora, CentOS and other Linux distributions that are based on them. But FirewallD is also available on other Linux distributions, including Ubuntu 16.04.

If you opt to use FirewallD instead of UFW, first uninstall UFW:

\$ apt-get purge ufw

Then install FirewallD:

```
$ apt-get install firewalld
```

Verify that it's running:

```
$ systemctl status firewalld
```

If it's not running, start it:

```
$ systemctl start firewalld
```

Then enable it so that it starts on boot:

```
$ systemctl enable firewalld
```

On the node that will be a Swarm manager, use the following commands to open the necessary ports:

```
$ firewall-cmd --add-port=22/tcp --permanent
$ firewall-cmd --add-port=2376/tcp --permanent
$ firewall-cmd --add-port=2377/tcp --permanent
$ firewall-cmd --add-port=7946/tcp --permanent
$ firewall-cmd --add-port=7946/udp --permanent
$ firewall-cmd --add-port=4789/udp --permanent
```

Note: If you make a mistake and need to remove an entry, type:

```
firewall-cmd --remove-port=port-number/tcp -permanent.
```

Afterwards, reload the firewall:

```
$ firewall-cmd --reload
```

Then restart Docker.

```
$ systemctl restart docker
```

Then on each node that will function as a Swarm worker, execute the following commands:

```
$ firewall-cmd --add-port=22/tcp --permanent
$ firewall-cmd --add-port=2376/tcp --permanent
$ firewall-cmd --add-port=7946/tcp --permanent
$ firewall-cmd --add-port=7946/udp --permanent
$ firewall-cmd --add-port=4789/udp --permanent
```

Afterwards, reload the firewall:

```
$ firewall-cmd --reload
```

Then restart Docker.

```
systemctl restart docker
```

You've successfully used FirewallD to open the necessary ports for Docker Swarm.

# Method 3 — Opening Docker Swarm Ports Using IPTables

To use IPtables on any Linux distribution, you'll have to first uninstall any other firewall utilities. If you're switching from FirewallD or UFW, first uninstall them.

Then install the iptables-persistent package, which manages the automatic loading of IPtables rules:

```
$ apt-get install iptables-persistent
```

Next, flush any existing rules using this command:

```
$ netfilter-persistent flush
```

Now you can add rules using the **iptables** utility. This first set of command should be executed on the nodes that will serve as Swarm managers.

```
$ iptables -A INPUT -p tcp --dport 22 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 2376 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 2377 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 7946 -j ACCEPT
$ iptables -A INPUT -p udp --dport 7946 -j ACCEPT
$ iptables -A INPUT -p udp --dport 4789 -j ACCEPT
```

After you enter all of the commands, save the rules to disk:

```
$ netfilter-persistent save
```

Then restart Docker.

\$ sudo systemctl restart docker

On the nodes that will function as Swarm workers, execute these commands:

```
$ iptables -A INPUT -p tcp --dport 22 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 2376 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 7946 -j ACCEPT
$ iptables -A INPUT -p udp --dport 7946 -j ACCEPT
$ iptables -A INPUT -p udp --dport 4789 -j ACCEPT
```

Save these new rules to disk:

\$ netfilter-persistent save

Then restart Docker:

\$ sudo systemctl restart docker

That's all it takes to open the necessary ports for Docker Swarm using IPTables. You can learn more about how these rules work in the tutorial How the Iptables Firewall Works.

If you wish to switch to FirewallD or UFW after using this method, the proper way to go about it is to first stop the firewall:

\$ sudo netfilter-persistent stop

Then flush the rules:

\$ sudo netfilter-persistent flush

Finally, save the now empty tables to disk:

\$ sudo netfilter-persistent save

Then you can switch to UFW or FirewallD.

### Conclusion

FirewallD, IPTables Tools and UFW are the three firewall management applications in the Linux world. You just learned how to use each to open the network ports needed to set up Docker Swarm. Which method you use is just a matter of personal preference, as they are all equally capable.

| By: finid              | ○ Upvote (14) | ☐ Subscribe |
|------------------------|---------------|-------------|
| Editor:<br>Brian Hogan |               |             |

## Introducing Projects on DigitalOcean

Organize your resources according to how you work.

**READ MORE** 

#### **Related Tutorials**

How to Use Traefik as a Reverse Proxy for Docker Containers on Ubuntu 18.04

How To Provision and Manage Remote Docker Hosts with Docker Machine on Ubuntu 18.04

Webinar Series: Building Blocks for Doing CI/CD with Kubernetes

## How To Install and Secure OpenFaaS Using Docker Swarm on Ubuntu 16.04 How To Install Docker Compose on Debian 9

| 6 Comments      |  |  |  |
|-----------------|--|--|--|
|                 |  |  |  |
| Leave a comment |  |  |  |
|                 |  |  |  |
|                 |  |  |  |
|                 |  |  |  |

Log In to Comment

^ JKON July 27, 2017

- Did you notice that when using ufw as a firewall and for example:
  - You have blocked all the ports with UFW except 22
  - You have docker container running with port binding "80:80"

The traffic will still go through to your docker container. Docker does some fancy stuff with iptables when running the containers. This does not seem very secure. Either you need to have your docker virtual networks carefully crafted or you need to bind the ports to 127.0.0.1:PORT:PORT, which I'm not sure how well with works in multi node swarm mode.

// JKON

When I follow the instructions for setting up a swarm, the swarm works initially, but after a few minutes it becomes unreachable from docker cloud and from the docker for mac application. It says "Docker Cloud is receiving heartbeats, but cannot connect to the swarm Resolution: Swarm is not publicly reachable, it may be behind a firewall or NAT"

Anything else I should try? This is my ufw configuration:

| 22/tcp        | ALLOW | Anywhere |      |
|---------------|-------|----------|------|
| 2376/tcp      | ALLOW | Anywhere |      |
| 2377/tcp      | ALLOW | Anywhere |      |
| 7946/tcp      | ALLOW | Anywhere |      |
| 7946/udp      | ALLOW | Anywhere |      |
| 4789/udp      | ALLOW | Anywhere |      |
| 6783/tcp      | ALLOW | Anywhere |      |
| 6783/udp      | ALLOW | Anywhere |      |
| 2375/tcp      | ALLOW | Anywhere |      |
| 443/tcp       | ALLOW | Anywhere |      |
| 80/tcp        | ALLOW | Anywhere |      |
| 8080/tcp      | ALLOW | Anywhere |      |
| 9000/tcp      | ALLOW | Anywhere |      |
| 9000/udp      | DENY  | Anywhere |      |
| 22/tcp (v6)   | ALLOW | Anywhere | (v6) |
| 2376/tcp (v6) | ALLOW | Anywhere | (v6) |
| 2377/tcp (v6) | ALLOW | Anywhere | (v6) |
| 7946/tcp (v6) | ALLOW | Anywhere | (v6) |
| 7946/udp (v6) | ALLOW | Anywhere | (v6) |
| 4789/udp (v6) | ALLOW | Anywhere | (v6) |
| 6783/tcp (v6) | ALLOW | Anywhere | (v6) |
| 6783/udp (v6) | ALLOW | Anywhere | (v6) |
| 2375/tcp (v6) | ALLOW | Anywhere | (v6) |
| 443/tcp (v6)  | ALLOW | Anywhere | (v6) |
| 80/tcp (v6)   | ALLOW | Anywhere | (v6) |
| 8080/tcp (v6) | ALLOW | Anywhere | (v6) |
| 9000/tcp (v6) | ALLOW | Anywhere | (v6) |

## ^ kobenauf November 2, 2017

I ran a series of "ufw allow" commands, restarted docker, checked "ufw status" and see the firewall rules there. When I look at the droplet in my DO dashboard, the Networking->Firewalls section says "You haven't applied any Firewalls to this Droplet yet." Is the droplet firewall something different?

## ^ mikkel418725b8766e1a77ce54 January 28, 2018

O I have to log into EACH AND EVERY SERVER to configure the firewall? What if I have 200 servers? Or something I don't get here?

## ^ tannerchung February 8, 2018

to a node but unable to use **docker-machine env**. And, my swarm is able to spin up containers on a worker, but unable to redirect traffic from a web browser to any services located only on a worker.

I'm now trying to add security group permissions based on this chart <a href="https://docs.docker.com/datacenter/ucp/2.2/guides/admin/install/system-requirements/#ports-used">https://docs.docker.com/datacenter/ucp/2.2/guides/admin/install/system-requirements/#ports-used</a> and the ports you suggested.. but can you help explain why 4789 is not on the list and why the other ports you mentioned aren't detailed with ingress and egress?

#### <u>tannerchung</u> February 8, 2018

 So docker-machine worked after I added 2376 TCP ingress to my Open Stack Security Group.

You mention that 2377 TCP is used between nodes only for managers but the docker docs say

managers, workers in TCP 2377 (configurable) Port for communication betwee workers out TCP 2377 (configurable) Port for communication between swarm node

mangers and workers for 2377.. is that right? nevermind about 4789, it's on the list managers, workers in, out UDP 4789 Port for overlay networking



This work is licensed under a Creative Commons Attribution-NonCommercial-ShareAlike 4.0 International License.



Copyright © 2018 DigitalOcean™ Inc.

Community Tutorials Questions Projects Tags Newsletter RSS

Distros & One-Click Apps Terms, Privacy, & Copyright Security Report a Bug Write for DOnations Shop