Configure linux dns server step by step guide example and implementation

A DNS server, or name server, is used to resolve an IP address to a hostname or vice versa. You can set up four different types of DNS servers:

- A master DNS server for your domain(s), which stores authoritative records for your domain.
- A slave DNS server, which relies on a master DNS server for data.
- A **caching-only DNS server**, which stores recent requests like a proxy server. It otherwise refers to other DNS servers.
- A **forwarding-only DNS server**, which refers all requests to other DNS servers.

Before configuring BIND to create a DNS server, you must understand some basic DNS concepts.

The entire hostname with its domain such as *server.example.com* is called a fully qualified domain name (FQDN). The right-most part of the FQDN such as .com or .net is called the *top level domain*, with the remaining parts of the FQDN, which are separated by periods, being subdomains

These sub-domains are used to divide FQDNs into zones, with the DNS information for each zone being maintained by at least one *authoritative name server*.

The authoritative server that contains the master zone file, which can be modified to update DNS information about the zone, is called the *primary master server*, or just *master server*.

The additional name servers for the zone are called *secondary servers* or *slave servers*. Secondary servers retrieve information about the zone through a zone transfer from the master server or from another secondary server. DNS information about a zone is never modified directly on the secondary server

chroot features

chroot feature is run named as user **named**, and it also limit the files named can see. When installed, **named** is fooled into thinking that the directory /var/named/chroot is actually the **root** or / directory. Therefore, named files normally found in the /etc directory are found in /var/named/chroot/etc directory instead, and those you would expect to find in /var/named are actually located in /var/named/chroot/var/named.

The advantage of the chroot feature is that if a hacker enters your system via a BIND exploit, the hacker's access to the rest of your system is isolated to the files under the chroot directory and nothing else. This type of security is also known as a chroot jail.

Configure dns server

In this example we will configure a dns server and will test from client side.

For this example we are using three systems one linux server one linux clients and one window clients

bind and **caching-nameserver** rpm is required to configure dns. check them for install if not found install them

```
[root@Server ~ ]# rpm -qa bind*
bind-libs-9.3.3-10.e15
bind-chroot-9.3.3-10.e15
bind-devel-9.3.3-10.e15
bind-utils-9.3.3-10.e15
bind-libbind-devel-9.3.3-10.e15
bind-9.3.3-10.e15
bind-sdb-9.3.3-10.e15
[root@Server ~ ]# rpm -qa cach*
caching-nameserver-9.3.3-10.e15
[root@Server ~ ]# rpm -qa cach*
cachefilesd-0.8-2.e15
```

set hostname to server.example.com and ip address to 192.168.0.254

main configuration file for dns server is **named.conf**. By default this file is not created in /var/named/chroot/etc/ directory. Instead of named.conf a sample file /var/named/chroot/etc/named.caching-nameserver.conf is created. This file is use to make a caching only name server. You can also do editing in this file after changing its name to **named.conf** to configure master dns server or you can manually create a new **named.conf** file.

```
In our example we are creating a new named.conf file [root@Server etc]# vi /var/named/chroot/etc/named.conf _
```

We are using bind's **chroot** features so all our necessary files will be located in chroot directory. Set directory location to /var/named. Further we will set the location of **forward zone** and **reverse lookup zone** files. If you cannot create this file manually then download this file and copy to /var/named/chroot/etc/

To download do right click here and choose save link As.. named.conf

Or do editing exactly as shown here in image

save this file with :wq and exit

Configure zone file

We have defined two zone files **example.com.zone** for forward zone and **0.168.192.in-addr.arpa** for reverse zone. These files will be store in /**var/named/chroot/var/named/** location. We will use two sample files for creating these files.

Change directory to /var/named/chroot/var/named and copy the sample files to name which we have set in named.conf

```
[root@Server named]# cd /var/named/chroot/var/named
[root@Server named]# cp localhost.zone example.com.zone
[root@Server named]# cp named.local 0.168.192.in-addr.arpa.zone
[root@Server named]# _
```

Now open forward zone file **example.com.zone**

```
[root@Server named]# vi example.com.zone _
```

By default this file will look like this

Change this file exactly as shown in image below

```
STTL
        86400
                  SOA
                               example.com.
                                                   root (
                                            42
                                                              : serial
                                            3H
                                                              : refresh
                                            15M
                                                               retry
                                            1W
                                                               expiru
                                            1D )
                                                              : minimum
                 NS
                                   server.example.com.
                 NS
                                   client1.client.com.
server
                 À
                                   192.168.0.254
client1
                 À
                                   192.168.0.1
                                   192.168.0.2
clientZ
                 Ĥ
```

If you feel difficulty to modify this file then download this configured file and copy to /var/named/chroot/var/named

To download do right click here and choose save link As.. example.com.zone

```
Now open reverse lookup zone file 0.168.192.in-addr.arpa
```

```
[root@Server named]# vi 0.168.192.in-addr.arpa.zone _
```

By default this file will look like this

```
STTL
        86400
        IN
                 SOA
                          localhost. root.localhost.
                                                       Serial
                                         1997022700 ;
                                         28800
                                                       Refresh
                                         14400
                                                       Retry
                                         3600000
                                                       Expire
                                         86400 )
                                                     : Minimum
                          localhost.
        ΙM
                 NS
        ΙN
                 PTR
                          localhost.
```

Change this file exactly as shown in image below

```
$TTL
        86400
              SOA
                       example.com. root.server.example.com.
                                        1997022700 ; Serial
                                        28800
                                                    : Refresh
                                        14400
                                                      Retry
                                        3600000
                                                    : Expire
                                        86400 )
                                                    : Minimum
          ΙN
                  NS
                          server.example.com
254
          ΙH
                  PTR
                          server.example.com.
          ΙN
                  PTR
                          client1.example.com.
          IN
                  PTR
                          client2.
```

If you feel difficulty to modify this file then download this configured file and copy to /var/named/chroot/var/named

To download do right click here and choose save link As.. 0.168.192.in-addr.arpa

```
Now changed the ownership of these zone files to named group
```

```
[root@Server named]# chgrp named example.com.zone
[root@Server named]# chgrp named 0.168.192.in-addr.arpa.zone
[root@Server named]# _
```

Now start the named service

```
[root@Server named]# chkconfig named on
[root@Server named]# service named restart
Stopping named:
Starting named:
[ OK ]
[root@Server named]# _
```

If service restart without any error means you have successfully configured master name server in our next article we will learn how to configure salve dns server and test it.