

# **Developer Tutorials**

Last generated: March 01, 2018



## **Table of Contents**

## **Developer Tutorials**

Splice Machine Tutorials	
Introduction	1
splice> Command Line	
Getting Started With splice>	
Scripting splice>	
RIWrap Summary	
Ingestion and Streaming	
Uploading Data to S3	22
Setting up S3 Access	
Importing Data: Tutorial Overview	
Importing Data: Parameter Usage	
Importing Data: Input Data Handling	
Importing Data: Error Handling	
Importing Data: Usage Examples	68
Importing Data: Bulk HFile Examples	74
Importing Data: Importing TPCH Data	85
Creating a Kafka Producer	110
Configuring a Kafka Feed	111
Using Apache Storm	112
MQTT Spark Streaming	116
Analytics and Machine Learning	
Using Zeppelin	
Connecting Programmatically	
Connecting through HAProxy	130
Connecting with Java	
Connecting with JRuby	
Connecting with Jython	
Connecting with Scala	
Connecting with NodeJS	
Installing our ODBC Driver	
Connecting with Python	

Connecting with C and ODBC	
Connecting BI Tools	
Connecting DBeaver	171
Connecting DBVisualizer	
Connecting Cognos	
Connecting SQuirreL	
Connecting Tableau	

## **Splice Machine Tutorials**

This guide includes tutorials to help you quickly become proficient in various aspects of using Splice Machine:

Section	Description
Data Ingestion	This section includes topics that show you how to get data into your database:
and Streaming	Importing Data Tutorial
	Streaming with Kafka and Splice Machine
	Spark Streaming with MQTT
	Using Apache Storm with Splice Machine
Connecting Your Database	This section introduces our JDBC and ODBC drivers and contains mini-tutorials to help you use our drivers to connect to your Splice Machine database with various programming languages, including:
	Connecting with AngularJS and JDBC
	Connecting with Java and JDBC
	Connecting with JRuby and JDBC
	Connecting with Jython and JDBC
	Connecting with Scala and JDBC
	Connecting with C and ODBC
	Connecting with Python and ODBC
	This section also contains mini-tutorials to help you connect specific Business Intelligence tools to your Splice Machine database, including:
	Connecting Cognos to Splice Machine
	Connecting DBeaver to Splice Machine
	Connecting DBVisualizer to Splice Machine
	Connecting SQuirreL to Splice Machine
	Connecting Tableau to Splice Machine
Analytics and Machine Learning	<u>Using Zeppelin with Splice Machine</u>

## **Getting Started With the splice> Command Line Interface**

This is an On-Premise-Only topic! Learn about our products

The splice command line interpreter is an easy way to interact with your Splice Machine database. This topic introduces splice and some of the more common commands you'll use



The command line interpreter, as documented here, is not available in our Cloud-Managed Database-as-Service product.

You can complete this tutorial by watching a short video or by following the written version.

#### Watch the Video

The following video shows you how to launch and start using the splice command line interpreter to connect to and interact with your database.

#### **Follow the Written Version**

This topic walks you through getting started with the splice command line interpreter, in these sections:

- Starting splice>
- >> Basic Syntax Rules
- Connecting to a Database
- >> Displaying Database Objects
- >> Basic DDL and DML Statements

**NOTE:** Although we focus here on executing command lines with the splice>, you can also use the command line interface to directly execute any SQL statement, including the DDL and DML statements that we introduce in the last section of this topic.

## Starting splice>

To launch the splice> command line interpreter, follow these steps:

1. Open a terminal window

#### 2. Navigate to your splicemachine directory

cd  $\sim$ /splicemachine #Use the correct path for your Splice Machine installation

#### 3. Start splice>

```
./bin/sqlshell.sh
```

The full path to this script on Splice Machine standalone installations is ./splicemachine/bin/sqlshell.sh.

#### 4. The command line interpreter starts:

```
Running Splice Machine SQL ShellFor help: "Splice> help;"SPLICE** = curre nt connectionsplice>
```

SPLICE is the name of the default connection, which becomes the current connection when you start the interpreter.

#### Restarting splice>

If you are running the standalone version of Splice Machine and your computer goes to sleep, any live database connections are lost. You'll need to restart Splice Machine by following these steps:

Step	Command
Exit splice>	splice> quit; (exit;)
Stop Splice Machine processes	\$ ./bin/stop-splice.sh
Restart Splice Machine processes	\$ ./bin/start-splice.sh
Restart splice>	\$ ./bin/sqlshell.sh

## **Basic Syntax Rules**

When using the command line (the splice> prompt), you must end each SQL statement with a semicolon (;). For example:

```
splice> select * from myTable;
```

You can extend SQL statements across multiple lines, as long as you end the last line with a semicolon. Note that the splice> command line interface prompts you with a fresh > at the beginning of each line. For example:

```
splice> select * from myTable> where i > 1;
```

In most cases, the commands you enter are not case sensitive; you can Certain identifiers and keywords are case sensitive: this means that these commands are all equivalent:

```
splice> show connections;
splice> SHOW CONNECTIONS;
splice> Show Connections;
```

The Command Line Syntax topic contains a complete syntax reference for splice>.

### **Connecting to a Database**

When you start splice>, you are automatically connected to your default database. You can connect to other databases with the <a href="mailto:connect">connect</a> command:

```
connect 'jdbc:splice://srv55:1527/splicedb;user=splice;password=admin' AS DEMO;
```

#### **Anatomy of a Connection String**

Here's how to breakdown the connection strings we use to connect to a database:

Examples	Component	Comments
jdbc:splice:	Connection driver name	
srv55:1527 localhost:1527	Server Name:Port	splice> listens on port 1527
splicedb	Database name	The name of the database you're connecting to on the server.
user=splice;password=admin	Connection parameters	Any required connection parameters, such as userId and password.
AS DEMO	Optional connection identifier	The name that you want associated with this connection.  If you don't supply a name, Splice Machine assigns one for your; for example: CONNECTION1.

#### **Displaying Database Objects**

We'll first explore the show command, which is available to view numerous object types in your database, including: connections, schemas, tables, indexes, views, procedures, and others.

#### **Displaying and Changing Connections**

You can connection to multiple database in Splice Machine; one connection is designated as the current database; this is the database with which you're currently working.

To view your current connections, use the <a href="mailto:show connections">show connections</a> command:

You can use the set connection command to modify the current connection:

```
splice> SET CONNECTION DEMO;
splice> show connections;
DEMO* - jdbc:splice://srv55:1527/splicedb
SPLICE - jdbc:splice://localhost:1527/splicedb
* = current connection
```

You can use the disconnect command to close a connection:

```
splice> Disconnect DEMO;
splice> show Connections;
SPLICE - jdbc:splice://localhost:1527/splicedb
No current connection
```

Notice that there's now no current connection because we've disconnected the connection named DEMO, which had been the current connection. We can easily resolve this by connecting to a named connection:

```
splice> connect splice;
splice> show connections;
SPLICE* - jdbc:splice://localhost:1527/splicedb
* = current connection
```

Finally, to disconnect from all connections:

```
splice> disconnect all;
splice> show connections;
No connections available
```

#### **Displaying Schemas**

Use the **show schemas** command to display the schemas that are defined in your currently connected database:

The current schema is used as the default value when you issue commands that optionally take a schema name as a parameter. For example, you can optionally specify a schema name in the show tables command; if you don't include a schema name, Splice Machine assumes the current schema name.

To display the current schema name, use the built-in <a href="current schema">current schema</a> function:

To change which schema is current, use the SQL set schema statement:

#### **Displaying Tables**

The show tables command displays a list of all tables in all of the schemas in your database:

splice> SHOW		CONGLOM_ID REMARKS
	· –	
SYS	SYSALIASES	256
SYS	SYSBACKUP	992
SYS	SYSBACKUPFILESET	1008
SYS	SYSBACKUPITEMS	1104
SYS	SYSBACKUPJOBS	1216
SYS	SYSCHECKS	336
SYS	SYSCOLPERMS	608
SYS	SYSCOLUMNS	80
SYS	SYSCOLUMNSTATS	1264
SYS	SYSCONGLOMERATES	48
SYS	SYSCONSTRAINTS	304
SYS	SYSDEPENDS	368
SYS	SYSFILES	288
SYS	SYSFOREIGNKEYS	272
SYS	SYSKEYS	240
SYS	SYSPERMS	912
SYS	SYSPHYSICALSTATS	1280
SYS	SYSPRIMARYKEYS	320
SYS	SYSROLES	816
SYS	SYSROUTINEPERMS	656
SYS	SYSSCHEMAPERMS	1328
SYS	SYSSCHEMAS	32
SYS	SYSSEQUENCES	864
SYS	SYSSTATEMENTS	384
SYS	SYSTABLEPERMS	592
SYS	SYSTABLES	64
SYS	SYSTABLESTATS	1296
SYS	SYSTRIGGERS	576
SYS	SYSUSERS	928
SYS	SYSVIEWS	352
SYSIBM	SYSDUMMY1	1312
SPLICE	CUSTOMERS	1568
SPLICE	T_DETAIL	1552
SPLICE	T_HEADER	1536
34 rows sele	cted	

#### To display the tables in a specific schema (named SPLICE):

To examine the structure of a specific table, use the  ${\tt DESCRIBE}$  command:

<pre>splice&gt; describe T_DETAIL; COLUMN_NAME L</pre>	TYPE_NAM	E   DEC	NUM	COLUM	COLUMN_DE	F CHAR_OCTE	IS_NUL
TRANSACTION HEADER KEY	BIGINT	10	10	119	NULL	NULL	NO
TRANSACTION DETAIL KEY	BIGINT	10	110	119	NULL	NULL	NO
CUSTOMER MASTER ID	BIGINT	10	110	19	NULL	NULL	YES
TRANSACTION DT	DATE	10	10	10	NULL	NULL	NO
ORIGINAL_SKU_CATEGORY_ID	INTEGER	10	10	10	NULL	NULL	YES
5 rows selected							

## **Displaying Indexes**

You can display all of the indexes in a schema:

splice> show	indexes in SPLI	CE;				
TABLE_NAME NGLOM_NO	INDEX_NAME	COLUMN_NAME	ORDINAL	NON_UNIQUE	E TYPE  ASC	&   CO
T_DETAIL 85	TDIDX1	ORIGINAL_SKU_CATEGO&	.   1	true	BTREE A	15
T_DETAIL 85	TDIDX1	TRANSACTION_DT	2	true	BTREE A	15
T_DETAIL 85	TDIDX1	CUSTOMER_MASTER_ID	3	true	BTREE A	15
T_HEADER 01	THIDX2	CUSTOMER_MASTER_ID	1	true	BTREE A	16
T_HEADER 01	THIDX2	TRANSACTION_DT	2	true	BTREE A	16
5 rows select	ed					

Or you can display the indexes defined for a specific table:

splice> show TABLE_NAME NGLOM_NO	indexes FROM T_  INDEX_NAME	DETAIL;  COLUMN_NAME	ORDINAL	& NON_UNIQU	E TYPE  ASC8	& CO
T_DETAIL	TDIDX1	ORIGINAL_SKU_CATEGO	§   1	true	BTREE A	15
85						
T_DETAIL 85	TDIDX1	TRANSACTION_DT	2	true	BTREE A	15
T_DETAIL	TDIDX1	CUSTOMER_MASTER_ID	3	true	BTREE A	15
85						
3 rows select	ed					



Note that we use IN to display the indexes in a schema, and FROM to display the indexes in a table.

#### **Displaying Views**

Similarly to indexes, you can use the <a href="mailto:show\_views">show\_views</a> command to display all of the indexes in your database or in a schema:

```
splice> show views;
TABLE_SCHEM | TABLE_NAME
                         |CONGLOM ID|REMARKS
SYS
            |SYSCOLUMNSTATISTICS |NULL
SYS
           |SYSTABLESTATISTICS |NULL
2 rows selected
splice> show views in sys; TABLE SCHEM | TABLE NAME
                                              |CONGLOM ID|REMARKS
SYS
            |SYSCOLUMNSTATISTICS |NULL
                                         |SYSTABLESTATISTICS |NULL
SYS
2 rows selected
```

#### **Displaying Stored Procedures and Functions**

You can create *user-defined database functions* that can be evaluated in SQL statements; these functions can be invoked where most other built-in functions are allowed, including within SQL expressions and SELECT statement. Functions must be deterministic, and cannot be used to make changes to the database. You can use the show functions command to display which functions are defined in your database or schema:

You can also group a set of SQL commands together with variable and logic into a *stored procedure*, which is a subroutine that is stored in your database's data dictionary. Unlike user-defined functions, a stored procedure is not an expression and can only be invoked using the CALL statement. Stored procedures allow you to modify the database and return Result Sets or nothing at all. You can use the <a href="mailto:show procedures">how procedures</a> command to display which functions are defined in your database or schema:

splice> show procedor PROCEDURE_SCHEM	ures in SQLJ;  PROCEDURE_NAME	REMARKS
SQLJ	INSTALL_JAR	com.splicemachine.db.catalog.SystemProcedure
s.INSTALL_JAR		
SQLJ	REMOVE_JAR	com.splicemachine.db.catalog.SystemProcedure
s.REMOVE_JAR		
SQLJ	REPLACE_JAR	com.splicemachine.db.catalog.SystemProcedure
s.REPLACE_JAR		
3 rows selected		

#### **Basic DDL and DML Statements**

This section introduces the basics of running SQL Data Definition Language (*DDL*) and Data Manipulation Language (*DML*) statements from splice>.

- >> Getting Started With the splice > Command Line Interface
- >> Getting Started With the splice > Command Line Interface
- Inserting Data
- >> Selecting and Displaying Data

See the DML Statements sections in our SQL Reference Manual for more information.

#### **CREATE Statements**

SQL uses CREATE statements to create objects such as <u>tables</u>. For example:

```
splice > CREATE schema MySchema1;
0 rows inserted/updated/deleted
splice> create Schema mySchema2;
0 rows inserted/updated/deleted
splice> show schemas;
TABLE SCHEM
MYSCHEMA1MYSCHEMA2NULLID
SPLICE
SQLJ
SYS
SYSCAT
SYSCS DIAG
SYSCS UTIL
SYSFUN
SYSIBM
SYSPROC
SYSSTAT
13 rows selected
splice > SET SCHEMA MySchemal;
0 rows inserted/updated/deleted
splice > CREATE TABLE myTable ( myNum int, myName VARCHAR(64) );
0 rows inserted/updated/deleted
splice > CREATE TABLE Players(
          SMALLINT NOT NULL PRIMARY KEY,
             VARCHAR(64) NOT NULL,
VARCHAR(64) NOT NULL,
    Team
   Name
   Position CHAR(2),
   DisplayName VARCHAR(24),
   BirthDate DATE
   );
0 rows inserted/updated/deleted
splice > SHOW TABLES IN MySchemal;
TABLE_SCHEM | TABLE_NAME | CONGLOM_ID | REMARKS
_____
                           |1616
MYSCHEMA1
           MYTABLE
MYSCHEMA1 | PLAYERS
                                   |1632
2 rows selected
splice> describe Players;
COLUMN NAME | TYPE NAME | DEC& | NUM& | COLUM& | COLUMN DEF | CHAR OCTE& | IS NULL&
______
             |SMALLINT |0 |10 |5
                                       NULL
                                                  |NULL
            |VARCHAR |NULL|NULL|64 |NULL
                                                  |128
TEAM
NAME | VARCHAR | NULL | NULL | 64 | NULL | 128 | POSITION | CHAR | NULL | NULL | 2 | NULL | 4 | DISPLAYNAME | VARCHAR | NULL | NULL | 24 | NULL | 48 | BIRTHDATE | DATE | 0 | 10 | 10 | NULL | NULL |
                                                             | NO
                                                              |YES
                                                              |YES
6 rows selected
```

See the CREATE Statements section in our SQL Reference Manual for more information.

#### **DROP Statements**

SQL uses DROP statements to delete objects such as tables. For example:

```
splice> DROP schema MySchema2 restrict; 0 rows inserted/updated/deleted
```

You **must** include the keyword restrict when dropping a schema; this enforces the rule that the schema cannot be deleted from the database if there are any objects defined in the schema.

```
splice> show schemas;
TABLE SCHEM
______
MYSCHEMA1
MYSCHEMA2
NULLID
SPLICE
SQLJ
SYS
SYSCAT
SYSCS DIAG
SYSCS UTIL
SYSFUN
SYSIBM
SYSPROC
SYSSTAT
12 rows selected
splice > DROP TABLE myTable;
0 rows inserted/updated/deleted
splice > SHOW TABLES IN MySchemal;
TABLE_SCHEM | TABLE_NAME | CONGLOM_ID | REMARKS
_____
MYSCHEMA1 | PLAYERS
                            |1632 |1 row selected
```

See the <u>DROP Statements</u> section in our SQL Reference Manual for more information.

#### Inserting Data

Once you've created a table, you can use <u>INSERT</u> statements to insert records into that table; for example:

#### Selecting and Displaying Data

Now that you have a bit of data in your table, you can use <u>SELECT</u> statements to select specific records or portions of records. This section contains several simple examples of selecting data from the Players table we created in the previous section.

You can select a single column from all of the records in a table; for example:

You can select all columns from all of the records in a table; for example:

```
splice> select * from Players;

ID |TEAM |NAME |POS&|DISPLAYNAME |BIRTHDATE

27 |Cards |Earl Hastings |OF |Speedy Earl |1982-04-22

73 |Giants |Lester Johns |P |Big John |1984-06-09

99 |Giants |Joe Bojangles |C |Little Joey |1991-07-11

3 rows selected
```

You can also qualify which records to select with a WHERE clause; for example:

You can easily count the records in a table by using the SELECT statement; for example:

## See Also

- >> To learn how to script splice> commands, please see the Scripting Splice Machine Commands tutorial.
- >> For more information about the splice> command line interpreter, see the Command Line Reference Manual, which includes information about and examples of all supported commands.
- >> This documentation includes a number of other tutorials to help you become proficient with Splice Machine.

## Scripting the splice> Command Line Interface

This is an On-Premise-Only topic! Learn about our products

You can use two simple and different methods to script the splice> command line interpreter; both of described here:

- >> Running a File of splice > Commands
- >> Running Splice Machine From a Shell Script

## Running a File of splice > Commands

You can create a simple text file of command lines and use the splice> run command to run the commands in that file. Follow these steps:

#### 1. Create a file of SQL commands:

First, create a file that contains any SQL commands you want to run against your Splice Machine database. For this example, we'll create a file named <code>mySQLScript.sql</code> that connects to a database, creates a table, inserts records into that table, and then displays the records in the table.

```
connect 'jdbc:splice://localhost:1527/splicedb;user=splice;password=admi
n';
create table players (
ID SMALLINT NOT NULL PRIMARY KEY,
Team VARCHAR (64) NOT NULL,
Name VARCHAR (64) NOT NULL,
 Position CHAR(2),
DisplayName VARCHAR (24),
 BirthDate DATE );
INSERT INTO Players
  VALUES (99, 'Giants', 'Joe Bojangles', 'C', 'Little Joey', '07/11/199
1'),
          (73, 'Giants', 'Lester Johns', 'P', 'Big John', '06/09/1984'),
          (27, 'Cards', 'Earl Hastings', 'OF', 'Speedy Earl', '04/22/198
2');
SELECT * FROM Players;
```

#### 2. Start splice>

If you've not yet done so, start Splice Machine and the splice> command line interface. If you don't know how to do so, please see our <u>Introduction to the splice> Command Line Interface</u>.

#### 3. Run the SQL Script

Now, in splice>, run your script with the <u>run</u> command:

```
run 'mySQLScript.sql';
```

You'll notice that splice> displays exactly the same results as you would see if you typed each command line into the interface:

```
splice> connect 'jdbc:splice://localhost:1527/splicedb;user=splice;passwo
rd=admin';
splice> create table players (
ID SMALLINT NOT NULL PRIMARY KEY,
Team VARCHAR (64) NOT NULL,
Name VARCHAR (64) NOT NULL,
Position CHAR(2),
DisplayName VARCHAR(24),
BirthDate DATE );
0 rows inserted/updated/deleted
splice> INSERT INTO Players
  VALUES (99, 'Giants', 'Joe Bojangles', 'C', 'Little Joey', '07/11/199
1'),
         (73, 'Giants', 'Lester Johns', 'P', 'Big John', '06/09/1984'),
         (27, 'Cards', 'Earl Hastings', 'OF', 'Speedy Earl', '04/22/198
2');
3 rows inserted/updated/deleted
splice> SELECT * FROM Players;
ID | TEAM | NAME
                                     | POS& | DISPLAYNAME
                                                                  ΙB
IRTHDATE
27 | Cards | Earl Hastings | OF | Speedy Earl
                                                                  11
982-04-22
73 | Giants | Lester Johns
                                    |P |Big John
                                                                  11
984-06-09
99 | Giants | Joe Bojangles | C | Little Joey
                                                                  | 1
991-07-11
3 rows selected
splice>
```

## Running Splice Machine From a Shell Script

You can also use a shell script to start the splice> command line interpreter and run command lines with Unix heredoc (<<) input redirection. For example, we can easily rework the SQL script we used in the previous section into a shell script that starts splice>, runs several commands/statements, and then exits splice>.

#### 1. Create a shell script

For this example, we'll create a file named <code>myShellScript.sql</code> that uses the same commands as we did in the previous example:

```
#!/bin/bashecho "Running splice> commands from a shell script"./bin/sqlsh
ell.sh << EOFconnect 'jdbc:splice://localhost:1527/splicedb;user=splice;p
assword=admin';
create table players (
ID SMALLINT NOT NULL PRIMARY KEY,
Team VARCHAR(64) NOT NULL,
Name VARCHAR (64) NOT NULL,
Position CHAR(2),
 DisplayName VARCHAR(24),
 BirthDate DATE );
INSERT INTO Players
  VALUES (99, 'Giants', 'Joe Bojangles', 'C', 'Little Joey', '07/11/199
1'),
          (73, 'Giants', 'Lester Johns', 'P', 'Big John', '06/09/1984'),
          (27, 'Cards', 'Earl Hastings', 'OF', 'Speedy Earl', '04/22/198
2');
SELECT * FROM Players;exit;EOF
```

If you're not familiar with this kind of input redirection: the << specifies that an interactive program (./bin/sqlshell.sh) will receive its input from the lines in the file until it encounters EOF. The program responds exactly as it would had a user directly typed in those commands.

#### 2. Make your script executable

Be sure to update permissions on your script file to allow it to run:

```
chmod +x myShellScript.sh
```

#### 3. Run the script

In your terminal window, invoke the script:

```
./myShellScript.sh
```

You'll notice that splice> starts and runs exactly as it did in the SQL script example above, then exits.

```
Running Splice Machine Commands from a Shell Script...
======= rlwrap detected and enabled. Use up and down arrow keys to sc
roll through command line history. =======
Running Splice Machine SQL shell
For help: "splice> help; "splice> connect 'jdbc:splice://srv55:1527/splice
db; user=splice; password=admin';
splice> create table players (
ID SMALLINT NOT NULL PRIMARY KEY,
Team VARCHAR (64) NOT NULL,
Name VARCHAR (64) NOT NULL,
Position CHAR(2),
DisplayName VARCHAR(24),
BirthDate DATE );
0 rows inserted/updated/deleted
splice> INSERT INTO Players
  VALUES (99, 'Giants', 'Joe Bojangles', 'C', 'Little Joey', '07/11/199
1'),
         (73, 'Giants', 'Lester Johns', 'P', 'Big John', '06/09/1984'),
         (27, 'Cards', 'Earl Hastings', 'OF', 'Speedy Earl', '04/22/198
2');
3 rows inserted/updated/deleted
splice> SELECT * FROM Players;
ID | TEAM | NAME
                                      |POS&|DISPLAYNAME
                                                                    ΙB
IRTHDATE
27 | Cards | Earl Hastings | OF | Speedy Earl
                                                                   | 1
982-04-22
73 |Giants |Lester Johns
                                      |P |Big John
                                                                    11
984-06-09
99 | Giants | Joe Bojangles | C | Little Joey
                                                                    11
991-07-11
3 rows selected
```

## **Using nohub for Long-Running Scripts**

If you want to run an unattended shell script that may take a long time, you can: use the Unix nohup utility, which allows you to start a script in the background and redirect its output. This means that you can start the script, log out, and view the output at a later time. For example:

```
nohup ./myShellScript.sh > ./myShellScript.out 2>&1 &
```

Once you've issued this command, you can log out, and subsequently view the output of your script in the myShellScript.out file.

## rlWrap Commands Synopsis

This is an On-Premise-Only topic! Learn about our products

The rlWrap program is a readline wrapper, a small utility that uses the GNU readline library to allow the editing of keyboard input for any command; it also provides a history mechanism that is very handy for fixing or reusing commands. Splice Machine strongly recommends that you use rlWrap when interacting with your database via our command line interface, which is also known as the splice prompt.

**NOTE:** You can customize many aspects of <code>rlWrap</code> and <code>readline</code>, including the keyboard bindings for the available commands. For more information, see the Unix man page for <code>readline</code>.

The following table summarizes some of the common keyboard options you can use with rlWrap; this table uses the default bindings that are in place when you install rlWrap on MacOS; keyboard bindings may be different in your environment.

Command	Description
CTRL-@	Set mark
CTRL-A	Move to the beginning of the line
CTRL-B	Move back one character
CTRL-D	Delete the highlighted character
CTRL-E	Move to the end of the line
CTRL-F	Move forward one character
CTRL-H	Backward delete character
CTRL-J	Accept (submit) the line
CTRL-L	Clear the screen
CTRL-M	Accept the line
CTRL-N	Move to the next line in history
CTRL-P	Move to the previous line in history
CTRL-R	Reverse search through your command line history
CTRL-S	Forward search through your command line history

Command	Description
CTRL-T	Transpose characters: switch the highlighted character with the one preceding it
CTRL-U	Discard from the cursor position to the beginning of the line
CTRL-]	Search for a character on the line
CTRL	Undo
ALT-<	Go to the beginning of the history
ALT->	Go to the end of the history
ALT-B	Backward word
ALT-C	Capitalize the current word
ALT-F	Forward word
ALT-L	Downcase word
ALT-R	Revert line
ALT-T	Transpose words
ALT-U	Uppercase word

Note that the ALT key is labeled as the option key on Macintosh keyboards.

NOTE: If you're using the <code>splice></code> prompt in the Terminal.app on MacOS, the <code>ALT-commands</code> listed above only work if you select the <code>Use Option</code> as <code>Meta key</code> setting in the keyboard preferences for your terminal window

## **Uploading Your Data to an S3 Bucket**

You can easily load data into your Splice Machine database from an Amazon Web Services (AWS) S3 bucket. This tutorial walks you through creating an S3 bucket (if you need to) and uploading your data to that bucket for subsequent use with Splice Machine.

NOTE: For more information about S3 buckets, see the AWS documentation.

After completing the configuration steps described here, you'll be able to load data into Splice Machine from an S3 bucket.


## Create and Upload Data to an AWS S3 Bucket

Follow these steps to first create a new bucket (if necessary) and upload data to a folder in an AWS S3 bucket:

- Log in to the AWS Database Console
   Your permissions must allow for you to create an S3 bucket.
- 2. Select Services at the top of the dashboard




3. Select S3 in the Storage section:




#### 4. Create a new bucket

a. Select Create Bucketfrom the S3screen




**b.** Provide a name and select a region for your bucket

The name you select must be unique; AWS will notify you if you attempt to use an already-used name. For optimal performance, choose a region that is close to the physical location of your data; for example:




c. Click the Next button to advance to the property settings for your new bucket:



You can click one of the Learn more buttons to view or modify details.

**d.** Click the **Next** button to advance to view or modify permissions settings for your new bucket:




**e.** Click **Next** to review your settings for the new bucket, and then click the **Create bucket** button to create your new S3 bucket. You'll then land on your S3 Management screen.


#### 5. Upload data to your bucket

After you create the bucket:

a. Select Create folder, enter a name for the new folder, and click the Save button.



**b.** Click the **Upload** button to select file(s) to upload to your new bucket folder. You can then drag files into the upload screen, or click **Add Files** and navigate to the files you want to upload to your folder.



- **c.** You can then optionally set permissions and properties for the files you are uploading. Once you're done, click the Upload button, and AWS will copy the files into the folder in your S3 bucket.
- 6. Make sure Splice Machine can access your bucket:

Review the IAM configuration options in our <u>Configuring an S3 Bucket for Splice Machine Access</u> tutorial to allow Splice Machine to import your data.

## Configuring an S3 Bucket for Splice Machine Access

Splice Machine can access S3 buckets, making it easy for you to store and manage your data on AWS. To do so, you need to configure your AWS controls to allow that access. This topic walks you through the required steps.

**NOTE:** You must have administrative access to AWS to configure your S3 buckets for Splice Machine.


## **Configure S3 Bucket Access**

You can follow these steps to configure access to your S3 bucket(s) for Splice Machine; when you're done, you will have:

- >> created an IAM policy for an S3 bucket
- >> created an IAM user
- >> generated access credential for that user
- >> attached the security policy to that user
  - Log in to the AWS Database Console
     You must have administrative access to configure S3 bucket access.
  - 2. Select Services at the top of the dashboard



Access the IAM (Identify and Access Management) service:
 Select IAM in the Security, Identity & Compliance section:





### Security, Identity & Com.

IAM

Inspector

Certificate Manager

Directory Service

WAF & Shield

Compliance Reports



#### Migration

Route 53

**VPC** 

CloudFront


Direct Connect

ElastiCache Redshift


Networking & Content .

### 4. Create a new policy:


a. Select Policies from the IAM screen, then select Create Policy:



b. Select Create Your Own Policy to enter your own policy:




**c.** In the Review Policy section, which should be pre-selected, specify a name for this policy (we call it splice access):



**d.** Paste the following JSON object specification into the **Policy Document** field and then modify the highlighted values to specify your bucket name and folder path.

```
{
    "Version": "2017-04-17",
    "Statement": [
            "Effect": "Allow",
            "Action": [
              "s3:PutObject",
              "s3:GetObject",
              "s3:GetObjectVersion",
              "s3:DeleteObject",
              "s3:DeleteObjectVersion"
            "Resource": "arn:aws:s3:::<bucket name>/<prefix>/*"
        } ,
            "Effect": "Allow",
            "Action": "s3:ListBucket",
            "Resource": "arn:aws:s3:::<bucket name>",
            "Condition": {
                "StringLike": {
                    "s3:prefix": [
                        "<prefix>/*"
            }
        },
            "Effect": "Allow",
            "Action": "s3:GetAccelerateConfiguration",
            "Resource": "arn:aws:s3:::<bucket name>"
    ]
```

e. Click Validate Policy to verify that your policy settings are valid.




f. Click Create Policy to create and save the policy.


### 5. Add Splice Machine as a user:

After you create the policy:

- a. Select Users from the left-hand navigation pane.
- b. Click Add User.
- c. Enter a User name (we've used SpliceMachine) and select Programmatic access as the access type:




- d. Click Attach existing policies directly.
- e. Select the policy you just created and click Next:



f. Review your settings, then click Create User.

### 6. Save your access credentials

You **must** write down your Access key ID and secret access key; you will be unable to recover the secret access key.



# Importing Data Into Your Splice Machine Database

This tutorial guides you through importing (loading) data into your Splice Machine database. It contains these topics:

Tutorial Topic	Description	
1: Tutorial Overview	This topic. Introduces the import options that are available to you and helps you determine which option best meets your needs.	
2: Parameter Usage	Provides detailed specifications of the parameter values you must supply to the import procedures.	
3: Input Data Handling	Provides detailed information and tips about input data handling during ingestion.	
4: Error Handling	Helps you to understand and use logging to discover and repair any input data problems that occur during an ingestion process.	
5: Usage Examples	Walks you through examples of importing data with the SYSCS_UTIL.IMPORT_DATA, SYSCS_UTIL.UPSERT_DATA_FROM_FILE, and SYSCS_UTIL.MERGE_DATA_FROM_FILE system procedures.	
6: Bulk HFile Examples	Walks you through examples of using the SYSCS_UTIL.BULK_IMPORT_HFILE system procedure.	
7: Importing TPCH Data	Walks you through importing TPCH sample data into your database.	

## **Overview of Importing Data Into Your Database**

The remainder of this topic introduces you to importing (loading) data into your Splice Machine database. It summarizes the different import procedures we provide, presents a quick look at the procedure declarations, and helps you to decide which one matches your conditions. It contains the following sections:

- >> Data Import Procedures summarizes the built-in system procedures that you can use to import your data.
- Which Procedure Should I Use to Import My Data? presents a decision tree that makes it easy to decide which procedure to use for your circumstances.
- >> Import Procedures Syntax shows the syntax for our import procedures.


# **Data Import Procedures**

Splice Machine includes four different procedures for importing data into your database, three of which use identical syntax; the fourth provides a more behind-the-scenes method that is quicker when loading large data sets, but requires more work and care on your part. The table below summarizes these import procedures:

System Procedure	Description
SYSCS_UTIL.IMPORT_DATA	Imports data into your database, creating a new record in your table for each record in the imported data. SYSCS_UTIL.IMPORT_DATA inserts the default value of each column that is not specified in the input.
SYSCS_UTIL.UPSERT_DATA_FROM_FILE	Imports data into your database, creating new records and *updating existing records* in the table. Identical to SYSCS_UTIL.IMPORT_DATA except that will update matching records. SYSCS_UTIL.UPSERT_DATA_FROM_FILE also inserts or updates the value in the table of each column that is not specified in the input; inserting the default value (or NULL if there is no default) for that column.
SYSCS_UTIL.MERGE_DATA_FROM_FILE	Imports data into your database, creating new records and *updating existing records* in the table. Identical to SYSCS_UTIL.UPSERT_DATA_FROM_FILE except that it does not replace values in the table for unspecified columns when updating an existing record in the table.
SYSCS_UTIL.BULK_IMPORT_HFILE	Takes advantage of HBase bulk loading to import table data into your database by temporarily converting the table file that you're importing into HFiles, importing those directly into your database, and then removing the temporary HFiles. This procedure uses syntax very similar to the other import procedures and has improved performance for large tables; however, the bulk HFile import requires extra work on your part and lacks constraint checking.

## Which Procedure Should I Use to Import My Data?

The following diagram helps you decide which of our data importation procedures best fits your needs:



#### **Notes**

- >> The IMPORT\_DATA procedure imports new records into a database. The UPSERT\_DATA\_FROM\_FILE and MERGE\_DATA\_FROM\_FILE procedures import new records and update existing records. Importing all new records is faster because the database doesn't need to check if the record already exists in the database.
- >> If your table contains auto-generated column values and you don't want those values overwritten when a record gets updated, use the MERGE DATA FROM FILE procedure (UPSERT DATA FROM FILE will overwrite).
- >> The BULK\_IMPORT\_HFILE procedure is great when you're importing a very large dataset and need extra performance. However, it does not perform constraint checking.

# **Import Procedures Syntax**

Here are the declarations of our four data import procedures; as you can see, three of our four import procedures use identical parameters, and the fourth (SYSCS UTIL.BULK IMPORT HFILE) adds a couple extra parameters at the end:

```
call SYSCS UTIL.BULK IMPORT HFILE (
   schemaName,
   tableName,
   insertColumnList | null,
   fileName,
   columnDelimiter | null,
   characterDelimiter | null,
   timestampFormat | null,
   dateFormat | null,
   timeFormat | null,
   maxBadRecords,
   badRecordDirectory | null,
   oneLineRecords | null,
   charset | null,
   bulkImportDirectory,
   skipSampling
);
```

You'll find descriptions and detailed reference information for all of these parameters in the <u>Import Parameters</u> topic of this tutorial.

And you'll find detailed reference descriptions of all four procedures in our SQL Reference Manual.

### See Also

- >> Importing Data: Input Parameters
- >> Importing Data: Input Data Handling
- >> Importing Data: Error Handling
- >> Importing Data: Usage Examples
- >> Importing Data: Bulk HFile Examples

- >> Importing Data: Importing TPCH Data
- >> SYSCS\_UTIL.IMPORT\_DATA
- >> SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE
- SYSCS\_UTIL.MERGE\_DATA\_FROM\_FILE
- >> SYSCS UTIL.BULK IMPORT HFILE

# Importing Data: Specifying the Import Parameter Values

This topic first shows you the syntax of each of the four import procedures, and then provides detailed information about the input parameters you need to specify when calling one of the Splice Machine data ingestion procedures.

## **Import Procedures Syntax**

Three of our four data import procedures use identical parameters:

```
SYSCS UTIL. IMPORT DATA (
SYSCS UTIL.UPSERT DATA FROM FILE (
SYSCS UTIL.MERGE DATA FROM FILE (
   schemaName,
   tableName,
   insertColumnList | null,
   fileOrDirectoryName,
   columnDelimiter | null,
   characterDelimiter | null,
   timestampFormat | null,
   dateFormat | null,
   timeFormat | null,
   badRecordsAllowed,
   badRecordDirectory | null,
   oneLineRecords | null,
   charset | null
 );
```

The fourth procedure, SYSCS UTIL.BULK IMPORT HFILE, adds a couple extra parameters at the end:

```
SYSCS UTIL.BULK IMPORT HFILE
  ( schemaName,
   tableName,
   insertColumnList | null,
   fileName,
   columnDelimiter | null,
   characterDelimiter | null,
   timestampFormat | null,
   dateFormat | null,
   timeFormat | null,
   maxBadRecords,
   badRecordDirectory | null,
   oneLineRecords | null,
   charset | null,
   bulkImportDirectory,
   skipSampling
 );
```

# **Overview of Parameters Used in Import Procedures**

All of the Splice Machine data import procedures share a number of parameters that describe the table into which you're importing data, a number of input data format details, and how to handle problematic records.

The following table summarizes these parameters. Each parameter name links to its reference description, found below the table:

Category	Parameter	Description	Example Value
Table Info	schemaName	The name of the schema of the table in which to import.	SPLICE
IIIIO	tableName	The name of the table in which to import	playerTeams
Data Location	<u>insertColumnList</u>	The names, in single quotes, of the columns to import. If this is null, all columns are imported.	'ID, TEAM'
	fileOrDirectoryName	Either a single file or a directory. If this is a single file, that file is imported; if this is a directory, all of the files in that directory are imported. You can import compressed or uncompressed files.	/data/mydata/ mytable.csv  's3a://splice- benchmark-data/ flat/TPCH/100/
		SYSCS_UTIL.MERGE_DATA_FROM_ FILE procedure only works with single files; you cannot specify a directory name when calling SYSCS_UTIL.MERGE_DATA_FROM_ FILE.	region'
		On a cluster, the files to be imported MUST be on S3, HDFS (or MapR-FS). If you're using our Database Service product, files can only be imported from S3.	
Data Formats	oneLineRecords	A Boolean value that specifies whether (true) each record in the import file is contained in one input line, or (false) if a record can span multiple lines.	true
	charset	The character encoding of the import file. The default value is UTF-8.	null
	<u>columnDelimiter</u>	The character used to separate columns, Specify null if using the comma (, ) character as your delimiter.	" "
	characterDelimiter	The character is used to delimit strings in the imported data.	1111

Category	Parameter	Description	Example Value
	timestampFormat	The format of timestamps stored in the file. You can set this to null if there are no time columns in the file, or if the format of any timestamps in the file match the Java.sql.Timestamp default format, which is: "yyyy-MM-dd HH:mm:ss".  All of the timestamps in the file you are importing must use the same format.	'yyyy-MM-dd HH:mm:ss.SSZ'
	dateFormat	The format of datestamps stored in the file. You can set this to null if there are no date columns in the file, or if the format of any dates in the file match pattern: "yyyy-MM-dd".	yyyy-MM-dd
	timeFormat	The format of time values stored in the file. You can set this to null if there are no time columns in the file, or if the format of any times in the file match pattern: "HH:mm:ss".	HH:mm:ss
Problem Logging	badRecordsAllowed	The number of rejected (bad) records that are tolerated before the import fails. If this count of rejected records is reached, the import fails, and any successful record imports are rolled back. Specify 0 to indicate that no bad records are tolerated, and specify -1 to indicate that all bad records should be logged and allowed.	25
	badRecordDirectory	The directory in which bad record information is logged. Splice Machine logs information to the <import_file_name>.bad file in this directory; for example, bad records in an input file named foo.csv would be logged to a file named badRecordDirectory/foo.csv.bad.</import_file_name>	'importErrsDir'
		On a cluster, this directory <b>MUST be on S3, HDFS (or MapR-FS)</b> . If you're using our Database Service product, files can only be imported from S3.	

Category	Parameter	Description	Example Value
Bulk HFile Import	bulkImportDirectory (outputDirectory)	For SYSCS_UTIL.BULK_IMPORT_HFILE, this is the name of the directory into which the generated HFiles are written prior to being imported into your database.  For the SYSCS_UTIL.COMPUTE_SPLIT_KEY procedure, where it is named outputDirectory, this parameter specifies the directory into which the split keys are written.	hdfs:///tmp/ test_hfile_import/
	skipSampling	The skipSampling parameter is a Boolean value that specifies how you want the split keys used for the bulk HFile import to be computed. Set to false to have SYSCS_UTIL.BULK_IMPORT_HFILE automatically determine splits for you.  This parameter is only used with the SYSCS_UTIL.BULK_IMPORT_HFILE system procedure.	false

## **Import Parameters Reference**

This section provides reference documentation for all of the data importation parameters.

#### schemaName

The schemaName is a string that specifies the name of the schema of the table into which you are importing data.

Example: SPLICE

#### tableName

The tableName is a string that specifies the name of the table into which you are importing data.

Example: playerTeams

#### insertColumnList

The insertColumnList parameter is a string that specifies the names, in single quotes, of the columns you wish to import. If this is null, all columns are imported.

If you don't specify an insertColumnList and your input file contains more columns than are in the table, then the the extra columns at the end of each line in the input file are ignored. For example, if your table contains columns (a, b, c) and your file contains columns (a, b, c, d, e), then the data in your file's d and e columns will be ignored.

>> If you do specify an insertColumnList, and the number of columns doesn't match your table, then any other columns in your table will be replaced by the default value for the table column (or NULL if there is no default for the column). For example, if your table contains columns (a, b, c) and you only want to import columns (a, c), then the data in table's b column will be replaced with the default value for that column.

Example: ID, TEAM

See <u>Importing and Updating Records</u> for additional information about handling of missing, generated, and default values during data importation.

### fileOrDirectoryName

The fileOrDirectoryName (or fileName) parameter is a string that specifies the location of the data that you're importing. This parameter is slightly different for different procedures:

- >> For the SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE or SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE procedures, this is either a single file or a directory. If this is a single file, that file is imported; if this is a directory, all of the files in that directory are imported.
- >>> For the SYSCS\_UTIL.MERGE\_DATA\_FROM\_FILE and SYSCS\_UTIL.BULK\_IMPORT\_HFILE procedure, this can only be a single file (directories are not allowed).

#### NOTE:

On a cluster, the files to be imported **MUST** be on **S3**, **HDFS** (or **MapR-FS**), as must the badRecordDirectory directory. If you're using our Database Service product, files can only be imported from **S3**. The files must also be readable by the hbase user.

**Example:** data/mydata/mytable.csv

### **Importing from S3**

If you are importing data that is stored in an S3 bucket on AWS, you need to specify the data location in an s3a URL that includes access key information.

**Example:** s3a://splice-benchmark-data/flat/TPCH/100/region

See <u>Specifying Your Input Data Location</u> for additional information about specifying your input data location.

### **Importing Compressed Files**

Note that files can be compressed or uncompressed, including BZIP2 compressed files.

Importing multiple files at once improves parallelism, and thus speeds up the import process. Uncompressed files can be imported faster than compressed files. When using compressed files, the compression algorithm makes a difference; for example,

- y gzip-compressed files cannot be split during importation, which means that import work on such files cannot be performed in parallel.
- >> In contrast, bzip2-compressed files can be split and thus can be imported using parallel tasks. Note that bzip2 is CPU intensive compared to LZ4 or LZ0, but is faster than gzip because files can be split.

#### oneLineRecords

The oneLineRecords parameter is a Boolean value that specifies whether each line in the import file contains one complete record:

- >> If you specify true or null, then each record is expected to be found on a single line in the file.
- >> If you specify false, records can span multiple lines in the file.

Multi-line record files are slower to load, because the file cannot be split and processed in parallel; if you import a directory of multiple line files, each file as a whole is processed in parallel, but no splitting takes place.

Example: true

#### charset

The charset parameter is a string that specifies the character encoding of the import file. The default value is UTF-8.

NOTE: Currently, any value other than UTF-8 is ignored, and UTF-8 is used.

Example: null

#### columnDelimiter

The columnDelimiter parameter is a string that specifies the character used to separate columns, You can specify null if using the comma (, ) character as your delimiter.

In addition to using plain text characters, you can specify the following special characters as delimiters:

Special character	Display	
\t	Tab	

Special character	Display
\f	Formfeed
\b	Backspace
\\	Backslash
^a (or ^A)	NOTE: If you are using a script file from the splice> command line, your script can contain the actual Control-a character as the value of this parameter.

### Example: '|'

See Column Delimiters for additional information about column delimiters.

### characterDelimiter

The characterDelimiter parameter is a string that specifies which character is used to delimit strings in the imported data. You can specify null or the empty string to use the default string delimiter, which is the double-quote (").

In addition to using plain text characters, you can specify the following special characters as delimiters:

Special character	Display
\t	Tab
\f	Formfeed
\b	Backspace
\\	Backslash

Special character	Display		
^a (or ^A)	Control-a		
		NOTE: If you are using a script file from the splice> command line, your script can contain the actual Control-a character as the value of this parameter.	

#### Notes:

- >> If your input contains control characters such as newline characters, make sure that those characters are embedded within delimited strings.
- >> To use the single quote (') character as your string delimiter, you need to escape that character. This means that you specify four quotes (''') as the value of this parameter. This is standard SQL syntax.

#### Example: ''

See <u>Character Delimeters</u> for additional information about character delimiters.

### timestampFormat

The timestampFormat parameter specifies the format of timestamps in your input data. You can set this to null if either:

- >> there are no time columns in the file
- >>> all time stamps in the input match the Java.sql.Timestamp default format, which is: "yyyy-MM-dd HH:mm:ss".



All of the timestamps in the file you are importing must use the same format.

Splice Machine uses the following Java date and time pattern letters to construct timestamps:

Pattern Letter	Description	Format(s)
У	year	уу ог уууу
М	month	MM
d	day in month	dd

Pattern Letter	Description	Format(s)
h	hour (0-12)	hh
Н	hour (0-23)	нн
m	minute in hour	mm
S	seconds	ss
S	tenths of seconds	s, ss, sss, ssss, sssss or ssssss*
		*Specify SSSSSS to allow a variable number (any number) of digits after the decimal point.
Z	time zone text	e.g. Pacific Standard time
Z	time zone, time offset	e.g0800

The default timestamp format for Splice Machine imports is: yyyy-MM-dd HH:mm:ss, which uses a 24-hour clock, does not allow for decimal digits of seconds, and does not allow for time zone specification.

**NOTE:** The standard Java library does not support microsecond precision, so you **cannot** specify millisecond (S) values in a custom timestamp format and import such values with the desired precision.

### Timestamps and Importing Data at Different Locations

Note that timestamp values are relative to the geographic location at which they are imported, or more specifically, relative to the timezone setting and daylight saving time status where the data is imported.

This means that timestamp values from the same data file may appear differently after being imported in different timezones.

### **Examples**

The following tables shows valid examples of timestamps and their corresponding format (parsing) patterns:

Timestamp value	Format Pattern	Notes
2013-03-23 09:45:00	yyyy-MM-dd HH:mm:ss	This is the default pattern.
2013-03-23 19:45:00.98-05	yyyy-MM-dd HH:mm:ss.SSZ	This pattern allows up to 2 decimal digits of seconds, and requires a time zone specification.

Timestamp value	Format Pattern	Notes
2013-03-23 09:45:00-07	yyyy-MM-dd HH:mm:ssZ	This patterns requires a time zone specification, but does not allow for decimal digits of seconds.
2013-03-23 19:45:00.98-0530	yyyy-MM-dd HH:mm:ss.SSZ	This pattern allows up to 2 decimal digits of seconds, and requires a time zone specification.
2013-03-23 19:45:00.123	yyyy-MM-dd HH:mm:ss.SSS	This pattern allows up to 3 decimal digits of seconds, but does not allow a time zone specification.
2013-03-23 19:45:00.12		Note that if your data specifies more than 3 decimal digits of seconds, an error occurs.
2013-03-23 19:45:00.1298	yyyy-MM-dd HH:mm:ss.SSSS	This pattern allows up to 4 decimal digits of seconds, but does not allow a time zone specification.

See <u>Time and Date Formats in Input Records</u> for additional information about date, time, and timestamp values.

#### dateFormat

The dateFormat parameter specifies the format of datestamps stored in the file. You can set this to null if either:

- >> there are no date columns in the file
- >> the format of any dates in the input match this pattern: "yyyy-MM-dd".

Example: yyyy-MM-dd

See <u>Time and Date Formats in Input Records</u> for additional information about date, time, and timestamp values.

#### timeFormat

The timeFormat parameter specifies the format of time values in your input data. You can set this to null if either:

- >> there are no time columns in the file
- >> the format of any times in the input match this pattern: "HH:mm:ss".

Example: HH:mm:ss

See <u>Time and Date Formats in Input Records</u> for additional information about date, time, and timestamp values.

#### badRecordsAllowed

The badRecordsAllowed parameter is integer value that specifies the number of rejected (bad) records that are tolerated before the import fails. If this count of rejected records is reached, the import fails, and any successful record imports are rolled back.

These values have special meaning:

- >> If you specify -1 as the value of this parameter, all record import failures are tolerated and logged.
- >> If you specify 0 as the value of this parameter, the import will fail if even one record is bad.

Example: 25

### badRecordDirectory

The badRecordDirectory parameter is a string that specifies the directory in which bad record information is logged. The default value is the directory in which the import files are found.

Splice Machine logs information to the <import\_file\_name>.bad file in this directory; for example, bad records in an input file named foo.csv would be logged to a file named badRecordDirectory/foo.csv.bad.

The badRecordDirectory directory must be writable by the hbase user, either by setting the user explicity, or by opening up the permissions; for example:

```
sudo -su hdfs hadoop fs -chmod 777 /badRecordDirectory
```

Example: 'importErrsDir'

### bulkImportDirectory

**NOTE:** This parameter is only used with the SYSCS\_UTIL.BULK\_IMPORT\_HFILE system procedure.

The bulkImportDirectory parameter is a string that specifies the name of the directory into which the generated HFiles are written prior to being imported into your database. The generated files are automatically removed after they've been imported.

**Example:** 'hdfs:///tmp/test hfile import/'

Please review the <u>Bulk HFile Import Walkthrough</u> topic to understand how importing bulk HFiles works.

#### skipSampling

**NOTE:** This parameter is only used with the SYSCS\_UTIL.BULK\_IMPORT\_HFILE system procedure.

The skipSampling parameter is a Boolean value that specifies how you want the split keys used for the bulk HFile import to be computed:

- If skipSampling is true, you need to use our SYSCS\_UTIL.COMPUTE\_SPLIT\_KEY and SYSCS\_UTIL.SYSCS\_SPLIT\_TABLE\_OR\_INDEX\_AT\_POINTS system procedures to manually split your table before calling SYSCS\_UTIL.BULK\_IMPORT\_HFILE. This allows you more control over the splits, but adds a layer of complexity.
- >> If skipSampling is false, then SYSCS\_UTIL.BULK\_IMPORT\_HFILE samples your input data and computes the table splits for you, in the following steps. It:
  - 1. Scans (sample) the data
  - 2. Collects a rowkey histogram
  - 3. Uses that histogram to calculate the split key for the table
  - 4. Uses the calculated split key to split the table into HFiles

Example: false

Please review the <u>Bulk HFile Import Walkthrough</u> topic to understand how importing bulk HFiles works.

## See Also

- >> Importing Data: Tutorial Overview
- Importing Data: Input Data Handling
- >> Importing Data: Error Handling
- >> Importing Data: Usage Examples
- >> Importing Data: Bulk HFile Examples
- >> Importing Data: Importing TPCH Data
- >> SYSCS UTIL.IMPORT DATA
- >> SYSCS UTIL.UPSERT DATA FROM FILE
- >> SYSCS UTIL.MERGE DATA FROM FILE
- >> SYSCS\_UTIL.BULK\_IMPORT\_HFILE

# **Importing Data: Input Considerations**

This topic provides detailed information about how the parameter values you specify when importing data are handled by Splice Machine's built-in import procedures.

For a summary of our import procedures and determining which to use, please see Importing Data: Overview.

For reference descriptions of the parameters used by those import procedures, please see Importing Data: Parameter Usage.

This topic includes the following sections:

Section	Description
Specifying Your Input Data Location	Describes how to specify the location of your input data when importing.
Input Data File Format	Information about input data files, including importing compressed files and multi-line records.
Delimiters in Your Input Data	Discusses the use of column and characters delimiters in your input data.
Time and Date Formats in Input Records	All about the date, time, and timestamp values in your input data.
Importing and Updating Records	Discusses importing new records and updating existing database records, handling missing values in the input data, and handling of generated and default values.
Importing CLOBs and BLOBs	Discussion of importing CLOBs and BLOBs into your Splice Machine database.
Scripting Your Imports	Shows you how to script your import processes.

## **Specifying Your Input Data Location**

Some customers get confused by the the fileOrDirectoryName parameter that's used in our import procedures. How you use this depends on whether you are importing a single file or a directory of files, and whether you're importing data into a standalone version or cluster version of Splice Machine. This section contains these three subsections:

- Standalone Version Input File Path
- >> HBase Input File Path
- >> AWS Input File Path

### Standalone Version Input File Path

If you are running a stand alone environment, the name or path will be to a file or directory on the file system. For example:

/users/myname/mydata/mytable.csv/users/myname/mydatadir

### **HBase Input File Path**

If you are running this on a cluster, the path is to a file on HDFS (or the MapR File system). For example:

```
/data/mydata/mytable.csv/data/myname/mydatadir
```

### **AWS S3 Input File Path**

Finally, if you're importing data from an S3 bucket, you need to supply your AWS access and secret key codes, and you need to specify an s3a URL. This is also true for logging bad record information to an S3 bucket directory, as will be the case when using our Database-as-Service product.

For information about configuring Splice Machine access on AWS, please review our <u>Configuring an S3 Bucket for Splice</u> <u>Machine Access</u> topic, which walks you through using your AWS dashboard to generate and apply the necessary credentials.

Once you've established your access keys, you can include them inline; for example:

```
call SYSCS_UTIL.IMPORT_DATA ('TPCH', 'REGION', null, 's3a://(access key):(secret ke
y)@splice-benchmark-data/flat/TPCH/100/region', '|', null, null, null, null, null, -1, 's3
a://(access key):(secret key)@splice-benchmark-data/flat/TPCH/100/importLog', true,
null);
```

Alternatively, you can specify the keys once in the core-site.xml file on your cluster, and then simply specify the s3a URL; for example:

```
call SYSCS_UTIL.IMPORT_DATA ('TPCH', 'REGION', null, 's3a://splice-benchmark-data/fl
at/TPCH/100/region', '|', null, null, null, 0, '/BAD', true, null);
```

To add your access and secret access keys to the core-site.xml file, define the fs.s3a.awsAccessKeyId and fs.s3a.awsSecretAccessKey properties in that file:

## **Input Data File Format**

This section contains the following information about the format of the input data files that you're importing:

- >> Importing Compressed Files
- >> Importing Multi-line Records
- >> Importing Large Datasets in Groups of Files

### **Importing Compressed Files**

We recommend importing files that are either uncompressed, or have been compressed with bz2 or 1z4 compression.

If you import files compressed with gzip, Splice Machine cannot distribute the contents of your file across your cluster nodes to take advantage of parallel processing, which means that import performance will suffer significantly with gzip files.

### **Importing Multi-line Records**

If your data contains line feed characters like CTRL-M, you need to set the oneLineRecords parameter to false. Splice Machine will accommodate to the line feeds; however, the import will take longer because Splice Machine will not be able to break the file up and distribute it across the cluster.

To improve import performance, avoid including line feed characters in your data and set the oneLineRecords parameter to true.

### Importing Large Datasets in Groups of Files

If you have a lot of data (100s of millions or billions of records), you may be tempted to create one massive file that contains all of your records and import that file; Splice Machine recommends against this; instead, we urge you to manage your data in smaller files. Specifically, we suggest that you split your data into files that are:

- >> approximately 40 GB
- >> have approximately 50 million records, depending on how wide your table is

If you have a lot of files, group them into multiple directories, and import each directory individually. For example, here is a structure our Customer Success engineers like to use:

- /data/mytable1/group1
- /data/mytable1/group2
- /data/mytable1/group3

## **Delimiters in Your Input Data**

This section discusses the delimiters that you use in your input data, in these subsections:

- >> Using Special Characters for Delimiters
- >> Column Delimiters
- Character Delimiters

## **Use Special Characters for Delimiters**

One common gotcha we see with customer imports is when the data you're importing includes a special character that you've designated as a column or character delimiter. You'll end up with records in your bad record directory and can spend hours trying to determine the issue, only to discover that it's because the data includes a delimiter character. This can happen with columns that contain data such as product descriptions.

#### **Column Delimiters**

The standard column delimiter is a comma (, ); however, we've all worked with string data that contains commas, and have figured out to use a different column delimiter. Some customers use the pipe (|) character, but frequently discover that it is also used in some descriptive data in the table they're importing.

In addition to using plain text characters, you can specify the following special characters as delimiters:

Special character	Display
\t	Tab
\f	Formfeed
\b	Backspace
\\	Backslash
^a (or ^A)	NOTE: If you are using a script file from the splice> command line, your script can contain the actual Control-a character as the value of this parameter.

We recommend using a control character like CTRL-A for your column delimiter. This is known as the SOH character, and is represented by 0x01 in hexadecimal. Unfortunately, there's no way to enter this character from the keyboard in the Splice Machine command line interface; instead, you need to create a script file and type the control character using a text editor like *vi* or *vim*:

- >> Open your script file in vi or vim.
- >> Enter into INSERT mode.
- >> Type CTRL-V then CTRL-A for the value of the column delimiter parameter in your procedure call. Note that this typically echoes as ^A when you type it in vi or vim.

### **Character Delimiters**

By default, the character delimiter is a double quote. This can produce the same kind of problems that we see with using a comma for the column delimiter: columns values that include embedded quotes or use the double quote as the symbol for inches. You can use escape characters to include the embedded quotes, but it's easier to use a special character for your delimiter.

We recommend using a control character like CTRL-A for your column delimiter. Unfortunately, there's no way to enter this character from the keyboard in the Splice Machine command line interface; instead, you need to <u>create a script file</u> and type the control character using a text editor like *vi* or *vim*:

- Open your script file in vi or vim.
- >> Enter into INSERT mode.
- >> Type CTRL-V then CTRL-G for the value of the character delimiter parameter in your procedure call. Note that this typically echoes as ^G when you type it in vi or vim.

## Time and Date Formats in Input Records

Perhaps the most common difficulty that customers have with importing their data is with date, time, and timestamp values.

Splice Machine adheres to the Java SimpleDateFormat syntax for all date, time, and timestamp values, SimpleDateFormat is described here:

[https://docs.oracle.com/javase/8/docs/api/java/text/SimpleDateFormat.html][1]{: target="\_blank"}

Splice Machine's implementation of SimpleDateFormat is case-sensitive; this means, for example, that a lowercase h is used to represent an hour value between 0 and 12, whereas an uppercase H is used to represent an hour between 0 and 23.

### **All Values Must Use the Same Format**

Splice Machine's Import procedures only allow you to specify one format each for the date, time, and timestamp columns in the table data you are importing. This means that, for example, every date in the table data must be in the same format.

All of the Date values in the file (or group of files) you are importing must use the same date format.

All of the Time values in the file (or group of files) you are importing must use the same time format.

All of the Timestamp values in the file (or group of files) you are importing must use the same timestamp format.

#### **Additional Notes**

A few additional notes:

- >> The Timestamp data type has a range of 1678-01-01 to 2261-12-31. Some customers have used dummy timestamp values like 9999-01-01, which will fail because the value is out of range for a timestamp. Note that this is not an issue with Date values.
- >> Splice Machine suggests that, if your data contains any date or timestamp values that are not in the format yyyy-MM-dd HH: mm:ss, you create a simple table that has just one or two columns and test importing the format. This is a simple way to confirm that the imported data is what you expect.

- >> Detailed information about each of these data types is found in our SQL Reference Manual:
  - >> Timestamp Data Type
  - >> Date Data Type
  - >> Time Data Type

## **Importing and Updating Records**

This section describes certain aspects of how records are imported and updated when you import data into your database, including these subsections:

- >> Inserting and Updating Column Values When Importing Data
- >> Inserting and Updated Generated or Default Values
- >> Handling Missing Values

### Inserting and Updating Column Values When Importing Data

This section summarizes what happens when you are importing, upserting, or merging records into a database table, based on:

- >> Whether you are importing a new record or updating an existing record.
- >> If the column is specified in your insertColumnList parameter.
- >> If the table column is a generated value or has a default value.

The important difference in actions taken when importing data occurs when you are updating an existing record with the UPSERT or MERGE and your column list does not contain the name of a table column:

- For newly inserted records, the default or auto-generated value is always inserted, as usual.
- >> If you are updating an existing record in the table with UPSERT, the default auto-generated value in that record is overwritten with a new value.
- >> If you are updating an existing record in the table with MERGE, the column value is not updated.

#### Importing a New Record Into a Database Table

The following table shows the actions taken when you are importing new records into a table in your database. These actions are the same for all three importation procedures (IMPORTing, UPSERTing, or MERGEing):

Column included in importColumnList?	Table column conditions	Action Taken
YES	N/A	Import value inserted into table column if valid; if not valid, a bad record error is logged.
NO	Has Default Value	Default value is inserted into table column.

Column included in importColumnList?	Table column conditions	Action Taken
	Is Generated Value	Generated value is inserted into table column.
	None	NULL is inserted into table column.

The table below shows what happens with default and generated column values when adding new records to a table using one of our import procedures; we use an example database table created with this statement:

```
CREATE TABLE myTable (

cola INT,

colB CHAR(12) DEFAULT 'myDefaultVal',

colC INT);
```

insertColumnList	Values in import record	Values inserted into database	Notes
"colA, colB, colC"	1,,2	[1,NULL,2]	
"colA, colB, colC"	3,de,4	[3,de,4]	
"colA, colB, colC"	1,2,	Error: column B wrong type	
"colA, colB, colC"	1, DEFAULT, 2	[1,"DEFAULT",2]	DEFAULT is imported as a literal value
Empty	1,,2	[1,myDefaultVal,2]	
Empty	3,de,4	[3,de,4]	
Empty	1,2,	Error: column B wrong type	
"colA, colC"	1,2	[1,myDefaultVal,2]	
"colA,colC"	3,4	[3,myDefaultVal,4]	

Note that the value `DEFAULT` in the imported file **is not interpreted** to mean that the default value should be applied to that column; instead:

>> If the target column in your database has a string data type, such as CHAR or VARCHAR, the literal value "DEFAULT" is

inserted into your database..

>> If the target column is not a string data type, an error will occur.

### Importing Into a Table that Contains Generated or Default Values

When you export a table with generated columns to a file, the actual column values are exported, so importing that same file into a different database will accurately replicate the original table values.

If you are importing previously exported records into a table with a generated column, and you want to import some records with actual values and apply generated or default values to other records, you need to split your import file into two files and import each:

- >> Import the file containing records with non-default values with the column name included in the insertColumnList.
- >> Import the file containing records with default values with the column name excluded from the insertColumnList.

### **Updating a Table Record with UPSERT**

The following table shows the action taken when you are using the SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE procedure to update an existing record in a database table:

Column included in importColumnList?	Table column conditions	Action Taken
YES	N/A	Import value updated in table column if valid; if not valid, a bad record error is logged.
NO	Has Default Value	Table column is overwritten with default value.
	Is Generated Value	Table column is overwritten with newly generated value.
	None	Table column is overwritten with NULL value.

### Updating a Table Record with MERGE

The following table shows the action taken when you are using the SYSCS\_UTIL.MERGE\_DATA\_FROM\_FILE procedure to update an existing record in a database table:

Column included in importColumnList?	Table column conditions	Action Taken
YES	N/A	Import value updated in table column if valid; if not valid, a bad record error is logged.
NO	N/A	Table column is not updated.

## **Importing CLOBs and BLOBs**

If you are importing CLOBs, pay careful attention to tips 4 and 7. Be sure to use special characters for both your column and character delimiters. If your CLOB data can span multiple lines, be sure to set the oneLineRecords parameter to false.

At this time, the Splice Machine import procedures do not import work with columns of type BLOB. You can create a virtual table interface (VTI) that reads the BLOBs and inserts them into your database.

## **Scripting Your Imports**

You can make import tasks much easier and convenient by creating *import scripts*. An import script is simply a call to one of the import procedures; once you've verified that it works, you can use and clone the script and run unattended imports.

An import script is simply a file in which you store splice> commands that you can execute with the run command. For example, here's an example of a text file named myimports.sql that we can use to import two csv files into our database:

```
call SYSCS_UTIL.IMPORT_DATA ('SPLICE','mytable1',null,'/data/mytable1/data.csv',nul
1,null,null,null,null,0,'/BAD/mytable1',null,null);call SYSCS_UTIL.IMPORT_DATA ('SPL
ICE','mytable2',null,'/data/mytable2/data.csv',null,null,null,null,null,0,'/BAD/myta
ble2',null,null);
```

To run an import script, use the splice> run command; for example:

```
splice> run 'myimports.sql';
```

You can also start up the splice command line interpreter with the name of a file to run; for example:

```
sqlshell.sh -f myimports.sql
```

In fact, you can script almost any sequence of Splice Machine commands in a file and run that script within the command line interpreter or when you start the interpreter.

### See Also

- >> Importing Data: Tutorial Overview
- >> Importing Data: Input Parameters
- >> Importing Data: Error Handling
- >> Importing Data: Usage Examples
- >> Importing Data: Bulk HFile Examples
- >> Importing Data: Importing TPCH Data
- >> SYSCS\_UTIL.IMPORT\_DATA
- >> SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE

- >> SYSCS\_UTIL.MERGE\_DATA\_FROM\_FILE
- >> SYSCS UTIL.BULK IMPORT HFILE

# **Importing Data: Logging and Error Handling**

This topic describes the logging and error handling features of Splice Machine data imports.

## Logging

Each of these import procedures includes a logging facility:

- >> SYSCS UTIL.IMPORT DATA
- >> SYSCS UTIL.UPSERT DATA FROM FILE
- >> SYSCS UTIL.MERGE DATA FROM FILE
- >> SYSCS UTIL.BULK IMPORT HFILE

Errors are logged to a file in the directory that you specify in the badRecordDirectory parameter when you call one of the procedures.

The badRecordDirectory parameter is a string that specifies the directory in which bad record information is logged. The default value is the directory in which the import files are found.

Splice Machine logs information to the <import\_file\_name>.bad file in this directory; for example, bad records in an input file named foo.csv would be logged to a file named badRecordDirectory/foo.csv.bad.

The badRecordDirectory directory must be writable by the hbase user, either by setting the user explicity, or by opening up the permissions; for example:

```
sudo -su hdfs hadoop fs -chmod 777 /badRecordDirectory
```

NOTE: On a cluster, the badRecordDirectory directory MUST be on S3, HDFS (or MapR-FS). If you're using our Database Service product, this directory must be on S3.

## **Stopping the Import Due to Too Many Errors**

All of the import procedures also take a badRecordsAllowed or maxBadRecords parameter, the value of which determines how many erroneous input data record errors are allowed before the import is stopped. If this count of rejected records is reached, the import fails, and any successful record imports are rolled back.

These badRecordsAllowed values have special meaning:

- → If you specify -1, all record import failures are tolerated and logged.
- >> If you specify 0, the import will fail as soon as one bad record is detected.

# **Managing Logging When Importing Multiple Files**

In addition to importing a single file, the <a href="SYSCS\_UTIL.IMPORT\_DATA">SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE</a> procedures can import all of the files in a directory.

When you are importing a large amount of data and have divided the files you are importing into groups, then it's a good idea to change the location of the bad record directory for each group; this will make debugging bad records a lot easier for you.

You can change the value of the badRecordDirectory to include your group name; for example, we typically use a strategy like the following:

Group Files Location	badRecordDirectory Parameter Value
/data/mytable1/group1	/BAD/mytable1/group1
/data/mytable1/group2	/BAD/mytable1/group2
/data/mytable1/group3	/BAD/mytable1/group3

You'll then be able to more easily discover where the problem record is located.

### See Also

- >> Importing Data: Tutorial Overview
- >> Importing Data: Input Parameters
- >> Importing Data: Input Data Handling
- >> Importing Data: Usage Examples
- >> Importing Data: Bulk HFile Examples
- >> Importing Data: Importing TPCH Data
- >> SYSCS UTIL.IMPORT DATA
- >> SYSCS UTIL.UPSERT DATA FROM FILE
- >> SYSCS UTIL.MERGE DATA FROM FILE
- >> SYSCS\_UTIL.BULK\_IMPORT\_HFILE

# Importing Data: Examples of Using the Import, Upsert, and Merge Procedures

This topic provides several examples of importing data into Splice Machine using our *standard* import procedures (IMPORT DATA, UPSERT DATA FROM FILE, and MERGE DATA FROM FILE):

- >> Example 1: Importing data into a table with fewer columns than in the file
- >> Example 2: How Upsert and Merge handle missing columns differently
- >> Example 3: Importing a subset of data from a file into a table
- >> Example 4: Specifying a timestamp format for an entire table
- >> Example 5: Importing strings with embedded special characters
- >> Example 6: Using single quotes to delimit strings

# Import, Upsert, or Merge?

The <u>Importing Data: Import Overview</u> topic provides the information you need to decide which of our import procedures best meets your needs, including an easy-to-use decision tree.

To summarize, our three standard import procedures operate very similarly, with a few key differences:

- >> IMPORT DATA imports data into your database, creating a new record in your table for each record in the imported data.
- >> UPSERT\_DATA\_FROM\_FILE import data into your database, creating new records and updating existing records in the table. If a column is not specified in the input, UPSERT\_DATA\_FROM\_FILE inserts the default value (or NULL, if no default) into that column in the imported record.
- >> MERGE\_DATA\_FROM\_FILE is identical to UPSERT\_DATA\_FROM\_FILE except that it does not replace values in the table for unspecified columns when updating an existing record in the table.

#### A fourth option works differently:

>>> BULK\_IMPORT\_HFILE creates temporary HFiles and imports from them, which improves import speed, but eliminates constraint checking and adds complexity. Examples of bulk HFile imports are found in the <a href="Importing Data: Bulk HFile">Importing Data: Bulk HFile</a> Examples tutorial topic.

# **Example 1: Importing data into a table with fewer columns than in the file**

If the table into which you're importing data has less columns than the data file that you're importing, how the "extra" data columns in the input data are handled depends on whether you specify an insertColumnList:

>> If you don't specify a specify an insertColumnList and your input file contains more columns than are in the table, then the extra columns at the end of each line in the input file are ignored. For example, if your table contains columns (a, b, c) and your file contains columns (a, b, c, d, e), then the data in your file's d and e columns will be ignored.

>> If you do specify an insertColumnList to IMPORT\_DATA or MERGE\_DATA, and the number of columns in your input file doesn't match the number in your table, then any other columns in your table will be replaced by the default value for the table column (or NULL if there is no default for the column). For example, if your table contains columns (a, b, c) and you only want to import columns (a, c), then the data in table's b column will be replaced with the default value (or NULL) for that column.

Here's an example that does not specify a column list. If you create a table with this statement:

```
CREATE TABLE playerTeams(ID int primary key, Team VARCHAR(32));
```

And your data file looks like this:

```
1, Cards, Molina, Catcher2, Giants, Posey, Catcher3, Royals, Perez, Catcher
```

When you import the file into playerTeams, only the first two columns are imported:

### **How Missing Columns are Handled With an Insert Column List**

In this example, we'll illustrate how the different data importation procedures modify columns in your table when you've specified an insertColumnList that is not 1-to-1 with the columns in your table.

The SYSCS\_UTIL.IMPORT\_DATA and SYSCS\_UTIL.UPSERT\_DATA\_FROM\_FILE procedures handle this situation in the same way, assigning default values (or NULL if no default is defined) to any table column that is not being inserted or updated from the input data file. The SYSCS\_UTIL.MERGE\_DATA\_FROM\_FILE handles this differently: it does not overwrite generated values when updating records.

**NOTE:** This distinction is particularly important when loading record updates into a table with auto-generated column values that you do not want overwritten.

We'll create two sample tables, populate each with the same data, and load the same input file data into each to illustrate the differences between how the Upsert and Merge procedures.

```
CREATE SCHEMA test;
SET SCHEMA test;
CREATE TABLE testUpsert (
       al INT,
       bl INT,
       c1 INT GENERATED BY DEFAULT AS IDENTITY(start with 1, increment by 1),
       d1 INT DEFAULT 999,
       PRIMARY KEY (a1)
);
CREATE TABLE testMerge (
       al INT,
       bl INT,
       c1 INT GENERATED BY DEFAULT AS IDENTITY(start with 1, increment by 1),
       d1 INT DEFAULT 999,
       PRIMARY KEY (a1)
);
INSERT INTO testUpsert(a1,b1) VALUES (1,1), (2,2), (3,3), (6,6);
splice> select * from testUpsert;
    |B1 |C1
                |1
        | 1
                             1999
1
             12
        12
2
                             1999
3
        13
                  | 3
                             1999
               | 4
         16
                          |999
4 rows selected
INSERT INTO testMerge (a1,b1) VALUES (1,1), (2,2), (3,3), (6,6);
splice> select * from testMerge;
A1 |B1 |C1
                             |D1
               |1
        11
                            1999
                  |2
        |2
2
                             1999
             | 3
| 4
                             1999
3
        13
        16
                             1999
4 rows selected
```

Note that column c1 contains auto-generated values, and that column `d1` has the default value 999.

Here's the data that we're going to import from file ttest.csv:

```
0 | 0
1 | 2
2 | 4
3 | 6
4 | 8
```

Now, let's call UPSERT DATA FROM FILE and MERGE DATA FROM FILE and see how the results differ:

```
CALL SYSCS UTIL.UPSERT DATA FROM FILE('TEST', 'testUpsert', 'a1, b1', '/Users/garyh/Document
s/ttest.csv','|',null,null,null,null,0,'/var/tmp/bad/',false,null);
rowsImported | failedRows | files | dataSize
                                                          |failedLog
               10
                                11
                                         120
                                                           NONE
splice> SELECT * FROM testUpsert;
A1 |B1 |C1 |D1
                |10001
                         1999
       10
1
       12
                 |10002
                          1999
        | 4
2
                 |10003
                          1999
3
       16
                 110004
                          1999
       | 8
                 |10005
4
                          1999
       16
               | 4
                           1999
6 rows selected
CALL SYSCS UTIL.MERGE DATA FROM FILE('TEST','testMerge','a1,b1','/Users/garyh/Documents/
ttest.csv','|',null,null,null,null,0,'/var/tmp/bad/',false,null);
rowsUpdated | rowsInserted | failedRows
                                          |files
   |failedLog
3
                                10
               12
                                                 | 1
                                                          12
              INONE
splice> select * from testMerge;
A1 |B1 |C1 |D1
              |10001 |999
|1 |999
       10
1
        12
2
        | 4
                 12
                          1999
3
        16
                 | 3
                           1999
                 |10002
4
       | 8
                          |999
              | 4
       | 6
                           1999
6 rows selected
```

#### You'll notice that:

- >> The generated column (c1) is not included in the insertColumnList parameter in these calls.
- >> The results are identical except for the values in the generated column.
- >> The generated values in c1 are not updated in existing records when merging data, but are updated when upserting data.

### **Example 3: Importing a subset of data from a file into a table**

This example uses the same table and import file as does the previous example, and it produces the same results. The difference between these two examples is that this one explicitly imports only the first two columns (which are named ID and TEAM) of the file and uses the IMPORT DATA procedure:

## **Example 4: Specifying a timestamp format for an entire table**

This examples demonstrates how you can use a single timestamp format for the entire table by explicitly specifying a single timeStampFormat. Here's the data:

```
Mike,2013-04-21 09:21:24.98-05
Mike,2013-04-21 09:15:32.78-04
Mike,2013-03-23 09:45:00.68-05
```

You can then import the data with the following call:



Note that the time shown in the imported table depends on the timezone setting in the server timestamp. In other words, given the same csv file, if imported on different servers with timestamps set to different time zones, the value in the table shown will be different. Additionally, daylight savings time may account for a 1-hour difference if timezone is specified.

# **Example 5: Importing strings with embedded special characters**

This example imports a csv file that includes newline (Ctrl-M) characters in some of the input strings. We use the default double-quote character as our character delimiter to import data such as the following:

```
1, This field is one line, Able
2, "This field has two lines
This is the second line of the field", Baker
3, This field is also just one line, Charlie
```

We then use the following call to import the data:

```
SYSCS_UTIL.IMPORT_DATA('SPLICE', 'MYTABLE', null, 'data.csv', '\t', null, null, null, null, null, 0, 'importErrsDir', false, null);
```

We can also explicitly specify double quotes (or any other character) as our delimiter character for strings:

```
SYSCS_UTIL.IMPORT_DATA('SPLICE', 'MYTABLE', null, 'data.csv', '\t', '"', null, null, null, null, 0, 'importErrsDir', false, null);
```

### **Example 6: Using single quotes to delimit strings**

This example performs the same import as the previous example, simply substituting single quotes for double quotes as the character delimiter in the input:

```
1, This field is one line, Able
2, 'This field has two lines
This is the second line of the field', Baker
3, This field is also just one line, Charlie
```

Note that you must escape single quotes in SQL, which means that you actually define the character delimiter parameter with four single quotes, as shown here:

```
SYSCS_UTIL.IMPORT_DATA('SPLICE', 'MYTABLE', null, 'data.csv', '\t', '''', null, null, null, null, 0, 'importErrsDir', false, null);
```

# See Also

- >> Importing Data: Tutorial Overview
- >> Importing Data: Input Parameters
- >> Importing Data: Input Data Handling
- >> Importing Data: Error Handling
- >> Importing Data: Bulk HFile Examples
- >> Importing Data: Importing TPCH Data
- >> SYSCS UTIL.IMPORT DATA
- >> SYSCS UTIL.UPSERT DATA FROM FILE
- >> SYSCS UTIL.MERGE DATA FROM FILE
- >> SYSCS\_UTIL.BULK\_IMPORT\_HFILE

# Importing Data With the Bulk HFile Import Procedure

This tutorial describes how to import data using HFiles into your Splice Machine database with the <a href="mailto:syscs\_util.bulk\_import\_hfile">SYSCS\_UTIL.BULK\_IMPORT\_HFILE</a> system procedure. This topic includes these sections:

- >> How Importing Your Data as HFiles Works presents an overview of using the HFile import functions.
- >>> <u>Configuration Settings</u> describes any configuration settings that you may need to modify when using the <u>SYSCS\_UTIL\_BULK\_IMPORT\_HFILE</u> procedure to import data into your database.
- >> <u>Importing Data From the Cloud</u> links to our instructions for configuring Splice Machine access to your data in the cloud.
- Manually Computing Table Splits outlines the steps you use to manually compute table splits, if you prefer to not have that handled automatically.
- >>> <u>Examples of Using SYSCS\_UTIL.BULK\_IMPORT\_HFILE</u> walks through using this procedure both with automatic table splits and with two different methods of manually computing table splits.

Our Importing Data: Usage Examples topic walks you through using our standard import procedures (SYSCS\_UTIL.IMPORT\_DATA, SYSCS\_UTIL.SYSCS\_UPSERT\_DATA\_FROM\_FILE, and SYSCS\_UTIL.SYSCS\_MERGE\_DATA\_FROM\_FILE), which are simpler to use, though their performance is slightly lower than importing HFiles.



Bulk importing HFiles boosts import performance; however, constraint checking is not applied to the imported data. If you need constraint checking, use one of our standard import procedures.

# How Importing Your Data as HFiles Works

Our HFile data import procedure leverages HBase bulk loading, which allows it to import your data at a faster rate; however, using this procedure instead of our standard <a href="SYSCS\_UTIL.IMPORT\_DATA">SYSCS\_UTIL.IMPORT\_DATA</a> procedure means that constraint checks are not performing during data importation.

You import a table as HFiles using our SYSCS\_UTIL.BULK\_IMPORT\_HFILE procedure, which temporarily converts the table file that you're importing into HFiles, imports those directly into your database, and then removes the temporary HFiles.

Before it generate HFiles, SYSCS\_UTIL.BULK\_IMPORT\_HFILE must determine how to split the data into multiple regions by looking at the primary keys and figuring out which values will yield relatively evenly-sized splits; the objective is to compute splits such that roughly the same number of table rows will end up in each split.

You have two choices for determining the table splits:

>> You can have SYSCS\_UTIL.BULK\_IMPORT\_HFILE scan and analyze your table to determine the best splits automatically by calling SYSCS\_UTIL.BULK\_IMPORT\_HFILE with the skipSampling parameter set to true. We walk you through using this approach in the first example below, <a href="Example 1: Bulk HFile Import with Automatic Table Splitting">Example 1: Bulk HFile Import with Automatic Table Splitting</a>

- >> You can compute the splits yourself and then call SYSCS\_UTIL.BULK\_IMPORT\_HFILE with the skipSampling parameter set to false. Computing the splits requires these steps, which are described in the next section, Manually Computing Table Splits.
  - 1. Determine which values make sense for splitting your data into multiple regions. This means looking at the primary keys for the table and figuring out which values will yield relatively evenly-sized (in number of rows) splits.
  - 2. Call our system procedures to compute the HBase-encoded keys and set up the splits inside your Splice Machine database.
  - 3. Call the SYSCS\_UTIL.BULK\_IMPORT\_HFILE procedure with the skipSampling parameter to false to perform the import.

# **Configuration Settings**

Due to how Yarn manages memory, you need to modify your YARN configuration when bulk-importing large datasets. Make these two changes in your Yarn configuration:

```
yarn.nodemanager.pmem-check-enabled=false
yarn.nodemanager.vmem-check-enabled=false
```

# Importing Data From the Cloud

If you are importing data that is stored in an S3 bucket on AWS, you need to specify the data location in an s3a URL that includes access key information. Our Configuring an S3 Bucket for Splice Machine Access walks you through using your AWS dashboard to generate and apply the necessary credentials.

# **Manually Computing Table Splits**

If you're computing splits for your import (and calling the <code>SYSCS\_UTIL.BULK\_IMPORT\_HFILE</code> procedure with <code>skipSampling</code> parameter to <code>false</code>), you need to select one of these two methods of computing the table splits:

>> You can call <a href="mailto:syscs\_split\_table\_or\_index">SYSCS\_SPLIT\_TABLE\_OR\_INDEX</a> to compute the splits; the <a href="mailto:Example 2">Example 2</a> example walks you through this.

-or-

>> You can call <a href="mailto:syscs\_util.compute\_split\_key">Syscs\_util.syscs\_split\_table\_or\_index\_at\_points</a> to set up the splits in your database; the <a href="mailto:example 3">Example 3</a> example walks you through this.

In either case, after computing the splits, you call SYSCS\_UTIL.BULK\_IMPORT\_HFILE to split your input file into HFiles, import your data, and then remove the temporary HFiles.

Here's a quick summary of how you can compute your table splits:

1. Create a directory on HDFS for the import; for example:

```
sudo -su hdfs hadoop fs -mkdir hdfs:///tmp/test_hfile_import
```

2. Determine primary key values that can horizontally split the table into roughly equal sized partitions.

Ideally, each partition should be about 1/2 the size of your hbase.hregion.max.filesize setting, which leaves room for the region to grow after your data is imported.

The size of each partition must be less than the value of hbase.hregion.max.filesize.

- 3. Store those keys in a CSV file.
- 4. Compute the split keys and then split the table.
- 5. Repeat steps 1, 2, and 3 to split the indexes on your table.
- 6. Call the <u>SYSCS\_UTIL.BULK\_IMPORT\_HFILE</u> procedure to split the input data file into HFiles and import the HFiles into your Splice Machine database. The HFiles are automatically deleted after being imported.

You'll find detailed descriptions of these steps in these two examples:

- >> Example 2: Using SPLIT TABLE OR INDEX to Compute Table Splits
- >> Example 3: Using SYSCS\_UTIL.COMPUTE\_SPLIT\_KEY and SPLIT\_TABLE\_OR\_INDEX\_AT\_POINTS to Compute Table Splits.

# Examples of Using SYSCS UTIL.BULK IMPORT HFILE

This section contains example walkthroughs of using the SYSCS\_UTIL.BULK\_IMPORT\_HFILE system procedure in three different ways:

- >>> <u>Example 1</u> uses the automatic table splitting built into SYSCS\_UTIL.BULK\_IMPORT\_HFILE to import a table into your Splice Machine database.
- >>> <u>Example 2</u> uses the SYSCS\_UTIL.COMPUTE\_SPLIT\_TABLE\_OR\_INDEX system procedure to calculate the table splits before calling SYSCS\_UTIL.BULK\_IMPORT\_HFILE to import a table into your Splice Machine database.
- >>> Example 3 uses the SYSCS\_UTIL.COMPUTE\_SPLIT\_KEY and SYSCS\_UTIL.SYSCS\_SPLIT\_TABLE\_OR\_INDEX\_AT\_POINTS system procedures to calculate the table splits before calling SYSCS\_UTIL.BULK\_IMPORT\_HFILE to import a table into your Splice Machine database.

### **Example 1: Bulk HFile Import with Automatic Table Splitting**

This example details the steps used to import data in HFile format using the Splice Machine SYSCS\_UTIL.BULK\_IMPORT\_HFILE system procedure with automatic splitting.

Follow these steps:

1. Create a directory on HDFS for the import; for example:

```
sudo -su hdfs hadoop fs -mkdir hdfs:///tmp/test_hfile_import
```

Make sure that the directory you create has permissions set to allow Splice Machine to write your csv and Hfiles there.

2. Create table and index:

```
CREATE TABLE TPCH.LINEITEM (
    L ORDERKEY BIGINT NOT NULL,
    L PARTKEY INTEGER NOT NULL,
    L SUPPKEY INTEGER NOT NULL,
    L LINENUMBER INTEGER NOT NULL,
    L QUANTITY DECIMAL (15,2),
    L EXTENDEDPRICE DECIMAL(15,2),
    L DISCOUNT DECIMAL(15,2),
    L TAX DECIMAL(15,2),
    L RETURNFLAG VARCHAR(1),
    L LINESTATUS VARCHAR(1),
    L SHIPDATE DATE,
    L COMMITDATE DATE,
    L RECEIPTDATE DATE,
    L SHIPINSTRUCT VARCHAR (25),
    L SHIPMODE VARCHAR (10),
    L COMMENT VARCHAR (44),
    PRIMARY KEY (L ORDERKEY, L LINENUMBER)
);
CREATE INDEX L SHIPDATE IDX on TPCH.LINEITEM(
   L SHIPDATE,
   L PARTKEY,
   L EXTENDEDPRICE,
   L DISCOUNT
);
```

#### 3. Import the HFiles Into Your Database

Once you have split your table and indexes, call this procedure to generate and import the HFiles into your Splice Machine database:

The generated HFiles are automatically deleted after being imported.

## Example 2: Using SPLIT TABLE OR INDEX to Compute Table Splits

The example in this section details the steps used to import data in HFile format using the Splice Machine SYSCS UTIL.SYSCS SPLIT TABLE OR INDEX and SYSCS UTIL.BULK IMPORT HFILE system procedures.

Follow these steps:

1. Create a directory on HDFS for the import; for example:

```
sudo -su hdfs hadoop fs -mkdir hdfs:///tmp/test_hfile_import
```

Make sure that the directory you create has permissions set to allow Splice Machine to write your csv and Hfiles there.

2. Create table and index:

```
CREATE TABLE TPCH.LINEITEM (
   L ORDERKEY BIGINT NOT NULL,
    L PARTKEY INTEGER NOT NULL,
    L SUPPKEY INTEGER NOT NULL,
    L LINENUMBER INTEGER NOT NULL,
    L QUANTITY DECIMAL (15,2),
    L EXTENDEDPRICE DECIMAL(15,2),
    L DISCOUNT DECIMAL(15,2),
    L TAX DECIMAL(15,2),
    L RETURNFLAG VARCHAR(1),
    L LINESTATUS VARCHAR(1),
    L SHIPDATE DATE,
    L COMMITDATE DATE,
    L RECEIPTDATE DATE,
    L SHIPINSTRUCT VARCHAR (25),
    L SHIPMODE VARCHAR (10),
    L COMMENT VARCHAR (44),
    PRIMARY KEY (L ORDERKEY, L LINENUMBER)
    );
CREATE INDEX L SHIPDATE IDX on TPCH.LINEITEM(
    L SHIPDATE,
    L PARTKEY,
   L EXTENDEDPRICE,
    L DISCOUNT
    );
```

#### 3. Compute the split row keys for your table and set up the split in your database:

a. Find primary key values that can horizontally split the table into roughly equal sized partitions.

For this example, we provide 3 keys in a file named lineitemKey.csv. Note that each of our three keys includes a second column that is null:

```
1500000|
3000000|
4500000|
```

For every N lines of split data you specify, you'll end up with N+1 regions; for example, the above 3 splits will produce these 4 regions:

```
0 -> 1500000
1500000 -> 3000000
3000000 -> 4500000
4500000 -> (last possible key)
```

**b.** Specify the column names in the csv file in the columnList parameter; in our example, the primary key columns are:

```
'L_ORDERKEY,L_LINENUMBER'
```

c. Invoke SYSCS\_UTIL.SYSCS\_SPLIT\_TABLE\_OR\_INDEX to compute hbase split row keys and set up the splits

#### 4. Compute the split keys for your index:

- a. Find index values that can horizontally split the table into roughly equal sized partitions.
- **b.** For this example, we provide 2 index values in a file named <code>shipDateIndex.csv</code>. Note that each of our keys includes <code>null</code> column values:

```
1994-01-01|||
1996-01-01|||
```

c. Specify the column names in the csv file in the columnList parameter; in our example, the index columns are:

```
'L_SHIPDATE,L_PARTKEY,L_EXTENDEDPRICE,L_DISCOUNT'
```

**d.** Invoke SYSCS\_UTIL.SYSCS\_SPLIT\_TABLE\_OR\_INDEX to compute hbase split row keys and set up the index splits

#### 5. Import the HFiles Into Your Database

Once you have split your table and indexes, call this procedure to generate and import the HFiles into your Splice Machine database:

The generated HFiles are automatically deleted after being imported.

# Example 3: Using SYSCS\_UTIL.COMPUTE\_SPLIT\_KEY and SPLIT TABLE OR INDEX AT POINTS to Compute Table Splits

The example in this section details the steps used to import data in HFile format using the Splice Machine SYSCS\_UTIL.COMPUTE\_SPLIT\_KEY, SYSCS\_UTIL.SYSCS\_SPLIT\_TABLE\_OR\_INDEX\_AT\_POINTS, and SYSCS\_UTIL.BULK\_IMPORT\_HFILE system procedures.

Follow these steps:

1. Create a directory on HDFS for the import; for example:

```
sudo -su hdfs hadoop fs -mkdir hdfs:///tmp/test_hfile_import
```

Make sure that the directory you create has permissions set to allow Splice Machine to write your csv and Hfiles there.

2. Create table and index:

```
CREATE TABLE TPCH.LINEITEM (
     L ORDERKEY BIGINT NOT NULL,
     L PARTKEY INTEGER NOT NULL,
     L SUPPKEY INTEGER NOT NULL,
     L LINENUMBER INTEGER NOT NULL,
     L QUANTITY DECIMAL (15,2),
     L EXTENDEDPRICE DECIMAL(15,2),
     L DISCOUNT DECIMAL (15,2),
     L TAX DECIMAL(15,2),
     L RETURNFLAG VARCHAR (1),
     L LINESTATUS VARCHAR (1),
     L SHIPDATE DATE,
     L COMMITDATE DATE,
     L RECEIPTDATE DATE,
     L SHIPINSTRUCT VARCHAR (25),
     L SHIPMODE VARCHAR (10),
     L COMMENT VARCHAR (44),
     PRIMARY KEY (L ORDERKEY, L LINENUMBER)
);
```

#### 3. Compute the split row keys for the table:

a. Find primary key values that can horizontally split the table into roughly equal sized partitions.

For this example, we provide 3 keys in a file named lineitemKey.csv. Note that each of our three keys includes a second column that is null:

```
1500000|
3000000|
4500000|
```

For every N lines of split data you specify, you'll end up with N+1 regions; for example, the above 3 splits will produce these 4 regions:

```
0 -> 1500000
1500000 -> 3000000
3000000 -> 4500000
4500000 -> (last possible key)
```

**b.** Specify the column names in the csv file in the columnList parameter; in our example, the primary key columns are:

```
'L_ORDERKEY,L_LINENUMBER'
```

**c.** Invoke SYSCS\_UTIL.COMPUTE\_SPLIT\_KEY to compute hbase split row keys and write them to a file:

#### 4. Set up the table splits in your database:

a. Use SHOW TABLES to discover the conglomerate ID for the TPCH.LINEITEM table, which for this example is 1536. This means that the split keys file for this table is in the hdfs://tmp/test\_hfile\_import/1536 directory. You'll see values like these:

```
\xE4\x16\xE3`\xE4-\xC6\xC0\xE4D\xAA
```

b. Now use those values in a call to our system procedure to split the table inside the database:

### 5. Compute the split keys for your index:

- **a.** Find index values that can horizontally split the table into roughly equal sized partitions.
- **b.** For this example, we provide 2 index values in a file named <code>shipDateIndex.csv</code>. Note that each of our keys includes <code>null column values</code>:

```
1994-01-01|||
1996-01-01|||
```

**c.** Specify the column names in the csv file in the columnList parameter; in our example, the index columns are:

```
'L_SHIPDATE,L_PARTKEY,L_EXTENDEDPRICE,L_DISCOUNT'
```

d. Invoke SYSCS UTIL.COMPUTE SPLIT KEY to compute hbase split row keys and write them to a file:

#### 6. Set up the indexes in your database:

**a.** Copy the row key values from the output file:

```
\xEC\xB0Y9\xBC\x00\x00\x00\x00\x80
\xEC\xBF\x08\x9C\x14\x00\x00\x00\x00\x80
```

**b.** Now call our system procedure to split the index:

```
call SYSCS_UTIL.SYSCS_SPLIT_TABLE_OR_INDEX_AT_POINTS(
    'TPCH','LINEITEM','L_SHIPDATE_IDX',
    '\xEC\xB0Y9\xBC\x00\x00\x00\x00\x80,
    \xEC\xBF\x08\x9C\x14\x00\x00\x00\x00\x00\x80');
```

#### 7. Import the HFiles Into Your Database

Once you have split your table and indexes, call this procedure to generate and import the HFiles into your Splice Machine database:

The generated HFiles are automatically deleted after being imported.

# See Also

- >> Importing Data: Tutorial Overview
- >> Importing Data: Input Parameters
- >> Importing Data: Input Data Handling
- >> Importing Data: Error Handling
- >> Importing Data: Usage Examples
- >> Importing Data: Importing TPCH Data
- >> SYSCS\_UTIL.IMPORT\_DATA
- >> SYSCS UTIL.UPSERT DATA FROM FILE
- >> SYSCS UTIL.MERGE DATA FROM FILE
- >> SYSCS UTIL.BULK IMPORT HFILE

# **Importing TPCH Data Into Your Database**

This topic walks you through importing the TPCH sample data into your Splice Machine database and then querying that data, in these sections:

- >> Import TPCH Data walks you through importing TPCH data from our AWS bucket into your Splice Machine database.
- >> Importing Your Own Data links to our tutorial that helps you to import your own data.
- >> The TPCH Queries includes the SQL source for each of the TPCH queries, so you can quickly run any of them against your newly imported data.

# **Import TPCH Data**

You can use the following steps to import TPCH data into your new Splice Machine database:

1. Create the schema and tables

You can copy/paste the following SQL statements to create the schema and tables for importing the sample data:

```
CREATE SCHEMA TPCH;
CREATE TABLE TPCH.LINEITEM (
L ORDERKEY BIGINT NOT NULL,
L PARTKEY INTEGER NOT NULL,
L SUPPKEY INTEGER NOT NULL,
 L LINENUMBER INTEGER NOT NULL,
 L QUANTITY DECIMAL (15,2),
 L EXTENDEDPRICE DECIMAL(15,2),
 L DISCOUNT DECIMAL (15,2),
 L TAX DECIMAL(15,2),
 L RETURNFLAG VARCHAR(1),
 L LINESTATUS VARCHAR(1),
 L SHIPDATE DATE,
 L COMMITDATE DATE,
 L RECEIPTDATE DATE,
 L SHIPINSTRUCT VARCHAR (25),
 L SHIPMODE VARCHAR (10),
 L COMMENT VARCHAR (44),
 PRIMARY KEY (L ORDERKEY, L LINENUMBER)
 );
CREATE TABLE TPCH.ORDERS (
O ORDERKEY BIGINT NOT NULL PRIMARY KEY,
O CUSTKEY INTEGER,
 O ORDERSTATUS VARCHAR(1),
 O TOTALPRICE DECIMAL(15,2),
 O ORDERDATE DATE,
 O ORDERPRIORITY VARCHAR (15),
 O CLERK VARCHAR (15),
 O SHIPPRIORITY INTEGER ,
 O COMMENT VARCHAR (79)
 );
CREATE TABLE TPCH.CUSTOMER (
 C CUSTKEY INTEGER NOT NULL PRIMARY KEY,
 C NAME VARCHAR (25),
 C ADDRESS VARCHAR (40),
 C NATIONKEY INTEGER NOT NULL,
 C PHONE VARCHAR (15),
 C ACCTBAL DECIMAL (15,2),
 C MKTSEGMENT VARCHAR (10),
 C COMMENT VARCHAR (117)
 );
CREATE TABLE TPCH.PARTSUPP (
 PS PARTKEY INTEGER NOT NULL ,
 PS SUPPKEY INTEGER NOT NULL ,
```

```
PS AVAILQTY INTEGER,
 PS SUPPLYCOST DECIMAL (15,2),
 PS COMMENT VARCHAR (199),
 PRIMARY KEY(PS_PARTKEY, PS_SUPPKEY)
CREATE TABLE TPCH.SUPPLIER (
 S SUPPKEY INTEGER NOT NULL PRIMARY KEY,
 S NAME VARCHAR(25),
 S ADDRESS VARCHAR (40) ,
 S NATIONKEY INTEGER ,
 S PHONE VARCHAR (15) ,
 S ACCTBAL DECIMAL (15,2),
 S COMMENT VARCHAR (101)
 );
CREATE TABLE TPCH.PART (
 P PARTKEY INTEGER NOT NULL PRIMARY KEY,
 P NAME VARCHAR (55) ,
 P MFGR VARCHAR(25),
 P BRAND VARCHAR (10) ,
 P TYPE VARCHAR(25),
 P SIZE INTEGER ,
 P CONTAINER VARCHAR (10) ,
 P RETAILPRICE DECIMAL(15,2),
 P COMMENT VARCHAR (23)
 );
CREATE TABLE TPCH.REGION (
 R REGIONKEY INTEGER NOT NULL PRIMARY KEY,
 R NAME VARCHAR (25),
 R COMMENT VARCHAR (152)
 );
CREATE TABLE TPCH.NATION (
N NATIONKEY INTEGER NOT NULL,
N NAME VARCHAR (25),
 N REGIONKEY INTEGER NOT NULL,
 N COMMENT VARCHAR (152),
 PRIMARY KEY (N NATIONKEY)
```

#### 2. Import data

We've put a copy of the TPCH data in an AWS S3 bucket for convenient retrieval. You can copy/paste the following SYSCS UTIL.IMPORT DATA statements to quickly pull that data into your database:

```
call SYSCS UTIL.IMPORT DATA ('TPCH', 'LINEITEM', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/lineitem', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'ORDERS', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/orders', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'CUSTOMER', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/customer', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'PARTSUPP', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/partsupp', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'SUPPLIER', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/supplier', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'PART', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/part', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'REGION', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/region', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
call SYSCS UTIL.IMPORT DATA ('TPCH', 'NATION', null, 's3a:/splice-bench
mark-data/flat/TPCH/1/nation', '|', null, null, null, null, 0, '/tmp/BA
D', true, null);
```

#### 3. Run a query

You can now copy/paste TPCH Query 01 against the imported data to verify that all's well:

```
-- OUERY 01
select
   l returnflag,
   l linestatus,
   sum(l quantity) as sum qty,
    sum(l extendedprice) as sum base price,
    sum(l extendedprice * (1 - l discount)) as sum disc price,
    sum(1 extendedprice * (1 - 1 discount) * (1 + 1 tax)) as sum charge,
    avg(l quantity) as avg qty,
    avg(l extendedprice) as avg price,
    avg(l discount) as avg disc,
    count(*) as count order
from
   TPCH.lineitem
where
    1 shipdate = date({fn TIMESTAMPADD(SQL TSI DAY, -90, cast('1998-12-0
1 00:00:00' as timestamp))})
group by
   1 returnflag,
   l linestatus
order by
   l returnflag,
   l linestatus
-- END OF QUERY
```

We've also included the SQL for most of the other TPCH queries in this topic, should you want to try others.

# **Importing Your Own Data**

You can follow similar steps to import your own data. Setting up your import requires some precision; we encourage you to look through our <u>Importing Your Data Tutorial</u> for guidance and tips to make that process go smoothly.

# **The TPCH Queries**

Here are a number of additional queries you might want to run against the TPCH data:

```
-- QUERY 01
select
   l returnflag,
   l linestatus,
   sum(l_quantity) as sum_qty,
    sum(l extendedprice) as sum base price,
    sum(l_extendedprice * (1 - l_discount)) as sum_disc_price,
   sum(l_extendedprice * (1 - l_discount) * (1 + l_tax)) as sum_cha
rge,
   avg(l quantity) as avg qty,
   avg(l extendedprice) as avg price,
   avg(l discount) as avg_disc,
   count(*) as count order
from
   TPCH.lineitem
where
   1 shipdate = date({fn TIMESTAMPADD(SQL TSI DAY, -90, cast('199
8-12-01 00:00:00' as timestamp))})
group by
   l_returnflag,
   l linestatus
order by
   l returnflag,
   l linestatus
-- END OF QUERY
```

```
-- QUERY 02
select
   s acctbal,
    s name,
   n name,
   p partkey,
   p mfgr,
    s address,
    s phone,
   s comment
from
   TPCH.part,
   TPCH.supplier,
   TPCH.partsupp,
   TPCH.nation,
   TPCH.region
where
   p partkey = ps partkey
   and s suppkey = ps suppkey
   and p size = 15
   and p type like '%BRASS'
    and s nationkey = n nationkey
    and n regionkey = r regionkey
    and r name = 'EUROPE'
    and ps supplycost = (
        select
            min(ps supplycost)
        from
            TPCH.partsupp,
            TPCH.supplier,
            TPCH.nation,
            TPCH.region
        where
            p partkey = ps partkey
            and s suppkey = ps suppkey
            and s_nationkey = n nationkey
            and n regionkey = r regionkey
            and r name = 'EUROPE'
order by
   s acctbal desc,
   n name,
   s name,
   p partkey
{limit 100}
```

```
-- QUERY 03
select
   l orderkey,
   sum(l_extendedprice * (1 - l_discount)) as revenue,
   o orderdate,
   o shippriority
from
   TPCH.customer,
   TPCH.orders,
   TPCH.lineitem
where
   c mktsegment = 'BUILDING'
   and c_custkey = o_custkey
   and l_orderkey = o_orderkey
   and o orderdate date('1995-03-15')
   and 1 shipdate date('1995-03-15')
group by
   l orderkey,
   o orderdate,
   o_shippriority
order by
   revenue desc,
   o_orderdate
{limit 10}
-- END OF QUERY
```

```
-- QUERY 04
select
   o orderpriority,
   count(*) as order count
   TPCH.orders
where
   o_orderdate >= date('1993-07-01')
   and o_orderdate add_months('1993-07-01',3)
   and exists (
       select
       from
           TPCH.lineitem
       where
           l orderkey = o orderkey
           and l_commitdate l_receiptdate
   )
group by
   o_orderpriority
order by
   o orderpriority
-- END OF QUERY
```

# Query05 -- QUERY 05 select n name, sum(l extendedprice \* (1 - l discount)) as revenue TPCH.customer, TPCH.orders, TPCH.lineitem, TPCH.supplier, TPCH.nation, TPCH.region where c custkey = o custkey and 1 orderkey = o orderkey and 1 suppkey = s suppkey and c nationkey = s nationkey and s nationkey = n nationkey and n regionkey = r regionkey and r name = 'ASIA' and o orderdate >= date('1994-01-01') and o orderdate date({fn TIMESTAMPADD(SQL TSI YEAR, 1, cast('19 94-01-01 00:00:00' as timestamp))}) group by n name order by revenue desc -- END OF QUERY

```
-- QUERY 06
select
    sum(l_extendedprice * l_discount) as revenue
from
    TPCH.lineitem
where
    l_shipdate >= date('1994-01-01')
    and l_shipdate date({fn TIMESTAMPADD(SQL_TSI_YEAR, 1, cast('1994-01-01 00:00:00' as timestamp))})
    and l_discount between .06 - 0.01 and .06 + 0.01
    and l_quantity 24
-- END OF QUERY
```

```
-- QUERY 07
select
    supp nation,
    cust nation,
    1 year,
   sum(volume) as revenue
from
        select
            n1.n name as supp nation,
            n2.n name as cust nation,
            year(l shipdate) as l year,
            l extendedprice * (1 - 1 discount) as volume
        from
            TPCH.supplier,
            TPCH.lineitem,
            TPCH.orders,
            TPCH.customer,
            TPCH.nation n1,
            TPCH.nation n2
        where
            s suppkey = 1 suppkey
            and o orderkey = 1 orderkey
            and c custkey = o custkey
            and s nationkey = n1.n nationkey
            and c_nationkey = n2.n_nationkey
            and (
                (n1.n name = 'FRANCE' and n2.n name = 'GERMANY')
                or (n1.n name = 'GERMANY' and n2.n name = 'FRANCE')
            and 1 shipdate between date('1995-01-01') and date('199
6-12-31')
   ) as shipping
group by
   supp nation,
    cust nation,
   l year
order by
   supp nation,
   cust nation,
   l year
-- END OF QUERY
```

```
-- QUERY 08
select
   o_year,
    sum(case
        when nation = 'BRAZIL' then volume
   end) / sum(volume) as mkt share
from
        select
            year (o orderdate) as o year,
            l extendedprice * (1 - 1 discount) as volume,
            n2.n name as nation
        from
            TPCH.part,
            TPCH.supplier,
            TPCH.lineitem,
            TPCH.orders,
            TPCH.customer,
            TPCH.nation n1,
            TPCH.nation n2,
            TPCH.region
       where
            p partkey = l partkey
            and s suppkey = 1 suppkey
            and l_orderkey = o_orderkey
            and o custkey = c custkey
            and c nationkey = n1.n nationkey
            and nl.n regionkey = r regionkey
            and r name = 'AMERICA'
            and s nationkey = n2.n nationkey
            and o orderdate between date('1995-01-01') and date('199
6-12-31')
            and p type = 'ECONOMY ANODIZED STEEL'
   ) as all nations
group by
   o year
order by
   o year
-- END OF QUERY
```

```
-- QUERY 09
select
   nation,
   o year,
   sum (amount) as sum profit
from
        select
            n name as nation,
            year (o orderdate) as o year,
            l_extendedprice * (1 - l_discount) - ps_supplycost * l_q
uantity as amount
        from
            TPCH.part,
            TPCH.supplier,
            TPCH.lineitem,
            TPCH.partsupp,
            TPCH.orders,
            TPCH.nation
       where
            s suppkey = 1 suppkey
            and ps suppkey = 1 suppkey
            and ps partkey = 1 partkey
            and p partkey = 1 partkey
            and o orderkey = 1 orderkey
            and s_nationkey = n_nationkey
            and p name like '%green%'
   ) as profit
group by
   nation,
   o year
order by
   nation,
   o year desc
-- END OF QUERY
```

```
-- QUERY 10
select
   c custkey,
   c name,
   sum(l_extendedprice * (1 - l_discount)) as revenue,
   c acctbal,
   n name,
   c address,
   c phone,
   c comment
from
   TPCH.customer,
   TPCH.orders,
   TPCH.lineitem,
   TPCH.nation
where
   c custkey = o custkey
   and 1 orderkey = o orderkey
   and o orderdate >= date('1993-10-01')
   and o_orderdate ADD_MONTHS('1993-10-01',3)
   and 1 returnflag = 'R'
   and c nationkey = n nationkey
group by
   c custkey,
   c name,
   c acctbal,
   c phone,
   n name,
   c address,
   c comment
order by
   revenue desc
{limit 20}
-- END OF QUERY
```

```
-- QUERY 11
select
   ps partkey,
   sum(ps_supplycost * ps_availqty) as value
   TPCH.partsupp,
   TPCH.supplier,
   TPCH.nation
where
   ps suppkey = s suppkey
   and s_nationkey = n_nationkey
   and n name = 'GERMANY'
group by
   ps_partkey having
       sum(ps_supplycost * ps_availqty) > (
            select
                sum(ps_supplycost * ps_availqty) * 0.0001000000
            from
                TPCH.partsupp,
                TPCH.supplier,
                TPCH.nation
            where
                ps_suppkey = s_suppkey
                and s_nationkey = n_nationkey
                and n name = 'GERMANY'
        )
order by
   value desc
-- END OF QUERY
```

```
-- QUERY 12
select
   l shipmode,
    sum(case
        when o orderpriority = '1-URGENT'
           or o orderpriority = '2-HIGH'
           then 1
        else 0
    end) as high line count,
    sum(case
        when o orderpriority > '1-URGENT'
           and o orderpriority > '2-HIGH'
           then 1
        else 0
   end) as low line count
from
   TPCH.orders,
   TPCH.lineitem
where
   o_orderkey = l_orderkey
   and 1 shipmode in ('MAIL', 'SHIP')
   and 1 commitdate 1 receiptdate
   and 1 shipdate 1 commitdate
        and 1 receiptdate >= date('1994-01-01')
        and 1 receiptdate date({fn TIMESTAMPADD(SQL TSI YEAR, 1, ca
st('1994-01-01 00:00:00' as timestamp))})
group by
   l shipmode
order by
   l shipmode
-- END OF QUERY
```

```
-- QUERY 13
select
    c count,
    count(*) as custdist
from
        select
            c custkey,
            count (o orderkey)
        from
            TPCH.customer left outer join tpch.orders on
                c custkey = o custkey
                and o comment not like '%special%requests%'
        group by
            c custkey
    ) as c orders (c custkey, c count)
group by
   c count
order by
   custdist desc,
   c count desc
-- END OF QUERY
```

```
-- QUERY 14
select
    100.00 * sum(case
        when p_type like 'PROMO%'
            then l_extendedprice * (1 - l_discount)
        else 0
    end) / sum(l_extendedprice * (1 - l_discount)) as promo_revenue
from
    TPCH.lineitem,
    TPCH.part
where
    l_partkey = p_partkey
    and l_shipdate >= date('1995-09-01')
    and l_shipdate add_months('1995-09-01',1)
-- END OF QUERY
```

```
-- QUERY 15
select
   s suppkey,
   s name,
   s_address,
   s phone,
   total_revenue
   TPCH.supplier,
   TPCH.revenue0
where
   s suppkey = supplier no
   and total revenue = (
       select
           max(total revenue)
       from
          TPCH.revenue0
   )
order by
  s_suppkey
-- END OF QUERY
```

```
-- QUERY 16
select
   p brand,
   p type,
   p_size,
   count(distinct ps suppkey) as supplier cnt
from
   TPCH.partsupp,
   TPCH.part
where
   p partkey = ps partkey
   and p brand > 'Brand#45'
   and p type not like 'MEDIUM POLISHED%'
   and p_size in (49, 14, 23, 45, 19, 3, 36, 9)
   and ps suppkey not in (
       select
            s_suppkey
        from
           TPCH.supplier
       where
            s comment like '%Customer%Complaints%'
group by
   p brand,
   p_type,
   p size
order by
   supplier cnt desc,
   p_brand,
   p_type,
   p_size
-- END OF QUERY
```

```
-- QUERY 17
select
   sum(l extendedprice) / 7.0 as avg yearly
   TPCH.lineitem,
   TPCH.part
where
   p_partkey = l_partkey
   and p brand = 'Brand#23'
   and p container = 'MED BOX'
   and l_quantity (
       select
            0.2 * avg(l quantity)
        from
           TPCH.lineitem
       where
           l_partkey = p_partkey
-- END OF QUERY
```

```
-- QUERY 18
select
   c name,
   c custkey,
   o orderkey,
   o orderdate,
   o_totalprice,
   sum(l_quantity)
from
   TPCH.customer,
   TPCH.orders,
   TPCH.lineitem
where
    o orderkey in (
       select
            1 orderkey
        from
            TPCH.lineitem
       group by
           l_orderkey having
                sum(l quantity) > 300
    and c_custkey = o_custkey
   and o orderkey = 1 orderkey
group by
   c name,
   c custkey,
   o orderkey,
   o orderdate,
   o totalprice
order by
   o totalprice desc,
   o orderdate
{limit 100}
-- END OF QUERY
```

```
-- QUERY 19
select
    sum(l extendedprice* (1 - l discount)) as revenue
   TPCH.lineitem,
   TPCH.part
where
        p partkey = l partkey
        and p brand = 'Brand#12'
        and p container in ('SM CASE', 'SM BOX', 'SM PACK', 'SM PK
G')
        and 1 quantity >= 1 and 1 quantity = 1 + 10
        and p size between 1 and 5
        and 1 shipmode in ('AIR', 'AIR REG')
        and 1 shipinstruct = 'DELIVER IN PERSON'
    )
    or
        p_partkey = l_partkey
        and p brand = 'Brand#23'
        and p container in ('MED BAG', 'MED BOX', 'MED PKG', 'MED PA
CK')
        and 1 quantity >= 10 and 1 quantity = 10 + 10
        and p size between 1 and 10
        and l_shipmode in ('AIR', 'AIR REG')
        and 1 shipinstruct = 'DELIVER IN PERSON'
    )
    or
       p partkey = 1 partkey
        and p brand = 'Brand#34'
        and p container in ('LG CASE', 'LG BOX', 'LG PACK', 'LG PK
G')
        and 1 quantity >= 20 and 1 quantity = 20 + 10
        and p size between 1 and 15
        and 1 shipmode in ('AIR', 'AIR REG')
        and 1 shipinstruct = 'DELIVER IN PERSON'
-- END OF QUERY
```

```
-- QUERY 21
select
    s name,
   count(*) as numwait
   TPCH.supplier,
   TPCH.lineitem 11,
   TPCH.orders,
   TPCH.nation
where
    s suppkey = 11.1 suppkey
    and o orderkey = 11.1 orderkey
   and o orderstatus = 'F'
    and l1.1_receiptdate > l1.1_commitdate
    and exists (
       select
        from
           TPCH.lineitem 12
       where
           12.1 orderkey = 11.1 orderkey
            and 12.1 suppkey > 11.1 suppkey
    and not exists (
       select
        from
            TPCH.lineitem 13
        where
            13.1 orderkey = 11.1 orderkey
            and 13.1 suppkey > 11.1 suppkey
            and 13.1 receiptdate > 13.1 commitdate
    and s_nationkey = n_nationkey
   and n name = 'SAUDI ARABIA'
group by
   s name
order by
   numwait desc,
   s name
{limit 100}
-- END OF QUERY
```

```
-- QUERY 22
select
    cntrycode,
    count(*) as numcust,
    sum(c acctbal) as totacctbal
from
        select
            SUBSTR(c phone, 1, 2) as cntrycode,
            c acctbal
        from
            TPCH.customer
        where
            SUBSTR(c phone, 1, 2) in
                ('13', '31', '23', '29', '30', '18', '17')
            and c acctbal > (
                select
                    avg(c acctbal)
                from
                    TPCH.customer
                where
                    c \ acctbal > 0.00
                    and SUBSTR(c phone, 1, 2) in
                         ('13', '31', '23', '29', '30', '18', '17')
            and not exists (
                select
                from
                    TPCH.orders
                where
                    o_custkey = c_custkey
    ) as custsale
group by
   cntrycode
order by
   cntrycode
-- END OF QUERY
```

## See Also

- >> Importing Data: Tutorial Overview
- >> Importing Data: Input Parameters
- >> Importing Data: Input Data Handling

- >> Importing Data: Error Handling
- >> Importing Data: Usage Examples
- >> Importing Data: Bulk HFile Examples
- >> SYSCS UTIL. IMPORT DATA
- >> SYSCS UTIL.UPSERT DATA FROM FILE
- >> SYSCS UTIL.MERGE DATA FROM FILE
- >> SYSCS UTIL.BULK IMPORT HFILE

# **Streaming Data with Kafka: Creating a Producer**

This topic demonstrates how to create a Kafka Producer to feed data into Splice Machine; we'll subsequently use this producer in other tutorials.

### Watch the Video:

The following video shows you how to create a Kafka producer to feed data into Splice Machine.

# Streaming Data with Kafka: Configuring a Feed

This topic demonstrates how to create a Kafka Feed , which puts messages on a Kafka Queue. We'll make use of this class in other tutorials.

### Watch the Video:

The following video shows you how to configure a Kafka feed to Splice Machine.

## **Integrating Apache Storm with Splice Machine**

This topic walks you through building and running two different examples of integrating Storm with Splice Machine:

- >> Inserting Random Values in Splice Machine with Storm
- Inserting Data into Splice Machine from MySQL

## **Inserting Random Values in Splice Machine with Storm**

This example iterates through a list of random words and numbers, inserting the values into a Splice Machine database; follow along in these steps:

### 1. Download the Sample Code:

Pull the code from our git repository:

https://github.com/splicemachine/splice-community-sample-code/tree/master/tutorial-storm

#### 2. Check the prerequisites:

You must be running Splice Machine 2.0 or later on the same machine on which you will run this example code. If Splice Machine is running on a different machine, you'll need to modify the server variable in the SpliceDumperTopology.java file; change it to the name of the server that is running Splice Machine.

You also must have mayen v.3.3.9 or later installed.

#### 3. Create the test table in Splice Machine:

This example inserts data into a Splice Machine table named testTable. You need to create that table by entering this command at the <a href="mailto:splice">splice</a> prompt:

```
splice> CREATE TABLE testTable( word VARCHAR(100), number INT );
```

#### 4. Compile the sample code:

Compile the sample code with this command

```
% mvn clean compile dependency:copy-dependencies
```

#### 5. Run the sample code:

Follow these steps:

- a. Make sure that Splice Machine is running and that you have created the testTable table.
- **b.** Execute this script to run the program:

```
% run-storm.sh
```

**c.** Query testTable in Splice Machine to verify that it has been populated with random words and numbers:

```
splice> select * from testTable;
```

## **About the Sample Code Classes**

The random insertion example contains the following java classes, each of which is described below:

Class	Description	
SpliceCommunicator.java	Contains methods for communicating with Splice Machine.	
SpliceConnector.java	Establishes a JDBC connection with Splice Machine.	
SpliceDumperBolt.java	Dumps data into Splice Machine.	
SpliceDumperTopology.java	Defines the Storm topology for this example.	
SpliceIntegerSpout.java	Emits tuples that are inserted into the Splice Machine table.	

## Inserting Data into Splice Machine from MySQL

This example uses Storm to read data from a MySQL database, and insert that data into a table in Splice Machine.

#### 1. Download the Sample Code:

Pull the code from our git repository:

https://github.com/splicemachine/splice-community-sample-code/tree/master/tutorial-storm

#### 2. Check the prerequisites:

You must be running Splice Machine 2.0 or later on the same machine on which you will run this example code. If Splice Machine is running on a different machine, you'll need to modify the <code>server</code> variable in the <code>MySqlToSpliceTopology.java</code> file; change it to the name of the server that is running Splice Machine.

You also must have maven v.3.3.9 or later installed.

This example assumes that your MySQL database instance is running on the same machine on which you're running Splice Machine, and that the root user does not have a password. If either of these is not true, then you need to modify the call to the <code>seedBufferQueue</code> method in the <code>MySqlSpout.java</code> file. This method takes four parameters that you may need to change:

```
seedBufferQueue( MySqlServer, MySqlDatabase, mySqlUserName, mySqlPasswor
d );
```

The default settings used in this example are:

```
seedBufferQueue( "localhost", "test", "root", "" );
```

#### 3. Create the students table in Splice Machine:

This example inserts data into a Splice Machine table named students. You need to create that table by entering this command at the splice> prompt:

```
splice> CREATE TABLE students( name VARCHAR(100) );
```

#### 4. Create the students table in your MySQL database:

This example read data from a MySQL table named students. You need to create that table in MySQL:

```
$$ CREATE TABLE students( id INTEGER, name VARCHAR(100) );
```

If your MySQL instance is on a different machine

#### 5. Compile the sample code:

Compile the sample code with this command

```
% mvn clean compile dependency:copy-dependencies
```

#### 6. Run the sample code:

Follow these steps:

- a. Make sure that Splice Machine is running and that you have created the testTable table.
- **b.** Execute this script to run the program:

```
% run-mysql-storm.sh
```

c. Query the students table in Splice Machine to verify that it has been populated with data from the MySQL table:

```
splice> select * from students;
```

## **About the Sample Code Classes**

This example contains the following java classes:

Class	Description	
MySqlCommunicator.java	Contains methods for communicating with MySQL.	
MySqlConnector.java	Establishes a JDBC connection with MySQL.	
MySqlSpliceBolt.java	Dumps data from MySQL into Splice Machine.	
MySqlSpout.java	Emits tuples from MySQL that are inserted into the Splice Machine table.	
MySqlToSpliceTopology.java	Defines the Storm topology for this example.	
SpliceCommunicator.java	Contains methods for communicating with Splice Machine.	
SpliceConnector.java	Establishes a JDBC connection with Splice Machine.	

## **Streaming MQTT Spark Data**

This topic walks you through using MQTT Spark streaming with Splice Machine. MQTT is a lightweight, publish-subscribe messaging protocol designed for connecting remotely when a small footprint is required. MQTT is frequently used for data collection with the Internet of Things (IoT).

The example code in this tutorial uses <u>Mosquitto</u>, which is an open source message broker that implements the MQTT. This tutorial uses a cluster managed by MapR; if you're using different platform management software, you'll need to make a few adjustments in how the code is deployed on your cluster.

NOTE: All of the code used in this tutorial is available in our GitHub community repository.

You can complete this tutorial by watching a short video or by following the written directions below.

### Watch the Video

The following video shows you how to:

- put messages on an MQTT queue
- >> consume those messages using Spark streaming
- save those messages to Splice Machine with a virtual table (VTI)

## Written Walk Through

This section walks you through the same sequence of steps as the video, in these sections:

- >> Deploying the Tutorial Code walks you through downloading and deploying the sample code.
- >> About the Sample Code describes the high-level methods in each class.
- About the Sample Code Scripts describes the scripts used to deploy and execute the sample code.

## **Deploying the Tutorial Code**

Follow these steps to deploy the tutorial code:

Download the code from our <u>GitHub community repository</u>.
 Pull the code from our git repository:

https://github.com/splicemachine/splice-community-sample-code/tree/master/tutorial-mqtt-spark-streaming

#### 2. Compile and package the code:

mvn clean compile package

#### 3. Copy three JAR files to each server:

Copy these three files:

./target/splice-tutorial-mqtt-2.0.jarspark-streaming-mqtt\_2.10-1.6.1.jarorg.eclipse.paho.client.mqttv3-1.1.0.jar

to this directory on each server:

/opt/splice/default/lib

#### 4. Restart Hbase

#### 5. Create the target table in splice machine:

Run this script to create the table:

create-tables.sql

#### 6. Start Mosquitto:

sudo su /usr/sbin/mosquitto -d -c /etc/mosquitto/mosquitto.conf > /var/lo q/mosquitto.log 2>&1

#### 7. Start the Spark streaming script:

```
sudo -su mapr ./run-mqtt-spark-streaming.sh tcp://srv61:1883 /testing 10
```

The first parameter (tcp://srv61:1883) is the MQTT broker, the second (/testing) is the topic name, and the third (10) is the number of seconds each stream should run.

#### 8. Start putting messages on the queue:

Here's a java program that is set up to put messages on the queue:

java -cp /opt/splice/default/lib/splice-tutorial-mqtt-2.0-SNAPSHOT.jar:/o
pt/splice/default/lib/org.eclipse.paho.client.mqttv3-1.1.0.jar com.splice
machine.tutorials.sparkstreaming.mqtt.MQTTPublisher tcp://localhost:1883
/testing 1000 R1

The first parameter (tcp://localhost:1883) is the MQTT broker, the second (/testing) is the topic name, the third (1000) is the number of iterations to execute, and the fourth parameter (R1) is a prefix for this run.

**NOTE:** The source code for this utility program is in a different GitHub project than the rest of this code. You'll find it in the <a href="mailto:tutorial-kafka-producer">tutorial-kafka-producer</a> Github project.

## **About the Sample Code**

This section describes the main class methods used in this MQTT example code; here's a summary of the classes:

Java Class	Description	
MQTTPublisher	Puts csv messages on an MQTT queue.	
SparkStreamingMQTT	The Spark streaming job that reads messages from the MQTT queue.	
SaveRDD	Inserts the data into Splice Machine using the RFIDMessageVTI class.	
RFIDMessageVTI	A virtual table interface for parsing an RFIDMessage.	
RFIDMessage	Java object (a POJO) for converting from a csv string to an object to a database entry.	

#### **MQTTPublisher**

This class puts CSV messages on an MQTT queue. The function of most interest in MQTTPublisher.java is DoDemo, which controls our sample program:

```
public void doDemo() {
   try {
        long startTime = System.currentTimeMillis();
        client = new MgttClient(broker, clientId);
        client.connect();
        MqttMessage message = new MqttMessage();
        for (int i=0; inumMessages; i++) {
            // Build a csv string
            message.setPayload( prefix + "Asset" + i ", Location" + i + "," + new Ti
mestamp((new Date()).getTime())).getBytes());
            client.publish(topicName, message);
            if (i % 1000 == 0) {
                System.out.println("records:" + i + " duration=" + (System.currentTi
meMillis() - startTime));
                startTime = System.currentTimeMillis();
        client.disconnect();
    } catch (MqttException e) {
        e.printStackTrace();
```

DoDemo does a little initialization, then starts putting messages out on the queue. Our sample program is set up to loop until it creates numMessages messages; after every 1000 messages, it displays a status message that helps us determine how much time is going to put messages on the queue, and how much to take them off the queue.

DoDemo builds a csv record (line) for each message, setting an asset ID, a location ID, and a timestamp in the payload of the message. It them publishes that message to the topic topicName.

### **SparkStreamingMQTT**

Once the messages are on the queue, our SparkStreamingMQTT class object reads them from the queue and inserts them into our database. The main method in this class is processMQTT:

```
public void processMQTT(final String broker, final String topic, final int numSecond
s) {
   LOG.info("******* SparkStreamingMQTTOutside.processMQTT start");
   // Create the spark application and set the name to MQTT
   SparkConf sparkConf = new SparkConf().setAppName("MQTT");
   // Create the spark streaming context with a 'numSeconds' second batch size
   jssc = new JavaStreamingContext(sparkConf, Durations.seconds(numSeconds));
   jssc.checkpoint(checkpointDirectory);
   LOG.info("******* SparkStreamingMQTTOutside.processMQTT about to read the M
OTTUtils.createStream");
   //2. MQTTUtils to collect MQTT messages
   JavaReceiverInputDStreamString> messages = MQTTUtils.createStream(jssc, broker,
topic);
   LOG.info("******* SparkStreamingMQTTOutside.processMQTT about to do foreach
RDD");
    //process the messages on the queue and save them to the database
   messages.foreachRDD(new SaveRDD());
   LOG.info("******* SparkStreamingMQTTOutside.processMQTT prior to context.st
rt");
   // Start the context
   jssc.start();
   jssc.awaitTermination();
```

The processMQTT method takes three parameters:

broker

The URL of the MQTT broker.

topic

The MQTT topic name.

numSeconds

The number of seconds at which streaming data will be divided into batches.

The processMQTT method processes the messages on the queue and saves them by calling the SaveMDD class.

#### **SaveRDD**

The SaveRDD class is an example of a Spark streaming function that uses our virtual table interface (VTI) to insert data into your Splice Machine database. This function checks for messages in the stream, and if there any, it creates a connection your database and uses a prepared statement to insert the messages into the database.

```
/**
 * This is an example of spark streaming function that
 * inserts data into Splice Machine using a VTI.
 * @author Erin Driggers
public class SaveRDD implements FunctionJavaRDDString>, Void>, Externalizable {
   private static final Logger LOG = Logger.getLogger(SaveRDD.class);
    @Override
   public Void call(JavaRDDString> rddRFIDMessages) throws Exception {
        LOG.debug("About to read results:");
        if (rddRFIDMessages != null '& rddRFIDMessages.count() > 0) {
            LOG.debug("Data to process:");
            //Convert to list
            ListString> rfidMessages = rddRFIDMessages.collect();
            int numRcds = rfidMessages.size();
            if (numRcds > 0) {
                try {
                    Connection con = DriverManager.getConnection("jdbc:splice://loca
lhost:1527/splicedb;user=splice;password=admin");
                    //Syntax for using a class instance in a VTI, this could also b
e a table function
                    String vtiStatement = "INSERT INTO IOT.RFID "
                            + "select s.* from new com.splicemachine.tutorials.spark
streaming.mqtt.RFIDMessageVTI(?) s ("
                            + RFIDMessage.getTableDefinition() + ")";
                    PreparedStatement ps = con.prepareStatement(vtiStatement);
                    ps.setObject(1, rfidMessages);
                    ps.execute();
                } catch (Exception e) {
                    //It is important to catch the exceptions as log messages becaus
e it is difficult
                    //to trace what is happening otherwise
                    LOG.error ("Exception saving MQTT records to the database" + e.ge
tMessage(), e);
                } finally {
                    LOG.info("Complete insert into IOT.RFID");
        return null;
```

The heart of this function is the statement that creates the prepared statement, using a VTI class instance:

Note that the statement references both our RFIDMessage and RFIDMessageVTI classes, which are described below.

### **RFIDMessageVTI**

The RFIDMessageVTI class implements an example of a virtual table interface that reads in a list of strings that are in CSV format, converts that into an RFIDMessage object, and returns the resultant list in a format that is compatible with Splice Machine.

This class features an override of the getDataSet method, which loops through each CSV record from the input stream and converts it into an RFIDMessage object that is added onto a list of message items:

```
@Override
public DataSetLocatedRow> getDataSet(SpliceOperation op, DataSetProcessor dsp, ExecR
ow execRow) throws StandardException {
    operationContext = dsp.createOperationContext(op);
   //Create an arraylist to store the key / value pairs
   ArrayListLocatedRow> items = new ArrayListLocatedRow>();
    try {
        int numRcds = this.records == null ? 0 : this.records.size();
        if (numRcds > 0) {
            LOG.info("Records to process:" + numRcds);
            //Loop through each record convert to a SensorObject
            //and then set the values
            for (String csvString : records) {
                CsvBeanReader beanReader = new CsvBeanReader(new StringReader(csvStr
ing), CsvPreference.STANDARD PREFERENCE);
                RFIDMessage msg = beanReader.read(RFIDMessage.class, header, process
ors);
                items.add(new LocatedRow(msg.getRow()));
    } catch (Exception e) {
        LOG.error("Exception processing RFIDMessageVTI", e);
    } finally {
        operationContext.popScope();
    return new ControlDataSet>(items);
```



For more information about using our virtual table interface, see <u>Using the Splice</u> Machine Virtual Table Interface.

### **RFIDMessage**

The RFIDMessage class creates a simple Java object (a POJO) that represents an RFID message; we use this to convert an incoming CSV-formatted message into an object. This class includes getters and setters for each of the object properties, plus the getTableDefinition and getRow methods:

```
/**
 * Used by the VTI to build a Splice Machine compatible resultset
 * @return
 * @throws SQLException
 * @throws StandardException
public ValueRow getRow() throws SQLException, StandardException {
   ValueRow valueRow = new ValueRow(5);
   valueRow.setColumn(1, new SQLVarchar(this.getAssetNumber()));
   valueRow.setColumn(2, new SQLVarchar(this.getAssetDescription()));
   valueRow.setColumn(3, new SQLTimestamp(this.getRecordedTime()));
   valueRow.setColumn(4, new SQLVarchar(this.getAssetType()));
   valueRow.setColumn(5, new SQLVarchar(this.getAssetLocation()));
   return valueRow;
}
 * Table definition to use when using a VTI that is an instance of a class
 * @return
 * /
public static String getTableDefinition() {
   return "ASSET NUMBER varchar(50), "
   + "ASSET DESCRIPTION varchar(100), "
   + "RECORDED TIME TIMESTAMP, "
   + "ASSET TYPE VARCHAR(50), "
   + "ASSET LOCATION VARCHAR (50) ";
```

The getTableDefinition method is a string description of the table into which you're inserting records; this pretty much replicates the specification you would use in an SQL CREATE TABLE statement.

The getRow method creates a data row with the appropriate number of columns, uses property getters to set the value of each column, and returns the row as a resultset that is compatible with Splice Machine.

## **About the Sample Code Scripts**

These are also two scripts that we use with this tutorial:

Class	Description
/ddl/create-tables.sql	A simple SQL script that you can use to have Splice Machine create the table into which RFID messages are stored.
/scripts/run-mqtt-spark- streaming.sh	Starts the Spark streaming job.

# **Connecting with Apache Zeppelin**

This is an On-Premise-Only topic! Learn about our products

This tutorial walks you through connecting your on-premise Splice Machine database with Apache Zeppelin, which is a webbased notebook project currently in incubation at Apache. In this tutorial, you'll learn how to use SQL to query your Splice Machine database from Zeppelin.

#### NOTE:

Zeppelin is already integrated into the Splice Machine Database-as-Service product; please see our <u>Using Zeppelin</u> documentation for more information.

See <a href="https://zeppelin.apache.org/">https://zeppelin.apache.org/</a> to learn more about Apache Zeppelin.

You can complete this tutorial by watching a short video, or by following the written directions below.

### Watch the Video

The following video shows you how to connect Splice Machine with Apache Zeppelin...

## **Written Walk Through**

This section walks you through using SQL to guery a Splice Machine database with Apache Zeppelin..

#### 1. Install Zeppelin:

If you're running on AWS, you can install the Zeppelin sandbox application; if you're using an on-premise database, we recommend following the <u>instructions in this video</u>.

- 2. Create a new interpreter to run with Splice:
  - a. Select the Interpreter tab in Zeppelin.
  - **b.** Click the **Create** button (in the upper right of the Zeppelin window) to create a new interpreter. Fill in the property fields as follows:

Name	Whatever name you like; we're using SpliceMachine		
Interpreter	Select jdbc from the drop-down list of interpreter types.		
default.url	jdbc:splice:/myServer:1527/splicedb		
	(replace myServer with the name of the server that you're using)		
default password	admin		
default userld	splice		
common.max_count	1000		
default.driver	com.splicemachine.db.jdbc.ClientDriver		
Artifacts	Insert the path to the Splice Machine jar file; for example:		
	/tmp/db-client-2.5.0.1708-SNAPSHOT.jar		

c. Click the Save button to save your interpreter definition.

#### 3. Create a note:

Select the Notebook tab in Zeppelin, and then click + Create new note.

- a. Specify a name and click the Create Note button.
- **b.** Enable interpreters for the note. In this case, we move the Splice Machine interpreter to the top of the list, then click the Save button to make it the default interpreter:



c. Create a Zeppelin paragraph (a jdbc action) that calls a stored procedure. The procedure we're calling in this tutorial is named MOVIELENS; it is used to analyze data in a table. In this case, we're using this procedure to report statistics on the Age column in our movie watchers database. This Zeppelin paragraph looks like this:

```
%jdbccall MOVIELENS.ContinuousFeatureReport('movielens.user_demographic
s');
```

The %jdbc specifies that we're creating a paragraph that uses a JDBC interpreter; since we've made the SpliceMachine driver our default JDBC connector, it will be used.


d. The results of this call look like this:



**e.** We can also create a new paragraph that performs additional analysis; you'll see that whenever you run a paragraph in Zeppelin, it automatically leaves room at the bottom to create another paragraph.

```
%jdbcselect count(1) num_age, age from MOVIELENS.USER_DEMOGRAPHICS grou
p by age;
```

The results of this paragraph:




### 4. Change how you view your data

To get a better sense of what you can do with Zeppelin, we'll modify how we visualize this data:

a. Click the rightmost settings icon, then click settings.



- b. Move age to the xAxis, and the number of people of that age to the yAxis.
- **c.** You'll now see the distribution of ages:



**d.** Click the graphs button to select other data visualizations:



## Configuring Load Balancing and High Availability with HAProxy

HAProxy is an open source utility that is available on most Linux distributions and cloud platforms for load-balancing TCP and HTTP requests. Users can leverage this tool to distribute incoming client requests among the region server nodes on which Splice Machine instances are running.

The advantages of using HAProxy with Splice Machine clusters are:

- >> Users need to point to only one JDBC host and port for one Splice Machine cluster, which may have 100s of nodes.
- >> The HAProxy service should ideally be running on a separate node that is directing the traffic to the region server nodes; this means that if one of the region server node goes down, users can still access the data from another region server node.
- >> The load balance mechanism in HAProxy helps distribute the workload evenly among the set of nodes; you can optionally select this algorithm in your configuration, which can help increase throughput rate.

The remainder of this topic walks you through:

- Configuring HAProxy on a non-Splice Machine node that is running Red Hat Enterprise Linux.
- >> Using HAProxy on a Kerberos-enabled cluster

## **Configuring HAProxy with Splice Machine**

The following example shows you how to configure HAProxy load balancer on a non-Splice Machine node on a Red Hat Enterprise Linux system. Follow these steps:

1. Install HAProxy as superuser:

# yum install haproxy

2. Configure the /etc/haproxy/haproxy.cfg file, following the comments in the sample file below: In this example, we set the incoming requests to haproxy\_host:1527, which uses a balancing algorithm of least connections to distribute among the nodes srv127, srv128, srv129, and srv130. This means that the incoming connection is routed to the region server that has the least number of connections; thus, the client JDBC URL should point to <haproxy host>:1527.

**NOTE:** The HAProxy manual describes other balancing algorithms that you can use.

Here is the haproxy.cfg file for this example:

```
# Global settings
#-----
global
   # to have these messages end up in /var/log/haproxy.log you will
   # need to:
   # 1) configure syslog to accept network log events. This is done
      by adding the '-r' option to the SYSLOGD OPTIONS in
      /etc/sysconfig/syslog
   # 2) configure local2 events to go to the /var/log/haproxy.log
    file. A line like the following can be added to
    /etc/sysconfig/syslog
   # local2.*
                              /var/log/haproxy.log
  maxconn 4000
  log 127.0.0.1 local2
  user haproxy
  group haproxy
#-----
# common defaults that all the 'listen' and 'backend' sections will
# use if not designated in their block
#-----
defaults
  log global
  retries 2
  timeout connect 30000
  timeout server 50000
   timeout client 50000
#-----
# This enables jdbc/odbc applications to connect to HAProxy host:1527 por
# so that HAProxy can balance between the splice engine cluster nodes
# where each node's splice engine instance is listening on port 1527
#-----
listen splice-cluster
  bind *:1527
  log global
  mode tcp
  option tcplog
  option tcp-check
  option log-health-checks
  timeout client 3600s
```

```
timeout server 3600s
   balance leastconn
   server srv127 10.1.1.227:1527 check
   server srv128 10.1.1.228:1527 check
   server srv129 10.1.1.229:1527 check
   server srv130 10.1.1.230:1527 check
#-----
# (Optional) set up the stats admin page at port 1936
listen
      stats :1936
   mode http
   stats enable
   stats hide-version
   stats show-node
   stats auth admin:password
   stats uri /haproxy?stats
```

Note that some of the parameters may need tuning per the sizing and workload nature:

- >> The maxconnections parameter indicates how many concurrent connections are served at any given time; you may need to configure this, based on size of the cluster and expected inbound requests.
- >> Similarly, the timeout values, which are by default in msecs, should be tuned so that the connection does not get terminated while a long-running query is executed.

#### 3. Start the HAProxy service:

As superuser, follow these steps to enable the HAProxy service:

Distribution	Instructions	
Redhat / CentOS EL6	<pre># chkconfig haproxy on # service haproxy start</pre>	
	If you change the configuaration file, reload it with this command:	
	# service haproxy reload	

Distribution	Instructions
Redhat / CentOS EL7	<pre># systemctl enable haproxy ln -s '/usr/lib/systemd/system/haproxy.service '/etc/systemd/system/multi-user.target.wants/haprox y.service' # systemctl start haproxy</pre>
	If you change the configuaration file, reload it with this command:
	# systemctl haproxy reload

**NOTE:** You can find the HAProxy process id in: /var/run/haproxy.pid. If you encounter any issues starting the service, check if Selinux is enabled; you may want to disable it initially.

#### 4. Connect:

You can now connect JDBC clients, including the Splice Machine command line interpreter, sqlshell.sh. Use the following JDBC URL:

```
jdbc:splice://<haproxy host>:1527/splicedb;user=splice;password=admin
```

For ODBC clients to connect through HAProxy, ensure that the DSN entry in file .odbc.ini is pointing to the HAProxy host.


#### 5. Verify that inbound requests are being routed correctly:

### 6. View traffic statistics:

If you have enabled HAProxy stats, as in our example, you can view the overall traffic statistics in browser at:

```
http://<haproxy host>:1936/haproxy?stats
```

You'll see a report that looks similar to this:



## Using HAProxy with Splice Machine on a Kerberos-Enabled Cluster

Your JDBC and ODBC applications can authenticate to the backend region server through HAProxy on a Splice Machine cluster that has Kerberos enabled,

You can enable Kerberos mode on a CDH5.8.x or later cluster using the configuration wizard described here:

https://www.cloudera.com/documentation/enterprise/5-8-x/topics/cm\_sg\_intro\_kerb.htm 1.

## **Kerberos and Application Access**

As a Kerberos pre-requisite for Splice Machine JDBC and ODBC access:

- Database users must be added in the Kerberos realm as principals
- >> Keytab entries must be generated and deployed to the remote clients on which the applications are going to connect.

HAProxy will then transparently forward the connections to the back-end cluster in Kerberos setup.

### **Kerberos and ODBC Access**

To connect to a Kerberos-enabled cluster with ODBC, follow these steps:

1. Verify that the odbc.ini configuration file for the DSN you're connecting to includes this setting:

USE KERBEROS=1

See our Using the Splice Machine ODBC Driver for more information.

2. A default security principal user must be established with a TGT in the ticket cache prior to invoking the driver. You can use the following command to establish the principal user:

```
kinit principal
```

Where *principal* is the name of the user who will be accessing Splice Machine. Enter the password for this user when prompted.

3. Launch the application that will connect using ODBC. The ODBC driver will use that default Kerberos *principal* when authenticating with Splice Machine.

### **Example**

This example assumes that you are using the default user name splice. Follow these steps to connect with through HAProxy:

1. Create the principal in Kerberos Key Distribution Center

Create the principal splice@kerberos\_realm\_name in Kerberos Key Distribution Center (KDC). This generates a keytab file named splice.keytab.

2. Copy the generated keytab file

Copy the splice. keytab file that to all client systems.

3. Connect:

You can now connect to the Kerberos-enabled Splice Machine cluster with JDBC through HAProxy, using the following URL:

```
jdbc:splice://<haproxy_host>:1527/splicedb;principal=splice@<realm_nam
e>;keytab=/<path>/splice.keytab
```

Use the same steps to allow other Splice Machine users to connect by adding them to the Kerberos realm and copying the keytab files to their client systems. This example sets up access for a new user name jdoe.

1. Create the user in your Splice Machine database:

```
call syscs_util.syscs_create_user( 'jdoe', 'jdoe' );
```

2. Grant privileges to the user

For this example, we are granting all privileges on a table named myTable to the new user:

```
grant all privileges on splice.myTable to jdoe;
```

- 3. Use KDC to create a new principal and generate a keytab file. For example:
  - # kadmin.local addprinc -randkey jdoe@SPLICEMACHINE.COLO
- 4. Set the password for the new principal:
  - # kadmin.local cpw jdoeEnter password for principal "jdoe@SPLICEMACHINE.C
    OLO":
- 5. Create keytab file jdoe.keytab
  - # kadmin: xst -k jdoe.keytab jdoe@SPLICEMACHINE.COLO
- 6. Copy the generated keytab file to the client system
- 7. Connect through HAProxy with the following URL:

jdbc:splice://ha-proxy-host:1527/splicedb;principal=jdoe@SPLICEMACHINE.CO
LO;keytab=/home/splice/user1.keytab

## Connecting to Splice Machine with Java and JDBC

This topic shows you how to compile and run a sample Java program that connects to Splice Machine using our JDBC driver. The SampleJDBC program does the following:

- >> connects to a standalone (localhost) version of Splice Machine
- >> creates a table named MYTESTTABLE
- >> inserts several sample records
- issues a query to retrieve those records

Follow the written directions below, which includes the raw code for the SampleJDBC example program.

## **Compile and Run the Sample Program**

This section walks you through compiling and running the SampleJDBC example program, in the following steps:

#### 1. Locate the Splice Machine JDBC Driver:

Our JDBC driver is automatically installed on your computer(s) when you install Splice Machine. You'll find it in the jdbc-driver folder under the splicemachine directory; typically:

/splicemachine/jdbc-driver/

- or -

/splicemachine/jdbc-driver/db-client-2.5.0.1734.jar

**NOTE:** The build number, e.g. 1729, varies with each Splice Machine software update.

### 2. Copy the example program code:

You can copy and paste the code below:

```
package com.splicemachine.cs.tools
import java.sql.*;
/**
* Simple example that establishes a connection with splice and does a fe
w basic JDBC operations
* /
public class SampleJDBC {
public static void main(String[] arg) {
    //JDBC Connection String - sample connects to local database
    String dbUrl = "jdbc:splice://localhost:1527/splicedb;user=splice;pas
sword=admin";
    try{
        //For the JDBC Driver - Use the Apache Derby Client Driver
        Class.forName("com.splicemachine.db.jdbc.ClientDriver");
    }catch(ClassNotFoundException cne){
        cne.printStackTrace();
        return; //exit early if we can't find the driver
    try(Connection conn = DriverManager.getConnection(dbUrl)){
        //Create a statement
        try(Statement statement = conn.createStatement()){
            //Create a table
            statement.execute("CREATE TABLE MYTESTTABLE(a int, b varcha
r(30))");
            //Insert data into the table
            statement.execute("insert into MYTESTTABLE values (1,'a')");
            statement.execute("insert into MYTESTTABLE values (2,'b')");
            statement.execute("insert into MYTESTTABLE values (3,'c')");
            statement.execute("insert into MYTESTTABLE values (4,'c')");
            statement.execute("insert into MYTESTTABLE values (5,'c')");
            int counter=0;
            //Execute a Query
            try(ResultSet rs=statement.executeQuery("select a, b from MYT
ESTTABLE")) {
                while(rs.next()){
                    counter++;
                    int val a=rs.getInt(1);
                    String val b=rs.getString(2);
                    System.out.println("record=["+counter+"] a=["+va
l a+"] b=["+val b+"]");
```

```
}
}catch (SQLException se) {
    se.printStackTrace();
}
```

Note that the code uses the default JDBC URL and driver class values:

Connection Parameter	Default Value	Comments
JDBC URL	jdbc:splice:// <mark><hostname></hostname></mark> :1527/splicedb	Use localhost as the <a href="https://www.norm.new.no">hostname&gt; value for the standalone version of Splice Machine.</a> On a cluster, specify the IP address of an HBase RegionServer.
JDBC driver class	com.splicemachine.db.jdbc.ClientDriver	

#### 3. Compile the code

Compile and package the code into splice-jdbc-test-0.1.0-SNAPSHOT.jar.

#### 4. Run the program:

When you run the program, your CLASSPATH must include the path to the Splice Machine JDBC driver. If you did compile and package your code into splice-jdbc-test-0.1.0-SNAPSHOT.jar, you can run the program with this command line:

```
java -cp splice-installer-<platformVersion>/resources/jdbc-driver/ com.sp
licemachine.cs.tools.SampleJDBC
```

The command should display a result like the following:

```
record=[1] a=[1] b=[a]
record=[2] a=[2] b=[b]
record=[3] a=[3] b=[c]
record=[4] a=[4] b=[c]
record=[5] a=[5] b=[c]
```

## Connecting to Splice Machine with JRuby and JDBC

This topic shows you how to compile and run a sample JRuby program that connects to Splice Machine using our JDBC driver. The JRubyJDBC program does the following:

- >> connects to a standalone (localhost) version of Splice Machine
- >> selects and displays the records in a table

## **Compile and Run the Sample Program**

This section walks you through compiling and running the JRubyJDBC example program, in the following steps:

### 1. Install the JDBC Adapter gem

Use the following command to install the activerecord-jdbcderby-adapter gem:

```
gem install activerecord-jdbcderby-adapter
```

### 2. Configure the connection

You must assign the database connectivity parameters in the <code>config/database.yml</code> file for your JRuby application. Your connectivity parameters should look like the following, which use our default database, user, URL, and password values:

```
# Configure Using Gemfile
# gem 'activerecord-jdbcsqlite3-adapter'
# gem 'activerecord-jdbcderby-adapter'
#
development:
    adapter: jdbcderby
    database: splicedb
    username: splice
    password: admin
    driver: com.splicemachine.db.jdbc.ClientDriver
    url: jdbc:splice://localhost:1527/splicedb
```



Use <code>localhost:1527</code> with the standalone (local computer) version of splicemachine. If you're running Splice Machine on a cluster, substitute the address of your server for <code>localhost</code>; for example:

jdbc:splice://mySrv123cba:1527/splicedb.

### 3. Create the sample data table

Create the MYTESTTABLE table in your database and add a little test data. Your table should look something like the following:

```
splice> describe SPLICE.MYTESTTABLE;
COLUMN NAME | TYPE NAME | DEC | NUM | COLUMN | COLUMN DEF | CHAR OCTE | I
S NULL
                   | INTEGER | 0 | 10 | 10 | NULL | NULL | YES | VARCHAR | NULL | 30 | NULL | 60 | YES
2 rows selected
splice> select * from MYTESTTABLE order by A;
   |a
|b
1
2
3
     | C
4
     | C
5
     | C
5 rows selected
```

### 4. Copy the code

You can copy the example program code and paste it into your editor:

```
require 'java'
module JavaLang
include package "java.lang"
end
module JavaSql
include package 'java.sql'
end
import 'com.splicemachine.db.jdbc.ClientDriver'
begin
    conn = JavaSql::DriverManager.getConnection("jdbc:splice://localhos
t:1527/splicedb;user=splice;password=admin");
    stmt = conn.createStatement
    rs = stmt.executeQuery("select a, b from MYTESTTABLE")
    counter = 0
    while (rs.next) do
       counter+=1
       puts "Record=[" + counter.to s + "] a=[" + rs.getInt("a").to s +
"] b=[" + rs.getString("b") + "]"
    end
   rs.close
    stmt.close
   conn.close()
   rescue JavaLang::ClassNotFoundException => e
        stderr.print "Java told me: #{e}n"
    rescue JavaSql::SQLException => e
        stderr.print "Java told me: #{e}n"
end
```

### 5. Run the program

Run the JRubyConnect program as follows

```
jruby jrubyjdbc.rb
```

The command should display a result like the following:

```
Record=[1] a=[3] b=[c]
Record=[2] a=[4] b=[c]
Record=[3] a=[5] b=[c]
Record=[4] a=[1] b=[a]
Record=[5] a=[2] b=[b]
```

## **Connecting to Splice Machine with Jython and JDBC**

This topic shows you how to compile and run a sample Jython program that connects to Splice Machine using our JDBC driver. The print tables program does the following:

- >> connects to a standalone (localhost) version of Splice Machine
- >> selects and displays records from one of the system tables

### **Compile and Run the Sample Program**

This section walks you through compiling and running the print tables example program, in the following steps:

1. Add the Splice client jar to your CLASSPATH; for example:

export CLASSPATH=/splicemachine/jdbc-driver/

2. Copy the example program code:

You can copy and paste the code below; note that this example uses our default connectivity parameters (database, user, URL, and password values):

```
from java.sql import DriverManager
from java.lang import Class
from java.util import Properties
       = 'jdbc:splice://localhost:1527/splicedb'
driver = 'com.splicemachine.db.jdbc.ClientDriver'
props = Properties()
props.setProperty('user', 'splice')
props.setProperty('password', 'admin')
     = Class.forName(driver).newInstance()
conn = DriverManager.getConnection(url, props)
stmt
     = conn.createStatement()
     = stmt.executeQuery("select * from sys.systables")
rowCount = 0
while (rs.next() and rowCount < 10) :</pre>
   rowCount += 1
   print "Record=[" + str(rowCount) + \"]
        id = [" + rs.getString('TABLEID') + \"]
        name = [" + rs.getString('TABLENAME') + \"]
        type = [" + rs.getString('TABLETYPE') + "]"
rs.close()
stmt.close()
conn.close()
```

### 3. Save the code to print files.jy.

### 4. Run the program:

Run the print tables.jy program as follows:

```
jython print_tables.jy
```

The command should display a result like the following:

```
Record=[1] id=[f9f140e7-0144-fcd8-d703-00003cbfba48] name=[ASDAS] typ
e=[T]
Record=[2] id=[c934c123-0144-fcd8-d703-00003cbfba48] name=[DDC NOTMAILABL
E] type=[T]
Record=[3] id=[dd5cc163-0144-fcd8-d703-00003cbfba48] name=[FRANK EMCONT 2
0130430] type=[T]
Record=[4] id=[f584c1a3-0144-fcd8-d703-00003cbfba48] name=[INACTIVE QA] t
ype=[T]
Record=[5] id=[cfcc41df-0144-fcd8-d703-00003cbfba48] name=[NUM GROOM4] ty
pe=[T]
Record=[6] id=[6b7f4217-0144-fcd8-d703-00003cbfba48] name=[PP LL QA] typ
e=[T]
Record=[7] id=[ac154287-0144-fcd8-d703-00003cbfba48] name=[QUAL BRANDS] t
ype=[T]
Record=[8] id=[d67d42c7-0144-fcd8-d703-00003cbfba48] name=[SCIENCE CAT Q
A] type=[T]
Record=[9] id=[c1e0c303-0144-fcd8-d703-00003cbfba48] name=[TESTOUTPUT2] t
ype=[T]
Record=[10] id=[f408c343-0144-fcd8-d703-00003cbfba48] name=[UAC 1267 AV
J] type=[T]
```

## **Connecting to Splice Machine with Scala and JDBC**

This topic shows you how to compile and run a sample Scala program that connects to Splice Machine using our JDBC driver. The SampleScalaJDBC program does the following:

- >> connects to a standalone (localhost) version of Splice Machine
- >> creates a table named MYTESTTABLE
- >> inserts several sample records
- >> selects and displays records from one of the system tables

## **Compile and Run the Sample Program**

This section walks you through compiling and running the SampleScalaJDBC example program, in the following steps:

1. Add the Splice client jar to your CLASSPATH; for example:

export CLASSPATH=/splicemachine/jdbc-driver/

2. Copy the example program code:

You can copy and paste the code below; note that this example uses our default connectivity parameters (database, user, URL, and password values):

```
package com.splicemachine.tutorials.jdbc
import java.sql.DriverManager
import java.sql.Connection
* Simple example of Establishes a connection with splice and executes s
tatements
* /
object SampleScalaJDBC{
        def main(args: Array[String]) {
                // connect to the database named "splicedb" on the localh
ost
                val driver = "com.splicemachine.db.jdbc.ClientDriver"
                val dbUrl = "jdbc:splice://localhost:1527/splicedb;user=s
plice;password=admin"
                var connection:Connection = null
                try {
                        // make the connection
                        Class.forName(driver)
                        connection = DriverManager.getConnection(dbUrl)
                        // create the statement
                        var statement = connection.createStatement()
                        //Create a table
                        statement.execute("CREATE TABLE MYTESTTABLE(a in
t, b varchar(30))");
                        statement.close
                        //Insert data into the table
                        var pst = connection.prepareStatement("insert int
o MYTESTTABLE (a,b) values (?,?)")
                        pst.setInt(1, 1)
                        pst.setString (2, "a")
                        pst.executeUpdate()
                        pst.clearParameters()
                        pst.setInt (1, 2)
                        pst.setString (2, "b")
                        pst.executeUpdate()
```

```
pst.clearParameters()
                        pst.setInt (1, 3)
                        pst.setString (2, "c")
                        pst.executeUpdate()
                        pst.clearParameters()
                        pst.setInt (1, 4)
                        pst.setString (2, "c")
                        pst.executeUpdate()
                        pst.clearParameters()
                        pst.setInt(1, 5)
                        pst.setString (2, "c")
                        pst.executeUpdate()
                        pst.close
                        //Read the data
                        statement = connection.createStatement()
                        val resultSet = statement.executeQuery("select
a, b from MYTESTTABLE")
                        var counter =0
                        while ( resultSet.next() ) {
                                counter += 1
                                val val a = resultSet.getInt(1)
                                val val b = resultSet.getString(2)
                                println("record=[" + counter + "] a=[" +
val a + "] b=[" +val b + "]")
                        resultSet.close()
                        statement.close()
                } catch {
                        case ex : java.sql.SQLException => println("SQLEx
ception: "+ex)
                } finally {
                        connection.close()
```

- 3. Save the code to SampleScalaJDBC.scala.
- 4. Compile the program:

```
scalac SampleScalaJDBC.scala
```

### 5. Run the program:

Run the SampleScalaJDBC program as follows:

```
scala SampleScalaJDBC
```

The command should display a result like the following:

```
record=[1] a=[5] b=[c]

record=[2] a=[1] b=[a]

record=[3] a=[2] b=[b]

record=[4] a=[3] b=[c]

record=[5] a=[4] b=[c]
```

# **Connecting to Splice Machine with NodeJS / AngularJS**

This topic shows you how to connect to Splice Machine with NodeJS and AngularJS.

## **Watch the Video**

The following video shows you how to connect NodeJS and Angularjs with Splice Machine.

## **Using the Splice Machine ODBC Driver**

This topic describes how to configure and use the Splice Machine ODBC driver, which you can use to connect with other databases and business tools that need to access your database.



You **must** use the *Splice Machine* ODBC driver; other drivers will not work correctly.

This topic describes how to install and configure the Splice Machine ODBC driver for these operating systems:

- Installing the Splice Machine ODBC Driver on Windows
- >> Installing the Splice Machine ODBC Driver on Linux
- Installing the Splice Machine ODBC Driver on MacOS

This topic also includes an example that illustrates using our ODBC driver with the C language.

## **Installing and Configuring the Driver on Windows**

You can install the Windows version of the Splice Machine ODBC driver using the provided Windows installer (.msi file); we provide both 64-bit and 32-bit versions of the driver. Follow these steps to install the driver:

#### 1. Download the installer:


You can download the driver installer from our ODBC download site:

The file you download will have a name similar to these:

- >> splice odbc setup 64bit 1.0.28.0.msi
- >> splice odbc setup 32bit 1.0.28.0.msi

### 2. Start the installer


Double-click the installers .msi file to start installation. You'll see the Welcome screen:



Click the Next button to proceed.

- **3.** Accept the license agreement.
- 4. Select the destination folder for the driver

The default destination is generally fine, but you can select a different location if you like:



Click the Next button to continue to the Ready to Install screen.

#### 5. Click install

Click the Install button on the Ready to install screen. Installation can take a minute or two to complete.

**NOTE:** The installer may notify you that you either need to stop certain software before continuing, or that you can continue and then reboot your computer after the installation completes.


### 6. Finish the installation

Click the Finish button, and you're ready to use the Splice Machine ODBC driver.

### 7. Start the Windows ODBC Data Source Administrator tool


You need to add our ODBC driver to the set of Windows ODBC data sources, using the Windows ODBC Data Source Administrator tool; You can read about this tool here: <a href="https://msdn.microsoft.com/en-us/library/ms712362(v=vs.85).aspx">https://msdn.microsoft.com/en-us/library/ms712362(v=vs.85).aspx</a>.

You can find and start the Windows ODBC Administrator tool using a Windows search for ODBC on your computer; here's what it looks like on Windows 7:



### 8. Add the Splice Machine driver as a data source


Click the Add\_button the User DSN tab of the ODBC Data Source Administrator screen, and then select the Splice Machine driver you just installed:



### 9. Configure your new data source:

When you click the Finish button in the *Create New Data Source* screen, the ODBC Administrator tool displays the data source configuration screen.

Set the fields in the *Data Source* and *Splice Machine Login* sections similarly to the settings shown here:




The default user name is splice, and the default password is admin.

NOTE: For Server: on a cluster, specify the IP address of an HBase RegionServer. If you're running the standalone version of Splice Machine, specify localhost.

If you have Splice Machine running, you can click the *Test...* button at the bottom of the Configuration dialog to verify that all is well.

### 10. Configure logging (optional):

You can optionally configure the ODBC driver to log activity. This can be handy for debugging connection issues; however, it adds overhead and will have a significant impact on performance. Click the <u>Logging Options</u> button in the ODBC Administrator *Configuration* screen to enable or disable logging:



### **Installing the Driver on Linux**

Follow these steps to install the Splice Machine ODBC driver on a Linux computer:

### 1. Make sure you have unixODBC installed.

You must have version 2.2.12 or later of the unixODBC driver manager installed to run the Splice Machine ODBC driver.

Some Linux distributions include unixODBC, while others do not. Our driver will not work without it. For more information about unixODBC, see: <a href="http://www.unixodbc.org">http://www.unixodbc.org</a>.

### 2. Download the installer:

You can download the driver installer from our ODBC download site: <a href="https://www.splicemachine.com/get-started/odbc-driver-download/">https://www.splicemachine.com/get-started/odbc-driver-download/</a>

Download the installer to the Linux computer on which you want to install the driver. The file will have a name similar to this:

### 3. Unzip the installation package

Use the following command to unpack the tarball you installed, substituting in the actual version number from the download:

This creates a directory named splice odbc 64-<version>.

### 4. Install the driver:

Navigate to the directory that was created when you unzipped the tarball, and run the install script:

If you run the script as root, the default installation directory is /usr/local/splice:

```
sudo ./install.sh
```

If you run the script as a different user, the driver is installed to ~/splice.

```
./install.sh
```

The script creates a splice directory in the install location; you'll be prompted for that location, which defaults to /usr/local.

You'll also be prompted to enter the IP address of the Splice Machine server, which defaults to 127.0.0.1.

The install directory, e.g. /usr/local/splice, will contain two subdirectories:

Directory	Contents
lib64	The driver binary.
errormessages	The XML error message source for any error messages issued by the driver.

### 5. Configure the driver:

If you ran the installation script as root, the odbc.ini, odbcinst.ini, and splice.odbcdriver.ini configuration files were copied into the /etc folder, and any previous copies were renamed, e.g. odbc.ini.1. If you did not run the installation script as root, then hidden versions of the same files are located in your \$HOME directory: .odbc.ini, .odbcinst.ini, and .splice.odbcdriver.ini.

File	Description
odbc.ini	Specifies the ODBC data sources (DSNs).
odbcinst.ini	Specifies the ODBC drivers.
splice.odbcdriver.ini	Configuration information specific to the Splice Machine ODBC driver.

The default version of the odbc.ini file looks like this:

```
[ODBC Data Sources]
SpliceODBC64 = SpliceODBCDriver
[SpliceODBC64]
Description = Splice Machine ODBC 64-bit
              = /usr/local/splice/lib64/libsplice odbc.so
Driver
              = splice
PWD
              = admin
              = 127.0.0.1
URL
PORT
              = 1527
              = peerAuthentication
SSL
            = /home/splice/client.pem
= /home/splice/client.key
SSL CERT
SSL_PKEY
SSL TRUST
              = TRUE
```

If you specified a different installation directory, you need to update the <code>Driver</code> location setting in your <code>odbc.ini</code> file. This is not typically required; however, if you do make this change, you should copy your modified file to the <code>/etc</code> directory.

```
cp odbc.ini /etc/
```

If you are connecting to a Kerberos-enabled cluster using ODBC, you must add this parameter:

```
USE KERBEROS = 1
```

For more information about connecting to a Kerberos-enabled cluster, see <u>Connecting to Splice Machine Through HAProxy</u>.

### 6. Configure Driver Logging, if desired

You can edit the splice.odbcdriver.ini file to configure driver logging, which is disabled by default:

```
[Driver]
DriverManagerEncoding=UTF-16
DriverLocale=en-US
ErrorMessagesPath=/usr/local/splice/errormessages/
LogLevel=0
LogNamespace=
LogPath=
ODBCInstLib=/usr/lib64/libodbcinst.so
```

To configure logging, modify the LogLevel and LogPath values:

# LogLevel You can specify one of the following values: 0 = OFF1 = LOG FATAL 2 = LOG ERROR3 = LOG WARNING4 = LOG INFO5 = LOG DEBUG6 = LOG TRACE The larger the LogLevel value, the more verbose the logging. Logging does impact driver performance. LogPath The path to the directory in which you want the logging files stored. Two log files are written in this directory: splice driver.log Contains driver interactions with the application and the driver manager. Contains information about the drivers interaction splice derby.log with the Splice Machine cluster.

After configuring logging, copy the file to /etc:

### 7. Verify your installation

You can test your installation by using the following command to run isql:

isql SpliceODBC64 splice admin

### **Installing the Driver on MacOS**

Follow these steps to install the Splice Machine ODBC driver on a MacOS computer:



Our MacOS ODBC driver is currently in Beta release.

### 1. Make sure you have iODBC installed.

You must have an ODBC administration driver to manage ODBC data sources on your Mac. We recommend installing the iODBC driver for the Mac, which you'll find on the iODBC site: <a href="www.iodbc.org/">www.iodbc.org/</a>

#### 2. Download the installer:

You can download the driver installer from our ODBC download site: <a href="https://www.splicemachine.com/get-started/odbc-driver-download/">https://www.splicemachine.com/get-started/odbc-driver-download/</a>

Download the installer to the MacOS computer on which you want to install the driver. The file will have a name similar to this:

### 3. Unzip the installation package

Use the following command to unpack the tarball you installed, substituting in the actual version number from the download:

This creates a directory named splice odbc macosx64.

#### 4. Install the driver:

Navigate to the directory that was created when you unzipped the tarball, and run the install script:

```
./install.sh
```

Follow the installer prompts. In most cases, you can simply accept the default values.

The installer will create several files in the install directory, including these three files, which contain the configuration info that can be modified as required:

File	Description
odbc.ini	Specifies the ODBC data sources (DSNs).
odbcinst.ini	Specifies the ODBC drivers.
splice.odbcdriver.ini	Configuration information specific to the Splice Machine ODBC driver.

If you have not previously installed our ODBC driver, the installer will also copy the files into \$HOME/Library/ODBC for use with iODBC.

### 5. Configure the driver:

The installed driver is configured with settings that you specified when responding to the installer prompts. You can change values as follows:

### a. Edit the odbc.ini file to match your configuration.

You'll find the odbc.ini file in your \$HOME/Library/ODBC directory; we also create a link to this file in \$HOME/.odbc.ini. You can edit odbc.ini (or .odbc.ini) from either location.

NOTE: The URL field in the odbc.ini file is actually the IP address of the Splice Machine server.

The default version of the odbc.ini file looks like this:

```
[ODBC Data Sources]

SpliceODBC64 = SpliceODBCDriver

[SpliceODBC64]

Description = Splice Machine ODBC 64-bit

Driver = /usr/local/splice/lib64/libsplice_odbc.so

UID = splice

PWD = admin

URL = 0.0.0.0

PORT = 1527
```

If you are connecting to a Kerberos-enabled cluster using ODBC, you must add this parameter:

```
USE KERBEROS = 1
```

For more information about connecting to a Kerberos-enabled cluster, see <u>Connecting to Splice Machine Through HAProxy</u>.

### b. Edit (if desired) and copy the splice.odbcdriver.ini file:

The splice.odbcdriver.ini file contains information specific to the driver. You can edit this file to configure driver logging, which is disabled by default:

```
[Driver]
DriverManagerEncoding=UTF-16
DriverLocale=en-US
ErrorMessagesPath=/usr/local/splice/errormessages/
LogLevel=0
LogNamespace=
LogPath=
ODBCInstLib=/usr/lib64/libodbcinst.so
```

A copy of the Splice Machine ODBC configuration file, splice.odbcdriver.ini, which contains the default values, was copy to /Library/ODBC/SpliceMachine during installation. You will need root access to modify this file:

sudo vi /Library/ODBC/SpliceMachine/splice.odbcdriver.ini

To configure logging, modify the LogLevel and LogPath values:

### LogLevel

You can specify one of the following values:

0 = OFF

1 = LOG FATAL

2 = LOG ERROR

3 = LOG WARNING

4 = LOG INFO

5 = LOG DEBUG

6 = LOG\_TRACE

The larger the LogLevel value, the more verbose the logging.



Logging does impact driver performance.

### LogPath

The path to the directory in which you want the logging files stored. Two log files are written in this directory:

splice\_driver.log contains driver interactions with the

application and the driver manager

splice\_derby.log contains information about the drivers

interaction with the Splice Machine cluster

### 6. Verify your installation

You can test your installation by launching the 64-bit version of the iODBC Data Source Administrator for both configuring and testing your DSNs. Note that you can also perform your odbc.ini modifications with this tool instead of manually editing the file.

## Using the ODBC Driver with C

This section contains a simple example of using the Splice Machine ODBC driver with the C programming language. This program simply displays information about the installed driver. You can compile and run it by following these steps:

### 1. Copy the code

You can copy and paste the code below:

```
#include <stdio.h>
#include <sql.h>
#include <sqlext.h>
main() {
   SQLHENV env;
   char driver[256];
   char attr[256];
   SQLSMALLINT driver ret;
   SQLSMALLINT attr ret;
   SOLUSMALLINT direction;
   SOLRETURN ret;
   SQLAllocHandle (SQL HANDLE ENV, SQL NULL HANDLE, &env);
   SQLSetEnvAttr(env, SQL ATTR ODBC VERSION, (void *) SQL OV ODBC3, 0);
   direction = SQL FETCH FIRST;
   while (SQL SUCCEEDED (ret = SQLDrivers (env, direction,
         driver, sizeof(driver), &driver ret,
         attr, sizeof(attr), &attr ret))) {
         direction = SQL FETCH NEXT;
      printf("%s - %s\n", driver, attr);
      if (ret == SQL SUCCESS WITH INFO) printf("\tdata truncation\n");
```

### 2. Compile it

```
#!/bin/bash
# gcc -I /usr/local/splice/unixODBC/include listODBCdriver.c -o listODBCd
river -L/usr/local/splice/lib -lodbc -lodbcinst -lodbccr
```

### 3. Run the program

Run the compiled listODBCdriver:

```
prompt:~$ ./listODBCdriver
```

The command should display a result like the following:

```
Splice Machine - Description=Splice Machine ODBC Driver
```

## **Connecting to Splice Machine with Python and ODBC**

This topic shows you how to compile and run a sample Python program that connects to Splice Machine using our ODBC driver. The SpliceODBCConnect.py program does the following:

- >> connects to a standalone (localhost) version of Splice Machine
- >> retrieves and displays records from several system tables
- >> creates a tables inserts several sample records into it
- >> selects and aggregates records from the new table

## **Compile and Run the Sample Program**

This section walks you through compiling and running the SpliceODBCConnect.py example program, in the following steps:

### 1. Install the Splice Machine ODBC driver

Follow our instructions for installing the driver on Unix or Windows.

### 2. Install the pyodbc module

You need to install the pyodbc open source Python module, which implements the DB API 2.0 specification and can be used with Python 2.4 or higher. See <a href="https://github.com/mkleehammer/pyodbc">https://github.com/mkleehammer/pyodbc</a> for more information about this module.

To install pyodbc on the server on which you'll be running your job:

```
yum install gcc-c++pip install pyodbc
```

### 3. Confirm that you can connect

To confirm that you're ready to use the ODBC driver, launch the python shell and enter the following commands, replacing <a href="SpliceODBC64">SpliceODBC64</a> with the name of your data source (which is found in the odbc.ini file that you edited when installing our ODBC driver):

```
import pyodbc
cnxn = pyodbc.connect("DSN=SpliceODBC64")
cursor = cnxn.cursor()
cursor.execute("select * from SYS.SYSTABLES")
row = cursor.fetchone()
print('row:',row)
```

### 4. Copy the example program code:

You can copy and paste the code below:

```
#!/usr/bin/python
# This program is used to demonstrate connecting to Splice Machine using
import pyodbc
#Connect to Splice Machine using an Datasource
cnxn = pyodbc.connect("DSN=SpliceODBC64")
#Open a cursor
cursor = cnxn.cursor()
#Build a select statement
cursor.execute("select * from SYS.SYSTABLES")
#Fetch one record from the select
row = cursor.fetchone()
#If there is a record, print it
if row:
       print(row)
#The following will continue to retrieve one record at a time from the re
sultset
while 1:
       row = cursor.fetchone()
        if not row:
               break
        print('table name:', row.TABLENAME)
#The following is an example of using the fetchall option, instead of ret
rieving one record at time
cursor.execute("select * from SYS.SYSSCHEMAS")
rows = cursor.fetchall()
for row in rows:
        print(row.SCHEMAID, row.SCHEMANAME)
#Create a table
cursor.execute("CREATE TABLE MYPYTHONTABLE(a int, b varchar(30))")
#Insert data into the table
cursor.execute("insert into MYPYTHONTABLE values (1,'a')");
cursor.execute("insert into MYPYTHONTABLE values (2,'b')");
cursor.execute("insert into MYPYTHONTABLE values (3,'c')");
cursor.execute("insert into MYPYTHONTABLE values (4,'c')");
cursor.execute("insert into MYPYTHONTABLE values (5,'c')");
```

```
#Commit the creation of the table
cnxn.commit();

#Confirm the records are in the table
row = cursor.execute("select count(1) as TOTAL from SPLICE.MYPYTHONTABL
E").fetchone()
print(row.TOTAL)
```

- 5. Save the code to SpliceODBCConnect.py.
- 6. Run the program:

Run the SpliceODBCConnect.py program as follows:

```
python ./SpliceODBCConnect.py
```

## Connecting to Splice Machine with C and ODBC

This topic shows you how to compile and run a sample C program that exercises the Splice Machine ODBC driver. The <code>listODBCdriver</code> program verifies that the driver is correctly installed and available.

## **Compile and Run the Sample Program**

This section walks you through compiling and running the <code>listODBCdriver</code> example program, which simply displays information about the installed driver.

### 1. Install the ODBC driver

<u>Follow our instructions</u> for installing the driver on Unix or Windows.

### 2. Copy the example program code

You can copy and paste the code below:

```
#include <stdio.h>
#include <sql.h>
#include <sqlext.h>
main() {
   SQLHENV env;
   char driver[256];
   char attr[256];
   SQLSMALLINT driver ret;
   SQLSMALLINT attr ret;
   SQLUSMALLINT direction;
   SOLRETURN ret;
   SQLAllocHandle (SQL HANDLE ENV, SQL NULL HANDLE, &env);
   SQLSetEnvAttr(env, SQL ATTR ODBC VERSION, (void *) SQL OV ODBC3, 0);
   direction = SQL FETCH FIRST;
   while (SQL SUCCEEDED (ret = SQLDrivers (env, direction,
         driver, sizeof(driver), &driver ret,
         attr, sizeof(attr), &attr ret))) {
         direction = SQL FETCH NEXT;
      printf("%s - %s\n", driver, attr);
      if (ret == SQL SUCCESS WITH INFO) printf("\tdata truncation\n");
```

### 3. Compile it

```
#!/bin/bash
# gcc -I /usr/local/splice/unixODBC/include listODBCdriver.c -o listODBCd
river -L/usr/local/splice/lib -lodbc -lodbcinst -lodbccr
```

### 4. Run the program

Run the compiled listODBCdriver:

```
prompt:~$ ./listODBCdriver
```

The command should display a result like the following:

Splice Machine - Description=Splice Machine ODBC Driver

## **Connecting DBeaver with Splice Machine Using JDBC**


This topic shows you how to connect DBeaver to Splice Machine using our JDBC driver. To complete this tutorial, you need to:

- >> Have Splice Machine installed and running on your computer.
- Have DBeaver installed on your computer. You can download an installer and find directions on the DBeaver web site (<u>dbeaver.jkiss.org</u>).

## **Connect DBeaver with Splice Machine**

This section walks you through configuring DBeaver to connect with Splice Machine

- 1. Install DBeaver, if you've not already done so Follow the instructions on the DBeaver web site.
- 2. Start a Splice Machine session on the computer on which you have installed DBeaver Splice Machine must be running to create and use it with DBeaver.
- 3. Configure a Splice Machine connection in DBeaver
  Follow the instructions in the next section, Configure a DBeaver Connection for Splice Machine, to create and test a new connection in DBeaver.
- 4. Connect DBeaver to Splice Machine In DBeaver's Database Navigator, select the Splice Machine connection you configured. Your database will display, and you can inspect objects or enter SQL to interact with your data.




### **Configure a DBeaver Connection for Splice Machine**

Follow these steps to configure and test a new driver and connection alias in DBeaver .

- 1. Start a Splice Machine session on the computer on which you have installed DBeaver
- 2. Open the DBeaver application.
- 3. Select Driver Manager in the DBeaver Database menu, then click the New button to create a new driver:
  - a. Specify values in the Create New Driver form; these are the default values:

Field	Value
Driver Name:	Any name you choose
Class Name:	com.splicemachine.db.jdbc.ClientDriver
URL Template:	<pre>jdbc:splice://{host}:{port}/splicedb;create=false</pre>
Default Port:	1527
Description:	Any description you want to specify


**b.** Click the Add File button, then navigate to and select the Splice JDBC Driver jar file. which you'll find it in the jdbc-driver folder under the splicemachine directory on your computer.




NOTE: Instead of manually entering the Class Name for your driver, you can click the Find Class button to discover the driver class name associated with the file you've located.</span>

**4.** Click ok to save the driver entry and close the form.

- 5. Select New Connection in the DBeaver Database menu, then follow these steps to create a new connection that uses our driver:
  - **a.** Scroll through the connection type list and select the Splice Machine JDBC driver that you just created, then click the Next button:




b. Several of the fields in the *Generic JDBC Connection Settings* screen were pre-populated for you when you selected the driver. You need to fill in the <u>User name</u>: (default is splice) and <u>Password</u>: (default is admin) field values:




c. Click the Test Connection button to verify your connection.

**NOTE:** Splice Machine must be running on your computer for the connection test to succeed.

**d.** Click the Next button to reveal the network configuration screen. If you have VPN requirements, enter the appropriate information in this screen; if not, simply click the Next button again.



**e.** You can optionally modify any settings in the *Finish connection creation* screen; then click the Finish button to save your new connection.



# **Connecting DBVisualizer with Splice Machine Using JDBC**

This topic shows you how to connect DBVisualizer to Splice Machine using our JDBC driver. To complete this tutorial, you need to:


- >> Have Splice Machine installed and running on your computer.
- >> Have DBVisualizer installed on your computer. You can find directions on the DBVisualizer web site (<a href="https://www.dbvis.com">https://www.dbvis.com</a>); you can also download a free trial version of DBVisualizer from there.

## **Connect DBVisualizer with Splice Machine**

This section walks you through configuring DBVisualizer to connect with Splice Machine

- 1. Install DBVisualizer, if you've not already done so Follow the instructions on the DBVis web site.
- 2. Configure a Splice Machine connection in DBVisualizer

  Follow the instructions in the next section, Configure a DBVisualizer Connection for Splice Machine, to create and test a new connection in DBVisualizer.
- 3. Connect DBVisualizer to Splice Machine
  In DBVisualizer, open the connection alias you created and click the Connect button. Your database will display in DBVisualizer, and you can inspect objects or enter SQL to interact with your data.




### **Configure a DBVisualizer Connection for Splice Machine**

Follow these steps to configure and test a new driver entry and connection in DBVisualizer.

- 1. Start a Splice Machine session on the computer on which you have installed DBVisualizer.
- 2. Open the DBVisualizer application.
- 3. Use the Driver Manager to create a new DBVisualizer driver entry.

Select Driver Manager from the Tools menu; in the Driver Manager screen:


- **a.** Click the green plus sign + button to add a new driver entry.
- **b.** Name the driver and enter jdbc:splice://localhost:1527/splicedb in the URL Format field:



- c. In the Driver File Paths section, click User Specified, and then click the yellow folder icon.
- **d.** Navigate to and select the Splice JDBC Driver jar file. which you'll find it in the jdbc-driver folder under the splicemachine directory on your computer.
- e. Close the Driver Manager screen.

#### 4. Create a DBVisualizer connection alias that uses the new driver:

- a. Select Create Database Connection from the Database menu. If prompted about using the Wizard, click the No Wizard button.
- b. Name the connection (we use Splice Machine), then click the empty field next to the Driver (JDBC) caption and select the driver you just created:



c. Enter the following URL into the Database URL field that appears once you've selected the driver:

jdbc:splice://localhost:1527/splicedb



Use localhost:1527 with the standalone (local computer) version of splicemachine. If you're running Splice Machine on a cluster, substitute the address of your server for localhost; for example: jdbc:splice://mySrv123cba:1527/splicedb.

**d.** Fill in the Userid (splice) and Password (admin) fields. Then click the Connect button. Your Splice Machine database will now display in DBVisualizer:

# **Connecting Cognos with Splice Machine Using ODBC**

This topic shows you how to connect Cognos to Splice Machine using our ODBC driver. To complete this tutorial, you need to:

- Have Cognos installed on your Windows or MacOS computer. You can find directions on the IBM web site (<a href="http://www-03.ibm.com/software/products/en/cognos-analytics">http://www-03.ibm.com/software/products/en/cognos-analytics</a>); you can also download a free trial version of Cognos from there.
- Have the Splice Machine ODBC driver installed on your computer. Follow our instructions.

#### Watch the Video

The following video shows you how to connect Cognos to Splice Machine using our ODBC driver.

# **Connecting SQuirreL with Splice Machine Using JDBC**

This topic shows you how to connect SQuirreL to Splice Machine using our JDBC driver. To complete this tutorial, you need to:

- >> Have Splice Machine installed and running on your computer.
- Have SQuirreL installed on your computer. You can find directions on the SQuirreL web site (<a href="http://squirrel-sql.sourceforge.net/">http://squirrel-sql.sourceforge.net/</a>); you can also download a free trial version of SQuirreL from there. You must also install the Derby plug-in for SQuirreL.

## **Connect SQuirreL with Splice Machine**

This section walks you through configuring SQuirreL to connect with Splice Machine

- 1. Install SQuirreL, if you've not already done so: Follow the instructions on the SQuirreL web site.
- 2. Install the Derby plug-in for Squirrrel


This plug-in is required to operate with Splice Machine. If you didn't select the Derby plug-in when you installed SQuirreL, you can <u>download Apache Derby here</u> and drop the plugin file into the plugin/ directory of your SQuirrel SQL installation directory. See <u>SQuirrel's Plugin Overview</u> for more info.

- 3. Start a Splice Machine session on the computer on which you have installed SQuirreL Splice Machine must be running to create and use it with SQuirreL.
- Configure a Splice Machine connection in SQuirreL
   Follow the instructions in the next section, <u>Configure a SQuirreL Connection for Splice Machine</u>, to create and

Follow the instructions in the next section, <u>Configure a SQuirreL Connection for Splice Machine</u>, to create and test a new connection in SQuirreL.

5. Connect SQuirreL to Splice Machine

In SQuirreL, open the connection alias you created, enter your credentials, and click the Connect button. Your database will display in SQuirreL, and you can inspect objects or enter SQL to interact with your data.




### **Configure a SQuirreL Connection for Splice Machine**

Follow these steps to configure and test a new driver and connection alias in SQuirreL.


- 1. Start a Splice Machine session on the computer on which you have installed SQuirreL
- 2. Open the SQuirreL application.
- 3. Click the SQuirreL Drivers tab, which is near the upper left of the window:



- 4. In the *Drivers* tab, click the blue + sign Create a New Driver icon to display the *Add Driver* window.
  - **a.** Name the driver and enter jdbc:splice://localhost:1527/splicedb in the Example URL field:




c. Navigate to and select the Splice JDBC Driver jar file. which you'll find it in the jdbc-driver folder under the splicemachine directory on your computer.




**d.** Now, back in the Add Driver screen, click the List Drivers button verify that you see the Splice Machine driver:

com.splicemachine.db.jdbc.ClientDriver


- e. Click the OK button to add the driver entry in SQuirreL.
- 5. Create a connection alias in SQuirreL
  - **a.** Click the *Aliases* tab in the SQuirreL window, and then click the Create new Alias (blue + sign) button.
  - b. Enter a name for your alias and select the driver you just created from the drop-down list



and admin for the Password: value.



d. Click the Connect button to verify your connection. You should see the success message:



# **Connecting Tableau with Splice Machine Using ODBC**

This topic shows you how to connect Tableau to Splice Machine using our ODBC driver. To complete this tutorial, you need to:

- >> Have Tableau installed on your Windows or MacOS computer. You can find directions on the Tableau web site (<a href="www.tableau.com">www.tableau.com</a>); you can also download a free trial version of Tableau from there.
- >> Have the Splice Machine ODBC driver installed on your computer. Follow the instructions in our Developer's Guide.

## **Connect Tableau with Splice Machine**

This section walks you through configuring Tableau on a Windows PC to connect with Splice Machine using our ODBC driver.

1. Install Tableau, if you've not already done so Follow the instructions on the Tableau web site.

#### 2. Install the Splice Machine ODBC driver

<u>Follow our instructions</u> for installing the driver on Unix or Windows. This includes instructions for setting up your data source (DSN), which we'll use with Tableau.

#### 3. Connect from Tableau:

Follow these steps to connect to your data source in Tableau:

a. Open the list of connections:

Click Connect to Data on Tableau's opening screen to reveal the list of possible data connections.

b. Select ODBC:

Scroll to the bottom of the To a server list, click More Servers, then click Other Databases (ODBC).

**c.** Select your DSN and connect:

Select the DSN you just created (typically named Splice Machine) when installing our ODBC driver) from the drop-down list, and then click the Connect button.

d. Select the schema:

Select the schema you want to work with (splice), and then select the Single Table option.

e. Select the table to view:

Click the search (magnifying glass) icon, and then select the table you want to view from the drop-down list.

For example, we choose the CUSTOMERS table and specify CUSTOMERS (SPLICE) as the connection name for use in Tableau.

4. After you click ox, *Tableau* is ready to work with your data.