

15 – FUNCTIONS & PARAMETERS

COMP256 – COMPUTING ABSTRACTIONS
DICKINSON COLLEGE

HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - Values of the **function's parameters (FP)**
 - Return address (RA)**
 - Values of the function's **local variables (LV)**

```
main() {  
    read x;  
    read y;  
    read z;  
  
    m = max3(x,y,z);  
  
    print m;  
}  
  
max3(a,b,c) {  
    x=max(a,b)  
    y=max(x,c)  
    return y;  
}  
  
max(a,b) {  
    x = a;  
    if (b > a)  
        x = b;  
    return x;  
}
```

1

HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values

```
main() {  
    read x;  
    read y;  
    read z;  
  
    A m = max3(x,y,z);  
    print m;  
}  
  
max3(a,b,c) {  
    B x=max(a,b)  
    C y=max(x,c)  
    return y;  
}  
  
max(a,b) {  
    x = a;  
    if (b > a)  
        x = b;  
    return x;  
}
```

LV: \emptyset
RA: Exit
FP: \emptyset

2

3

HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values


```
main() {  
    read x;  
    read y;  
    read z;  
  
    A m = max3(x,y,z);  
    print m;  
}  
  
max3(a,b,c) {  
    B x=max(a,b)  
    C y=max(x,c)  
    return y;  
}  
  
max(a,b) {  
    x = a;  
    if (b > a)  
        x = b;  
    return x;  
}
```

LV: x=3 y=7 z=4
RA: Exit
FP: \emptyset

main

HLL FUNCTION CALL STACK


- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



5

HLL FUNCTION CALL STACK


- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



6

HLL FUNCTION CALL STACK


- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



7


HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values




8

9

HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values




10

11


HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values




HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values




12

13

HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values




14

15


HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's **local variable (LV)** values



HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's local variable (LV)** values

```

main() {
    read x;
    read y;
    read z;

    A m = max3(x,y,z); 7
    print m;
}

max3(a,b,c) {
    B x=max(a,b)
    C y=max(x,c)
    return y;
}

max(a,b) {
    x = a;
    if (b > a)
        x = b;
    return x;
}
  
```

LV: x=3 y=7 z=4 m=7
RA: Exit
FP: \emptyset

16

17

7

HLL FUNCTION CALL STACK

- The (function) **call stack** maintains the state of a running program.
- Each function call adds a **stack frame** to the call stack.
- A stack frame contains the:
 - function's parameter (FP)** values
 - Return address (RA)**
 - function's local variable (LV)** values

```

main() {
    read x;
    read y;
    read z;

    A m = max3(x,y,z);
    print m;
}

max3(a,b,c) {
    B x=max(a,b)
    C y=max(x,c)
    return y;
}

max(a,b) {
    x = a;
    if (b > a)
        x = b;
    return x;
}
  
```

LV: x=3 y=7 z=4 m=7
RA: Exit
FP: \emptyset

LV: x=3 y=7 z=4 m=7
RA: Exit
FP: \emptyset

UNPACKING THE FUNCTION CALL ABSTRACTION

- Function calls in a high level language are an abstraction for the low level instructions in assembly/machine language that explicitly manage the stack frames.

- These instructions:

- Put parameter values into the stack frame
- Call the function
- Preserve the return address into the stack frame
- Preserve used register values in the stack frame
- Retrieve parameters from the stack frame
- Execute the function
- Set the return value
- Restore used register values from stack frame
- Restore the return address from stack frame
- Remove parameters from stack frame
- Return from the function
- Get the return value and continue execution

Calling Code
Function Code
Calling Code

FUNCTION CALLS IN ASSEMBLY

MAIN:

...
CALL FUNC

Get the return value
and continue execution.

Put the parameter values
into the stack frame.

HALT

Preserve the return address
and used register values in
the stack frame.

FUNC:

...
...

Remove parameters
from stack frame.

Retrieve parameters
from the stack frame.

...
RET

Execute the function.
Set the return value.

Restore used registers
and return address
from stack frame.

CALLING AND RETURNING


Instruction	Example	Meaning
CALL L RET	CALL FUNC RET	$R12 = PC + 4, PC = FUNC$ $PC = R12$ R12 is a reserved register used for the return address of function calls.
MAIN:	... CALL FUNC ... HALT	
FUNC:	... RET	

MANAGING STACK FRAMES

Instruction	Example	Meaning
PUSH R POP R	PUSH R2 POP R2	$MM[R13] = R2; R13 = R13 - 4$ $R13 = R13 + 4; R2 = MM[R13]$
.stacksize 100 LOAD R0 #10 PUSH R0 ADD R0 R0 #5 PUSH R0 POP R1 POP R2		.stacksize 100 Set aside 100 bytes, enough for 25 pushes, for the function call stack and initialize R13. R13 is a reserved register that holds the memory address for the next PUSH operation. Register indirect addressing is used to access values in the stack frames.

WHERE FOR ART THOU STACK?

- The .stacksize directive:
 - Sets aside the specified number of bytes to be used for the call stack.
 - Initializes the value of R13 to the address at which the next PUSH will occur.
 - Known as the *top of the stack*.



GENERAL PURPOSE & RESERVED REGISTERS

- R0-R11: General purpose registers
 - Use them however you want in your programs.
- R12: The Return Address when a CALL is made
 - Set by CALL, used by RET
- R13: The Stack Pointer (address for the next PUSH)
 - Used by PUSH and POP
- R14: The Return Value from a function.
 - Functions will place their return value into R14, calling code will retrieve the return value from R14.
- R15: Scratch Register
 - Used by the assembler for intermediate results. Do not use.

AN EXAMPLE

```
main() {
    read x;
    read y;

    m = max(x,y);

    print m;
}
```

```
max(a,b) {
    x = a;
    if (b > a)
        x = b;

    return x;
}
```

MAX FUNCTION

```
max(a,b) {
    x = a;
    if (b > a)
        x = b;

    return x;
}
```

```
MAX: PUSH R12      * + 4
      PUSH R1      * + 8
      PUSH R2      * + 12
      PUSH R3      * + 16

      LOAD R2 R13 +20 * R2 is b
      LOAD R1 R13 +24 * R1 is a

      MOV R3 R1      * R3 is x = a
      BGEQ R1 R2 SKIP * a >= b
      MOV R3 R2      * x = b
      MOV R14 R3      * RV = x

      POP R3
      POP R2
      POP R1
      POP R12

      ADD R13 R13 #8

      RET
```

MAIN FUNCTION

```
x: .word
y: .word
m: .word

* Allocate the call stack
.stacksize 100 * 100 bytes/25 words

main() {
    read x;
    read y;

    m = max(x,y);

    print m;
}

MAIN: LOAD R0 STDIN      * read x
      STORE R0 X
      LOAD R1 STDIN      * read y
      STORE R1 Y

      * Put parameters in stack frame for call
      PUSH R0             * X
      PUSH R1             * Y

      CALL MAX            * Transfer control to MAX

RA:   STORE R14 M          * Get the return value
      STORE R14 STDOUT

      HALT
```