Microkernel Construction

Inter-Process-Communication


SS2014

Use Cases

- Generally in microkernels:
 - Control transfer (synchronization)
 - Data transfer (send/receive data)
- Specifically
 - Grant access to resources (memory, io-ports, capabilities)
 - Manage and handle page faults, interrupts and other resources
 - Timeouts
 - Yield CPU (sleep)
- Allows feature-rich user-level protocols on top
 - Tailored for client/server communication
 - Microkernel talks some simple protocols to support user applications (page fault IPC, exception IPC)
- Optimized for performance

System calls

- Monolithic kernel: 2 kernel entries/exits
- Microkernel: 4 kernel entries/exits + 2 context switches



Benjamin Engel Torsten Frenzel

TU Dresden
Operating
Systems Group

Calls between system services

- Monolithic kernel: 1 function call
- Microkernel: 4 kernel entries/exits + 2 context switches

Network Subsystem Driver

Monolithic kernel

Hardware

Network Subsystem

1 4 2 3

Microkernel

Hardware

Benjamin Engel Torsten Frenzel


TU Dresden Operating Systems Group

POSIX IPC Primitives

Semaphore


- Atomic increment and decrement of counter with wait queue
- Used to synchronize critical sections
- Shared memory
 - Special file type, that uses physical memory
- Message queue
 - Special file type for block-based synchronous communication
- Pipe
 - Untyped, directed communication channel
- FIFO
 - Special file type similar to a pipe
 - Blocking and non-blocking mode
- Regular files
- Signals
 - Asynchronous trigger; many have predefined actions

Recap: Thread Switch



- Enter Kernel
- Switch A → B
- Exit Kernel

Send Message (async)



Send

- Prepare Message
- Enter Kernel
- Allocate in-kernel message buffer
- Copy message in
- Find Receiver and tag new msg available
- Exit Kernel

Receive

- Enter Kernel
- Copy message out to user memory
- Free in-kernel message buffer
- Exit Kernel

IPC Properties and Terms

- Connectionless vs. connection-oriented
 - What is the order of delivered messages
- Reliable vs. Unreliable
 - Can a message get lost
- Point-to-point vs broadcast or multicast
 - How many receiver can be addressed
- Asynchronous vs. synchronous
 - Does the sender wait for the receiver
- Buffer vs. unbuffered
 - Message buffering within the kernel
- Direct vs. indirect
 - How is the destination addressed
- Data items
 - What type of data items are transferred

Synchronous vs. Asynchronous IPC

Synchronous IPC

- Sender blocks if receiver is not ready
- Requires no data buffering inside the kernel
- Wait queue for every receiving thread
 - Holds blocked senders for the receiver
 - Requires enqueue/deqeue policy

Asynchronous IPC

- Sender does not block if receiver is not ready
- Requires data buffering inside the kernel
- Suitable for interrupts because only one bit is transferred


Direct vs. Indirect IPC

Direct IPC:

Sending thread addresses another thread

Indirect IPC:

- Sending thread addresses communication object (called: port, portal, gate, endpoint)
- IPC object redirects message to a receiver thread
- Advantage 1: Hide the implementation of server threads
- Advantage 2: Possibility to hold state for client-server connection



Benjamin Engel Torsten Frenzel

TU Dresden
Operating
Systems Group

IPC Primitives

- Send
 - Send to specific thread/IPC object
- Closed receive
 - Receive from specific thread
- Open receive
 - Receive from any thread
- Send and closed wait
 - Send to and receive from specific thread/IPC object
 - Typical client operation call
- Send and open receive
 - Receive from any thread and send to specific thread
 - Typical server operation reply-and-wait
- Sleep
 - Neither send nor receive
 - Yield until timeout expires

Example: Mutual Exclusion with IPC

- User-level protocol provides mutual exclusion:
 - Synchronization thread protects critical section
 - Worker thread calls synchronization thread before entering
 - Synchronization thread replies if critical section can be entered
 - Worker thread blocks if critical section not available
 - Worker thread calls synchronization thread after leaving
 - Synchronization thread sends reply to next waiting worker thread
- Implementation not optimal for performance but correct
- Others:
 - Producer-consumer synchronization together with shared memory
 - Connection-oriented client-server communication

IPC Types

Register-only IPC

Very fast but amount of data is limited to number of registers

UTCB IPC

- User Thread Control Block: user accessible, kernel-provided and pinned page, message buffer with guaranteed no page faults
- Copy data from one UTCB to another UTCB
- Fast but amount of data is limited to UTCB size

User-memory IPC

- Copy of memory areas between user address-spaces
- Amount of data is not limited
- Page faults can occur


Flexpage IPC


- Mapping of memory areas and capabilities
- Page fault IPC is special case

Interrupt IPC

- Relaying Interrupts and Exceptions as messages


User Thread Control Block







Benjamin Engel Torsten Frenzel

TU Dresden Operating Systems Group







Wait, we can do more ...

- Sending pages instead of data → establishing shared memory regions
- Sending resources (precisely: access rights to resources)
 - → granting fine grained IO access to devices
- Sending IPC endpoints → build more communication channels between Thread
- Sending Interrupts → kernel translates interrupts to IPC messags
- Generalizes to capability transfers
 - Cap Mem → access right to a page
 - Cap_IO → resembles IO port rights
 - Cap_Obj → Kernel objects, like IPC endpoints, Threads,
 Semaphores, ...

Memory transfer: Flexpages

- Flexpages describe areas in address spaces (size aligned)
- Remember: Segments: Base + Limit
- Flexpage size 2^{size}, smallest is hardware page (e.g. 4KiB)


	Base		Or	der		~	
31		12	11	7	6		0

- 32bit, 4Kib page size → 20 bit Base
- 5 bit order → 2⁰ up to 2³¹, covers whole address space
 (6 bit in case of 64 bit address space)
- Sender and Receiver specifies Send/Recv-Flexpage

Base	Order	Size	Address Range
0	0	4KiB	0x00000000 - 0x00000FFF
0x4000	2	16KiB	0x00004000 - 0x00007FFF
0xC0000000	18	1GiB	0xC0000000 - 0xFFFFFFF
0x4000	3	32KiB	Invalid, not size aligned


UTCB IPC

- UTCBs hold relevant information of a thread
 - Kernel and user accessible (read and write)
 - Task-local and associated with **one** or more threads
 - No page faults can occur on access
- Can be used as message buffer




User-Memory IPC with Kernel Buffer

- Two copy operations
 - Copy send buffer to kernel buffer in sender's address space
 - Switch to receiver's address space
 - Copy kernel buffer to receive buffer in receiver's address space



User-Memory IPC with IPC Window

- IPC window provides 'view' into another address space
 - Temporary mapping inside the kernel address space
 - Flushed on each thread switch
- One copy operation
 - Map receive buffer to IPC window
 - Copy send buffer to IPC window




Benjamin Engel Torsten Frenzel

TU Dresden
Operating
Systems Group

Flexpage IPC


- Sender specifies one or more Send-flexpages
 - Send-flexpage is a flexpage with send base in receive window
- Receiver specifies Receive window flexpage



Flexpage IPC (2)

Send-flexpage is smaller than the receive window

 Target position in receive window is derived from page alignment and send base




Benjamin Engel Torsten Frenzel

TU Dresden Operating Systems Group Example: send flexpage has ¼ size of receive flexpage → 4 possibilities to map flexpage into receive window

Flexpage IPC (3)

Send flexpage is larger than receive window

- Source position in send flexpage is derived from page alignment and send base
- ⇒ send base is a hot spot for mapping IPC
- ⇒ Actual *send base* depends on information about the receiver




Example: receive flexpage has 1/4 size of send flexpage

Exception IPC

- For every exception to be handled, have a thread ready to receive, e.g. x86 exception #14 → page fault handler
- Kernel prepares IPC message with selected architectural state, in case of page faults: faulting address
- Kernel opens whole faulting address space to receive a flexpage, thus accepting any mapping
- Page fault handler thread replies with flexpage to resolve page fault

Pagefault Handling

- General pagefault mechanism:
 - 1. Application causes a page fault
 - 2. Kernel sends Pagefault IPC to pager thread
 - 3. Pager thread replies with flexpage IPC
 - 4. Application receives mapping and resumes



Benjamin Engel Torsten Frenzel


TU Dresden
Operating
Systems Group

Interrupt IPC

- Kernel has driver to program interrupt controller
- Interrupts from peripheral devices (disk,network, ...) preempt current activity and trap in the kernel
- Interrupts are implemented as special sender object
 - Threads can attach itself to interrupts
 - Thread can wait and receive message from an interrupt
 - Thread can wait on many interrupts using open wait
 - One bit of information is transferred
 - Interrupt is enqueued into sender queue of receiver thread if thread is not ready
- Interrupt source is disabled after it is has triggered and needs to be explicitly enabled by the receiver

Switching from Send to Receive

- Switch from send part to receive part atomically
- Why prepare receive part atomically?
 - Servers do not trust clients
 - → Servers reply with timeout zero
 - Client needs to be ready to receive immediately after sending
 - → Flip one bit to switch from send to receive part



Pagefaults during IPC

- Long IPC can touch user memory
 - → Page faults can occur if virtual address is not mapped to physical memory
 - Page fault in sender's address space
 - Page fault in IPC window (receiver's address space)
- Page fault handler suspends ongoing IPC operation
 - Save current IPC state (somewhere)
 - Setup nested page fault IPC
 - → Start another IPC during ongoing IPC
 - If page fault IPC succeeded:
 - Restore suspended IPC operation
 - If page fault IPC failed:
 - Abort ongoing IPC operation
- Even more complicated if ongoing page fault IPC is canceled

IPC Termination

- Normally
- Abnormally because of non-existing partner
- Abnormally because of memory copy failure
 - Due to too small send or receive buffer
- Abnormally because of memory map failure
 - Due to shortage of page tables
- IPC partner is canceled by another thread
 - Cancel operation executed before rendezvous
- IPC partner is aborted by another thread
 - Cancel operation executed after rendezvous
- IPC partner is killed by another thread
- Timeout occurs
 - Send/receive IPC timeout
 - Send/receive page fault timeout