GRL: a generic C++ reinforcement learning library

Wouter Caarls <mailto:wouter@caarls.org>
June 11th, 2015

1 Introduction

GRL is a C++ reinforcement learning library that aims to easily allow evaluating different algorithms through a declarative configuration interface.

2 Directory structure

```
|-- base
                             Base library
   |-- include
                             Header files
    `-- src
                             Source files
        |-- agents
                             Agents (fixed, black box, td)
        |-- discretizers
                             Action discretizers
        |-- environments
                             Environments (pendulum, cart-pole)
                             Experiments (online, batch)
       |-- experiments
        |-- policies
                             Control policies (PID, Q-based)
        |-- predictors
                             Value function predictors (SARSA, AC)
        |-- projectors
                             State projectors (tile coding, fourier)
       |-- representations Representations (linear, ann)
       |-- samplers
                             Action samplers (greedy, e-greedy)
       |-- traces
                             Elibility traces (accumulating, replacing)
       `-- visualizations
                             Visualizations (value function, policy)
|-- addons
                             Optional modules
   I-- cma
                             CMA-ES black-box optimizer
   |-- gl
                             OpenGL-based visualizations
    |-- glut
                             GLUT-based visualizer
   |-- 11r
                             Locally linear regression representation
   |-- matlab
                             Matlab interoperability
   |-- muscod
                             Muscod interoperability
   |-- odesim
                             Open Dynamics Engine environment
    |-- rbdl
                             Rigid Body Dynamics Library dynamics
    `-- ros
                             ROS interoperability
```

3 Prerequisites

GRL requires some libraries in order to compile. Which ones exactly depends on which agents and environments you would like to build, but the full list is

- Git
- GCC (including g++)
- Boost (for shared_ptr)
- Eigen
- GLUT
- QT4 (including the OpenGL bindings)
- TinvXML
- MuParser
- ODE, the Open Dynamics Engine
- Python (including Tkinter and the yaml reader)

On Ubuntu 14.04, these may be installed with the following command:

4 Building

GRL may be built with or without ROS's catkin. When building with, simply merge ${\tt grl.rosinstall}$ with your catkin workspace

```
wcaarls@vbox:~$ mkdir indigo_ws
wcaarls@vbox:~$ cd indigo_ws
wcaarls@vbox:~/indigo_ws$ rosws init src /opt/ros/indigo
wcaarls@vbox:~/indigo_ws$ cd src
wcaarls@vbox:~/indigo_ws/src$ rosws merge /path/to/grl.rosinstall
```

```
wcaarls@vbox:~/indigo_ws/src$ rosws up
wcaarls@vbox:~/indigo_ws/src$ cd ..
wcaarls@vbox:~/indigo_ws$ catkin_make

Otherwise, follow the standard CMake steps of (in the grl directory)
wcaarls@vbox:~/src/grl$ mkdir build
wcaarls@vbox:~/src/grl$ cd build
wcaarls@vbox:~/src/grl/build$ cmake ..
-- The C compiler identification is GNU 4.8.2
...
wcaarls@vbox:~/src/grl/build$ make
Scanning dependencies of target yaml-cpp
...
```

5 Running

The most important executables in grl are the deployer (grld) and configurator (grlc). The configurator allows you to generate configuration files easily. To see an example, run

```
wcaarls@vbox:~/src/grl/bin$ ./grlc ../cfg/pendulum/sarsa_tc.yaml
```

More information on the configurator can be found in Section 8. Once you have configured your experiment, you can either run it directly from the configurator, or save it and run it using the deployer. For example:

```
wcaarls@vbox:~/src/grl/build$ ./grld ../cfg/pendulum/sarsa_tc.yaml
```

6 Build environment

The whole grl system is built as a single package, with the exception of mprl_msgs. This is done to facilitate building inside and outside catkin. There is one CMakeLists.txt that is used in both cases. The ROS interoperability is selectively built based on whether cmake was invoked by catkin_make or not.

Modules are built by calling their respective build.cmake scripts, which is done by grl_build_library. The include directory is set automatically, as is an SRC variable pointing to the library's source directory.

The build system has a simplistic dependency management scheme through grl_link_libraries. This calls the link.cmake files of the libraries on which the current library depends. Typically they will add some target_link_libraries and add upstream dependencies. grl_link_libraries also automatically adds the upstream library's include directory.

7 Class structure

Most classes in grl derive from Configurable, a base class that standardizes configuration such that the object hierarchy may be constructed declaratively in a configuration file. Directly beneath Configurable are the abstract base classes defining the operation of various parts of the reinforcement learning environment, being:

- Agent RL-GLUE¹ style agent interface, receiving observations in an episodic manner and returning actions.
- Discretizer Provides a list of discrete points spanning a continuous space.
- Environment RL-GLUE style environment interface, receiving actions and returning observations.
- Experiment Top-level interface, which typically calls the agent and environment in the correct manner, but may in general implement any experiment.
- Optimizer Black-box optimization of control policies, suggesting policies and acting on their cumulative reward.
- Policy Basic control policy that implements the state-action mapping.
- Predictor Basic reinforcement learning interface that uses transitions to predict a value function or model.
- Projector Projects an observation onto a feature vector, represented as a Projection.
- Representation Basic supervised learning interface that uses samples to approximate a function. As such, it generally supports reading, writing and updating of any vector-to-vector mapping.
- Sampler (Stochastically) chooses an item from a vector of (generally unnormalized) values.
- Trace Stores a trace of projections with associated eligibilities that can be iterated over.
- Visualization Draws on the screen to visualize some aspect of the learning process.
- Visualizer Keeps track of visualizations and provides the interface to the graphics subsystem.

Each abstract base class is generally implemented in various concrete classes, with or without additional hierarchy. A list can be requested by running

wcaarls@vbox:~/src/grl/bin\$./grlq

A typical example of the information flow between the various classes can be seen in Figure 1, which depicts the standard TD control setting.

¹http://http://glue.rl-community.org




Figure 1: Information flow diagram for regular TD control. Rectangles (and dashed rectangles) are Configurable objects, while the others are the data passed between them.

7.1 Configuration

Each Configurable subclass must define its type and a short description using the TYPEINFO macro:

```
class OnlineLearningExperiment : public Experiment
{
   public:
     TYPEINFO("experiment/online_learning", "Interactive learning experiment")
   /* ... */
};
```

This textual description of the type is used to facilitate user configuration by limiting the selection of parameter values, as well as enforcing the type hierarchy. In general, the textual description should follow the C++ class hierarchy, but this is not obligatory.

The basic Configurable interface has three important functions:

7.1.1 request

```
virtual void request(ConfigurationRequest *config);
```

request is called by the configurator to find out which parameters the object requires to be set, and which parameters it exports for other objects to use. To do this, it should extend the given ConfigurationRequest by pushing configuration request parameters (CRPs). A basic CRP has the following signature:

```
CRP(string name, string desc, TYPE value)
```

where TYPE is one of int, double, Vector, or string. For example:

```
config->push_back(CRP("steps", "Number of steps per learning run", steps_));
config->push_back(CRP("output", "Output base filename", output_));
```

The value argument is used both to determine the type of the parameter and the default value suggested by the configurator. request may also be called while the program is running, in which case it is expected to return the current value of all parameters.

To use other Configurable objects as parameters, use

```
CRP(string name, string type, string desc, Configurable *value)
```

The extra type field restricts which Configurable objects may be used to configure this parameter. Only objects whose TYPEINFO starts with the given type are eligible. For example:

restricts the "policy" parameter to classes derived from ParameterizedPolicy. Note that this extra type hierarchy is related to, but not derived from the actual class hierarchy. Care must therefore be taken in the correct usage of TYPEINFO.

Some parameters are not requested, but rather *provided* by an object. In that case. These have the following signature:

```
CRP(string name, string type, string desc, CRP::Provided)
```

Examples of provided parameters are the number of observation dimensions (provided by Tasks) or the current system state (provided by some Environments).

7.1.2 configure

```
virtual void configure(Configuration *config);
```

configure is called after all parameters (including other Configurable objects) have been initialized. The parameter values may be accessed using mapping syntax (config["parameter"]). Note that Configurable objects are passed as void pointers and must still be cast to their actual class:

```
steps_ = config["steps"];
output_ = config["output"].str();
policy_ = (ParameterizedPolicy*)config["policy"].ptr();
```

Note the use of .str() and .ptr() for strings and objects, respectively. Provided parameters should be written to the configuration instead of read, like so:

```
config.set("state", state_);
```

7.1.3 reconfigure

```
virtual void reconfigure(const Configuration *config);
```

Some parameters may be defined as reconfigurable by appending CRP::Online to the respective CRP signature. In the case of a reconfiguration, reconfigure will be called with the new values of those parameters in config. reconfigure may also be used for general messaging, equivalent to RL-GLUE's message calls. In that case, it is often helpful to reconfigure all objects in the object hierarchy, which can be done using

```
void Configurable::walk(const Configuration &config);
```

Examples are resetting the hierarchy for a new run (config["action"] = "reset") or saving the current state of all memories (config["action"] = "save"). In the latter case, Configurable::path() may be used to determine an object's location in the object hierarchy.

7.2 Roles

While using the configurator, the user often has to select previously defined objects as the value of certain parameters. If all such previously defined objects are presented as possibilities, the list would quickly grow very large. To make setting these parameters easier, a class may have various *roles* while providing the same interface. In that case, only previously defined objects with a role that starts with the requested role are valid choices.

An example is a Representation, which may represent a state-value function, action-value function, control policy or model. Each has a different number of inputs and outputs, and chosing the wrong representation will result in mismatches. An object requesting a Representation may therefore request a certain role. For example:

```
config->push_back(CRP("representation", "representation.value/action",
```

```
"Q-value representation", representation_));
```

requests any representation that represents action-values. A newly defined representation will do, of course, but from the previously defined ones only the ones with the right role are eligible.

The same strategy is used for basic types, for example:

make sure the only suggested previously defined values for the "outputs" parameter are ones with the "action_dims" role. As an added convenience, if the parameter is defined as a *system parameter* (CRP::System), meaning that

the choice is not free but rather defined by the structure of the configuration, and only a single value was previously defined, that value is automatically used.

The role that needs to be requested may depend on the role of the requesting object itself. In that case, the following signature for request should be used:

virtual void request(const std::string &role, ConfigurationRequest *config);

8 Configurator




Figure 2: Python configurator user interface

9 Matlab interface

If Matlab is installed (and can be found on the path), a MEX interfaces for the agents and environments is built. If you want to use these, make sure that you're building with a compatible compiler, both by setting the CC and CXX variables in your call to cmake and by correctly configuring mex.

9.1 Environments

To initialize an environment, call

```
>> spec = grl_env('cfg/matlab/pendulum_swingup.yaml');
```

Where the argument specifies a configuration file that has a top-level 'environment' tag. **spec** gives some information about the environment, such as number of dimensions, minimum and maximum values, etc. Next, retrieve the first observation of an episode with

```
>> o = grl_env('start');
```

where \circ is the observation from the environment. All following steps should be called using

```
>> [o, r, t] = grl_env('step', a);
```

where a is the action suggested by the agent, r is the reward given by the environment and t signals termination of the episode. If t is 2, the episode ended in an absorbing state. When all episodes are done, exit cleanly with

```
>> grl_env('fini');
```

9.2 Agents

To initialize the agent, use

```
>> grl_agent('init', 'cfg/matlab/sarsa.yaml');
```

Where the argument specifies a configuration file that has a top-level 'agent' tag. Next, give the first observation of an episode with

```
>> a = grl_agent('start', o);
```

where o is the observation from the environment and a is the action suggested by the agent. All following steps should be called using

```
>> a = grl_agent('step', r, o);
```

where \mathbf{r} is the reward given by the environment. To signal the end of an episode (absorbing state), use

```
>> a = grl_agent('end', r);
```

To end an episode without an absorbing state, simply start a new one. To exit cleanly after all epsiodes are finished (which also allows you to reinitialize the agent with different options), call

```
>> grl_agent('fini');
```