■ NetApp

Install or upgrade

ONTAP 9

NetApp July 17, 2023

This PDF was generated from https://docs.netapp.com/us-en/ontap/mediator/index.html on July 17, 2023. Always check docs.netapp.com for the latest.

Table of Contents

nstall or upgrade	. 1
Prepare to install or upgrade the ONTAP Mediator service	. 1
Upgrade the host operating system and then the ONTAP Mediator	. 2
Enable access to the repositories	. 0
Download the Mediator installation package	14
Verify the ONTAP Mediator code signature	15
Install the ONTAP Mediator installation package	20
Verify the installation	37
Post-installation configuration	38

Install or upgrade

Prepare to install or upgrade the ONTAP Mediator service

To install the ONTAP Mediator service, you must ensure all prerequisites are met, get the installation package and run the installer on the host. This procedure is used for an installation or an upgrade of an existing installation.

- Beginning with ONTAP 9.7, you can use any version of ONTAP Mediator to monitor a MetroCluster IP configuration.
- Beginning with ONTAP 9.8, you can use any version of ONTAP Mediator to monitor an SM-BC relationship.

Before you begin

You must meet the following prerequisites.

ONTAP Mediator version	Supported Linux versions
1.6	 Red Hat Enterprise Linux: 8.4, 8.5, 8.6, 8.7, 9.0, 9.1 Rocky Linux 8 and 9
1.5	 Red Hat Enterprise Linux: 7.6, 7.7, 7.8, 7.9, 8.1, 8.2, 8.3, 8.4, 8.5 CentOS: 7.6, 7.7, 7.8, 7.9
1.4	 Red Hat Enterprise Linux: 7.6, 7.7, 7.8, 7.9, 8.1, 8.2, 8.3, 8.4, 8.5 CentOS: 7.6, 7.7, 7.8, 7.9
1.3	 Red Hat Enterprise Linux: 7.6, 7.7, 7.8, 7.9, 8.1, 8.2, 8.3 CentOS: 7.6, 7.7, 7.8, 7.9
1.2	 Red Hat Enterprise Linux: 7.6, 7.7, 7.8, 8.1 CentOS: 7.6, 7.7, 7.8



The kernel version must match the operating system version.

- · 64-bit physical installation or virtual machine
- 8 GB RAM
- · User: Root access

Any library packages except the kernel can safely be updated but might require a reboot to take affect within the ONTAP Mediator application. A service window is recommended when a reboot is required.

If you install the yum-utils package, you can use the needs-restarting command.

The kernel core can be updated if it is being updated to a version that is still supported by the ONTAP Mediator version matrix. A reboot will be mandatory, so a service window is required.

The SCST kernel module must be uninstalled prior to the reboot, then re-installed after the reboot.



Upgrading to a kernel beyond the supported OS release for the specific ONTAP Mediator release is not support. (This likely indicates that the tested SCST module won't compile).

Upgrade the host operating system and then the ONTAP Mediator

To upgrade the host OS for ONTAP Mediator to a later version, you must first uninstall ONTAP Mediator.

Before you begin

The best practices for installing Red Hat Enterprise Linux or CentOS and the associated repositories on your system are listed below. Systems installed or configured differently might require additional steps.

- You must install Red Hat Enterprise Linux or CentOS according to Red Hat best practices. Due to end-of-life support for CentOS 8.x versions, compatible versions of CentOS 8.x are not recommended.
- While installing the ONTAP Mediator service on Red Hat Enterprise Linux or CentOS, the system must have access to the appropriate repository so that the installation program can access and install all the required software dependencies.
- For the yum installer to find dependent software in the Red Hat Enterprise Linux repositories, you must have registered the system during the Red Hat Enterprise Linux installation or afterwards by using a valid Red Hat subscription.

See the Red Hat documentation for information about the Red Hat Subscription Manager.

- The following ports must be unused and available for the Mediator:
 - · 31784
 - 。 3260
- If using a third-party firewall: refer to Firewall requirements for ONTAP Mediator
- If the Linux host is in a location without access to the internet, you must ensure that the required packages are available in a local repository.

If you are using Link Aggregation Control Protocol (LACP) in a Linux environment, you must correctly configure the kernel and make sure the sysctl net.ipv4.conf.all.arp ignore is set to "2".

What you'll need

The following packages are required by the ONTAP Mediator service:

	Additional packages for RHEL 9.x / Rocky Linux 9
	,

- openssl
- · openssl-devel
- kernel-devel-\$ (uname -r)
- gcc
- make
- · libselinux-utils
- patch
- bzip2
- · perl-Data-Dumper
- perl-ExtUtils-MakeMaker
- · efibootmgr
- mokutil

- python3-pip
- · elfutils-libelf-devel
- · policycoreutils-python-utils
- · redhat-lsb-core
- python39
- python39-devel

- python3-pip
- · elfutils-libelf-devel
- · policycoreutils-python-utils
- python3
- python3-devel

The Mediator installation package is a self-extracting compressed tar file that includes:

- An RPM file containing all dependencies that cannot be obtained from the supported release's repository.
- · An install script.

A valid SSL certification is recommended.

About this task

When you upgrade the host OS for ONTAP Mediator to a later major version (for example, from 7.x to 8.x) using the leapp-upgrade tool, you must uninstall ONTAP Mediator because the tool tries to detect new versions of any RPMs that are installed in the repositories that are registered with the system.

Because an .rpm file was installed as part of the ONTAP Mediator installer, it is included in that search. However, because that .rpm file was unpacked as part of the installer and not downloaded from a registered repository, an upgrade cannot be found. In this case, the leapp-upgrade tool uninstalls the package.

In order to preserve the log files, which will be used to triage support cases, you should back up the files prior to doing an OS upgrade and restore them after a reinstall of the ONTAP Mediator package. Because the ONTAP Mediator is being reinstalled, any ONTAP Clusters that are connected to it will need to be reconnected after the new installation.



The following steps should be performed in order. Immediately after you reinstall ONTAP Mediator, you should stop the ontap_mediator service, replace the log files, and restart the service. This will ensure logs will not be lost.

Steps

1. Back up the log files.

```
[rootmediator-host ~]# tar -czf ontap_mediator_file_backup.tgz -C
/opt/netapp/lib/ontap_mediator ./log
./ontap_mediator/server_config/ontap_mediator.user_config.yaml
[rootmediator-host ~]# tar -tf ontap_mediator_file_backup.tgz
./log/
./log/ontap_mediator.log
./log/scstadmin.log
./log/ontap_mediator_stdout.log
./log/ontap_mediator_requests.log
./log/install_20230419134611.log
./log/scst.log
./log/ontap_mediator_syslog.log
./log/ontap_mediator_syslog.log
./ontap_mediator/server_config/ontap_mediator.user_config.yaml
[rootmediator-host ~]#
```

2. Perform upgrade with leapp-upgrade tool.

```
[rootmediator-host ~]# leapp preupgrade --target 8.4
    ..<snip upgrade checks>..
    ..<fix issues found>..
[rootmediator-host ~]# leapp upgrade --target 8.4
    ..<snip upgrade>..
[rootmediator-host ~]# cat /etc/os-release | head -2
NAME="Red Hat Enterprise Linux"
VERSION="8.4 (Ootpa)"
[rootmediator-host ~]#
```

3. Reinstall ONTAP Mediator.



Perform the rest of the steps immediately after reinstalling ONTAP Mediator to prevent a loss of log files.

```
[rootmediator-host ~]# ontap-mediator-1.6.0/ontap-mediator-1.6.0

ONTAP Mediator: Self Extracting Installer

..<snip installation>..
[rootmediator-host ~]#
```

4. Stop the ontap_mediator service.

```
[rootmediator-host ~]# systemctl stop ontap_mediator
[rootmediator-host ~]#
```

5. Replace the log files.

```
[rootmediator-host ~]# tar -xf ontap_mediator_log_backup.tgz -C
/opt/netapp/lib/ontap_mediator
[rootmediator-host ~]#
```

6. Start the ontap_mediator service.

```
[rootmediator-host ~]# systemctl start ontap_mediator
[rootmediator-host ~]#
```

7. Reconnect all ONTAP clusters to the upgraded ONTAP Mediator

Mediator IP	Port	Node	Configurat	ion
Connection				
			Status	Statu
172.31.40.122				
	31784	siteA-node2	true	false
		siteA-node1	true	false
		siteB-node2	true	false
		siteB-node2	true	false
siteA::> metroc	cluster	configuration-setti	ngs mediator remo	ve
Removing the me	ediator	and disabling Autom	atic Unplanned Sw	itchover.
It may take a f	ew minu	tes to complete.		
Please enter th	ne userna	ame for the mediato	r: mediatoradmin	
Please enter th	ne passw	ord for the mediato	r:	
Confirm the med	liator pa	assword:		
Automatic Unpla	inned Sw	itchover is disable	d for all nodes	•
Removing mediat	or maill	ooxes		
Successfully re siteA::> metroc -address 172.31 Adding the medi	cluster of the cluster of the cluster of the cluster of the cluster and the cluster of the clust	he mediator. configuration-setti d enabling Automati		
Successfully resiteA::> metrocolores 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metrocolores	cluster of the cluste	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switch r: mediatoradmin r:	hover. It
Successfully resiteA::> metroconductors 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metroconductors IP	cluster of the cluste	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switcr: mediatoradminr:	hover. It
siteA::> metroc-address 172.31 Adding the medimay take a few Please enter th Please enter th Confirm the med Successfully ad	cluster of the cluste	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switch: r: mediatoradmin r: ngs mediator show Configurat	hover. It
Successfully resiteA::> metroconductors 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metroconductors IP	cluster of the cluste	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switch r: mediatoradmin r:	hover. It
Successfully resiteA::> metroconductors 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metroconductors IP	cluster of the cluste	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switch: r: mediatoradmin r: ngs mediator show Configurat	hover. It
Successfully resiteA::> metroconductors 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metroconductors IP	cluster of the cluste	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switch: r: mediatoradmin r: ngs mediator show Configurat	hover. It
Successfully resiteA::> metrocolor address 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metrocolor Mediator IP Connection	emoved the cluster of	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti	c Unplanned Switch: r: mediatoradmin r: ngs mediator show Configurat	hover. It
Successfully resiteA::> metrocolor address 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metrocolor Mediator IP Connection	emoved the cluster of	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti Node	c Unplanned Switch r: mediatoradmin r: ngs mediator show Configurat Status	hover. It
Successfully resiteA::> metrocolor address 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metrocolor Mediator IP Connection	emoved the cluster of	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti Node	c Unplanned Switch r: mediatoradmin r: ngs mediator show Configurat Status true	hover. It ion Status true
Successfully resiteA::> metrocolor address 172.31 Adding the medimay take a few Please enter the Please enter the Confirm the med Successfully additeA::> metrocolor Mediator IP Connection	emoved the cluster of	he mediator. configuration-setti d enabling Automati to complete. ame for the mediato ord for the mediato assword: mediator. configuration-setti Node siteA-node2 siteA-node1	c Unplanned Switch r: mediatoradmin r: ngs mediator show Configurat Status true true	ion Statu

Procedure for SnapMirror Business Continuity

For SnapMirror Business Continuity, if you installed your TLS certificate outside of the /opt/netapp directory, then you will not need to reinstall it. If you were using the default generated self-signed certificate or put your custom certificate in the /opt/netapp directory, then you should back it up and restore it.

```
peer1::> snapmirror mediator show
Mediator Address Peer Cluster Connection Status Quorum Status
______ ____
172.31.49.237 peer2
                      unreachable true
peer1::> snapmirror mediator remove -mediator-address 172.31.49.237
-peer-cluster peer2
Info: [Job 39] 'mediator remove' job queued
peer1::> job show -id 39
                        Owning
                        Vserver
                                 Node
Job ID Name
                                         State
39
                       peer1
                                 peer1-node1 Success
     mediator remove
    Description: Removing entry in mediator
peer1::> security certificate show -common-name ONTAPMediatorCA
Vserver Serial Number Certificate Name
Type
  -----
_____
peer1
       4A790360081F41145E14C5D7CE721DC6C210007F
                     ONTAPMediatorCA
server-ca
   Certificate Authority: ONTAP Mediator CA
       Expiration Date: Mon Apr 17 10:27:54 2073
peer1::> security certificate delete -common-name ONTAPMediatorCA *
1 entry was deleted.
peer1::> security certificate install -type server-ca -vserver
peer1
Please enter Certificate: Press <Enter> when done
  ..<snip ONTAP Mediator CA public key>..
You should keep a copy of the CA-signed digital certificate for
future reference.
```

The installed certificate's CA and serial number for reference:

CA: ONTAP Mediator CA

serial: 44786524464C5113D5EC966779D3002135EA4254

The certificate's generated name for reference: ONTAPMediatorCA

peer2::> security certificate delete -common-name ONTAPMediatorCA *
1 entry was deleted.

peer2::> security certificate install -type server-ca -vserver peer2

Please enter Certificate: Press <Enter> when done ..<snip ONTAP Mediator CA public key>..

You should keep a copy of the CA-signed digital certificate for future reference.

The installed certificate's CA and serial number for reference:

CA: ONTAP Mediator CA

serial: 44786524464C5113D5EC966779D3002135EA4254

The certificate's generated name for reference: ONTAPMediatorCA

peer1::> snapmirror mediator add -mediator-address 172.31.49.237
-peer-cluster peer2 -username mediatoradmin

Notice: Enter the mediator password.

Enter the password:

Enter the password again:

Info: [Job: 43] 'mediator add' job queued

peer1::> job show -id 43

		Owning		
Job	ID Name	Vserver	Node	State
43	mediator add	peer1	peer1-node2	Success
	Description: Creating a	mediator e	ntry	

Enable access to the repositories

You should enable access to repositories so ONTAP Mediator can access the required packages during the installation process

Steps

1. Determine which repositories must be accessed, as shown in the following table:

If your operating system is	You must provide access to these repositories
RHEL 7.x	rhel-7-server-optional-rpms
RHEL 8.x	rhel-8-for-x86_64-baseos-rpms
	rhel-8-for-x86_64-appstream-rpms
RHEL 9.x	• rhel-9-for-x86_64-baseos-rpms
	• rhel-9-for-x86_64-appstream-rpms
CentOS 7.x	C7.6.1810 - Base repository
Rocky Linux 8	appstream
	• baseos
Rocky Linux 9	• appstream
	• baseos

2. Use one of the following procedures to enable access to the repositories listed above so ONTAP Mediator can access the required packages during the installation process.

Use this procedure if your operating system is **RHEL 7.x** to enable access to repositories:

Steps

1. Subscribe to the required repository:

```
subscription-manager repos --enable rhel-7-server-optional-rpms
```

The following example shows the execution of this command:

```
[root@localhost ~]# subscription-manager repos --enable rhel-7-server-optional-rpms
Repository 'rhel-7-server-optional-rpms' is enabled for this system.
```

2. Run the yum repolist command.

The following example shows the execution of this command. The "rhel-7-server-optional-rpms" repository should appear in the list.

```
[root@localhost ~]# yum repolist
Loaded plugins: product-id, search-disabled-repos, subscription-
manager
rhel-7-server-optional-rpms | 3.2 kB 00:00:00
rhel-7-server-rpms | 3.5 kB 00:00:00
(1/3): rhel-7-server-optional-rpms/7Server/x86 64/group
| 26 kB 00:00:00
(2/3): rhel-7-server-optional-rpms/7Server/x86 64/updateinfo
| 2.5 MB 00:00:00
(3/3): rhel-7-server-optional-rpms/7Server/x86 64/primary db
| 8.3 MB 00:00:01
repo id
                                             repo name
status
rhel-7-server-optional-rpms/7Server/x86 64
                                             Red Hat Enterprise
Linux 7 Server - Optional (RPMs)
                                   19,447
rhel-7-server-rpms/7Server/x86 64
                                             Red Hat Enterprise
Linux 7 Server (RPMs)
                                   26,758
repolist: 46,205
[root@localhost ~]#
```

Procedure for RHEL 8.x operating system

Use this procedure if your operating system is **RHEL 8.x** to enable access to repositories:

Steps

1. Subscribe to the required repository:

```
subscription-manager repos --enable rhel-8-for-x86_64-baseos-rpms subscription-manager repos --enable rhel-8-for-x86_64-appstream-rpms
```

The following example shows the execution of this command:

```
[root@localhost ~]# subscription-manager repos --enable rhel-8-for-x86_64-baseos-rpms

Repository 'rhel-8-for-x86_64-baseos-rpms' is enabled for this system.

[root@localhost ~]# subscription-manager repos --enable rhel-8-for-x86_64-appstream-rpms

Repository 'rhel-8-for-x86_64-appstream-rpms' is enabled for this system.
```

2. Run the yum repolist command.

The newly subscribed repositories should appear in the list.

Procedure for RHEL 9.x operating system

Use this procedure if your operating system is **RHEL 9.x** to enable access to repositories:

Steps

1. Subscribe to the required repository:

```
subscription-manager repos --enable rhel-9-for-x86_64-baseos-rpms subscription-manager repos --enable rhel-9-for-x86_64-appstream-rpms
```

The following example shows the execution of this command:

```
[root@localhost ~]# subscription-manager repos --enable rhel-9-for-
x86_64-baseos-rpms
Repository 'rhel-9-for-x86_64-baseos-rpms' is enabled for this system.
[root@localhost ~]# subscription-manager repos --enable rhel-9-for-
x86_64-appstream-rpms
Repository 'rhel-9-for-x86_64-appstream-rpms' is enabled for this system.
```

2. Run the yum repolist command.

The newly subscribed repositories should appear in the list.

Use this procedure if your operating system is **CentOS 7.x** to enable access to repositories:



The following examples are showing a repository for CentOS 7.6 and might not work for other CentOS versions. Use the base repository for your version of CentOS.

Steps

- 1. Add the C7.6.1810 Base repository. The C7.6.1810 Base vault repository contains the "kernel-devel" package needed for ONTAP Mediator.
- 2. Add the following lines to /etc/yum.repos.d/CentOS-Vault.repo.

```
[C7.6.1810-base]
name=CentOS-7.6.1810 - Base
baseurl=http://vault.centos.org/7.6.1810/os/$basearch/
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/RPM-GPG-KEY-CentOS-7
enabled=1
```

3. Run the yum repolist command.

The following example shows the execution of this command. The CentOS-7.6.1810 - Base repository should appear in the list.

```
Loaded plugins: fastestmirror
Loading mirror speeds from cached hostfile
 * base: distro.ibiblio.org
 * extras: distro.ibiblio.org
 * updates: ewr.edge.kernel.org
C7.6.1810-base
                                              | 3.6 kB 00:00:00
(1/2): C7.6.1810-base/x86 64/group gz
                                             | 166 kB 00:00:00
(2/2): C7.6.1810-base/x86 64/primary db
                                             | 6.0 MB 00:00:04
repo id
                            repo name
                                                    status
C7.6.1810-base/x86 64
                            CentOS-7.6.1810 - Base 10,019
base/7/x86 64
                            CentOS-7 - Base
                                                    10,097
extras/7/x86 64
                            CentOS-7 - Extras
                                                    307
updates/7/x86 64
                            CentOS-7 - Updates
                                                    1,010
repolist: 21,433
[root@localhost ~]#
```

Procedure for Rocky Linux 8 or 9 operating systems

Use this procedure if your operating system is **Rocky Linux 8** or **Rocky Linux 9** to enable access to repositories:

Steps

1. Subscribe to the required repositories:

```
dnf config-manager --set-enabled baseos
dnf config-manager --set-enabled appstream
```

2. Perform a clean operation:

```
dnf clean all
```

3. Verify the list of repositories:

```
dnf repolist
```

Example for Rocky Linux 8

Example for Rocky Linux 9

Download the Mediator installation package

Download the Mediator installation package as part of the installation process.

Steps

1. Download the Mediator installation package from the ONTAP Mediator page.

ONTAP Mediator download page

2. Confirm that the Mediator installation package is in the current working directory:

ls

```
[root@mediator-host ~] #1s ontap-mediator-1.5.0.tgz
```



For ONTAP Mediator versions 1.4 and earlier, the installer is named ontap-mediator.

If you are at a location without access to the internet, you must ensure that the installer has access to the required packages.

- 3. If necessary, move the Mediator installation package from the download directory to the installation directory on the Linux Mediator host.
- 4. Unzip the installer package:

```
tar xvfz ontap-mediator-1.6.0.tgz
```

```
[root@scs000099753 ~] # tar xvfz ontap-mediator-1.6.0.tgz ontap-mediator-1.6.0/
ontap-mediator-1.6.0/ONTAP-Mediator-production.pub
ontap-mediator-1.6.0/tsa-prod-chain-ONTAP-Mediator.pem
ontap-mediator-1.6.0/tsa-prod-ONTAP-Mediator.pem
ontap-mediator-1.6.0/csc-prod-ONTAP-Mediator.pem
ontap-mediator-1.6.0/csc-prod-chain-ONTAP-Mediator.pem
ontap-mediator-1.6.0/ontap-mediator-1.6.0
ontap-mediator-1.6.0/ontap-mediator-1.6.0.sig.tsr
ontap-mediator-1.6.0/ontap-mediator-1.6.0.tsr
ontap-mediator-1.6.0/ontap-mediator-1.6.0.sig
```

Verify the ONTAP Mediator code signature

You should verify the ONTAP Mediator code signature before installing the Mediator installation package.

Before you begin

Before verifying the Mediator code signature, your system must meet the following requirements.

- openssl versions 1.0.2 to 3.0 for basic verification
- openssl version 1.1.0 or later for Time Stamping Authority (TSA) operations
- Public internet access for OCSP verification



The following files are included in the download package:

File	Description
ONTAP-Mediator-development.pub	The public key used to verify the signature
csc-prod-chain-ONTAP-Mediator.pem	The public certification CA chain of trust
csc-prod-ONTAP-Mediator.pem	The certificate used to generate the key
ontap-mediator-1.6.0	The product installation executable for version 1.6.0
ontap-mediator-1.6.0.sig	The SHA-256 hashed, then RSA-signed using the csc-prod key, signature for the installer
ontap-mediator-1.6.0.sig.tsr	The revocation request for use by OCSCP for the installer's signature
tsa-prod-ONTAP-Mediator.pem	The public certificate for the TSR
tsa-prod-chain-ONTAP-Mediator.pem	The public certificate CA Chain for the TSR

Steps

- 1. Perform the revocation check on csc-prod-ONTAP-Mediator.pem by using Online Certificate Status Protocol (OCSP).
 - a. Find the OCSP URL used to register the certificate because developer certificates might not provide a uri.

```
openssl x509 -noout -ocsp_uri -in csc-prod-chain-ONTAP-Mediator.pem
```

b. Generate an OCSP request for the certificate.

```
openssl ocsp -issuer csc-prod-chain-ONTAP-Mediator.pem -CAfile csc-prod-chain-ONTAP-Mediator.pem -cert csc-prod-ONTAP-Mediator.pem -reqout req.der
```

c. Connect to the OCSP Manager to send the OCSP request:

openssl ocsp -issuer csc-prod-chain-ONTAP-Mediator.pem -CAfile csc-prod-chain-ONTAP-Mediator.pem -cert csc-prod-ONTAP-Mediator.pem -url \${ocsp_uri} -resp_text -respout resp.der -verify_other csc-prod-chain-ONTAP-Mediator.pem

2. Verify the trust chain of the CSC and expiration dates against the local host:

openssl verify



The openss1 version from the PATH must have a valid cert.pem (not self-signed).

openssl verify -untrusted csc-prod-chain-ONTAP-Mediator.pem -CApath \${OPENSSLDIR} csc-prod-ONTAP-Mediator.pem # Failure action: The Code-Signature-Check certificate has expired or is invalid. Download a newer version of the ONTAP Mediator.

openssl verify -untrusted tsa-prod-chain-ONTAP-Mediator.pem -CApath \${OPENSSLDIR} tsa-prod-ONTAP-Mediator.pem # Failure action: The Time-Stamp certificate has expired or is invalid. Download a newer version of the ONTAP Mediator.

3. Verify the ontap-mediator-1.5.0.sig.tsr and ontap-mediator-1.6.0.tsr files using the associated certificates:

openssl ts -verify



.tsr files contain the time stamp response associated with the installer and the code signature. Processing confirms that the time stamp has a valid signature from TSA and that your input file has not changed. The verification is performed locally on your machine. Independently, there is no need to access TSA servers.

openssl ts -verify -data ontap-mediator-1.6.0.sig -in ontap-mediator-1.6.0.sig.tsr -CAfile tsa-prod-chain-ONTAP-Mediator.pem -untrusted tsa-prod-ONTAP-Mediator.pem

openssl ts -verify -data ontap-mediator-1.6.0 -in ontap-mediator-1.6.0.tsr -CAfile tsa-prod-chain-ONTAP-Mediator.pem -untrusted tsa-prod-ONTAP-Mediator.pem

4. Verify signatures against the key:

openssl -dgst -verify

openssl dgst -sha256 -verify ONTAP-Mediator-production.pub -signature ontap-mediator-1.6.0.sig ontap-mediator-1.6.0

```
[root@scspa2695423001 ontap-mediator-1.6.0]# pwd
/root/ontap-mediator-1.6.0
[root@scspa2695423001 ontap-mediator-1.6.0] # ls -1
total 63660
-r--r-- 1 root root 8582 Feb 19 15:02 csc-prod-chain-ONTAP-
Mediator.pem
-r--r-- 1 root root 2373 Feb 19 15:02 csc-prod-ONTAP-
Mediator.pem
-r-xr-xr-- 1 root root 65132818 Feb 20 15:17 ontap-mediator-1.6.0
-rw-r--r-- 1 root root 384 Feb 20 15:17 ontap-mediator-1.6.0.sig
-rw-r--r-- 1 root root 5437 Feb 20 15:17 ontap-mediator-
1.6.0.sig.tsr
-rw-r--r-- 1 root root 5436 Feb 20 15:17 ontap-mediator-1.6.0.tsr
-r--r-- 1 root root 625 Feb 19 15:02 ONTAP-Mediator-
production.pub
-r--r-- 1 root root 3323 Feb 19 15:02 tsa-prod-chain-ONTAP-
Mediator.pem
-r--r-- 1 root root 1740 Feb 19 15:02 tsa-prod-ONTAP-
Mediator.pem
[root@scspa2695423001 ontap-mediator-1.6.0]#
[root@scspa2695423001 ontap-mediator-1.6.0]#
/root/verify ontap mediator signatures.sh
++ openssl version -d
++ cut -d '"' -f2
+ OPENSSLDIR=/etc/pki/tls
+ openssl version
OpenSSL 1.1.1k FIPS 25 Mar 2021
++ openssl x509 -noout -ocsp uri -in csc-prod-chain-ONTAP-Mediator.pem
+ ocsp uri=http://ocsp.entrust.net
+ echo http://ocsp.entrust.net
http://ocsp.entrust.net
+ openssl ocsp -issuer csc-prod-chain-ONTAP-Mediator.pem -CAfile csc-
prod-chain-ONTAP-Mediator.pem -cert csc-prod-ONTAP-Mediator.pem -reqout
req.der
+ openssl ocsp -issuer csc-prod-chain-ONTAP-Mediator.pem -CAfile csc-
prod-chain-ONTAP-Mediator.pem -cert csc-prod-ONTAP-Mediator.pem -url
http://ocsp.entrust.net -resp text -respout resp.der -verify other csc-
prod-chain-ONTAP-Mediator.pem
OCSP Response Data:
    OCSP Response Status: successful (0x0)
    Response Type: Basic OCSP Response
    Version: 1 (0x0)
    Responder Id: C = US, O = "Entrust, Inc.", CN = Entrust Extended
Validation Code Signing CA - EVCS2
```

Produced At: Feb 28 05:01:00 2023 GMT Responses: Certificate ID: Hash Algorithm: shal Issuer Name Hash: 69FA640329AB84E27220FE0927647B8194B91F2A Issuer Key Hash: CE894F8251AA15A28462CA312361D261FBF8FE78 Serial Number: 511A542B57522AEB7295A640DC6200E5 Cert Status: good This Update: Feb 28 05:00:00 2023 GMT Next Update: Mar 4 04:59:59 2023 GMT Signature Algorithm: sha512WithRSAEncryption 3c:1d:49:b0:93:62:37:3e:c7:38:e3:9f:9f:62:82:73:ed:f4: ea:00:6b:f1:01:cd:79:57:92:f1:9d:5d:85:9b:60:59:f8:6c: e6:f4:50:51:f3:4c:8a:51:dd:50:68:16:8f:20:24:7e:39:b0: 44:94:8d:b0:61:da:b9:08:36:74:2d:44:55:62:fb:92:be:4a: e7:6c:8c:49:dd:0c:fd:d8:ce:20:08:0d:0f:5a:29:a3:19:03: 9f:d3:df:41:f4:89:0f:73:18:3f:ac:bb:a7:a3:96:7d:c5:70: 4c:57:cd:17:17:c6:8a:60:d1:37:c9:2d:81:07:2a:d7:a6:02: ee:ce:88:16:22:db:e3:43:64:1e:9b:0d:4d:31:66:fa:ab:a5: 52:99:94:4a:4a:d0:52:c5:34:f5:18:c7:15:5b:ce:74:c2:fc: 61:ea:55:aa:f1:2f:82:a3:6a:95:8d:7e:2b:38:49:4f:bf:b1: 68:7b:1b:24:8b:1f:4d:c5:77:f0:71:af:9c:34:c8:7a:82:50: 09:a2:19:6e:c6:30:4f:da:a2:79:08:f9:d0:ff:85:d9:2a:84: cf:0c:aa:75:8f:72:c9:a7:a2:83:e8:8b:cf:ed:0c:69:75:b6: 2a:7b:6b:58:99:01:d8:34:ad:e1:89:25:27:1b:fa:d9:6d:32: 97:3a:0b:0a:8e:a3:9e:e3:f4:e0:d6:1a:c9:b5:14:8c:3e:54: 3b:37:17:1a:93:44:84:8b:4a:87:97:1e:76:43:3e:d3:ec:8b: 7e:56:4a:3f:01:31:c0:e5:58:fb:50:ce:6f:b1:e7:35:f9:b7: a3:ef:6b:3b:21:95:37:a6:5b:8f:f0:15:18:36:65:89:a1:9c: 9b:69:00:b4:b1:65:6a:bc:11:2d:d4:9b:b4:97:cc:cb:7a:0c: 16:11:c1:75:58:7e:13:ab:56:3c:3f:93:5b:95:24:c6:54:52: 1f:86:a9:16:ce:d9:ea:8b:3a:f3:4f:c4:8f:ad:de:e8:3e:3c: d2:51:51:ad:33:7f:d8:c5:33:24:26:f1:2d:9d:0e:9f:55:d0: 68:bf:af:bd:68:4a:40:08:bc:92:a0:62:54:7d:16:7b:36:29: 15:b1:cd:58:8e:fb:4a:f2:3e:94:8b:fe:56:95:cc:24:32:af: 5f:71:99:18:ed:0c:64:94:f7:54:48:87:48:d0:6d:b3:42:04: 96:03:73:a2:8e:8a:6a:b2:af:ee:56:19:a1:c6:35:12:59:ad: 19:6a:fe:e0:f1:27:cc:96:4e:f0:4f:fb:6a:bd:ce:05:2c:aa: 79:7c:df:02:5c:ca:53:7d:60:12:88:7c:ce:15:c7:d4:02:27: c1:ab:cf:71:30:1e:14:ba WARNING: no nonce in response Response verify OK csc-prod-ONTAP-Mediator.pem: good This Update: Feb 28 05:00:00 2023 GMT Next Update: Mar 4 04:59:59 2023 GMT

```
+ openssl verify -untrusted csc-prod-chain-ONTAP-Mediator.pem -CApath
/etc/pki/tls csc-prod-ONTAP-Mediator.pem
csc-prod-ONTAP-Mediator.pem: OK
+ openssl verify -untrusted tsa-prod-chain-ONTAP-Mediator.pem -CApath
/etc/pki/tls tsa-prod-ONTAP-Mediator.pem
tsa-prod-ONTAP-Mediator.pem: OK
+ openssl ts -verify -data ontap-mediator-1.6.0.sig -in ontap-mediator-
1.6.0.sig.tsr -CAfile tsa-prod-chain-ONTAP-Mediator.pem -untrusted tsa-
prod-ONTAP-Mediator.pem
Using configuration from /etc/pki/tls/openssl.cnf
Verification: OK
+ openssl ts -verify -data ontap-mediator-1.6.0 -in ontap-mediator-
1.6.0.tsr -CAfile tsa-prod-chain-ONTAP-Mediator.pem -untrusted tsa-
prod-ONTAP-Mediator.pem
Using configuration from /etc/pki/tls/openssl.cnf
Verification: OK
+ openssl dgst -sha256 -verify ONTAP-Mediator-production.pub -signature
ontap-mediator-1.6.0.sig ontap-mediator-1.6.0
Verified OK
[root@scspa2695423001 ontap-mediator-1.6.0]#
```

Install the ONTAP Mediator installation package

To install the ONTAP Mediator service, you must get the installation package and run the installer on the host.

About this task

- Beginning with ONTAP Mediator 1.4, the Secure Boot mechanism is enabled on UEFI systems. When Secure Boot is enabled, you must take additional steps to register the security key after installation:
 - Follow instructions in the README file to sign the SCST kernel module.:

```
/opt/netapp/lib/ontap_mediator/ontap_mediator/SCST_mod_keys/README.module-
signing
```

Locate the required keys:

/opt/netapp/lib/ontap mediator/ontap mediator/SCST mod keys



After installation, the README files and key location are also provided in the system output.

Steps

- 1. Run the installer and respond to the prompts as required:
 - ./ontap-mediator-1.6.0/ontap-mediator-1.6.0 -y

```
[root@scs000099753 ~]# ./ontap-mediator-1.5.0/ontap-mediator-1.6.0 -y
```

The installation process proceeds to create the required accounts and install required packages. If you have a previous version of Mediator installed on the host, you will be prompted to confirm that you want to upgrade.

```
[root@scs000099753 ~]# ./ontap-mediator-1.6.0/ontap-mediator-1.6.0 -y
ONTAP Mediator: Self Extracting Installer
+ Extracting the ONTAP Mediator installation/upgrade archive
+ Performing the ONTAP Mediator run-time code signature check
  Using openssl from the path: /usr/bin/openssl configured for
CApath:/etc/pki/tls
+ Unpacking the ONTAP Mediator installer
ONTAP Mediator requires two user accounts. One for the service
(netapp), and one for use by ONTAP to the mediator API (mediatoradmin).
Using default account names: netapp + mediatoradmin
Enter ONTAP Mediator user account (mediatoradmin) password:
Re-Enter ONTAP Mediator user account (mediatoradmin) password:
+ Checking if SELinux is in enforcing mode
+ Checking for default Linux firewall
success
success
success
Preparing for installation of ONTAP Mediator packages.
+ Installing required packages.
Last metadata expiration check: 0:25:24 ago on Fri 21 Oct 2022 04:00:13
PM EDT.
Package openssl-1:1.1.1k-4.el8.x86 64 is already installed.
Package gcc-8.4.1-1.el8.x86 64 is already installed.
Package python36-3.6.8-2.module+el8.1.0+3334+5cb623d7.x86 64 is already
installed.
Package libselinux-utils-2.9-5.el8.x86 64 is already installed.
Package perl-Data-Dumper-2.167-399.el8.x86 64 is already installed.
Package efibootmgr-16-1.el8.x86 64 is already installed.
Package mokutil-1:0.3.0-11.el8.x86 64 is already installed.
```

Package python3-pip-9.0.3-19.el8.noarch is already installed. Package policycoreutils-python-utils-2.9-14.el8.noarch is already installed. Dependencies resolved. ______ ______ _____ Package Architecture Version Repository Size ______ ______ _____ Installing: bzip2 x86 64 1.0.6-26.el8 rhel-8-forx86 64-baseos-rpms 60 k elfutils-libelf-devel x86 64 0.186-1.el8 rhel-8-forx86 64-baseos-rpms 60 k kernel-devel x86 64 4.18.0-348.el8 rhel-8-forx86 64-baseos-rpms 20 M make x86 64 1:4.2.1-11.el8 rhel-8-forx86 64-baseos-rpms 498 k openssl-devel x86 64 1:1.1.1k-7.el8 6 rhel-8-forx86 64-baseos-rpms 2.3 M patch x86 64 2.7.6-11.el8 rhel-8-for-138 k x86 64-baseos-rpms perl-ExtUtils-MakeMaker noarch 1:7.34-1.el8 rhel-8-forx86 64-appstream-rpms 301 k python36-devel x86 64 3.6.8-38.module+el8.5.0+12207+5c5719bc rhel-8-forx86 64-appstream-rpms 17 k redhat-lsb-core x86 64 4.1-47.el8 rhel-8-forx86 64-appstream-rpms 45 k Upgrading: срр x86 64 8.5.0-10.1.el8 6 rhel-8-forx86 64-appstream-rpms 10 M elfutils-libelf x86 64

0.186-1.el8			rhel-8-for-
x86_64-baseos-rpms	229 k		
elfutils-libs		x86_64	
0.186-1.el8			rhel-8-for-
x86_64-baseos-rpms	295 k		
gcc		x86_64	
8.5.0-10.1.el8_6			rhel-8-for-
x86_64-appstream-rpms	23 M		
libgcc		x86_64	
8.5.0-10.1.el8_6			rhel-8-for-
x86_64-baseos-rpms	80 k		
libgomp		x86_64	
8.5.0-10.1.el8_6			rhel-8-for-
x86_64-baseos-rpms	207 k		
libsemanage		x86_64	
2.9-8.el8			rhel-8-for-
x86_64-baseos-rpms	168 k		
mokutil		x86_64	
1:0.3.0-11.el8_6.1			rhel-8-for-
x86_64-baseos-rpms	46 k		
openssl		x86_64	
1:1.1.1k-7.el8_6			rhel-8-for-
x86_64-baseos-rpms	709 k		
openssl-libs		x86_64	
1:1.1.1k-7.el8_6			rhel-8-for-
x86_64-baseos-rpms	1.5 M		
platform-python-pip		noarch	
9.0.3-22.el8			rhel-8-for-
x86_64-baseos-rpms	1.6 M		
policycoreutils		x86_64	
2.9-19.e18			rhel-8-for-
x86_64-baseos-rpms	374 k		
policycoreutils-python-utils		noarch	
2.9-19.e18	0.50		rhel-8-for-
x86_64-baseos-rpms	253 k	0.6.6.4	
python3-libsemanage		x86_64	1 1 0 6
2.9-8.e18	100 1		rhel-8-for-
x86_64-baseos-rpms	128 k		
python3-pip		noarch	h - 1 0 C
9.0.3-22.el8	20.1		rhel-8-for-
x86_64-appstream-rpms	20 k	m = = == ==1=	
python3-policycoreutils		noarch	
2.9-19.el8	0 0 16		rhel-8-for-
x86_64-baseos-rpms	2.2 M	0 ((1	
python36	Ole e	x86_64	h - 1 0 C
3.6.8-38.module+e18.5.0+12207+5c571	Dae		rhel-8-for-

x86_64-appstream-rpms	19 k		
Installing dependencies:			
annobin		x86_64	
10.29-3.el8			rhel-8-for-
x86_64-appstream-rpms	117 k		
at		x86_64	
3.1.20-11.el8			rhel-8-for-
x86_64-baseos-rpms	81 k		
bc		x86_64	
1.07.1-5.el8			rhel-8-for-
x86_64-baseos-rpms	129 k		
cups-client		x86_64	
1:2.2.6-38.el8			rhel-8-for-
x86_64-appstream-rpms	169 k		
dwz		x86_64	
0.12-10.el8			rhel-8-for-
x86_64-appstream-rpms	109 k		
ed		x86_64	
1.14.2-4.el8			rhel-8-for-
x86_64-baseos-rpms	82 k		
efi-srpm-macros		noarch	
3-3.el8			rhel-8-for-
x86_64-appstream-rpms	22 k		
esmtp		x86_64	
1.2-15.el8			EPEL-8
57 k			
ghc-srpm-macros		noarch	
1.4.2-7.el8			rhel-8-for-
x86_64-appstream-rpms	9.4 k		
go-srpm-macros		noarch	
2-17.el8			rhel-8-for-
x86_64-appstream-rpms	13 k		
keyutils-libs-devel		x86_64	
1.5.10-6.el8			rhel-8-for-
x86_64-baseos-rpms	48 k		
krb5-devel		x86_64	
1.18.2-14.el8			rhel-8-for-
x86_64-baseos-rpms	560 k		
libcom_err-devel		x86_64	
1.45.6-2.el8			rhel-8-for-
x86_64-baseos-rpms	38 k		
libesmtp		x86_64	
1.0.6-18.el8			EPEL-8
70 k			
libkadm5		x86_64	
1.18.2-14.el8			rhel-8-for-

x86 64-baseos-rpms	187 k		
liblockfile	10 / K	x86 64	
1.14-1.el8		X00_04	rhel-8-for-
x86 64-appstream-rpms	32 k		INCI O IOI
libselinux-devel	J2 K	x86 64	
2.9-5.el8		X00_04	rhel-8-for-
	200 k		INET-0-101-
x86_64-baseos-rpms	200 K	06 61	
libsepol-devel		x86_64	mbal O fan
2.9-3.e18	07 1-		rhel-8-for-
x86_64-baseos-rpms	87 k	0 6 6 4	
libverto-devel		x86_64	11 0 6
0.3.0-5.el8	10.1		rhel-8-for-
x86_64-baseos-rpms	18 k	0.6.64	
m4		x86_64	1 1 0 6
1.4.18-7.el8	000		rhel-8-for-
x86_64-baseos-rpms	223 k	0.6.6.4	
mailx		x86_64	1 1 0 6
12.5-29.el8	0.5.		rhel-8-for-
x86_64-baseos-rpms	257 k		
ncurses-compat-libs		x86_64	
6.1-9.20180224.e18			rhel-8-for-
x86_64-baseos-rpms	328 k		
ocaml-srpm-macros		noarch	
5-4.el8			rhel-8-for-
x86_64-appstream-rpms	9.5 k		
openblas-srpm-macros		noarch	
2-2.el8			rhel-8-for-
x86_64-appstream-rpms	8.0 k		
pcre2-devel		x86_64	
10.32-2.el8			rhel-8-for-
x86_64-baseos-rpms	605 k		
pcre2-utf16		x86_64	
10.32-2.el8			rhel-8-for-
x86_64-baseos-rpms	229 k		
pcre2-utf32		x86_64	
10.32-2.el8			rhel-8-for-
x86_64-baseos-rpms	220 k		
perl-CPAN-Meta-YAML		noarch	
0.018-397.el8			rhel-8-for-
x86_64-appstream-rpms	34 k		
perl-ExtUtils-Command		noarch	
1:7.34-1.el8			rhel-8-for-
x86_64-appstream-rpms	19 k		
_ perl-ExtUtils-Install		noarch	
2.14-4.el8			rhel-8-for-
2.14 4.610			

perl-ExtUtils-Manifest	noa	arch
1.70-395.el8		rhel-8-for-
x86_64-appstream-rpms	37 k	
perl-ExtUtils-ParseXS	noa	arch
1:3.35-2.el8		rhel-8-for-
x86_64-appstream-rpms	83 k	
perl-JSON-PP	noa	arch
1:2.97.001-3.el8		rhel-8-for-
x86_64-appstream-rpms	68 k	
perl-Math-BigInt	noa	arch
1:1.9998.11-7.el8		rhel-8-for-
x86_64-baseos-rpms	196 k	
perl-Math-Complex	noa	arch
1.59-421.el8		rhel-8-for-
x86_64-baseos-rpms	109 k	
perl-Test-Harness	noa	arch
1:3.42-1.el8		rhel-8-for-
x86_64-appstream-rpms	279 k	
perl-devel	x8	6_64
4:5.26.3-419.el8_4.1		rhel-8-for-
x86 64-appstream-rpms	599 k	
perl-srpm-macros	noa	arch
1-25.el8		rhel-8-for-
x86 64-appstream-rpms	11 k	
perl-version	x8	6 64
6:0.99.24-1.el8		rhel-8-for-
x86 64-appstream-rpms	67 k	
platform-python-devel	x8	6 64
3.6.8-41.el8		rhel-8-for-
x86 64-appstream-rpms	249 k	
python-rpm-macros		arch
3-41.el8		rhel-8-for-
x86 64-appstream-rpms	15 k	2
python-srpm-macros		arch
3-41.el8	1100	rhel-8-for-
x86 64-appstream-rpms	15 k	INCL O LOL
python3-pyparsing		arch
2.1.10-7.el8	1100	rhel-8-for-
	142 k	THET 0-101-
x86_64-baseos-rpms		arch
<pre>python3-rpm-generators 5-7.el8</pre>	ПО	
	25 1-	rhel-8-for-
x86_64-appstream-rpms	25 k	la
python3-rpm-macros	noa	arch
3-41.el8	4.4.1	rhel-8-for-
x86_64-appstream-rpms	14 k	
qt5-srpm-macros	noa	arch

5.15.2-1.el8			rhel-8-for-
x86_64-appstream-rpms	11 k		
redhat-lsb-submod-security		x86_64	
4.1-47.el8			rhel-8-for-
x86_64-appstream-rpms	22 k		
redhat-rpm-config		noarch	
125-1.el8			rhel-8-for-
x86_64-appstream-rpms	87 k		
rust-srpm-macros		noarch	
5-2.el8			rhel-8-for-
x86_64-appstream-rpms	9.3 k		
spax		x86_64	
1.5.3-13.el8			rhel-8-for-
x86_64-baseos-rpms	217 k		
systemtap-sdt-devel		x86_64	
4.6-4.el8			rhel-8-for-
x86_64-appstream-rpms	86 k		
time		x86_64	1 1 0 6
1.9-3.el8	E 4 1		rhel-8-for-
x86_64-baseos-rpms	54 k	0.6.64	
unzip		x86_64	1 1 0 6
6.0-46.e18	106 1-		rhel-8-for-
x86_64-baseos-rpms	196 k	0.6 .64	
util-linux-user		x86_64	whol 0 for
2.32.1-28.el8	100 k		rhel-8-for-
x86_64-baseos-rpms zip	100 K	x86 64	
3.0-23.e18		X00_04	rhel-8-for-
x86_64-baseos-rpms	270 k		11161 0 101
zlib-devel	270 K	x86 64	
1.2.11-17.el8		X00_04	rhel-8-for-
x86 64-baseos-rpms	58 k		inci o ioi
Installing weak dependencies:	00 K		
perl-CPAN-Meta		noarch	
2.150010-396.el8		11001011	rhel-8-for-
x86 64-appstream-rpms	191 k		11101 0 101
perl-CPAN-Meta-Requirements		noarch	
2.140-396.el8			rhel-8-for-
x86 64-appstream-rpms	37 k		
perl-Encode-Locale		noarch	
1.05-10.module+el8.3.0+6498+9eecfe51			rhel-8-for-
x86 64-appstream-rpms	22 k		
perl-Time-HiRes		x86 64	
4:1.9758-2.el8		_	rhel-8-for-
x86_64-appstream-rpms	61 k		
_			

```
Transaction Summary
_____
_____
Install 69 Packages
Upgrade 17 Packages
Total download size: 72 M
Is this ok [y/N]: y
Downloading Packages:
(1/86): perl-ExtUtils-Install-2.14-4.el8.noarch.rpm
735 kB/s | 46 kB 00:00
(2/86): libesmtp-1.0.6-18.el8.x86 64.rpm
1.0 MB/s | 70 kB
                   00:00
(3/86): esmtp-1.2-15.el8.x86 64.rpm
747 kB/s | 57 kB
                    00:00
(4/86): rust-srpm-macros-5-2.el8.noarch.rpm
308 kB/s | 9.3 kB
                    00:00
(5/86): perl-ExtUtils-Manifest-1.70-395.el8.noarch.rpm
781 kB/s | 37 kB
                    00:00
(6/86): perl-CPAN-Meta-2.150010-396.el8.noarch.rpm
2.7 MB/s | 191 kB
                   00:00
(7/86): ocaml-srpm-macros-5-4.el8.noarch.rpm
                    00:00
214 kB/s | 9.5 kB
(8/86): perl-JSON-PP-2.97.001-3.el8.noarch.rpm
1.2 MB/s | 68 kB
                    00:00
(9/86): perl-ExtUtils-MakeMaker-7.34-1.el8.noarch.rpm
5.8 MB/s | 301 kB
                    00:00
(10/86): ghc-srpm-macros-1.4.2-7.el8.noarch.rpm
317 kB/s | 9.4 kB
                    00:00
(11/86): perl-Test-Harness-3.42-1.el8.noarch.rpm
                    00:00
4.5 MB/s | 279 kB
(12/86): perl-ExtUtils-Command-7.34-1.el8.noarch.rpm
520 kB/s | 19 kB
                    00:00
15 MB/s | 1.5 MB 00:00
Total
35 MB/s | 72 MB 00:02
Running transaction check
Transaction check succeeded.
Running transaction test
```

```
Transaction test succeeded.
Running transaction
 Preparing
 Running scriptlet: openssl-libs-1:1.1.1k-7.el8 6.x86 64
 Upgrading : openssl-libs-1:1.1.1k-7.el8 6.x86 64
1/103
 Running scriptlet: openssl-libs-1:1.1.1k-7.el8 6.x86 64
1/103
 Upgrading : libgcc-8.5.0-10.1.el8 6.x86 64
2/103
 Running scriptlet: libgcc-8.5.0-10.1.el8 6.x86 64
2/103
 Upgrading : elfutils-libelf-0.186-1.el8.x86 64
3/103
 Installing : perl-version-6:0.99.24-1.el8.x86 64
4/103
 Installing : perl-CPAN-Meta-Requirements-2.140-396.el8.noarch
5/103
 Upgrading : libsemanage-2.9-8.el8.x86 64
6/103
 Installing : zlib-devel-1.2.11-17.el8.x86 64
7/103
 Installing : python-srpm-macros-3-41.el8.noarch
8/103
 Installing : python-rpm-macros-3-41.el8.noarch
9/103
 Installing : python3-rpm-macros-3-41.el8.noarch
10/103
 Installing : perl-Time-HiRes-4:1.9758-2.el8.x86_64
11/103
 Installing : perl-ExtUtils-ParseXS-1:3.35-2.el8.noarch
12/103
 Installing : perl-Test-Harness-1:3.42-1.el8.noarch
13/103
 Upgrading : python3-libsemanage-2.9-8.el8.x86 64
14/103
 Upgrading : policycoreutils-2.9-19.el8.x86 64
15/103
 Running scriptlet: policycoreutils-2.9-19.el8.x86 64
15/103
 Upgrading : python3-policycoreutils-2.9-19.el8.noarch
16/103
 Installing : dwz-0.12-10.el8.x86_64
17/103
```

Installing : ncurses-compat-libs-6.1-9.20180224.el8.x86 64 18/103 Installing : libesmtp-1.0.6-18.el8.x86 64 19/103 Installing : mailx-12.5-29.el8.x86 64 20/103 Installing : libkadm5-1.18.2-14.el8.x86 64 21/103 Upgrading : libgomp-8.5.0-10.1.el8 6.x86 64 22/103 Running scriptlet: libgomp-8.5.0-10.1.el8 6.x86 64 22/103 : platform-python-pip-9.0.3-22.el8.noarch Upgrading 23/103 Upgrading : python3-pip-9.0.3-22.el8.noarch 24/103 : python36-3.6.8-Upgrading 38.module+el8.5.0+12207+5c5719bc.x86 64 25/103 Running scriptlet: python36-3.6.8-38.module+el8.5.0+12207+5c5719bc.x86 64 25/103 Upgrading : cpp-8.5.0-10.1.el8 6.x86 64 26/103 Running scriptlet: cpp-8.5.0-10.1.el8 6.x86 64 26/103 Upgrading : gcc-8.5.0-10.1.el8 6.x86 64 27/103 Running scriptlet: gcc-8.5.0-10.1.el8 6.x86 64 27/103 Installing : annobin-10.29-3.el8.x86 64 28/103 Installing : unzip-6.0-46.el8.x86 64 29/103 Installing : zip-3.0-23.el8.x86 64 30/103 Installing : perl-Math-Complex-1.59-421.el8.noarch 31/103 Installing : perl-Math-BigInt-1:1.9998.11-7.el8.noarch 32/103 Installing : perl-JSON-PP-1:2.97.001-3.el8.noarch 33/103 Installing : make-1:4.2.1-11.el8.x86 64 34/103 Running scriptlet: make-1:4.2.1-11.el8.x86 64 34/103

Installing : libcom err-devel-1.45.6-2.el8.x86 64 35/103 Installing : util-linux-user-2.32.1-28.el8.x86 64 36/103 Installing : libsepol-devel-2.9-3.el8.x86 64 37/103 Installing : pcre2-utf32-10.32-2.el8.x86 64 38/103 Installing : pcre2-utf16-10.32-2.el8.x86 64 39/103 Installing : pcre2-devel-10.32-2.el8.x86 64 40/103 Installing : libselinux-devel-2.9-5.el8.x86 64 41/103 Installing : patch-2.7.6-11.el8.x86 64 42/103 Installing : python3-pyparsing-2.1.10-7.el8.noarch 43/103 Installing : systemtap-sdt-devel-4.6-4.el8.x86 64 44/103 Installing : spax-1.5.3-13.el8.x86 64 Running scriptlet: spax-1.5.3-13.el8.x86 64 45/103 Installing : m4-1.4.18-7.el8.x86 64 Running scriptlet: m4-1.4.18-7.el8.x86 64 46/103 Installing : libverto-devel-0.3.0-5.el8.x86 64 47/103 Installing : bc-1.07.1-5.el8.x86 64 48/103 Running scriptlet: bc-1.07.1-5.el8.x86 64 48/103 Installing : at-3.1.20-11.el8.x86 64 49/103 Running scriptlet: at-3.1.20-11.el8.x86 64 Installing : keyutils-libs-devel-1.5.10-6.el8.x86 64 50/103 Installing : krb5-devel-1.18.2-14.el8.x86 64 51/103 Installing : time-1.9-3.el8.x86 64 Running scriptlet: time-1.9-3.el8.x86 64

Upgrading : policycoreutils-python-utils-2.9-19.el8.noarch 80/103 Installing : elfutils-libelf-devel-0.186-1.el8.x86 64 81/103 Upgrading : elfutils-libs-0.186-1.el8.x86 64 82/103 Upgrading : mokutil-1:0.3.0-11.el8 6.1.x86 64 83/103 Upgrading : openssl-1:1.1.1k-7.el8 6.x86 64 84/103 Installing : kernel-devel-4.18.0-348.el8.x86 64 85/103 Running scriptlet: kernel-devel-4.18.0-348.el8.x86 64 85/103 Installing : bzip2-1.0.6-26.el8.x86 64 86/103 : policycoreutils-python-utils-2.9-14.el8.noarch Cleanup 87/103 : python3-policycoreutils-2.9-14.el8.noarch Cleanup 88/103 Cleanup : python36-3.6.8-2.module+el8.1.0+3334+5cb623d7.x86 64 89/103 Running scriptlet: python36-3.6.8-2.module+el8.1.0+3334+5cb623d7.x86 64 89/103 : elfutils-libs-0.185-1.el8.x86 64 Cleanup 90/103 : openssl-1:1.1.1k-4.el8.x86 64 Cleanup 91/103 Cleanup : python3-libsemanage-2.9-6.el8.x86 64 92/103 Running scriptlet: gcc-8.4.1-1.el8.x86 64 93/103 : gcc-8.4.1-1.el8.x86 64 Cleanup 93/103 Running scriptlet: policycoreutils-2.9-14.el8.x86 64 94/103 Cleanup : policycoreutils-2.9-14.el8.x86 64 94/103 Cleanup : mokutil-1:0.3.0-11.el8.x86 64 95/103

```
: python3-pip-9.0.3-19.el8.noarch
  Cleanup
96/103
            : platform-python-pip-9.0.3-19.el8.noarch
 Cleanup
97/103
 Cleanup
             : openssl-libs-1:1.1.1k-4.el8.x86 64
98/103
  Running scriptlet: openssl-libs-1:1.1.1k-4.el8.x86 64
98/103
 Cleanup : libsemanage-2.9-6.el8.x86 64
99/103
 Running scriptlet: cpp-8.4.1-1.el8.x86 64
100/103
 Cleanup
           : cpp-8.4.1-1.el8.x86 64
100/103
             : libgcc-8.5.0-3.el8.x86 64
 Cleanup
101/103
 Running scriptlet: libgcc-8.5.0-3.el8.x86 64
101/103
 Running scriptlet: libgomp-8.4.1-1.el8.x86 64
102/103
            : libgomp-8.4.1-1.el8.x86 64
 Cleanup
102/103
  Running scriptlet: libgomp-8.4.1-1.el8.x86 64
102/103
 Cleanup : elfutils-libelf-0.185-1.el8.x86 64
103/103
 Running scriptlet: elfutils-libelf-0.185-1.el8.x86 64
103/103
 Verifying : esmtp-1.2-15.el8.x86 64
1/103
 Verifying : libesmtp-1.0.6-18.el8.x86 64
  . . .
Upgraded:
  cpp-8.5.0-10.1.el8_6.x86_64
                                                       elfutils-
libelf-0.186-1.el8.x86_64 elfutils-libs-0.186-1.el8.x86_64
gcc-8.5.0-10.1.el8 6.x86 64
  libgcc-8.5.0-10.1.el8 6.x86 64
                                                       libgomp-
8.5.0-10.1.el8 6.x86 64 libsemanage-2.9-8.el8.x86 64
mokutil-1:0.3.0-11.el8_6.1.x86_64
 openssl-1:1.1.1k-7.el8 6.x86 64
                                                       openssl-
libs-1:1.1.1k-7.el8 6.x86 64 platform-python-pip-9.0.3-22.el8.noarch
policycoreutils-2.9-19.el8.x86 64
  policycoreutils-python-utils-2.9-19.el8.noarch
libsemanage-2.9-8.el8.x86 64 python3-pip-9.0.3-22.el8.noarch
```

```
python3-policycoreutils-2.9-19.el8.noarch
  python36-3.6.8-38.module+el8.5.0+12207+5c5719bc.x86 64
Installed:
  annobin-10.29-3.el8.x86 64
                                                                    at-
3.1.20-11.el8.x86_64
                                                bc-1.07.1-5.el8.x86 64
 bzip2-1.0.6-26.el8.x86 64
cups-client-1:2.2.6-38.el8.x86 64
                                                    dwz-0.12-
10.el8.x86 64
  ed-1.14.2-4.el8.x86 64
efi-srpm-macros-3-3.el8.noarch
                                                    elfutils-libelf-
devel-0.186-1.el8.x86 64
  esmtp-1.2-15.el8.x86 64
ghc-srpm-macros-1.4.2-7.el8.noarch
                                                  go-srpm-macros-2-
17.el8.noarch
  kernel-devel-4.18.0-348.el8.x86 64
keyutils-libs-devel-1.5.10-6.el8.x86 64
                                                   krb5-devel-1.18.2-
14.el8.x86 64
  libcom err-devel-1.45.6-2.el8.x86 64
libesmtp-1.0.6-18.el8.x86 64
                                                    libkadm5-1.18.2-
14.el8.x86 64
  liblockfile-1.14-1.el8.x86 64
libselinux-devel-2.9-5.el8.x86_64
                                                   libsepol-devel-2.9-
3.el8.x86 64
  libverto-devel-0.3.0-5.el8.x86 64
                                                                    m4-
1.4.18-7.el8.x86 64
                                                 mailx-12.5-
29.el8.x86 64
 make-1:4.2.1-11.el8.x86 64
ncurses-compat-libs-6.1-9.20180224.el8.x86 64 ocaml-srpm-macros-
5-4.el8.noarch
  openblas-srpm-macros-2-2.el8.noarch
openssl-devel-1:1.1.1k-7.el8 6.x86 64
                                                   patch-2.7.6-
11.el8.x86 64
  pcre2-devel-10.32-2.el8.x86 64
pcre2-utf16-10.32-2.el8.x86_64
                                                    pcre2-utf32-10.32-
2.el8.x86 64
  perl-CPAN-Meta-2.150010-396.el8.noarch
perl-CPAN-Meta-Requirements-2.140-396.el8.noarch perl-CPAN-Meta-
YAML-0.018-397.el8.noarch
  perl-Encode-Locale-1.05-10.module+el8.3.0+6498+9eecfe51.noarch
perl-ExtUtils-Command-1:7.34-1.el8.noarch
                                                    perl-ExtUtils-
Install-2.14-4.el8.noarch
  perl-ExtUtils-MakeMaker-1:7.34-1.el8.noarch
                                            perl-ExtUtils-
perl-ExtUtils-Manifest-1.70-395.el8.noarch
ParseXS-1:3.35-2.el8.noarch
  perl-JSON-PP-1:2.97.001-3.el8.noarch
perl-Math-BigInt-1:1.9998.11-7.el8.noarch
                                                  perl-Math-Complex-
```

```
1.59-421.el8.noarch
  perl-Test-Harness-1:3.42-1.el8.noarch
perl-Time-HiRes-4:1.9758-2.el8.x86 64
                                                   perl-devel-
4:5.26.3-419.el8 4.1.x86 64
 perl-srpm-macros-1-25.el8.noarch
perl-version-6:0.99.24-1.el8.x86 64
                                                    platform-python-
devel-3.6.8-41.el8.x86 64
  python-rpm-macros-3-41.el8.noarch
python-srpm-macros-3-41.el8.noarch
                                                    python3-pyparsing-
2.1.10-7.el8.noarch
  python3-rpm-generators-5-7.el8.noarch
python3-rpm-macros-3-41.el8.noarch
                                                    python36-devel-
3.6.8-38.module+el8.5.0+12207+5c5719bc.x86 64
  qt5-srpm-macros-5.15.2-1.el8.noarch
redhat-lsb-core-4.1-47.el8.x86 64
                                                    redhat-lsb-submod-
security-4.1-47.el8.x86 64
 redhat-rpm-config-125-1.el8.noarch
rust-srpm-macros-5-2.el8.noarch
                                                    spax-1.5.3-
13.el8.x86 64
  systemtap-sdt-devel-4.6-4.el8.x86 64
time-1.9-3.el8.x86 64
                                                    unzip-6.0-
46.el8.x86 64
 util-linux-user-2.32.1-28.el8.x86 64
zip-3.0-23.el8.x86 64
                                                    zlib-devel-1.2.11-
17.el8.x86 64
Complete!
OS package installations finished
+ Installing ONTAP Mediator. (Log: /tmp/ontap mediator.JixKGP/ontap-
mediator-1.6.0/ontap-mediator-1.6.0/install 20221021155929.log)
    This step will take several minutes. Use the log file to view
progress.
    Sudoer config verified
    ONTAP Mediator rsyslog and logging rotation enabled
+ Install successful. (Moving log to
/opt/netapp/lib/ontap mediator/log/install 20221021155929.log)
+ WARNING: This system supports UEFI
           Secure Boot (SB) is currently disabled on this system.
           If SB is enabled in the future, SCST will not work unless
the following action is taken:
           Using the keys in
/opt/netapp/lib/ontap mediator/ontap mediator/SCST mod keys follow
           instructions in
/opt/netapp/lib/ontap mediator/ontap mediator/SCST mod keys/README.modu
le-signing
           to sign the SCST kernel module. Note that reboot will be
```

```
needed.

SCST will not start automatically when Secure Boot is enabled and not configured properly.

+ Note: ONTAP Mediator uses a kernel module compiled specifically for the current

OS. Using 'yum update' to upgrade the kernel might cause service interruption.

For more information, see /opt/netapp/lib/ontap_mediator/README

[root@scs000099753 ~]# cat /etc/redhat-release

Red Hat Enterprise Linux release 8.5 (Ootpa)

[root@scs000099753 ~]#
```

Verify the installation

After the ONTAP Mediator has been installed, you should verify that the ONTAP Mediator services are running.

Steps

- 1. View the status of the ONTAP Mediator services:
 - a. systemctl status ontap mediator

```
[root@scspr1915530002 ~]# systemctl status ontap mediator
ontap mediator.service - ONTAP Mediator
Loaded: loaded (/etc/systemd/system/ontap mediator.service; enabled;
vendor preset: disabled)
Active: active (running) since Mon 2022-04-18 10:41:49 EDT; 1 weeks 0
days ago
Process: 286710 ExecStop=/bin/kill -s INT $MAINPID (code=exited,
status=0/SUCCESS)
Main PID: 286712 (uwsgi)
Status: "uWSGI is ready"
Tasks: 3 (limit: 49473)
Memory: 139.2M
CGroup: /system.slice/ontap mediator.service
      -286712 /opt/netapp/lib/ontap_mediator/pyenv/bin/uwsgi --ini
/opt/netapp/lib/ontap mediator/uwsgi/ontap mediator.ini
      ├-286716 /opt/netapp/lib/ontap mediator/pyenv/bin/uwsqi --ini
/opt/netapp/lib/ontap mediator/uwsgi/ontap mediator.ini
      -286717 /opt/netapp/lib/ontap mediator/pyenv/bin/uwsgi --ini
/opt/netapp/lib/ontap mediator/uwsgi/ontap mediator.ini
[root@scspr1915530002 ~]#
```

b. systemctl status mediator-scst

2. Confirm the ports that are used by the ONTAP Mediator service:

netstat

```
[root@scspr1905507001 ~]# netstat -anlt | grep -E '3260|31784'

tcp 0 0 0.0.0.0:31784 0.0.0.0:* LISTEN

tcp 0 0 0.0.0.0:3260 0.0.0.0:* LISTEN

tcp6 0 0 :::3260 :::* LISTEN
```

Post-installation configuration

After the ONTAP Mediator service is installed and running, additional configuration tasks must be performed in the ONTAP storage system to use the Mediator features:

- To use the ONTAP Mediator service in a MetroCluster IP configuration, see Configuring the ONTAP Mediator service from a MetroCluster IP configuration.
- To use SnapMirror Business Continuity, see Install ONTAP Mediator Service and confirm the ONTAP cluster configuration.

Configure ONTAP Mediator security policies

The ONTAP Mediator server supports several configurable security settings. The default values for all settings are provide in a low_space_threshold_mib: 10read-only file:

/opt/netapp/lib/ontap_mediator/server_config/ontap_mediator.user_config.yaml

All values that are placed in the <code>ontap_mediator.user_config.yaml</code> will override the default values and be maintained across all ONTAP Mediator upgrades.

After you modify ontap mediator.user config.yaml, restart the ONTAP Mediator service:

```
systemctl restart ontap_mediator
```

The following attributes can be configured: NOTE: Other default values in the ontap mediator.config.yaml should not be modified.

 Settings used to install third-party SSL certificates as replacements for the default self-signed certificates

```
cert path:
'/opt/netapp/lib/ontap mediator/ontap mediator/server config/ontap media
tor server.crt'
key path:
'/opt/netapp/lib/ontap mediator/ontap mediator/server config/ontap media
tor server.key'
ca cert path:
'/opt/netapp/lib/ontap mediator/ontap mediator/server config/ca.crt'
ca key path:
'/opt/netapp/lib/ontap mediator/ontap mediator/server config/ca.key'
ca serial path:
'/opt/netapp/lib/ontap mediator/ontap mediator/server config/ca.srl'
cert valid days: '1095'
                                          # Used to set the expiration
on client certs to 3 years
x509 passin pwd: 'pass:ontap'
                                         # passphrase for the signed
client cert
```

· Settings that provide protections against brute-force password guessing attacks

To enable the feature, set a value for the window seconds and the retry limit

Examples:

• Provide a 5-minute window for guesses, and then reset the count to zero failures:

```
authentication lock window seconds: 300
```

• Lock the account if five failures occur within the window timeframe:

```
authentication retry limit: 5
```

 Reduce the impact of brute-force password guessing attacks by setting a delay that occurs prior to rejecting each attempt, which slows the attacks.

```
authentication failure delay seconds: 5
```

```
authentication_failure_delay_seconds: 0  # seconds (float) to delay failed auth attempts prior to response, 0 = no delay authentication_lock_window_seconds: null  # seconds (int) since the oldest failure before resetting the retry counter, null = no window authentication_retry_limit: null  # number of retries to allow before locking API access, null = unlimited
```

• Fields that control the password complexity rules of the ONTAP Mediator API user account

```
password_min_length: 8

password_max_length: 64

password_uppercase_chars: 0  # min. uppercase characters

password_lowercase_chars: 1  # min. lowercase character

password_special_chars: 1  # min. non-letter, non-digit

password_nonletter_chars: 2  # min. non-letter characters (digits, specials, anything)
```

• Setting that controls the required free space on the /opt/netapp/lib/ontap_mediator disk.

If the space is lower than the set threshold, the service will issue a warning event.

```
low_space_threshold_mib: 10
```

Copyright information

Copyright © 2023 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.