# Stochastic survival of the densest in neurons

May 22, 2023

## 1 Glossary

#### variables:

 $W_s =$  number of wild type mtDNA molecules in the soma  $M_s =$  number of mutant mtDNA molecules in the soma  $W_a =$  number of wild type mtDNA molecules in the axon  $M_a =$  number of mutant mtDNA molecules in the axon

#### parameters:

 $\mu=$  death rate or degradation rate  $\gamma=$  transport rate between two units  $\delta_m=$  mutant deficiency ratio  $C_b=$  adaptive birth rate control strength parameter  $C_t=$  adaptive transport rate control strength parameter  $NSS_A=$  carrying capacity of axon  $NSS_S=$  carrying capacity of soma

# 2 Equations governing per capita reaction rates and rates of change in the model

## 2.1 Per capita rates:

All per capita reaction rates are identical for wildtype (wt) and mutant (mt) mtDNA molecules, and defined as follows:

#### 2.1.1 Birth rates:

mtDNA is produced in the soma only. The rate of production is sufficient to supply both the soma and the axon.

$$Birth_{soma} = 2\mu + C_b \times (Nss_S - W_s - \delta_m M_s) \tag{1}$$

$$Birth_{axon} = 0 (2)$$

#### 2.1.2 Death rates:

mtDNA is degraded with equal rates in the soma and axon.

$$Death_{soma} = \mu \tag{3}$$

$$Death_{axon} = \mu \tag{4}$$

### 2.1.3 Transport rates:

mtDNA is transported between the soma and the axon. At steady state, anterograde (soma to axon) transport is 2x the rate of retrograde transport.

$$Move_{soma-axon} = 2\gamma + C_t \times (Nss_A - W_a - \delta_m M_a)$$
 (5)

$$Move_{axon-soma} = \gamma$$
 (6)

### 2.2 Absolute rates of change:

Thus the absolute rates of change for the four model variables are:

$$\frac{dW_s}{dt} = W_s \times ([2\mu + C_b \times (Nss_S - W_s - \delta_m M_s)] - [\mu] - [2\gamma + C_t \times (Nss_A - W_a - \delta_m M_a)]) + W_a \times [\gamma]$$
 (7)

$$\frac{dM_s}{dt} = M_s \times ([2\mu + C_b \times (Nss_S - W_s - \delta_m M_s)] - [\mu] - [2\gamma + C_t \times (Nss_A - W_a - \delta_m M_a)]) + M_a \times [\gamma]$$
 (8)

$$\frac{dW_a}{dt} = W_a \times ([0] - [\mu] - [\gamma]) + W_s \times [2\gamma + C_t \times (Nss_A - W_a - \delta_m M_a)]$$

$$\tag{9}$$

$$\frac{dM_a}{dt} = M_a \times ([0] - [\mu] - [\gamma]) + M_s \times [2\gamma + C_t \times (Nss_A - W_a - \delta_m M_a)]$$

$$\tag{10}$$

## 3 Steady states and simplification

A crucial steady state for the system occurs when both the soma and the axon are at carrying capacity, and the ratio of wild-type to mutant molecules, and the absolute number of molecules is identical in both units:

$$W_s = W_a \wedge M_s = M_a \wedge Nss_S = Nss_A \wedge Nss_S - W_s - \delta_m M_s = 0 \wedge Nss_A - W_a - \delta_m M_a = 0 \tag{11}$$

In such cases, the adaptive birth rate and transport rate terms are both 0:

$$C_b \times (Nss_S - W_s - \delta_m M_s) = 0 \wedge C_t \times (Nss_A - W_a - \delta_m M_a) = 0$$

$$\tag{12}$$

Thus, the system is reduced such that the rates are:

$$Birth_{soma} = 2\mu \tag{13}$$

$$Birth_{axon} = 0 (14)$$

$$Death_{soma} = \mu \tag{15}$$

$$Death_{axon} = \mu \tag{16}$$

$$Move_{soma-axon} = 2\gamma$$
 (17)

$$Move_{axon-soma} = \gamma$$
 (18)

Thus the absolute rates of change for the four model variables are:

$$\frac{dW_s}{dt} = W_s \times [2\mu - \mu - 2\gamma] + W_a \times [\gamma] = 0 \tag{19}$$

$$\frac{kdM_s}{dt} = M_s \times [2\mu - \mu - 2\gamma] + M_a \times [\gamma] = 0$$
(20)

$$\frac{dlW_a}{dt} = W_a \times [-\mu - \gamma] + W_s \times [2\gamma] = 0 \tag{21}$$

$$\frac{dM_a}{dt} = M_a \times [-\mu - \gamma] + M_s \times [2\gamma] = 0 \tag{22}$$

Thus  $\mu = \gamma$ .

# 4 simplified model

### 4.1 glossary

### variables:

 $W_s$  = number of wildtype mtDNA molecules in the soma

 $M_s$  = number of mutant mtDNA molecules in the soma

 $W_a$  = number of wildtype mtDNA molecules in the axon

 $M_a$  = number of mutant mtDNA molecules in the axon

#### parameters:

 $\lambda = \text{death/degradation rate}$  and transport rate (replacing  $\mu$  and  $\gamma$ )

 $\delta_m = \text{mutant deficiency ratio}$ 

 $C_b$  = adaptive birth rate control strength parameter

 $C_t = \text{adaptive transport rate control strength parameter}$ 

NSS =carrying capacity of axon and carrying capacity of soma

## 4.2 equations with explicit birth, death and transport rates

$$\frac{dW_s}{dt} = W_s \times ([2\lambda + C_b \times (Nss - W_s - \delta_m M_s)] - [\lambda] - [2\lambda + C_t \times (Nss - W_a - \delta_m M_a)]) + W_a \times [\lambda]$$
 (23)

$$\frac{dM_s}{dt} = M_s \times ([2\lambda + C_b \times (Nss - W_s - \delta_m M_s)] - [\lambda] - [2\lambda + C_t \times (Nss - W_a - \delta_m M_a)]) + M_a \times [\lambda]$$
(24)

$$\frac{dW_a}{dt} = W_a \times ([0] - [\lambda] - [\lambda]) + W_s \times [2\lambda + C_t \times (Nss - W_a - \delta_m M_a)]$$
(25)

$$\frac{dM_a}{dt} = M_a \times ([0] - [\lambda] - [\lambda]) + M_s \times [2\lambda + C_t \times (Nss - W_a - \delta_m M_a)]$$
(26)

## 4.3 new eqs.

$$\frac{dW_s}{dt} = W_s \times ([2\mu + C_b \times (Nss - W_s - \delta_m M_s)] - [\mu] - [2\gamma]) + W_a \times [\gamma]$$
(27)

$$\frac{dM_s}{dt} = M_s \times ([2\mu + C_b \times (Nss - W_s - \delta_m M_s)] - [\mu] - [2\gamma]) + M_a \times [\gamma]$$
(28)

$$\frac{dW_a}{dt} = W_a \times ([0] - [\mu] - [\gamma]) + W_s \times [2\gamma]$$
(29)

$$\frac{dM_a}{dt} = M_a \times ([0] - [\mu] - [\gamma]) + M_s \times [2\gamma]$$
(30)