
**Function Call Convention** 

#### Content



## **Function Call Convention**


#### Function call convention:

- → How functions work
- → Program-metadata on the stack


#### Stack based buffer overflow:

→ Overwrite program-metadata on the stack


## x32 Memory Layout



How do they work?







```
push 0x1
push 0x2
push 0x3
pop
push 0x4
```

push 0x1

push 0x2

push 0x3

pop

push 0x4

0x01

push 0x1

push 0x2

push 0x3

pop

push 0x4

0x01

0x02

push 0x1

push 0x2

push 0x3

pop

push 0x4

0x03
0x02
0x01

push 0x1

push 0x2

push 0x3

pop

push 0x4

0x01

0x02

push 0x1
push 0x2
push 0x3
pop
push 0x4

0x04
0x02
0x01

## Stack on intel




## Intel stack registers:

+ ESP: Stack Pointer

**→ EBP**: (Stack-) **B**ase **P**ointer

EBP = 0x1000ESP = 0x0FF8



## Stack in computers



Stack is using process memory as basis

CPU instruction support (because stack is so useful)

#### Note:

- ◆ CPU instructions like push/pop are just for ease of use
- ★ The "stack values" can be accessed (read, write) like every other memory address
- → You can point the stack (ebp, esp) to wherever in the memory you want
- There's usually just ONE stack per process (thread)

Functions and the Stack



## What is a function?

- **→** Self contained subroutine
- ★ Re-usable
- → Can be called from anywhere
- ★ After function is finished: Jump to the calling function (calee)

```
void main(void) {
 int blubb = 0;
 foobar(blubb);
 return;
void foobar (int arg1) {
 char compass1[];
 char compass2[];
```



# What does the function foobar() need?

- **→** Function Argument:
  - **♦** blubb
- **★** Local variables
  - **+**Compass1
  - +Compass2
- ★ And: Address of next instruction in main()
  - **→**&return



Saved IP (&\_\_libc\_start)
Saved Frame Pointer
Local Variables <main>

SIP SFP blubb

Stack Frame <main>


Argument for <foobar>
Saved IP (&return)

Saved Frame Pointer

Local Variables <foobar>

&blubb
SIP
SFP
compass1
compass2


Stack Frame <foobar>







```
void main(void) {
                      Pointer
 int blubb = 0; <----
 foobar(&blubb);
                               &blubb
 return; <
                               SIP
                Pointer
                               SFP
                               compass1
void foobar(int *arg1)
                               compass2
 char compass1[];
 char compass2[];
                    allocate
```





## SIP: Stored Instruction Pointer

- ◆ Copy of EIP
- → Points to the address where control flow continues after end of function
  - ★(return, ret)
- → Usually points into the code section



## SBP: Stored Base Pointer

- → Copy of EBP
- ★ Every function has its own little stack frame
- → Stack frame is where local variables, function arguments etc. are
- ★ A function should only access its own stack frame
- → Most of the function epilogue and prologue handle setting up and removing the stack frame
- → Note: It is not 100% necessary to completely understand it - but you will see it in the disassembly of every function
- → Note: You can compile programs without using SBP (ASM will be a bit harder to read)



#### Attention! Assembler ahead!

→ AT&T vs Intel syntax

## Intel syntax:

mov eax, 1

mov ebx,0ffh

int 80h

## AT&T syntax:

movl \$1,%eax

movl \$0xff, %ebx

int \$0x80

Don't hang me if I messed this up somewhere



#### In ASM:

call 0x11223344 <&foobar>



<function code> (0x11223344)



#### In ASM:

call 0x11223344 <&foobar> push EIP jmp 0x11223344 mov ebp, esp <function code> mov esp, ebp ret




**Prolog** 

#### In ASM:

```
call 0x11223344 <&foobar>
     push EIP
     jmp 0x11223344
mov ebp, esp
<function code>
                           Function
mov esp, ebp
ret
     pop eip
```

**Epilog** 







## Recap:

- → User data is on the stack
- → Also: important stuff is on the stack (Instruction Pointer, SIP)
- ◆ Stack grows down

  ◆ The stack grows down

  ◆ The
- → Writes go up

```
int add(int x, int y) {
  int sum;
  sum = x + y;
  return sum;
}
```

С	=	add(3,	4)

push 4
push 3
call add

push 4
push 3
push EIP
jmp add

C

**ASM** 

ASM, detailed

# push 4 push 3 push EIP jmp add

# add():

```
push ebp
mov ebp, esp,
sub esp, 0x10
mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp – 0x04], eax
mov eax, DWORD PTR [ebp - 0x04]
leave
ret
```

# push 4 push 3 push EIP jmp add

# add():

```
push ebp
mov ebp, esp,
sub esp, 0x10
mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp – 0x04], eax
mov eax, DWORD PTR [ebp – 0x04]
mov esp, ebp ; leave
pop ebp
               ; leave
ret
```

```
push 4
push 3
push EIP
jmp add
```

# add():

```
push ebp
mov ebp, esp,
sub esp, 0x10
mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp – 0x04], eax
mov eax, DWORD PTR [ebp – 0x04]
mov esp, ebp ; leave
pop ebp
               ; leave
pop eip
               ; ret
```

#### x32 Call Convention Details




# add():


```
push 4
push 3
push EIP
jmp add
```


```
push ebp
mov ebp, esp,
sub esp, 0x10
```


```
mov esp, ebp ; leave
pop ebp ; leave
pop eip ; ret
```


**Function Prolog** 


























**Execute Function** 


#### x32 Call Convention - Execute Function





**Function Epilog** 















```
call <addr> =
 push EIP
  jmp <addr>
leave =
 mov esp, ebp
 pop ebp
ret =
 pop eip
```

#### x32 Call Convention - Function Calling

```
Why "leave"?
     → Opposite of "enter"
"enter":
    push ebp
    mov ebp, esp
    sub esp, imm
Why no "enter" used?
      enter:
           ★ 8 cycle latency
           → 10-20 micro ops
      call <addr>; mov ebp, esp; sub esp, imm:
           → 3 cycles latency

→ 4-6 micro ops
```

### x32 Call Convention - Function Calling




#### Recap:

- ★ When a function is called:
  - → EIP is pushed on the stack (=SIP)
  - → ("call" is doing implicit "push EIP")
- ★ At the end of the function:
  - → SIP is recovered into EIP
  - → ("ret" is doing implicit "pop EIP")

Accessing the Stack







- A) push 0x1
  B) mov [ebp-0x10], 0x1
- C) mov eax, 0x1000 mov [eax], 0x1

Function Calls in x64

#### x32 Call Convention - Function Call in x64

Differences between x32 and x64 function calls:

Arguments are in registers (not on stack)

RDI, RSI, RDX, R8, R9

Differences between x32 and x64 function calls

Different ASM commands doing the same thing

```
callq (call)
leaveq (leave)
retq (ret)
```

#### x32 Call Convention - Function Call in x64

Some random x64 architecture facts:

The stack should stay 8-byte aligned at all times

An n-byte item should start at an address divisible by n

→ E.g. 64 bit number: 8 bytes, can be at 0x00, 0x08, 0x10, 0x18, ...

%rsp points to the lowest occupied stack location

not the next one to use!








x32	Parameter	Syscall nr in
x32 userspace	stack	
x32 syscalls	ebx, ecx, edx, esi, edi, ebp	eax

x64	Parameter	Syscall nr in
x64 userspace	rdi, rsi, rdx, rcx, r8, r9	
x64 syscall	rdi, rsi, rdx, r10, r8, r9	rax

http://stackoverflow.com/questions/2535989/what-are-the-calling-conventions-for-unix-linux-system-calls-on-x86-64

#### **EBP Cheat Sheet**





#### **EBP Cheat Sheet**

Outro

### Further questions

Can you implement push/pop in ASM? (without actually using push/pop)

#### **Answers**

#### Pseudocode:

```
# EAX is the new ESP
push <data>:
    sub eax, 4
    mov (%eax), <data>

pop <register>:
    mov <register>, (%eax)
    add eax, 4
```