
Akdeniz University Computer Engineering Department


CSE206 Computer Organization

Week14-15: Assembly Language, Data Transfers, Addressing, and Arithmetic

Assoc.Prof.Dr. Taner Danışman tdanisman@akdeniz.edu.tr



Registers



X64 Registers

64-bit register	Lower 32 bits	Lower 16 bits	Lower 8 bits
rax	eax	ax	al
rbx	ebx	bx	bl
rcx	есх	СХ	cl
rdx	edx	dx	dl
rsi	esi	si	sil
rdi	edi	di	dil
rbp	ebp	bp	bpl
rsp	esp	sp	spl

64 extends x86's 8 general-purpose registers to be 64-bit, and adds 8 new 64-bit registers. The 64-bit registers have names beginning with "r", so for example the 64-bit extension of **eax** is called **rax**.

Some Specialized Register Uses (1 of 2)

- General-Purpose
 - ►EAX accumulator
 - ECX loop counter
 - ESP stack pointer
 - ESI, EDI index registers
 - EBP extended frame pointer (stack)
- Segment
 - CS code segment
 - DS data segment
 - SS stack segment
 - ES, FS, GS additional segments

Chapter Overview (Chp #3 from Irvine)

- http://kipirvine.com/asm/
- <u>http://kipirvine.com/asm/examples/index.htm</u>
- http://kipirvine.com/asm/examples/Irvine_7th_Edition.msi

- Read Chapter #3
- Basic Elements of Assembly Language
- Example: Adding and Subtracting Integers
- Assembling, Linking, and Running Programs
- Defining Data
- Symbolic Constants

Integer Constants

- Optional leading + or sign
- binary, decimal, hexadecimal, or octal digits
- Common radix characters:
 - h hexadecimal
 - d decimal
 - ■b binary
 - -r encoded real

Examples: 30d, 6Ah, 42, 1101b

Hexadecimal beginning with letter: 0A5h

Integer Expressions

Operators and precedence levels:

Operator	Name	Precedence Level
()	parentheses	1
+,-	unary plus, minus	2
*,/	multiply, divide	3
MOD	modulus	3
+,-	add, subtract	4

Examples:

Expression	Value
16 / 5	3
-(3 + 4) * (6 - 1)	-35
-3 + 4 * 6 - 1	20
25 mod 3	1

Irvine, Kip R. Assembly Language for x86 Processors 7/e, 2015.

Character and String Constants

- Enclose character in single or double quotes
 - ►'A', "X"
 - ASCII character = 1 byte
- Enclose strings in single or double quotes
 - ∕="ABC"
 - **-** 'xyz'
 - Each character occupies a single byte
- Embedded quotes:
 - 'Say "Goodnight," Gracie

Reserved Words and Identifiers

- Reserved words cannot be used as identifiers
 - Instruction mnemonics, directives, type attributes, operators, predefined symbols
- Identifiers
 - ▶ 1-247 characters, including digits
 - not case sensitive
 - first character must be a letter, _, @, ?, or \$

Directives

- Commands that are recognized and acted upon by the assembler
 - Not part of the Intel instruction set
 - Used to declare code, data areas, select memory model, declare procedures, etc.
 - not case sensitive
- Different assemblers have different directives
 - NASM not the same as MASM, for example

Instructions

- Assembled into machine code by assembler
- Executed at runtime by the CPU
- We use the Intel IA-32 instruction set
- An instruction contains:
 - Label (optional)
 - Mnemonic (required)
 - Operand (depends on the instruction)
 - Comment (optional)

- Act as place markers
 - marks the address (offset) of code and data
- Follow identifer rules
- Data label
 - must be unique
 - example: myArray (not followed by colon)
- Code label
 - target of jump and loop instructions
 - example: L1: (followed by colon)

Mnemonics and Operands

- Instruction Mnemonics
 - memory aid
 - examples: MOV, ADD, SUB, MUL, INC, DEC
- Operands
 - constant
 - constant expression
 - register
 - memory (data label)

Constants and constant expressions are often called immediate values

Comments

- Comments are good!
 - explain the program's purpose
 - when it was written, and by whom
 - revision information
 - tricky coding techniques
 - application-specific explanations
- Single-line comments
 - begin with semicolon (;)
- Multi-line comments
 - begin with COMMENT directive and a programmer-chosen character
 - end with the same programmer-chosen character

Instruction Format Examples

- No operands
 - stc ; set Carry flag
- One operand
 - inc eax ; register
 - inc myByte ; memory
- Two operands
 - add ebx,ecx ; register, register
 - sub myByte,25 ; memory, constant
 - add eax,36 * 25 ; register, constant-expression

The Hello World Program -16 bit

```
.MODEL small
   .STACK 100h
   .DATA
Message DB 'Hello, world!',13,10,'$'
   .CODE
  mov ax,@data
                         ;set DS to point to the data segment
  mov ds, ax
                           ;DOS print string function
   mov ah,9
       dx, OFFSET Message ; point to "Hello, world!"
   mov
                           ;display "Hello, world!"
   int 21h
                           ;DOS terminate program function
       ah,4ch
   mov
                           ;terminate the program
   int 21h
   END
```



19

Printing digits – 16 bit

```
data segment
data ends
code segment
    assume ds : data, cs : code
start:
   mov ax, data
   mov ds, ax
    mov bl, 00h
    mov ch, 00h
    mov cl, 0ah
11
   mov dh, 00h
    mov dl, bl
    add dl, '0'
    mov ah, 02h
    int 21h
    inc bl
loop 11
```

```
mov ah, 4ch
   int 21h
code ends
end start
 output
    0123456789
```

General Program Template


```
; Program Template
                              (Template.asm)
; Program Description:
 Author:
; Creation Date:
; Revisions:
; Date:
                     Modified by:
.386
.model flat, stdcall
.stack 4096
ExitProcess PROTO, dwExitCode:DWORD
.data
; declare variables here
.code
main PROC
    ; write your code here
    INVOKE ExitProcess, 0
main ENDP
; (insert additional procedures here)
END main
```

Assembling, Linking, and Running Programs

- Assemble-Link-Execute Cycle
- Listing File
- Map File

Assemble-Link Execute Cycle

- The following diagram describes the steps from creating a source program through executing the compiled program.
- If the source code is modified, Steps 2 through 4 must be repeated.



Listing File

- Use it to see how your program is compiled
- Contains
 - source code
 - addresses
 - object code (machine language)
 - segment names
 - symbols (variables, procedures, and constants)

Defining Data

- Intrinsic Data Types
- Data Definition Statement
- Defining BYTE and SBYTE Data
- Defining WORD and SWORD Data
- Defining DWORD and SDWORD Data
- Defining QWORD Data
- Defining TBYTE Data
- Defining Real Number Data
- Little Endian Order
- Adding Variables to the AddSub Program
- Declaring Uninitialized Data

Intrinsic Data Types (1 of 2)

- BYTE, SBYTE
 - →8-bit unsigned integer; 8-bit signed integer
- WORD, SWORD
 - 16-bit unsigned & signed integer
- DWORD, SDWORD
 - 32-bit unsigned & signed integer
- QWORD
 - 64-bit integer
- **TBYTE**
 - ■80-bit integer

Intrinsic Data Types (2 of 2)

- REAL4
 - → 4-byte IEEE short real
- REAL8
 - 8-byte IEEE long real
- REAL10
 - 10-byte IEEE extended real

Data Definition Statement

- A data definition statement sets aside storage in memory for a variable.
- May optionally assign a name (label) to the data
- Syntax:

[name] directive initializer [,initializer] . . .

value1 BYTE 10

All initializers become binary data in memory

Defining BYTE and SBYTE Data

Each of the following defines a single byte of storage:

- MASM does not prevent you from initializing a BYTE with a negative value, but it's considered poor style.
- If you declare a SBYTE variable, the Microsoft debugger will automatically display its value in decimal with a leading sign.

Defining Byte Arrays

Examples that use multiple initializers:

```
list1 BYTE 10,20,30,40
list2 BYTE 10,20,30,40
    BYTE 50,60,70,80
    BYTE 81,82,83,84
list3 BYTE ?,32,41h,00100010b
list4 BYTE 0Ah,20h,'A',22h
```

Defining Strings (1 of 3)

- A string is implemented as an array of characters
 - For convenience, it is usually enclosed in quotation marks
 - It often will be null-terminated

Examples:

Defining Strings (2 of 3)

To continue a single string across multiple lines, end each line with a comma:

```
menu BYTE "Checking Account",0dh,0ah,0dh,0ah,
   "1. Create a new account",0dh,0ah,
   "2. Open an existing account",0dh,0ah,
   "3. Credit the account",0dh,0ah,
   "4. Debit the account",0dh,0ah,
   "5. Exit",0ah,0ah,
   "Choice> ",0
```

Defining Strings (3 of 3)

- End-of-line character sequence:
 - → ODh = carriage return
 - 0Ah = line feed

```
str1 BYTE "Enter your name: ",0Dh,0Ah

BYTE "Enter your address: ",0

newLine BYTE 0Dh,0Ah,0
```

Idea: Define all strings used by your program in the same area of the data segment.

Using the DUP Operator

- Use DUP to allocate (create space for) an array or string.
 Syntax: counter DUP (argument)
- Counter and argument must be constants or constant expressions

Defining WORD and SWORD Data

- Define storage for 16-bit integers
 - or double characters
 - single value or multiple values

```
word1
      WORD
                          ; largest unsigned value
            65535
word2
      SWORD -32768
                          ; smallest signed value
word3
      WORD
                          ; uninitialized, unsigned
word4
      WORD
            "AB"
                          ; double characters
myList WORD 1,2,3,4,5
                          ; array of words
array WORD 5 DUP(?)
                          ; uninitialized array
```

Defining DWORD and SDWORD Data

Storage definitions for signed and unsigned 32-bit integers:

Defining QWORD, TBYTE, Real Data

Storage definitions for quadwords, tenbyte values, and real numbers:

```
quad1 QWORD 1234567812345678h

val1 TBYTE 100000000123456789Ah

rVal1 REAL4 -2.1

rVal2 REAL8 3.2E-260

rVal3 REAL10 4.6E+4096

ShortArray REAL4 20 DUP(0.0)
```

Little Endian Order

All data types larger than a byte store their individual bytes in reverse order. The least significant byte occurs at the first (lowest) memory address.

Example:

val1 DWORD 12345678h

0000:	78
0001:	56
0002:	34
0003:	12

Adding Variables to AddSub

```
TITLE Add and Subtract, Version 2
                                          (AddSub2.asm)
; This program adds and subtracts 32-bit unsigned
; integers and stores the sum in a variable.
INCLUDE Irvine32.inc
.data
val1 DWORD 10000h
val2 DWORD 40000h
val3 DWORD 20000h
finalVal DWORD ?
. code
main PROC
                          ; start with 10000h
   mov eax, val1
   add eax, val2
                 ; add 40000h
   sub eax, val3 ; subtract 20000h
   mov finalVal, eax ; store the result (30000h)
   call DumpRegs
                            ; display the registers
   exit
main ENDP
END main
```

Declaring Unitialized Data

Use the .data? directive to declare an unintialized data segment:

.data?

Within the segment, declare variables with "?" initializers: smallArray DWORD 10 DUP(?)

Advantage: the program's EXE file size is reduced.

What's Next

- Basic Elements of Assembly Language
- Example: Adding and Subtracting Integers
- Assembling, Linking, and Running Programs
- Defining Data
- Symbolic Constants

Symbolic Constants

- Equal-Sign Directive
- Calculating the Sizes of Arrays and Strings
- EQU Directive
- TEXTEQU Directive

Calculating the Size of a Byte Array

- current location counter: \$
 - subtract address of list
 - difference is the number of bytes

```
list BYTE 10,20,30,40
ListSize = ($ - list)
```

Calculating the Size of a Word Array

Divide total number of bytes by 2 (the size of a word)

```
list WORD 1000h,2000h,3000h,4000h
ListSize = ($ - list) / 2
```

Calculating the Size of a Doubleword Array

Divide total number of bytes by 4 (the size of a doubleword)

```
list DWORD 1,2,3,4
ListSize = ($ - list) / 4
```

EQU Directive

- Define a symbol as either an integer or text expression.
- Cannot be redefined

```
PI EQU <3.1416>
pressKey EQU <"Press any key to continue...",0>
.data
prompt BYTE pressKey
```

TEXTEQU Directive

- Define a symbol as either an integer or text expression.
- Called a text macro
- Can be redefined

```
continueMsg TEXTEQU <"Do you wish to continue (Y/N)?">
rowSize = 5
.data
prompt1 BYTE continueMsg
count TEXTEQU %(rowSize * 2) ; evaluates the expression
setupAL TEXTEQU <mov al,count>
.code
setupAL ; generates: "mov al,10"
```

Addressing modes

The three basic modes of addressing are

Register addressing

In this addressing mode, a register contains the operand. Depending upon the instruction, the register may be the first operand, the second operand or both.

MOV DX, TAX_RATE; Register in first operand MOV COUNT, CX; Register in second operand MOV EAX, EBX; Both the operands are in registers

As processing data between registers does not involve memory, it provides fastest processing of data.

Immediate addressing

An immediate operand has a constant value or an expression. The first operand defines the length of the data.

BYTE_VALUE DB 150; A byte value is defined WORD_VALUE DW 300; A word value is defined ADD BYTE_VALUE, 65; An immediate operand 65 is added MOV AX, 45H; Immediate constant 45H is transferred to AX

Memory addressing

When an instruction with two operands uses immediate addressing, the first operand may be a register or memory location, and the second operand is an immediate constant.

Memory Addressing Modes

Direct Memory Addressing

This way of addressing results in slower processing of data.

- When operands are specified in memory addressing mode, direct access to main memory, usually to the data segment, is required.
- To locate the exact location of data in memory, we need the segment start address, which is typically found in the DS register and an offset value. This offset value is also called effective address.

ADD BYTE_VALUE, DL; Adds the register in the memory location ,MOV BX, WORD VALUE; Operand from the memory is added to register

Direct Offset Addressing

This addressing mode uses the arithmetic operators to modify an address.

BYTE_TABLE DB 14, 15, 22, 45; Tables of bytes

BYTE_TABLE DB 14, 15, 22, 45; Tables of bytes
WORD TABLE DW 134, 345, 564, 123; Tables of words
MOV CL, BYTE_TABLE[2]; Gets the 3rd element of the BYTE_TABLE
MOV CL, BYTE_TABLE + 2; Gets the 3rd element of the BYTE_TABLE
MOV CX, WORD_TABLE[3]; Gets the 4th element of the WORD_TABLE
MOV CX, WORD_TABLE + 3; Gets the 4th element of the WORD_TABLE

Indirect Memory Addressing

Memory Addressing Modes

Indirect Addressing

- This addressing mode utilizes the computer's ability of Segment:Offset addressing.
- Generally, the base registers EBX, EBP (or BX, BP) and the index registers (DI, SI), coded within square brackets for memory references, are used for this purpose.
- Indirect addressing is generally used for variables containing several elements like, arrays.

```
MY_TABLE TIMES 10 DW 0; Allocates 10 words (2 bytes) each initialized to 0
MOV EBX, [MY_TABLE]; Effective Address of MY_TABLE in EBX
MOV [EBX], 110; MY_TABLE[0] = 110
ADD EBX, 2; EBX = EBX +2
MOV [EBX], 123; MY_TABLE[1] = 123
```

Chapter Overview

- Data Transfer Instructions
- Addition and Subtraction
- Data-Related Operators and Directives
- Indirect Addressing
- → JMP and LOOP Instructions

Data Transfer Instructions

- Operand Types
- Instruction Operand Notation
- Direct Memory Operands
- MOV Instruction
- Zero & Sign Extension
- XCHG Instruction
- Direct-Offset Instructions

Operand Types

- Immediate a constant integer (8, 16, or 32 bits)
 - value is encoded within the instruction
- Register the name of a register
 - register name is converted to a number and encoded within the instruction
- Memory reference to a location in memory
 - memory address is encoded within the instruction, or a register holds the address of a memory location

Instruction Operand Notation

Operand	Description
reg8	8-bit general-purpose register: AH, AL, BH, BL, CH, CL, DH, DL
reg16	16-bit general-purpose register: AX, BX, CX, DX, SI, DI, SP, BP
reg32	32-bit general-purpose register: EAX, EBX, ECX, EDX, ESI, EDI, ESP, EBP
reg	Any general-purpose register
sreg	16-bit segment register: CS, DS, SS, ES, FS, GS
imm	8-, 16-, or 32-bit immediate value
imm8	8-bit immediate byte value
imm16	16-bit immediate word value
imm32	32-bit immediate doubleword value
reg/mem8	8-bit operand, which can be an 8-bit general register or memory byte
reg/mem16	16-bit operand, which can be a 16-bit general register or memory word
reg/mem32	32-bit operand, which can be a 32-bit general register or memory doubleword
mem	An 8-, 16-, or 32-bit memory operand

Direct Memory Operands

- A direct memory operand is a named reference to storage in memory
- The named reference (label) is automatically dereferenced by the assembler

■ Move from source to destination. Syntax:

MOV destination, source


- No more than one memory operand permitted
- CS, EIP, and IP cannot be the destination
- No immediate to segment moves

```
.data
count BYTE 100
wVal WORD 2
. code
  mov bl, count
  mov ax, wVal
  mov count, al
  mov al, wVal
                           error
  mov ax, count
                           error
  mov eax, count
```

Explain why each of the following MOV statements are invalid:

```
.data
bVal BYTE
             100
bVal2 BYTE
wVal WORD
dVal DWORD 5
. code
                   immediate move to DS not permitted
   mov ds, 45
                   size mismatch
   mov esi, wVal
                  EIP cannot be the destination
   mov eip,dVal
   mov 25,bVal
                   immediate value cannot be destination
   mov bVal2,bVal
                  memory-to-memory move not permitted
```

When you copy a smaller value into a larger destination, the MOVZX instruction fills (extends) the upper half of the destination with zeros.




```
mov bl,10001111b

movzx ax,bl ; zero-extension
```

The destination must be a register.

Sign Extension

The MOVSX instruction fills the upper half of the destination with a copy of the source operand's sign bit.



```
mov bl,10001111b
movsx ax,bl ; sign extension
```

The destination must be a register.

XCHG exchanges the values of two operands. At least one operand must be a register. No immediate operands are permitted.

Direct-Offset Operands

A constant offset is added to a data label to produce an effective address (EA). The address is dereferenced to get the value inside its memory location.

```
.data
arrayB BYTE 10h,20h,30h,40h
.code
mov al,arrayB+1 ; AL = 20h
mov al,[arrayB+1] ; alternative notation
```

Q: Why doesn't arrayB+1 produce 11h?

Direct-Offset Operands (cont)

A constant offset is added to a data label to produce an effective address (EA). The address is dereferenced to get the value inside its memory location.

```
.data
arrayW WORD 1000h,2000h,3000h
arrayD DWORD 1,2,3,4
.code
mov ax,[arrayW+2] ; AX = 2000h
mov ax,[arrayW+4] ; AX = 3000h
mov eax,[arrayD+4] ; EAX = 00000002h
```

Write a program that rearranges the values of three doubleword values in the following array as: 3, 1, 2.

```
.data
arrayD DWORD 1,2,3
```

• Step1: copy the first value into EAX and exchange it with the value in the second position.

```
mov eax,arrayD
xchg eax,[arrayD+4]
```

 Step 2: Exchange EAX with the third array value and copy the value in EAX to the first array position.

```
xchg eax,[arrayD+8]
mov arrayD,eax
```

We want to write a program that adds the following three bytes:

```
.data
myBytes BYTE 80h,66h,0A5h
```

What is your evaluation of the following code?

```
mov al,myBytes
add al,[myBytes+1]
add al,[myBytes+2]
```

• What is your evaluation of the following code?

```
mov ax,myBytes
add ax,[myBytes+1]
add ax,[myBytes+2]
```

Any other possibilities?

Evaluate this . . . (cont)

```
.data
myBytes BYTE 80h,66h,0A5h
```

How about the following code. Is anything missing?

```
movzx ax,myBytes
mov bl,[myBytes+1]
add ax,bx
mov bl,[myBytes+2]
add ax,bx ; AX = sum
```

Yes: Move zero to BX before the MOVZX or mov bl,... instruction. ©

What's Next

- Data Transfer Instructions
- Addition and Subtraction
- Data-Related Operators and Directives
- Indirect Addressing
- → JMP and LOOP Instructions
- ► 64-Bit Programming

Addition and Subtraction

- INC and DEC Instructions
- ADD and SUB Instructions
- → NEG Instruction
- Implementing Arithmetic Expressions
- Flags Affected by Arithmetic
 - Zero
 - Sign
 - Carry
 - Overflow

INC and DEC Instructions

- Add 1, subtract 1 from destination operand
 - operand may be register or memory
- INC destination
 - Logic: destination ← destination + 1
- DEC destination

```
.data
myWord WORD 1000h
myDword DWORD 1000000h
. code
  inc myWord ; 1001h
  dec myWord ; 1000h
  inc myDword ; 10000001h
  mov ax,00FFh
                   ; AX = 0100h
  inc ax
  mov ax,00FFh
                   ; AX = 0000h
  inc al
```

Your turn...

Show the value of the destination operand after each of the following instructions executes:

```
.data
myByte BYTE OFFh, 0
.code

mov al,myByte  ; AL = FFh
mov ah,[myByte+1] ; AH = 00h
dec ah ; AH = FFh
inc al ; AL = 00h
dec ax ; AX = FEFF
```

ADD and SUB Instructions

- ADD destination, source
 - Logic: destination ← destination + source
- SUB destination, source
- Same operand rules as for the MOV instruction

NEG (negate) Instruction

Reverses the sign of an operand. Operand can be a register or memory operand.

Implementing Arithmetic Expressions

HLL compilers translate mathematical expressions into assembly language. You can do it also. For example:

```
Rval = -Xval + (Yval - Zval)
Rval DWORD ?
Xval DWORD 26
Yval DWORD 30
Zval DWORD 40
.code
   mov eax, Xval
                             ; EAX = -26
   neg eax
   mov ebx, Yval
                            ; EBX = -10
   sub ebx, Zval
   add eax, ebx
   mov Rval, eax
                            ; -36
```

Translate the following expression into assembly language. Do not permit Xval, Yval, or Zval to be modified:

```
Rval = Xval - (-Yval + Zval)
```


Assume that all values are signed doublewords.

```
mov ebx, Yval
neg ebx
add ebx, Zval
mov eax, Xval
sub eax, ebx
mov Rval, eax
```

Flags Affected by Arithmetic

- The ALU has a number of status flags that reflect the outcome of arithmetic (and bitwise) operations
 - based on the contents of the destination operand
- Essential flags:
 - Zero flag set when destination equals zero
 - Sign flag set when destination is negative
 - Carry flag set when unsigned value is out of range
 - Overflow flag set when signed value is out of range
- The MOV instruction never affects the flags.

Concept Map



You can use diagrams such as these to express the relationships between assembly language concepts.

The Zero flag is set when the result of an operation produces zero in the destination operand.

Remember...

- A flag is set when it equals 1.
- A flag is clear when it equals 0.

The Sign flag is set when the destination operand is negative. The flag is clear when the destination is positive.

```
mov cx, 0

sub cx, 1

add cx, 2

; CX = -1, SF = 1

; CX = 1, SF = 0
```

The sign flag is a copy of the destination's highest bit:

```
mov al,0

sub al,1

add al,2

; AL = 11111111b, SF = 1

; AL = 00000001b, SF = 0
```

Signed and Unsigned Integers A Hardware Viewpoint

 All CPU instructions operate exactly the same on signed and unsigned integers

The CPU cannot distinguish between signed and unsigned integers

➤ YOU, the programmer, are solely responsible for using the correct data type with each instruction

Overflow and Carry Flags

- A Hardware Viewpoint

 How the ADD instruction affects OF and CF:
 - CF = (carry out of the MSB)
 - → OF = CF XOR MSB
- How the SUB instruction affects OF and CF:
 - CF = INVERT (carry out of the MSB)
 - negate the source and add it to the destination
 - OF = CF XOR MSB

MSB = Most Significant Bit (high-order bit)

XOR = eXclusive-OR operation

NEG = Negate (same as SUB 0,operand)

Carry Flag (CF)

The Carry flag is set when the result of an operation generates an unsigned value that is out of range (too big or too small for the destination operand).

For each of the following marked entries, show the values of the destination operand and the Sign, Zero, and Carry flags:

```
mov ax,00FFh
add ax,1 ; AX=0100h SF=0 ZF=0 CF=0
sub ax,1 ; AX=00FFh SF=0 ZF=0 CF=0
add al,1 ; AL=00h SF=0 ZF=1 CF=1
mov bh,6Ch
add bh,95h ; BH=01h SF=0 ZF=0 CF=1

mov al,2
sub al,3 ; AL=FFh SF=1 ZF=0 CF=1
```

Overflow Flag (OF)

The Overflow flag is set when the signed result of an operation is invalid or out of range.

The two examples are identical at the binary level because 7Fh equals +127. To determine the value of the destination operand, it is often easier to calculate in hexadecimal.

A Rule of Thumb

- When adding two integers, remember that the Overflow flag is only set when . . .
 - Two positive operands are added and their sum is negative
 - Two negative operands are added and their sum is positive

```
What will be the values of the Overflow flag?

mov al,80h
add al,92h
; OF = 1

mov al,-2
add al,+127
; OF = 0
```

What's Next


- Data Transfer Instructions
- Addition and Subtraction
- Data-Related Operators and Directives
- Indirect Addressing
- → JMP and LOOP Instructions
- ► 64-Bit Programming

Data-Related Operators and Directives

- OFFSET Operator
- PTR Operator
- TYPE Operator
- LENGTHOF Operator
- SIZEOF Operator
- ► LABEL Directive

OFFSET Operator

- OFFSET returns the distance in bytes, of a label from the beginning of its enclosing segment
 - Protected mode: 32 bits
 - Real mode: 16 bits



The Protected-mode programs we write use only a single segment (flat memory model).

Let's assume that the data segment begins at 00404000h:

```
.data
bVal BYTE ?
wVal WORD ?
dVal DWORD ?
dVal2 DWORD ?
. code
mov esi, OFFSET bVal ; ESI = 00404000
mov esi, OFFSET wVal ; ESI = 00404001
mov esi, OFFSET dVal ; ESI = 00404003
mov esi, OFFSET dVal2; ESI = 00404007
```

Relating to C/C++

The value returned by OFFSET is a pointer. Compare the following code written for both C++ and assembly language:

```
// C++ version:
char array[1000];
char * p = array;
```

```
; Assembly language:

.data
array BYTE 1000 DUP(?)
.code
mov esi,OFFSET array
```

PTR Operator

Overrides the default type of a label (variable). Provides the flexibility to access part of a variable.

```
.data
myDouble DWORD 12345678h
.code
mov ax,myDouble ; error - why?
mov ax,WORD PTR myDouble ; loads 5678h
mov WORD PTR myDouble,4321h ; saves 4321h
```

Little endian order is used when storing data in memory (see Section 3.4.9).

Little Endian Order

- Little endian order refers to the way Intel stores integers in memory.
- Multi-byte integers are stored in reverse order, with the least significant byte stored at the lowest address
- For example, the doubleword 12345678h would be stored as:

byte	offset		
78	0000		
56	0001		
34	0002		
12	0003		

When integers are loaded from memory into registers, the bytes are automatically re-reversed into their correct positions.

PTR Operator Examples

.data
myDouble DWORD 12345678h

doubleword	word	byte	offset	
12345678	5678	78	0000	myDouble
		56	0001	myDouble + 1
	1234	34	0002	myDouble + 2
		12	0003	myDouble + 3

PTR Operator (cont)

PTR can also be used to combine elements of a smaller data type and move them into a larger operand. The CPU will automatically reverse the bytes.

```
.data
myBytes BYTE 12h,34h,56h,78h

.code
mov ax,WORD PTR [myBytes] ; AX = 3412h
mov ax,WORD PTR [myBytes+2] ; AX = 7856h
mov eax,DWORD PTR myBytes ; EAX = 78563412h
```

Write down the value of each destination operand:

```
.data
varB BYTE 65h,31h,02h,05h
varW WORD 6543h,1202h
varD DWORD 12345678h
```

. code

```
mov ax,WORD PTR [varB+2]; a. 0502hmov bl,BYTE PTR varD; b. 78hmov bl,BYTE PTR [varW+2]; c. 02hmov ax,WORD PTR [varD+2]; d. 1234hmov eax,DWORD PTR varW; e. 12026543h
```