

02 – Arrays

CS1022 – Introduction to Computing II

Dr Adam Taylor / adam.taylor@tcd.ie School of Computer Science and Statistics Nothing very new here ... we have already been using arrays!

Array – an ordered collection of elements stored sequentially in memory

e.g. integers, ASCII characters, lottery numbers

Homogeneous elements?

(at least with respect to size)

Dimension: number of elements in array

Address	Memory	Index
0xA000101C	??????	
0×A0001018	31	5
0×A0001014	28	4
0×A0001010	127	3
0×A000100C	9	2
0×A0001008	28	1
0×A0001004	3	0
0×A0001000	??????	
0xA0000FFC	??????	
	• • •	
	→ 32 bits = 1 word →	

Efficient access at a specific index is an important feature of arrays

Referred to as "random access"

Example: retrieve the 4th element (index=3) of an array of words

Step 1: translate array index into byte offset from start address of array in memory


```
<br/><br/>byte offset> = <index> × <elem size>
```

Step 2: add byte offset to array base address to access element

<address> = <array start address> + <byte offset>

Efficient random access using Scaled Register Offset addressing mode:

Generally CPU speed increases much faster than memory access speed Relatively speaking, memory is getting slower*



Memory speed lags behind CPU speed

Déjà Vu!

```
LDR R1, =myArray; start address of myArray
LDR R0, =0; sum = 0
LDR R4, =0; count = 0


whSum CMP R4, #10; while (count < 10)
BHS eWhSum; {
LDR R6, [R1, R4, LSL #2]; num = myArray[count]
ADD R0, R0, R6; sum = sum + num
ADD R4, R4, #1; count = count + 1
B whSum; }
eWhSum;
```

The pseudo-code comments have changed but the program is identical (See Addressing Modes)

Arrays can have more than one dimension

e.g. a two-dimensional array – analogous to a table containing elements arranged in rows and columns

Stored in memory by mapping the 2D array into 1D memory, e.g.



 $a_{0,3}$

 $a_{0,2}$


 $a_{0,1}$

 $a_{0,0}$

 $a_{1,0}$

Row-major order: 2D array is stored in memory by storing each row contiguously in memory

Column-major order: 2D array is stored in memory by storing each column contiguously in memory (in image)



2D array declared in memory

```
AREA TestData, DATA, READWRITE

col_size EQU 6  ; just for convenience, not required row_size EQU 8  ; just for convenience, not required array DCD 6, 3, 8, 2, 5, 2, 9, 1 ; row 0

DCD 3, 7, 2, 8, 5, 7, 2, 7 ; row 1

DCD 2, 4, 7, 4, 2, 6, 7, 4 ; row 2

DCD 1, 9, 3, 2, 9, 5, 6, 8 ; row 3

DCD 7, 5, 3, 7, 5, 8, 2, 1 ; row 4

DCD 6, 4, 8, 9, 0, 3, 2, 5 ; row 5
```

... or equivalently ...

AREA TestData, DATA, READWRITE

Example: retrieve the element at the 4th row and 3rd column of a 2D array of words with 6 rows and 8 columns – array[3][2]

Step 1: translate 2D array index into 1D array index

Step 2: translate 1D array index into byte offset from start address of array in memory

Step 3: add byte offset to array base address to access element

Example: retrieve the element at the 4th row and 3rd column of a 2D array of words with 6 rows and 8 columns – array[3][2]

```
LDR r4, =array ; pArr = address of array start
LDR r5, =col size; load col size
LDR r6, =row size; load row size
; looking for array[3][2] (4th row, 3rd column)
LDR r1, =3; row = 3
LDR r2, =2; col = 4
; <byte offset> = ((row * <row size>) + col) * <elem size>
MUL r7, r1, r6; index = row * row size
ADD r7, r7, r2; index = index + col
LDR r0, [r4, r7, LSL #2]; elem = Memory.Word[pArr + (index*4)]
```

e.g. a 3D array of size sz×sy×sx

In general, the index of element a[z][y][x] is:

$$index = ((z \times sy \times sx) + (y \times sx) + x)$$

e.g. a 4D array of size sz×sy×sx×sw

In general, the index of element a[z][y][x][w] is:

$$index = ((z \times sy \times sx \times sw) + (y \times sx \times sw) + (x \times sw) + w)$$

Warning: an array of bytes with odd dimensions may cause the data following the array to be odd aligned, requiring padding of one byte (similarly for half-words)