vdsf API Reference Manual 0.1.0

Generated by Doxygen 1.4.7

Mon Nov 26 16:33:48 2007

CONTENTS 1

		4		4
\mathbf{C}	Λn	ıtα	n	tc
		ııı		LO

1 vdsf API Module Index	1
2 vdsf API Directory Hierarchy	1
3 vdsf API Data Structure Index	2
4 vdsf API File Index	2
5 vdsf API Module Documentation	3
6 vdsf API Directory Documentation	21
7 vdsf API Data Structure Documentation	23
8 vdsf API File Documentation	27
1 vdsf API Module Index	
1.1 vdsf API Modules	
Here is a list of all modules:	
API functions for vdsf folders.	3
API functions for vdsf hash maps.	5

11

12

16

2 vdsf API Directory Hierarchy

API functions for vdsf processes.

API functions for vdsf sessions.

API functions for vdsf FIFO queues.

2.1 vdsf API Directories

This directory hierarchy is sorted roughly, but not completely, alphabetically:

2	$\mathbf{v}\mathbf{d}\mathbf{c}\mathbf{f}$	A DI	Data	Structure	Indov

2

src	22
include	2
vdsf	22

3 vdsf API Data Structure Index

3.1 vdsf API Data Structures

Here are the data structures with brief descriptions:

vdsFolderEntry (This data structure is used to iterate throught all objects in a folder)

23
vdsInfo (This data structure is used to retrieve the status of the virtual data space)

24
vdsObjStatus (This data structure is used to retrieve the status of objects) 25

4 vdsf API File Index

4.1 vdsf API File List

Here is a list of all files with brief descriptions:

/home/project/VDSF/vdsf/trunk/src/include/vdsf/vds.h	27
/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsCommon.h	27
/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsErrors.h	30
/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsFolder.h (This file provides the API needed to access a VDSF folder)	34
/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsHashMap.h (This file provides the API needed to access a VDSF hash map)	35
/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsProcess.h (This file provides the API functions for vdsf processes)	36
/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsQueue.h (This file provides the API needed to access a VDSF FIFO queue)	37

/home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsSession.h (This file provides the API needed to create and use a session) 38

5 vdsf API Module Documentation

5.1 API functions for vdsf folders.

Functions

- VDSF_EXPORT int vdsFolderClose (VDS_HANDLE objectHandle) Close a folder.
- VDSF_EXPORT int vdsFolderGetFirst (VDS_HANDLE objectHandle, vds-FolderEntry *pEntry)

Iterate through the folder - no data items are removed from the folder by this function.

VDSF_EXPORT int vdsFolderGetNext (VDS_HANDLE objectHandle, vds-FolderEntry *pEntry)

Iterate through the folder.

 VDSF_EXPORT int vdsFolderOpen (VDS_HANDLE sessionHandle, const char *folderName, size_t nameLengthInBytes, VDS_HANDLE *object-Handle)

Open an existing folder (see vdsCreateObject to create a new folder).

 VDSF_EXPORT int vdsFolderStatus (VDS_HANDLE objectHandle, vdsObj-Status *pStatus)

Return the status of the folder.

5.1.1 Function Documentation

5.1.1.1 VDSF_EXPORT int vdsFolderClose (VDS_HANDLE objectHandle)

Close a folder.

This function terminates the current access to the folder in shared memory (the folder itself is untouched).

Parameters:

← *objectHandle* The handle to the folder (see vdsFolderOpen).

Returns:

0 on success or a vdsErrors on error.

5.1.1.2 VDSF_EXPORT int vdsFolderGetFirst (VDS_HANDLE objectHandle, vdsFolderEntry * pEntry)

Iterate through the folder - no data items are removed from the folder by this function.

Data items which were added by another session and are not yet committed will not be seen by the iterator. Likewise, destroyed data items (even if not yet committed) are invisible.

Parameters:

- ← *objectHandle* The handle to the folder (see vdsFolderOpen).
- \rightarrow *pEntry* The data structure provided by the user to hold the content of each item in the folder. Memory allocation for this buffer is the responsability of the caller.

Returns:

0 on success or a vdsErrors on error.

5.1.1.3 VDSF_EXPORT int vdsFolderGetNext (VDS_HANDLE objectHandle, vdsFolderEntry * pEntry)

Iterate through the folder.

Data items which were added by another session and are not yet committed will not be seen by the iterator. Likewise, destroyed data items (even if not yet committed) are invisible.

Evidently, you must call vdsFolderGetFirst to initialize the iterator.

Parameters:

- ← *objectHandle* The handle to the folder (see vdsFolderOpen).
- → pEntry The data structure provided by the user to hold the content of each item in the folder. Memory allocation for this buffer is the responsability of the caller.

Returns:

0 on success or a vdsErrors on error.

5.1.1.4 VDSF_EXPORT int vdsFolderOpen (VDS_HANDLE sessionHandle, const char * folderName, size_t nameLengthInBytes, VDS_HANDLE * object-Handle)

Open an existing folder (see vdsCreateObject to create a new folder).

Parameters:

- ← sessionHandle The handle to the current session.
- ← *folderName* The fully qualified name of the folder.
- ← *nameLengthInBytes* The length of *folderName* (in bytes) not counting the null terminator (null-terminators are not used by the vdsf engine).
- → *objectHandle* The handle to the folder, allowing us access to the folder in shared memory. On error, this handle will be set to zero (NULL) unless the objectHandle pointer itself is NULL.

Returns:

0 on success or a vdsErrors on error.

5.1.1.5 VDSF_EXPORT int vdsFolderStatus (VDS_HANDLE objectHandle, vdsObjStatus * pStatus)

Return the status of the folder.

Parameters:

- ← *objectHandle* The handle to the folder (see vdsFolderOpen).
- \rightarrow *pStatus* A pointer to the status structure.

Returns:

0 on success or a vdsErrors on error.

5.2 API functions for vdsf hash maps.

5.2.1 Detailed Description

Hash maps use unique keys - the data items are not sorted.

Functions

VDSF_EXPORT int vdsHashMapClose (VDS_HANDLE objectHandle)
 Close a Hash Map.

 VDSF_EXPORT int vdsHashMapDelete (VDS_HANDLE objectHandle, const void *key, size_t keyLength)

Remove the data item identified by the given key from the hash map.

 VDSF_EXPORT int vdsHashMapGet (VDS_HANDLE objectHandle, const void *key, size_t keyLength, void *buffer, size_t bufferLength, size_t *returned-Length)

Retrieve the data item identified by the given key from the hash map.

 VDSF_EXPORT int vdsHashMapGetFirst (VDS_HANDLE objectHandle, void *key, size_t keyLength, void *buffer, size_t bufferLength, size_t *retKeyLength, size_t *retDataLength)

Iterate through the hash map.

 VDSF_EXPORT int vdsHashMapGetNext (VDS_HANDLE objectHandle, void *key, size_t keyLength, void *buffer, size_t bufferLength, size_t *retKeyLength, size_t *retDataLength)

Iterate through the hash map.

 VDSF_EXPORT int vdsHashMapInsert (VDS_HANDLE objectHandle, const void *key, size_t keyLength, const void *data, size_t dataLength)

Insert a data element in the hash map.

 VDSF_EXPORT int vdsHashMapOpen (VDS_HANDLE sessionHandle, const char *hashMapName, size_t nameLengthInBytes, VDS_HANDLE *object-Handle)

Open an existing hash map (see vdsCreateObject to create a new object).

- VDSF_EXPORT int vdsHashMapReplace (VDS_HANDLE objectHandle, const void *key, size_t keyLength, const void *data, size_t dataLength)
 - Replace a data element in the hash map.
- VDSF_EXPORT int vdsHashMapStatus (VDS_HANDLE objectHandle, vds-ObjStatus *pStatus)

Return the status of the hash map.

5.2.2 Function Documentation

5.2.2.1 VDSF_EXPORT int vdsHashMapClose (VDS_HANDLE objectHandle)

Close a Hash Map.

This function terminates the current access to the hash map in shared memory (the hash map itself is untouched).

Warning:

Closing an object does not automatically commit or rollback data items that were inserted or removed. You still must use either vdsCommit or vdsRollback to end the current unit of work.

Parameters:

← *objectHandle* The handle to the hash map (see vdsHashMapOpen).

Returns:

0 on success or a vdsErrors on error.

5.2.2.2 VDSF_EXPORT int vdsHashMapDelete (VDS_HANDLE objectHandle, const void * key, size_t keyLength)

Remove the data item identified by the given key from the hash map.

Data items which were added by another session and are not yet committed will not be seen by this function and cannot be removed. Likewise, destroyed data items (even if not yet committed) are invisible.

The removals only become permanent after a call to vdsCommit.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- \leftarrow key The key of the item to be removed.
- \leftarrow *keyLength* The length of the *key* buffer (in bytes).

Returns:

0 on success or a vdsErrors on error.

5.2.2.3 VDSF_EXPORT int vdsHashMapGet (VDS_HANDLE objectHandle, const void * key, size_t keyLength, void * buffer, size_t bufferLength, size_t * returnedLength)

Retrieve the data item identified by the given key from the hash map.

Data items which were added by another session and are not yet committed will not be seen by this function. Likewise, destroyed data items (even if not yet committed) are invisible.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- \leftarrow key The key of the item to be retrieved.
- \leftarrow *keyLength* The length of the *key* buffer (in bytes).
- \rightarrow *buffer* The buffer provided by the user to hold the content of the data item. Memory allocation for this buffer is the responsability of the caller.
- \leftarrow *bufferLength* The length of *buffer* (in bytes).
- → returnedLength The actual number of bytes in the data item.

Returns:

0 on success or a vdsErrors on error.

5.2.2.4 VDSF_EXPORT int vdsHashMapGetFirst (VDS_HANDLE object-Handle, void * key, size_t keyLength, void * buffer, size_t bufferLength, size_t * retKeyLength, size_t * retDataLength)

Iterate through the hash map.

Data items which were added by another session and are not yet committed will not be seen by the iterator. Likewise, destroyed data items (even if not yet committed) are invisible.

Data items retrieved this way will not be sorted.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- \rightarrow key The key buffer provided by the user to hold the content of the key associated with the first element. Memory allocation for this buffer is the responsability of the caller.
- \leftarrow *keyLength* The length of the *key* buffer (in bytes).
- \rightarrow *buffer* The buffer provided by the user to hold the content of the first element. Memory allocation for this buffer is the responsability of the caller.
- ← bufferLength The length of buffer (in bytes).
- → retKeyLength The actual number of bytes in the key
- \rightarrow retDataLength The actual number of bytes in the data item.

Returns:

0 on success or a vdsErrors on error.

5.2.2.5 VDSF_EXPORT int vdsHashMapGetNext (VDS_HANDLE object-Handle, void * key, size_t keyLength, void * buffer, size_t bufferLength, size_t * retKeyLength, size_t * retDataLength)

Iterate through the hash map.

Data items which were added by another session and are not yet committed will not be seen by the iterator. Likewise, destroyed data items (even if not yet committed) are invisible.

Evidently, you must call vdsHashMapGetFirst to initialize the iterator. Not so evident - calling vdsHashMapGet will reset the iteration to the data item retireved by this function (they use the same internal storage). If this cause a problem, please let us know.

Data items retrieved this way will not be sorted.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- → key The key buffer provided by the user to hold the content of the key associated with the data element. Memory allocation for this buffer is the responsability of the caller.
- \leftarrow *keyLength* The length of the *key* buffer (in bytes).
- \rightarrow *buffer* The buffer provided by the user to hold the content of the data element. Memory allocation for this buffer is the responsability of the caller.
- ← *bufferLength* The length of *buffer* (in bytes).
- → retKeyLength The actual number of bytes in the key
- \rightarrow retDataLength The actual number of bytes in the data item.

Returns:

0 on success or a vdsErrors on error.

5.2.2.6 VDSF_EXPORT int vdsHashMapInsert (VDS_HANDLE objectHandle, const void * key, size_t keyLength, const void * data, size_t dataLength)

Insert a data element in the hash map.

The additions only become permanent after a call to vdsCommit.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- \leftarrow key The key of the item to be inserted.
- ← keyLength The length of the key buffer (in bytes).
- \leftarrow *data* The data item to be inserted.

 \leftarrow *dataLength* The length of *data* (in bytes).

Returns:

0 on success or a vdsErrors on error.

5.2.2.7 VDSF_EXPORT int vdsHashMapOpen (VDS_HANDLE sessionHandle, const char * hashMapName, size_t nameLengthInBytes, VDS_HANDLE * object-Handle)

Open an existing hash map (see vdsCreateObject to create a new object).

Parameters:

- ← sessionHandle The handle to the current session.
- ← *hashMapName* The fully qualified name of the hash map.
- ← nameLengthInBytes The length of hashMapName (in bytes) not counting the null terminator (null-terminators are not used by the vdsf engine).
- → objectHandle The handle to the hash map, allowing us access to the map in shared memory. On error, this handle will be set to zero (NULL) unless the objectHandle pointer itself is NULL.

Returns:

0 on success or a vdsErrors on error.

5.2.2.8 VDSF_EXPORT int vdsHashMapReplace (VDS_HANDLE object-Handle, const void * key, size_t keyLength, const void * data, size_t dataLength)

Replace a data element in the hash map.

The replacements only become permanent after a call to vdsCommit.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- \leftarrow key The key of the item to be replaced.
- \leftarrow *keyLength* The length of the *key* buffer (in bytes).
- ← data The new data item that will replace the previous data.
- ← *dataLength* The length of *data* (in bytes).

Returns:

0 on success or a vdsErrors on error.

5.2.2.9 VDSF_EXPORT int vdsHashMapStatus (VDS_HANDLE objectHandle, vdsObjStatus * pStatus)

Return the status of the hash map.

Parameters:

- ← *objectHandle* The handle to the hash map (see vdsHashMapOpen).
- \rightarrow *pStatus* A pointer to the status structure.

Returns:

0 on success or a vdsErrors on error.

5.3 API functions for vdsf processes.

Functions

- VDSF_EXPORT void vdsExit ()
 This function terminates all access to the VDS.
- VDSF_EXPORT int vdsInit (const char *wdAddress, int protectionNeeded)
 This function initializes access to a VDS.

5.3.1 Function Documentation

5.3.1.1 VDSF_EXPORT void vdsExit ()

This function terminates all access to the VDS.

This function will also close all sessions and terminate all accesses to the different objects.

This function takes no argument and always end successfully (even if called twice or if vdsInit was not called).

5.3.1.2 VDSF_EXPORT int vdsInit (const char * wdAddress, int protection-Needed)

This function initializes access to a VDS.

It takes 2 input arguments, the address of the watchdog and an integer (used as a boolean, 0 for false, 1 for true) to indicate if sessions and other objects (Queues, etc) are shared amongst threads (in the current process) and must be protected. Recommendation: always set protectionNeeded to 0 (false) unless you cannot do otherwise. In other words it is recommended to use one session handle for each thread. Also if

the same queue needs to be accessed by two threads it is more efficient to have two different handles instead of sharing a single one.

[Additional note: API objects (or C handles) are just proxies for the real objects sitting in shared memory. Proper synchronization is already done in shared memory and it is best to avoid to synchronize these proxy objects.]

Upon successful completion, the process handle is set. Otherwise the error code is returned.

Parameters:

- ← wdAddress The address of the watchdog. Currently a string with the port number ("12345").
- protectionNeeded A boolean value indicating if multi-threaded locks are needed or not.

Returns:

0 on success or a vdsErrors on error.

5.4 API functions for vdsf FIFO queues.

5.4.1 Detailed Description

A reminder: FIFO, First In First Out.

Data items are placed at the end of the queue and retrieved from the beginning of the queue.

Functions

- VDSF_EXPORT int vdsQueueClose (VDS_HANDLE objectHandle) Close a FIFO queue.
- VDSF_EXPORT int vdsQueueGetFirst (VDS_HANDLE objectHandle, void *buffer, size_t bufferLength, size_t *returnedLength)

Iterate through the queue - no data items are removed from the queue by this function.

 VDSF_EXPORT int vdsQueueGetNext (VDS_HANDLE objectHandle, void *buffer, size_t bufferLength, size_t *returnedLength)

Iterate through the queue - no data items are removed from the queue by this function.

• VDSF_EXPORT int vdsQueueOpen (VDS_HANDLE sessionHandle, const char *queueName, size_t nameLengthInBytes, VDS_HANDLE *object-Handle)

Open an existing FIFO queue (see vdsCreateObject to create a new queue).

• VDSF_EXPORT int vdsQueuePop (VDS_HANDLE objectHandle, void *buffer, size_t bufferLength, size_t *returnedLength)

Remove the first item from the beginning of a FIFO queue and return it to the caller.

 VDSF_EXPORT int vdsQueuePush (VDS_HANDLE objectHandle, const void *pItem, size_t length)

Insert a data element at the end of the FIFO queue.

 VDSF_EXPORT int vdsQueueStatus (VDS_HANDLE objectHandle, vdsObj-Status *pStatus)

Return the status of the queue.

5.4.2 Function Documentation

5.4.2.1 VDSF_EXPORT int vdsQueueClose (VDS_HANDLE objectHandle)

Close a FIFO queue.

This function terminates the current access to the queue in shared memory (the queue itself is untouched).

Warning:

Closing an object does not automatically commit or rollback data items that were inserted or removed. You still must use either vdsCommit or vdsRollback to end the current unit of work.

Parameters:

← *objectHandle* The handle to the queue (see vdsQueueOpen).

Returns:

0 on success or a vdsErrors on error.

5.4.2.2 VDSF_EXPORT int vdsQueueGetFirst (VDS_HANDLE objectHandle, void * buffer, size_t bufferLength, size_t * returnedLength)

Iterate through the queue - no data items are removed from the queue by this function.

Data items which were added by another session and are not yet committed will not be seen by the iterator. Likewise, destroyed data items (even if not yet committed) are invisible.

Parameters:

- ← *objectHandle* The handle to the queue (see vdsQueueOpen).
- → *buffer* The buffer provided by the user to hold the content of the first element. Memory allocation for this buffer is the responsability of the caller.
- ← bufferLength The length of buffer (in bytes).
- → returnedLength The actual number of bytes in the data item.

Returns:

0 on success or a vdsErrors on error.

5.4.2.3 VDSF_EXPORT int vdsQueueGetNext (VDS_HANDLE objectHandle, void * buffer, size_t bufferLength, size_t * returnedLength)

Iterate through the queue - no data items are removed from the queue by this function.

Data items which were added by another session and are not yet committed will not be seen by the iterator. Likewise, destroyed data items (even if not yet committed) are invisible.

Evidently, you must call vdsQueueGetFirst to initialize the iterator. Not so evident - calling vdsQueuePop will reset the iteration to the last element (they use the same internal storage). If this cause a problem, please let us know.

Parameters:

- ← *objectHandle* The handle to the queue (see vdsQueueOpen).
- \rightarrow *buffer* The buffer provided by the user to hold the content of the next element. Memory allocation for this buffer is the responsability of the caller.
- ← bufferLength The length of buffer (in bytes).
- → returnedLength The actual number of bytes in the data item.

Returns:

0 on success or a vdsErrors on error.

5.4.2.4 VDSF_EXPORT int vdsQueueOpen (VDS_HANDLE sessionHandle, const char * queueName, size_t nameLengthInBytes, VDS_HANDLE * object-Handle)

Open an existing FIFO queue (see vdsCreateObject to create a new queue).

Parameters:

← sessionHandle The handle to the current session.

- \leftarrow *queueName* The fully qualified name of the queue.
- ← *nameLengthInBytes* The length of *queueName* (in bytes) not counting the null terminator (null-terminators are not used by the vdsf engine).
- → *objectHandle* The handle to the queue, allowing us access to the queue in shared memory. On error, this handle will be set to zero (NULL) unless the objectHandle pointer itself is NULL.

Returns:

0 on success or a vdsErrors on error.

5.4.2.5 VDSF_EXPORT int vdsQueuePop (VDS_HANDLE objectHandle, void * buffer, size_t bufferLength, size_t * returnedLength)

Remove the first item from the beginning of a FIFO queue and return it to the caller.

Data items which were added by another session and are not yet committed will not be seen by this function. Likewise, destroyed data items (even if not yet committed) are invisible.

The removals only become permanent after a call to vdsCommit.

Parameters:

- ← *objectHandle* The handle to the queue (see vdsQueueOpen).
- \rightarrow *buffer* The buffer provided by the user to hold the content of the data item. Memory allocation for this buffer is the responsability of the caller.
- ← bufferLength The length of buffer (in bytes).
- → returnedLength The actual number of bytes in the data item.

Returns:

0 on success or a vdsErrors on error.

5.4.2.6 VDSF_EXPORT int vdsQueuePush (VDS_HANDLE objectHandle, const void * pItem, size_t length)

Insert a data element at the end of the FIFO queue.

The additions only become permanent after a call to vdsCommit.

Parameters:

- ← *objectHandle* The handle to the queue (see vdsQueueOpen).
- \leftarrow *pItem* The data item to be inserted.

 \leftarrow *length* The length of *pItem* (in bytes).

Returns:

0 on success or a vdsErrors on error.

5.4.2.7 VDSF_EXPORT int vdsQueueStatus (VDS_HANDLE objectHandle, vdsObjStatus * pStatus)

Return the status of the queue.

Parameters:

- ← *objectHandle* The handle to the queue (see vdsQueueOpen).
- \rightarrow *pStatus* A pointer to the status structure.

Returns:

0 on success or a vdsErrors on error.

5.5 API functions for vdsf sessions.

Functions

- VDSF_EXPORT int vdsCommit (VDS_HANDLE sessionHandle)
 - Commit all insertions and deletions (of the current session) executed since the previous call to vdsCommit or vdsRollback.
- VDSF_EXPORT int vdsCreateObject (VDS_HANDLE sessionHandle, const char *objectName, size_t nameLengthInBytes, vdsObjectType objectType)

Create a new object in shared memory.

 VDSF_EXPORT int vdsDestroyObject (VDS_HANDLE sessionHandle, const char *objectName, size_t nameLengthInBytes)

Destroy an existing object in shared memory.

 VDSF_EXPORT int vdsErrorMsg (VDS_HANDLE sessionHandle, char *message, size_t msgLengthInBytes)

Return the error message associated with the last error(s).

• VDSF_EXPORT int vdsExitSession (VDS_HANDLE sessionHandle)

Terminate the current session.

VDSF_EXPORT int vdsGetInfo (VDS_HANDLE sessionHandle, vdsInfo *p-Info)

Return information on the current status of the VDS (Virtual Data Space).

 VDSF_EXPORT int vdsGetStatus (VDS_HANDLE sessionHandle, const char *objectName, size_t nameLengthInBytes, vdsObjStatus *pStatus)

Return the status of the named object.

vious call to vdsCommit or vdsRollback.

- VDSF_EXPORT int vdsInitSession (VDS_HANDLE *sessionHandle)
 This function initializes a session.
- VDSF_EXPORT int vdsLastError (VDS_HANDLE sessionHandle)
 Return the last error seen in previous calls (of the current session).
- VDSF_EXPORT int vdsRollback (VDS_HANDLE sessionHandle)
 Rollback all insertions and deletions (of the current session) executed since the pre-

5.5.1 Function Documentation

5.5.1.1 VDSF_EXPORT int vdsCommit (VDS_HANDLE sessionHandle)

Commit all insertions and deletions (of the current session) executed since the previous call to vdsCommit or vdsRollback.

Insertions and deletions subjected to this call include both data items inserted and deleted from data containers (maps, etc.) and objects themselves created with vds-CreateObj and/or destroyed with vdsDestroyObj.

Note: the internal calls executed by the engine to satisfy this request cannot fail. As such, you cannot find yourself with an ugly situation where some operations were committed and others not. If an error is returned by this function, nothing was committed.

Parameters:

← sessionHandle Handle to the current session.

Returns:

0 on success or a vdsErrors on error.

5.5.1.2 VDSF_EXPORT int vdsCreateObject (VDS_HANDLE sessionHandle, const char * objectName, size_t nameLengthInBytes, vdsObjectType objectType)

Create a new object in shared memory.

The creation of the object only becomes permanent after a call to vdsCommit.

This function does not provide a handle to the newly created object. Use vdsQueue-Open and similar functions to get the handle.

Parameters:

- ← sessionHandle Handle to the current session.
- ← *objectName* The fully qualified name of the object.
- ← *nameLengthInBytes* The length of *objectName* (in bytes) not counting the null terminator (null-terminators are not used by the vdsf engine).
- ← *objectType* The type of object to create (folder, queue, etc.).

Returns:

0 on success or a vdsErrors on error.

5.5.1.3 VDSF_EXPORT int vdsDestroyObject (VDS_HANDLE sessionHandle, const char * objectName, size_t nameLengthInBytes)

Destroy an existing object in shared memory.

The destruction of the object only becomes permanent after a call to vdsCommit.

Parameters:

- ← sessionHandle Handle to the current session.
- ← *objectName* The fully qualified name of the object.
- ← *nameLengthInBytes* The length of *objectName* (in bytes) not counting the null terminator (null-terminators are not used by the vdsf engine).

Returns:

0 on success or a vdsErrors on error.

5.5.1.4 VDSF_EXPORT int vdsErrorMsg (VDS_HANDLE sessionHandle, char * message, size_t msgLengthInBytes)

Return the error message associated with the last error(s).

If the length of the error message is greater than the length of the provided buffer, the error message will be truncated to fit in the provided buffer.

Caveat, some basic errors cannot be captured, if the provided handles (session handles or object handles) are incorrect (NULL, for example). Without a proper handle, the code cannot know where to store the error...

Parameters:

- \leftarrow sessionHandle Handle to the current session.
- → *message* Buffer for the error message. Memory allocation for this buffer is the responsability of the caller.
- ← msgLengthInBytes The length of message (in bytes). Must be at least 32 bytes.

Returns:

0 on success or a vdsErrors on error.

5.5.1.5 VDSF_EXPORT int vdsExitSession (VDS_HANDLE sessionHandle)

Terminate the current session.

An implicit call to vdsRollback is executed by this function.

Once this function is executed, attempts to use the session handle might lead to memory violation (and, possibly, crashes).

Parameters:

← sessionHandle Handle to the current session.

Returns:

0 on success or a vdsErrors on error.

5.5.1.6 VDSF_EXPORT int vdsGetInfo (VDS_HANDLE sessionHandle, vdsInfo * pInfo)

Return information on the current status of the VDS (Virtual Data Space).

The fetched information is mainly about the current status of the memory allocator.

Parameters:

- ← sessionHandle Handle to the current session.
- \rightarrow *pInfo* A pointer to the vdsInfo structure.

Returns:

0 on success or a vdsErrors on error.

5.5.1.7 VDSF_EXPORT int vdsGetStatus (VDS_HANDLE sessionHandle, const char * objectName, size_t nameLengthInBytes, vdsObjStatus * pStatus)

Return the status of the named object.

Parameters:

- ← sessionHandle Handle to the current session.
- ← *objectName* The fully qualified name of the object.
- ← *nameLengthInBytes* The length of *objectName* (in bytes) not counting the null terminator (null-terminators are not used by the vdsf engine).
- → pStatus A pointer to the vdsObjStatus structure.

Returns:

0 on success or a vdsErrors on error.

5.5.1.8 VDSF_EXPORT int vdsInitSession (VDS_HANDLE * sessionHandle)

This function initializes a session.

It takes one output argument, the session handle.

Upon successful completion, the session handle is set and the function returns zero. Otherwise the error code is returned and the handle is set to NULL.

This function will also initiate a new transaction.

Upon normal termination, the current transaction is rolled back. You MUST explicitly call vdseCommit to save your changes.

Parameters:

 \rightarrow sessionHandle The handle to the newly created session.

Returns:

0 on success or a vdsErrors on error.

5.5.1.9 VDSF_EXPORT int vdsLastError (VDS_HANDLE sessionHandle)

Return the last error seen in previous calls (of the current session).

Caveat, some basic errors cannot be captured, if the provided handles (session handles or object handles) are incorrect (NULL, for example). Without a proper handle, the code cannot know where to store the error...

Parameters:

← sessionHandle Handle to the current session.

Returns:

The last error.

5.5.1.10 VDSF_EXPORT int vdsRollback (VDS_HANDLE sessionHandle)

Rollback all insertions and deletions (of the current session) executed since the previous call to vdsCommit or vdsRollback.

Insertions and deletions subjected to this call include both data items inserted and deleted from data containers (maps, etc.) and objects themselves created with vds-CreateObj and/or destroyed with vdsDestroyObj.

Note: the internal calls executed by the engine to satisfy this request cannot fail. As such, you cannot find yourself with an ugly situation where some operations were roll-backed and others not. If an error is returned by this function, nothing was rollbacked.

Parameters:


← sessionHandle Handle to the current session.

Returns:

0 on success or a vdsErrors on error.

6 vdsf API Directory Documentation

6.1 /home/project/VDSF/vdsf/trunk/src/include/ Directory Reference



Directories

directory vdsf

6.2 /home/project/VDSF/vdsf/trunk/src/ Directory Reference



Directories

• directory include

6.3 /home/project/VDSF/vdsf/trunk/src/include/vdsf/ Directory Reference



Files

- file vds.h
- file vdsCommon.h
- file vdsErrors.h
- file vdsFolder.h

This file provides the API needed to access a VDSF folder.

• file vdsHashMap.h

This file provides the API needed to access a VDSF hash map.

• file vdsProcess.h

This file provides the API functions for vdsf processes.

• file vdsQueue.h

This file provides the API needed to access a VDSF FIFO queue.

• file vdsSession.h

This file provides the API needed to create and use a session.

7 vdsf API Data Structure Documentation

7.1 vdsFolderEntry Struct Reference

#include <vdsCommon.h>

7.1.1 Detailed Description

This data structure is used to iterate throught all objects in a folder.

Note: the actual name of an object (and the length of this name) might vary if you are using different locales (internally, names are stored as wide characters (4 bytes)).

Data Fields

- vdsObjectType type

 The object type.
- int status

Status (created but not committed, etc.

• size_t nameLengthInBytes

The actual length of the name of the object.

• char name [VDS_MAX_NAME_LENGTH *4]

The name of the object.

7.1.2 Field Documentation

7.1.2.1 char vdsFolderEntry::name[VDS_MAX_NAME_LENGTH *4]

The name of the object.

$7.1.2.2 \quad size_t \ vdsFolderEntry::nameLengthInBytes$

The actual length of the name of the object.

7.1.2.3 int vdsFolderEntry::status

Status (created but not committed, etc.

) - not used in version 0.1

7.1.2.4 vdsObjectType vdsFolderEntry::type

The object type.

The documentation for this struct was generated from the following file:

• /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsCommon.h

7.2 vdsInfo Struct Reference

#include <vdsCommon.h>

7.2.1 Detailed Description

This data structure is used to retrieve the status of the virtual data space.

Data Fields

• size_t totalSizeInBytes

Total size of the virtual data space.

• size_t allocatedSizeInBytes

Total size of the allocated blocks.

• size_t numObjects

Number of API objects in the vds (internal objects are not counted).

• size_t numGroups

Total number of groups of blocks.

• size_t numMallocs

Number of calls to allocate groups of blocks.

• size t numFrees

Number of calls to free groups of blocks.

• size_t largestFreeInBytes

Largest contiguous group of free blocks.

7.2.2 Field Documentation

7.2.2.1 size_t vdsInfo::allocatedSizeInBytes

Total size of the allocated blocks.

7.2.2.2 size_t vdsInfo::largestFreeInBytes

Largest contiguous group of free blocks.

7.2.2.3 size_t vdsInfo::numFrees

Number of calls to free groups of blocks.

7.2.2.4 size_t vdsInfo::numGroups

Total number of groups of blocks.

7.2.2.5 size_t vdsInfo::numMallocs

Number of calls to allocate groups of blocks.

7.2.2.6 size_t vdsInfo::numObjects

Number of API objects in the vds (internal objects are not counted).

7.2.2.7 size_t vdsInfo::totalSizeInBytes

Total size of the virtual data space.

The documentation for this struct was generated from the following file:

• /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsCommon.h

7.3 vdsObjStatus Struct Reference

#include <vdsCommon.h>

7.3.1 Detailed Description

This data structure is used to retrieve the status of objects.

Data Fields

vdsObjectType type

The object type.

• int status

Status (created but not committed, etc.

• size_t numBlocks

The number of blocks allocated to this object.

• size_t numBlockGroup

The number of groups of blocks allocated to this object.

• size t numDataItem

The number of data items in thisa object.

size_t freeBytes

The amount of free space available in the blocks allocated to this object.

7.3.2 Field Documentation

7.3.2.1 size_t vdsObjStatus::freeBytes

The amount of free space available in the blocks allocated to this object.

7.3.2.2 size_t vdsObjStatus::numBlockGroup

The number of groups of blocks allocated to this object.

7.3.2.3 size_t vdsObjStatus::numBlocks

The number of blocks allocated to this object.

7.3.2.4 size_t vdsObjStatus::numDataItem

The number of data items in thisa object.

7.3.2.5 int vdsObjStatus::status

Status (created but not committed, etc.

) - not used in version 0.1

7.3.2.6 vdsObjectType vdsObjStatus::type

The object type.

The documentation for this struct was generated from the following file:


• /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsCommon.h

8 vdsf API File Documentation

8.1 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vds.h File Reference

```
#include <vdsf/vdsErrors.h>
#include <vdsf/vdsCommon.h>
#include <vdsf/vdsProcess.h>
#include <vdsf/vdsSession.h>
#include <vdsf/vdsFolder.h>
#include <vdsf/vdsHashMap.h>
#include <vdsf/vdsQueue.h>
```

Include dependency graph for vds.h:




8.2 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vds-Common.h File Reference

#include <stdlib.h>

Include dependency graph for vdsCommon.h:



This graph shows which files directly or indirectly include this file:



Data Structures

struct vdsFolderEntry

This data structure is used to iterate throught all objects in a folder.

• struct vdsObjStatus

This data structure is used to retrieve the status of objects.

• struct vdsInfo

This data structure is used to retrieve the status of the virtual data space.

Defines

• #define VDSF_EXPORT

Uses to tell the VC++ compiler to export/import a function or variable on Windows (the macro is empty on other platforms).

• #define VDS_MAX_NAME_LENGTH 256

Maximum number of characters (or bytes if not supporting i18n) of the name of a vds object (not counting the name of the parent folder(s)).

• #define VDS_MAX_FULL_NAME_LENGTH 1024

Maximum number of characters (or bytes if not supporting i18n) of the fully qualified name of a vds object (including the name(s) of its parent folder(s)).

Typedefs

typedef void * VDS_HANDLE

VDS_HANDLE is an opaque data type used by the C API to reference objects created in the API module.

Enumerations

 enum vdsObjectType { VDS_FOLDER = 1, VDS_QUEUE = 2, VDS_HASH_-MAP = 3, VDS_LAST_OBJECT_TYPE }

The object type as seen from the API.

• enum vdsIteratorType { VDS_FIRST = 1, VDS_NEXT = 2 }

8.2.1 Define Documentation

8.2.1.1 #define VDS MAX FULL NAME LENGTH 1024

Maximum number of characters (or bytes if not supporting i18n) of the fully qualified name of a vds object (including the name(s) of its parent folder(s)).

If the software was compiled with i18n, this maximum is the number of wide characters (4 bytes). Otherwise it is the number of bytes (which should equal the number of characters unless something funny is going on like using UTF-8 as locale and using —disable-i18n with configure...).

Note: setting this value eliminates a possible loophole since some heap memory must be allocated to hold the wide characters string for the duration of the operation (open, close, create or destroy).

8.2.1.2 #define VDS_MAX_NAME_LENGTH 256

Maximum number of characters (or bytes if not supporting i18n) of the name of a vds object (not counting the name of the parent folder(s)).

If the software was compiled with i18n, this maximum is the number of wide characters (4 bytes). Otherwise it is the number of bytes (which should equal the number of characters unless something funny is going on like using UTF-8 as locale and using —disable-i18n with configure...).

8.2.1.3 #define VDSF EXPORT

Uses to tell the VC++ compiler to export/import a function or variable on Windows (the macro is empty on other platforms).

8.2.2 Typedef Documentation

8.2.2.1 typedef void* VDS_HANDLE

VDS_HANDLE is an opaque data type used by the C API to reference objects created in the API module.

8.2.3 Enumeration Type Documentation

8.2.3.1 enum vdsIteratorType

Enumerator:

VDS_FIRST VDS_NEXT

8.2.3.2 enum vdsObjectType

The object type as seen from the API.

Enumerator:

VDS_FOLDER VDS_QUEUE VDS_HASH_MAP VDS_LAST_OBJECT_TYPE

8.3 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsErrors.h File Reference

This graph shows which files directly or indirectly include this file:



Enumerations

enum vdsErrors {
 VDS_OK = 0, VDS_INTERNAL_ERROR = 666, VDS_ENGINE_BUSY = 1, VDS_NOT_ENOUGH_VDS_MEMORY = 2,

VDS_NOT_ENOUGH_HEAP_MEMORY = 3, VDS_NOT_ENOUGH_-RESOURCES = 4, VDS_WRONG_TYPE_HANDLE = 5, VDS_NULL_-HANDLE = 6.

VDS_NULL_POINTER = 7, VDS_INVALID_LENGTH = 8, VDS_PROCESS_ALREADY_INITIALIZED = 21, VDS_PROCESS_NOT_INITIALIZED = 22,

VDS_INVALID_WATCHDOG_ADDRESS = 23, VDS_INCOMPATIBLE_-VERSIONS = 24, VDS_SOCKET_ERROR = 25, VDS_CONNECT_ERROR = 26,

VDS_SEND_ERROR = 27, VDS_RECEIVE_ERROR = 28, VDS_BACKSTORE_FILE_MISSING = 29, VDS_ERROR_OPENING_VDS = 30,

VDS_LOGFILE_ERROR = 41, VDS_SESSION_CANNOT_GET_LOCK = 42, VDS_SESSION_IS_TERMINATED = 43, VDS_INVALID_OBJECT_NAME = 51,

VDS_NO_SUCH_OBJECT = 52, VDS_NO_SUCH_FOLDER = 53, VDS_OBJECT_ALREADY_PRESENT = 54, VDS_IS_EMPTY = 55,

VDS_WRONG_OBJECT_TYPE = 56, VDS_OBJECT_CANNOT_GET_-LOCK = 57, VDS_REACHED_THE_END = 58, VDS_INVALID_ITERATOR = 59,

VDS_OBJECT_NAME_TOO_LONG = 60, VDS_FOLDER_IS_NOT_EMPTY = 61, VDS_ITEM_ALREADY_PRESENT = 62, VDS_NO_SUCH_ITEM = 63, VDS_OBJECT_IS_DELETED = 64, VDS_OBJECT_NOT_INITIALIZED = 65, VDS_I18N_CONVERSION_ERROR = 66 }

8.3.1 Enumeration Type Documentation

8.3.1.1 enum vdsErrors

Enumerator:

VDS OK No error.

DS_OK NO error

VDS_INTERNAL_ERROR Abnormal internal error - it should not happen!

VDS_ENGINE_BUSY Cannot get a lock on a system object, the engine is "busy".

This might be the result of either a very busy system where unused cpu cycles are rare or a lock might be held by a crashed process.

VDS_NOT_ENOUGH_VDS_MEMORY Not enough memory in the VDS.

VDS_NOT_ENOUGH_HEAP_MEMORY Not enough heap memory (non-VDS memory). **VDS_NOT_ENOUGH_RESOURCES** There are not enough resources to correctly process the call.

This might be due to a lack of POSIX semaphores on systems where locks are implemented that way or a failure in initializing a pthread_mutex (or on Windows, a critical section).

- VDS_WRONG_TYPE_HANDLE The provided handle is of the wrong type.
- VDS_NULL_HANDLE The provided handle is NULL (zero).
- **VDS_NULL_POINTER** One of the arguments of an API function is an invalid NULL pointer.
- **VDS_INVALID_LENGTH** An invalid length was provided (it will usually indicate that the length value is set to zero.
- **VDS_PROCESS_ALREADY_INITIALIZED** The process was already initialized.

Was vdsInit() called for a second time?

VDS_PROCESS_NOT_INITIALIZED The process was not properly initialized.

Was vdsInit() called?

VDS_INVALID_WATCHDOG_ADDRESS The watchdog address is invalid (empty string, NULL pointer, etc.)

VDS_INCOMPATIBLE_VERSIONS API - memory-file version mismatch.

VDS_SOCKET_ERROR Generic socket error.

- **VDS_CONNECT_ERROR** Socket error when trying to connect to the watch-dog.
- **VDS_SEND_ERROR** Socket error when trying to send a request to the watchdog.
- **VDS_RECEIVE_ERROR** Socket error when trying to receive a reply from the watchdog.
- **VDS_BACKSTORE_FILE_MISSING** The vds backstore file is missing (the name of this file is provided by the watchdog).
- VDS_ERROR_OPENING_VDS Generic i/o error when attempting to open the vds.
- **VDS_LOGFILE_ERROR** Error accessing the directory for the log files or error opening the log file itself.
- **VDS_SESSION_CANNOT_GET_LOCK** Cannot get a lock on the session (a pthread_mutex or a critical section on Windows).
- **VDS_SESSION_IS_TERMINATED** An attempt was made to use a session object (a session handle) after this session was terminated.

- **VDS_INVALID_OBJECT_NAME** Permitted characters for names are alphanumerics, spaces (' '), dashes ('-') and underlines ('_').
 - The first character must be alphanumeric.
- VDS_NO_SUCH_OBJECT The object was not found (but its folder does exist).
- **VDS_NO_SUCH_FOLDER** One of the parent folder of an object does not exist.
- **VDS_OBJECT_ALREADY_PRESENT** Attempt to create an object which already exists.
- **VDS_IS_EMPTY** The object (data container) is empty.
- **VDS_WRONG_OBJECT_TYPE** Attempt to create an object of an unknown object type.
- VDS_OBJECT_CANNOT_GET_LOCK Cannot get lock on the object.
 This might be the result of either a very busy system where unused cpu cycles are rare or a lock might be held by a crashed process.
- **VDS_REACHED_THE_END** The search/iteration reached the end without finding a new item/record.
- **VDS_INVALID_ITERATOR** An invalid value was used for a vdsIteratorType parameter.
- VDS_OBJECT_NAME_TOO_LONG The name of the object is too long.
 The maximum length of a name cannot be more than VDS_MAX_NAME_LENGTH (or VDS_MAX_FULL_NAME_LENGTH for the fully qualified name).
- **VDS_FOLDER_IS_NOT_EMPTY** You cannot delete a folder if there are still undeleted objects in it.
 - Technical: a folder does not need to be empty to be deleted but all objects in it must be "marked as deleted" by the current session. This enables writing recursive deletions
- VDS_ITEM_ALREADY_PRESENT An item with the same key was found.
- *VDS_NO_SUCH_ITEM* The item was not found in the hash map.
- **VDS_OBJECT_IS_DELETED** The object is scheduled to be deleted soon. Operations on this data container are not permitted at this time.
- VDS_OBJECT_NOT_INITIALIZED Object must be open first before you can access them.
- VDS_I18N_CONVERSION_ERROR i18n string conversion error.
 - In other words, the name of the object cannot be converted to/frm your current locale.

8.4 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsFolder.h File Reference

8.4.1 Detailed Description

This file provides the API needed to access a VDSF folder.

#include <vdsf/vdsCommon.h>

Include dependency graph for vdsFolder.h:



This graph shows which files directly or indirectly include this file:



Functions

- VDSF_EXPORT int vdsFolderClose (VDS_HANDLE objectHandle) Close a folder.
- VDSF_EXPORT int vdsFolderGetFirst (VDS_HANDLE objectHandle, vds-FolderEntry *pEntry)

Iterate through the folder - no data items are removed from the folder by this function.

VDSF_EXPORT int vdsFolderGetNext (VDS_HANDLE objectHandle, vds-FolderEntry *pEntry)

Iterate through the folder.

• VDSF_EXPORT int vdsFolderOpen (VDS_HANDLE sessionHandle, const char *folderName, size_t nameLengthInBytes, VDS_HANDLE *object-Handle)

Open an existing folder (see vdsCreateObject to create a new folder).

 VDSF_EXPORT int vdsFolderStatus (VDS_HANDLE objectHandle, vdsObj-Status *pStatus)

Return the status of the folder.

8.5 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsHash-Map.h File Reference

8.5.1 Detailed Description

This file provides the API needed to access a VDSF hash map.

Hash maps use unique keys - the data items are not sorted.

#include <vdsf/vdsCommon.h>

Include dependency graph for vdsHashMap.h:



This graph shows which files directly or indirectly include this file:



Functions

- VDSF_EXPORT int vdsHashMapClose (VDS_HANDLE objectHandle) Close a Hash Map.
- VDSF_EXPORT int vdsHashMapDelete (VDS_HANDLE objectHandle, const void *key, size_t keyLength)

Remove the data item identified by the given key from the hash map.

 VDSF_EXPORT int vdsHashMapGet (VDS_HANDLE objectHandle, const void *key, size_t keyLength, void *buffer, size_t bufferLength, size_t *returned-Length)

Retrieve the data item identified by the given key from the hash map.

 VDSF_EXPORT int vdsHashMapGetFirst (VDS_HANDLE objectHandle, void *key, size_t keyLength, void *buffer, size_t bufferLength, size_t *retKeyLength, size_t *retDataLength)

Iterate through the hash map.

 VDSF_EXPORT int vdsHashMapGetNext (VDS_HANDLE objectHandle, void *key, size_t keyLength, void *buffer, size_t bufferLength, size_t *retKeyLength, size_t *retDataLength)

Iterate through the hash map.

VDSF_EXPORT int vdsHashMapInsert (VDS_HANDLE objectHandle, const void *key, size_t keyLength, const void *data, size_t dataLength)
 Insert a data element in the hash map.

 VDSF_EXPORT int vdsHashMapOpen (VDS_HANDLE sessionHandle, const char *hashMapName, size_t nameLengthInBytes, VDS_HANDLE *object-Handle)

Open an existing hash map (see vdsCreateObject to create a new object).

- VDSF_EXPORT int vdsHashMapReplace (VDS_HANDLE objectHandle, const void *key, size_t keyLength, const void *data, size_t dataLength)

 Replace a data element in the hash map.
- VDSF_EXPORT int vdsHashMapStatus (VDS_HANDLE objectHandle, vds-ObjStatus *pStatus)

Return the status of the hash map.

8.6 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsProcess.h File Reference

8.6.1 Detailed Description

This file provides the API functions for vdsf processes.

#include <vdsf/vdsCommon.h>

Include dependency graph for vdsProcess.h:



This graph shows which files directly or indirectly include this file:



Functions

• VDSF_EXPORT void vdsExit ()

This function terminates all access to the VDS.

VDSF_EXPORT int vdsInit (const char *wdAddress, int protectionNeeded)
 This function initializes access to a VDS.

8.7 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsQueue.h File Reference

8.7.1 Detailed Description

This file provides the API needed to access a VDSF FIFO queue.

#include <vdsf/vdsCommon.h>

Include dependency graph for vdsQueue.h:



This graph shows which files directly or indirectly include this file:



Functions

- VDSF_EXPORT int vdsQueueClose (VDS_HANDLE objectHandle) Close a FIFO queue.
- VDSF_EXPORT int vdsQueueGetFirst (VDS_HANDLE objectHandle, void *buffer, size_t bufferLength, size_t *returnedLength)

 $\label{thm:condition} \textit{Iterate through the queue - no data items are removed from the queue by this function.}$

• VDSF_EXPORT int vdsQueueGetNext (VDS_HANDLE objectHandle, void *buffer, size_t bufferLength, size_t *returnedLength)

Iterate through the queue - no data items are removed from the queue by this function.

 VDSF_EXPORT int vdsQueueOpen (VDS_HANDLE sessionHandle, const char *queueName, size_t nameLengthInBytes, VDS_HANDLE *object-Handle)

Open an existing FIFO queue (see vdsCreateObject to create a new queue).

• VDSF_EXPORT int vdsQueuePop (VDS_HANDLE objectHandle, void *buffer, size_t bufferLength, size_t *returnedLength)

Remove the first item from the beginning of a FIFO queue and return it to the caller.

 VDSF_EXPORT int vdsQueuePush (VDS_HANDLE objectHandle, const void *pItem, size_t length)

Insert a data element at the end of the FIFO queue.

 VDSF_EXPORT int vdsQueueStatus (VDS_HANDLE objectHandle, vdsObj-Status *pStatus)

Return the status of the queue.

8.8 /home/project/VDSF/vdsf/trunk/src/include/vdsf/vdsSession.h File Reference

8.8.1 Detailed Description

This file provides the API needed to create and use a session.

#include <vdsf/vdsCommon.h>

Include dependency graph for vdsSession.h:



This graph shows which files directly or indirectly include this file:



Functions

VDSF_EXPORT int vdsCommit (VDS_HANDLE sessionHandle)

Commit all insertions and deletions (of the current session) executed since the previous call to vdsCommit or vdsRollback.

 VDSF_EXPORT int vdsCreateObject (VDS_HANDLE sessionHandle, const char *objectName, size_t nameLengthInBytes, vdsObjectType objectType)

Create a new object in shared memory.

 VDSF_EXPORT int vdsDestroyObject (VDS_HANDLE sessionHandle, const char *objectName, size_t nameLengthInBytes)

Destroy an existing object in shared memory.

 VDSF_EXPORT int vdsErrorMsg (VDS_HANDLE sessionHandle, char *message, size_t msgLengthInBytes)

Return the error message associated with the last error(s).

- VDSF_EXPORT int vdsExitSession (VDS_HANDLE sessionHandle)

 Terminate the current session.
- VDSF_EXPORT int vdsGetInfo (VDS_HANDLE sessionHandle, vdsInfo *p-Info)

Return information on the current status of the VDS (Virtual Data Space).

- VDSF_EXPORT int vdsGetStatus (VDS_HANDLE sessionHandle, const char *objectName, size_t nameLengthInBytes, vdsObjStatus *pStatus)

 Return the status of the named object.
- VDSF_EXPORT int vdsInitSession (VDS_HANDLE *sessionHandle)
 This function initializes a session.
- VDSF_EXPORT int vdsLastError (VDS_HANDLE sessionHandle)

 Return the last error seen in previous calls (of the current session).
- VDSF_EXPORT int vdsRollback (VDS_HANDLE sessionHandle)

Rollback all insertions and deletions (of the current session) executed since the previous call to vdsCommit or vdsRollback.

Index

/home/project/VDSF/vdsf/trunk/src/	numBlocks
Directory Reference, 21	vdsObjStatus, 26
/home/project/VDSF/vdsf/trunk/src/includ	e/numDataItem
Directory Reference, 21	vdsObjStatus, 26
/home/project/VDSF/vdsf/trunk/src/includ	e/ndshFrees
Directory Reference, 21	vdsInfo, 24
/home/project/VDSF/vdsf/trunk/src/includ	e/ ndsh/Gdsulp s
26	vdsInfo, 24
/home/project/VDSF/vdsf/trunk/src/includ	e/ndshMddCommon.h,
27	vdsInfo, 24
/home/project/VDSF/vdsf/trunk/src/includ	e/wdshObjEutsors.h,
30	vdsInfo, 24
/home/project/VDSF/vdsf/trunk/src/includ	e/vdsf/vdsFolder.h,
33	status
/home/project/VDSF/vdsf/trunk/src/includ	e/vdsf/vdsFaldevEntry, 23
34	vdsObjStatus, 26
/home/project/VDSF/vdsf/trunk/src/includ	e/vdsf/vdsProcess.h, totalSizeInBytes
/home/project/VDSF/vdsf/trunk/src/includ	e/vdsf/VdsQueih, type
/home/project/VDSF/vdsf/trunk/src/includ	
allocatedSizeInBytes	VDS_BACKSTORE_FILE_MISSING
vdsInfo, 24	vdsErrors.h, 32
API functions for vdsf FIFO queues., 12	VDS_CONNECT_ERROR
API functions for vdsf folders., 2	vdsErrors.h, 32
API functions for vdsf hash maps., 5	VDS_ENGINE_BUSY
API functions for vdsf processes., 10	vdsErrors.h, 31
API functions for vdsf sessions., 16	VDS_ERROR_OPENING_VDS
All Functions for vasi sessions., To	vdsErrors.h, 32
freeBytes	VDS_FIRST
vdsObjStatus, 26	vdsCommon.h, 29
vascojstatas, 20	VDS_FOLDER
largestFreeInBytes	vdsCommon.h, 30
vdsInfo, 24	VDS_FOLDER_IS_NOT_EMPTY
,	vdsErrors.h, 32
name	VDS_HANDLE
vdsFolderEntry, 23	vdsCommon.h, 29
nameLengthInBytes	VDS_HASH_MAP
vdsFolderEntry, 23	vdsCommon.h, 30
numBlockGroup	VDS_I18N_CONVERSION_ERROR
vdsObjStatus, 26	vdsErrors.h, 33

VDS_INCOMPATIBLE_VERSIONS	VDS_OBJECT_CANNOT_GET_LOCK
vdsErrors.h, 31	vdsErrors.h, 32
VDS_INTERNAL_ERROR	VDS_OBJECT_IS_DELETED
vdsErrors.h, 31	vdsErrors.h, 33
VDS_INVALID_ITERATOR	VDS_OBJECT_NAME_TOO_LONG
vdsErrors.h, 32	vdsErrors.h, 32
VDS_INVALID_LENGTH	VDS_OBJECT_NOT_INITIALIZED
vdsErrors.h, 31	vdsErrors.h, 33
VDS_INVALID_OBJECT_NAME	VDS_OK
vdsErrors.h, 32	vdsErrors.h, 31
VDS_INVALID_WATCHDOG	VDS_PROCESS_ALREADY
ADDRESS	INITIALIZED
vdsErrors.h, 31	vdsErrors.h, 31
VDS_IS_EMPTY	VDS_PROCESS_NOT_INITIALIZED
vdsErrors.h, 32	vdsErrors.h, 31
VDS_ITEM_ALREADY_PRESENT	VDS_QUEUE
vdsErrors.h, 33	vdsCommon.h, 30
VDS_LAST_OBJECT_TYPE	VDS_REACHED_THE_END
vdsCommon.h, 30	vdsErrors.h, 32
VDS_LOGFILE_ERROR	VDS_RECEIVE_ERROR
vdsErrors.h, 32	vdsErrors.h, 32
VDS_MAX_FULL_NAME_LENGTH	VDS_SEND_ERROR
vdsCommon.h, 28	vdsErrors.h, 32
VDS_MAX_NAME_LENGTH	VDS_SESSION_CANNOT_GET
vdsCommon.h, 29	LOCK
VDS_NEXT	vdsErrors.h, 32
vdsCommon.h, 29	VDS_SESSION_IS_TERMINATED
VDS_NO_SUCH_FOLDER	vdsErrors.h, 32
vdsErrors.h, 32	VDS_SOCKET_ERROR
VDS_NO_SUCH_ITEM	vdsErrors.h, 32
vdsErrors.h, 33	VDS_WRONG_OBJECT_TYPE
VDS_NO_SUCH_OBJECT	vdsErrors.h, 32
vdsErrors.h, 32	VDS_WRONG_TYPE_HANDLE
VDS_NOT_ENOUGH_HEAP	vdsErrors.h, 31
MEMORY	vdsCommit
vdsErrors.h, 31	vdsSession_c, 17
VDS_NOT_ENOUGH_RESOURCES	vdsCommon.h
vdsErrors.h, 31	VDS_FIRST, 29
VDS_NOT_ENOUGH_VDS_MEMORY	VDS_FOLDER, 30
vdsErrors.h, 31	VDS_HASH_MAP, 30
VDS_NULL_HANDLE	VDS_LAST_OBJECT_TYPE, 30
vdsErrors.h, 31	VDS_NEXT, 29
VDS_NULL_POINTER	VDS_QUEUE, 30
vdsErrors.h, 31	vdsCommon.h
VDS_OBJECT_ALREADY_PRESENT	VDS_HANDLE, 29
vdsErrors.h. 32	

VDS_MAX_FULL_NAME	VDS_NULL_HANDLE, 31
LENGTH, 28	VDS_NULL_POINTER, 31
VDS_MAX_NAME_LENGTH, 29	VDS_OBJECT_ALREADY
VDSF_EXPORT, 29	PRESENT, 32
vdsIteratorType, 29	VDS_OBJECT_CANNOT_GET
vdsObjectType, 29	LOCK, 32
vdsCreateObject	VDS_OBJECT_IS_DELETED, 33
vdsSession_c, 17	VDS_OBJECT_NAME_TOO
vdsDestroyObject	LONG, 32
vdsSession_c, 17	VDS_OBJECT_NOT
vdsErrorMsg	INITIALIZED, 33
vdsSession_c, 18	VDS_OK, 31
vdsErrors	VDS_PROCESS_ALREADY
vdsErrors.h, 31	INITIALIZED, 31
vdsErrors.h	VDS_PROCESS_NOT
VDS_BACKSTORE_FILE	INITIALIZED, 31
MISSING, 32	VDS_REACHED_THE_END, 32
VDS_CONNECT_ERROR, 32	VDS_RECEIVE_ERROR, 32
VDS_ENGINE_BUSY, 31	VDS_SEND_ERROR, 32
VDS_ERROR_OPENING_VDS, 32	VDS_SESSION_CANNOT_GET
VDS_FOLDER_IS_NOT_EMPTY,	LOCK, 32
32	VDS_SESSION_IS
VDS_I18N_CONVERSION	TERMINATED, 32
ERROR, 33	VDS_SOCKET_ERROR, 32
VDS_INCOMPATIBLE	VDS_WRONG_OBJECT_TYPE,
VERSIONS, 31	32
VDS_INTERNAL_ERROR, 31	VDS_WRONG_TYPE_HANDLE,
VDS_INVALID_ITERATOR, 32	31
VDS_INVALID_LENGTH, 31	vdsErrors.h
VDS_INVALID_DELYOTH, ST	vdsErrors, 31
32	vdsExit
VDS_INVALID_WATCHDOG	vdsProcess_c, 11
ADDRESS, 31	vdsFrocess_c, 11 vdsExitSession
VDS_IS_EMPTY, 32	vdsSession_c, 18
VDS_IS_EMITT, 32 VDS_ITEM_ALREADY	VDSF_EXPORT
PRESENT, 33	vdsCommon.h, 29
VDS_LOGFILE_ERROR, 32	vdsFolder_c
VDS_NO_SUCH_FOLDER, 32	vdsFolderClose, 3
VDS_NO_SUCH_ITEM, 33	vdsFolderGetFirst, 3
VDS_NO_SUCH_HEM, 33 VDS_NO_SUCH_OBJECT, 32	vdsFolderGetNext, 4
	vdsFolderOpen, 4
VDS_NOT_ENOUGH_HEAP	* '
MEMORY, 31	vdsFolderStatus, 4
VDS_NOT_ENOUGH	vdsFolder o 2
RESOURCES, 31	vdsFolder_c, 3
VDS_NOT_ENOUGH_VDS	vdsFolderEntry, 22
MEMORY, 31	vdsFolderEntry

name, 23	allocatedSizeInBytes, 24
nameLengthInBytes, 23	largestFreeInBytes, 24
status, 23	numFrees, 24
type, 23	numGroups, 24
vdsFolderGetFirst	numMallocs, 24
vdsFolder_c, 3	numObjects, 24
vdsFolderGetNext	totalSizeInBytes, 25
vdsFolder_c, 4	vdsInit
vdsFolderOpen	vdsProcess_c, 11
vdsFolder_c, 4	vdsInitSession
vdsFolderStatus	vdsSession_c, 19
vdsFolder_c, 4	vdsIteratorType
vdsGetInfo	vdsCommon.h, 29
vdsSession_c, 19	vdsLastError
vdsGetStatus	vdsSession_c, 20
vdsSession_c, 19	vdsObjectType
vdsHashMap_c	vdsCommon.h, 29
vdsHashMapClose, 6	vdsObjStatus, 25
vdsHashMapDelete, 6	vdsObjStatus
vdsHashMapGet, 7	freeBytes, 26
vdsHashMapGetFirst, 7	numBlockGroup, 26
vdsHashMapGetNext, 8	numBlocks, 26
vdsHashMapInsert, 9	numDataItem, 26
vdsHashMapOpen, 9	status, 26
vdsHashMapReplace, 10	type, 26
vdsHashMapStatus, 10	vdsProcess_c
vdsHashMapClose	vdsExit, 11
vdsHashMap_c, 6	vdsInit, 11
vdsHashMapDelete	vdsQueue_c
vdsHashMap_c, 6	vdsQueueClose, 12
vdsHashMapGet	vdsQueueGetFirst, 13
vdsHashMap_c, 7	vdsQueueGetNext, 13
vdsHashMapGetFirst	vdsQueueOpen, 14
vdsHashMap_c, 7	vdsQueuePop, 14
vdsHashMapGetNext	vdsQueuePush, 15
vdsHashMap_c, 8	vdsQueueStatus, 15
vdsHashMapInsert	vdsQueueClose
vdsHashMap_c, 9	vdsQueue_c, 12
vdsHashMapOpen	vdsQueueGetFirst
vdsHashMap_c, 9	vdsQueue_c, 13
vdsHashMapReplace	vdsQueueGetNext
vdsHashMap_c, 10	vdsQueue_c, 13
vdsHashMapStatus	vdsQueueOpen
vdsHashMap_c, 10	vdsQueue_c, 14
vdsInfo, 23	vdsQueuePop
vdsInfo	-
VUSIIIIU	vdsQueue_c, 14

```
vdsQueuePush
    vdsQueue_c, 15
vdsQueueStatus
    vdsQueue_c, 15
vds \\ Rollback
    vdsSession_c, 20
vdsSession_c
    vdsCommit, 17
    vdsCreateObject, 17
    vdsDestroyObject, 17
    vdsErrorMsg, 18
    vdsExitSession, 18
    vdsGetInfo, 19
    vdsGetStatus, 19
    vdsInitSession, 19
    vdsLastError, 20
    vdsRollback, 20
```