Design Principles and Design Patterns

D. Ryan Bartling

March 17, 2019

Outline

Introduction

Symptoms of Rotting Design

Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

Introduction

Introduction

Symptoms of Rotting Design


Principles of Object Oriented Class Design

Package Design

Architecture Desigr

Conclusion

Architecture and Dependencies



Introduction

Symptoms of Rotting Design

Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

1. Rigidity

- 1. Rigidity
- 2. Fragility

- 1. Rigidity
- 2. Fragility
- 3. Immobility

- 1. Rigidity
- 2. Fragility
- 3. Immobility
- 4. Viscosity



- Deficient in or devoid of flexibility
- ➤ Software for which extra effort is expended in order to make changes.

Ryan Bartling

- Deficient in or devoid of flexibility
- Software for which extra effort is expended in order to make changes.
- The system is hard to change because every change forces many other changes to other parts of the system.

Ryan Bartling



How it happens

Overly procedural code

How it happens

- Overly procedural code
- Lack of abstractions

How it happens

- Overly procedural code
- Lack of abstractions
- Solving a generic problem with implementation specific details

Ryan Bartling

How it happens

- Overly procedural code
- Lack of abstractions
- Solving a generic problem with implementation specific details
- Spreading a single responsibility throughout several parts

Ryan Bartling

How it happens

- Overly procedural code
- Lack of abstractions
- Solving a generic problem with implementation specific details
- Spreading a single responsibility throughout several parts
- ▶ When components need a lot of knowledge about each other in order to function


```
#include <stdint.h>
 2
       #define ADC_BITS (12)
 4
       #define ADC DATA SHIFT (2)
 5
       #define ADC_SIGN_CONVERSION (1)
 6
       #define RAW_ADC_BITS (15) // Sum of the above bits
 7
 8
       #define LFSR_LENGTH (4)
9
       #define LFSR_REPEATS (2)
10
       #define CORRELATED_BITS (20) // ADC bits + lfsr length + log2(repeats)
11
12
       typedef int16_t rpo_raw_adc_t;
13
      typedef int24_t rpo_correlated_int_t;
14
15
       \#if\ sizeof(rpo\_raw\_adc\_t) < (RAW\_ADC\_BITS / 2 + 1)
16
            error "rpo_raw_adc_t is too small to store ADC results"
17
       #endif
18
19
       \#if\ size of (rpo\_correlated\_int\_t) < (RAW\_ADC\_BITS / 2 + 1)
20
           error "rpo correlated int t is too small to store correlated adc results"
21
       #endif
```


```
#include <stdint.h>
 2
 3
       #define ADC_BITS (14) // Changing this
       #define ADC_DATA_SHIFT (2)
 4
 5
       #define ADC_SIGN_CONVERSION (1)
 6
       #define RAW_ADC_BITS (17) // Changes this
 7
 8
       #define LFSR_LENGTH (4)
9
       #define LFSR_REPEATS (2)
10
       #define CORRELATED_BITS (22) // Changes this
11
12
       typedef int24_t rpo_raw_adc_t; // Changes this
13
      typedef int24_t rpo_correlated_int_t;
14
15
       \#if\ sizeof(rpo\_raw\_adc\_t) < (RAW\_ADC\_BITS / 2 + 1)
16
            error "rpo_raw_adc_t is too small to store ADC results"
17
       #endif
18
19
       #if sizeof(rpo_correlated_int_t) < (RAW_ADC_BITS / 2 + 1)</pre>
20
           error "rpo correlated int t is too small to store correlated adc results"
21
       #endif
```


Refactor to reduce rigidity


```
#include <stdint.h>
 2
 3
      #define ADC_BITS (14)
      #define ADC_DATA_SHIFT (2)
      #define ADC_SIGN_CONVERSION (1)
 6
      #define RAW_ADC_BITS (ADC_BITS + ADC_DATA_SHIFT + ADC_SIGN_CONVERSION)
      typedef_min_int(rpo_raw_adc_t, RAW_ADC_BITS);
 8
9
      #define LFSR_LENGTH (4)
10
      #define LFSR_REPEATS (2)
11
      #define CORRELATED_BITS (RAW_ADC_BITS + LFSR_LENGTH + log_2(LFSR_REPEATS))
12
      typedef_min_int(rpo_correlated_int_t, CORRELATED_BITS);
```











How to avoid it

▶ Break the code into smaller, self-contained concepts


- ▶ Break the code into smaller, self-contained concepts
- ► Solve the details and provide a problem oriented abstraction

- ▶ Break the code into smaller, self-contained concepts
- ▶ Solve the details and provide a problem oriented abstraction
- Solving a generic problem with implementation specific details

- ▶ Break the code into smaller, self-contained concepts
- Solve the details and provide a problem oriented abstraction
- Solving a generic problem with implementation specific details
- Write DRY code (Don't repeat yourself)

- ▶ Break the code into smaller, self-contained concepts
- Solve the details and provide a problem oriented abstraction
- Solving a generic problem with implementation specific details
- Write DRY code (Don't repeat yourself)
- Define the code in logical pieces. Set boundaries and responsibilities.






Fragility

- ► Easily broken or destroyed
- Software for which extra risk is incurred in order to make changes.
- Changes cause the system to break in places that have no conceptual relationship to the part that was changed.







- ► Implicit dependencies
- Unmanaged shared resources
- Relying on implementation details
- Relying upon side effects of operations
- Reaching past abstraction layers

- ► Implicit dependencies
- Unmanaged shared resources
- Relying on implementation details
- Relying upon side effects of operations
- Reaching past abstraction layers
- Unmanaged complexity

Fragility

Changing the sensor to use mode 1...

...Breaks the sd card (when sensor is initialized after the sd card)

Fragility

We can fix it with dynamic resource allocation...

```
void
      sdcard_init(void) {
          if(spi_success != spi_acquire(mode_0, card_cs_pin)) { return; }
          fat init():
 5
          spi_release();
 6
 7
 8
      void
 9
      sensor_init(void) {
10
          if(spi_success != spi_acquire(mode_1, sensor_cs_pin)) { return; }
11
          spi_write(SENSOR_CONFIGURATION, sensor_cs_pin);
12
          spi_release();
13
```

If multi threaded, we could spin lock...

```
void
      sdcard_init(void) {
          while(spi_success != spi_acquire(mode_0, card_cs_pin)) {}
          fat_init();
 4
 5
          spi_release();
 6
 7
 8
      void
 9
      sensor_init(void) {
10
          while(spi_success != spi_acquire(mode_1, sensor_cs_pin)) {}
11
          spi_write(SENSOR_CONFIGURATION, sensor_cs_pin);
12
          spi_release();
13
```

We could also have a common allocation and assert correctness...

```
void
       sys_init(void) {
           spi_init(mode_0);
 5
 6
      void
      sdcard init(void) {
           assert(mode_0 == spi_mode_get() && "Wrong spi mode for sdcard");
           fat_init();
10
11
12
      void
13
      sensor_init(void) {
14
           assert(mode_0 == spi_mode_get() && "Wrong spi mode for sensor");
15
           spi_write(SENSOR_CONFIGURATION, sensor_cs_pin);
16
```





How to avoid it

- Explicit dependencies
- ► Law of Demeter: principle of least knowledge
- Avoid side effects, and don't rely on the side effects of other modules


How to avoid it

- Explicit dependencies
- ► Law of Demeter: principle of least knowledge
- Avoid side effects, and don't rely on the side effects of other modules
- Rely on the published API

How to avoid it

- Explicit dependencies
- ► Law of Demeter: principle of least knowledge
- Avoid side effects, and don't rely on the side effects of other modules
- Rely on the published API
- Invent and simplify







- ► Incapable of being moved
- Software for which extra effort is required in order to reuse.

- ► Incapable of being moved
- Software for which extra effort is required in order to reuse.
- ► It is hard to disentangle the system into components that can be reused in other systems.

How it happens


Direct dependency on things you don't own

- Direct dependency on things you don't own
- ► Too many responsibilities

How it happens


Depend upon the concept, not the details

- Depend upon the concept, not the details
- Reduce responsibilities to solve distinct problems





- ► Having or characterized by a high resistance to flow
- Software projects in which design preserving changes are more difficult than hacks.



Viscosity

- ► Viscous Design
 - When making changes, preserving the design is difficult

Viscous Environment

Viscosity

- Viscous Design
 - When making changes, preserving the design is difficult
 - ▶ When a more correct solution is not the easier solution
- Viscous Environment

Viscosity

- Viscous Design
 - When making changes, preserving the design is difficult
 - ▶ When a more correct solution is not the easier solution
 - "That is the right way to do this, but we can't do that in this project"
- Viscous Environment

- Viscous Design
 - When making changes, preserving the design is difficult
 - ▶ When a more correct solution is not the easier solution
 - ► "That is the right way to do this, but we can't do that in this project"
- Viscous Environment
 - Long builds can prevent people from making the appropriate change since it will triger a longer build.

- Viscous Design
 - When making changes, preserving the design is difficult
 - ▶ When a more correct solution is not the easier solution
 - ► "That is the right way to do this, but we can't do that in this project"
- ► Viscous Environment
 - Long builds can prevent people from making the appropriate change since it will triger a longer build.
 - Slow/unreliable Tests "I can't run these tests after each change, I'd get no work done. Besides, they always fail anyway."

- Viscous Design
 - When making changes, preserving the design is difficult
 - ▶ When a more correct solution is not the easier solution
 - ► "That is the right way to do this, but we can't do that in this project"
- Viscous Environment
 - Long builds can prevent people from making the appropriate change since it will triger a longer build.
 - Slow/unreliable Tests "I can't run these tests after each change, I'd get no work done. Besides, they always fail anyway."
 - ► Slow/cumbersom tools (e.g. if checking in files)

- Viscous Policies
 - Management steps in to avoid the issues above
 - "We cannot afford to have anyone touch the Fobnicator stack, because too many things depend upon it"

- Viscous Policies
 - Management steps in to avoid the issues above
 - "We cannot afford to have anyone touch the Fobnicator stack, because too many things depend upon it"
 - Policies can remain long after the original problem was solved.

Viscous Policies

- Management steps in to avoid the issues above
- "We cannot afford to have anyone touch the Fobnicator stack, because too many things depend upon it"
- Policies can remain long after the original problem was solved.
- Process can also result in viscocity. If a more correct soluton triggers a heavier round of reviews, the incorrect solution that can get by with less review and documentation will be favored by the developers. E.g. Creating a new module requires upfront design review. Adding the same code inside an existing module requires only the normal code review.

Introduction

Symptoms of Rotting Desigr

Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

SOLID Principles

► Single Responsibility Principle (SRP)

- ► Single Responsibility Principle (SRP)
- ▶ Open Closed Principle (OCP)

- ► Single Responsibility Principle (SRP)
- ► Open Closed Principle (OCP)
- ► Liskov Substitution Principle (LSP)

- Single Responsibility Principle (SRP)
- ► Open Closed Principle (OCP)
- ► Liskov Substitution Principle (LSP)
- ► Interface Segregation Principle (ISP)

- ► Single Responsibility Principle (SRP)
- ► Open Closed Principle (OCP)
- ► Liskov Substitution Principle (LSP)
- ► Interface Segregation Principle (ISP)
- ► Dependency Inversion Principle (DIP)

Responsibility

Responsibility

Cohesion

Responsibility

- Cohesion
- ► Reason to change

Responsibility

- Cohesion
- ► Reason to change
- ► Axis of change

```
class modem {
       public:
 3
           void
 4
           dial();
 5
           void
 6
           hangup();
 7
           void
 8
           send();
 9
           void
10
           rcv();
11
```

```
class modem {
      public:
 3
          void
4
          dial(); // Connection management
 5
          void
6
          hangup(); // Connection management
 7
          void
8
          send();
9
          void
10
          rcv();
11
```

```
class modem {
      public:
          void
4
          dial();
5
          void
6
          hangup();
 7
          void
8
          send(); // Data Management
9
          void
10
          rcv(); // Data Management
11
```

```
class modem_connection {
 1
 2
      public:
 3
           void
          dial():
 4
 5
          void
6
          hangup();
 7
 8
9
      class modem_data {
10
      public:
11
          void
12
          send();
13
          void
14
          rcv();
15
16
17
      class modem_impl {
18
      private:
19
          modem_connection connection;
20
          modem data
                            data:
21
```

Caution:

oduction Rotting Code Class Design Package Design Architecture Design

Single Responsibility Principle

Caution:

➤ Too much splitting of modules can lead to an overly complicated design. duction Rotting Code Class Design Package Design Architecture Design

Single Responsibility Principle

Caution:

- Too much splitting of modules can lead to an overly complicated design.
- ► If the code does not change in a way that the two responsibilities change at different times, then there's no need to separate.


▶ "Open for Extension"


- ▶ "Open for Extension"
 - ▶ Behavior of the module can be modified through extension

- "Open for Extension"
 - ▶ Behavior of the module can be modified through extension
- ► "Closed for Modification"


- ▶ "Open for Extension"
 - ▶ Behavior of the module can be modified through extension
- "Closed for Modification"
 - Extending the behavior requires no change in source code or binary executables.

oduction Rotting Code Class Design Package Design Architecture Design






Client depends on server




- Client depends on server
- Changing server requires modification of client



- Client depends on server
- Changing server requires modification of client
- Use of clients with different servers requires duplication of code





► Enables client implementations for multiple servers

```
1
    2
3
    enum shape_type_t { circle, square };
4
    struct shape_s {
5
      shape_type_t shape_type;
6
    8
    #include "shape.h"
9
    struct circle s {
10
      shape_type_t shape_type;
11
      double
           radius:
12
      point
          center:
13
14
15
    void
16
    drawCircle(struct circle_s *);
17
18
    19
    #include "shape.h"
20
    struct square_s {
      shape_type_t shape_type;
21
22
      double
           side:
23
      point
          top_left;
24
25
26
    void
27
    drawSquare(struct square_s *);
```

```
1
    2
    // Adding a new shape, requires modification of enum
3
    enum shape_type_t { circle, square };
4
    struct shape_s {
5
      shape_type_t shape_type;
6
    8
    #include "shape.h"
9
    struct circle s {
10
      shape_type_t shape_type;
11
      double
            radius:
12
      point
           center:
13
14
15
    void
16
    drawCircle(struct circle_s *);
17
18
    19
    #include "shape.h"
20
    struct square_s {
2.1
      shape_type_t shape_type;
22
      double
            side:
23
      point
           top_left;
24
25
26
    void
27
    drawSquare(struct square_s *);
```

```
1
     2
3
     typedef struct shape_t *shape_pointer_t;
4
5
     void
6
     DrawAllShapes(shape_pointer_t *shapes, int n) {
7
        for(int i = 0: i < nl i++) {
           struct shape_s *s = shapes[i];
9
           switch(shape->shape_type) {
10
           case circle: drawCircle((struce circle_s *)shape); break;
           case square: drawSquare((struce square_s *)shape); break;
11
12
13
14
```

Class Design

Open Closed Principle

```
1
    enum shape_type_t { circle, square };
3
   void (*DrawFunction)(void *);
   struct shape_s {
4
5
      DrawFunction draw;
6
   } void
7
   DrawShape(void *):
8
9
   10
   void
11
   DrawShape(void *shape_in) {
12
      shape = (struct shape_s *)shape_in;
13
      shape.draw(shape in):
14
15
16
    17
   struct circle s {
18
      DrawFunction draw;
19
      double
             radius:
20
      point
             center:
21
22
23
   void
24
   drawCircle(struct circle s *):
25
26
    27
   struct square s {
28
      DrawFunction draw;
29
      double
             side;
30
      point
          top_left;
31
32
```

Ryan Bartling


void


```
3
    typedef struct shape_t *shape_pointer_t;
4
5
    void
6
    DrawAllShapes(shape_pointer_t *shapes, int n) {
7
       for(int i = 0: i < nl i++) {
8
          struct shape_s *shape = shapes[i];
9
          DrawShape(shape);
10
11
```


Design Principles

Depend upon abstractions.

Depend upon abstractions. Do not depend upon concretions.







Package Design

Introduction

Symptoms of Rotting Design

Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

Package Principles

Package Cohesion

Package Principles

Package Cohesion

Package Coupling

- Package Cohesion
 - ► Release Reuse Equivalency Principle (REP)
- Package Coupling

- Package Cohesion
 - ► Release Reuse Equivalency Principle (REP)
 - Common Closure Principle (CCP)
- Package Coupling

- Package Cohesion
 - Release Reuse Equivalency Principle (REP)
 - Common Closure Principle (CCP)
 - Common Reuse Principle (CRP)
- Package Coupling

- Package Cohesion
 - ► Release Reuse Equivalency Principle (REP)
 - Common Closure Principle (CCP)
 - Common Reuse Principle (CRP)
- Package Coupling
 - Acyclic Dependencies Principle (ADP)

- Package Cohesion
 - ► Release Reuse Equivalency Principle (REP)
 - Common Closure Principle (CCP)
 - Common Reuse Principle (CRP)
- Package Coupling
 - Acyclic Dependencies Principle (ADP)
 - ► Stable Dependencies Principle (SDP)

- Package Cohesion
 - ► Release Reuse Equivalency Principle (REP)
 - Common Closure Principle (CCP)
 - Common Reuse Principle (CRP)
- Package Coupling
 - Acyclic Dependencies Principle (ADP)
 - Stable Dependencies Principle (SDP)
 - Stable Abstractions Principle (SAP)

Architecture Design

Introduction

Symptoms of Rotting Design

Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

Conclusion

Introduction

Symptoms of Rotting Design

Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

References

- https://fi.ort.edu.uy/innovaportal/file/2032/1/ design_principles.pdf
- http://www.butunclebob.com/ArticleS.UncleBob. PrinciplesOfOod
- http://notherdev.blogspot.com/2013/07/ code-smells-rigidity.html
- https: //dev.to/bob/how-do-you-know-your-code-is-bad
- http://staff.cs.utu.fi/~jounsmed/doos_06/slides/ slides_060321.pdf
- https://softwareengineering.stackexchange.com/ questions/357127/clear-examples-for-code-smells

Ryan Bartling