Design Principles and Design Patterns

D. Ryan Bartling

July 8, 2018

Outline

Introduction

Symptoms of Rotting Design


Principles of Object Oriented Class Design

Package Design

Architecture Design

Conclusion

Architecture and Dependencies



Symptoms of Rotting Design

- 1. Rigidity
- 2. Fragility
- 3. Immobility
- 4. Viscosity

- Deficient in or devoid of flexibility
- Software for which extra effort is expended in order to make changes.
- ► The system is hard to change because every change forces many other changes to other parts of the system.

How it happens


- Code written in a procedural way
- Lack of abstractions
- ► Solving a generic problem with implementation specific details
- Spreading a single responsibility throughout several parts
- ▶ When components need a lot of knowledge about each other in order to function

```
1
      #include <stdint.h>
 2
 3
      #define ADC_BITS (12)
4
      #define ADC_DATA_SHIFT (2)
 5
      #define ADC SIGN CONVERSION (1)
 6
      #define RAW_ADC_BITS (15) // Sum of the above bits
 8
      #define LFSR LENGTH (4)
9
      #define LFSR REPEATS (2)
10
      #define CORRELATED_BITS (20) // ADC bits + lfsr length + log2(repeats)
11
12
      typedef int16_t rpo_raw_adc_t;
13
      typedef int24_t rpo_correlated_int_t;
14
15
      \#if\ sizeof(rpo\_raw\_adc\_t) < (RAW\_ADC\_BITS / 2 + 1)
16
      #error "rpo_raw_adc_t is too small to store ADC results"
17
      #endif
18
19
      #if sizeof(rpo_correlated_int_t) < (RAW_ADC_BITS / 2 + 1)</pre>
20
      #error "rpo_correlated_int_t is too small to store correlated adc results"
21
      #endif
```

```
1
      #include <stdint.h>
 2
 3
      #define ADC_BITS (14) // Changing this
4
      #define ADC_DATA_SHIFT (2)
 5
      #define ADC SIGN CONVERSION (1)
 6
      #define RAW_ADC_BITS (17) // Changes this
 8
      #define LFSR LENGTH (4)
9
      #define LFSR REPEATS (2)
      #define CORRELATED_BITS (22) // Changes this
10
11
12
      typedef int24_t rpo_raw_adc_t; // Changes this
13
      typedef int24_t rpo_correlated_int_t;
14
15
      \#if\ sizeof(rpo\_raw\_adc\_t) < (RAW\_ADC\_BITS / 2 + 1)
16
      #error "rpo_raw_adc_t is too small to store ADC results"
17
      #endif
18
19
      #if sizeof(rpo_correlated_int_t) < (RAW_ADC_BITS / 2 + 1)</pre>
20
      #error "rpo_correlated_int_t is too small to store correlated adc results"
21
      #endif
```

Refactor to reduce rigidity

```
#include <stdint.h>
 2
 3
      #define ADC_BITS (14)
 4
      #define ADC_DATA_SHIFT (2)
 5
      #define ADC_SIGN_CONVERSION (1)
 6
      #define RAW_ADC_BITS (ADC_BITS + ADC_DATA_SHIFT + ADC_SIGN_CONVERSION)
      typedef_min_int(rpo_raw_adc_t, RAW_ADC_BITS);
 8
9
      #define LFSR_LENGTH (4)
10
      #define LFSR_REPEATS (2)
11
      #define CORRELATED_BITS (RAW_ADC_BITS + LFSR_LENGTH + log_2(LFSR_REPEATS))
      typedef_min_int(rpo_correlated_int_t, CORRELATED_BITS);
12
```



Ryan Bartling

Design Principles

Notes:

Customer wants a feature: be able to test a new feature

Create the code to test the new feature

This requires new test case steps

Which in turn requires a new workflow to execute the new test case steps

Also new execution command

Also new test configurations

Also new command line arguments

Etc.

How to avoid it

- ▶ Break the code into smaller, self-contained concepts
- Solve the details and provide a problem oriented abstraction
- Solving a generic problem with implementation specific details
- Write DRY code (Don't repeat yourself)
- Define the code in logical pieces. Set boundaries and responsibilities.

Fragility

- Easily broken or destroyed
- Software for which extra risk is incurred in order to make changes.
- ► Changes cause the system to break in places that have no conceptual relationship to the part that was changed.

- Implicit dependencies
- Unmanaged shared resources
- Relying on implementation details
- Relying upon side effects of operations
- Reaching past abstraction layers
- Unmanaged complexity

Fragility

```
void sdcard_init(void) {
    spi_init(mode_0, card_cs_pin);
    fat_init();
}

void sensor_init(void) {
    spi_init(mode_0, sensor_cs_pin);
    spi_write(SENSOR_CONFIGURATION, sensor_cs_pin);
}
```

Fragility

Changing the sensor to use mode 1...

```
void sdcard_init(void) {
    spi_init(mode_0, card_cs_pin);
    fat_init();
}

void sensor_init(void) {
    spi_init(mode_1, sensor_cs_pin); // Breaks the sd card
    spi_write(SENSOR_CONFIGURATION, sensor_cs_pin);
}
```

...Breaks the sd card (when sensor is initialized after the sd card)

How to avoid it

- Implicit dependencies
- ► Law of Demeter: principle of least knowledge
- Avoid side effects, and don't rely on the side effects of other modules
- Rely on the published API
- Invent and simplify

Immobility

- ► Incapable of being moved
- ▶ Software for which extra effort is required in order to reuse.
- ▶ It is hard to disentangle the system into components that can be reused in other systems.

Immobility

How it happens

- Direct dependency on things you don't own
- ► Too many responsibilities

Immobility

How it happens

- Depend upon the concept, not the details
- ► Reduce responsibilities to solve distinct problems

- ▶ Having or characterized by a high resistance to flow
- Software projects in which design preserving changes are more difficult than hacks.

Viscous Design

- When making changes, preserving the design is difficult
- ▶ When a more correct solution is not the easier solution
- "That is the right way to do this, but we can't do that in this project"

Viscous Environment

- ▶ Long builds can prevent people from making the appropriate change since it will triger a longer build.
- ► Slow/unreliable Tests "I can't run these tests after each change, I'd get no work done. Besides, they always fail anyway."
- ► Slow/cumbersom tools (e.g. if checking in files)

Viscous Policies

- Management steps in to avoid the issues above
- "We cannot afford to have anyone touch the Fobnicator stack, because too many things depend upon it"
- Policies can remain long after the original problem was solved.
- ▶ Process can also result in viscocity. If a more correct soluton triggers a heavier round of reviews, the incorrect solution that can get by with less review and documentation will be favored by the developers. E.g. Creating a new module requires upfront design review. Adding the same code inside an existing module requires only the normal code review.

Software develops along the path of least resistence. If hacks are easier, that's what your project will consist of.

Principles of Object Oriented Class Design

SOLID Principles

- ► Single Responsibility Principle (SRP)
- ▶ Open Closed Principle (OCP)
- ► Liskov Substitution Principle (LSP)
- ► Interface Segregation Principle (ISP)
- ► Dependency Inversion Principle (DIP)

Single Responsibility Principle

Responsibility

- Cohesion
- Reason to change
- Axis of change

```
class modem_connection
 2
 3
       public:
4
         void dial();
 5
          void hangup();
6
 7
8
     class modem_data
9
10
       public:
11
         void send();
12
          void rcv():
13
14
15
     class modem_impl
16
17
       private:
18
          modem_connection connection;
19
          modem_data
                           data:
20
```


Single Responsibility Principle

Caution:

- Too much splitting of modules can lead to an overly complicated design.
- If the code does not change in a way that the two responsibilities change at different times, then there's no need to separate.


- ▶ "Open for Extension"
 - ▶ Behavior of the module can be extended through extension
- "Closed for Modification"
 - Extending the behavior requires no change in source code or binary executables.

Open Closed Principle



- Client depends on server
- Changing server requires modification of client
- Use of clients with different servers requires duplication of code

Open Closed Principle



► Enables client implementations for multiple servers

Open Closed Principle

```
1
   2
   enum shape_type_t { circle, square };
3
   struct shape_s {
4
     shape_type_t shape_type;
5
6
   8
   #include "shape.h"
9
   struct circle_s {
10
     shape_type_t shape_type;
11
     double
             radius:
12
     point
            center:
13
14
15
   void drawCircle(struct circle_s *);
16
17
   18
   #include "shape.h"
19
   struct square_s {
20
     shape_type_t shape_type;
21
     double
             side:
22
     point top_left;
23
24
25
   void drawSquare(struct square s *):
```

Open Closed Principle

```
1
2
3
    typedef struct shape_t *shape_pointer_t;
4
5
    void DrawAllShapes(shape_pointer_t *shapes, int n)
6
7
        for (int i = 0; i < nl i++) {
8
           struct shape_s *s = shapes[i];
9
           switch (shape->shape_type) {
10
           case circle:
11
              drawCircle((struce circle_s *)shape);
12
              break:
13
           case square:
              drawSquare((struce square_s *)shape);
14
15
              break:
16
17
18
```

Rotting Code Class Design Package Design Architecture Design Conclusion

Open Closed Principle

```
2
   enum shape_type_t { circle, square };
3
   void (*DrawFunction)(void *):
4
   struct shape_s {
5
     DrawFunction draw;
6
7
   void DrawShape(void *);
8
9
   void DrawShape(void * shape_in){
11
     shape = (struct shape_s *) shape_in;
12
     shape.draw(shape in):
13
14
15
   16
   struct circle s {
17
     DrawFunction draw;
18
     double
             radius;
19
     point
            center:
20
21
22
   void drawCircle(struct circle s *):
23
24
   25
   struct square_s {
26
     DrawFunction draw:
27
     double
             side:
28
           top_left;
     point
29
30
31
   void drawSquare(struct square_s *);
```

stroduction Rotting Code Class Design Package Design Architecture Design Conclusion

Open Closed Principle

```
1
2
3
    typedef struct shape_t *shape_pointer_t;
4
5
    void DrawAllShapes(shape_pointer_t *shapes, int n)
6
7
       for (int i = 0; i < nl i++) {
8
         struct shape_s *shape = shapes[i];
9
         DrawShape(shape);
10
11
```

roduction Rotting Code Class Design Package Design Architecture Design Conclusion


Liskov Substitution Principle

roduction Rotting Code Class Design Package Design Architecture Design Conclusion


Interface Segregation Principle

Dependency Inversion Principle


Depend upon abstractions. Do not depend upon concretions.



troduction Rotting Code Class Design Package Design Architecture Design Conclusion



stroduction Rotting Code Class Design Package Design Architecture Design Conclusion



oduction Rotting Code Class Design Package Design Architecture Design Conclusio

Principles of Package Architecture

Package Principles

- Package Cohesion
 - Release Reuse Equivalency Principle (REP)
 - Common Closure Principle (CCP)
 - Common Reuse Principle (CRP)
- Package Coupling
 - Acyclic Dependencies Principle (ADP)
 - Stable Dependencies Principle (SDP)
 - Stable Abstractions Principle (SAP)

Principles of Package Architecture

roduction Rotting Code Class Design Package Design Architecture Design Conclusion

Principles of Package Architecture

References

- https://fi.ort.edu.uy/innovaportal/file/2032/1/ design_principles.pdf
- http://www.butunclebob.com/ArticleS.UncleBob. PrinciplesOfOod
- http://notherdev.blogspot.com/2013/07/ code-smells-rigidity.html
- https:
 //dev.to/bob/how-do-you-know-your-code-is-bad
- http://staff.cs.utu.fi/~jounsmed/doos_06/slides/ slides_060321.pdf
- ▶ https://softwareengineering.stackexchange.com/questions/357127/clear-examples-for-code-smells

Questions