## VLAN & Trunking w/ DHCP using 3 Routers

```
Create VLANs:
Switch# configure terminal
Switch(config)# vlan 10
Switch(config-vlan)# name Sales
Switch(config-vlan)# exit
Switch(config)# vlan 20
Switch(config-vlan)# name Marketing
Switch(config-vlan)# exit
Switch(config)# vlan 30
Switch(config-vlan)# name HR
Switch(config-vlan)# exit
Assign Access Ports to VLANs:
On Switch 1:
Switch(config)# interface range fastEthernet 0/1-10
Switch(config-if-range)# switchport mode access
Switch(config-if-range)# switchport access vlan 10
Switch(config-if-range)# exit
Switch(config)# interface range fastEthernet 0/11-20
Switch(config-if-range)# switchport mode access
Switch(config-if-range)# switchport access vlan 20
Switch(config-if-range)# exit
Switch(config)# interface range fastEthernet 0/21-24
Switch(config-if-range)# switchport mode access
Switch(config-if-range)# switchport access vlan 30
Switch(config-if-range)# exit
On Switch 2 (similar configuration for access ports on Switch 2):
Switch(config)# interface range fastEthernet 0/1-10
Switch(config-if-range)# switchport mode access
Switch(config-if-range)# switchport access vlan 10
Switch(config-if-range)# exit
Switch(config)# interface range fastEthernet 0/11-20
```

Switch(config-if-range)# switchport mode access

Switch(config-if-range)# switchport access vlan 20

```
Switch(config-if-range)# exit
```

Switch(config)# interface range fastEthernet 0/21-24
Switch(config-if-range)# switchport mode access
Switch(config-if-range)# switchport access vlan 30
Switch(config-if-range)# exit

Trunk Between Switch 1 and Switch 2

On Switch 1 (assuming gigabitethernet 0/2 connects to Switch 2):
Switch(config)# interface gigabitethernet 0/2
Switch(config-if)# switchport mode trunk
Switch(config-if)# switchport trunk allowed vlan 10,20,30
Switch(config-if)# exit

On Switch 2 (assuming gigabitethernet 0/2 connects to Switch 1):

Switch(config)# interface gigabitethernet 0/2
Switch(config-if)# switchport mode trunk
Switch(config-if)# switchport trunk allowed vlan 10,20,30
Switch(config-if)# exit

On Switch 2 (assuming gigabitethernet 0/1 connects to Switch 3):

Switch(config)# interface gigabitethernet 0/1
Switch(config-if)# switchport mode trunk
Switch(config-if)# switchport trunk allowed vlan 10,20,30
Switch(config-if)# exit

On Switch 3 (assuming gigabitethernet 0/2 connects to Switch 2):

Switch(config)# interface gigabitethernet 0/2
Switch(config-if)# switchport mode trunk
Switch(config-if)# switchport trunk allowed vlan 10,20,30
Switch(config-if)# exit

Trunk Between Router and Switch 1
On Switch 1 (assuming gigabitethernet 0/1 connects to the router's gigabitEthernet 0/0):

```
Switch(config)# interface gigabitethernet 0/1
Switch(config-if)# switchport mode trunk
Switch(config-if)# switchport trunk allowed vlan 10,20,30
Switch(config-if)# exit
```

Enable Sub-Interfaces on gigabitEthernet 0/0 for Each VLAN:
This sets up sub-interfaces for VLAN 10 and VLAN 20 with IP addresses for each subnet.

Router> enable
Router# configure terminal
Router(config)# interface gigabitEthernet 0/0
Router(config-if)# no shutdown
Router(config-if)# exit

Router(config)# interface gigabitEthernet 0/0.10
Router(config-subif)# encapsulation dot1Q 10
Router(config-subif)# ip address 192.168.10.1 255.255.255.0
Router(config-subif)# exit

Router(config)# interface gigabitEthernet 0/0.20
Router(config-subif)# encapsulation dot1Q 20
Router(config-subif)# ip address 192.168.20.1 255.255.255.0
Router(config-subif)# exit

Router(config)# interface gigabitEthernet 0/0.30
Router(config-subif)# encapsulation dot1Q 30
Router(config-subif)# ip address 192.168.30.1 255.255.255.0
Router(config-subif)# exit

Configure DHCP Pools on the Router:

Set up DHCP pools for each VLAN to provide IP addresses to clients on each subnet.

Router(config)# ip dhcp pool Sales
Router(dhcp-config)# network 192.168.10.0 255.255.255.0
Router(dhcp-config)# default-router 192.168.10.1
Router(dhcp-config)# dns-server 1.1.1.1 / 8.8.8.8
Router(dhcp-config)# exit

Router(config)# ip dhcp pool Marketing
Router(dhcp-config)# network 192.168.20.0 255.255.255.0

```
Router(dhcp-config)# default-router 192.168.20.1
Router(dhcp-config)# dns-server 1.1.1.1 / 8.8.8.8
Router(dhcp-config)# exit
```

Router(config)# ip dhcp pool HR

Router(dhcp-config)# network 192.168.30.0 255.255.255.0

Router(dhcp-config)# default-router 192.168.30.1

Router(dhcp-config)# dns-server 1.1.1.1 / 8.8.8.8

Router(dhcp-config)# exit

Exclude the Router's IP Addresses from the DHCP Pool:

Router(config)# ip dhcp excluded-address 192.168.10.1 Router(config)# ip dhcp excluded-address 192.168.20.1 Router(config)# ip dhcp excluded-address 192.168.30.1

Verify the Configuration Verify trunking

Switch# show interfaces trunk

Verify VLAN assignment

Switch# show vlan brief

## On the Router:

Verify sub-interface status

Router# show ip interface brief

## Disable Inter-VLAN Routing:

 Run this command to prevent the router from routing traffic between sub-interfaces.

Router(config)# no ip routing