## Chapter 3. Transport Layer

# Chapter 3: Transport Layer

#### Our goals:

- understand principles behind transport layer services:
  - multiplexing/demultiplexing
  - reliable data transfer
  - flow control
  - congestion control

- learn about transport layer protocols in the Internet:
  - UDP: connectionless transport
  - TCP: connection-oriented transport
  - TCP congestion control


# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
  - send side: breaks app messages into segments, passes to network layer
  - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
  - Internet: TCP and UDP



# Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
  - relies on, enhances, network layer services

#### Household analogy:

- 12 kids sending letters to 12 kids
- processes = kids
- app messages = letters in envelopes
- hosts = houses
- \* transport protocol = Ann and Bill who demux to in-house siblings
- network-layer protocol = postal service

## Internet transport-layer protocols

- reliable, in-order delivery (TCP)
  - congestion control
  - flow control
  - connection setup
- unreliable, unordered delivery: UDP
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# Multiplexing/demultiplexing


#### <u>Demultiplexing at rcv host:</u>

delivering received segments to correct socket

= socket = process


#### Multiplexing at send host:

gathering data from multiple sockets, enveloping data with header (later used for demultiplexing)



## How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries 1 transport-layer segment
  - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

# Connectionless demultiplexing

recall: create sockets with host-local port numbers:

```
DatagramSocket mySocket1 = new
   DatagramSocket(12534);
DatagramSocket mySocket2 = new
   DatagramSocket(12535);
```


recall: when creating datagram to send into UDP socket, must specify

(dest IP address, dest port number)

- when host receives UDP segment:
  - checks destination port number in segment
  - directs UDP segment to socket with that port number
- IP datagrams with different source IP addresses and/or source port numbers directed to same socket

## Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket (6428);




SP provides "return address"

### Connection-oriented demux


- TCP socket identified by 4-tuple:
  - source IP address
  - source port number
  - dest IP address
  - dest port number
- recv host uses all four values to direct segment to appropriate socket

- server host may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
- web servers have different sockets for each connecting client
  - non-persistent HTTP will have different socket for each request

# Connection-oriented demux (cont)



# Connection-oriented demux: Threaded Web Server



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

### <u>UDP: User Datagram Protocol [RFC 768]</u>

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out of order to app
- connectionless:
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

#### Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

### UDP: more

 often used for streaming multimedia apps


loss tolerant

rate sensitive

other UDP uses

- DNS
- SNMP
- reliable transfer over UDP: add reliability at application layer
  - application-specific error recovery!

Length, in bytes of UDP segment, including header



UDP segment format

## UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

#### Sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field


#### Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected.
     But maybe errors
     nonetheless? More later

....

## Internet Checksum Example

- Note: when adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers




# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

## Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


## Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Reliable data transfer: getting started



### Reliable data transfer: getting started


#### We'll:

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- \* consider only unidirectional data transfer
  - but control info will flow on both directions!
- \* use finite state machines (FSM) to specify sender, receiver

event causing state transition actions taken on state transition state: when in this state state "state" next state event uniquely determined actions by next event

### Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - no bit errors
  - no loss of packets
- \* separate FSMs for sender, receiver:
  - sender sends data into underlying channel
  - receiver read data from underlying channel



receiver

### Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- \* the question: how to recover from errors:

How do humans recover from "errors" during conversation?

### Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- \* the question: how to recover from errors:
  - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
  - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
  - sender retransmits pkt on receipt of NAK
- \* new mechanisms in rdt2.0 (beyond rdt1.0):
  - error detection
  - receiver feedback: control msgs (ACK,NAK) rcvr->sender


## rdt2.0: FSM specification

rdt\_send(data) sndpkt = make\_pkt(data, checksum) udt\_send(sndpkt) rdt\_rcv(rcvpkt) && isNAK(rcvpkt) Wait for Wait for call from ACK or udt\_send(sndpkt) NAK above rdt\_rcv(rcvpkt) && isACK(rcvpkt) Λ sender


#### receiver

rdt\_rcv(rcvpkt) && corrupt(rcvpkt) udt send(NAK) Wait for call from below rdt\_rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt,data) deliver\_data(data) udt\_send(ACK)

## rdt2.0: operation with no errors



### rdt2.0: error scenario



### rdt2.0 has a fatal flaw!

#### What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


#### Handling duplicates:

- \* sender retransmits current pkt if ACK/NAK garbled
- \* sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

#### stop and wait

Sender sends one packet, then waits for receiver response

### rdt2.1: sender, handles garbled ACK/NAKs



### rdt2.1: receiver, handles garbled ACK/NAKs

rdt rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq0(rcvpkt) extract(rcvpkt,data) deliver\_data(data) sndpkt = make pkt(ACK, chksum) udt\_send(sndpkt) rdt\_rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make\_pkt(NAK, chksum) udt\_send(sndpkt) Wait for Wait foi 0 from 1 from rdt\_rcv(rcvpkt) && below, not corrupt(rcvpkt) && below has seq1(rcvpkt) sndpkt = make pkt(ACK, chksum) udt\_send(sndpkt) rdt\_rcv(rcvpkt) && notcorrupt(rcvpkt) && has\_seq1(rcvpkt) extract(rcvpkt,data) deliver\_data(data) sndpkt = make\_pkt(ACK, chksum)

udt send(sndpkt)

rdt\_rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make\_pkt(NAK, chksum) udt\_send(sndpkt)

rdt\_rcv(rcvpkt) && not corrupt(rcvpkt) && has\_seq0(rcvpkt)

sndpkt = make\_pkt(ACK, chksum) udt send(sndpkt)

## rdt2.1: discussion

#### Sender:

- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "current" pkt has 0 or 1 seq. #


#### Receiver:

- \* must check if received packet is duplicate
  - state indicates whether O or 1 is expected pkt seq#
- \* note: receiver can not know if its last ACK/NAK received OK at sender

## rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

## rdt2.2: sender, receiver fragments




## rdt3.0: channels with errors and loss


#### New assumption:

- underlying channel can also lose packets (data or ACKs)
  - checksum, seq. #, ACKs, retransmissions will be of help, but not enough
- Approach: sender waits "reasonable" amount of time for ACK
- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but use of seq. #'s already handles this
  - receiver must specify seq # of pkt being ACKed
- requires countdown timer


## rdt3.0 sender




## rdt3.0 in action



(a) operation with no loss



## rdt3.0 in action



## Performance of rdt3.0

- rdt3.0 works, but performance stinks
- \* ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microseconds}$$

U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- if RTT=30 msec, 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- network protocol limits use of physical resources!

# rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

# Pipelined protocols

pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

two generic forms of pipelined protocols: go-Back-N, selective repeat

# Pipelining: increased utilization



# Pipelined Protocols

## Go-back-N: big picture:

- \* sender can have up to N unacked packets in pipeline
- rcvr only sends cumulative acks
  - doesn't ack packet if there's a gap
- \* sender has timer for oldest unacked packet
  - if timer expires, retransmit all unack'ed packets


## Selective Repeat: big pic

- \* sender can have up to N unack'ed packets in pipeline
- rcvr sends individual ack for each packet
- sender maintains timer for each unacked packet
  - when timer expires, retransmit only unack'ed packet

# Go-Back-N

#### Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
  - may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

## GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextsegnum])
                          if (base == nextsegnum)
                            start timer
                          nextseqnum++
                       else
   Λ
                         refuse_data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt_send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt_send(sndpkt[nextsegnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                            start_timer
```


## GBN: receiver extended FSM



## ACK-only: always send ACK for correctly-received pkt with highest in-order seq #

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order pkt:
  - discard (don't buffer) -> no receiver buffering!
  - Re-ACK pkt with highest in-order seq #


# GBN in action



# Selective Repeat

- \* receiver individually acknowledges all correctly received pkts
  - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
  - sender timer for each unACKed pkt
- sender window
  - N consecutive seq #'s
  - again limits seq #s of sent, unACK'ed pkts

## Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

# Selective repeat

#### -sender

#### data from above:

if next available seq # in window, send pkt

#### timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase, sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

#### receiver

pkt n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

**⋄** ACK(n)

#### otherwise:

ignore


## Selective repeat in action



## Selective repeat: dilemma

## Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



# Chapter 3 outline


- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte steam:
  - no "message boundaries"
- pipelined:
  - TCP congestion and flow control set window size
- send & receive buffers



## full duplex data:

- bi-directional data flow in same connection
- MSS: maximum segment size

#### connection-oriented:

handshaking (exchange of control msgs) inits sender, receiver state before data exchange

#### flow controlled:

sender will not overwhelm receiver

# TCP segment structure


URG: urgent data (generally not used)

> ACK: ACK # valid

PSH: push data now (generally not used)

> RST, SYN, FIN: connection estab (setup, teardown commands)

> > Internet checksum' (as in UDP)



counting by bytes of data (not segments!)

> # bytes rcvr willing to accept


# TCP seq. #'s and ACKs

#### <u>Seq. #'s:</u>

byte stream "number" of first byte in segment's data

#### ACKs:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
  - A: TCP spec doesn't say, - up to implementor



simple telnet scenario

# Practice:

- Suppose A sends two TCP segments backto-back to B. The first segment has sequence number 90; the second has sequence number 110
  - a) How much data is the first segment?
  - b) Suppose that the first segment arrives at B.
     In the acknowledgement that B sends to A,
     what will be the acknowledgment number?

# TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- longer than RTT
  - but RTT varies
- \* too short: premature timeout
  - unnecessary retransmissions
- \* too long: slow reaction to segment loss

- Q: how to estimate RTT?
- \* SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT


# TCP Round Trip Time and Timeout

```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
```

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- \* typical value:  $\alpha = 0.125$

# Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



# TCP Round Trip Time and Timeout

## Setting the timeout

- EstimatedRTT plus "safety margin"
  - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

#### Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- pipelined segments
- cumulative acks
- \* TCP uses single retransmission timer

- \* retransmissions are triggered by:
  - timeout events
  - duplicate acks
- initially consider simplified TCP sender:
  - ignore duplicate acks
  - ignore flow control, congestion control

## TCP sender events:

## data rcvd from app:

- Create segment with seq#
- seq # is byte-stream number of first data byte in segment
- \* start timer if not already running (think of timer as for oldest unacked segment)
- expiration interval: TimeOutInterval

#### timeout:

- retransmit segment that caused timeout
- \* restart timer

#### Ack rcvd:

- If acknowledges previously unacked segments
  - update what is known to be acked
  - start timer if there are outstanding segments


```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSeqNum
      if (timer currently not running)
         start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
      start timer
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```

# TCP sender (simplified)


#### Comment:

- SendBase-1: last cumulatively acked byte <u>Example:</u>
- SendBase-1 = 71;
  y= 73, so the rcvr
  wants 73+;
  y > SendBase, so
  that new data is
  acked

## TCP: retransmission scenarios



# TCP retransmission scenarios (more)



Cumulative ACK scenario

# TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send duplicate ACK, indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment starts at lower end of gap

# Fast Retransmit

- time-out period often relatively long:
  - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
  - sender often sends many segments back-toback
  - if segment is lost, there will likely be many duplicate ACKs.

- if sender receives 3
  ACKs for the same
  data, it supposes that
  segment after ACKed
  data was lost:
  - fast retransmit: resend segment before timer expires




Figure 3.37 Resending a segment after triple duplicate ACK
Transport Layer 3-73

## Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
          if (y > SendBase) {
             SendBase = y
              if (there are currently not-yet-acknowledged segments)
                 start timer
          else {
               increment count of dup ACKs received for y
               if (count of dup ACKs received for y = 3) {
                   resend segment with sequence number y
```

a duplicate ACK for already ACKed segment

fast retransmit

## Consideration

\* We saw that TCP waits until it has received three duplicate ACKs before performing a fast retransmit. Why do you think the TCP designers chose not to perform a fast retransmit after the first duplicate ACK for a segment is received?


## Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP Flow Control

receive side of TCP connection has a receive buffer:




 app process may be slow at reading from buffer

#### flow control-

sender won't overflow receiver's buffer by transmitting too much, too fast

 speed-matching service: matching the send rate to the receiving app's drain rate

### TCP Flow control: how it works



(suppose TCP receiver discards out-of-order segments)

- spare room in buffer
- = RcvWindow

- rcvr advertises spare room by including value of RcvWindow in segments
- sender limits unACKed data to RcvWindow
  - guarantees receive buffer doesn't overflow

## Consideration

What is the relationship between the variable LastByteRcvd and the variable y in section 3.5.4

## Problems caused by flow control

- When RecvWin=0, sender doesn't send data. How does the sender restart to send?
- ❖ TCP's Solution: RecvWin management is not directly tied to the acks. When RecvWin=0, sender doesn't send data unless (1)urgent data; (2)1-byte segment to make the receiver announce next window size.

## TCP Transmission Policy(1)

- The trade-off in determining the optimal size of TCP segments.
  - Too large: IP level fragment
  - Too small: Reduce communication Performance


## TCP Transmission Policy(2)

- Problem1: Application data come in byteby-byte at sender. (Recall telnet)
- Nagle's algorithm: send the first byte, wait for ACK, and accumulate bytes in buffer.

## TCP Transmission Policy(3)

- Problem2:silly window syndrome.
  - The receiver receives a large block->buffer is full;
  - The app reads buffer byte-by-byte -> receiver sends one window update to sender after processing one byte -> sender sends data byte by byte.

## TCP Transmission Policy(4)



Silly Window Syndrome

## TCP Transmission Policy(5)

Clark's solution: receiver waits until it has a decent amount of buffer available. The receiver should not send a window update until it can handle the MSS.

## Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

### TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
  - seq. #s
  - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator Socket clientSocket = new Socket ("hostname", "port number");
- server: contacted by client Socket connectionSocket = welcomeSocket.accept();

#### Three way handshake:

- Step 1: client host sends TCP SYN segment to server
  - specifies initial seq #
  - no data
- **Step 2:** server host receives SYN, replies with SYNACK segment
  - server allocates buffers
  - specifies server initial seq.#
- <u>Step 3:</u> client receives SYNACK, replies with ACK segment, which may contain data


### TCP Connection Management (cont.)

#### Closing a connection:

client closes socket: clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




### TCP Connection Management (cont.)

**Step 3:** client receives FIN, replies with ACK.


> Enters "timed wait" will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



## TCP Connection Management (cont)



## Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


## Principles of Congestion Control


#### Congestion:


- \* informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- a top-10 problem!

### Causes/costs of congestion: scenario 1

- two senders, two receivers
- one router, infinite buffers
- \* no retransmission








- large delayswhen congested
- maximum achievable throughput


### Causes/costs of congestion: scenario 2


- one router, finite buffers
- sender retransmission of timed-out packet
  - application-layer input = application-layer output:  $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes retransmissions:  $\lambda'_{in} \geq \lambda_{in}$



### Congestion scenario 2a: ideal case


\* sender sends only when router buffers available






### Congestion scenario 2b: known loss


- packets may get dropped at router due to full buffers
  - sometimes lost
- \* sender only resends if packet known to be lost (admittedly idealized)



### Congestion scenario 2b: known loss


- packets may get dropped at router due to full buffers
  - sometimes not lost
- sender only resends if packet known to be lost (admittedly idealized)






## Congestion scenario 2c: duplicates


- packets may get dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





### Congestion scenario 2c: duplicates

- packets may get dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




#### "costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
  - decreasing goodput


### Causes/costs of congestion: scenario 3

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as  $\lambda_{in}$  and  $\lambda'_{in}$  increase ?



### Causes/costs of congestion: scenario 3



#### another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

### Approaches towards congestion control

Two broad approaches towards congestion control:

## end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

# network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate sender should send at

### Case study: ATM ABR congestion control


#### ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
  - sender should use available bandwidth
- if sender's path congested:
  - sender throttled to minimum guaranteed rate

## RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
  - NI bit: no increase in rate (mild congestion)
  - CI bit: congestion indication
- \* RM cells returned to sender by receiver, with bits intact

### Case study: ATM ABR congestion control



- \* two-byte ER (explicit rate) field in RM cell
  - congested switch may lower ER value in cell
  - sender' send rate thus maximum supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
  - if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

## Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP congestion control: additive increase, multiplicative decrease


 approach: increase transmission rate (window size), probing for usable bandwidth, until loss occurs

 additive increase: increase cwnd by 1 MSS every RTT until loss detected

multiplicative decrease: cut cwnd in half after

loss

saw tooth behavior: probing for bandwidth



## TCP Congestion Control: details

sender limits transmission:LastByteSent-LastByteAcked

≤ cwnd

roughly,

rate = 
$$\frac{\text{cwnd}}{\text{RTT}}$$
 Bytes/sec

 cwnd is dynamic, function of perceived network congestion

# How does sender perceive congestion?


- loss event = timeout or3 duplicate acks
- TCP sender reduces rate (cwnd) after loss event

#### three mechanisms:

- AIMD
- slow start
- conservative after timeout events

## TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = 1 MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



## Refinement: inferring loss

- after 3 dup ACKs:
  - cwnd is cut in half
  - window then grows linearly
- but after timeout event:
  - cwnd instead set to 1 MSS;
  - window then grows exponentially
  - to a threshold, then grows linearly


#### Philosophy:

- 3 dup ACKs indicates
   network capable of
   delivering some segments
- timeout indicates a "more alarming" congestion scenario

### Refinement

Q: when should the exponential increase switch to linear?


A: when cwnd gets to 1/2 of its value before timeout.



#### Implementation:

- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event

## Summary: TCP Congestion Control



## TCP throughput

- \* what's the average throughout of TCP as a function of window size and RTT?
  - ignore slow start
- \* let W be the window size when loss occurs.
  - when window is W, throughput is W/RTT
  - just after loss, window drops to W/2, throughput to W/2RTT.
  - average throughout: .75 W/RTT

### TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms RTT, want 10
   Gbps throughput
- requires window size W = 83,333 in-flight segments
- throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- $\star$   $\rightarrow$  L = 2·10<sup>-10</sup> Wow a very small loss rate!
- new versions of TCP for high-speed

### TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



## Why is TCP fair?

#### two competing sessions:

- \* additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



## Fairness (more)

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - pump audio/video at constant rate, tolerate packet loss

## Fairness and parallel TCP connections

- nothing prevents app from opening parallel connections between 2 hosts.
- web browsers do this
- example: link of rate R supporting 9 connections;
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2!

## Chapter 3: Summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation and implementation in the Internet
  - UDP
  - TCP

#### Next:

- leaving the network "edge" (application, transport layers)
- into the network
  "core"