


Coil Library: Guide to Handling Images in Android Jetpack Compose




Beatrice Kinya



¥ @B_Kinya



in Beatrice Kinya



What is Coil?

- Coil is an image loading library, backed by Kotlin Coroutines
- It handles loading images from the internet
- · It can also cache images so that you do not have to download images several times







Time to Write Code

Up Next





Subcomposition

- Subcomposition changes the flow of compose layout.
- · Instead of composing its children in composition phase, it composes in layout phase.
- This makes subcomposition less performant compared to regular composition.
- Hence, use subcomposition only when you have to and in the parts of the UI where performance is not very critical
- Check out this article to learn more about subcomposition: https:// kinya.hashnode.dev/custom-compose-layouts-clf5ua9jw01mms1nv5k6d84zp





AsynclmagePainter

- Asynclmage and SubcomposeAsynclmage uses AsynclmagePainter under the hood.
- AsynclmagePainter is a Painter that executes ImageRequest asynchronously and renders result.
- If you want to use the Painter but cannot use AsyncImage, for instance in advanced animation, you'd use **AsyncImagePainter.**







Time to Write More Code 🌦 🚇

Up Next





AsynclmagePainter Cont'

- An image request needs size to determine the output image dimensions, i.e width and height.
- Compose resolves size during layout phase. Check Jetpack Compose docs to learn more about compose phases: https://developer.android.com/jetpack/compose/ layouts/basics.
- Therefore, AsyncImagePainter.State will be loading in the initial composition even if the image is already in memory.
- To ensure AsyncImagePainter.State is up-to-date in the first composition, set the image size on the image request or use SubcomposeAsyncImage.





AsynclmagePainter Cont'

- AsyncImagePainter will not finish loading if AsyncImagePainter.onDraw is not called
- This can occur if a composable has unbounded width and height constraints like LazyColumn or LazyRow.
- To use AsyncImagePainter with either of lazy layouts you can either:
 - Set bounded width or height respectively or
 - Set image size on the image request.





Set Bounded Width or Height on the Image

```
@Composable
fun ImagesList() {
    LazyColumn() {
        items(3) {
            val painter =
                rememberAsyncImagePainter(model = "<image_url>")
            Image(
                modifier = Modifier.width(300.dp).height(200.dp),
                painter = painter, contentDescription = "Top breed")
```





Set Image Size on ImageRequest

```
@Composable
fun ImagesList() {
    LazyColumn() {
        items(3) {
            val imageRequest = ImageRequest.Builder(LocalContext.current)
                .data("<Image Url>")
                .size(Size.ORIGINAL)
                .build()
            val painter =
                rememberAsyncImagePainter(model = imageRequest)
            Image(
                painter = painter, contentDescription = "Top breed")
```





Summary

- Using AsyncImage to load images
- SubcomposeAsyncImage
- · AsynclmagePainter an alternative to Asynclmage for loading images
- Transitions



