Properties of Matter

Dominik Szablonski

November 24, 2024

Contents

1	Properties of Solids and Liquids 4					
	1.1	Introduction	4			
	1.2	Elasticity of Solids	4			
		1.2.1 Young's Modulus	4			
		1.2.2 Shear Modulus	5			
		1.2.3 Bulk Modulus	5			
	1.3	Properties of Static Liquids	5			
		1.3.1 Hydrostatic Pressure	5			
		1.3.2 Buoyency and Archimedes Principle	6			
	1.4	Flow of Incompressible Liquid	6			
		1.4.1 Conservation of mass and the continuity equation	6			
		1.4.2 Bernoulli's Principle	7			
		1.4.3 Flow Properties and Viscocity	8			
	1.5	Liquid Surfaces	8			
		1.5.1 Liquids in a Container	8			
			10			
		OV.				
2	$Th\epsilon$		11			
	2.1	First law of thermodynamics	11			
		2.1.1 Cyclic Process	12			
		2.1.2 Quasistatic Process	12			
		2.1.3 Reversible Processes	12			
		2.1.4 Work Done	13			
		2.1.5 Heat Capacity	13			
		2.1.6 Adiabatic Processes	14			
	2.2	Second Law of Thermodynamics	15			
		2.2.1 Heat engines	15			
		2.2.2 Heat pumps and refrigirators	16			
		2.2.3 Carnot's Cycle	17			
		2.2.4 Statements of the Second Law	18			
	2.3		18			
		2.3.1 Proof	19			
		2.3.2 Mathematical definition of entropy	19			
		2.3.3 The law of increase in entropy	20			
		2.3.4 Thermally Isolated Systems	20			
		2.3.5 Entropy and Heat Capacity	20			
			21			
	2.4	v	21			
		2.4.1 Work Availability	21			
			22			
		Si .	22			
		94	22			
		- v	 23			
		·	- 24			
	2.5		$\frac{1}{24}$			
	-		$\frac{1}{24}$			

C0	ONTENTS			3	
	2.5.2	Clausius-Clapeyron Relation		25	
A	A Definitions				
В	Important	Misc. Facts		27	

Chapter 1

Properties of Solids and Liquids

1.1 Introduction

The kinetic energy per particle is $\approx k_B T$. Solids form when,

$$k_B T \ll \epsilon$$
 (1.1)

where ϵ is the binding energy. Further, liquids form when,

$$k_B T \approx \epsilon$$
 (1.2)

and gasses when,

$$k_B T >> \epsilon.$$
 (1.3)

1.2 Elasticity of Solids

Solids exibit elastic behaviour, i.e., when stress is applied they deform (strain) and return to their original shape once removed. The way solids resist strain is defined by elastic moduli, which are general defined,

Elastic Modulus =
$$\frac{\text{Stress}}{\text{Strain}}$$
. (1.4)

1.2.1 Young's Modulus

Definition. E - The ability of a solid to resist forces along a given axis.

Consider a setup like in fig. 1.1. Stress is given by, $\frac{F}{A}$ and strain by, $\frac{\Delta l}{l}$ where Δl is the deformation along the axis of the force. We then have,

$$E = \frac{F}{A} \left(\frac{\Delta l}{l}\right)^{-1}.$$
(1.5)




Figure 1.1: Solid underegoing deformation due to a force along its axis.




Figure 1.2: A solid undergoing shearing due to a force parallel to and along one of its faces.




Figure 1.3: A solid of volume V being compressed by a force, dF, leading to an infinitesimal change in its volume dV.

1.2.2 Shear Modulus

Definition. G - The ability of a solid to resist shearing when a force is applied parallel to the surface of the solid.

Consider a setup like in fig. 1.2. If the solid shears by Δx due to a force F, then its strain is,

$$\frac{\Delta x}{l} = \tan \theta \cong \theta \tag{1.6}$$

for small θ . The shear modulus is then,

$$G = \frac{F}{A} \left(\frac{\Delta x}{l}\right)^{-1} = \frac{F}{A\theta} \,. \tag{1.7}$$

1.2.3 Bulk Modulus

Definition. K - Resistance of a material to compression.

The bulk modulus describes the stress due to a change in pressure dP. If we consider a setup like in fig. 1.3, the change in volume is -dV, the strain is dV/V, so the bulk modulus is,

$$K = -V \frac{\mathrm{d}P}{\mathrm{d}V} \,. \tag{1.8}$$

The minus sign indicates that an increase in pressure results in a decrease in volume.

1.3 Properties of Static Liquids

1.3.1 Hydrostatic Pressure

Consider a column of liquid of constant density ρ_l , a depth d, and cross-sectional area A as in fig. 1.4. Since the liquid is static (no net flow), we have $F_{\text{net}} = 0$. The force at d is then,

$$F = P_0 A + \rho dg A = P(d) A m \tag{1.9}$$

so the pressure at d is,

$$P(d) = P_0 + \rho g d \,. \tag{1.10}$$

 \implies as d increases linearly, so does P.




Figure 1.4: A column of liquid of constant density ρ , vertical height h_0 , and cross-sectional area A.




Figure 1.5: An arbitrary hollow shape of volume V filled with liquid of density ρ , immersed in a liquid of the same density.

1.3.2 Buoyency and Archimedes Principle

Consider an arbitrary hollow shape of volume V filled with liquid of density ρ_l , immersed in a liquid of the same density, as in fig. 1.5. The weight of the object is given by,

$$F_w = \rho_l V g. \tag{1.11}$$

The pressure acting on the body must be equal and opposite to its weight. We call this the *buoyency* force,

$$F_b = \rho_l V g. \tag{1.12}$$

The buoyency force is equal and opposite to the weight of the liquid displaced. I.e., in the case that the mass has a density ρ_b such that $\rho_l > \rho_b$, the force it feels is still of the form eq. (1.12), so will float above the surface of the water.

1.4 Flow of Incompressible Liquid

The molecules in a liquid or gas can easily flow, with the same time and position dependent velocity, $\mathbf{v}(\mathbf{r},t)$.

1.4.1 Conservation of mass and the continuity equation

The rate of mass flow through an area element of a surface d**S** is $\rho \mathbf{v} \cdot d\mathbf{S}$. The rate of mass flow into a volume bounded by a surface S is this expression evaluated over all space,

$$\frac{\mathrm{d}m}{\mathrm{d}t} = \rho \int_{S} \mathbf{v} \cdot \mathrm{d}\mathbf{S} \,. \tag{1.13}$$

For a liquid of constant density, eq. (1.13) must equal 0,

$$\int_{S} \mathbf{v} \cdot d\mathbf{S} = 0 \tag{1.14}$$




Figure 1.6: Frictionless pipe of arbitrary shape, with each end at a diffferent height h_1 and h_2 such that $h_2 < h_1$.

and by the divergence theorem,

$$\nabla \cdot \mathbf{v} = 0 \tag{1.15}$$

In the case of compressible liquids (i.e., where $\rho = \rho(\mathbf{r})$), conservation of mass is satisfied via the continuity equation,

$$\boxed{\frac{\partial \rho}{\partial t} + \boldsymbol{\nabla} \cdot (\rho \mathbf{v}) = 0}.$$
(1.16)

1.4.2 Bernoulli's Principle

We will investigate how pressure of a liquid depends on flow speed. We assume no surface or iscous forces, and we assume flow is time independent, i.e., $\mathbf{v} = \mathbf{v}(\mathbf{r})$.

Particles will flow in streamlines. Consider adjacent streamlines which form a tube of arbitrary shape, where each end is at a different vertical height, h_1 and h_2 such that $h_2 < h_1$, and there is no flow in or out of the tube, as in fig. 1.6. The liquid enters at height h_1 , with velocity v_1 , pressure P_1 , through an area A_1 . The liquid leaves at height h_1 , with velocity h_2 , pressure P_2 , through an area A_2 .

From the conservation of mass,

$$v_1 A_1 = v_2 A_2. (1.17)$$

In a time dt, the work done by pressure P_1 on the liquid at entry is,

$$dW_1 = P_1 A_1 v_1 dt (1.18)$$

and similarly for the exit,

$$dW_2 = P_2 A_2 v_2 dt. (1.19)$$

The kinetic energy of the liquid is,

$$dK_1 = \frac{1}{2} (\rho v_1 A_1 dt) v_1^2, \qquad (1.20)$$

and the potential energy,

$$dV = (\rho v_1 A_1 dt) gh_1, \tag{1.21}$$

and similarly for the exit. By conservation of energy,

$$dW_1 + dK_1 + dV_1 = dW_2 + dK_2 + dV_2$$

$$A_1 v_1 \left(P_1 + \frac{1}{2} \rho v_1^2 + \rho g h_1 \right) dt = A_2 v_2 \left(P_2 + \frac{1}{2} \rho v_2^2 + \rho g h_2 \right) dt$$
(1.22)

By eq. (1.17), we can divide eq. (1.22) by $A_1v_1 dt$,

$$P_1 + \frac{1}{2}\rho v_1^2 + \rho g h_1 = P_2 + \frac{1}{2}\rho v_2^2 + \rho g h_2$$
 (1.23)

which leads to Bernoulli's equation,

$$P(h,v) + \rho gh + \frac{1}{2}\rho v^2 = \text{constant}$$
(1.24)

 \implies faster moving liquids have lower pressure.

1.4.3 Flow Properties and Viscocity

Laminar Flow

Definition. Smooth, regular streamlines that are locally parallel to each other

The drag force on a spherical object of radius R insterted into a liquid under laminar flow is caused by the liquid's resistance to shearing, and is given by Stoke's law,

$$\boxed{\mathbf{F}_D = 6\pi\nu R\mathbf{v}}\tag{1.25}$$

where ν is the viscocity of the liquid.

Turbulent Flow

Definition. Streamlines are irregular and chaotic du to formation of eddies in the flow.

The drag force on an object placed in the stream ocurs due to the inertial force required to push the liquid out of the way of the object. The drag force is given by,

$$\boxed{\mathbf{F}_D = \frac{1}{2}\rho v^2 C_D A\hat{\mathbf{v}}} \tag{1.26}$$

where A is the cross-sectional area of the object and C_D is a dimensionaless drag coefficiant.

Laminar-Turbulent Transition and Reynold's Number

Whether a liquid expriences laminar or turbulent flow depends on the ratio of inertial force to viscous force. This ratio is given by Reynold's number,

$$Re = \frac{\rho L v}{\nu} \tag{1.27}$$

where L is the length of the object moving through the liquid.

1.5 Liquid Surfaces

Free Surface: The surface interface of a liquid is characterised by the surface free energy γ . This is the energy required to increase the surface area of the interface.

Liquid-Liquid Interface: At the interface between two liquids, it is only energetically favourable for them to mix if $\gamma < 0$.

Liquid-Solid Interface: For $\gamma < 0$, it is energetically favourable for the liquid to spread over the surface of the solid.

1.5.1 Liquids in a Container

Contact Angle

We are interested in the way a liquid-gas interface meets the solid wall of a container. The shape of the liquid near the wall is known as the meniscus, as in fig. 1.7. We can approximate the meniscus as linear, wehre the liquid meets the wall at the contact angle θ , at a height h, and horizontal distance l from the surface of the liquid.

Let us consider the following surface-free energies,




Figure 1.7

- 1. Solid-gas γ_{sg} ,
- 2. Solid-liquid γ_{sl} ,
- 3. Liquid-gas γ_{lq} .

The meniscus free energy (per unit length of the meniscus, thus having dimensions of force) is given by,

$$F_{\text{men}} = (\gamma_{sl} - \gamma_{sg}) + \gamma_{lg} \left(\sqrt{h^2 + l^2} - l \right). \tag{1.28}$$

The free energy is minimised when,

$$\frac{\partial F_{\text{men}}}{\partial h} = (\gamma_{sl} - \gamma_{sg}) + \gamma_{lg} \left(\frac{1}{2} \frac{2h}{\sqrt{h^2 + l^2}} \right) = 0.$$
 (1.29)

We have that,

$$\frac{h}{\sqrt{h^2 + l^2}} = \cos \theta \tag{1.30}$$

which allows us to find Young's equation relating contact angle to surface free energy,

$$\gamma_{lg}\cos\theta = \gamma_{sg} - \gamma_{sl}. \tag{1.31}$$

Capillary Action

This occurs when a column of liquid is placed in a narrow tube. Consider a tube of radius R at height h relative to the surface of the bulk liquid. The surface free energy gain is,

$$\Delta F_s = 2\pi r h \left(\gamma_{sl} - \gamma_{sq}\right) \tag{1.32}$$

while the increase in gravitational potential energy is,

$$\Delta F_g = \pi R^2 h \rho g \frac{h}{2} \tag{1.33}$$

where h/2 is used as that is the location of the centre of mass.

The total free energy is,

$$F = \Delta F_s + \Delta F_g = \frac{\pi}{2} R^2 h^2 \rho g + 2\pi R h \left(\gamma_{sl} - \gamma_{sg} \right)$$

$$\tag{1.34}$$

which is minimised when,

$$\frac{\partial F}{\partial h} = \pi R^2 h \rho g + 2\pi R \left(\gamma_{sl} - \gamma_{sg} \right) = 0, \tag{1.35}$$

which can be rearranged to give a function for h,

$$h = -\frac{2}{(\gamma_{sl} - \gamma_{sg})} \rho g R = \frac{2\gamma_{lg} \cos \theta}{\rho g R}$$
(1.36)

1.5.2 Surface Tension and Surface Free Energy

Consider a wire frame, with one side of length l, free to move in the x direction. A thing iglm of liquid covers the space within the frame and shifts teh wire a distacen dx in order of minimise the overall free energy.

The work done on the wire to move a distance dx due to a force F applied by the thin film of liquid is,

$$dW = F dx. (1.37)$$

The work also contributes to increasing the surface area of the liquid by,

$$dA = sl dx. (1.38)$$

The energy increase is given by,

$$dE_s = \gamma \, dA = 2\gamma l \, dx \,. \tag{1.39}$$

Equating eq. (1.37) and eq. (1.39) gives an expression for the surface tension,

$$F = 2\gamma l \tag{1.40}$$

Chapter 2

Thermodynamics

In this chapter we deal with analysing the macroscopic properties of objects composed of many microscopic atoms and particles. We will first consider an idea gas, i.e., one in which,

- the particles have no volume,
- and the particles have no interatomic forces acting between them.

This allows us to write down the ideal gas equation in two forms,

$$\underbrace{P}_{\text{Pressure}} \underbrace{Volume}_{\text{Volume}} \underbrace{n}_{\text{Moles}} \underbrace{R}_{\text{Temperature}} \underbrace{T}_{\text{Temperature}} \tag{2.1}$$

$$PV = \underbrace{N}_{\substack{\text{Number of} \\ \text{molecules}}} \underbrace{k_b}_{\substack{\text{constant}}} T. \tag{2.2}$$

1 mole of substance contains N_A (Avogadro's number) amount of molecules. We further have a relation between the molar gas constant and the Boltzman constant which states,

$$R = N_A k_b. (2.3)$$

In this course, we will often discuss 2 different variables,

- 1. **Intensive Variables** Value is not proportional to the amount of substance.
- 2. Extensive Variables Value is linearly proportional to the amount of substance.

2.1 First law of thermodynamics

Law 1.

$$\underbrace{\Delta E}_{\substack{Change \ in \\ internal \ energy}} = \underbrace{W}_{\substack{Work \ done \\ on \ the \ system}} + \underbrace{Q}_{\substack{Heat \ supplied \\ to \ a \ system}}$$
(2.4)

We say that E is a function of state, meaning that the value of E is path independent. For an ideal gas, we have that E = E(T) which is the energy due to the kinetic energy of the particles. If we take the limit as $\Delta E \to 0$,

$$dE = dQ + dW. (2.5)$$

Furthermore, W and Q are not functions of state, meaning that their values are path dependent. This means that,

$$\Delta E = W + Q \equiv \text{Const}$$
 (2.6)

however, W and Q will not be constant as they depend on the shape of the function they take on.




Figure 2.1

2.1.1 Cyclic Process

This is a process which starts and ends in the same equilibrium state, so there is no change in energy over the cycle,

$$\oint dE = E_{\text{final}} - E_{\text{initial}} = 0.$$
(2.7)

From the first law,

$$\oint dW + \oint dQ = 0$$
(2.8)

and thus,

$$\boxed{\oint dW = -\oint dQ} \tag{2.9}$$

for a cyclic process.

2.1.2 Quasistatic Process

This is a process that occurs so slowly that the system is always instantaneously in thermal equilibrium. For a quasistatic process, the force applied is approximately equal to the pressure of the fluid itself,

2.1.3 Reversible Processes

For a reversible process, we require,

- 1. The process must be quasistatic.
- 2. There is no external friction.
- 3. The process must not cause permanent change to the system.

Free expansion of an isolated gas

Let us consider a gas confined in a volume which is seperated in half, with the gas initially in only one part of the volume as in fig. 2.1. If we remove the partition instantaneously, we have,

$$W = 0$$
 $\Rightarrow \Delta E = 0.$ (2.11)

However, this process is non-reversible, as we have caused a permanent change to the system.

Isothermal expansion of an ideal gas

Now consider a setup as in fig. 2.2, where we use a piston to change the volume of the container, and we use a source to keep the temperature of the gas constant. We have,

$$W < 0$$
 $\Longrightarrow (Q + W) = 0$ $\Longrightarrow \Delta E = 0.$ (2.12)

This process is reversible given that,

- The piston is frictionless,
- The piston moves slowly.




Figure 2.2

2.1.4 Work Done

Generally, the work done on a fluid is represented by an the area under the curve one an $indicator\ diagram$, which plots pressure against volume. If we consider a piston of cross-sectional area A compressing a fluid, we can write the work done as,

$$dW = \mathbf{F} \cdot d\mathbf{x} = \underbrace{\frac{|\mathbf{F}|}{A}}_{P} \underbrace{A \, dx}_{-dV} = -P \, dV.$$
 (2.13)

For an ideal gas at temperature, we can evaluate this as,

$$W = -\int_{V_i}^{V_f} \frac{nRT}{V} dV$$

$$= nRT \ln \left(\frac{V_i}{V_f}\right).$$
(2.14)

For a cyclic process, the net work done is an enclosed area on the P-V diagram.

Reversible Work

Stretching of a wire

If we have a string under tension Γ which undergoes an infinitesimal change in length $d\ell$, we have,

$$dW = \Gamma d\ell. \tag{2.15}$$

Increase in surface area

For a surface tension γ and a change in area dA,

$$dW = \gamma \, dA \,. \tag{2.16}$$

2.1.5 Heat Capacity

Heat capacity C is the amount of energy required to raise the temperature by dT,

$$dQ = C dT. (2.17)$$

Heat capacity at constant volume

Rewriting the first law,

$$dQ = C_V dT = dE - dW = dE + \underbrace{P dV}_{0}$$
(2.18)

where the subscript V indicates volume is being held constnat. We can take P dV = 0 since V is constant, and $\Delta V \to 0$, dV = 0. Let us write E = (V, T),

$$dE = \frac{\partial E}{\partial T} dT + \underbrace{\frac{\partial E}{\partial T} dV}_{0}.$$
 (2.19)

Equating eq. (2.18) to (2.19), we get,

$$dQ = C_V dT = \frac{\partial E}{\partial T} dT \tag{2.20}$$

from which we obtain our final expression,

$$C_V = \frac{\partial E}{\partial T}. (2.21)$$

Heat capacity at constant pressure

Rewriting the first law,

$$dQ = C_P dT = dE + P dV. (2.22)$$

Writing E = E(T, P),

$$dE = \frac{\partial E}{\partial T} dT + \underbrace{\frac{\partial E}{\partial P} dP}_{0}.$$
(2.23)

We can then obtain our final relation,

$$C_P = \frac{\partial E}{\partial T} + P \frac{\partial V}{\partial T}$$
 (2.24)

Ideal Gas

In an ideal gas, E = E(T), i.e., energy has sole dependence on temperature. Thus,

$$\frac{\mathrm{d}E}{\mathrm{d}T} = \frac{\partial E}{\partial T} = C_V(T). \tag{2.25}$$

From the ideal gas law,

$$P\frac{\partial V}{\partial T} = nR. \tag{2.26}$$

From which we get the relation,

$$C_P(T) = C_V(T) + nR$$
 (2.27)

2.1.6 Adiabatic Processes

For an adiabtic process, there is no heat transfer, i.e., Q = 0. From the first law and eq. (2.25),

$$dE - dW = C_V dT - dW = 0. (2.28)$$

From the ideal gas equation,

$$T = \frac{PV}{nR} \tag{2.29}$$

whose differential is,

$$dT = \frac{1}{nR} \left(P \, dV + V \, dP \right) \tag{2.30}$$

from which the differential of E follows,

$$dE = \frac{C_V}{nR} \left(P \, dV + V \, dP \right). \tag{2.31}$$

Substituting eq. (2.31) into eq. (2.25) and assuming a reversible process (dW = -P dV), we obtain,

$$C_V dT + P dV = \frac{C_V}{nR} (P dV + V dP) + P dV = 0$$

$$C_V V dP + \underbrace{(C_V nR)}_{C_P} P dV = 0$$

$$\implies \frac{1}{P} dP + \frac{C_P}{C_V} \frac{1}{V} dV = 0.$$
(2.32)




Figure 2.3

If we have that C_P and C_V are constant, let us define,

$$\gamma = \frac{C_P}{C_V} \tag{2.33}$$

which is also constant. We can integrate eq. (2.32) from $(P_1, V_1) \rightarrow (P_2, V_2)$,

$$\int_{P_1}^{P_2} \frac{1}{P} dP + \gamma \int_{V_1}^{V_2} \frac{1}{V} dV = 0 \implies \ln \left(\frac{P_2 V_2^{\gamma}}{P_1 V_1^{\gamma}} \right) = 0$$
 (2.34)

Removing the logarithm from eq. (2.34), we obtain an expression relating the initial and final pressure and volume for an adiabatic process,

$$P_2 V_2^{\gamma} = P_1 V_2^{\gamma} \tag{2.35}$$

and by using the ideal gas law, we can eliminate variables and find expressions involving temperature,

$$T_2 V_2^{\gamma - 1} = T_1 V_1^{\gamma - 1} \tag{2.36}$$

$$T_{2}V_{2}^{\gamma-1} = T_{1}V_{1}^{\gamma-1}$$

$$T_{2}P_{2}^{\frac{1}{\gamma}-1} = T_{1}P_{1}^{\frac{1}{\gamma}-1}$$
(2.36)

2.2Second Law of Thermodynamics

Law 2. The direction of heat flow approaches equilibrium, such that,

- Systems at an intermediate temperature reach equilibrium at an intermediate temperature.
- Heat naturally flows from hot bodies to cold bodies,
- We require an engine to produce work from heat.

2.2.1Heat engines

Heat engines produce work from heat. They operate in a cyclic process such that,

$$\Delta E = \oint dE = 0. \tag{2.38}$$

Sterling Engine

The Sterling engine is a piston operating between two heat reservoirs, with a hot reservoir at temperature T_H and a hot reservoir at temperature T_C where $T_C < T_H$ and contains an ideal gas. It works in a cycle such that,

- 1. Isothermal expansion
 - Work done by gas,

$$W_1 = nRT_H \ln \left(\frac{V_B}{V_A}\right) \tag{2.39}$$

• Heat absorbed,

$$Q_1 = W_1 \tag{2.40}$$

- 2. Contact cooling
 - No work done.
 - Heat *ejected*,

$$Q_2 = E(T_H) - E(T_C) (2.41)$$

- 3. Isothermal compression
 - Work done on gas,

$$W_3 = nRT_C \ln \left(\frac{V_B}{V_A}\right) \tag{2.42}$$

• Heat ejected

$$Q_3 = W_3 \tag{2.43}$$

- 4. Contact heating
 - No work done
 - Heat absorbed,

$$Q_4 = E(T_H) - E(T_C) (2.44)$$

This cycle can be visualised on an indicator diagram as in fig. 2.3. Furthermore, this cycle can all be derived from the first law and dW = -P dV.

Let us look at the cycle in more detail. The net work done by the gas is,

$$W = W_1 - W_3 = nR(T_H - T_C) \ln\left(\frac{V_B}{V_A}\right).$$
 (2.45)

The heat absorbed from the resevoir is at T_H is,

$$Q_H = Q_1 + Q_4. (2.46)$$

The heat ejected to the hot resevoir is,

$$Q_C = Q_2 + Q_3. (2.47)$$

From the first law,

$$\Delta E = (-W) + (Q_H - Q_C) = 0 \tag{2.48}$$

and therefore,

$$W = Q_H - Q_C = nR \ln \left(\frac{V_B}{V_A}\right) T_H + C_V \Delta T - nR \ln \left(\frac{V_B}{V_A}\right) T_C = nR \ln \left(\frac{V_B}{V_A}\right) \Delta T.$$
 (2.49)

where $\Delta T = T_H - T_C$. The efficiency of the engine is the ratio of desired output to required input, so,

$$\eta_E = \frac{W}{Q_H} = \frac{Q_H - Q_C}{Q_H} = \frac{nR \ln\left(\frac{V_B}{V_A}\right) \Delta T}{nR \ln\left(\frac{V_B}{V_A}\right) T_H + C_V \Delta T}.$$
 (2.50)

A schematic of the heat flow of a Sterling engine is shown in fig. 2.4.

2.2.2 Heat pumps and refrigirators

These are the opposite of engines, they do work on a system to extract heat.




Figure 2.4

Refrigerrator

Work is done to extract heat Q_C from a system to lower its temperature T_C . In this case, the efficiency of the system is given as,

$$\eta_R = \frac{Q_C}{Q_H - Q_C}.\tag{2.51}$$

Heat Pump

In a heat pump, we extract heat from a cooler resevoir at T_C to heat a system to T_H . The desired outut is Q_H , so,

$$\eta_P = \frac{Q_H}{Q_H - Q_W}. (2.52)$$

If an engine is reversible, then,

$$\eta_P = \frac{1}{\eta_E}.\tag{2.53}$$

2.2.3 Carnot's Cycle

Carnot's theorem states,

Theorem.

- 1. A reversible engine is most efficient.
- 2. All reversible engines, operating between two heat baths, have the same efficiency, η_C depending only on T_H and T_C .

This type of engine can be constructed using the Carnot cycle (whose P-V diagram is shown in fig. 2.5),

- 1. Isothermal Expansion at T_H ,
 - $\Delta T = 0, \Delta E = 0.$
 - $dW = nRT_H \ln \left(\frac{V_B}{V_A}\right)$.
- 2. Adiabatic Expansion
 - $dQ \implies dE = dW$
 - $PV^{\gamma} = \text{Const.} \implies P \propto V^{-\gamma}$
 - By the ideal gas law, $P = \frac{nRT}{V} \implies \frac{nRT}{V}V^{\gamma} = \text{Const.} \implies T_H V_B^{\gamma-1} = T_C V_C^{\gamma-1}$.
- 3. Isothermal Compression
 - $Q = nRT_C \ln \left(\frac{V_C}{V_D} \right)$
- 4. Adiabatic Compression
 - $\bullet \ T_H V_A^{\gamma 1} = T_C V_D^{\gamma 1}.$




Figure 2.5

From the cycle above, we find that the ratio,

$$\frac{V_B}{V_A} = \frac{V_C}{V_D} \tag{2.54}$$

holds. From this, we can write down the efficiency of this engine,

$$\eta_C = \frac{W}{Q_H} = \frac{nRT_H \ln\left(\frac{V_B}{V_A}\right) - nRT_C \ln\left(\frac{V_C}{V_D}\right)}{nRT_H \ln\left(\frac{V_B}{V_A}\right)} = \frac{nRT_H \ln\left(\frac{V_B}{V_A}\right) - nRT_C \ln\left(\frac{V_B}{V_A}\right)}{nRT_H \ln\left(\frac{V_B}{V_A}\right)}$$
(2.55)

from which we can write donw the final expression for the Carnot efficiency,

$$\eta_C = 1 - \frac{T_C}{T_H}$$
(2.56)

Let us note that we find that the Stirling cycle approaches Carnot efficiency for small values of C_V .

2.2.4 Statements of the Second Law

It is difficult to state the second law in a concise, general way through only understanding heat. However, below are two common formulations.

Kelvin-Planck Statement

It is impossible to construct an engine which, operating in a cycle, produces no effect other than the extraction of heat from the reservoir and the performance of an equivalent amount of work.

Claussius Statement

It is impossible to construct a refrigirator which, operating in a cycle, produces no effect other than the transfer of heat from a cooler body to a hotter one.

2.3 Entropy

Entropy is encoded into Calusiu's inequality, which states that if a system is taken over a cycle, absorbing infinitesimal amounts of heat dQ, from various reservoirs at varing temperatures T, throughout, then

$$\oint \frac{\mathrm{d}Q}{T} \le 0.$$
(2.57)

2.3. ENTROPY 19




Figure 2.6




Figure 2.7

2.3.1 Proof

Let us consider a cycle as in fig. 2.6. We have that the heat input is,

$$Q_H = \oint dQ_H = T_H \oint \frac{dQ_i}{T_i} \tag{2.58}$$

and the total work done is,

$$W = \oint dW_i. \tag{2.59}$$

The only way for this cycle to be possible is if the work done is 0 or negative. Thus,

$$\oint dW_i \le 0.$$
(2.60)

We can write $\oint dW_i = \oint dQ_i$ and,

$$\oint \frac{\mathrm{d}Q_i}{T_i} \le 0.$$
(2.61)

2.3.2 Mathematical definition of entropy

We define infinitesimal entropy of a system,

$$dS = \frac{dQ}{T}. (2.62)$$

We only have constant entropy in equilibrium. Let us consider a process like in fig. 2.7. The total

entropy of this sytem is,

$$\oint \frac{dQ}{T} = \int_{A}^{B} \frac{dQ}{T} + \int_{B}^{A} \frac{dQ}{T} = 0$$

$$\implies \int_{A}^{B} \frac{dQ}{T} - \int_{A}^{B} \frac{dQ}{T} = 0$$
(2.63)

thus we have shown that entropy is path independent and thus is a function of state. Let us now define entropy further. Let us consider a reference state O as we go from A to B. We have,

$$\int_{A}^{B} = \int_{A}^{O} \frac{dQ}{T} + \int_{B}^{A} \frac{dQ}{T}$$

$$= \int_{O}^{B} \frac{dQ}{T} - \int_{O}^{A} \frac{dQ}{T}$$

$$= S(B) - S(A).$$
(2.64)

We can then define the entropy,

$$S(A) = \int_{O}^{A} \frac{\mathrm{d}Q_{\text{rev}}}{T} \,. \tag{2.65}$$

NOTE: Entropy is defined in terms of a reversible process.

2.3.3 The law of increase in entropy

Let us now consider a similar scenario to fig. 2.7, but we have an irreversible process as we go from A to B. Applying Clausius' inequality,

$$\int_{A}^{B} \frac{dQ_{\text{irrev}}}{T} + \int_{B}^{A} \frac{dQ_{\text{rev}}}{T} \le 0$$

$$\int_{A}^{B} \frac{dQ_{\text{irrev}}}{T} \ge \int_{A}^{B} \frac{dQ_{\text{rev}}}{T}$$
(2.66)

which gives us our final statement,

$$S(B) - S(A) \ge \int_{A}^{B} \frac{\mathrm{d}Q_{\text{irrev}}}{T} \tag{2.67}$$

2.3.4 Thermally Isolated Systems

For thermally isolated systems, it always holds that,

$$S(B) - S(A) \ge 0. \tag{2.68}$$

For a system doing the maximum amount of work, we have that,

$$S(B) - S(A) = 0. (2.69)$$

For a system acting between two finite reservoirs, they will reach a final temperature given by,

$$T_f = \sqrt{T_H T_C}. (2.70)$$

2.3.5 Entropy and Heat Capacity

Entropy can be used to define the heat capacity of for a given constant variable X. This is given by,

$$C_X = T \left(\frac{\partial S}{\partial T}\right)_X \tag{2.71}$$

which, integrating, gives,

$$S(T,X) - S(T_0,X) = \int_{T_0}^T \frac{C_X(T',X)}{T'} dT'.$$
 (2.72)

2.3.6 Fundamental Relation of Thermodynamics

The fundamental theorem of thermodynamics is a restatement of the second law,

$$dE = T dS + dW_{\text{rev}}. (2.73)$$

For an ideal gas, this is,

$$dE = T dS - P dV. (2.74)$$

If we think of the second law, and energy being of the form $E \equiv E(S, V)$, we can write,

$$dE = \left(\frac{\partial E}{\partial S}\right)_V dS + \left(\frac{\partial E}{\partial V}\right)_S dV \tag{2.75}$$

which wen equating coefficients allows us to find,

$$T = \left(\frac{\partial E}{\partial S}\right)_{V} \qquad \qquad \boxed{P = -\left(\frac{\partial E}{\partial V}\right)_{S}}$$
 (2.76)

2.4 Thermodynamic Potentials

From the fundamental relation of thermodynamics, we are able to derive different thermodynamic potentials, which allow us to state whether a reaction can happen spontaneously.

2.4.1 Work Availability

We wish to find the maximum amount of work we can extract from a system initially out of equilibrium with the surroundings. A system like this will always increases its entropy if it can. We have that, for a system with the environment at pressure P_0 and temperature T_0 , we have,

$$\Delta S_{\text{tot}} = \Delta S_{\text{sys}} + \Delta S_{\text{env}}$$

$$= \Delta S + \frac{Q}{T_0}$$

$$= \Delta S + \frac{-\Delta E - P \, dV}{T_0}$$

$$= \frac{T_0 \Delta S - \Delta E - P \, dV}{T_0} \ge 0$$
(2.77)

From this we can define the availability of a system,

$$-\Delta A = T_0 \Delta S - \Delta E - P \, dV > 0, \tag{2.78}$$

for which we have that the entropy of a system increases given that $\Delta A \leq 0$. We can further interpret the availability as the useful work done by a system. We have that,

$$W_{\text{useful}} \le -\Delta A$$
. (2.79)

We can further relate available work to thermodynamic potentials (described in detail in sections below).

• For a process at constant temperature and pressure, the availability is related to the Gibbs free energy,

$$W_{\text{usefull}} \le -\Delta G \tag{2.80}$$

• For a process at constant volume and temperature, the availability is related to the Helmholtz free energy,

$$W_{\text{useful}} \le -\Delta F$$
 (2.81)

2.4.2 Helmholtz Free Energy

We can derive this from the Helmholtz free energy from the fundamental relation of thermodynamics,

$$dE = T dS - P dV$$

$$= T dS + S dT - S dT - P dV$$

$$= d(TS) - S dT - P dV$$

$$\Longrightarrow \underbrace{dE - TS}_{dF} = \underbrace{-S dT - P dV}_{dT=0, dV=0}$$
(2.82)

From this we can define the Helmholtz free energy,

$$F(T,V) = E - TS. (2.83)$$

Which holds for constnat T and V. We can further consider the expansion of dF,

$$dF = \left(\frac{\partial F}{\partial T}\right)_V dT + \left(\frac{\partial F}{\partial V}\right)_T dV \tag{2.84}$$

and equating coefficients,

$$S = -\left(\frac{\partial F}{\partial T}\right)_{V} \qquad P = -\left(\frac{\partial F}{\partial V}\right)_{T}. \tag{2.85}$$

We then have that,

$$dF \le 0 \tag{2.86}$$

where equality holds for equilibrium, and spontaneous change for dF < 0.

2.4.3 Gibbs Free Energy

We derive the Gibbs free energy from the Helmholtz free energy. We have,

$$dF = d(E - TS) = -S dT - P dV$$

$$= -S dT - p dV - v dP + V dP$$

$$= -S dT - d(PV) + V dP = d(E - TS)$$

$$\Longrightarrow \underbrace{d(E - TS + PV)}_{dG} = -S dT + V dP$$
(2.87)

The Gibbs free energy is then,

$$G(T,P) = E - TS + PV. (2.88)$$

The Gibbs free energy tells us about the non-reversible work in the system. Expanding d(E - TS + PV),

$$dE - S dT - T dS + P dV + V dP = S dT + V dP^{0}$$

$$\implies dE - T dS + P dV = dW_{\text{other}}$$

$$dE - T dS + P dV = dW_{\text{other}}$$
(2.89)

2.4.4 Enthalpy

Enthalpy is derived from the Gibbs free energy. We consider enthalpy at constant entropy and pressure. Furthermore, for a system at constant pressure, the enthalpy is interpreted as the heat released during the process. The derivation is shown below,

$$d(E - TS + PV) = -S dT + V dP$$

$$= -S dT - T dS + T dS + V dP$$

$$= -d(TS) + T dS + V dP$$

$$\implies d(E + PV) = T dS + V dP$$
(2.90)

we then define the enthalpy H,

$$H = E + PV (2.91)$$

where we have,

$$dH = T dS V dP$$
 (2.92)

and the relations,

$$\left(\frac{\partial H}{\partial S}\right)_{P} = T \qquad \left(\frac{\partial H}{\partial P}\right)_{S} = V. \tag{2.93}$$

We can further define the Gibbs free energy in terms of enthalpy,

$$dG = dH - T dS \tag{2.94}$$

where we require $dG \leq 0$ for spontaneous change.

2.4.5 Interpretation of Thermodynamic Potentials

Internal Energy

For thermally isolated systems, (Q = 0),

$$\Delta A = \Delta E + P_0 \Delta V = 0$$

$$\Rightarrow \Delta E = -P_0 \Delta V. \tag{2.95}$$

Entropy

For thermally isolated systems at fixed volume,

$$\Delta A = -T_0 \Delta S \tag{2.96}$$

thus,

$$(\Delta S)_{E,V} \ge 0 \tag{2.97}$$

for spontaneous change. I.e., entropy must be maximised.

Helmholtz Free Energy

For a system that starts and ends at the same temperature, with constant volume,

$$\Delta A = \Delta (E - T_0 S) = \Delta F \tag{2.98}$$

so,

$$(\Delta F)_{T,V} \le 0 \tag{2.99}$$

for spontaneous change.

Gibbs Free Energy

If the system starts and ends at the same pressure and temperature, the availability becomes,

$$\Delta A = \Delta (E - T_0 S + P_0 V) = \Delta G \tag{2.100}$$

thus for spontaneous change,

$$(\Delta G)_{T,P} \le 0 \tag{2.101}$$

and for equilibrium, we minimise the Gibbs free energy.

Enthalpy

For a system at constant pressure, the work done is $P_0\Delta V$. From the first law,

$$\Delta E = Q - P_0 \Delta V. \tag{2.102}$$

The change in enthalpy is,

$$\Delta H = \Delta E + P_0 \Delta V \tag{2.103}$$

and we therefore have,

$$(\Delta H)_P = Q \tag{2.104}$$

so the change in enthalpy is the heat released during a process.

2.4.6 Maxwell Relations

The Maxwell relations are given below, with proof given for the first below,

$$\left(\frac{\partial P}{\partial S}\right)_{V} = -\left(\frac{\partial T}{\partial V}\right)_{S} \tag{2.105}$$

$$\left(\frac{\partial S}{\partial V}\right)_T = \left(\frac{\partial P}{\partial T}\right)_V \tag{2.106}$$

$$\left(\frac{\partial T}{\partial P}\right)_{S} = \left(\frac{\partial V}{\partial S}\right)_{P} \tag{2.107}$$

$$\left(\frac{\partial S}{\partial P}\right)_T = -\left(\frac{\partial V}{\partial T}\right)_P \tag{2.108}$$

We will show the proof for eq. (2.105), but the proofs for all other relations follow similarly.

Proof.

$$dE = T dS - P dV = \left(\frac{\partial E}{\partial S}\right) dS + \left(\frac{\partial E}{\partial V}\right)_S dV$$

$$\partial E = \frac{\partial E}{\partial S} + \frac$$

$$\begin{split} T &= (\frac{\partial E}{\partial S})_V & P &= -\left(\frac{\partial E}{\partial V}\right)_S \\ &\frac{\partial}{\partial V}\left(\frac{\partial E}{\partial S}\right) = \frac{\partial}{\partial S}\left(\frac{\partial E}{\partial V}\right) \\ &\Longrightarrow \left(\frac{\partial P}{\partial S}\right)_V = -\left(\frac{\partial T}{\partial V}\right)_S \end{split}$$

2.5 Phase Transitions

In order to consider phase transitions, we must consider *open systems*, i.e., systems where the number of particles can change. We can then write the internal energy to account for open systems,

$$E = TS - PV + \mu N \tag{2.109}$$

where μ is the chemical potential. We can then write the FTR,

$$dE = T dS - P dV + \mu dN. \qquad (2.110)$$

We can visualise phase transitions on a P-T diagram, as in figure 2.8,

2.5.1 Phase Transition Conditions

For a substance to transition from one state to another, it must be possible for the two states to be in equilibrium. Considering a total isolated systems composed of two systems in two different states,

$$S(E, V, N) = S_1(E_1, V_1, N_1) + S_2(E_2, V_2, N_2)$$
(2.111)

Considering dS for each part of the system, we obtain the differentials,

$$\left(\frac{\partial S_1}{\partial E_1}\right)_{V_1, N_1} = \left(\frac{\partial S_2}{\partial E_2}\right)_{V_2, N_2}$$
(2.112)

$$\left(\frac{\partial S_1}{\partial V_1}\right)_{E_1,N_1} = \left(\frac{\partial S_2}{\partial V_2}\right)_{E_2,N_2} \tag{2.113}$$

$$\left(\frac{\partial S_1}{\partial N_1}\right)_{E_1,V_1} = \left(\frac{\partial S_2}{\partial N_2}\right)_{E_2,V_2} \tag{2.114}$$




Figure 2.8

These lead to the conditions for phase equilibrium,

- $T_1 = T_2$, no heat flow between systems.
- $P_1 = P_2$, the systems are at mechanical equilibrium.
- $\mu_1 = \mu_2$, there is no preference to be in one state over another.

2.5.2 Clausius-Clapeyron Relation

If we approximate the interface line between two states as being linear, such that we go from points $(T, P) \to (T + \delta T, P + \delta P)$, we can write the Clausius-Clapeyron relation as,

$$\frac{\delta P}{\delta T} = \frac{\Delta H}{T \Delta \mathcal{V}} \tag{2.115}$$

where V is the molar volume, and ΔH is the molar change in enthalpy, often written as L, and referred to as the latent heat.

Appendix A

Definitions

Isothermal Process: Happens at constant temperature, $\Delta E=0$ for an ideal gas.

Isobaric Process: Happens at constant pressure.

Isochoric Process: Happens at constant volume \implies dW = 0.

Adiabatic Process: Happens with no heat flow \implies dQ = 0.

Heat Capacity: Relates heat flow to temperature change dQ = C dT.

Appendix B

Important Misc. Facts

For an ideal gas at constant volume, the change in energy $\mathrm{d}E$ is always given by,

$$dE = C_V dT (B.1)$$