
z/OS Version 2 Release 4

C Curses





© Copyright International Business Machines Corporation 1996, 2019.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About This Book	XXV
Typographical conventions	XXV
Other documents	
Where to find more information	xxv
Summary of Changes	xxvii
Chamter 1 The Correct Library	4
Chapter 1. The Curses Library	
Terminology	
Naming Conventions	
Structure of a Curses ProgramReturn Values	
Chapter 2. Initializing Curses	5
Chapter 3. Windows in the Curses Environment	
The Default Window Structure	
The Current Window Structure	
Subwindows	
Pads	
raus	
Chapter 4. Manipulating Window Data with Curses	11
Chapter 5. Curses Interfaces	13
addch()	13
Name	13
Synopsis	13
Description	
Return Value	13
Errors	13
Application Usage	13
See Also	13
addchstr()	13
Name	13
Synopsis	14
Description	
Return Value	14
Errors	14
Application Usage	14
See Also	14
addnstr()	14
Name	14
Synopsis	14
Description	
Return Value	
Errors	15
See Also	15
addnwstr()	
Name	15

Synopsis	
Description	16
Return Value	16
Errors	16
See Also	
add_wch()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
add_wchnstr()	
Name	
Synopsis	
Description	
Return Value	17
Errors	17
See Also	17
attroff()	18
Name	18
Synopsis	18
Description	
Return Value	
Errors	
See Also	
attr_get()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
baudrate()	
Name	
Synopsis	
Description	
Return Value	20
Errors	20
See Also	20
beep()	20
Name	20
Synopsis	20
Description	
Return Value	
Errors	
Application Usage	
See Also	
bkgd()	
Name	
Synopsis	
Description	
Return Value	
bkgd()	
Errors	
Application Usage	
See Also	
bkgrnd()	22

Name	
Synopsis	
Description	22
Return Value	22
Errors	22
See Also	22
border()	23
Name	23
Synopsis	23
Description	23
Return Value	23
Errors	23
Application Usage	23
See Also	
border_set()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
box()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
box_set()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
can_change_color()	26
Name	26
Synopsis	26
Description	26
Return Value	27
Errors	27
Application Usage	27
See Also	28
cbreak()	28
Name	28
Synopsis	28
Description	
Return Value	
Errors	
Application Usage	
See Also	
chgat()	
Name	
Synopsis	
Description	
Return Value	
Errors	29

See Also	29
clear()	29
Name	29
Synopsis	
Description	
Return Value	
Errors	
See Also	
clearok()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
clrtobot()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
clrtoeol()	
Name	
Synopsis	
Description	32
Return Value	32
Errors	32
See Also	32
color_content()	
Name	
Synopsis	32
Description	
COLOR_PAIRS	
Name	
Synopsis	
Description	33
COLS	33
Name	33
Synopsis	33
Description	
See Also	
copywin()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
curscr	
Name	
Synopsis	
DescriptionSee Also	
curs_set() Name	
Synopsis	34

Return Value 3 Errors 3 See Also 3 cur_term() 3 Name 3 Synopsis 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3 See Also 3
See Also 3 cur_term() 3 Name 3 Synopsis 3 Description 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3
cur_term() 3 Name 3 Synopsis 3 Description 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3
Name 3 Synopsis 3 Description 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3
Name 3 Synopsis 3 Description 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3
Synopsis 3 Description 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3
Description 3 See Also 3 def_prog_mode() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 Application Usage 3
See Also
def_prog_mode()
Name
Synopsis
Description
Return Value
Errors
Application Usage3
,,
See Also
delay_output()
Name
Synopsis3
Description
Return Value
Errors
Application Usage
See Also
delch()
Name3
Synopsis3
Description3
Return Value
Errors
See Also3
del_curterm()3
Name3
Synopsis3
Description3
Return Value3
Errors3
Application Usage3
See Also3
deleteIn()
Name3
Name3 Synopsis3
Name3
Name3 Synopsis3
Name
Name
Name
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3 Name 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3 Name 3 Synopsis 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3 Name 3 Synopsis 3 Description 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3 Name 3 Synopsis 3 Description 3 Return Value 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3
Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delscreen() 3 Name 3 Synopsis 3 Description 3 Return Value 3 Errors 3 See Also 3 delwin() 3

Return Value	
Errors	40
See Also	40
derwin()	40
Name	40
Synopsis	40
Description	40
Return Value	
Errors	41
Application Usage	
See Also	
doupdate()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
dupwin()	
Name	
Synopsis.	
Description	
Return Value	
Errors	
See Also	
echo()	
Name	
Synopsis	
Description	
Return Value	
ErrorsSee Also	
echochar()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
echo_wchar()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
endwin()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
erase()	
Name	45

Synopsis	45
Description	45
erasechar()	45
Name	45
Synopsis	45
Description	45
Return Value	46
Errors	46
Application Usage	46
See Also	
filter()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
flash()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
flushinp()	
Name	
Synopsis	
Description	
·	
Return Value	
Errors	
See Also	
getbegyx()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
getbkgd()	
Name	
Synopsis	
Description	
getbkgrnd()	
Name	
Synopsis	
Description	
getcchar()	
Name	
Synopsis	
Description	49
Return Value	50
Errors	50
Application Usage	50
See Also	50
getch()	50
Name	50

	Synopsis	
	Description	
	Return Value	
	Errors	
	Application Usage	
	See Also	
ge.	tmaxyx()	
	Name	
	Synopsis	
	Description	
ge	tnstr()	
	Name	
	Synopsis	
	Description	
	Errors	
	Application Usage	
	See Also	
ďΟ.	tn_wstr()	
ge	Name	
	Synopsis	
	Description	
	Return Value	
	Errors	
	Application Usage	
	See Also	
۵e.	tparyx()	
50	Name	
	Synopsis	
	Description	
ge:	tstr()	
0	Name	
	Synopsis	
	Description	
ge:	t_wch()	
_	Name	
	Synopsis	.54
	Description	54
	Return Value	. 55
	Errors	
	Application Usage	
	See Also	
ge ⁻	twin()	
	Name	
	Synopsis	
	Description	
	Return Value	
	Errors	
	See Also	
ge	t_wstr()	
	Name	
	Synopsis	
	Description	
ge	tyx()	
	Name	
	Synopsis	
	Description	
ha	lfdelav()	. 56

Name	
Synopsis	56
Description	56
Return Value	56
Errors	57
Application Usage	57
See Also	57
has_colors()	
Name	
Synopsis	
Description	
has_ic()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
hline()	
Name	
Synopsis	
Description	
Return Value	
Errors	
hline()	
Application Usage	
See Also	
hline_set()	
Name	
Synopsis	
Description	
Return Value	
Errors	
hline_set()	
See Also	
idcok()	
Name	60
Synopsis	60
Description	60
Return Value	60
Errors	60
See Also	60
idlok()	60
Name	
Synopsis	
Description	
immedok()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
inch()	
Name	
Synopsis	
JYIIUUJSIS	

Description	
Return Value	62
Errors	62
Application Usage	62
See Also	62
inchnstr()	62
Name	62
Synopsis	62
Description	
Return Value	
Errors	
Application Usage	
See Also	
init color()	
Name	
Synopsis	
Description	
initscr()	
Name	
Synopsis	
Description	
initscr()	
Return Value	
Errors	
Application Usage	
See Also	
innstr()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
innwstr()	
Name	
Synopsis	
Description	
Return Value	
Errors	66
Application Usage	66
See Also	
insch()	66
Name	66
Synopsis	66
Description	66
Return Value	67
Errors	67
Application Usage	
See Also	
insdelln()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
insertln()	

Name	
Synopsis	68
Description	68
Return Value	68
Errors	68
See Also	68
insnstr()	68
Name	68
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
ins_nwstr()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
insstr()	
Name	
Synopsis	
Description	
instr()	
Name	
Synopsis	
Description	
ins_wch()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
ins_wstr()	
-	
Name	
Synopsis	
Description	
intrflush()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
in_wch()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
in_wchnstr()	
Name	73

Synopsis	
Description	73
Return Value	73
Errors	73
Application Usage	73
See Also	73
inwstr()	73
Name	73
Synopsis	74
Description	
isendwin()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
is linetouched()	
Name	
Synopsis.	
Description	
Return Value	
Errors	
Application Usage	
See Also	
keyname()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
keypad()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
killchar()	
Name	
Synopsis	
Description	
leaveok()	
Name	
Synopsis	
Description	
LINES	
Name	
Synopsis	
Description	
See Also	78
longname()	78
Name	78
Synopsis	78
Description	78
Return Value	78

Errors	
Application Usage	78
See Also	78
meta()	78
Name	78
Synopsis	78
Description	
Return Value	
Errors	
Application Usage	
See Also	
move()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
mv	
Name	
Description	
See Also	
mvcur()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
mvderwin()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
mvprintw()	
Name	
Synopsis	83
Description	83
Return Value	83
Errors	83
See Also	83
mvscanw()	83
Name	83
Synopsis	83
Description	
Return Value	
Errors	
See Also	
mvwin()	
Name	
Synopsis	
Description	
Return Value.	
Errors	
Application Usage	
, 100 11 04 10 11 0 04 10 11 10 11 11 11 11 11 11 11 11 11 11	.

See Also	84
napms()	84
Name	84
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
newpad()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
newterm()	
Name	86
Synopsis	86
Description	86
newwin()	86
Name	86
Synopsis	
Description	
nl()	
Name	
Synopsis.	
Description	
Return Value	
Errors	
Application Usage	
See Also	
no	
Name	
Description	
nodelay()	
Name	
Synopsis	
Description	88
Return Value	88
Errors	88
See Also	88
noqiflush()	88
Name	88
Synopsis	88
Description	
Return Value	
Errors	
Application Usage	
See Also	
notimeout()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	90

overlay()	
Name	
Synopsis	90
Description	90
Return Value	90
Errors	90
See Also	90
pair_content()	90
Name	
Synopsis	
Description	
pechochar()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
pnoutrefresh()	
Name	
Synopsis	
Description	
printw()	
Name	
Synopsis	
Description	
putp()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
putwin()	
Name	
Synopsis	93
Description	93
qiflush()	93
Name	93
Synopsis	93
Description	
raw() [']	
Name	
Synopsis	
Description	
redrawwin()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
• • • • • • • • • • • • • • • • • • • •	
See Also	
refresh()	
Name	
Synopsis	95

Description	
reset_prog_mode()	95
Name	95
Synopsis	95
Description	95
resetty()	95
Name	95
Synopsis	95
Description	95
Return Value	
Errors	95
See Also	95
restartterm()	96
Name	96
Synopsis	96
Description	96
ripoffline()	
Name	96
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
savetty()	
Name	
Synopsis	
Description	
scanw()	
Name	
Synopsis	
Description	
scr_dump()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
scrl()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
scrollok()	
Name	
Synopsis	
Description	
setcchar()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
~~~ · · · · · · · · · · · · · · · · · ·	±00

set_curterm()	
Name	100
Synopsis	100
Description	100
setscrreg()	100
Name	100
Synopsis	100
Description	
set_term()	
Name	
Synopsis	100
Description	
Return Value	
Errors	101
Application Usage	
See Also	
setupterm()	
Name	101
Synopsis	
Description	
slk attroff()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
standend()	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
start color()	
Name	
Synopsis	
Description	
stdscr	
Name	
Synopsis	
Description	
See Also	
subpad()	
Name	
Synopsis	
Description	
subwin()	
Name	
Synopsis	
Description	
syncok()	
Name	
Synopsis	
Description	
Return Value	
Errors	105

Application Usage	105
See Also	106
termattrs()	106
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
termname()	
<u>u</u>	
Name	
Synopsis	
Description	
Return Value	
Errors	
See Also	
tgetent()	
Name	
Synopsis	107
Description	107
Return Value	107
Errors	107
Application Usage	107
See Also	
tigetflag()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
timeout()	
Name	
Synopsis	
Description	
touchline()	
Name	
Synopsis	
Description	
tparm()	
Name	
Synopsis	109
Description	110
tputs()	110
Name	110
Synopsis	110
Description	
typeahead()	
Name	
Synopsis	
Description	
Return Value	
ErrorsSee Also	
unctrl()	
Name	
Synopsis	111

	Description	
	Return Value	.111
	Errors	. 111
	See Also	.111
ung	getch()	.111
Ì	Name	
	Synopsis	
	Description	
	Return Value.	
	Errors	
	See Also	
unt	ouchwin()	
	Name	
	Synopsis	
	Description	
	e_env()	
	Name	
	Synopsis	
	Description	
	Return Value	
	Errors	
	See Also	
	attr()	
	Name	
	Synopsis	
	Description	
	Return Value	
	Errors	. 113
	Application Usage	. 113
	See Also	.114
vlir	ne()	. 114
	Name	. 114
	Synopsis	
	Description	
	ne_set()	
	Name	
	Synopsis	
	Description	
	printw()	
	Name	
	Synopsis	
	Description	
	·	
	Return Value	
	Errors	
	Application Usage	
	See Also	
	_printw()	
	Name	
	Synopsis	
	Description	
	Return Value	
	Errors	
	Application Usage	. 115
	See Also	
	scanw()	
	Name	
	Synopsis	
	Description	

Return Value	
Errors	116
Application Usage	116
See Also	
vw scanw()	
Name	
Synopsis	
Description	
Return Value	
Errors	
Application Usage	
See Also	
W	
Name	
Description	
wunctrl()	
Name	
Synopsis	
Description	
Return Value	120
Errors	120
See Also	120
Chapter 6. Headers	121
- <cursesh></cursesh>	121
Name	
Synopsis	
Description	
See Also	
<termh></termh>	
Name	
Synopsis	
Description	
See Also	
<unctrlh></unctrlh>	
Name	
Description	
See Also	
See Also	135
Chantay 7 Tarminfo Course Format (ENHANCED CUDGES)	127
Chapter 7. Terminfo Source Format (ENHANCED CURSES)	
Source File Syntax	
Minimum Guaranteed Limits	
Formal Grammar	
Defined Capabilities	
Sample Entry	
Types of Capabilities in the Sample Entry	
Device Capabilities	
Basic Capabilities	
Parameterized Strings	
Cursor Motions	
Area Clears	
Insert/Delete Line	
Insert/Delete Character	157
Insert/Detete Character	
Highlighting, Underlining, and Visible Bells	157
Highlighting, Underlining, and Visible BellsKeypad	157 158 160
Highlighting, Underlining, and Visible Bells	157 158 160

Status Lines	
Line Graphics	162
Color Manipulation	
Miscellaneous	165
Special Cases	
Similar Terminals	166
Printer Capabilities	
Rounding Values	166
Printer Resolution	
Specifying Printer Resolution	167
Capabilities that Cause Movement	168
Alternate Character Sets	172
Dot-Matrix Graphics	
Effect of Changing Printing Resolution	
Print Quality	175
Printing Rate and Buffer Size	
Selecting a Terminal	
Application Usage	176
Conventions for Device Aliases	176
Variations of Terminal Definitions	176
Notices	179
Terms and conditions for product documentation	
IBM Online Privacy Statement	
Policy for unsupported hardware	
Minimum supported hardware	
Trademarks	
Glossary	
T	405

# **About This Book**

This manual describes the curses interface for application programs using the z/OS C language. Readers are expected to be experienced C language programmers and to be familiar with open systems standards or a UNIX operating system. This book also assumes that readers are somewhat familiar with MVS systems and with the information for MVS and its accompanying products. Readers also should have read z/OS Introduction and Release Guide which describes the services and the concepts of z/OS. This manual is organized as follows:

- Chapter 1, "The Curses Library," on page 1 gives an overview of Curses. It discusses the use of some of the key data types and gives general rules for important common concepts such as characters, renditions and window properties. It contains general rules for the common Curses operations and operating modes. This information is implicitly referenced by the interface definitions in Chapter 2. The chapter explains the system of naming the Curses functions and presents a table of function families. Finally, the chapter contains notes regarding use of macros and restrictions on block-mode terminals.
- Chapter 5, "Curses Interfaces," on page 13 defines the Curses functional interfaces.
- <u>Chapter 6, "Headers," on page 121</u> defines the contents of headers, which declare constants, macros and data structures that are needed by programs using the services provided by <u>Chapter 7, "Terminfo</u> Source Format (ENHANCED CURSES)," on page 137.
- Chapter 7, "Terminfo Source Format (ENHANCED CURSES)," on page 137 discusses the terminfo database, which Curses uses to describe terminals. The chapter specifies the source format of a terminfo entry, using a formal grammar, an informal discussion, and an example. Boolean, numeric and string capabilities are presented in tabular form. The remainder of the chapter discusses the use of these capabilities by the writer of a terminfo entry to describe the characteristics of the terminal in use.
- The glossary contains definitions of terms used in this manual.

# **Typographical conventions**

The following typographical conventions are used throughout this document:

- Bold font is used in text for options to commands, filenames, keywords, type names, data structures and their members.
- Italic strings are used for emphasis or to identify the first instance of a word requiring definition. Italics in text also denote:
  - Command operands, command option-arguments or variable names, for example, substitutable argument prototypes
  - Environment variables, which are also shown in capitals
  - Utility names
  - External variables, such as errno
  - Functions; these are shown as follows: name(); names without parentheses are C external variables, C function family names, utility names, command operands or command option-arguments.
- Normal font is used for the names of constants and literals.
- The notation <file.h> indicates a header file.
- Names surrounded by braces, for example, {ARG_MAX}, represent symbolic limits or configuration values which may be declared in appropriate headers by means of the C #define construct.
- The notation [EABCD] is used to identify an error value EABCD.
- Syntax, code examples and user input in interactive examples are shown in fixed width font. Brackets shown in this font, [], are part of the syntax and do not indicate optional items. In syntax the | symbol is

used to separate alternatives, and ellipses (...) are used to show that additional arguments are optional.

- Bold fixed width font is used to identify brackets that surround optional items in syntax, [], and to identify system output in interactive examples.
- Variables within syntax statements are shown in italic fixed width font.
- Ranges of values are indicated with parentheses or brackets as follows:
  - (a,b) means the range of all values from a to b, including neither a nor b
  - [a,b] means the range of all values from a to b, including a and b
  - [a,b) means the range of all values from a to b, including a, but not b
  - (a,b] means the range of all values from a to b, including b, but not a.

#### Notes:

- Symbolic limits are used in this document instead of fixed values for portability. The values of most of these constants are defined in limits.h> or <unistd.h>.
- The values of errors are defined in <errno.h>.

# Other documents

The following documents are referenced in this specification:

- ANSI standard X3.159-1989, Programming Language C.
- ISO 8859-1:1987, Information Processing 8-bit Single-byte Coded Graphic Character Sets Part 1: Latin Alphabet No. 1.
- ISO/IEC 646:1991, Information Processing ISO 7-bit Coded Character Set for Information Interchange.
- ISO/IEC 9899:1990, Programming Languages C (technically identical to ANSI standard X3.159-1989).
- System V Interface Definition (Spring 1986 Issue 2).
- System Interface Definitions (1989 3rd Edition).
- System V Release 2.0
  - UNIX System V Release 2.0 Programmer's Reference Manual (April 1984 Issue 2).
  - UNIX System V Release 2.0 Programming Guide (April 1984 Issue 2).
- Operating System API Reference, UNIXO SVR4.2 (1992) (ISBN: 0-13-017658-3).

## Where to find more information

For an overview of the information associated with z/OS, see z/OS Information Roadmap.

### z/OS Basic Skills in IBM Knowledge Center

z/OS Basic Skills in IBM Knowledge Center is a Web-based information resource intended to help users learn the basic concepts of z/OS, the operating system that runs most of the IBM mainframe computers in use today. IBM Knowledge Center is designed to introduce a new generation of Information Technology professionals to basic concepts and help them prepare for a career as a z/OS professional, such as a z/OS system programmer.

Specifically, z/OS Basic Skills is intended to achieve the following objectives:

- Provide basic education and information about z/OS without charge
- Shorten the time it takes for people to become productive on the mainframe
- Make it easier for new people to learn z/OS.

z/OS Basic Skills in IBM Knowledge Center (www.ibm.com/support/knowledgecenter/zosbasics/com.ibm.zos.zbasics/homepage.html) is available to all users (no login required).


# **Summary of Changes**

Summary of Changes for SA38-0690-00 z/OS Version 2 Release 1

This book contains information also presented in OS/390 C Curses, SC28-1907-01.

# **Chapter 1. The Curses Library**

The Curses library provides a set of functions that enable you to manipulate a terminal's display regardless of the terminal type. Throughout this documentation, the Curses library is referred to as curses. The basis of curses programming is the window data structure. Using this structure, you can manipulate data on a terminal's display. You can instruct curses to treat the entire terminal display as one large window or you can create multiple windows on the display. The windows can be different sizes and can overlap one another. The following figure shows a typical curses application with a single large window and one subwindow



Each window on a terminal's display has its own window data structure. This structure keeps state information about the window such as its size and where it is located on the display. Curses uses the window data structure to obtain relevant information it needs to carry out your instructions.

# **Terminology**

When programming with curses, you should be familiar with the following terms:

#### Term

#### **Definition**

### current character

The character that the logical cursor is currently on.

#### current line

The line that the logical cursor is currently on.

#### curscr

A virtual default window provided by curses. The curscr (current screen) is an internal representation of what currently appears on the terminal's external display. You should not modify the curscr.

### display

A physical display connected to a workstation.

## logical cursor

The cursor location within each window. The window data structure keeps track of the location of its logical cursor.

## pad

A type of window that is larger than the dimensions of the terminal's display. Unlike other windows, a pad is not associated with any particular portion of the display.

## physical cursor

The cursor that appears on a display. The workstation uses this cursor to write to the display. There is only one physical cursor per display. To change the position of the physical cursor, you must do a refresh.

#### screen

The window that fills the entire display. The screen is synonymous with the stdscr (standard screen).

#### stdscr

A virtual default window provided by curses that represents the entire display.

### window

A pointer to a C data structure and the graphic representation of that data structure on the display. A window can be thought of as a two-dimensional array representing how all or part of the display looks at any point in time. Windows range in size from the entire display to a single character.

# **Naming Conventions**

A single curses function can have two or more versions. Curses functions with multiple versions follow distinct naming conventions that identify the separate versions. These conventions add a prefix to a standard curses function and identify what arguments the function requires or what actions take place when the function is called. The different versions of curses function names use three prefixes:

#### **Prefix**

### **Description**

W

Identifies a function that requires a window argument.

p

Identifies a function that requires a pad argument.

#### mv

Identifies a function that first performs a move to the program-supplied coordinates.

Some curses functions with multiple versions do not include one of the preceding prefixes. These functions use the curses default window stdscr (standard screen). The majority of functions that use the stdscr are functions created in the /usr/include/curses.h file using #define statements. The preprocessor replaces these statements at compilation time. As a result, these functions do not appear in the compiled assembly code, a trace, a debugger, or the curses source code.

If a curses function has only a single version, it does not necessarily use stdscr. For example, the **printw()** function prints a string to the stdscr. The **wprintw()** function prints a string to a specific window by supplying the Window argument. The **mvprintw()** function moves the specified coordinates to the stdscr and then performs the same function as the **printw()** function. Likewise, the **mvwprintw()** function moves the specified coordinates to the specified window and then performs the same function as the **wprintw()** function.

A function with the basic name is often provided for historical compatibility and operates only on single-byte characters. A function with the same name plus the *w* infix operates on wide (multi-byte) characters. A function with the same name plus the *w* infix operates on complex characters and their renditions.

When a function with the same basic name operates on a single character, there is sometimes a function with the same name plus the n infix that operates on multiple characters. An n argument specifies the number of characters to process. The respective manual page specifies the outcome if the value of n is inappropriate.

# **Structure of a Curses Program**

In general, a curses program has the following progression:

- · Start curses.
- Check for color support (optional).
- Start color (optional).
- Create one or more windows.
- Manipulate windows.
- Destroy one or more windows window.
- · Stop curses.

Your program does not have to follow this progression exactly.

# **Return Values**

With a few exceptions, all curses functions return either the integer value ERR or the integer value OK. Subroutines that do not follow this convention are noted appropriately. Subroutines that return pointers always return a null pointer on an error.

# **Chapter 2. Initializing Curses**

You must include the **curses.h** file at the beginning of any program that calls curses functions. To do this, use the following statement:

#include <curses.h>

Before you can call functions that manipulate windows or screens, you must call the **initscr()** or **newterm()** function. These functions first save the terminal's settings. These functions then call the **setupterm()** function to establish a curses terminal.

Before exiting a curses program, you must call the **endwin()** function. The **endwin()** function restores tty modes, moves the cursor to the lower left corner of the screen, and resets the terminal into the proper nonvisual mode. You can also temporarily suspend curses. If you need to suspend curses, use a shell escape or system call for example. To resume after a temporary escape, you should call the **wrefresh()** or **doupdate()** function. The **isendwin()** function is helpful if, for optimization reasons, you don't want to call the **wrefresh()** function needlessly. You can determine if the **endwin()** function was called without any subsequent calls to the **wrefresh()** function by using the **isendwin()** function.

Most interactive, screen-oriented programs require character-at-a-time input without echoing the result to the screen. To establish your program with character-at-a-time input, call the **cbreak()** and **noecho()** functions after calling the initscr function. When accepting this type of input, programs should also call the following functions:


- nonl() function.
- intrflush() function with the Window parameter set to the stdscr and the Flag parameter set to FALSE. The Window parameter is required but ignored You can use stdscr as the value of the Window parameter, because stdscr is already created for you.
- keypad() function with the Window parameter set to the stdscr and the Flag parameter set to TRUE.

# **Chapter 3. Windows in the Curses Environment**

A curses program manipulates windows that appear on a terminal's display. A window is a rectangular portion of the display. A window can be as large as the entire display or as small as a single character in length and height.

**Note:** Pads are the exception. A pad is a window that is not restricted by the size of the screen. For more information, see "Pads" on page 8.

The following figure shows the different types of windows that exist in the curses environment:



Within a curses program, windows are variables declared as type WINDOW. The WINDOW data type is defined in the /usr/include/curses.h file as a C data structure. You create a window by allocating a portion of a machine's memory for a window structure. This structure describes the characteristics of the window. When a program changes the window data internally in memory, it must use the wrefresh() function (or equivalent function) to update the external, physical screen to reflect the internal change in the appropriate window structure.

Curses supplies a default window when the Curses library is initialized. You can create your own windows known as user-defined windows. Except for the amount of memory available to a program, there is no limit to the number of windows you can create. A curses program can manipulate the default window, user-defined windows, or both.

# **The Default Window Structure**

Curses provides a virtual default window called stdscr. The stdscr represents, in memory, the entire terminal display. The stdscr window structure is created automatically when the Curses library is initialized and it describes the display. When the library is initialized, the length and width variables are set to the length and width of the physical display.

In addition to the stdscr, you can define your own windows. These windows are known as user-defined windows to distinguish them from the stdscr. Like the stdscr, user-defined windows exist in machine memory as structures.

Programs that use the stdscr first manipulate the stdscr and then call the **refresh()** function to refresh the external display so that it matches the stdscr window.

# **The Current Window Structure**


Curses also supports another virtual window called curser (current screen). The curser window is an internal representation of what currently appears on the terminal's external display.

When a program requires the external representation to match the internal representation, it must call a function, such as the **wrefresh()** function, to update the physical display (or the **refresh()** function if the program is working with the stdscr). When a refresh is called on an internal window, curses copies the changed portions of the window into the curser and updates the physical display.

The cursor is reserved for internal use by curses. You should not manipulate the cursor.

# **Subwindows**

Curses also allows you to construct subwindows. Subwindows are rectangular portions within other windows. A subwindow is also of type WINDOW. The window that contains a subwindow is known as the subwindow's parent and the subwindow is known as the containing window's child. The following figure demonstrates the parent child relationship.



Changes to either the parent window or the child window within the area overlapped by the subwindow are made to both windows. After modifying a subwindow, you should call the **touchline()** or **touchwin()** function on the parent window before refreshing it. The **touchline()** and **touchwin()** functions instruct curses to discard its optimization information for the parent window and to consider the window as having changed. A refresh called on the parent refreshes the children as well.

A subwindow can also be a parent window. The process of layering windows inside of windows is called nesting. The number of nested subwindows is limited to the amount of memory available up to the value of SHRT_MAX as defined in the /usr/include/limits.h file. Before you can delete a parent window, you must first delete all of its children using the delwin() function. Curses returns an error if you try to delete a window before removing all of its children.

## **Pads**

A pad is a type of window that is not restricted by the terminal's display size or associated with a particular part of the display. You can use pads whenever your program requires a large window. Because a pad is usually larger than the physical display, only a portion of a pad is visible to the user at a given time.

Use pads when you have a large amount of related data that you want to keep all together in one window but you do not need to display all of the data at once.

Windows within pads are known as subpads. Subpads are positioned within a pad at coordinates relative to the parent pad. This placement differs from subwindows which are positioned using screen coordinates.

You should use the prefresh() function to show a portion of a pad on the display. Unlike other windows, scrolling or echoing of input does not automatically refresh a pad. Like subwindows, when changing the image of a subpad, you must call either the touchline() or touchwin() function on the parent pad before refreshing the parent. You can use all the curses function with pads except for the **newwin()**, **subwin()**, wrefresh(), and wnoutrefresh() functions. These functions are replaced with the newpad(), subpad(), prefresh(), and pnoutrefresh() functions.

# **Chapter 4. Manipulating Window Data with Curses**

When curses is initialized, the stdscr is provided automatically. You can manipulate the stdscr using the curses function library or you can create your own, user-defined windows.

# **Chapter 5. Curses Interfaces**

This chapter describes the Curses functions, macros and external variables to support application portability at the C-language source level. The interface definitions are collated as though any underscore characters were not present.

## addch()

### Name

addch, mvaddch, mvwaddch, waddch - add a single-byte character and rendition to a window and advance the cursor

### **Synopsis**

```
#include <curses.h>
int addch(const chtype ch);
int mvaddch(int y, int x, const chtype ch);
int mvwaddch(WINDOW *win, int y, int x, const chtype ch);
int waddch(WINDOW *win, const chtype ch);
```

### **Description**

The addch(), mvaddch(), mvwaddch() and waddch() functions place ch into the current or specified window at the current or specified position, and then advance the window's cursor position. These functions perform wrapping. These functions perform special-character processing.

#### Return Value

Upon successful completion, these functions return OK. Otherwise they return ERR.

### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

#### See Also

add_wch(), attroff(), doupdate(), <curses.h>.

# addchstr()

#### Name

addchstr, addchnstr, mvaddchstr, mvaddchnstr, mvwaddchstr, mvwaddchnstr waddchstr, waddchnstr - add string of single-byte characters and renditions to a window

### **Synopsis**

### **Description**

These functions overlay the contents of the current or specified window, starting at the current or specified position, with the contents of the array pointed to by *chstr* until a null *chtype* is encountered in the array pointed to by *chstr*.

These functions do not change the cursor position. These functions do not perform special-character processing. These functions do not perform wrapping.

The addchnstr(), mvaddchnstr(), mvwaddchnstr() and waddchnstr() functions copy at most n items, but no more than will fit on the line. If n is -1 then the whole string is copied, to the maximum number that fit on the line.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

### See Also

```
addch(), add_wch(), add_wchstr(), <curses.h>.
```

# addnstr()

### Name

addnstr, addstr, mvaddnstr, mvaddstr, mvwaddnstr, mvwaddstr waddnstr, waddstr - add a string of multibyte characters without rendition to a window and advance cursor

```
#include <curses.h>
int addnstr(const char *str, int n);
int addstr(const char *str);
```

```
int mvaddnstr(int y, int x, const char *str, int n);
int mvaddstr(int y, int x, const char *str);
int mvwaddnstr(WINDOW *win, int y, int x, char *const str, int n);
int mvwaddstr(WINDOW *win, int y, int x, char *const str);
int waddnstr(WINDOW *win, const char *str, int n);
int waddstr(WINDOW *win, const char *str);
```

These functions write the characters of the string *str* on the current or specified window starting at the current or specified position using the background rendition.

These functions advance the cursor position. These functions perform special character processing. These functions perform wrapping.

The addstr(), mvaddstr(), mvwaddstr() and waddstr() functions are similar to calling mbstowcs() on str, and then calling addwstr(), mvaddwstr(), mvwaddwstr() and waddwstr(), respectively.

The addnstr(), mvaddnstr(), mvwaddnstr() and waddnstr() functions use at most n bytes from str. These functions add the entire string when n is -1. These functions are similar to calling mbstowcs() on the first n bytes of str, and then calling addwstr(), mvaddwstr(), mvaddwstr() and waddwstr(), respectively.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

addnwstr(), mbstowcs(), <curses.h>.

## addnwstr()

#### Name

addnwstr, addwstr, mvaddnwstr, mvwaddnwstr, mvwaddnwstr, waddnwstr, waddnwstr, waddnwstr, waddwstr - add a wide-character string to a window and advance the cursor

```
#include <curses.h>
int addnwstr(const wchar_t *wstr, int n);
int addwstr(const wchar_t *wstr);
int mvaddnwstr(int y, int x, const wchar_t *wstr, int n);
int mvaddwstr(int y, int x, const wchar_t *wstr);
int mvwaddnwstr(WINDOW *win, int y, int x, const wchar_t *wstr, int n);
int mvwaddwstr(WINDOW *win, int y, int x, const wchar_t *wstr);
int waddnwstr(WINDOW *win, const wchar_t *wstr, int n);
int waddwstr(WINDOW *win, const wchar_t *wstr);
```

These functions write the characters of the wide character string *wstr* on the current or specified window at that window's current or specified cursor position.

These functions advance the cursor position. These functions perform special character processing. These functions perform wrapping.

The effect is similar to building a cchar_t from the wchar_t and the background rendition and calling wadd_wch(), once for each wchar_t character in the string. The cursor movement specified by the mv functions occurs only once at the start of the operation.

The addnwstr(), mvaddnwstr(), mvwaddnwstr() and waddnwstr() functions write at most n wide characters. If n is -1, then the entire string will be added.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

```
add_wch(), <curses.h>
```

## add_wch()

#### Name

add_wch, mvadd_wch, mvwadd_wch, wadd_wch - add a complex character and rendition to a window

## **Synopsis**

```
#include <curses.h>
int add_wch(cchar_t *const wch);
int wadd_wch(WINDOW *win, cchar_t *const wch);
int mvadd_wch(int y, int x, cchar_t *const wch);
int mvwadd_wch(WINDOW *win, int y, int x, cchar_t *const wch);
```

### **Description**

These functions add information to the current or specified window at the current or specified position, and then advance the cursor. These functions perform wrapping. These functions perform special-character processing.

- If wch refers to a spacing character, then any previous character at that location is removed, a new character specified by wch is placed at that location with rendition specified by wch; then the cursor advances to the next spacing character on the screen.
- If wch refers to a non-spacing character, all previous characters at that location are preserved, the non-spacing characters of wch are added to the spacing complex character, and the rendition specified by wch is ignored.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

addch(), <curses.h>.

## add_wchnstr()

### Name

add_wchnstr, add_wchstr, mvadd_wchstr, mvadd_wchstr, mvwadd_wchstr, mvwadd_wchstr, wadd_wchstr - add an array of complex characters and renditions to a window

### **Synopsis**

### **Description**

These functions write the array of cchar_t specified by *wchstr* into the current or specified window starting at the current or specified cursor position.

These functions do not advance the cursor. The results are unspecified if *wchstr* contains any special characters.

The functions end successfully on encountering a null cchar_t. The functions also end successfully when they fill the current line. If a character cannot completely fit at the end of the current line, those columns are filled with the background character and rendition.

The add_wchnstr(),  $mvadd_wchnstr()$ ,  $mvwadd_wchnstr()$  and  $wadd_wchnstr()$  functions end successfully after writing n cchar_ts (or the entire array of cchar_ts, if n is -1).

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

#### See Also

<curses.h>.

## attroff()

#### Name

attroff, attron, attrset, wattroff, wattron, wattrset - restricted window attribute control functions

### **Synopsis**

```
#include <curses.h>
int attroff(int attrs);
int attrset(int attrs);
int wattroff(WINDOW *win, int attrs);
int wattron(WINDOW *win, int attrs);
int wattrset(WINDOW *win, int attrs);
```

### **Description**

These functions manipulate the window attributes of the current or specified window.

The attroff() and wattroff() functions turn off  $\alpha ttrs$  in the current or specified window without affecting any others.

The attron() and wattron() functions turn on attrs in the current or specified window without affecting any others.

The attrset() and wattrset() functions set the background attributes of the current or specified window to attrs.

It is unspecified whether these functions can be used to manipulate attributes other than A_BLINK, A_BOLD, A_DIM, A_REVERSE, A_STANDOUT and A_UNDERLINE.

#### **Return Value**

These functions always return either OK or 1.

#### **Errors**

No errors are defined.

### See Also

```
attr_get(), standend(), <curses.h>.
```

# attr_get()

### Name

attr_get, attr_off, attr_on, attr_set, color_set, wattr_get, wattr_off, wattr_on, wattr_set, wcolor_set -- window attribute control functions

```
#include <curses.h>
int attr_get(attr_t *atttrs, short *color_pair_number, void *opts);
```

```
int attr_off(attr_t attrs, void *opts);
int attr_on(attr_t attrs, void *opts);
int attr_set(attr_t attrs, short color_pair_number, void *opts);
int color_set(short color_pair_number, void *opts);
in wattr_get (WINDOW *win, attr_t *attrs, short *color_pair_number, void *opts);
int wattr_off(WINDOW *win, attr_t attrs, void *opts);
int wattr_on(WINDOW *win, attr_t attrs, void *opts);
int wattr_set(WINDOW *win, attr_t attrs, short color_pair_number, void *opts);
int wcolor_set(WINDOW *win, short color_pair_number, void *opts);
```

These functions manipulate the attributes and color of the window rendition of the current or specified window.

The attr_get() and wattr_get() functions obtain the current rendition of a window. If attrs or color_pair_number is a null pointer, no information will be obtained on the corresponding rendition information and this is not an error.

The attr_off() and wattr_off() functions turn off attrs in the current or specified window without affecting any others.

The attr_on() and wattr_on() functions turn on attrs in the current or specified window without affecting any others.

The attr_set() and wattr_set() functions set the window rendition of the current or specified window to attrs and color_pair_number.

The color_set() and wcolor_set functions set the window color of the current or specified window to color pair number.

### **Return Value**

The attr_get() and wattr_get() functions return the current window attributes for the current or specified window.

The other functions always return OK.

#### **Errors**

No errors are defined.

#### See Also

attroff(), <curses.h>.

# baudrate()

#### Name

baudrate - get terminal baud rate

### **Synopsis**

```
#include <curses.h>
int baudrate(void);
```

### **Description**

The baudrate() function extracts the output speed of the terminal in bits per second.

### **Return Value**

The baudrate() function returns the output speed of the terminal.

### **Errors**

No errors are defined.

### See Also

tcgetattr(), <curses.h>.

# beep()

### Name

beep - audible signal

# **Synopsis**

```
#include <curses.h>
int beep(void);
```

### **Description**

The beep() function alerts the user. It sounds the audible alarm on the terminal, or if that is not possible, it flashes the screen (visible bell). If neither signal is possible, nothing happens.

### **Return Value**

The beep() function always returns OK.

### **Errors**

No errors are defined.

### **Application Usage**

Nearly all terminals have an audible alarm, but only some can flash the screen.

### See Also

flash(), <curses.h>.

## bkgd()

#### Name

bkgd, bkgdset, getbkgd, wbkgd, wbkgdset - turn off the previous background attributes, OR the requested attributes into the window rendition, and set or get background character and rendition using a single-byte character.

### **Synopsis**

```
#include <curses.h>
int bkgd(chtype ch);
void bkgdset(chtype ch);
chtype getbkgd(WINDOW *win);
int wbkgd(WINDOW *win, chtype ch);
void wbkgdset(WINDOW *win, chtype ch);
```

### Description

The bkgdset() and wbkgdset() functions turn off the previous background attributes, OR the requested attributes into the window rendition, and set the background attributes of the current or specified window based on the information in *ch*. If *ch* refers to a multi-column character, the results are undefined.

The bkgd() and wbkgd() functions turn off the previous background attributes, OR the requested attributes into the window rendition, and set the background property of the current or specified window and then apply this setting to every character position in that window:

- The rendition of every character on the screen is changed to the new background rendition.
- Wherever the former background character appears, it is changed to the new background character.

The getbkgd() function extracts the specified window's background character and rendition.

### **Return Value**

Upon successful completion, bkgd() and wbkgd() return OK. Otherwise, they return ERR.

The bkgdset() and wbkgdset() functions do not return a value.

Upon successful completion, getbkgd() returns the specified window's background character and rendition. Otherwise, it returns (chtype) ERR.

# bkgd()

#### **Errors**

No errors are defined.

# **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

### See Also

<curses.h>.

## bkgrnd()

#### Name

bkgrnd, bkgrndset, getbkgrnd, wbkgrnd, wbkgrndset, wgetbkgrnd — turn off the previous background attributes, OR the requested attributes into the window rendition, and set or get background character and rendition using a complex complex character

### **Synopsis**

```
#include <curses.h>
int bkgrnd(const cchar_t *wch);
void bkgrndset(const cchar_t *wch);
int getbkgrnd(cchar_t *wch);
int wbkgrnd(WINDOW *win, const cchar_t *wch);
void wbkgrndset(WINDOW *win, const cchar_t *wch);
int wgetbkgrnd(WINDOW *win, cchar_t *wch);
```

### **Description**

The bkgrndset() and wbkgrndset() functions turn off the previous background attributes, OR the requested attributes into the window rendition, and set the background property of the current or specified window based on the information in *wch*.

The bkgrnd() and wbkgrnd() functions turn off the previous background attributes, OR the requested attributes into the window rendition, and set the background property of the current or specified window and then apply this setting to every character position in that window:

- The rendition of every character on the screen is changed to the new background rendition.
- Wherever the former background character appears, it is changed to the new background character.

If *wch* refers to a non-spacing complex character for bkgrnd(), bkgrndset(), wbkgrnd() and wbkgrndset(), then *wch* is added to the existing spacing complex character that is the background character. If *wch* refers to a multi-column character, the results are unspecified.

The getbkgrnd() and wgetbkgrnd() functions store, into the area pointed to by wch, the value of the window's background character and rendition.

### **Return Value**

The bkgrndset() and wbkgrndset() functions do not return a value.

Upon successful completion, the other functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

<curses.h>.

## border()

#### Name

border, wborder - draw borders from single-byte characters and renditions

### **Synopsis**

### **Description**

The border() and wborder() functions draw a border around the edges of the current or specified window. These functions do not advance the cursor position. These functions do not perform special character processing. These functions do not perform wrapping.

The arguments in the left-hand column of the following table contain single-byte characters with renditions, which have the following uses in drawing the border:

Argument Name	Usage	Default Value
ls	Starting-column side	ACS_VLINE
rs	Ending-column side	ACS_VLINE
ts	First-line side	ACS_HLINE
bs	Last-line side	ACS_HLINE
tl	Corner of the first line and the starting column	ACS_ULCORNER
tr	Corner of the first line and the ending column	ACS_URCORNER
bl	Corner of the last line and the starting column	ACS_BLCORNER
br	Corner of the last line and the ending column	ACS_BRCORNER

If the value of any argument in the left-hand column is 0, then the default value in the right-hand column is used. If the value of any argument in the left-hand column is a multi-column character, the results are undefined.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

#### See Also

border_set(), box(), hline(), <curses.h>.

## border_set()

#### Name

border_set, wborder_set, - draw borders from complex characters and renditions

### **Synopsis**

## **Description**

The border_set() and wborder_set() functions draw a border around the edges of the current or specified window. These functions do not advance the cursor position. These functions do not perform special character processing. These functions do not perform wrapping.

The arguments in the left-hand column of the following table contain spacing complex characters with renditions, which have the following uses in drawing the border:

Argument Name	Usage	Default Value
ls	Starting-column side	WACS_VLINE
rs	Ending-column side	WACS_VLINE
ts	First-line side	WACS_HLINE
bs	Last-line side	WACS_HLINE
tl	Corner of the first line and the starting column	WACS_ULCORNER
tr	Corner of the first line and the ending column	WACS_URCORNER
bl	Corner of the last line and the starting column	WACS_BLCORNER
br	Corner of the last line and the ending column	WACS_BRCORNER

If the value of any argument in the left-hand column is a null pointer, then the default value in the right-hand column is used. If the value of any argument in the left-hand column is a multi-column character, the results are undefined.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

### See Also

box_set(), hline_set(), <curses.h>.

## box()

#### Name

box - draw borders from single-byte characters and renditions

### **Synopsis**

```
#include <curses.h>
int box(WINDOW *win, chtype verch, chtype horch);
```

### Description

The box() function draws a border around the edges of the specified window. This function does not advance the cursor position. This function does not perform special character processing. This function does not perform wrapping.

The function box (win, verch, horch) has an effect equivalent to:

```
wborder(win, verch, verch, horch, horch, 0, 0, 0, 0);
```

#### **Return Value**

Upon successful completion, box() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A prefix.

#### See Also

border(), box_set(), hline(), <curses.h>.

# box_set()

#### Name

box_set - draw borders from complex characters and renditions

```
#include <curses.h>
int box_set(WINDOW *win, const cchar_t *verch, const cchar_t *horch);
```

The box_set() function draws a border around the edges of the specified window. This function does not advance the cursor position. This function does not perform special character processing. This function does not perform wrapping.

The function box_set(win, verch, horch) has an effect equivalent to:

```
wborder_set(win, verch, verch, horch,
NULL, NULL, NULL, NULL);
```

### **Return Value**

Upon successful completion, this function returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

### See Also

border_set(), hline_set(), <curses.h>.

## can_change_color()

### Name

can_change_color, color_content, has_colors, init_color, init_pair, start_color, pair_content — color manipulation functions

## **Synopsis**

```
#include <curses.h>
bool can_change_color(void);
int color_content(short color, short *red, short *green, short *blue);
int COLOR_PAIR(int n);
bool has_colors(void);
int init_color(short color, short red, short green, short blue);
int init_pair(short pair, short f, short b);
int pair_content(short pair, short *f, short *b);
int PAIR_NUMBER(int value);
int start_color(void);
extern int COLOR_PAIRS;
extern int COLORS;
```

### **Description**

These functions manipulate color on terminals that support color.

### **Querying Capabilities**

The has_colors() function indicates whether the terminal is a color terminal. The can_change_color() function indicates whether the terminal is a color terminal on which colors can be redefined.

#### Initialization

The start_color() function must be called in order to enable use of colors and before any color manipulation function is called. The function initializes eight basic colors (black, blue, green, cyan, red, magenta, yellow, and white) that can be specified by the color macros (such as COLOR_BLACK) defined in **<curses.h>**. The initial appearance of these eight colors is not specified.

The function also initializes two global external variables:

- COLORS defines the number of colors that the terminal supports. (See Color Identification below.) If COLORS is 0, the terminal does not support redefinition of colors (and can_change_color() will return FALSE).
- COLOR_PAIRS defines the maximum number of color-pairs that the terminal supports. (See User-Defined Color Pairs below.)

The start_color() function also restores the colors on the terminal to terminal-specific initial values. The initial background color is assumed to be black for all terminals.

### **Color Identification**

The init_color() function redefines color number color, on terminals that support the redefinition of colors, to have the red, green, and blue intensity components specified by *red*, *green*, and *blue*, respectively. Calling init_color() also changes all occurrences of the specified color on the screen to the new definition.

The color_content() function identifies the intensity components of color number color. It stores the red, green, and blue intensity components of this color in the addresses pointed to by *red*, *green*, and *blue*, respectively.

For both functions, the color argument must be in the range from 0 to and including COLORS-1. Valid intensity values range from 0 (no intensity component) up to and including 1000 (maximum intensity in that component).

#### **User-Defined Color Pairs**

Calling init_pair() defines or redefines color-pair number pair to have foreground color f and background color f. Calling init_pair() changes any characters that were displayed in the color pair's old definition to the new definition and refreshes the screen.

After defining the color pair, the macro COLOR_PAIR(n) returns the value of color pair n. This value is the color attribute as it would be extracted from a chtype. Conversely, the macro PAIR_NUMBER(value) returns the color pair number associated with the color attribute value.

The pair_content() function retrieves the component colors of a color-pair number pair. It stores the foreground and background color numbers in the variables pointed to by f and b, respectively.

With init_pair() and pair_content(), the value of pair must be in a range from 0 to and including COLOR_PAIRS-1. (There may be an implementation-specific lower limit on the valid value of pair, but any such limit is at least 63.) Valid values for *f* and *b* are the range from 0 to and including COLORS-1.

#### **Return Value**

The has_colors() function returns TRUE if the terminal can manipulate colors; otherwise, it returns FALSE.

The can_change_color() function returns TRUE if the terminal supports colors and can change their definitions; otherwise, it returns FALSE.

Upon successful completion, the other functions return OK; otherwise, they return ERR.

#### **Errors**

No errors are defined.

### **Application Usage**

To use these functions, start_color() must be called, usually right after initscr().

The can_change_color() and has_colors() functions facilitate writing terminal-independent programs. For example, a programmer can use them to decide whether to use color or some other video attribute.

On color terminals, a typical value of COLORS is 8 and the macros such as COLOR_BLACK return a value within the range from 0 to and including 7. However, applications cannot rely on this to be true.

### See Also

```
attroff(), delscreen(), <curses.h>.
```

## cbreak()

### Name

cbreak, nocbreak, noraw, raw - input mode control functions

### **Synopsis**

```
#include <curses.h>
int cbreak(void);
int nocbreak(void);
int noraw(void);
int raw(void);
```

### **Description**

The cbreak() function sets the input mode for the current terminal to cbreak mode and overrides a call to raw().

The nocbreak() function sets the input mode for the current terminal to Cooked Mode without changing the state of ISIG and IXON.

The noraw() function sets the input mode for the current terminal to Cooked Mode and sets the ISIG and IXON flags.

The raw() function sets the input mode for the current terminal to Raw Mode.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

If the application is not certain what the input mode of the process was at the time it called initscr(), it should use these functions to specify the desired input mode.

#### See Also

<curses.h>.

## chgat()

### Name

chgat, mvchgat, mvwchgat, wchgat - change renditions of characters in a window

### **Synopsis**

### **Description**

These functions change the renditions of the next n characters in the current or specified window (or of the remaining characters on the line, if n is -1), starting at the current or specified cursor position. The attributes and colors are specified by attr and color as for setcchar().

These functions do not update the cursor. These functions do not perform wrapping.

A value of n that is greater than the remaining characters on a line is not an error.

The *opt*s argument is reserved for definition in a future edition of this document. Currently, the application must provide a null pointer as *opt*s.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

```
setcchar(), <curses.h>
```

# clear()

#### Name

clear, erase, wclear, werase - clear a window

```
#include <curses.h>
int clear(void);
int erase(void);
int wclear(WINDOW *win);
int werase(WINDOW *win);
```

The clear(), erase(), wclear() and werase() functions clear every position in the current or specified window.

The clear() and wclear() functions also achieve the same effect as calling clearok(), so that the window is cleared completely on the next call to wrefresh() for the window and is redrawn in its entirety.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

clearok(), doupdate(), <curses.h>.

## clearok()

### Name

clearok, idlok, leaveok, scrollok, setscrreg, wsetscrreg - terminal output control functions

### **Synopsis**

```
#include <curses.h>
int clearok(WINDOW *win, bool bf);
int idlok(WINDOW *win, bool bf);
int leaveok(WINDOW *win, bool bf);
int scrollok(WINDOW *win, bool bf);
int setscrreg(int top, int bot);
int wsetscrreg(WINDOW *win, int top, int bot);
```

### **Description**

These functions set options that deal with output within Curses.

The clearok() function assigns the value of *bf* to an internal flag in the specified window that governs clearing of the screen during a refresh. If, during a refresh operation on the specified window, the flag in curscr is TRUE or the flag in the specified window is TRUE, then the implementation clears the screen, redraws it in its entirety, and sets the flag to FALSE in curscr and in the specified window. The initial state is unspecified.

The idlok() function specifies whether the implementation may use the hardware insert-line, delete-line, and scroll features of terminals so equipped. If *bf* is TRUE, use of these features is enabled. If *bf* is FALSE, use of these features is disabled and lines are instead redrawn as required. The initial state is FALSE.

The leaveok() function controls the cursor position after a refresh operation. If *bf* is TRUE, refresh operations on the specified window may leave the terminal's cursor at an arbitrary position. If *bf* is FALSE, then at the end of any refresh operation, the terminal's cursor is positioned at the cursor position contained in the specified window. The initial state is FALSE.

The scrollok() function controls the use of scrolling. If *bf* is TRUE, then scrolling is enabled for the specified window. If *bf* is FALSE, scrolling is disabled for the specified window. The initial state is FALSE.

The setscrreg() and wsetscrreg() functions define a software scrolling region in the current or specified window. The *top* and *bot* arguments are the line numbers of the first and last line defining the scrolling region. (Line 0 is the top line of the window.) If this option and scrollok() are enabled, an attempt to move off the last line of the margin causes all lines in the scrolling region to scroll one line in the direction of the first line. Only characters in the window are scrolled. If a software scrolling region is set and scrollok() is not enabled, an attempt to move off the last line of the margin does not reposition any lines in the scrolling region.

#### **Return Value**

Upon successful completion, setscrreg() and wsetscrreg() return OK. Otherwise, they return ERR.

The other functions always return OK.

#### **Errors**

No errors are defined.

### **Application Usage**

The only reason to enable the idlok() feature is to use scrolling to achieve the visual effect of motion of a partial window, such as for a screen editor. In other cases, the feature can be visually annoying.

The leaveok() option provides greater efficiency for applications that do not use the cursor.

### See Also

```
clear(), delscreen(), doupdate(), scrl(), <curses.h>
```

## clrtobot()

#### Name

clrtobot, wclrtobot - clear from cursor to end of window

### **Synopsis**

```
#include <curses.h>
int clrtobot(void);
int wclrtobot(WINDOW *win);
```

### **Description**

The clrtobot() and wclrtobot() functions erase all lines following the cursor in the current or specified window, and erase the current line from the cursor to the end of the line, inclusive.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

### See Also

```
doupdate(), <curses.h>.
```

## clrtoeol()

### Name

clrtoeol, wclrtoeol - clear from cursor to end of line

### **Synopsis**

```
#include <curses.h>
int clrtoeol(void);
int wclrtoeol(WINDOW *win);
```

### **Description**

The clrtoeol() and wclrtoeol() functions erase the current line from the cursor to the end of the line, inclusive, in the current or specified window.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

### See Also

doupdate(), <curses.h>.

# color_content()

### Name

color_content - identify red/green/blue intensity of a color

### **Synopsis**

```
#include <curses.h>
int color_content(short color, short *red, short *green, short *blue);
```

# **Description**

Refer to can_change_color()

## COLOR_PAIRS

#### Name

COLOR_PAIRS, COLORS - external variables for color support

```
#include <curses.h>
```

```
extern int COLOR_PAIRS;
extern int COLORS;
```

Refer to can_change_color().

### COLS

#### Name

COLS - number of columns on terminal screen

### **Synopsis**

```
#include <curses.h>
extern int COLS;
```

## **Description**

The external variable COLS indicates the number of columns on the terminal screen.

### See Also

initscr(), <curses.h>.

## copywin()

#### Name

copywin - copy a region of a window

## **Synopsis**

### **Description**

The copywin() function provides a finer granularity of control over the overlay() and overwrite() functions. As in the prefresh() function, a rectangle is specified in the destination window, (dminrow, dmincol) and (dmaxrow, dmaxcol), and the upper-left-corner coordinates of the source window, (sminrow, smincol). If overlay is TRUE, then copying is non-destructive, as in overlay(). If overlay is FALSE, then copying is destructive, as in overwrite().

#### **Return Value**

Upon successful completion, copywin() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

### See Also

newpad(), overlay(), <curses.h>.

### curscr

#### Name

curscr - current window

### **Synopsis**

```
#include <curses.h>
extern WINDOW *curscr;
```

## **Description**

The external variable cursor points to an internal data structure. It can be specified as an argument to certain functions, such as clearok(), where permitted in this specification.

### See Also

clearok(), <curses.h>.

## curs_set()

#### Name

curs_set - set the cursor mode

## **Synopsis**

```
#include <curses.h>
int curs_set(int visibility);
```

## **Description**

The curs_set() function sets the appearance of the cursor based on the value of visibility:

Value of visibility	Appearance of Cursor
0	Invisible
1	Terminal-specific normal mode
2	Terminal-specific high visibility mode

The terminal does not necessarily support all the above values.

### **Return Value**

If the terminal supports the cursor mode specified by *visibility*, then curs_set() returns the previous cursor state. Otherwise, the function returns ERR.

### **Errors**

No errors are defined.

#### See Also

<curses.h>.

## cur_term()

#### Name

cur_term - current terminal information

### **Synopsis**

```
#include <term.h>
extern TERMINAL *cur_term;
```

### **Description**

The external variable *cur_term* identifies the record in the terminfo database associated with the terminal currently in use.

### See Also

```
set_curterm(), tigetflag(), <term.h>.
```

## def_prog_mode()

#### Name

def_prog_mode, def_shell_mode, reset_prog_mode, reset_shell_mode - save/restore program or shell terminal modes

# **Synopsis**

```
#include <curses.h>
int def_prog_mode(void);
int def_shell_mode(void);
int reset_prog_mode(void);
int reset_shell_mode(void);
```

## **Description**

The def_prog_mode() function saves the current terminal modes as the "program" (in Curses) state for use by reset_prog_mode().

The def_shell_mode() function saves the current terminal modes as the "shell" (not in Curses) state for use by reset_shell_mode().

The reset_prog_mode() function restores the terminal to the "program" (in Curses) state.

The reset_shell_mode() function restores the terminal to the "shell" (not in Curses) state.

These functions affect the mode of the terminal associated with the current screen.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

### **Application Usage**

The initscr() function achieves the effect of calling def_shell_mode() to save the prior terminal settings so they can be restored during the call to endwin(), and of calling def_prog_mode() to specify an initial definition of the program terminal mode.

Applications normally do not need to refer to the shell terminal mode. Applications may find it useful to save and restore the program terminal mode.

### See Also

doupdate(), endwin(), initscr(), <curses.h>.

## delay_output()

### Name

delay_output - delay output

### **Synopsis**

```
#include <curses.h>
int delay_output(int ms);
```

### Description

On terminals that support pad characters, delay_output() pauses the output for at least *ms* milliseconds. Otherwise, the length of the delay is unspecified.

### **Return Value**

Upon successful completion, delay_output() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

## **Application Usage**

Whether or not the terminal supports pad characters, the delay_output() function is not a precise method of timekeeping.

#### See Also

napms(), <curses.h>.

# delch()

#### Name

delch, mvdelch, mvwdelch, wdelch - delete a character from a window.

### **Synopsis**

```
#include <curses.h>
int delch(void);
int mvdelch(int y, int x);
int mvwdelch(WINDOW *win, int y, int x);
int wdelch(WINDOW *win);
```

### **Description**

These functions delete the character at the current or specified position in the current or specified window. This function does not change the cursor position.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

<curses.h>.

## del curterm()

#### Name

del curterm, restartterm, set curterm, setupterm - interfaces to the terminfo database

## **Synopsis**

```
#include <term.h>
int del_curterm(TERMINAL *oterm);
int restartterm(char *term, int fildes, int *errret);

TERMINAL *set_curterm(TERMINAL *nterm);
int setupterm(char *term, int fildes, int *errret);
extern TERMINAL *cur_term;
```

## Description

These functions retrieve information from the terminfo database.

To gain access to the terminfo database, setupterm() must be called first. It is automatically called by initscr() and newterm(). The setupterm() function initializes the other functions to use the terminfo record for a specified terminal (which depends on whether use_env() was called). It sets the *cur_term* external variable to a TERMINAL structure that contains the record from the terminfo database for the specified terminal.

The terminal type is the character string term; if term is a null pointer, the environment variable TERM is used. If TERM is not set or if its value is an empty string, then "unknown" is used as the terminal type. The application must set *fildes* to a file descriptor, open for output, to the terminal device, before calling

setupterm(). If *errret* is not null, the integer it points to is set to one of the following values to report the function outcome:

- **-1** The terminfo database was not found (function fails).
- **O**The entry for the terminal was not found in terminfo (function fails).
- **1** Success.

If setupterm() detects an error and *errret* is a null pointer, setupterm() writes a diagnostic message and exits.

A simple call to setupterm() that uses all the defaults and sends the output to stdout is:

```
setupterm((char *)0, fileno(stdout), (int *)0);
```

The set_curterm() function sets the variable *cur_term* to *nterm*, and makes all of the terminfo boolean, numeric, and string variables use the values from *nterm*.

The del_curterm() function frees the space pointed to by *oterm* and makes it available for further use. If *oterm* is the same as cur_term, references to any of the terminfo boolean, numeric, and string variables thereafter may refer to invalid memory locations until setupterm() is called again.

The restartterm() function assumes a previous call to setupterm() (perhaps from initscr() or newterm()). It lets the application specify a different terminal type in *term* and updates the information returned by baudrate() based on *fildes*, but does not destroy other information created by initscr(), newterm() or setupterm().

### **Return Value**

Upon successful completion, set_curterm() returns the previous value of cur_term. Otherwise, it returns a null pointer.

Upon successful completion, the other functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

An application would call setupterm() if it required access to the terminfo database but did not otherwise need to use Curses.

### See Also

baudrate(), erasechar(), has_ic(), longname(), putc(), termattrs(), termname(), tgetent(), tigetflag(), use_env(), <term.h>.

# deleteln()

#### Name

deleteln, wdeleteln - delete lines in a window

```
#include <curses.h>
int deleteln(void);
```

```
int wdeleteln(WINDOW *win);
```

The deleteln() and wdeleteln() functions delete the line containing the cursor in the current or specified window and move all lines following the current line one line toward the cursor. The last line of the window is cleared. The cursor position does not change.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

### See Also

insdelln(), <curses.h>.

# delscreen()

#### Name

delscreen - free storage associated with a screen

### **Synopsis**

```
#include <curses.h>
void delscreen(SCREEN *sp);
```

### **Description**

The delscreen() function frees storage associated with the SCREEN pointed to by *sp*.

### **Return Value**

The delscreen() function does not return a value.

### **Errors**

No errors are defined.

#### See Also

endwin(), initscr(), <curses.h>.

# delwin()

### Name

delwin - delete a window

### **Synopsis**

```
#include <curses.h>
int delwin(WINDOW *win);
```

### **Description**

The delwin() function deletes win, freeing all memory associated with it. The application must delete subwindows before deleting the main window.

### **Return Value**

Upon successful completion, delwin() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

### See Also

derwin(), dupwin(), <curses.h>.

## derwin()

#### Name

derwin, newwin, subwin - window creation functions

### **Synopsis**

## Description

The derwin() function is the same as subwin(), except that *begin_y* and *begin_x* are relative to the origin of the window orig rather than absolute screen positions.

The newwin() function creates a new window with *nlines* lines and *ncols* columns, positioned so that the origin is (*begin_y*, *begin_x*). If *nlines* is zero, it defaults to LINES - *begin_y*; if *ncols* is zero, it defaults to COLS - *begin_x*.

The subwin() function creates a new window with *nlines* lines and *ncols* columns, positioned so that the origin is at (*begin_y*, *begin_x*). (This position is an absolute screen position, not a position relative to the window *orig*.) If any part of the new window is outside *orig*, the function fails and the window is not created.

### **Return Value**

Upon successful completion, these functions return a pointer to the new window. Otherwise, they return a null pointer.

### **Errors**

No errors are defined.

### **Application Usage**

Before performing the first refresh of a subwindow, portable applications should call touchwin() or touchline() on the parent window.

Each window maintains internal descriptions of the screen image and status. The screen image is shared among all windows in the window hierarchy. Refresh operations rely on information on what has changed within a window, which is private to each window.

Refreshing a window, when updates were made to a different window, may fail to perform needed updates because the windows do not share this information.

A new full-screen window is created by calling:

```
newwin(0, 0, 0, 0);
```

### See Also

delwin(), is_linetouched(), doupdate(), <curses.h>.

## doupdate()

### Name

doupdate, refresh, wnoutrefresh, wrefresh - refresh windows and lines

## **Synopsis**

```
#include <curses.h>
int doupdate(void);
int refresh(void);
int wnoutrefresh(WINDOW *win);
int wrefresh(WINDOW *win);
```

### **Description**

The refresh() and wrefresh() functions refresh the current or specified window. The functions position the terminal's cursor at the cursor position of the window, except that if the leaveok() mode has been enabled, they may leave the cursor at an arbitrary position.

The wnoutrefresh() function determines which parts of the terminal may need updating. The doupdate() function sends to the terminal the commands to perform any required changes.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise they return ERR.

#### **Errors**

No errors are defined.

### **Application Usage**

Refreshing an entire window is typically more efficient than refreshing several subwindows separately. An efficient sequence is to call wnoutrefresh() on each subwindow that has changed, followed by a call to doupdate(), which updates the terminal.

The refresh() or wrefresh() function (or wnoutrefresh() followed by doupdate()) must be called to send output to the terminal, as other Curses functions merely manipulate data structures.

### See Also

```
clearok(), redrawwin(), <curses.h>.
```

# dupwin()

#### Name

dupwin - duplicate a window

## **Synopsis**

```
#include <curses.h>
WINDOW *dupwin(WINDOW *win);
```

## **Description**

The dupwin() function creates a duplicate of the window win.

### **Return Value**

Upon successful completion, dupwin() returns a pointer to the new window. Otherwise, it returns a null pointer.

#### **Errors**

No errors are defined.

### See Also

derwin(), doupdate(), <curses.h>.

# echo()

### Name

echo, noecho -- enable/disable terminal echo

```
#include <curses.h>
int echo(void);
int noecho(void);
```

The echo() function enables Echo mode for the current screen. The noecho() function disables Echo mode for the current screen is enabled and hardware echo mode of the tty driver is disabled. echo() and noecho() control software echo only. Hardware echo must remain disabled for the duration of the application, else the behavior is undefined.

### Return Value

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

getch(), <curses.h>.

## echochar()

### Name

echochar, wechochar - echo single-byte character and rendition to a window and refresh

### **Synopsis**

```
#include <curses.h>
int echochar(const chtype ch);
int wechochar(WINDOW *win, const chtype ch);
```

### **Description**

The echochar() function is equivalent to a call to addch() followed by a call to refresh().

The wechochar() function is equivalent to a call to waddch() followed by a call to wrefresh().

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

### See Also

addch(), doupdate(), echo_wchar(), <curses.h>.

## echo_wchar()

### Name

echo_wchar, wecho_wchar - write a complex character and immediately refresh the window

### **Synopsis**

```
#include <curses.h>
int echo_wchar(const cchar_t *wch);
int wecho_wchar(WINDOW *win, const cchar_t *wch);
```

### **Description**

The echo_wchar() function is equivalent to calling add_wch() and then calling refresh().

The wecho_wchar() function is equivalent to calling wadd_wch() and then calling wrefresh().

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

addch(), add_wch(), doupdate(), <curses.h>.

# endwin()

### Name

endwin - suspend Curses session

## **Synopsis**

```
#include <curses.h>
int endwin(void);
```

## **Description**

The endwin() function restores the terminal after Curses activity by at least restoring the saved shell terminal mode, flushing any output to the terminal and moving the cursor to the first column of the last line of the screen. Refreshing a window resumes program mode. The application must call endwin() for each terminal being used before exiting. If newterm() is called more than once for the same terminal, the first screen created must be the last one for which endwin() is called.

### **Return Value**

Upon successful completion, endwin() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

## **Application Usage**

The endwin() function does not free storage associated with a screen, so delscreen() should be called after endwin() if a particular screen is no longer needed.

To leave Curses mode temporarily, portable applications should call endwin(). Subsequently, to return to Curses mode, they should call doupdate(), refresh() or wrefresh().

### See Also

delscreen(), doupdate(), initscr(), isendwin(), <curses.h>.

# erase()

#### Name

erase, werase - clear a window

## **Synopsis**

```
#include <curses.h>
int erase(void);
int werase(WINDOW *win);
```

## Description

Refer to clear().

# erasechar()

#### Name

erasechar, erasewchar, killchar, killwchar - terminal environment query functions

# **Synopsis**

```
#include <curses.h>
char erasechar(void);
int erasewchar(wchar_t *ch);
char killchar(void);
int killwchar(wchar_t *ch);
```

# **Description**

The erasechar() function returns the current erase character. The erasewchar() function stores the current erase character in the object pointed to by *ch*. If no erase character has been defined, the function will fail and the object pointed to by *ch* will not be changed.

The killchar() function returns the current line kill character. The killwchar() function stores the current line kill character in the object pointed to by ch. If no line kill character has been defined, the function will fail and the object pointed to by ch will not be changed.

#### **Return Value**

The erasechar() function returns the erase character and killchar() returns the line kill character. The return value is unspecified when these characters are multi-byte characters.

Upon successful completion, erasewchar() and killwchar() return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

The erasechar() and killchar() functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix. Moreover, they do not reliably indicate cases in which when the erase or line kill character, respectively, has not been defined. The erasewchar() and killwchar() functions overcome these limitations.

### See Also

clearok(), delscreen(), tcgetattr(), <curses.h>.

## filter()

#### Name

filter - disable use of certain terminal capabilities

## **Synopsis**

```
#include <curses.h>
void filter(void);
```

# Description

The filter() function changes the algorithm for initializing terminal capabilities that assume that the terminal has more than one line. A subsequent call to initscr() or newterm() performs the following additional actions:

- Disable use of clear, cud, cud1, cup, cuu1 and vpa
- Set the value of the home string to the value of the cr string
- Set lines equal to 1.

Any call to filter() must precede the call to initscr() or newterm().

#### **Return Value**

The filter() function does not return a value.

### **Errors**

No errors are defined.

### See Also

initscr(), <curses.h>.

# flash()

#### Name

flash - flash the screen

## **Synopsis**

```
#include <curses.h>
int flash(void);
```

## **Description**

The flash() function alerts the user. It flashes the screen, or if that is not possible, it sounds the audible alarm on the terminal. If neither signal is possible, nothing happens.

### **Return Value**

The flash() function always returns OK.

#### **Errors**

No errors are defined.

## **Application Usage**

Nearly all terminals have an audible alarm, but only some can flash the screen.

### See Also

beep(), <curses.h>

# flushinp()

### Name

flushinp - discard input

# **Synopsis**

```
#include <curses.h>
int flushinp(void);
```

# Description

The flushinp() function discards (flushes) any characters in the input buffer associated with the current screen.

### **Return Value**

The flushinp() function always returns OK.

### **Errors**

No errors are defined.

### See Also

<curses.h>.

# getbegyx()

### Name

getbegyx, getmaxyx, getparyx, getyx - get cursor and window coordinates

## **Synopsis**

```
#include <curses.h>
void getbegyx(WINDOW *win, int y, int x);
void getmaxyx(WINDOW *win, int y, int x);
void getparyx(WINDOW *win, int y, int x);
void getyx(WINDOW *win, int y, int x);
```

## **Description**

The getyx() macro stores the cursor position of the specified window in y and x.

The getparyx() macro, if the specified window is a subwindow, stores in y and x the coordinates of the window's origin relative to its parent window. Otherwise, -1 is stored in y and x.

The getbegyx() macro stores the absolute screen coordinates of the specified window's origin in y and x.

The getmaxyx() macro stores the number of rows of the specified window in y and stores the window's number of columns in x.

#### **Return Value**

No return values are defined.

#### **Errors**

No errors are defined.

# **Application Usage**

These interfaces are macros and '&' cannot be used before the y and x arguments. Traditional implementations have often defined the following macros:

```
void getbegx(WINDOW *win, int x);
void getbegy(WINDOW *win, int y);
void getmaxx(WINDOW *win, int x);
void getmaxy(WINDOW *win, int y);
void getparx(WINDOW *win, int x);
void getpary(WINDOW *win, int y);
```

Although getbegyx(), getmaxyx() and getparyx() provide the required functionality, this does not preclude applications from defining these macros for their own use. For example, to implement void getbegx(WINDOW *win, int x); the macro would be

```
#define getbegx(_win,_x); /
{
    int _y; /
    getbegyx(_win,_y,_x);
}
```

### See Also

<curses.h>

# getbkgd()

#### Name

getbkgd - get background character and rendition using a single-byte character

## **Synopsis**

```
#include <curses.h>
chtype getbkgd(WINDOW *win);
```

## **Description**

Refer to bkgd().

# getbkgrnd()

#### Name

getbkgrnd - get background character and rendition

# **Synopsis**

```
#include <curses.h>
int getbkgrnd(cchar_t *ch);
```

## **Description**

Refer to bkgrnd().

# getcchar()

### Name

getcchar - get a wide character string and rendition from a cchar_t

# **Synopsis**

# Description

When *wch* is not a null pointer, the getcchar() function extracts information from a cchar_t defined by *wcval*, stores the character attributes in the object pointed to by *attrs*, stores the color pair in the object pointed to by *color_pair*, and stores the wide character string referenced by *wcval* into the array pointed to by *wch*.

When *wch* is a null pointer, getcchar() obtains the number of wide characters in the object pointed to by *wcval* and does not change the objects pointed to by *attrs* or *color_pair*.

The *opts* argument is reserved for definition in a future edition of this document. Currently, the application must provide a null pointer as *opts*.

#### **Return Value**

When *wch* is a null pointer, getcchar() returns the number of wide characters referenced by *wcval*, including the null terminator.

When wch is not a null pointer, getcchar() returns OK upon successful completion, and ERR otherwise.

#### **Errors**

No errors are defined.

## **Application Usage**

The *wcval* argument may be a value generated by a call to setcchar() or by a function that has a cchar_t output argument. If *wcval* is constructed by any other means, the effect is unspecified.

#### See Also

```
attroff(), can_change_color(), setcchar(), <curses.h>.
```

# getch()

#### Name

getch, wgetch, mvgetch, mvwgetch - get a single-byte character from the terminal

# **Synopsis**

```
#include <curses.h>
int getch(void);
int mvgetch(int y, int x);
int mvwgetch(WINDOW *win, int y, int x);
int wgetch(WINDOW *win);
```

# **Description**

These functions read a single-byte character from the terminal associated with the current or specified window. The results are unspecified if the input is not a single-byte character. If keypad() is enabled, these functions respond to the pressing of a function key by returning the corresponding KEY_ value defined in <curses.h>.

If echoing is enabled, then the character is echoed as though it were provided as an input argument to addch(), except for the following characters:

<backspace>,<br/><left-arrow> and<br/>the current erase<br/>character:

The input is interpreted and then the character at the resulting cursor position is deleted as though delch() were called, except that if the cursor was originally in the first column of the line, then the user is alerted as though beep() were called.

Function keys

The user is alerted as though beep() were called. Information concerning the function keys is not returned to the caller.

If the current or specified window is not a pad, and it has been moved or modified since the last refresh operation, then it will be refreshed before another character is read.

#### **Return Value**

Upon successful completion, **getch**(), **mvgetch**, **mvwgetch**() and **wgetch()** return the single-byte character, KEY_ value, or ERR. When in the nodelay mode and no data is available, ERR is returned.

#### **Errors**

No errors are defined.

## **Application Usage**

Applications should not define the escape key by itself as a single-character function.

When using these functions, nocbreak mode (nocbreak()) and echo mode (echo()) should not be used at the same time. Depending on the state of the terminal when each character is typed, the program may produce undesirable results.

#### See Also

cbreak(), doupdate(), insch(), <curses.h>.

# getmaxyx()

### Name

getmaxyx - get size of a window

# **Synopsis**

```
#include <curses.h>
void getmaxyx(WINDOW *win, int y, int x);
```

## **Description**

Refer to getbegyx().

# getnstr()

#### Name

getnstr, getstr, mvgetnstr, mvgetstr, mvwgetnstr, wgetstr, wgetnstr - get a multi-byte character string from the terminal

```
#include <curses.h>
int getnstr(char *str, int n);
int getstr(char *str);
int mvgetnstr(int y, int x, char *str, int n);
int mvgetstr(int y, int x, char *str);
int mvwgetnstr(WINDOW *win, int y, int x, char *str, int n);
```

```
int mvwgetstr(WINDOW *win, int y, int x, char *str);
int wgetnstr(WINDOW *win, char *str, int n);
int wgetstr(WINDOW *win, char *str);
```

The effect of getstr() is as though a series of calls to getch() were made, until a newline or carriage return is received. The resulting value is placed in the area pointed to by str. The string is then terminated with a null byte. The getnstr(), mvgetnstr(), mvwgetnstr() and wgetnstr() functions read at most n bytes, thus preventing a possible overflow of the input buffer. The user's erase and kill characters are interpreted, as well as any special keys (such as function keys, home key, clear key, and so on).

The mvgetstr() function is identical to getstr() except that it is as though it is a call to move() and then a series of calls to getch(). The mvwgetstr() function is identical to getstr() except it is as though a call to wmove() is made and then a series of calls to wgetch(). The mvgetnstr() function is identical to getnstr() except that it is as though it is a call to move() and then a series of calls to getch(). The mvwgetnstr() function is identical to getnstr() except it is as though a call to wmove() is made and then a series of calls to wgetch().

The getnstr(), wgetnstr(), mvgetnstr() and mvwgetnstr() functions will only return the entire multi-byte sequence associated with a character. If the array is large enough to contain at least one character, the functions fill the array with complete characters. If the array is not large enough to contain any complete characters, the function fails.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

Reading a line that overflows the array pointed to by *str* with getstr(), mvgetstr(), mvwgetstr() or wgetstr() causes undefined results. The use of getnstr(), mvgetnstr(), mvwgetnstr() or wgetnstr(), respectively, is recommended.

#### See Also

beep(), getch(), <curses.h>.

# getn_wstr()

#### Name

getn_wstr, get_wstr, mvgetn_wstr, mvget_wstr, mvwgetn_wstr, mvwget_wstr, wgetn_wstr, wget_wstr - get an array of wide characters and function key codes from a terminal

```
#include <curses.h>
int getn_wstr(wint_t *wstr, int n);
int get_wstr(wint_t *wstr);
int mvgetn_wstr(int y, int x, wint_t *wstr, int n);
int mvget_wstr(int y, int x, wint_t *wstr);
```

```
int mvwgetn_wstr(WINDOW *win, int y, int x, wint_t *wstr, int n);
int mvwget_wstr(WINDOW *win, int y, int x, wint_t *wstr);
int wgetn_wstr(WINDOW *win, wint_t *wstr, int n);
int wget_wstr(WINDOW *win, wint_t *wstr);
```

The effect of get_wstr() is as though a series of calls to get_wch() were made, until a newline character, end-of-line character, or end-of-file character is processed. An end-of-file character is represented by WEOF, as defined in <wchar.h>. A newline or end-of-line is represented as its wchar_t value. In all instances, the end of the string is terminated by a null wchar_t. The resulting values are placed in the area pointed to by wstr.

The user's erase and kill characters are interpreted and affect the sequence of characters returned.

The effect of wget_wstr() is as though a series of calls to wget_wch() were made.

The effect of mvget_wstr() is as though a call to move() and then a series of calls to get_wch() were made. The effect of mvwget_wstr() is as though a call to wmove() and then a series of calls to wget_wch() were made. The effect of mvget_nwstr() is as though a call to move() and then a series of calls to get_wch() were made. The effect of mvwget_nwstr() is as though a call to wmove() and then a series of calls to wget_wch() were made.

The getn_wstr(), mvgetn_wstr(), mvwgetn_wstr() and wgetn_wstr() functions read at most *n* characters, letting the application prevent overflow of the input buffer.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

Reading a line that overflows the array pointed to by wstr with get_wstr(), mvget_wstr(), mvwget_wstr() or wget_wstr() causes undefined results. The use of getn_wstr(), mvgetn_wstr(), mvwgetn_wstr() or wgetn_wstr(), respectively, is recommended.

These functions cannot return KEY_ values as there is no way to distinguish a KEY_ value from a valid wchar_t value.

#### See Also

```
get wch(), getstr(), <curses.h>, <wchar.h>.
```

# getparyx()

#### Name

getparyx - get subwindow origin coordinates

```
#include <curses.h>
void getparyx(WINDOW *win, int y, int x);
```

Refer to getbegyx().

# getstr()

#### Name

getstr - get a multi-byte character string from the terminal

## **Synopsis**

```
#include <curses.h>
int getstr(char *str);
```

## **Description**

Refer to getnstr().

# get_wch()

#### Name

get_wch, mvget_wch, mvwget_wch, wget_wch - get a wide character from a terminal

# **Synopsis**

```
#include <curses.h>
int get_wch(wint_t *ch);
int mvget_wch(int y, int x, wint_t *ch);
int mvwget_wch(WINDOW *win, int y, int x, wint_t *ch);
int wget_wch(WINDOW *win, wint_t *ch);
```

# Description

These functions read a character from the terminal associated with the current or specified window. If keypad() is enabled, these functions respond to the pressing of a function key by setting the object pointed to by *ch* to the corresponding KEY_ value defined in **<curses.h>** and returning KEY_CODE_YES.

Processing of terminal input is subject to the general rules.

If echoing is enabled, then the character is echoed as though it were provided as an input argument to add wch(), except for the following characters:

<backspace>,<br/><left-arrow> and<br/>the current erase<br/>character:

The input is interpreted and then the character at the resulting cursor position is deleted as though delch() were called, except that if the cursor was originally in the first column of the line, then the user is alerted as though beep() were called.

Function keys

The user is alerted as though beep() were called. Information concerning the function keys is not returned to the caller.

If the current or specified window is not a pad, and it has been moved or modified since the last refresh operation, then it will be refreshed before another character is read.

#### **Return Value**

When these functions successfully report the pressing of a function key, they return KEY_CODE_YES. When they successfully report a wide character, they return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

Applications should not define the escape key by itself as a single-character function.

When using these functions, nocbreak mode and echo mode should not be used at the same time. Depending on the state of the terminal when each character is typed, the application may produce undesirable results.

### See Also

beep(), cbreak(), ins_wch(), keypad(), move(), <curses.h>, <wchar.h>.

# getwin()

#### Name

getwin, putwin - dump window to, and reload window from, a file

## **Synopsis**

```
#include <curses.h>
WINDOW *getwin(FILE *filep);
int putwin(WINDOW *win, FILE *filep);
```

### **Description**

The getwin() function reads window-related data stored in the file by putwin(). The function then creates and initializes a new window using that data.

The putwin() function writes all data associated with win into the stdio stream to which filep points, using an unspecified format. This information can be retrieved later using getwin().

### **Return Value**

Upon successful completion, getwin() returns a pointer to the window it created. Otherwise, it returns a null pointer.

Upon successful completion, putwin() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

#### See Also

scr_dump(), <curses.h>.

# get_wstr()

#### Name

get_wstr - get an array of wide characters and function key codes from a terminal

## **Synopsis**

```
#include <curses.h>
int get_wstr(wint_t *wstr);
```

## **Description**

Refer to getn_wstr().

# getyx()

### Name

getyx - get cursor coordinates

## **Synopsis**

```
#include <curses.h>
void getyx(WINDOW *win, int y, int x);
```

# **Description**

Refer to getbegyx().

# halfdelay()

### Name

halfdelay - control input character delay mode

# **Synopsis**

```
#include <curses.h>
int halfdelay(int tenths);
```

# **Description**

The halfdelay() function sets the input mode for the current window to Half-Delay Mode and specifies tenths of seconds as the half-delay interval. The *tenths* argument must be in a range from 1 up to and including 255.

### **Return Value**

Upon successful completion, halfdelay() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

## **Application Usage**

The application can call nocbreak() to leave Half-Delay mode.

### See Also

```
cbreak(), <curses.h>.
```

# has_colors()

#### Name

has_colors - indicate whether terminal supports colors

## **Synopsis**

```
#include <curses.h>
bool has_colors(void);
```

## **Description**

Refer to can_change_color().

# has_ic()

### Name

has_ic, has_il - query functions for terminal insert and delete capability

# **Synopsis**

```
#include <curses.h>
bool has_ic(void);
bool has_il(void);
```

# **Description**

The has_ic() function indicates whether the terminal has insert- and delete-character capabilities.

The has_il() function indicates whether the terminal has insert- and delete-line capabilities, or can simulate them using scrolling regions.

### **Return Value**

The has_ic() function returns TRUE if the terminal has insert- and delete-character capabilities. Otherwise, it returns FALSE.

The has_il() function returns TRUE if the terminal has insert- and delete-line capabilities. Otherwise, it returns FALSE.

### **Errors**

No errors are defined.

## **Application Usage**

The has_il() function may be used to determine if it would be appropriate to turn on physical scrolling using scrollok().

### See Also

<curses.h>.

# hline()

### Name

hline, mvhline, mvvline, mvwvline, vline, whline, wvline - draw lines from single-byte characters and renditions

## **Synopsis**

```
#include <curses.h>
int hline(chtype ch, int n);
int mvhline(int y, int x, chtype ch, int n);
int mvvline(int y, int x, chtype ch, int n);
int mvwhline(WINDOW *win, int y, int x, chtype ch, int n);
int mvwvline(WINDOW *win, int y, int x, chtype ch, int n);
int vline(chtype ch, int n);
int whline(WINDOW *win, chtype ch, int n);
int wvline(WINDOW *win, chtype ch, int n);
```

## **Description**

These functions draw a line in the current or specified window starting at the current or specified position, using ch. The line is at most n positions long, or as many as fit into the window.

These functions do not advance the cursor position. These functions do not perform special character processing. These functions do not perform wrapping.

The hline(), mvhline(), mvwhline() and whline() functions draw a line proceeding toward the last column of the same line.

The vline(), mvvline() and wvline() functions draw a line proceeding toward the last line of the window.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# hline()

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

#### See Also

border(), box(), hline set(), <curses.h>.

# hline set()

#### Name

hline_set, mvhline_set, mvvline_set, mvwhline_set, wvline_set, wline_set, wvline_set - draw lines from complex characters and renditions

## **Synopsis**

```
#include <curses.h>
int hline_set(const cchar_t *wch, int n);
int mvhline_set(int y, int x, const cchar_t *wch, int n);
int mvvline_set(int y, int x, const cchar_t *wch, int n);
int mvwhline_set(WINDOW *win, int y, int x, const cchar_t *wch, int n);
int mvwvline_set(WINDOW *win, int y, int x, const cchar_t *wch, int n);
int vline_set(const cchar_t *wch, int n);
int whline_set(WINDOW *win, const cchar_t *wch, int n);
int wvline_set(WINDOW *win, cchar_t *const wch, int n);
```

## **Description**

These functions draw a line in the current or specified window starting at the current or specified position, using ch. The line is at most n positions long, or as many as fit into the window.

These functions do not advance the cursor position. These functions do not perform special character processing. These functions do not perform wrapping.

The hline_set(), mvhline_set(), mvwhline_set() and whline_set() functions draw a line proceeding toward the last column of the same line.

The vline_set(), mvvline_set(), mvvvline_set() and wvline_set() functions draw a line proceeding toward the last line of the window.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# hline_set()

### See Also

border_set(), <curses.h>.

# idcok()

#### Name

idcok - enable or disable use of hardware insert- and delete-character features

## **Synopsis**

```
#include <curses.h>
void idcok(WINDOW *win, bool bf);
```

# **Description**

The idcok() function specifies whether the implementation may use hardware insert- and delete-character features in *win* if the terminal is so equipped. If *bf* is TRUE, use of these features in *win* is enabled. If *bf* is FALSE, use of these features in *win* is disabled. The initial state is TRUE.

### **Return Value**

The idcok() function does not return a value.

### **Errors**

No errors are defined.

### See Also

clearok(), doupdate(), <curses.h>.

# idlok()

#### Name

idlok - enable or disable use of terminal insert- and delete-line features

# **Synopsis**

```
#include <curses.h>
int idlok(WINDOW *win, bool bf);
```

# **Description**

Refer to clearok().

# immedok()

#### Name

immedok - enable or disable immediate terminal refresh

## **Synopsis**

```
#include <curses.h>
void immedok(WINDOW *win, bool bf);
```

## **Description**

The immedok() function specifies whether the screen is refreshed whenever the window pointed to by win is changed. If bf is TRUE, the window is implicitly refreshed on each such change. If bf is FALSE, the window is not implicitly refreshed. The initial state is FALSE.

#### Return Value

The immedok() function does not return a value.

#### **Errors**

No errors are defined.

## **Application Usage**

The immedok() function is useful for windows that are used as terminal emulators.

### See Also

```
clearok(), doupdate(), <curses.h>.
```

# inch()

### Name

inch, mvinch, mvwinch, winch - input a single-byte character and rendition from a window

# **Synopsis**

```
#include <curses.h>
chtype inch(void);
chtype mvinch(int y, int x);
chtype mvwinch(WINDOW *win, int y, int x);
chtype winch(WINDOW *win);
```

# **Description**

These functions return the character and rendition, of type chtype, at the current or specified position in the current or specified window.

#### **Return Value**

Upon successful completion, the functions return the specified character and rendition. Otherwise, they return (chtype)ERR.

### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

#### See Also

<curses.h>.

# inchnstr()

#### Name

inchnstr, inchstr, mvinchnstr, mvinchstr, mvwinchnstr, mvwinchstr, winchnstr, winchstr - input an array of single-byte characters and renditions from a window

# **Synopsis**

```
#include <curses.h>
int inchnstr(chtype *chstr, int n);
int inchstr(chtype *chstr);
int mvinchnstr(int y, int x, chtype *chstr, int n);
int mvinchstr(int y, int x, chtype *chstr);
int mvwinchnstr(WINDOW *win, int y, int x, chtype *chstr, int n);
int mvwinchstr(WINDOW *win, int y, int x, chtype *chstr);
int winchnstr(WINDOW *win, chtype *chstr, int n);
int winchstr(WINDOW *win, chtype *chstr);
```

# **Description**

These functions place characters and renditions from the current or specified window into the array pointed to by *chstr*, starting at the current or specified position and ending at the end of the line.

The inchnstr(), mvinchnstr(), mvwinchnstr() and winchnstr() functions store at most n elements from the current or specified window into the array pointed to by *chstr*.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

Reading a line that overflows the array pointed to by *chstr* with inchstr(), mvinchstr(), mvwinchstr() or winchstr() causes undefined results. The use of inchnstr(), mvinchnstr(), mvwinchnstr() or winchnstr(), respectively, is recommended.

### See Also

inch(), <curses.h>.

# init_color()

#### Name

init_color, init_pair - redefine specified color or color pair

## **Synopsis**

```
#include <curses.h>
int init_color(short color, short red, short green, short blue);
int init_pair(short pair, short f, short b);
```

## **Description**

Refer to can_change_color().

# initscr()

#### Name

initscr, newterm - screen initialization functions

# **Synopsis**

```
#include <curses.h>
WINDOW *initscr(void);
SCREEN *newterm(char *type, FILE *outfile, FILE *infile);
```

# **Description**

The initscr() function determines the terminal type and initializes all implementation data structures. The TERM environment variable specifies the terminal type. The initscr() function also causes the first refresh operation to clear the screen. If errors occur, initscr() writes an appropriate error message to standard error and exits. The only functions that can be called before initscr() or newterm() are filter(), ripoffline(), slk_init(), use_env() and the functions whose prototypes are defined in <term.h>. Portable applications must not call initscr() twice.

The newterm() function can be called as many times as desired to attach a terminal device. The *type* argument points to a string specifying the terminal type, except that if *type* is a null pointer, the TERM environment variable is used. The *outfile* and *infile* arguments are file pointers for output to the terminal and input from the terminal, respectively. It is unspecified whether Curses modifies the buffering mode of these file pointers. The newterm() function should be called once for each terminal.

The initscr() function is equivalent to:

```
newterm(getenv("TERM"), stdout, stdin);
return stdscr;
```

If the current disposition for the signals SIGINT, SIGQUIT or SIGTSTP is SIGDFL, then initscr() may also install a handler for the signal, which may remain in effect for the life of the process or until the process changes the disposition of the signal.

The initscr() and newterm() functions initialize the cur_term external variable.

# initscr()

#### **Return Value**

Upon successful completion, initscr() returns a pointer to stdscr. Otherwise, it does not return.

Upon successful completion, newterm() returns a pointer to the specified terminal. Otherwise, it returns a null pointer.

#### **Errors**

No errors are defined.

## **Application Usage**

A program that outputs to more than one terminal should use newterm() for each terminal instead of initscr(). A program that needs an indication of error conditions, so it can continue to run in a line-oriented mode if the terminal cannot support a screen-oriented program, would also use this function.

Applications should perform any required handling of the SIGINT, SIGQUIT or SIGTSTP signals before calling initscr().

#### See Also

delscreen(), doupdate(), del_curterm(), filter(), slk_attroff(), use_env(), <curses.h>.

# innstr()

#### Name

innstr, instr, mvinnstr, mvinnstr, mvwinnstr, winnstr, winstr - input a multi-byte character string from a window

```
#include <curses.h>
int innstr(char *str, int n);
int instr(char *str);
int mvinnstr(int y, int x, char *str, int n);
int mvinstr(int y, int x, char *str);
int mvwinnstr(WINDOW *win, int y, int x, char *str, int n);
int mvwinstr(WINDOW *win, int y, int x, char *str);
int winnstr(WINDOW *win, char *str, int n);
int winnstr(WINDOW *win, char *str, int n);
int winstr(WINDOW *win, char *str);
```

These functions place a string of characters from the current or specified window into the array pointed to by *str*, starting at the current or specified position and ending at the end of the line.

The innstr(), mvinnstr() and winnstr() functions store at most n bytes in the string pointed to by str.

The innstr(), mvinnstr(), mvwinnstr() and winnstr() functions will only store the entire multi-byte sequence associated with a character. If the array is large enough to contain at least one character the array is filled with complete characters. If the array is not large enough to contain any complete characters, the function fails.

### **Return Value**

Upon successful completion, instr(), mvinstr(), mvwinstr() and winstr() return OK.

Upon successful completion, innstr(), mvinnstr(), mvwinnstr() and winnstr() return the number of characters actually read into the string. Otherwise, all these functions return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

Since multi-byte characters may be processed, there might not be a one-to-one correspondence between the number of column positions on the screen and the number of bytes returned.

These functions do not return rendition information.

Reading a line that overflows the array pointed to by *str* with instr(), mvinstr(), mvwinstr() or winstr() causes undefined results. The use of innstr(), mvinnstr(), mvwinnstr() or winnstr(), respectively, is recommended.

## See Also

<curses.h>.

# innwstr()

### Name

innwstr, inwstr, mvinnwstr, mvwinnwstr, mvwinwstr, winnwstr, winwstr - input a string of wide characters from a window

```
#include <curses.h>
int innwstr(wchar_t *wstr, int n);
int inwstr(wchar_t *wstr);
int mvinnwstr(int y, int x, wchar_t *wstr, int n);
int mvinwstr(int y, int x, wchar_t *wstr);
int mvwinnwstr(WINDOW *win, int y, int x, wchar_t *wstr, int n);
int mvwinwstr(WINDOW *win, int y, int x, wchar_t *wstr);
int winnwstr(WINDOW *win, wchar_t *wstr, int n);
int winwstr(WINDOW *win, wchar_t *wstr);
```

These functions place a string of wchar_t characters from the current or specified window into the array pointed to by *wstr* starting at the current or specified cursor position and ending at the end of the line.

These functions will only store the entire wide character sequence associated with a spacing complex character. If the array is large enough to contain at least one complete spacing complex character, the array is filled with complete characters. If the array is not large enough to contain any complete characters this is an error.

The innwstr(), mvwinnwstr() and winnwstr() functions store at most *n* characters in the array pointed to by *wstr*.

#### **Return Value**

Upon successful completion, inwstr(), mvinwstr(), mvwinwstr() and winwstr() return OK.

Upon successful completion, innwstr(), mvinnwstr(), mvwinnwstr() and winnwstr() return the number of characters actually read into the string. Otherwise, all these functions return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

Reading a line that overflows the array pointed to by *wstr* with inwstr(), mvinwstr(), mvwinwstr() or winwstr() causes undefined results. The use of innwstr(), mvinnwstr(), mvwinnwstr() or winnwstr(), respectively, is recommended.

These functions do not return rendition information.

#### See Also

<curses.h>.

# insch()

#### Name

insch, mvinsch, mvwinsch, winsch - insert a single-byte character and rendition into a window

# Synopsis

```
#include <curses.h>
int insch(chtype ch);
int mvinsch(int y, int x, chtype ch);
int mvwinsch(WINDOW *win, int y, int x, chtype ch);
int winsch(WINDOW *win, chtype ch);
```

# **Description**

These functions insert the character and rendition from *ch* into the current or specified window at the current or specified position.

These functions do not perform wrapping. These functions do not advance the cursor position. These functions perform special-character processing, with the exception that if a newline is inserted into the last line of a window and scrolling is not enabled, the behavior is unspecified.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

### See Also

ins_wch() <curses.h>.

# insdelln()

#### Name

insdelln, winsdelln - delete or insert lines into a window

## **Synopsis**

```
#include <curses.h>
int insdelln(int n);
int winsdelln(WINDOW *win, int n);
```

## **Description**

The insdelln() and winsdelln() functions perform the following actions:

- If *n* is positive, these functions insert *n* lines into the current or specified window before the current line. The *n* last lines are no longer displayed.
- If *n* is negative, these functions delete *n* lines from the current or specified window starting with the current line, and move the remaining lines toward the cursor. The last *n* lines are cleared.

The current cursor position remains the same.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

#### See Also

deleteln(), insertln(), <curses.h>.

# insertln()

### Name

insertln, winsertln - insert lines into a window

## **Synopsis**

```
#include <curses.h>
int insertln(void);
int winsertln(WINDOW *win);
```

## **Description**

The insertln() and winsertln() functions insert a blank line before the current line in the current or specified window. The bottom line is no longer displayed. The cursor position does not change.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

insdelln(), <curses.h>.

# insnstr()

### Name

insnstr, insstr, mvinsnstr, mvwinsnstr, mvwinsnstr, winsnstr, winsstr - insert a multi-byte character string into a window

# **Synopsis**

```
#include <curses.h>
int insnstr(const char *str, int n);
int insstr(const char *str);
int mvinsnstr(int y, int x, const char *str, int n);
int mvinsstr(int y, int x, const char *str);
int mvwinsnstr(WINDOW *win, int y, int x, const char *str, int n);
int mvwinsstr(WINDOW *win, int y, int x, const char *str);
int winsnstr(WINDOW *win, const char *str, int n);
int winsnstr(WINDOW *win, const char *str);
```

# **Description**

These functions insert a character string (as many characters as will fit on the line) before the current or specified position in the current or specified window.

These functions do not advance the cursor position. These functions perform special-character processing. The innstr() and innwstr() functions perform wrapping. The instr() and () inswstr functions do not perform wrapping.

The insnstr(), mvinsnstr(), mvwinsnstr() and winsnstr() functions insert at most n bytes. If n is less than 1, the entire string is inserted.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

## **Application Usage**

Since the string may contain multi-byte characters, there might not be a one-to-one correspondence between the number of column positions occupied by the characters and the number of bytes in the string.

#### See Also

<curses.h>

# ins_nwstr()

#### Name

ins_nwstr, ins_wstr, mvins_nwstr, mvwins_nwstr, mvwins_wstr, wins_nwstr, wins_wstr - insert a wide-character string into a window

## **Synopsis**

```
#include <curses.h>
int ins_nwstr(const wchar_t *wstr, int n);
int ins_wstr(const wchar_t *wstr);
int mvins_nwstr(int y, int x, const wchar_t *wstr, int n);
int mvins_wstr(int y, int x, const wchar_t *wstr);
int mvwins_nwstr(WINDOW *win, int y, int x, const wchar_t *wstr, int n);
int mvwins_wstr(WINDOW *win, int y, int x, const wchar_t *wstr);
int wins_nwstr(WINDOW *win, const wchar_t *wstr, int n);
int wins_wstr(WINDOW *win, const wchar_t *wstr);
```

## **Description**

These functions insert a wchar_t character string (as many wchar_t characters as will fit on the line) in the current or specified window immediately before the current or specified position.

Any non-spacing characters in the string are associated with the first spacing character in the string that precedes the non-spacing characters. If the first character in the string is a non-spacing character, these functions will fail.

These functions do not perform wrapping. These functions do not advance the cursor position. These functions perform special-character processing.

The ins_nwstr(), mvins_nwstr(), mvwins_nwstr() and wins_nwstr() functions insert at most *n* wchar_t characters. If *n* is less than 1, then the entire string is inserted.

#### Return Value

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Enhanced Curses**

### **Errors**

No errors are defined.

### See Also

<curses.h>.

# insstr()

#### Name

insstr - insert a multi-byte character string into the current window

## **Synopsis**

```
#include <curses.h>
int insstr(const char *str);
```

## **Description**

Refer to insnstr().

# instr()

#### Name

instr - input a multi-byte character string from the current window

# **Synopsis**

```
#include <curses.h>
int instr(char *str);
```

# **Description**

Refer to innstr().

# ins_wch()

### Name

ins_wch, mvins_wch, mvwins_wch, wins_wch - insert a complex character and rendition into a window

```
#include <curses.h>
int ins_wch(const cchar_t *wch);
int wins_wch(WINDOW *win, const cchar_t *wch);
int mvins_wch(int y, int x, const cchar_t *wch);
int mvwins_wch(WINDOW *win, int y, int x, const cchar_t *wch);
```

These functions insert the complex character *wch* with its rendition in the current or specified window at the current or specified cursor position.

These functions do not perform wrapping. These functions do not advance the cursor position. These functions perform special-character processing.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

For non-spacing characters, add_wch() can be used to add the non-spacing characters to a spacing complex character already in the window.

### See Also

```
add_wch(), <curses.h>.
```

# ins_wstr()

#### Name

ins_wstr - insert a wide-character string into the current window

# **Synopsis**

```
#include <curses.h>
int ins_wstr(const wchar_t *wstr);
```

## **Description**

Refer to ins_nwstr().

# intrflush()

### Name

intrflush - enable or disable flush on interrupt

# **Synopsis**

```
#include <curses.h>
int intrflush(WINDOW *win, bool bf);
```

# **Description**

The intrflush() function specifies whether pressing an interrupt key (interrupt, suspend or quit) will flush the input buffer associated with the current screen. If *bf* is a boolean that specifies whether pressing an

#### **Enhanced Curses**

interrupt key (interrupt, suspend or quit) will flush the output buffer associated with the current screen. The default for the option is inherited from the display driver settings. The *win* argument is ignored.

#### **Return Value**

Upon successful completion, intrflush() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

The same effect is achieved outside Curses using the NOFLSH local mode flag specified in the XBD specification (General Terminal Interface).

#### See Also

<curses.h>.

# in_wch()

#### Name

in_wch, mvin_wch, mvwin_wch, win_wch - input a complex character and rendition from a window

## **Synopsis**

```
#include <curses.h>
int in_wch(cchar_t *wcval);
int mvin_wch(int y, int x, cchar_t *wcval);
int mvwin_wch(WINDOW *win, int y, int x, cchar_t *wcval);
int win_wch(WINDOW *win, cchar_t *wcval);
```

## **Description**

These functions extract the complex character and rendition from the current or specified position in the current or specified window into the object pointed to by *wcval*.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

<curses.h>.

# in_wchnstr()

#### Name

in_wchnstr, in_wchstr, mvin_wchnstr, mvin_wchstr, mvwin_wchnstr, mvwin_wchstr, win_wchstr, win_wchstr, input an array of complex characters and renditions from a window

## **Synopsis**

```
#include <curses.h>
int in_wchnstr(cchar_t *wchstr, int n);
int in_wchstr(cchar_t *wchstr);
int mvin_wchnstr(int y, int x, cchar_t *wchstr, int n);
int mvin_wchstr(int y, int x, cchar_t *wchstr);
int mvwin_wchstr(WINDOW *win, int y, int x, cchar_t *wchstr, int n);
int mvwin_wchstr(WINDOW *win, int y, int x, cchar_t *wchstr);
int win_wchnstr(WINDOW *win, cchar_t *wchstr, int n);
int win_wchstr(WINDOW *win, cchar_t *wchstr);
```

## **Description**

These functions extract characters from the current or specified window, starting at the current or specified position and ending at the end of the line, and place them in the array pointed to by *wchstr*.

The in_wchnstr(), mvin_wchnstr(), mvwin_wchnstr() and win_wchnstr() fill the array with at most *n* cchar_t elements.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

Reading a line that overflows the array pointed to by *wchstr* with in_wchstr(), mvin_wchstr(), mvwin_wchstr() or win_wchstr() causes undefined results. The use of in_wchnstr(), mvin_wchnstr(), mvwin_wchnstr(), respectively, is recommended.

#### See Also

in_wch(), <curses.h>.

# inwstr()

#### Name

inwstr - input a string of wide characters from the current window

## **Synopsis**

```
#include <curses.h>
int inwstr(wchar_t *wstr);
```

# **Description**

Refer to innwstr().

# isendwin()

### Name

isendwin - determine whether a screen has been refreshed

## **Synopsis**

```
#include <curses.h>
bool isendwin(void);
```

## **Description**

The isendwin() function indicates whether the screen has been refreshed since the last call to endwin().

### **Return Value**

The isendwin() function returns TRUE if endwin() has been called without any subsequent refresh. Otherwise, it returns FALSE.

### **Errors**

No errors are defined.

### See Also

endwin(), <curses.h>.

# is_linetouched()

#### Name

is_linetouched, is_wintouched, touchline, touchwin, untouchwin, wtouchln - window refresh control functions

```
#include <curses.h>
bool is_linetouched(WINDOW *win, int line);
bool is_wintouched(WINDOW *win);
int touchline(WINDOW *win, int start, int count);
int touchwin(WINDOW *win);
int untouchwin(WINDOW *win);
```

```
int wtouchln(WINDOW *win, int y, int n, int changed);
```

The touchwin() function touches the specified window (that is, marks it as having changed more recently than the last refresh operation). The touchline() function only touches *count* lines, beginning with line *start*.

The untouchwin() function marks all lines in the window as unchanged since the last refresh operation.

Calling wtouchln(), if changed is 1, touches n lines in the specified window, starting at line y. If changed is 0, wtouchln() marks such lines as unchanged since the last refresh operation.

The is_wintouched() function determines whether the specified window is touched. The is_linetouched() function determines whether line *line* of the specified window is touched.

### **Return Value**

The is_linetouched() and is_wintouched() functions return TRUE if any of the specified lines, or the specified window, respectively, has been touched since the last refresh operation. Otherwise, they return FALSE.

Upon successful completion, the other functions return OK. Otherwise, they return ERR. Exceptions to this are noted in the preceding function descriptions.

### **Errors**

No errors are defined.

## **Application Usage**

Calling touchwin() or touchline() is sometimes necessary when using overlapping windows, since a change to one window affects the other window, but the records of which lines have been changed in the other window do not reflect the change.

#### See Also

doupdate(), <curses.h>.

# keyname()

#### Name

keyname, key_name - get name of key

# **Synopsis**

```
#include <curses.h>
char *keyname(int c);
char *key_name(wchar_t c);
```

# **Description**

The keyname() and key_name() functions generate a character string whose value describes the key c. The c argument of keyname() can be an 8-bit character or a key code. The c argument of key_name() must be a wide character.

The string has a format according to the first applicable row in the following table:

Input	Format of Returned String
Visible character	The same character
Control character	^X
Meta-character (keyname() only)	M-X
Key value defined in <b><curses.h></curses.h></b> (keyname() only)	KEY_name
None of the above	UNKNOWN KEY

The meta-character notation shown above is used only if meta-characters are enabled.

### **Return Value**

Upon successful completion, keyname() returns a pointer to a string as described above. Otherwise, it returns a null pointer.

#### **Errors**

No errors are defined.

## **Application Usage**

The return value of keyname() and key_name() may point to a static area which is overwritten by a subsequent call to either of these functions.

Applications normally process meta-characters without storing them into a window. If an application stores meta-characters in a window and tries to retrieve them as wide characters, keyname() cannot detect meta-characters, since wide characters do not support meta-characters.

### See Also

*meta()*, **<curses.h>**.

# keypad()

### Name

keypad - enable/disable abbreviation of function keys

# **Synopsis**

```
#include <curses.h>
int keypad(WINDOW *win, bool bf);
```

## **Description**

The keypad() function controls keypad translation. If bf is TRUE, keypad translation is turned on. If bf is FALSE, keypad translation is turned off. The initial state is FALSE.

This function affects the behavior of any function that provides keyboard input.

If the terminal in use requires a command to enable it to transmit distinctive codes when a function key is pressed, then after keypad translation is first enabled, the implementation transmits this command to the terminal before an affected input function tries to read any characters from that terminal.

### **Return Value**

Upon successful completion, keypad() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

### See Also

<curses.h>.

# killchar()

#### Name

killchar, killwchar - terminal environment query functions

## **Synopsis**

```
#include <curses.h>
char killchar(void);
int killwchar(wchar_t *ch);
```

# **Description**

Refer to erasechar().

# leaveok()

### Name

leaveok - control cursor position resulting from refresh operations

# **Synopsis**

```
#include <curses.h>
int leaveok(WINDOW *win, bool bf);
```

# **Description**

Refer to clearok().

### **LINES**

#### Name

LINES - number of lines on terminal screen

```
#include <curses.h>
extern int LINES;
```

The external variable LINES indicates the number of lines on the terminal screen.

### See Also

initscr(), <curses.h>.

# longname()

### Name

longname - get verbose description of current terminal

## **Synopsis**

```
#include <curses.h>
char *longname(void);
```

## **Description**

The longname() function generates a verbose description of the current terminal. The maximum length of a verbose description is 128 bytes. It is defined only after the call to initscr() or newterm().

#### **Return Value**

Upon successful completion, longname() returns a pointer to the description specified above. Otherwise, it returns a null pointer on error.

### **Errors**

No errors are defined.

# **Application Usage**

The return value of longname() may point to a static area which is overwritten by a subsequent call to newterm().

### See Also

initscr(), <curses.h>.

# meta()

#### Name

meta - enable/disable meta-keys

```
#include <curses.h>
int meta(WINDOW *win, bool bf);
```

Initially, whether the terminal returns 7 or 8 significant bits on input depends on the control mode of the display driver (see the XBD specification, General Terminal Interface). To force 8 bits to be returned, invoke meta(win, TRUE). To force 7 bits to be returned, invoke meta(win, FALSE). The win argument is always ignored. If the terminfo capabilities smm (meta_on) and rmm (meta_off) are defined for the terminal, smm is sent to the terminal when meta(win, TRUE) is called and rmm is sent when meta(win, FALSE) is called.

#### **Return Value**

Upon successful completion, meta() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

The same effect is achieved outside Curses using the CS7 or CS8 control mode flag specified in the XBD specification (General Terminal Interface).

The meta() function was designed for use with terminals with 7-bit character sets and a "meta" key that could be used to set the eighth bit.

### See Also

```
getch(), <curses.h>.
```

# move()

### Name

move, wmove - window cursor location functions

# **Synopsis**

```
#include <curses.h>
int move(int y, int x);
int wmove(WINDOW *win, int y, int x);
```

# Description

The move() and wmove() functions move the cursor associated with the current or specified window to (y, x) relative to the window's origin. This function does not move the terminal's cursor until the next refresh operation.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### Errors

No errors are defined.

#### See Also

```
doupdate(), <curses.h>.
```

#### mv

#### Name

mv - pointer page for functions with mv prefix

## **Description**

Most cases in which a Curses function has the mv prefix  1  indicate that the function takes y and x arguments and moves the cursor to that address as though move() were first called. (The corresponding functions without the mv prefix operate at the cursor position.)

The mv prefix is combined with a w prefix to produce Curses functions beginning with mvw.

The mv and mvw functions are discussed together with the corresponding functions that do not have these prefixes. They are found on the following entries:

Function		Refer to
mvaddch()	mvwaddch()	addch()
mvaddchnstr()	mvwaddchnstr()	addchstr()
mvaddchstr()	mvwaddchstr()	addchstr()
mvaddnstr()	mvwaddnstr()	addnstr()
mvaddstr()	mvwaddstr()	addnstr()
mvaddnwstr()	mvwaddnwstr()	addnwstr()
mvaddwstr()	mvwaddwstr()	addnwstr()
mvadd_wch()	mvwadd_wch()	add_wch()
mvadd_wchnstr()	mvwadd_wchnstr()	add_wchnstr()
mvadd_wchstr()	mvwadd_wchstr()	add_wchnstr()
mvchgat()	mvwchgat()	chgat()
mvdelch()	mvwdelch()	delch()
mvgetch()	mvwgetch()	getch()
mvgetnstr()	mvwgetnstr()	getnstr()
mvgetstr()	mvwgetstr()	getnstr()
mvgetn_wstr()	mvwgetn_wstr()	getn_wstr()
mvget_wch()	mvwget_wch()	get_wch()
mvget_wstr()	mvwget_wstr()	getn_wstr()
mvhline()	mvwhline()	hline()
mvhline_set()	mvwhline_set()	hline_set()
mvinch()	mvwinch()	inch()

¹ The mvcur(), mvderwin() and mvwin() functions are exceptions to this rule, in that mv is not a prefix with the usual meaning and there are no corresponding functions without the mv prefix. These functions have entries under their own names.

In the mvprintw() and mvscanw() functions, mv is a prefix with the usual meaning, but the functions have entries under their own names because the mv function is the first function in the family of functions in alphabetical order.

Function		Refer to
mvinchnstr()	mvwinchnstr()	inchnstr()
mvinchstr()	mvwinchstr()	inchnstr()
mvinnstr()	mvwinnstr()	innstr()
mvinnwstr()	mvwinnwstr()	innwstr()
mvinsch()	mvwinsch()	insch()
mvinsnstr()	mvwinsnstr()	insnstr()
mvinsstr()	mvwinsstr()	insnstr()
mvinstr()	mvwinstr()	innstr()
mvins_nwstr()	mvwins_nwstr()	ins_nwstr()
mvins_wch()	mvwins_wch()	ins_wch()
mvins_wstr()	mvwins_wstr()	ins_nwstr()
mvinwstr()	mvwinwstr()	innwstr()
mvin_wch()	mvwin_wch()	in_wch()
mvin_wchnstr()	mvwin_wchnstr()	in_wchnstr()
mvin_wchstr()	mvwin_wchstr()	in_wchnstr()
mvprintw()	mvwprintw()	amvprintw()
mvscanw()	mvwscanw()	mvscanw()
mvvline()	mvwvline()	hline()
mvvline_set()	mvwvline_set()	hline_set()

### See Also

W.

# mvcur()

### Name

mvcur - output cursor movement commands to the terminal

# **Synopsis**

```
#include <curses.h>
int mvcur(int oldrow, int oldcol, int newrow, int newcol);
```

# **Description**

The mvcur() function outputs one or more commands to the terminal that move the terminal's cursor to (newrow, newcol), an absolute position on the terminal screen. The (oldrow, oldcol) arguments specify the former cursor position. Specifying the former position is necessary on terminals that do not provide coordinate-based movement commands. On terminals that provide these commands, Curses may select a more efficient way to move the cursor based on the former position. If (newrow, newcol) is not a valid address for the terminal in use, mvcur() fails. If (oldrow, oldcol) is the same as (newrow, newcol), then mvcur() succeeds without taking any action. If mvcur() outputs a cursor movement command, it updates its information concerning the location of the cursor on the terminal.

#### **Return Value**

Upon successful completion, mvcur() returns OK.

Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

After use of mvcur(), the model Curses maintains of the state of the terminal might not match the actual state of the terminal. The application should touch and refresh the window before resuming conventional use of Curses.

### See Also

doupdate(), is_linetouched(), <curses.h>.

## mvderwin()

#### Name

mvderwin - define window coordinate transformation

### **Synopsis**

```
#include <curses.h>
int mvderwin(WINDOW *win, int par_y, int par_x);
```

## **Description**

The mvderwin() function specifies a mapping of characters. The function identifies a mapped area of the parent of the specified window, whose size is the same as the size of the specified window and whose origin is at (par_y, par_x) of the parent window.

- During any refresh of the specified window, the characters displayed in that window's display area of the terminal are taken from the mapped area.
- Any references to characters in the specified window obtain or modify characters in the mapped area.

That is, mvderwin() defines a coordinate transformation from each position in the mapped area to a corresponding position (same y, x offset from the origin) in the specified window.

#### **Return Value**

Upon successful completion, mvderwin() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

#### See Also

derwin(), doupdate(), dupwin(), <curses.h>.

# mvprintw()

#### Name

mvprintw, mvwprintw, printw, wprintw - print formatted output in window

## **Synopsis**

```
#include <curses.h>
int mvprintw(int y, int x, char *fmt, ...);
int mvwprintw(WINDOW *win, int y, int x, char *fmt, ...);
int printw(char *fmt, ...);
int wprintw(WINDOW *win, char *fmt, ...);
```

## **Description**

The mvprintw(), mvwprintw(), printw() and wprintw() functions are analogous to printf(). The effect of these functions is as though sprintf() were used to format the string, and then waddstr() were used to add that multi-byte string to the current or specified window at the current or specified cursor position.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

addnstr(), fprintf(), <curses.h>

# mvscanw()

#### Name

mvscanw, mvwscanw, scanw, wscanw - convert formatted input from a window

### **Synopsis**

```
#include <curses.h>
int mvscanw(int y, int x, char *fmt, ...);
int mvwscanw(WINDOW *win, int y, int x, char *fmt, ...);
int scanw(char *fmt, ...);
int wscanw(WINDOW *win, char *fmt, ...);
```

### **Description**

These functions are similar to scanf(). Their effect is as though mvwgetstr() were called to get a multi-byte character string from the current or specified window at the current or specified cursor position, and then sscanf() were used to interpret and convert that string.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

### **Errors**

No errors are defined.

### See Also

getnstr(), printw(), fscanf(), wcstombs(), <curses.h>.

# mvwin()

### Name

mvwin - move window

## **Synopsis**

```
#include <curses.h>
int mvwin(WINDOW *win, int y, int x);
```

## **Description**

The mvwin() function moves the specified window so that its origin is at position (y, x). If the move would cause any portion of the window to extend past any edge of the screen, the function fails and the window is not moved.

### **Return Value**

Upon successful completion, mvwin() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

The application should not move subwindows by calling mvwin().

#### See Also

derwin(), doupdate(), is_linetouched(), <curses.h>.

# napms()

### Name

napms - suspend the calling process

# **Synopsis**

```
#include <curses.h>
int napms(int ms);
```

### **Description**

The napms() function takes at least ms milliseconds to return.

### **Return Value**

The napms() function returns OK.

#### **Errors**

No errors are defined.

## **Application Usage**

A more reliable method of achieving a timed delay is the usleep() function.

#### See Also

delay_output(), usleep() <curses.h>.

# newpad()

#### Name

newpad, pnoutrefresh, prefresh, subpad - pad management functions

## **Synopsis**

```
#include <curses.h>
WINDOW *newpad(int nlines, int ncols);
int pnoutrefresh(WINDOW *pad, int pminrow, int pmincol, int sminrow, int smincol, int smaxrow, int smaxcol);
int prefresh(WINDOW *pad, int pminrow, int pmincol, int sminrow, int sminrow, int smincol, int smaxrow, int smaxcol);
WINDOW *subpad(WINDOW *orig, int nlines, int ncols, int begin_y, int begin_x);
```

## **Description**

The newpad() function creates a specialized WINDOW data structure representing a pad with *nlines* lines and *ncols* columns. A pad is like a window, except that it is not necessarily associated with a viewable part of the screen. Automatic refreshes of pads do not occur.

The subpad() function creates a subwindow within a pad with *nlines* lines and *ncols* columns. Unlike subwin(), which uses screen coordinates, the window is at position (*begin_y*, *begin_x*) on the pad. The window is made in the middle of the window *orig*, so that changes made to one window affect both windows.

The prefresh() and pnoutrefresh() functions are analogous to wrefresh() and wnoutrefresh() except that they relate to pads instead of windows. The additional arguments indicate what part of the pad and screen are involved. The *pminrow* and *pmincol* arguments specify the origin of the rectangle to be displayed in the pad. The *sminrow*, *smincol*, *smaxrow* and *smaxcol* arguments specify the edges of the rectangle to be displayed on the screen. The lower right-hand corner of the rectangle to be displayed in the pad is calculated from the screen coordinates, since the rectangles must be the same size. Both rectangles must be entirely contained within their respective structures. Negative values of *pminrow*, *pmincol*, *sminrow* or *smincol* are treated as if they were zero.

### **Return Value**

Upon successful completion, the newpad() and subpad() functions return a pointer to the pad data structure. Otherwise, they return a null pointer.

Upon successful completion, pnoutrefresh() and prefresh() return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

To refresh a pad, call prefresh() or pnoutrefresh(), not wrefresh(). When porting code to use pads from WINDOWS, remember that these functions require additional arguments to specify the part of the pad to be displayed and the location on the screen to be used for the display.

Although a subwindow and its parent pad may share memory representing characters in the pad, they need not share status information about what has changed in the pad. Therefore, after modifying a subwindow within a pad, it may be necessary to call touchwin() or touchline() on the pad before calling prefresh().

#### See Also

derwin(), doupdate(), is_linetouched(), <curses.h>.

# newterm()

#### Name

newterm - screen initialization function

# **Synopsis**

```
#include <curses.h>
SCREEN *newterm(char *type, FILE *outfile, FILE *infile);
```

# **Description**

Refer to initscr().

# newwin()

#### Name

newwin - create a new window

# **Synopsis**

```
#include <curses.h>
WINDOW *newwin(int nlines, int ncols, int begin_y, int begin_x);
```

# **Description**

Refer to derwin().

## nl()

#### Name

nl, nonl - enable/disable newline translation

## **Synopsis**

```
#include <curses.h>
int nl(void);
int nonl(void);
```

### **Description**

The nl() function enables a mode in which carriage return is translated to newline on input. The nonl() function disables the above translation. Initially, the above translation is enabled.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

The default translation adapts the terminal to environments in which newline is the line termination character. However, by disabling the translation with nonl(), the application can sense the pressing of the carriage return key.

### See Also

<curses.h>.

#### no

#### Name

no - pointer page for functions with no prefix

## **Description**

The no prefix indicates that a Curses function disables a mode. (The corresponding functions without the no prefix enable the same mode.)

The no functions are discussed together with the corresponding functions that do not have these prefixes. ² They are found on the following entries:

Function	Refer to
nocbreak()	cbreak()

² The nodelay() function has an entry under its own name because there is no corresponding delay() function.

The noqiflush() and notimeout() functions have an entry under their own names because they precede the corresponding function without the no prefix in alphabetical order.

Function	Refer to
noecho()	echo()
nonl()	nl()
noraw()	cbreak()

# nodelay()

### Name

nodelay - enable or disable block during read

## **Synopsis**

```
#include <curses.h>
int nodelay(WINDOW *win, bool bf);
```

## **Description**

The nodelay() function specifies whether Delay Mode or No Delay Mode is in effect for the screen associated with the specified window. If *bf* is TRUE, this screen is set to No Delay Mode. If *bf* is FALSE, this screen is set to Delay Mode. The initial state is FALSE.

#### **Return Value**

Upon successful completion, nodelay() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

### See Also

getch(), halfdelay(), <curses.h>.

# noqiflush()

#### Name

noqiflush, qiflush - enable/disable queue flushing

# **Synopsis**

```
#include <curses.h>
void noqiflush(void);
void qiflush(void);
```

# Description

The qiflush() function causes all output in the display driver queue to be flushed whenever an interrupt key (interrupt, suspend, or quit) is pressed. The noqiflush() causes no such flushing to occur. The default for the option is inherited from the display driver settings.

#### **Return Value**

These functions do not return a value.

### **Errors**

No errors are defined.

## **Application Usage**

Calling qiflush() provides faster response to interrupts, but causes Curses to have the wrong idea of what is on the screen. The same effect is achieved outside Curses using the NOFLSH local mode flag specified in the XBD specification (General Terminal Interface).

#### See Also

intrflush(), <curses.h>.

# notimeout()

### Name

notimeout, timeout, wtimeout - control blocking on input

## **Synopsis**

```
#include <curses.h>
int notimeout(WINDOW *win, bool bf);
void timeout(int delay);
void wtimeout(WINDOW *win, int delay);
```

### **Description**

The notimeout() function specifies whether Timeout Mode or No Timeout Mode is in effect for the screen associated with the specified window. If *bf* is TRUE, this screen is set to No Timeout Mode. If *bf* is FALSE, this screen is set to Timeout Mode. The initial state is FALSE.

The timeout() and wtimeout() functions set blocking or non-blocking read for the current or specified window based on the value of delay:

delay < 0	One or more blocking reads (indefinite waits for input) are used.
delay = 0	One or more non-blocking reads are used. Any Curses input function will fail if every character of the requested string is not immediately available.
delay > 0	Any Curses input function blocks for delay milliseconds and fails if there is still no input.

### **Return Value**

Upon successful completion, the notimeout() function returns OK. Otherwise, it returns ERR.

The timeout() and wtimeout() functions do not return a value.

#### **Errors**

No errors are defined.

### See Also

getch(), halfdelay(), nodelay(), <curses.h>.

# overlay()

#### Name

overlay, overwrite - copy overlapped windows

## **Synopsis**

```
#include <curses.h>
int overlay(const WINDOW *srcwin, WINDOW *dstwin);
int overwrite(const WINDOW *srcwin, WINDOW *dstwin);
```

## **Description**

The overlay() and overwrite() functions overlay *srcwin* on top of *dstwin*. The *scrwin* and *dstwin* arguments need not be the same size; only text where the two windows overlap is copied.

The overwrite() function copies characters as though a sequence of win_wch() and wadd_wch() were performed with the destination window's attributes and background attributes cleared.

The overlay() function does the same thing, except that, whenever a character to be copied is the background character of the source window, overlay() does not copy the character but merely moves the destination cursor the width of the source background character.

If any portion of the overlaying window border is not the first column of a multi-column character then all the column positions will be replaced with the background character and rendition before the overlay is done. If the default background character is a multi-column character when this occurs, then these functions fail.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

#### See Also

copywin(), <curses.h>.

# pair_content()

#### Name

pair_content, PAIR_NUMBER - get information on a color pair

# Synopsis

```
#include <curses.h>
int pair_content(short pair, short *f, short *b);
int PAIR_NUMBER(int value);
```

### **Description**

Refer to can_change_color().

# pechochar()

#### Name

pechochar, pecho_wchar - write a character and rendition and immediately refresh the pad

## **Synopsis**

```
#include <curses.h>
int pechochar(WINDOW *win, chtype ch);
int pecho_wchar(WINDOW *pad, const cchar_t *wch);
```

## **Description**

The pechochar() and pecho_wchar() functions output one character to a *pad* and immediately refresh the *pad*. They are equivalent to a call to waddch() or wadd_wch(), respectively, followed by a call to prefresh(). The last location of the *pad* on the screen is reused for the arguments to prefresh().

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

The pechochar() function is only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

#### See Also

```
echochar(), echo_char(), newpad(), <curses.h>.
```

# pnoutrefresh()

#### Name

pnoutrefresh, prefresh - refresh pads

# **Synopsis**

## **Description**

Refer to newpad().

# printw()

#### Name

printw - print formatted output in the current window

## **Synopsis**

```
#include <curses.h>
int printw(char *fmt, ...);
```

## **Description**

Refer to mvprintw().

# putp()

#### Name

putp, tputs - output commands to the terminal

## **Synopsis**

```
#include <term.h>
int putp(const char *str);
int tputs(const char *str, int affcnt, int (*putfunc)(int));
```

# Description

These functions output commands contained in the terminfo database to the terminal.

The putp() function is equivalent to tputs(str, 1, putchar). The output of putp() always goes to stdout, not to the fildes specified in setupterm().

The tputs() function outputs *str* to the terminal. The *str* argument must be a terminfo string variable or the return value from tgetstr(), tgoto(), tigetstr() or tparm(). The *affcnt* argument is the number of lines affected, or 1 if not applicable. If the terminfo database indicates that the terminal in use requires padding after any command in the generated string, tputs() inserts pad characters into the string that is sent to the terminal, at positions indicated by the terminfo database. The tputs() function outputs each character of the generated string by calling the user-supplied function *putfunc* (see below).

The user-supplied function putfunc (specified as an argument to tputs()) is either putchar() or some other function with the same prototype. The tputs() function ignores the return value of *putfunc*.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### **Application Usage**

After use of any of these functions, the model Curses maintains of the state of the terminal might not match the actual state of the terminal. The application should touch and refresh the window before resuming conventional use of Curses.

Use of these functions requires that the application contain so much information about a particular class of terminal that it defeats the purpose of using Curses.

On some terminals, a command to change rendition conceptually occupies space in the screen buffer (with or without width). Thus, a command to set the terminal to a new rendition would change the rendition of some characters already displayed.

### See Also

doupdate(), is_linetouched(), putchar(), tgetent(), tigetflag(), <term.h>.

# putwin()

#### Name

putwin - dump window to a file

# **Synopsis**

```
#include <curses.h>
int putwin(WINDOW *win, FILE *filep);
```

## **Description**

Refer to getwin().

# qiflush()

#### Name

qiflush - enable queue flushing

# Synopsis

```
#include <curses.h>
void qiflush(void);
```

## Description

Refer to nogiflush().

# raw()

#### Name

raw - set Raw Mode

#### **Enhanced Curses**

### **Synopsis**

```
#include <curses.h>
int raw(void);
```

## **Description**

Refer to cbreak().

# redrawwin()

### Name

redrawwin, wredrawln - line update status functions

## **Synopsis**

```
#include <curses.h>
int redrawwin(WINDOW *win);
int wredrawln(WINDOW *win, int beg_line, int num_lines);
```

# **Description**

The redrawwin() and wredrawln() functions inform the implementation that some or all of the information physically displayed for the specified window may have been corrupted. The redrawwin() function marks the entire window; wredrawln() marks only *num_lines* lines starting at line number *beg_line*. The functions prevent the next refresh operation on that window from performing any optimization based on assumptions about what is physically displayed there.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise they return ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

The redrawwin() and wredrawln() functions could be used in a text editor to implement a command that redraws some or all of the screen.

#### See Also

clearok(), doupdate(), <curses.h>.

# refresh()

#### Name

refresh - refresh current window

### **Synopsis**

```
#include <curses.h>
int refresh(void);
```

## **Description**

Refer to doupdate().

# reset_prog_mode()

### Name

reset_prog_mode, reset_shell_mode - restore program or shell terminal modes

## **Synopsis**

```
#include <curses.h>
int reset_prog_mode(void);
int reset_shell_mode(void);
```

# **Description**

Refer to def_prog_mode().

# resetty()

#### Name

resetty, savetty - save/restore terminal mode

# **Synopsis**

```
#include <curses.h>
int resetty(void);
int savetty(void);
```

# **Description**

The resetty() function restores the program mode as of the most recent call to savetty().

The savetty() function saves the state that would be put in place by a call to reset_prog_mode().

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

def_prog_mode(), <curses.h>.

# restartterm()

#### Name

restartterm - change terminal type

## **Synopsis**

```
#include <term.h>
int restartterm(char *term, int fildes, int *errret);
```

## **Description**

Refer to del_curterm().

# ripoffline()

#### Name

ripoffline - reserve a line for a dedicated purpose

## **Synopsis**

```
#include <curses.h>
int ripoffline(int line, int (*init)(WINDOW *win, int columns));
```

# **Description**

The ripoffline() function reserves a screen line for use by the application.

Any call to ripoffline() must precede the call to initscr() or newterm(). If *line* is positive, one line is removed from the beginning of stdscr; if *line* is negative, one line is removed from the end. Removal occurs during the subsequent call to initscr() or newterm(). When the subsequent call is made, the function pointed to by *init* is called with two arguments: a WINDOW pointer to the one-line window that has been allocated and an integer with the number of columns in the window. The initialization function cannot use the LINES and COLS external variables and cannot call wrefresh() or doupdate(), but may call wnoutrefresh().

Up to five lines can be ripped off. Calls to ripoffline() above this limit have no effect but report success.

### **Return Value**

The ripoffline() function returns OK.

#### **Errors**

No errors are defined.

# **Application Usage**

Calling slk_init() reduces the size of the screen by one line if initscr() eventually uses a line from stdscr to emulate the soft labels. If slk_init() rips off a line, it thereby reduces by one the number of lines an application can reserve by subsequent calls to ripoffline(). Thus, portable applications that use soft label functions should not call ripoffline() more than four times.

When initscr() or newterm() calls the initialization function pointed to by init, the implementation may pass NULL for the WINDOW pointer argument win. This indicates inability to allocate a one-line window

for the line that the call to ripoffline() ripped off. Portable applications should verify that win is not NULL before performing any operation on the window it represents.

#### See Also

doupdate(), initscr(), slk_attroff(), <curses.h>.

# savetty()

### Name

savetty - save terminal mode

# **Synopsis**

```
#include <curses.h>
int savetty(void);
```

# **Description**

Refer to resetty().

# scanw()

#### Name

scanw - convert formatted input from the current window

# **Synopsis**

```
#include <curses.h>
int scanw(char *fmt, ...);
```

# **Description**

Refer to mvscanw().

# scr_dump()

### Name

scr_dump, scr_init, scr_restore, scr_set - screen file input/output functions

# **Synopsis**

```
#include <curses.h>
int scr_dump(const char *filename);
int scr_init(const char *filename);
int scr_restore(const char *filename);
int scr_set(const char *filename);
```

### **Description**

The scr_dump() function writes the current contents of the virtual screen to the file named by *filename* in an unspecified format.

The scr_restore() function sets the virtual screen to the contents of the file named by *filename*, which must have been written using scr_dump(). The next refresh operation restores the screen to the way it looked in the dump file.

The scr_init() function reads the contents of the file named by *filename* and uses them to initialize the Curses data structures to what the terminal currently has on its screen. The next refresh operation bases any updates on this information, unless either of the following conditions is true:

- The terminal has been written to since the virtual screen was dumped to filename
- The terminfo capabilities *rmcup* and *nrrmc* are defined for the current terminal.

The scr_set() function is a combination of scr_restore() and scr_init(). It tells the program that the information in the file named by *filename* is what is currently on the screen, and also what the program wants on the screen. This can be thought of as a screen inheritance function.

#### **Return Value**

On successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### **Application Usage**

The scr_init() function is called after initscr() or a system() call to share the screen with another process that has done a scr_dump() after its endwin() call.

To read a window from a file, call getwin(); to write a window to a file, call putwin().

#### See Also

delscreen(), doupdate(), endwin(), getwin(), open(), read(), write(), <curses.h>

# scrl()

#### Name

scrl, scroll, wscrl - scroll a Curses window

## **Synopsis**

```
#include <curses.h>
int scrl(int n);
int scroll(WINDOW *win);
int wscrl(WINDOW *win, int n);
```

## Description

The scroll() function scrolls win one line in the direction of the first line.

The scrl() and wscrl() functions scroll the current or specified window. If n is positive, the window scrolls n lines toward the first line. Otherwise, the window scrolls -n lines toward the last line.

These functions do not change the cursor position. If scrolling is disabled for the current or specified window, these functions have no effect.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

<curses.h>.

# scrollok()

#### Name

scrollok - enable or disable scrolling on a window

## **Synopsis**

```
#include <curses.h>
int scrollok(WINDOW *win, bool bf);
```

### Description

Refer to clearok().

# setcchar()

#### Name

setcchar - set cchar_t from a wide character string and rendition

# **Synopsis**

# Description

The setcchar() function initializes the object pointed to by *wcval* according to the character attributes in *attrs*, the color pair in *color_pair* and the wide character string pointed to by *wch*.

The *opts* argument is reserved for definition in a future edition of this document. Currently, the application must provide a null pointer as *opts*.

#### **Return Value**

Upon successful completion, setcchar() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

### See Also

attroff(), can_change_color(), getcchar(), <curses.h>.

# set_curterm()

#### Name

set_curterm - set current terminal

## **Synopsis**

```
#include <term.h>
TERMINAL *set_curterm(TERMINAL *nterm);
```

# **Description**

Refer to del_curterm().

# setscrreg()

### Name

setscrreg, wsetscrreg - define software scrolling region

# **Synopsis**

```
#include <curses.h>
int setscrreg(int top, int bot);
int wsetscrreg(WINDOW *win, int top, int bot);
```

# **Description**

Refer to clearok().

# set_term()

### Name

set_term - switch between screens

## **Synopsis**

```
#include <curses.h>
SCREEN *set_term(SCREEN *new);
```

## **Description**

The set_term() function switches between different screens. The *new* argument specifies the new current screen.

### **Return Value**

Upon successful completion, set_term() returns a pointer to the previous screen. Otherwise, it returns a null pointer.

#### **Errors**

No errors are defined.

# **Application Usage**

This is the only function that manipulates SCREEN pointers; all other functions affect only the current screen.

#### See Also

initscr(), <curses.h>.

# setupterm()

### Name

setupterm - access the terminfo database

## **Synopsis**

```
#include <term.h>
int setupterm(char *term, int fildes, int *errret);
```

# **Description**

Refer to del curterm().

# slk_attroff()

#### Name

slk_attroff, slk_attr_off, slk_attr_on, slk_attrset, slk_attr_set, slk_clear, slk_color, slk_init, slk_label, slk_noutrefresh, slk_refresh, slk_restore, slk_set, slk_touch, slk_wset - soft label functions

## **Synopsis**

```
#include <curses.h>
int slk_attroff(const chtype attrs);
int slk_attr_off(const attr_t attrs, void *opts);
int slk_attron(const chtype attrs);
int slk_attr_on(const attr_t attrs, void *opts);
int slk_attrset(const chtype attrs);
int slk_attr_set(const attr_t attrs, short color_pair_number, void *opts);
int slk_clear(void);
int slk_color(short color_pair_number);
int slk_init(int fmt);
```

```
char *slk_label(int labnum);
int slk_noutrefresh(void);
int slk_refresh(void);
int slk_restore(void);
int slk_set(int labnum, const char *label, int justify);
int slk_touch(void);
int slk_wset(int labnum, const wchar_t *label, int justify);
```

### **Description**

The Curses interface manipulates the set of soft function-key labels that exist on many terminals. For those terminals that do not have soft labels, Curses takes over the bottom line of stdscr, reducing the size of stdscr and the value of the LINES external variable. There can be up to eight labels of up to eight display columns each.

To use soft labels, slk_init() must be called before initscr(), newterm() or ripoffline() is called. If initscr() eventually uses a line from stdscr to emulate the soft labels, then *fmt* determines how the labels are arranged on the screen. Setting *fmt* to 0 indicates a 3-2-3 arrangement of the labels; 1 indicates a 4-4 arrangement. Other values for *fmt* are unspecified.

The slk_init() function has the effect of calling ripoffline() to reserve one screen line to accommodate the requested format.

The slk_set() and slk_wset() functions specify the text of soft label number *labnum*, within the range from 1 to and including 8. The *label* argument is the string to be put on the label. With slk_set(), and slk_wset(), the width of the label is limited to eight column positions. A null string or a null pointer specifies a blank label. The justify argument can have the following values to indicate how to justify *label* within the space reserved for it:

0

Align the start of label with the start of the space

1 Center label within the space

2

Align the end of label with the end of the space

The slk_refresh() and slk_noutrefresh() functions correspond to the wrefresh() and wnoutrefresh() functions.

The slk_label() function obtains soft label number labnum.

The slk_clear() function immediately clears the soft labels from the screen.

The slk_restore() function immediately restores the soft labels to the screen after a call to slk_clear().

The slk_touch() function forces all the soft labels to be output the next time slk_noutrefresh() or slk_refresh() is called.

The slk_attron(), slk_attrset() and slk_attroff() functions correspond to attron(), attrset(), and attroff(). They have an effect only if soft labels are simulated on the bottom line of the screen.

The slk_attr_off(), slk_attr_on() and slk_attr_set(), and slk_color() functions correspond to slk_attroff(), slk_attron(), slk_attrset() and color_set() and thus support the attribute constants with WA_ prefix and color.

The *opts* argument is reserved for defintion in a future edition of this document. Currently, the application must provide a null pointer as *opts*.

### **Return Value**

Upon successful completion, slk_label() returns the requested label with leading and trailing blanks stripped. Otherwise, it returns a null pointer.

Upon successful completion, the other functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

When using multi-byte character sets, applications should check the width of the string by calling mbstowcs() and then wcswidth() before calling slk_set(). When using wide characters, applications should check the width of the string by calling wcswidth() before calling slk_set().

Since the number of columns that a wide character string will occupy is codeset-specific, call wcwidth() and wcswidth() to check the number of column positions in the string before calling slk_wset().

Most applications would use slk_noutrefresh() because a wrefresh() is likely to follow soon.

### See Also

```
attr_get(), attroff(), delscreen(), mbstowcs(), ripoffline(), wcswidth(), <curses.h>.
```

# standend()

#### Name

standend, standout, wstandend, wstandout - set and clear window attributes

## **Synopsis**

```
#include <curses.h>
int standend(void);
int standout(void);
int wstandend(WINDOW *win);
int wstandout(WINDOW *win);
```

### **Description**

The standend() and wstandend() functions turn off all attributes of the current or specified window.

The standout() and wstandout() functions turn on the standout attribute of the current or specified window.

#### **Return Value**

These functions always return 1.

### **Errors**

No errors are defined.

#### See Also

```
attroff(), attr_get(), <curses.h>.
```

# start_color()

#### Name

start_color - initialize use of colors on terminal

## **Synopsis**

```
#include <curses.h>
int start_color(void);
```

## **Description**

Refer to can_change_color().

## stdscr

#### Name

stdscr - default window

# **Synopsis**

```
#include <curses.h>
extern WINDOW *stdscr;
```

# **Description**

The external variable stdscr specifies the default window used by functions that do not specify a window using an argument of type WINDOW *. Other windows may be created using newwin().

#### See Also

derwin(), <curses.h>.

# subpad()

#### Name

subpad - create a subwindow in a pad

# **Synopsis**

```
#include <curses.h>
WINDOW *subpad(WINDOW *orig, int nlines, int ncols, int begin_y,
    int begin_x);
```

# Description

Refer to newpad().

# subwin()

#### Name

subwin - create a subwindow

## **Synopsis**

### **Description**

Refer to derwin().

# syncok()

#### Name

syncok, wcursyncup, wsyncdown, wsyncup - synchronise a window with its parents or children

# **Synopsis**

```
#include <curses.h>
int syncok(WINDOW *win, bool bf);
void wcursyncup(WINDOW *win);
void wsyncdown(WINDOW *win);
void wsyncup(WINDOW *win);
```

### **Description**

The syncok() function determines whether all ancestors of the specified window are implicitly touched whenever there is a change in the window. If *bf* is TRUE, such implicit touching occurs. If *bf* is FALSE, such implicit touching does not occur. The initial state is FALSE.

The wcursyncup() function updates the current cursor position of the ancestors of *win* to reflect the current cursor position of *win*.

The wsyncdown() function touches win if any ancestor window has been touched.

The wsyncup() function unconditionally touches all ancestors of win.

### **Return Value**

Upon successful completion, syncok() returns OK. Otherwise, it returns ERR.

The other functions do not return a value.

### **Errors**

No errors are defined.

# **Application Usage**

Applications seldom call wsyncdown() because it is called by all refresh operations.

### See Also

doupdate(), is_linetouched(), <curses.h>.

# termattrs()

#### Name

termattrs - get supported terminal video attributes

## **Synopsis**

```
#include <curses.h>
chtype termattrs(void);
attr_t term_attr(void);
```

## **Description**

The termattrs() function extracts the video attributes of the current terminal which is supported by the chtype data type.

The term_attrs() function extracts information for the video attributes of the current terminal which is supported for a cchar_t.

### **Return Value**

The termattrs() function returns a logical OR of A_values of all video attributes supported by the terminal. The term_attrs() function returns a logical OR of WA_ values of all video attributes supported by the terminal.

#### **Errors**

No errors are defined.

#### See Also

attroff(), attr_get(), <curses.h>.

# termname()

### Name

termname - get terminal name

## **Synopsis**

```
#include <curses.h>
char *termname(void);
```

### **Description**

The termname() function obtains the terminal name as recorded by setupterm().

### **Return Value**

The termname() function returns a pointer to the terminal name.

#### **Errors**

No errors are defined.

#### See Also

```
del_curterm(), getenv() initscr(), <curses.h>.
```

# tgetent()

#### Name

tgetent, tgetflag, tgetnum, tgetstr, tgoto - termcap database emulation (TO BE WITHDRAWN)

## **Synopsis**

```
#include <term.h>
int tgetent(char *bp, const char *name);
int tgetflag(char id[2]);
int tgetnum(char id[2]);
char *tgetstr(char id[2], char **area);
char *tgoto(char *cap, int col, int row);
```

## **Description**

The tgetent() function looks up the termcap entry for name. The emulation ignores the buffer pointer bp.

The tgetflag() function gets the boolean entry for id.

The tgetnum() function gets the numeric entry for id.

The tgetstr() function gets the string entry for id. If area is not a null pointer and does not point to a null pointer, tgetstr() copies the string entry into the buffer pointed to by *area and advances the variable pointed to by area to the first byte after the copy of the string entry.

The tgoto() function instantiates the parameters *col* and *row* into capability *cap* and returns a pointer to the resulting string.

All of the information available in the terminfo database need not be available through these functions.

#### **Return Value**

Upon successful completion, functions that return an integer return OK. Otherwise, they return ERR.

Functions that return pointers return a null pointer on error.

### **Errors**

No errors are defined.

# **Application Usage**

These functions are included as a conversion aid for programs that use the termcap library. Their arguments are the same and the functions are emulated using the terminfo database.

These functions are only guaranteed to operate reliably on character sets in which each character fits into a single byte, whose attributes can be expressed using only constants with the A_ prefix.

Any terminal capabilities from the terminfo database that cannot be retrieved using these interfaces can be retrieved using the interfaces described on the tigetflag() page.

#### **Enhanced Curses**

Portable applications must use tputs() to output the strings returned by tgetstr() and tgoto().

### See Also

```
putc(), setupterm(), tigetflg(), <term.h>.
```

# tigetflag()

#### Name

tigetflag, tigetnum, tigetstr, tparm - retrieve capabilities from the terminfo database

## **Synopsis**

### **Description**

The tigetflag(), tigetnum(), and tigetstr() functions obtain boolean, numeric and string capabilities, respectively, from the selected record of the terminfo database. For each capability, the value to use as *capname* appears in the Capname column.

The tparm() function takes as cap a string capability. If cap is parameterized, tparm() resolves the parameterization. If the parameterized string refers to parameters %p1 through %p9, then tparm() substitutes the values of p1 through p9, respectively.

### **Return Value**

Upon successful completion, tigetflg(), tigetnum() and tigetstr() return the specified capability. The tigetflag() function returns -1 if *capname* is not a boolean capability. The tigetnum() function returns -2 if *capname* is not a numeric capability. The tigetstr() function returns (char *)-1 if *capname* is not a string capability.

Upon successful completion, tparm() returns *str* with parameterization resolved. Otherwise, it returns a null pointer.

#### **Errors**

No errors are defined.

# **Application Usage**

For parameterized string capabilities, the application should pass the return value from tigetstr() to tparm(), as described above.

Applications intending to send terminal capabilities directly to the terminal (which should only be done using tputs() or putp()) instead of using Curses, normally should obey the following rules:

- Call reset_shell_mode() to restore the display modes before exiting.
- If using cursor addressing, output enter_ca_mode upon startup and output exit_ca_mode before exiting.

• If using shell escapes, output exit_ca_mode and call reset_shell_mode() before calling the shell; call reset_prog_mode() and output enter_ca_mode after returning from the shell.

All parameterized terminal capabilities defined in this document can be passed to tparm(). Some implementations create their own capabilities, create capabilities for non-terminal devices, and redefine the capabilities in this document. These practices are non-conforming because it may be that tparm() cannot parse these user-defined strings.

### See Also

```
def_prog_mode(), tgetent(), putp(), <term.h>.
```

# timeout()

### Name

timeout - control blocking on input

# **Synopsis**

```
#include <curses.h>
void timeout(int delay);
```

## **Description**

Refer to notimeout().

# touchline()

### Name

touchline, touchwin - window refresh control functions

# **Synopsis**

```
#include <curses.h>
int touchline(WINDOW *win, int start, int count);
int touchwin(WINDOW *win);
```

# **Description**

Refer to is_linetouched().

# tparm()

### Name

tparm - retrieve capabilities from the terminfo database

# **Synopsis**

```
#include <term.h>
```

#### **Enhanced Curses**

```
char *tparm(char *cap, long p1, long p2, long p3, long p4, long p5, long p6, long p7, long p8, long p9);
```

### **Description**

Refer to tigetflag().

# tputs()

### Name

tputs - output commands to the terminal

## **Synopsis**

```
#include <curses.h>
int tputs(const char *str, int affcnt, int (*putfunc)(int));
```

## Description

Refer to putp().

# typeahead()

#### Name

typeahead - control checking for typeahead

# **Synopsis**

```
#include <curses.h>
int typeahead(int fildes);
```

## Description

The typeahead() function controls the detection of typeahead during a refresh, based on the value of *fildes*:

- If *fildes* is a valid file descriptor, typeahead is enabled during refresh; Curses periodically checks *fildes* for input and aborts the refresh if any character is available. (This is the initial setting, and the typeahead file descriptor corresponds to the input file associated with the screen created by initscr() or newterm().) The value of *fildes* need not be the file descriptor on which the refresh is occurring.
- If fildes is -1, Curses does not check for typeahead during refresh.

### **Return Value**

Upon successful completion, typeahead() returns OK. Otherwise, it returns ERR.

### **Errors**

No errors are defined.

#### See Also

doupdate(), getch(), initscr(), <curses.h>.

# unctrl()

#### Name

unctrl - generate printable representation of a character

### **Synopsis**

```
#include <unctrl.h>
char *unctrl(chtype c);
```

### **Description**

The unctrl() function generates a character string that is a printable representation of c. If c is a control character, it is converted to the ^X notation. If c contains rendition information, the effect is undefined.

### **Return Value**

Upon successful completion, unctrl() returns the generated string. Otherwise, it returns a null pointer.

#### **Errors**

No errors are defined.

#### See Also

keyname(), wunctrl(), <unctrl.h>.

# ungetch()

#### Name

ungetch, unget_wch - push a character onto the input queue

## **Synopsis**

```
#include <curses.h>
int ungetch(int ch);
int unget_wch(const wchar_t wch);
```

## Description

The ungetch() function pushes the single-byte character ch onto the head of the input queue.

The unget_wch() function pushes the wide character wch onto the head of the input queue.

One character of push-back is guaranteed. If these functions are called too many times without an intervening call to getch() or get_wch(), the operation may fail.

#### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

### See Also

```
getch(), get_wch(), <curses.h>.
```

# untouchwin()

#### Name

untouchwin - window refresh control function

## **Synopsis**

```
#include <curses.h>
int untouchwin(WINDOW *win);
```

## **Description**

Refer to is_linetouched().

## use_env()

#### Name

use_env - specify source of screen size information

# **Synopsis**

```
#include <curses.h>
void use_env(bool boolval);
```

## **Description**

The use_env() function specifies the technique by which the implementation determines the size of the screen. If *boolval* is FALSE, the implementation uses the values of lines and columns specified in the terminfo database. If *boolval* is TRUE, the implementation uses the *LINES* and *COLUMNS* environment variables. The initial value is TRUE.

Any call to use_env() must precede calls to initscr(), newterm() or setupterm().

### **Return Value**

The function does not return a value.

### **Errors**

No errors are defined.

### See Also

del_curterm(), initscr(), <curses.h>.

# vidattr()

#### Name

vidattr, vid_attr, vidputs, vid_puts - output attributes to the terminal

### **Synopsis**

```
#include <curses.h>
int vidattr(chtype attr);
int vid_attr(attr_t attr, short color_pair_number, void *opt);
int vidputs(chtype attr,, int (*putfunc)(int));
int vid_puts(attr_t attr, short_pair_number, void *opt, int_t (*putfunc)(init_t));
```

## Description

These functions output commands to the terminal that change the terminal's attributes.

If the terminfo database indicates that the terminal in use can display characters in the rendition specified by *attr*, then vidattr() outputs one or more commands to request that the terminal display subsequent characters in that rendition. The function outputs by calling putchar(). The vidattr() function neither relies on nor updates the model that Curses maintains of the prior rendition mode.

The vidputs() function computes the same terminal output string that vidattr() does, based on *attr*, but vidputs() outputs by calling the user-supplied function *putfunc*. The vid_attr() and vid_puts() functions correspond to vidattr() and vidputs() respectively, but take a set of arguments, one of type **attr_t** for the attributes, short for the *color_pair_number* and a *void** and thus support the attribute constants with the WA_prefix.

The opts argument is reserved for definition in a future edition of this document. Currently, the application must provide a null pointer as opts.

The user-supplied function *putfunc* (specified as an argument to vidputs()) is either putchar() or some other function with the same prototype. The vidputs() function ignores the return value of *putfunc*.

The vid_attr() and vid_puts() functions correspond to vidattr() and vidputs(), respectively, but take an argument of type attr_t and thus support the attribute constants with the WA_prefix.

The user-supplied function *putwfunc* (specified as an argument to vid_puts()) is either putwchar() or some other function with the same prototype. The vid_puts() function ignores the return value of *putwfunc*.

### **Return Value**

Upon successful completion, these functions return OK. Otherwise, they return ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

After use of any of these functions, the model Curses maintains of the state of the terminal might not match the actual state of the terminal. The application should touch and refresh the window before resuming conventional use of Curses.

Use of these functions requires that the application contain so much information about a particular class of terminal that it defeats the purpose of using Curses.

#### **Enhanced Curses**

On some terminals, a command to change rendition conceptually occupies space in the screen buffer (with or without width). Thus, a command to set the terminal to a new rendition would change the rendition of some characters already displayed.

### See Also

doupdate(), is_linetouched(), putchar()), putwchar(), tigetflag(), <curses.h>.

# vline()

### Name

vline - draw vertical line

# **Synopsis**

```
#include <curses.h>
int vline(chtype ch, int n);
```

## **Description**

Refer to hline().

# vline_set()

#### Name

vline_set - draw vertical line from complex character and rendition

# **Synopsis**

```
#include <curses.h>
int vline_set(const cchar_t *ch, int n);
```

# **Description**

Refer to hline_set().

# vwprintw()

### Name

vwprintw - print formatted output in window

# **Synopsis**

```
#include <varargs.h>
#include <curses.h>
int vwprintw(WINDOW *, char *, va_list varglist);
```

### **Description**

The vwprintw() function achieves the same effect as wprintw() using a variable argument list. The third argument is a  $va_list$ , as defined in **<varargs.h>**.

#### **Return Value**

Upon successful completion, vwprintw() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

The vwprintw() function is deprecated because it relies on deprecated functions in the XSH specification. The vw_printw() function is preferred. The use of the vwprintw() and the vw_printw() functions in the same file will not work, due to the requirements to include **varargs.h** and **stdarg.h** which both contain definitions of  $va_list$ .

### See Also

mvprintw(), fprintf(), vw_printw(), <curses.h>, <varargs.h>.

# vw_printw()

#### Name

vw_printw - print formatted output in window

# **Synopsis**

```
#include <stdarg.h>
#include <curses.h>
int vw_printw(WINDOW *, char *, va_list varglist);
```

## Description

The vw_printw() function achieves the same effect as wprintw() using a variable argument list. The third argument is a  $va_list$ , as defined in **<stdarg.h>**.

#### **Return Value**

Upon successful completion, vw_printw() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

# **Application Usage**

The vw_printw() function is preferred over vwprintw(). The use of the vwprintw() and the vw_printw() functions in the same file will not work, due to the requirement to include **varargs.h** and **stdarg.h** which both contain definitions of  $va_list$ .

### See Also

mvprintw(), fprintf(), <curses.h>, <stdarg.h>.

# vwscanw()

#### Name

vwscanw - convert formatted input from a window

## **Synopsis**

```
#include <varargs.h>
#include <curses.h>
int vwscanw(WINDOW *, char *, va_list varglist);
```

# **Description**

The vwscanw() function achieves the same effect as wscanw() using a variable argument list. The third argument is a  $va_list$ , as defined in **<varargs.h>**.

#### **Return Value**

Upon successful completion, vwscanw() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

## **Application Usage**

The vwscanw() function is deprecated because it relies on deprecated functions in the XSH specification. The vw_scanw() function is preferred. The use of the vwscanw() and the vw_scanw() functions in the same file will not work, due to the requirement to include **varargs.h** and **stdarg.h** which both contain definitions of  $va_list$ .

#### See Also

fscanf(), mvscanw(), vw_scanw(), <curses.h>, varargs.h>.

# vw_scanw()

#### Name

vw_scanw - convert formatted input from a window

# **Synopsis**

```
#include <stdarg.h>
#include <curses.h>
int vw_scanw(WINDOW *, char *, va_list varglist);
```

# **Description**

The vw_scanw() function achieves the same effect as wscanw() using a variable argument list. The third argument is a  $v\alpha$ _list, as defined in **<stdarg.h>**.

### **Return Value**

Upon successful completion, vw_scanw() returns OK. Otherwise, it returns ERR.

#### **Errors**

No errors are defined.

### **Application Usage**

The vw_scanw() function is preferred over vwscanw(). The use of the vwscanw() and the vw_scanw() functions in the same file will not work, due to the requirement to include **varargs.h** and **stdarg.h** which both contain definitions of  $va_list$ .

#### See Also

fscanf(), mvscanw(), <curses.h>, <stdarg.h>.

#### W

#### Name

w - pointer page for functions with w prefix

# **Description**

Most uses of the w prefix indicate that a Curses function takes a win argument that specifies the affected window. ³ (The corresponding functions without the w prefix operate on the current window.)

The w functions are discussed together with the corresponding functions without the w prefix. They are found on the following entries:

Function	Refer to
* There is no corresponding function without the w	prefix.
waddch()	addch()
waddchnstr()	addchstr()
waddchstr()	addchstr()
waddnstr()	addnstr()
waddstr()	addnstr()
waddnwstr()	addnwstr()
waddwstr()	addnwstr()
wadd_wch()	add_wch()
wadd_wchnstr()	add_wchnstr()
wadd_wchstr()	add_wchnstr()
wattroff()	attroff()
wattron()	attroff()
wattrset()	attroff()
wattr_get()	attr_get()
wattr_off()	attr_get()
wattr_on()	attr_get()
wattr_set()	attr_get()

³ The wunctrl() function is an exception to this rule and has an entry under its own name.

Function	Refer to
wbkgd()	bkgd()
wbkgdset()	bkgd()
wbkgrnd()	bkgrnd()
wbkgrndset()	bkgrnd()
wborder()	border()
wborder_set()	border_set()
wchgat()	chgat()
wclear()	clear()
wclrtobot()	clrtobot()
wclrtoeol()	clrtoeol()
wcursyncup() *	syncok()
wdelch()	delch()
wdeleteln()	deleteln()
wechochar()	echochar()
wecho_wchar()	echo_wchar()
werase()	clear()
wgetbkgrnd()	bkgrnd()
wgetch()	getch()
wgetnstr()	getnstr()
wgetn_wstr()	getn_wstr()
wgetstr()	getnstr()
wget_wch()	get_wch()
wget_wstr()	getn_wstr()
whline()	hline()
whline_set()	hline_set()
winch()	inch()
winchnstr()	inchnstr()
winchstr()	inchnstr()
winnstr()	innstr()
winnwstr()	innwstr()
winsch()	insch()
winsdelln()	insdelln()
winsertln()	insertln()
winsnstr()	insnstr()
winsstr()	insnstr()
winstr()	innstr()
wins_nwstr()	ins_nwstr()

Function	Refer to
wins_wch()	ins_wch()
wins_wstr()	ins_nwstr()
winwstr()	innwstr()
win_wch()	in_wch()
win_wchnstr()	in_wchnstr()
win_wchstr()	in_wchnstr()
wmove()	move()
wnoutrefresh()	doupdate()
wprintw()	mvprintw()
wredrawln()	redrawln()
wrefresh()	doupdate()
wscanw()	mvscanw()
wscrl()	scrl()
wsetscrreg()	clearok()
wstandend()	standend()
wstandout()	standend()
wsyncdown() *	syncok()
wsyncup() *	syncok()
wtimeout()	notimeout()
wtouchln() *	is_linetouch()
wvline()	hline()
wvline_set()	hline_set()

# wunctrl()

#### Name

wunctrl - generate printable representation of a wide character

# **Synopsis**

```
#include <curses.h>
wchar_t *wunctrl(cchar_t *wc);
```

# **Description**

The wunctrl() function generates a wide character string that is a printable representation of the wide character wc.

This function also performs the following processing on the input argument:

- Control characters are converted to the ^X notation.
- Any rendition information is removed.

#### **Enhanced Curses**

# **Return Value**

Upon successful completion, wunctrl() returns the generated string. Otherwise, it returns a null pointer.

# **Errors**

No errors are defined.

# See Also

keyname(), unctrl(), <curses.h>.

# **Chapter 6. Headers**

This chapter describes the contents of headers used by the Curses functions, macros and external variables.

Headers contain the definition of symbolic constants, common structures, preprocessor macros and defined types. Each function in <u>Chapter 6</u>, "<u>Headers</u>," on page 121 specifies the headers that an application must include in order to use that function. In most cases only one header is required. These headers are present on an application development system; they do not have to be present on the target execution system.

#### <cursesh>

#### Name

curses.h - definitions for screen handling and optimization functions

# **Synopsis**

#include <curses.h>

# **Description**

#### **Objects**

The <curses.h> header provides a declaration for COLOR_PAIRS, COLORS, COLS, curscr, LINES and stdscr.

#### **Constants**

The following constants are defined:

#### **EOF**

Function return value for end-of-file

#### **ERR**

Function return value for failure

#### **FALSE**

Boolean false value

#### OK

Function return value for success

#### **TRUE**

Boolean true value

#### **WEOF**

Wide-character function return value for end-of-file, as defined in <wchar.h>.

The following constant is defined if the implementation supports the indicated revision of the X/Open Curses specification.

```
_XOPEN_CURSES X/Open Curses, Issue 4 Verson 2, May 1996, C610 <ISBN> (i.e. this document).
```

#### **Data Types**

The following data types are defined through **typedef**:

#### attr_t

An OR-ed set of attributes

#### bool

Boolean data type

#### chtype

A character, attributes and a color-pair

#### **SCREEN**

An opaque terminal representation

#### wchar_t

As described in <stddef.h>

#### wint t

As described in <wchar.h>

#### cchar_t

References a string of wide characters

#### **WINDOW**

An opaque window representation

The inclusion of <curses.h> may make visible all symbols from the headers <stdio.h>, <term.h>, <termios.h> and <wchar.h>.

#### **Attribute Bits**

The following symbolic constants are used to manipulate objects of type attr_t:

#### WA_ ALTCHARSET

Alternate character set

#### WA_ BLINK

Blinking

#### WA_ BOLD

Extra bright or bold

#### WA_ DIM

Half bright

#### WA_ HORIZONTAL

Horizontal highlight

#### WA_ INVIS

Invisible

#### WA_ LEFT

Left highlight

#### WA_ LOW

Low highlight

#### WA_ PROTECT

Protected

#### WA_ REVERSE

Reverse video

#### WA_ RIGHT

Right highlight

#### WA_ STANDOUT

Best highlighting mode of the terminal

#### WA_ TOP

Top highlight

#### **WA_ UNDERLINE**

Underlining

#### WA_ VERTICAL

Vertical highlight

These attribute flags shall be distinct.

The following symbolic constants are used to manipulate attribute bits in objects of type chtype:

#### **A_ALTCHARSET**

Alternate character set

#### **A_BLINK**

Blinking

#### A_BOLD

Extra bright or bold

#### A DIM

Half bright

#### A INVIS

Invisible

#### A_PROTECT

Protected

#### **A_REVERSE**

Reverse video

#### **A STANDOUT**

Best highlighting mode of the terminal

#### **A_UNDERLINE**

Underlining

These attribute flags need not be distinct except when _XOPEN_CURSES is defined and the application sets _XOPEN_SOURCE_EXTENDED to 1.

The following symbolic constants can be used as bit-masks to extract the components of a **chtype**:

#### **A_ATTRIBUTES**

Bit-mask to extract attributes

#### **A_CHARTEXT**

Bit-mask to extract a character

#### A_COLOR

Bit-mask to extract color-pair information

The following symbolic constants can be used as bit-masks to extract the components of a chtype:

#### **A_ATTRIBUTES**

Bit-mask to extract attributes

#### **A CHARTEXT**

Bit-mask to extract a character

#### A_COLOR

Bit-mask to extract color-pair information

#### **Line-Drawing Constants**

The <curses.h> header defines the symbolic constants shown in the leftmost two columns of the following table for use in drawing lines. The symbolic constants that begin with ACS_ are char constants. The symbolic constants that begin with WACS_ are cchar_t constants for use with the wide-character interfaces that take a pointer to a cchar_t.

In the POSIX locale, the characters shown in the POSIX Locale Default column are used when the terminal database does not specify a value using the acsc capability.

char Constant	char_t Constant	POSIX Locale Default	Glyph Description
ACS_ULCORNER	WACS ULCORNER	+	upper left-hand corner

char Constant	char_t Constant	POSIX Locale Default	Glyph Description
ACS_LLCORNER	WACS_LLCORNER	+	lower left-hand corner
ACS_URCORNER	WACS_URCORNER	+	upper right-hand corner
ACS_LRCORNER	WACS_LRCORNER	+	lower right-hand corner
ACS_RTEE	WACS_RTEE	+	right tee (- )
ACS_LTEE	WACS_LTEE	+	left tee ( -)
ACS_BTEE	WACS_BTEE	+	bottom tee ( )
ACS_TTEE	WACS_TTEE	+	top tee ( )
ACS_HLINE	WACS_HLINE	-	horizontal line
ACS_VLINE	WACS_VLINE	1	vertical line
ACS_PLUS	WACS_PLUS+	plus	
ACS_S1	WACS_S1	-	scan line 1
ACS_S9	WACS_S9	-	scan line 9
ACS_DIAMOND	WACS_DIAMOND	+	diamond
ACS_CKBOARD	WACS_CKBOARD	:	checker board (stipple)
ACS_DEGREE	WACS_DEGREE	1	degree symbol
ACS_PLMINUS	WACS_PLMINUS	#	plus/minus
ACS_BULLET	WACS_BULLET	0	bullet
ACS_LARROW	WACS_LARROW	<	arrow pointing left
ACS_RARROW	WACS_RARROW	>	arrow pointing right
ACS_DARROW	WACS_DARROW	V	arrow pointing down
ACS_UARROW	WACS_UARROW	٨	arrow pointing up
ACS_BOARD	WACS_BOARD	#	board of squares
ACS_LANTERN	WACS_LANTERN	#	lantern symbol

char Constant	char_t Constant	POSIX Locale Default	Glyph Description
ACS_BLOCK	WACS_BLOCK	#	solid square block

#### **Color-Related Macros**

The following color-related macros are defined:

COLOR_BLACK

COLOR_BLUE

**COLOR_GREEN** 

COLOR_CYAN

COLOR_RED

COLOR_MAGENTA

COLOR_YELLOW

COLOR_WHITE

#### **Coordinate-Related Macros**

The following coordinate-related macros are defined:

```
void getbegyx(WINDOW *win, int y, int x);
void getmaxyx(WINDOW *win, int y, int x);
void getparyx(WINDOW *win, int y, int x);
void getyx(WINDOW *win, int y, int x);
```

#### **Key Codes**

The following symbolic constants representing function key values are defined:

#### **Key Code**

**Description** 

#### KEY_CODE_YES

Used to indicate that a wchar_t variable contains a key code

#### **KEY_BREAK**

Break key

#### KEY_DOWN

Down arrow key

#### KEY UP

Up arrow key

#### **KEY_LEFT**

Left arrow key

#### **KEY_RIGHT**

Right arrow key

#### **KEY_HOME**

Home key

#### KEY_BACKSPACE

Backspace

#### KEY_F0

Function keys; space for 64 keys is reserved

#### KEY_F(n)

For 0_<n_<63

#### **CURSES**

KEY_DL

Delete line

KEY_IL

Insert line

KEY_DC

Delete character

KEY_IC

Insert char or enter insert mode

KEY_EIC

Exit insert char mode

**KEY_CLEAR** 

Clear screen

KEY_EOS

Clear to end of screen

KEY_EOL

Clear to end of line

**KEY_SF** 

Scroll 1 line forward

KEY_SR

Scroll 1 line backward (reverse)

KEY_NPAGE

Next page

KEY_PPAGE

Previous page

**KEY_STAB** 

Set tab

**KEY_CTAB** 

Clear tab

KEY_CATAB

Clear all tabs

KEY_ENTER

Enter or send

**KEY_SRESET** 

Soft (partial) reset

**KEY_RESET** 

Reset or hard reset

**KEY PRINT** 

Print or copy

KEY_LL

Home down or bottom

KEY_A1

Upper left of keypad

KEY_A3

Upper right of keypad

KEY_B2

Center of keypad

KEY_C1

Lower left of keypad

KEY_C3

Lower right of keypad

The virtual keypad is a 3-by-3 keypad arranged as follows:

A1	UP	А3
LEFT	B2	RIGHT
C1	DOWN	C3

Each legend, such as A1, corresponds to a symbolic constant for a key code from the preceding table, such as KEY_A1.

The following symbolic constants representing function key values are also defined:

#### **Key Code**

**Description** 

#### **KEY_BTAB**

Back tab key

#### **KEY BEG**

Beginning key

#### KEY_CANCEL

Cancel key

#### KEY_CLOSE

Close key

#### KEY_COMMAND

Cmd (command) key

#### KEY_COPY

Copy key

#### **KEY_CREATE**

Create key

#### KEY_END

End key

#### **KEY_EXIT**

Exit key

#### KEY_FIND

Find key

#### **KEY_HELP**

Help key

#### **KEY MARK**

Mark key

#### **KEY_MESSAGE**

Message key

#### **KEY_MOVE**

Move key

#### **KEY_NEXT**

Next object key

#### KEY_OPEN

Open key

#### **KEY_OPTIONS**

Options key

#### **KEY_PREVIOUS**

Previous object key

#### KEY_REDO

Redo key

#### KEY_REFERENCE

Reference key

#### **KEY_REFRESH**

Refresh key

#### **KEY_REPLACE**

Replace key

#### **KEY_RESTART**

Restart key

#### KEY_RESUME

Resume key

#### **KEY_SAVE**

Save key

#### **KEY_SBEG**

Shifted beginning key

#### **KEY_SCANCEL**

Shifted cancel key

#### **KEY_SCOMMAND**

Shifted command key

#### KEY_SCOPY

Shifted copy key

#### **KEY_SCREATE**

Shifted create key

#### KEY_SDC

Shifted delete char key

#### KEY_SDL

Shifted delete line key

#### **KEY_SELECT**

Select key

#### **KEY_SEND**

Shifted end key

#### KEY_SEOL

Shifted clear line key

#### **KEY_SEXIT**

Shifted exit key

#### **KEY_SFIND**

Shifted find key

#### **KEY_SHELP**

Shifted help key

#### **KEY_SHOME**

Shifted home key

#### **KEY SIC**

Shifted input key

#### **KEY_SLEFT**

Shifted left arrow key

#### KEY_SMESSAGE

Shifted message key

#### **KEY_SMOVE**

Shifted move key

#### **KEY_SNEXT**

Shifted next key

#### **KEY_SOPTIONS**

Shifted options key

#### **KEY_SPREVIOUS**

Shifted prev key

#### **KEY_SPRINT**

Shifted print key

#### KEY_SREDO

Shifted redo key

#### **KEY_SREPLACE**

Shifted replace key

#### **KEY SRIGHT**

Shifted right arrow

#### **KEY_SRSUME**

Shifted resume key

#### **KEY_SSAVE**

Shifted save key

#### KEY_SSUSPEND

Shifted suspend key

#### KEY_SUNDO

Shifted undo key

#### **KEY SUSPEND**

Suspend key

#### KEY_UNDO

Undo key

#### **Function Prototypes**

The following are declared as functions, and may also be defined as macros:

```
addch(const chtype);
int
           addchstr(const chtype *, init);
addchnstr(chtype *const chstr, int n);
addchstr(const chtype *);
int
int
int
           addnstr(const char *, init);
addnwstr(const wchar_t *, int);
int
int
int
           addstr(const char *);
           add_wch(const cchar_t *);
add_wchnstr(const cchar_t *, int);
int
int
int
           add_wchstr(const cchar_t *);
int
           addwstr(const wchar_t *);
           attroff(int);
int
           attron(int)
int
int
           attrset(int);
           attr_get(attr_t *, short *, void*);
attr_of(attr_t void *);
attr_on(attr_t, void *);
int
int
int
           attr_set(attr_t, short, void *);
baudrate(void);
int
int
int
           beep(void);
            bkgd(chtype);
int
void
           bkgdset(chtype);
           bkgrnd(const cchar_t *);
bkgrndset(const cchar_t *);
ind
void
           border(chtype, chtype, chtype, chtype, chtype, chtype, chtype, chtype);
border_set(const cchar_t *, const cchar_t *,
int
                              const cchar_t *, const cchar_t *,
const cchar_t *, const cchar_t *,
const cchar_t *, const cchar_t *,
const cchar_t *, const cchar_t *);
           box(WINDOW *, chtype, chtype);
box_set(WINDOW *, const cchar_t *, const cchar_t *);
can_change_color(void);
int
int
bool
           cbreak(void);
```

```
chgat(int, attr_t, short, const void *);
        clearok(WINDOW *, bool);
int
        clear(void);
        clrtobot(WINDOW *win, bool bf);
int
int
        clrtoeol(void);
        color_content(short, short *, short *, short *);
int
int
        COLOR_PAIR(int);
       Color_set(short,void *);
copywin(const WINDOW *, WINDOW *, int, int, int,
int
int
                 int, int, int, int);
int
        curs_set(int)
       def_prog_mode(void);
int
        def_shell_mode(void);
int
int
        delay_output(int);
int
        delch(void);
int
        deleteln(void)
       delscreen(SCREEN *);
void
int delwin(WINDOW *);
WINDOW *derwin(WINDOW *, int, int, int, int);
        doupdate(void);
WINDOW *dupwin(WINDOW *);
int
       echo(void);
        echochar(const chtype);
int
int
        echo_wchar(const cchar_t *);
int
        endwin(void);
char
       erasechar(void);
int
       erase(void);
        erasewchar(wchar_t *);
int
void
       filter(void);
int
        flash(void);
int
        flushinp(void);
chtype getbkgd(WINDOW *);
       getbkgrnd(cchar_t *);
getcchar(const cchar_t *, wchar_t *, attr_t *,
int
int
                  short *, void *);
        getch(void);
getnstr(char *, int);
int
int
int
        getn_wstr(wint_t *, int);
int
        getstr(char *);
        get_wch(wint_t *);
int
WINDOW *getwin(FILE *);
int
        get_wstr(wint_t *);
int
        halfdelay(int)
        has_colors(void);
bool
       has_ic(void);
bool
        has_il(void);
bool
        hline(chtype, int);
int
int
       hline_set(const cchar_t *, int);
        idcok(WINDOW *, bool);
void
        idlok(WINDOW *win, bool bf);
int
        immedok(WINDOW *, bool);
void
chtype inch(void);
int
        inchnstr(chtype *, int);
int
        inchstr(chtype *);
WINDOW *initscr(void);
int
        init_color(short, short, short, short);
int
        init_pair(short, short, short);
        innstr(char *, int);
innwstr(wchar_t *, int);
inneh(chtune);
int
int
        insch(chtype);
int
int
        insdelln(int;
int
        insertln(void);
int
        insnstr(cons char *, int);
int
        insstr(char *const str);
int
        ins_nwstr(const wchar_t *, int);
int
        insstr(const char *);
int
        instr(char *);
int
        ins_wch(const cchar_t *);
int
        ins_wchstr(const cchar_t *);
        intrflush(WINDOW *, bool);
int
int
        in_wch(cchar_t *);
        in_wchnstr(cchar_t *, int);
in_wchstr(cchar_t *);
int
int
int
        inwstr(wchar_t *);
        isendwin(void)
bool
        is_linetouched(WINDOW *, int);
bool
bool
        is_wintouched(WINDOW *);
char
       *keyname(int);
       *key_name(wchar_t);
char
int
        keypad(WINDOW *, bool);
char
        killchar(void);
        killwchar(wchar_t *);
```

```
leaveok(WINDOW *, bool);
int
                *longname(void);
char
                  meta(WINDOW *, bool);
move(int, int);
int
int
                  mvaddch(int, int, const chtype);
mvaddchnstr(int, int, const chtype *, int);
int
int
                  mvaddchstr(int, int, const chtype *);
mvaddnstr(int, int, const char *, int);
mvaddnwstr(int, int, const wchar_t *, int);
int
int
int
int
                  mvaddstr(int, int, const char *);
                  mvadd_wch(int, int, const cchar_t *);
mvadd_wchnstr(int, int, const cchar_t *, int);
mvadd_wchstr(int, int, const cchar_t *);
mvaddwstr(int, int, const wchar_t *);
mvaddwstr(int, int, int, attr_t, short, const void *);
int
int
int
int
int
int
                  mvcur(int, int, int, int);
                  mvdelch(int, int);
int
                  mvderwin(WINDOW *, int, int);
mvgetch(int, int);
int
int
                  mvgetnstr(int, int, char *, int);
mvgetn_wstr(int, int, wint_t *, int);
mvgetstr(int, int, char *);
mvget_wch(int, int, wint_t *);
mvget_wstr(int, int, wint_t *);
int
int
int
int
int
int mvhline(int, int, chtype, int);
int mvhline_set(int, int, const cchar_t *, int);
chtype mvinch(int, int);
int mvinchstr(int, int, chtype *, int);
int mvinchstr(int, int, chtype *);
int mvinchstr(int, int, chtype *);
                  mvinchst(int, int, char *, int);
mvinnwstr(int, int, char *, int);
mvinnwstr(int, int, wchar_t *, int);
mvinsch(int, int, chtype);
mvinsnstr(int, int, const char *, int);
int
int
int
int
in
                  mvins_nwstr(int, int, const wchar_t *, int);
int
                  mvinsstr(int, int, const char *);
                  mvinstr(int, int, char *);
mvins_wch(int, int, const cchar_t *);
int
int
int
                  mvins_watr(int, int, const wchar_t *);
                  mvin_wch(int, int, cchar_t *);
mvin_wchnstr(int, int, cchar_t *,);
mvin_wchstr(int, int, cchar_t *);
mvinwstr(int, int, wchar_t *);
mvinwstr(int, int, wchar_t *);
in
int
int
int
                 mvinwstr(int, int, wchar_t *);
mvprintw(int, int, char *, ...);
mvscanw(int, int, char *, ...);
mvvline(int, int, chtype, int);
mvvline_set(int, int, const cchar_t *, int);
mvwaddch(WINDOW *, int, int, const chtype);
mvwaddchstr(WINDOW *, int, int, const chtype *, init);
mvwaddchstr(WINDOW *, int, int, const chtype *);
mvwaddnstr(WINDOW *, int, int, const char *, int);
mvwaddnwstr(WINDOW *, int, int, const wchar_t *, int);
mvwaddstr(WINDOW *, int, int, const char *);
int
int
int
int
int
int
int
int
int
                  mvwaddstr(WINDOW *, int, int, const char *);
int
                  mvwadd_wch(WINDOW *, int, int, const cchar_t *);
mvwadd_wchnstr(WINDOW *, int, int, const cchar_t *, int);
mvwadd_wchnstr(WINDOW *, int, int, const cchar_t *);
int
int
int
                  mvwaddwstr(WINDOW *, int, int, const wchar_t *);
mvwchgat(WINDOW *, int, int, int, attr_t,
int
int
                                           short, const void *);
                 short, const void *);
mvwdelch(WINDOW *, int, int);
mvwgetch(WINDOW *, int, int);
mvwgetnstr(WINDOW *, int, int, char *, int);
mvwgetn_wstr(WINDOW *, int, int, wint_t *, int);
mvwgetstr(WINDOW *, int, int, wint_t *);
mvwget_wch(WINDOW *, int, int, wint_t *);
mvwget_wstr(WINDOW *, int, int, wint_t *);
mvwhline(WINDOW *, int, int, chype, int);
mvwhline_set(WINDOW *, int, int, const cchar_t *, int);
mvwin(WINDOW *, int, int):
int
int
int
int
int
int
int
int
int
                 mvwhline_set(WINDOW *, int, int, const cchar_t *, int);
mvwin(WINDOW *, int, int);
mvwinch(WINDOW *, int, int);
mvwinchnstr(WINDOW *, int, int, chtype *, int);
mvwinchstr(WINDOW *, int, int, chtype *);
mvwinnstr(WINDOW *, int, int, char *, int);
mvwinnwstr(WINDOW *, int, int, wchar_t *, int);
mvwinssch(WINDOW *, int, int, const char *, int);
mvwinsntr(WINDOW *, int, int, const char *, int);
mvwins_nwstr(WINDOW *, int, int, const wchar_t *, int);
mvwinsstr(WINDOW *, int, int, const char *):
int
chtype
int
int
int
int
int
int
int
int
                  mvwinsstr(WINDOW *, int, int, const char *);
                  mvwinstr(WINDOW *, int, int, char *);
mvwins_wch(WINDOW *, int, int, const cchar_t *);
mvwins_wstr(WINDOW *, int, int, const wchar_t *);
int
int
int
                  mvwin_wch(WINDOW *, int, int, cchar_t *);
int
                   mvwin_wchnstr(WINDOW *, int, int, cchar_t *, int);
```

```
mvwin_wchstr(WINDOW *, int, int, cchar_t *);
         mvwinwstr(WINDOW *, int, int, wchar_t *);
        mvwprintw(WINDOW *, int, int, char *, ...);
mvwscanw(WINDOW *, int, int, char *, ...);
mvwvline(WINDOW *, int, int, chtype, int);
mvwvline(WINDOW *, int, int, const cchar_t *, int);
int
int
int
int
int
         napms(int);
WINDOW *newpad(int, int);
SCREEN *newterm(char *, FILE *, FILE *);
WINDOW *newwin(int, int, int, int);
         nl(void)
int
         nocbreak(void);
         nodelay(WINDOW *, bool);
int
int
         noecho(void);
int
         nonl(void);
void
         noqiflush(void);
int
         noraw(void);
        notimeout(WINDOW *, bool);
overlay(const WINDOW *, WINDOW *);
overwrite(const WINDOW *, WINDOW *);
int
int
int
int
         pair_content(short, short *, short *);
         PAIR NUMBER(int);
int
        pechochar(WINDOW *, chtype);
pecho_wchar(WINDOW *, const cchar_t *);
pnoutrefresh(WINDOW *, int, int, int, int, int);
int
int
int
         prefresh(WINDOW *, int, int, int, int, int, int);
printw(char *, ...);
int
int
         putp(const char *);
putwin(WINDOW *, FILE *);
int
int
         qiflush(void);
void
int
         raw(void):
         redrawwin(WINDOW *);
int
int
         refresh(void);
int
         resetty(void)
int
         reset_prog_mode(void);
        reset_shell_mode(void);
resetty(void);
int
int
int
         ripoffline(int, int (*)(WINDOW *, int));
int
         savetty(void);
         scanw(char *, ...);
int
         scr_dump(const char *);
scr_init(const char *);
int
int
         scrl(int)
int
int
         scroll(WINDOW *);
         scrollok(WINDOW *, bool);
int
         scr_restore(const char *);
int
int
         scr_set(const char *);
int
         setcchar(cchar_t const wchar_t *, const attr_t,
        short, const void *);
setscrreg(int, int);
SCREEN *set_term(SCREEN *);
int setupterm(char *, int, int *);
int
         slk_attr_off(const attr_t void *);
int
         slk_attroff(const chtype);
int
         slk attr on(const attr t void *);
         slk_attron(const chtype);
int
         slk_attr_set(const attr_t, short, void *);
int
int
         slk_attrset(const chtype);
int
         slk_clear(void)
         slk_color(short);
int
       slk_init(int);
*slk_label(int)
int
char
        slk_noutrefresh(void);
int
int
         slk_refresh(void);
int
         slk_restore(void);
int
         slk_set(int, const char *, int);
int
         slk_touch(void);
         slk_wset(int, const wchar_t *, int);
int
int
         standend(void);
         standout(void)
int
int
         start_color(void);
WINDOW *subpad(WINDOW *, int, int, int, int);
WINDOW *subwin(WINDOW *, int, int, int, int);
int syncok(WINDOW *, bool);
chtype termattrs(void);
attr_t term_attrs(void);
char *termname(void);
        tigetflag(char *);
int
         tigetnum(char *);
int
char
       *tigetstr(char *);
void
        timeout(int)
        touchline(WINDOW *, int, int);
```

```
int
            touchwin(WINDOW *);
         *tparm(char *, long, long, long, long, long, long, long, long, long);
typeahead(int);
char
int
int
            ungetch(int);
int
            unget_wch(const wchar_t);
int
            untouchwin(WINDOW *);
           use_env(bool);
vid_attr(attr_t short, void *);
void
int
int
            vidattr(chtype);
           vid_puts(attr_t attr, short, void *, int (*)(int);
vidputs(chtype, int (*)(int));
int
int
            vline(chtype, int);
int
int
            vline_set(const cchar_t *, int);
           vwprintw(WINDOW *, char *, va_list *);
vw_printw(WINDOW *, char *, va_list *);
int
int
           vw_print(window *, char *, va_list *);
vwscanw(WINDOW *, char *, va_list *);
vw_scanw(WINDOW *, char *, va_list *);
waddch(WINDOW *, const chtype);
waddchnstr(WINDOW *, const chtype *, int);
int
int
int
int
           waddchstr(WINDOW *, const chtype *);
waddnstr(WINDOW *, const char *, int);
waddnwstr(WINDOW *, const wchar_t *, int);
int
int
int
           waddstr(WINDOW *, const char *);
int
           wadd_wch(WINDOW *, const cchar_t *);
int
           wadd_wchnstr(WINDOW *, const cchar_t *, int);
wadd_wchstr(WINDOW *, const cchar_t *);
int
int
           waddwstr(WINDOW *, const wchar_t *);
wattroff(WINDOW *, int);
int
int
           wattron(WINDOW *, int);
wattrset(WINDOW *, int);
wattr_get(WINDOW *, attr_t *, short *, void *);
int
int
int
           wattr_off(WINDOW *, attr_t void);
wattr_on(WINDOW *, attr_t void);
wattr_set(WINDOW *, attr_t, short, void *);
int
int
int
           wbkgd(WINDOW *, chtype);
wbkgdset(WINDOW *, chtype);
wbkgrnd(WINDOW *, const cchar_t *);
int
void
int
void
            wbkgrndset(WINDOW *, const cchar_t *);
           int
int
                                const cchar_t *, const cchar_t *,
const cchar_t *, const cchar_t *,
const cchar_t *, const cchar_t *);
           wchgat(WINDOW *, int, attr_t, short, const void *);
int
           wclear(WINDOW *);
int
           wclrtobot(WINDOW *)
int
            wclrtoeol(WINDOW *)
int
void
           wcursyncup(WINDOW *);
           wcolor_set(WINDOW *, short, void *);
wdelch(WINDOW *);
int
int
int
            wdeleteln(WINDOW *);
           wechochar(WINDOW *, const chtype);
wecho_wchar(WINDOW *, const cchar_t *);
int
int
           werase(WINDOW *);
int
           wgetbkgrnd(WINDOW *, cchar_t *);
int
int
           wgetch(WINDOW *);
           wgetnstr(WINDOW *, char *, int);
wgetn_wstr(WINDOW *, wint_t *, int);
int
int
           wgetstr(WINDOW *, char *);
wget_wch(WINDOW *, wint_t *);
wget_wstr(WINDOW *, wint_t *);
whline(WINDOW *, chtype, int);
int
int
int
int
           whline_set(WINDOW *, const cchar_t *, int);
int
chtype winch(WINDOW *)
            winchnstr(WINDOW *, chtype *, int ;
int
           winchstr(WINDOW *, chtype *);
winnstr(WINDOW *, char *, int);
winnwstr(WINDOW *, wchar_t *, int);
winsch(WINDOW *, chtype);
winsch(WINDOW *, int);
winschtln(WINDOW *, int);
int
int
int
int
int
int
            winsertln(WINDOW *);
           winsnstr(WINDOW *, const char *, int);
wins_nwstr(WINDOW *, const wchar_t *, int);
int
int
           wins_INST(WINDOW *, const wchar_t *, .
winstr(WINDOW *, const char *);
wins_wch(WINDOW *, const cchar_t *);
wins_wstr(WINDOW *, const wchar_t *);
win_wch(WINDOW *, cchar_t *);
win_wchstr(WINDOW *, cchar_t *, int);
win_wchostr(WINDOW *, cchar_t *, int);
int
int
int
int
int
int
            win_wchstr(WINDOW *, cchar_t *);
```

```
winwstr(WINDOW *, wchar_t *);
int
        wmove(WINDOW *, int, int);
        wnoutrefresh(WINDOW *);
int
        wprintw(WINDOW *, char *, ...);
wredrawln(WINDOW *, int, int);
int
int
int
        wrefresh(WINDOW *)
       wscanw(WINDOW *, char *, ...);
wscrl(WINDOW *, int);
wsetscrreg(WINDOW *, int, int);
int
int
int
        wstandend(WINDOW *);
int
int
        wstandout(WINDOW *);
void wsyncup(WINDOW *);
void wsyncdown(WINDOW *);
void wtimeout(WINDOW *, int);
        wtouchln(WINDOW *, int, int, int);
int
wchar_t *wunctrl(cchar_t *);
        wvline(WINDOW *, chtype, int);
        wvline_set(WINDOW *, const cchar_t *, int);
int
```

#### See Also

<stdio.h>, <term.h>, <termios.h>, <unctrl.h>, <wchar.h>.

#### <termh>

#### Name

term.h - terminal capabilities

# **Synopsis**

```
#include <term.h>
```

# Description

The following data type is defined through **typedef**:

#### **TERMINAL**

An opaque representation of the capabilities for a single terminal from the terminfo database.

The <term.h> header provides a declaration for the following object: *cur_term*. It represents the current terminal record from the terminfo database that the application has selected by calling set_curterm().

The <term.h> header contains the variable names listed in the Variable column.

The following are declared as functions, and may also be defined as macros:

```
del_curterm(TERMINAL *);
          putp(const char *);
int
          restartterm(char *,
int
                                      int, int *);
TERMINAL *set_curterm(TERMINAL *);
        setupterm(char *, int, int *);
int
          tgetent(char *, const char);
int
int tgetflag(char *);
int tgetnum(char *);
char *tgetstr(char *, char **);
char *tgoto(char *, int, int);
          tigetflag(char *);
int
         tigetnum(char *);
int
char *tigetstr(char *);
char *tparm(char *, long, long, long, long, long, long, long, long, long);
int tputs(const char *, int, int (*)(int));
```

#### See Also

printf(), putp(), tigetflag(), tgetent(), <curses.h>.

# <unctrlh>

#### Name

unctrl.h - definitions for unctrl()

# **Description**

The <unctrl.h> header defines the chtype type as defined in <curses.h>.

The following is declared as a function, and may also be defined as a macro:

char *unctrl(chtype);

# See Also

unctrl(), <curses.h>.

# **CURSES**

# **Chapter 7. Terminfo Source Format (ENHANCED CURSES)**

The **terminfo** database contains a description of the capabilities of a variety of devices, such as terminals and printers. Devices are described by specifying a set of capabilities, by quantifying certain aspects of the device, and by specifying character sequences that effect particular results.

This chapter specifies the format of **terminfo** source files.

X/Open-compliant implementations provide a facility that accepts source files in the format specified in this chapter as a means of entering information into the **terminfo** database. The facility for installing this information into the database is implementation-specific. A valid **terminfo** entry describing a given model of terminal can be added to **terminfo** on any X/Open-compliant implementation to permit use of the same terminal model.

The **terminfo** database is often used by screen-oriented applications such as **vi** and Curses programs, as well as by some utilities such as **ls** and **more**. This usage allows them to work with a variety of devices without changes to the programs.

# **Source File Syntax**

Source files can use the ISO 8859-1 codeset. The behavior when the source file is in another codeset is unspecified. Traditional practice has been to translate information from other codesets into the source file syntax.

**terminfo** source files consist of one or more device descriptions. Each description defines a mnemonic name for the terminal model. Each description consists of a header (beginning in column 1) and one or more lines that list the features for that particular device. Every line in a **terminfo** source file must end in a comma. Every line in a **terminfo** source file except the header must be indented with one or more white spaces (either spaces or tabs).

Entries in **terminfo** source files consist of a number of comma-separated fields. White space after each comma is ignored. Embedded commas must be escaped by using a backslash. The following example shows the format of a **terminfo** source file:

```
alias1 | alias2 | ... | aliasn | longname,
<white space> am, lines #24,
<white space> home=\Eeh,
```

The first line, commonly referred to as the header line, must begin in column one and must contain at least two aliases separated by vertical bars. The last field in the header line must be the long name of the device and it may contain any string.

Alias names must be unique in the **terminfo** database and they must conform to file naming conventions established by implementation-specific **terminfo** compilation utilities. Implementations will recognize alias names consisting only of characters from the portable filename character set except that implementations need not accept a first character of minus(-). For example, a typical restriction is that they cannot contain white space or slashes. There may be further constraints imposed on source file values by the implementation-specific **terminfo** compilation utilities.

Each capability in **terminfo** is of one of the following types:

- Boolean capabilities show that a device has or does not have a particular feature.
- Numeric capabilities quantify particular features of a device.
- String capabilities provide sequences that can be used to perform particular operations on devices.

Capability names adhere to an informal length limit of five characters. Whenever possible, capability names are chosen to be the same as or similar to those specified by the ANSI X3.64-1979 standard. Semantics are also intended to match those of the ANSI standard.

All string capabilities may have padding specified, with the exception of those used for input. Input capabilities, listed under the **Strings** section in the following tables, have names beginning with **key**. These capabilities are defined in **<term.h>**.

#### **Minimum Guaranteed Limits**

All X/Open-compliant implementations support at least the following limits for the terminfo source file:

Source File Characteristic	Minimum Guaranteed Value
Length of a line	1023 bytes
Length of a terminal alias	14 bytes
Length of a terminal model name	128 bytes
Width of a single field	128 bytes
Length of a string value	1000 bytes
Length of a string representing a numeric value	99 digits
Magnitude of a numeric value	0 up to and including 32767

An implementation may support higher limits than those specified above.

#### **Formal Grammar**

The grammar and lexical conventions in this section together describe the syntax for **terminfo** terminal descriptions within a terminfo source file. A terminal description that satisfies the requirements of this section will be accepted by all implementations.

```
descriptions : START_OF_HEADER_LINE4 rest_of_header_line feature_lines
| descriptions START_OF_HEADER_LINE rest_of_header_line
| feature_lines
 feature_lines : start_feature_line rest_of_feature_line
          | feature_lines start_feature_line rest_of_feature_line
start_feature_line : START_FEATURE_LINE_BOOLEAN<sup>5</sup>
 START_FEATURE_LINE_NUMERIC6
 START_FEATURE_LINE_STRING<sup>7</sup>
 rest_of_feature_line : features COMMA NEWLINE
         | COMMA NEWLINE
 features : COMMA feature
         | features COMMA feature
 aliases : PIPE ALIAS
         | aliases PIPE ALIAS
 feature : BOOLEAN
   | NUMERIC
```

| STRING

The lexical conventions for **terminfo** descriptions are as follows:

- 1. White space consists of the '' and <tab> character.
- 2. An ALIAS may contain any graph 8 characters other than ',',' and '|'.
- 3. A LONGNAME may contain any print 9 characters other than ',' and '|'.
- 4. A BOOLEAN feature may contain any print characters other than ',', '=', and '#'.
- 5. A NUMERIC feature consists of:
  - a. A name which may contain any print character other than ',', '=', and '#'.
  - b. The '#' character.
  - c. A positive integer which conforms to the C language convention for integer constants.
- 6. A STRING feature consists of:
  - a. A name which may contain any print character other than ',' '=', and '#'.
  - b. The '=' character.
  - c. A string which may contain any print characters other than ';'.
- 7. White space immediately following a ',' is ignored.
- 8. Comments consist of <bol>, optional whitespace, a required '#', and a terminating <eol>.
- 9. A header line must begin in column one.
- 10. A feature line must not begin in column one.
- 11. Blank lines are ignored.

# **Defined Capabilities**

X/Open defines the capabilities listed in the following table. All X/Open-compliant implementations must accept each of these capabilities in an entry in a **terminfo** source file. Implementations use this information to determine how properly to operate the current terminal. In addition, implementations return any of the current terminal's capabilities when the application calls the query functions listed in *tgetent()*.

The table of capabilities has the following columns:

#### Variable

Names for use by the Curses functions that operate on the **terminfo** database. These names are reserved and the application must not define them.

#### Capname

The short name for a capability specified in the **terminfo** source file. It is used for updating the source file and by the *tput* command.

#### Termcap

Codes provided for compatibility with older applications. These codes are **TO BE WITHDRAWN**. Because of this, not all **Capnames** have **Termcap** codes.

⁴ An ALIAS that begins in column one. This is handled by the lexical analyzer.

⁵ A BOOLEAN feature that begins after column one but is the first feature on the feature line. This is handled by the lexical analyzer.

⁶ A NUMERIC feature that begins after column one but is the first feature on the feature line. This is handled by the lexical analyzer.

A STRING feature that begins after column one but is the first feature on the feature line. This is handled by the lexical analyzer.

⁸ Graph characters are those characters for which *isgraph()* returns non-zero.

⁹ Print characters are those characters for which *isprint()* returns non-zero.

# **Booleans**

Variable	Capname	Termcap	Description
auto_left_margin	bw	bw	<b>cub1</b> wraps from column 0 to last column
auto_right_margin	am	am	Terminal has automatic margins
back_color_erase	bce	ut	Screen erased with background color
can_change	ссс	СС	Terminal can re-define existing color
ceol_standout_glitch	xhp	XS	Standout not erased by overwriting (hp)
col_addr_glitch	xhpa	YA	Only positive motion for <b>hpa/mhpa</b> caps
cpi_changes_res	сріх	YF	Changing character pitch changes resolution
cr_cancels_micro_mode	crxm	YB	Using <b>cr</b> turns off micro mode
dest_tabs_magic_smso	xt	xt	Destructive tabs, magic <b>smso</b> char (t1061)
eat_newline_glitch	xenl	xn	Newline ignored after 80 columns (Concept)
erase_overstrike	eo	eo	Can erase overstrikes with a blank
generic_type	gn	gn	Generic line type (e.g., dialup, switch)
hard_copy	hc	hc	Hardcopy terminal
hard_cursor	chts	HC	Cursor is hard to see
has_meta_key	km	km	Has a meta key (shift, sets parity bit)
has_print_wheel	daisy	YC	Printer needs operator to change character set
has_status_line	hs	hs	Has extra "status line"
hue_lightness_saturation	hls	hl	Terminal uses only HLS color notation (Tektronix)
<pre>insert_null_glitch</pre>	in	in	Insert mode distinguishes nulls
lpi_changes_res	lpix	YG	Changing line pitch changes resolution
memory_above	da	da	Display may be retained above the screen
memory_below	db	db	Display may be retained below the screen
move_insert_mode	mir	mi	Safe to move while in insert mode
move_standout_mode	msgr	ms	Safe to move in standout modes
needs_xon_xoff	nxon	nx	Padding won't work, xon/xoff required
no_esc_ctlc	xsb	xb	Beehive (f1=escape, f2=ctrl C)
no_pad_char	npc	NP	Pad character doesn't exist
non_dest_scroll_region	ndscr	ND	Scrolling region is nondestructive
non_rev_rmcup	nrrmc	NR	smcup does not reverse rmcup

Variable	Capname	Termcap	Description
over_strike	os	os	Terminal overstrikes on hard-copy terminal
prtr_silent	mc5i	5i	Printer won't echo on screen
row_addr_glitch	xvpa	YD	Only positive motion for <b>vpa/mvpa</b> caps
semi_auto_right_margin	sam	YE	Printing in last column causes <b>cr</b>
status_line_esc_ok	eslok	es	Escape can be used on the status line
tilde_glitch	hz	hz	Hazeltine; can't print tilde (˜)
transparent_underline	ul	ul	Underline character overstrikes
xon_xoff	xon	хо	Terminal uses xon/xoff handshaking

# **Numbers**

Variable	Capname	Termcap	Description
bit_image_entwining	bitwin	Yo	Number of passes for each bit-map row
bit_image_type	bitype	Yp	Type of bit image device
buffer_capacity	bufsz	Ya	Number of bytes buffered before printing
buttons	btns	ВТ	Number of buttons on the mouse
columns	cols	СО	Number of columns in a line
dot_horz_spacing	spinh	Yc	Spacing of dots horizontally in dots per inch
dot_vert_spacing	spinv	Yb	Spacing of pins vertically in pins per inch
init_tabs	it	it	Tabs initially every # spaces
label_height	lh	lh	Number of rows in each label
label_width	lw	lw	Number of columns in each label
lines	lines	li	Number of lines on a screen or a page
lines_of_memory	lm	lm	Lines of memory if > <b>lines;</b> 0 means varies
max_attributes	ma	ma	Maximum combined video attributes terminal can display
magic_cookie_glitch	xmc	sg	Number of blank characters left by <b>smso</b> or <b>rmso</b>
max_colors	colors	Co	Maximum number of colors on the screen
max_micro_address	maddr	Yd	Maximum value in microaddress
max_micro_jump	mjump	Ye	Maximum value in <b>parmmicro</b>
max_pairs	pairs	pa	Maximum number of color-pairs on the screen
maximum_windows	wnum	MW	Maximum number of definable windows
micro_col_size	mcs	Yf	Character step size when in micro mode
micro_line_size	mls	Yg	Line step size when in micro mode
no_color_video	ncv	NC	Video attributes that can't be used with colors

Variable	Capname	Termcap	Description
num_labels	nlab	Nl	Number of labels on screen (start at 1)
number_of_pins	npins	Yh	Number of pins in print-head
output_res_char	orc	Yi	Horizontal resolution in units per character
output_res_line	orl	Υj	Vertical resolution in units per line
output_res_horz_inch	orhi	Yk	Horizontal resolution in units per inch
output_res_vert_inch	orvi	Yl	Vertical resolution in units per inch
padding_baud_rate	pb	pb	Lowest baud rate where padding needed
print_rate	cps	Ym	Print rate in characters per second
virtual_terminal	vt	vt	Virtual terminal number
wide_char_size	widcs	Yn	Character step size when in double-wide mode
width_status_line	wsl	WS	Number of columns in status line

# Strings

Variable	Capname	Termcap	Description
acs_chars	acsc	ac	Graphic charset pairs aAbBcC
alt_scancode_esc	scesa	S8	Alternate escape for scancode emulation (default is for VT100)
back_tab	cbt	bt	Back tab
bell	bel	bl	Audible signal (bell)
<pre>bit_image_carriage_retur n</pre>	bicr	Yv	Move to beginning of same row
bit_image_newline	binel	Zz	Move to next row of the bit image
bit_image_repeat	birep	Xy	Repeat bit-image cell #1 #2 times
carriage_return	cr	cr	Carriage return
change_char_pitch	срі	ZA	Change number of characters per inch
change_line_pitch	lpi	ZB	Change number of lines per inch
change_res_horz	chr	ZC	Change horizontal resolution
change_res_vert	cvr	ZD	Change vertical resolution
change_scroll_region	csr	cs	Change to lines #1 through #2 (VT100)
char_padding	rmp	rP	Like <b>ip</b> but when in replace mode
char_set_names	csnm	Zy	Returns a list of character set names
clear_all_tabs	tbc	ct	Clear all tab stops
clear_margins	mgc	MC	Clear all margins (top, bottom, and sides)
clear_screen	clear	cl	Clear screen and home cursor
clr_bol	el1	cb	Clear to beginning of line, inclusive
clr_eol	el	ce	Clear to end of line

Variable	Capname	Termcap	Description
clr_eos	ed	cd	Clear to end of display
code_set_init	csin	ci	Init sequence for multiple codesets
color_names	colornm	Yw	Give name for color #1
column_address	hpa	ch	Set horizontal position to absolute #1
command_character	cmdch	CC	Terminal settable cmd character in prototype
create_window	cwin	CW	Define win #1 to go from #2,#3 to #4,#5
cursor_address	cup	cm	Move to row #1 col #2
cursor_down	cud1	do	Down one line
cursor_home	home	ho	Home cursor (if no <b>cup</b> )
cursor_invisible	civis	vi	Make cursor invisible
cursor_left	cub1	le	Move left one space.
cursor_mem_address	mrcup	CM	Memory relative cursor addressing
cursor_normal	cnorm	ve	Make cursor appear normal (undo <b>vs/vi</b> )
cursor_right	cuf1	nd	Non-destructive space (cursor or carriage right)
cursor_to_ll	u	11	Last line, first column (if no <b>cup</b> )
cursor_up	cuu1	up	Upline (cursor up)
cursor_visible	cvvis	VS	Make cursor very visible
define_bit_image_region	defbi	Yx	Define rectangular bit-image region
define_char	defc	ZE	Define a character in a character set
delete_character	dch1	dc	Delete character
delete_line	dl1	dl	Delete line
device_type	devt	dv	Indicate language/codeset support
dial_phone	dial	DI	Dial phone number #1
dis_status_line	dsl	ds	Disable status line
display_clock	dclk	DK	Display time-of-day clock
display_pc_char	dispc	S1	Display PC character
down_half_line	hd	hd	Half-line down (forward 1/2 linefeed)
ena_acs	enacs	eA	Enable alternate character set
end_bit_image_region	endbi	Yy	End a bit-image region
<pre>enter_alt_charset_mode</pre>	smacs	as	Start alternate character set
enter_am_mode	smam	SA	Turn on automatic margins
enter_blink_mode	blink	mb	Turn on blinking
enter_bold_mode	bold	md	Turn on bold (extra bright) mode
enter_ca_mode	smcup	ti	String to begin programs that use cup
enter_delete_mode	smdc	dm	Delete mode (enter)

Variable	Capname	Termcap	Description
enter_dim_mode	dim	mh	Turn on half-bright mode
<pre>enter_doublewide_mode</pre>	swidm	ZF	Enable double wide printing
<pre>enter_draft_quality</pre>	sdrfq	ZG	Set draft quality print
<pre>enter_horizontal_hl_mode</pre>	ehhlm		Turn on horizontal highlight mode
enter_insert_mode	smir	im	Insert mode (enter)
<pre>enter_italics_mode</pre>	sitm	ZH	Enable italics
<pre>enter_left_hl_mode</pre>	elhlm		Turn on left highlight mode
<pre>enter_leftward_mode</pre>	slm	ZI	Enable leftward carriage motion
<pre>enter_low_hl_mode</pre>	elohlm		Turn on low highlight mode
enter_micro_mode	smicm	ZJ	Enable micro motion capabilities
<pre>enter_near_letter_qualit y</pre>	snlq	ZK	Set near-letter quality print
<pre>enter_normal_quality</pre>	snrmq	ZL	Set normal quality print
<pre>enter_pc_charset_mode</pre>	smpch	S2	Enter PC character display mode
<pre>enter_protected_mode</pre>	prot	mp	Turn on protected mode
enter_reverse_mode	rev	mr	Turn on reverse video mode
enter_right_hl_mode	erhlm		Turn on right highlight mode
enter_scancode_mode	smsc	S4	Enter PC scancode mode
enter_secure_mode	invis	mk	Turn on blank mode (characters invisible)
enter_shadow_mode	sshm	ZM	Enable shadow printing
enter_standout_mode	smso	S0	Begin standout mode
<pre>enter_subscript_mode</pre>	ssubm	ZN	Enable subscript printing
<pre>enter_superscript_mode</pre>	ssupm	ZO	Enable superscript printing
<pre>enter_top_hl_mode</pre>	ethlm		Turn on top highlight mode
<pre>enter_underline_mode</pre>	smul	us	Start underscore mode
enter_upward_mode	sum	ZP	Enable upward carriage motion
<pre>enter_vertical_hl_mode</pre>	evhlm		Turn on vertical highlight mode
enter_xon_mode	smxon	SX	Turn on xon/xoff handshaking
erase_chars	ech	ec	Erase #1 characters
exit_alt_charset_mode	rmacs	ae	End alternate character set
exit_am_mode	rmam	RA	Turn off automatic margins
exit_attribute_mode	sgr0	me	Turn off all attributes
exit_ca_mode	rmcup	te	String to end programs that use <b>cup</b>
exit_delete_mode	rmdc	ed	End delete mode
exit_doublewide_mode	rwidm	ZQ	Disable double wide printing
exit_insert_mode	rmir	ei	End insert mode
exit_italics_mode	ritm	ZR	Disable italics

Variable	Capname	Termcap	Description
exit_leftward_mode	rlm	ZS	Enable rightward (normal) carriage motion
exit_micro_mode	rmicm	ZT	Disable micro motion capabilities
exit_pc_charset_mode	rmpch	S3	Disable PC character display mode
exit_scancode_mode	rmsc	S5	Disable PC scancode mode
exit_shadow_mode	rshm	ZU	Disable shadow printing
exit_standout_mode	rmso	se	End standout mode
exit_subscript_mode	rsubm	ZV	Disable subscript printing
exit_superscript_mode	rsupm	ZW	Disable superscript printing
exit_underline_mode	rmul	ue	End underscore mode
exit_upward_mode	rum	ZX	Enable downward (normal) carriage motion
exit_xon_mode	rmxon	RX	Turn off xon/xoff handshaking
fixed_pause	pause	PA	Pause for 2-3 seconds
flash_hook	hook	fh	Flash the switch hook
flash_screen	flash	vb	Visible bell (may move cursor)
form_feed	ff	ff	Hardcopy terminal page eject
from_status_line	fsl	fs	Return from status line
get_mouse	getm	Gm	Curses should get button events
goto_window	wingo	WG	Go to window #1
hangup	hup	HU	Hang-up phone
init_1string	is1	i1	Terminal or printer initialization string
init_2string	is2	is	Terminal or printer initialization string
init_3string	is3	i3	Terminal or printer initialization string
init_file	if	if	Name of initialization file
init_prog	iprog	iP	Path name of program for initialization
initialize_color	initc	IC	Set color #1 to RGB #2, #3, #4
initialize_pair	initp	Ip	Set color-pair #1 to fg #2, bg #3
insert_character	ich1	ic	Insert character
insert_line	il1	al	Add new blank line
insert_padding	ip	ip	Insert pad after character inserted

**Note:** The "**key_**" strings are sent by specific keys. The "**key_**" descriptions include the macro, defined in **<curses.h>**, for the code returned by *getch()* when the key is pressed (see *getch()*).

key_a1	ka1	K1	upper left of keypad
key_a3	ka3	К3	upper right of keypad
key_b2	kb2	K2	center of keypad
key_backspace	kbs	kb	sent by backspace key
key_beg	kbeg	@1	sent by beg(inning) key

Variable	Capname	Termcap	Description
key_btab	kcbt	kB	sent by back-tab key
key_c1	kc1	K4	lower left of keypad
key_c3	kc3	K5	lower right of keypad
key_cancel	kcan	@2	sent by cancel key
key_catab	ktbc	ka	sent by clear-all-tabs key
key_clear	kclr	kC	sent by clear-screen or erase key
key_close	kclo	03	sent by close key
key_command	kcmd	<b>@</b> 4	sent by cmd (command) key
key_copy	kcpy	<b>@</b> 5	sent by copy key
key_create	kcrt	<b>@</b> 6	sent by create key
key_ctab	kctab	kt	sent by clear-tab key
key_dc	kdch1	kD	sent by delete-character key
key_dl	kdl1	kL	sent by delete-line key
key_down	kcud1	kd	sent by terminal down-arrow key
key_eic	krmir	kM	sent by <b>rmir</b> or <b>smir</b> in insert mode
key_end	kend	<b>@7</b>	sent by end key
key_enter	kent	89	sent by enter/send key
key_eol	kel	kE	sent by clear-to-end-of-line key
key_eos	ked	kS	sent by clear-to-end-of-screen key
key_exit	kext	@9	sent by exit key
key_f0	kf0	k0	sent by function key f0
key_f1	kf1	k1	sent by function key f1
÷	:	• •	<b>:</b>
key_f62	kf62	Fq	sent by function key f62
key_f63	kf63	Fr	sent by function key f63
key_find	kfnd	00	sent by find key
key_help	khlp	%1	sent by help key
key_home	khome	kh	sent by home key
key_ic	kich1	kI	sent by ins-char/enter ins-mode key
key_il	kil1	kA	sent by insert-line key
key_left	kcub1	kl	sent by terminal left-arrow key
key_ll	kll	kH	sent by home-down key
key_mark	kmrk	%2	sent by mark key
key_message	kmsg	%3	sent by message key
key_mouse	kmous	Km	0631, Mouse event has occurred
key_move	kmov	%4	sent by move key
key_next	knxt	%5	sent by next-object key

Variable	Capname	Termcap	Description
key_npage	knp	kN	sent by next-page key
key_open	kopn	%6	sent by open key
key_options	kopt	%7	sent by options key
key_ppage	kpp	kP	sent by previous-page key
key_previous	kprv	%8	sent by previous-object key
key_print	kprt	%9	sent by print or copy key
key_redo	krdo	<b>%0</b>	sent by redo key
key_reference	kref	&1	sent by ref(erence) key
key_refresh	krfr	&2	sent by refresh key
key_replace	krpl	83	sent by replace key
key_restart	krst	&4	sent by restart key
key_resume	kres	&5	sent by resume key
key_right	kcuf1	kr	sent by terminal right-arrow key
key_save	ksav	&6	sent by save key
key_sbeg	kBEG	&9	sent by shifted beginning key
key_scancel	kCAN	0.3	sent by shifted cancel key
key_scommand	kCMD	*1	sent by shifted command key
key_scopy	kCPY	*2	sent by shifted copy key
key_screate	kCRT	*3	sent by shifted create key
key_sdc	kDC	*4	sent by shifted delete-char key
key_sdl	kDL	<b>*</b> 5	sent by shifted delete-line key
key_select	kslt	*6	sent by select key
key_send	kEND	<b>*</b> 7	sent by shifted end key
key_seol	kEOL	*8	sent by shifted clear-line key
key_sexit	kEXT	<b>*</b> 9	sent by shifted exit key
key_sf	kind	kF	sent by scroll-forward/down key
key_sfind	kFND	<b>*</b> 0	sent by shifted find key
key_shelp	kHLP	#1	sent by shifted help key
key_shome	kHOM	<b>#2</b>	sent by shifted home key
key_sic	kIC	<b>#</b> 3	sent by shifted input key
key_sleft	kLFT	#4	sent by shifted left-arrow key
key_smessage	kMSG	%a	sent by shifted message key
key_smove	kMOV	%b	sent by shifted move key
key_snext	kNXT	%c	sent by shifted next key
key_soptions	kOPT	%d	sent by shifted options key
key_sprevious	kPRV	%e	sent by shifted prev key
key_sprint	<b>kPRT</b>	%f	sent by shifted print key

Variable	Capname	Termcap	Description
key_sr	kri	kR	sent by scroll-backward/up key
key_sredo	kRDO	%g	sent by shifted redo key
key_sreplace	kRPL	%h	sent by shifted replace key
key_sright	kRIT	%i	sent by shifted right-arrow key
key_srsume	kRES	%j	sent by shifted resume key
key_ssave	kSAV	!1	sent by shifted save key
key_ssuspend	kSPD	!2	sent by shifted suspend key
key_stab	khts	kT	sent by set-tab key
key_sundo	kUND	!3	sent by shifted undo key
key_suspend	kspd	&7	sent by suspend key
key_undo	kund	83	sent by undo key
key_up	kcuu1	ku	sent by terminal up-arrow key
keypad_local	rmkx	ke	Out of "keypad-transmit" mode
keypad_xmit	smkx	ks	Put terminal in "keypad-transmit" mode
lab_f0	lf0	10	Labels on function key f0 if not f0
lab_f1	lf1	11	Labels on function key f1 if not f1
lab_f2	lf2	12	Labels on function key f2 if not f2
lab_f3	lf3	13	Labels on function key f3 if not f3
lab_f4	lf4	14	Labels on function key f4 if not f4
lab_f5	lf5	15	Labels on function key f5 if not f5
lab_f6	lf6	16	Labels on function key f6 if not f6
lab_f7	lf7	17	Labels on function key f7 if not f7
lab_f8	lf8	18	Labels on function key f8 if not f8
lab_f9	lf9	19	Labels on function key f9 if not f9
lab_f10	lf10	la	Labels on function key f10 if not f10
label_format	fln	Lf	Label format
label_off	rmln	LF	Turn off soft labels
label_on	smln	L0	Turn on soft labels
meta_off	rmm	mo	Turn off "meta mode"
meta_on	smm	mm	Turn on "meta mode" (8th bit)
micro_column_address	mhpa	ZY	Like <b>column_address</b> for micro adjustment
micro_down	mcud1	ZZ	Like <b>cursor_down</b> for micro adjustment
micro_left	mcub1	Za	Like <b>cursor_left</b> for micro adjustment
micro_right	mcuf1	Zb	Like <b>cursor_right</b> for micro adjustment
micro_row_address	mvpa	Zc	Like <b>row_address</b> for micro adjustment
micro_up	mcuu1	Zd	Like <b>cursor_up</b> for micro adjustment

Variable	Capname	Termcap	Description
mouse_info	minfo	Mi	Mouse status information
newline	nel	nw	Newline (behaves like cr followed by lf)
order_of_pins	porder	Ze	Matches software bits to print-head pins
orig_colors	ос	ос	Set all color(-pair)s to the original ones
orig_pair	ор	ор	Set default color-pair to the original one
pad_char	pad	рс	Pad character (rather than null)
parm_dch	dch	DC	Delete #1 chars
parm_delete_line	dl	DL	Delete #1 lines
parm_down_cursor	cud	DO	Move down #1 lines.
parm_down_micro	mcud	Zf	Like <b>parm_down_cursor</b> for micro adjust.
parm_ich	ich	IC	Insert #1 blank chars
parm_index	indn	SF	Scroll forward #1 lines.
parm_insert_line	il	AL	Add #1 new blank lines
parm_left_cursor	cub	LE	Move cursor left #1 spaces
parm_left_micro	mcub	Zg	Like <b>parm_left_cursor</b> for micro adjust.
parm_right_cursor	cuf	RI	Move right #1 spaces.
parm_right_micro	mcuf	Zh	Like <b>parm_right_cursor</b> for micro adjust.
parm_rindex	rin	SR	Scroll backward #1 lines.
parm_up_cursor	cuu	UP	Move cursor up #1 lines.
parm_up_micro	mcuu	Zi	Like <b>parm_up_cursor</b> for micro adjust.
<pre>pc_term_options</pre>	pctrm	S6	PC terminal options
pkey_key	pfkey	pk	Prog funct key #1 to type string #2
pkey_local	pfloc	pl	Prog funct key #1 to execute string #2
pkey_plab	pfxl	xl	Prog key #1 to xmit string #2 and show string #3
pkey_xmit	pfx	px	Prog funct key #1 to xmit string #2
plab_norm	pln	pn	Prog label #1 to show string #2
print_screen	mc0	ps	Print contents of the screen
prtr_non	тс5р	p0	Turn on the printer for #1 bytes
prtr_off	mc4	pf	Turn off the printer
prtr_on	mc5	ро	Turn on the printer
pulse	pulse	PU	Select pulse dialing
quick_dial	qdial	QD	Dial phone number #1, without progress detection
remove_clock	rmclk	RC	Remove time-of-day clock

Variable	Capname	Termcap	Description
repeat_char	rep	rp	Repeat char #1 #2 times
req_for_input	rfi	RF	Send next input char (for ptys)
req_mouse_pos	reqmp	RQ	Request mouse position report
reset_1string	rs1	r1	Reset terminal completely to sane modes
reset_2string	rs2	r2	Reset terminal completely to sane modes
reset_3string	rs3	r3	Reset terminal completely to sane modes
reset_file	rf	rf	Name of file containing reset string
restore_cursor	rc	rc	Restore cursor to position of last sc
row_address	vpa	CV	Set vertical position to absolute #1
save_cursor	sc	sc	Save cursor position
scancode_escape	scesc	S7	Escape for scancode emulation
scroll_forward	ind	sf	Scroll text up
scroll_reverse	ri	sr	Scroll text down
select_char_set	scs	Zj	Select character set
set0_des_seq	s0ds	s0	Shift into codeset 0 (EUC set 0, ASCII)
set1_des_seq	s1ds	s1	Shift into codeset 1
set2_des_seq	s2ds	s2	Shift into codeset 2
set3_des_seq	s3ds	s3	Shift into codeset 3
set_a_attributes	sgr1		Define second set of video attributes #1-#6
set_a_background	setab	AB	Set background color to #1 using ANSI escape
set_a_foreground	setaf	AF	Set foreground color to #1 using ANSI escape
set_attributes	sgr	sa	Define first set of video attributes #1-#9
set_background	setb	Sb	Set background color to #1
set_bottom_margin	smgb	Zk	Set bottom margin at current line
set_bottom_margin_parm	smgbp	Z1	Set bottom margin at line #1 or #2 lines from bottom
set_clock	sclk	SC	Set clock to hours (#1), minutes (#2), seconds (#3)
set_color_band	setcolor	Yz	Change to ribbon color #1
set_color_pair	scp	sp	Set current color pair to #1
set_foreground	setf	Sf	Set foreground color to #1
set_left_margin	smgl	ML	Set left margin at current column
set_left_margin_parm	smglp	Zm	Set left (right) margin at column #1 (#2)

Variable	Capname	Termcap	Description
set_lr_margin	smglr	ML	Sets both left and right margins
set_page_length	slines	YZ	Set page length to #1 lines
set_pglen_inch	slength	YI	Set page length to #1 hundredth of an inch
set_right_margin	smgr	MR	Set right margin at current column
set_right_margin_parm	smgrp	Zn	Set right margin at column #1
set_tab	hts	st	Set a tab in all rows, current column
set_tb_margin	smgtb	MT	Sets both top and bottom margins
set_top_margin	smgt	Zo	Set top margin at current line
set_top_margin_parm	smgtp	Zp	Set top (bottom) margin at line #1 (#2)
set_window	wind	wi	Current window is lines #1-#2 cols #3-#4
start_bit_image	sbim	Zq	Start printing bit image graphics
start_char_set_def	scsd	Zr	Start definition of a character set
stop_bit_image	rbim	Zs	End printing bit image graphics
stop_char_set_def	rcsd	Zt	End definition of a character set
subscript_characters	subcs	Zu	List of "subscript-able" characters
superscript_characters	supcs	Zv	List of "superscript-able" characters
tab	ht	ta	Tab to next 8-space hardware tab stop
these_cause_cr	docr	Zw	Printing any of these chars causes <b>cr</b>
to_status_line	tsl	ts	Go to status line, col #1
tone	tone	T0	Select touch tone dialing
user0	u0	u0	User string 0
user1	u1	u1	User string 1
user2	u2	u2	User string 2
user3	u3	u3	User string 3
user4	u4	u4	User string 4
user5	u5	u5	User string 5
user6	u6	u6	User string 6
user7	u7	u7	User string 7
user8	u8	u8	User string 8
user9	u9	u9	User string 9
underline_char	uc	uc	Underscore one char and move past it
up_half_line	hu	hu	Half-line up (reverse 1/2 linefeed)
wait_tone	wait	WA	Wait for dial tone
xoff_character	xoffc	XF	X-off character
xon_character	xonc	XN	X-on character

Variable	Capname	Termcap	Description
zero_motion	zerom	Zx	No motion for the subsequent character

#### **Sample Entry**

The following entry describes the AT&T; 610 terminal.

```
610|610bct|ATT610|att610|AT&T610;80column;98key; keyboard,
    am, eslok, hs, mir, msgr, xenl, xon,
    cols#80, it#8, lh#2, lines#24, lw#8, nlab#8, wsl#80,
    acsc='asfggjjkkllmmnncoppqqrssttuuvvwxxyyzz{{||}}˜˜,
    bel=G, blink=\E[5m, bold=\E[1m, cbt=\E[Z,
        civis=\E[25], clear=\E[H\E[J, cnorm=\E[25h\E[121,
        cr=\r, csr=\E[%i%pl%d;%p2%dr, cub=\E[%p1%dD, cub1=\b,
        cud=\E[%p1%dB, cud1=\E[B, cuf=\E[%p1%dA, cud1=\E[C,
        cup=\E[%p1%dA, cud2, cuf=\E[%p1%dA, cud1=\E[A,
        cvvis=\E[12;25h, dch=\E[%p1%dA, cud1=\E[A,
        cvvis=\E[12;25h, dch=\E[%p1%dA, cud1=\E[A,
        cvvis=\E[12;25h, dch=\E[%p1%dA, cud1=\E[A,
        cvvis=\E[12;25h, dch=\E[%p1%dA, cud1=\E[A,
        cvvis=\E[18]%dM, dl1=\E[M, ed=\E[J, el=\E[K, el1=\E[1K,
        flash=\E[5h$<200>\E[5l, fs1=\E8, nome=\E(H, ht=\t),
        ind=\EB,0 ind=\EB,0 ind=\EB,0 ind=\EB,0 invis=\E[8m,
        is1=\E[8]0 i=\E[3:4;5:13;151\E[13;201\E[7h\E[12h\E(B\E)0,
        is2=\E[6m, o, is3=\E(B\E)0, kLFT=\E[\s,0, kRTT=\E[\s,0, kud1=\E[B,
        kcuf1=\E[C, kcud1=\E[A, kfP=\E0c, kfP0=\E0c, kfP0=\EB,
        kfB=\E0c, kf2=\E0f, kf(CW=\E0g, kf6=\E0h, kf7=\E0i,
        kf8=\E0j, kf9=\EN, kfP3=\EN, kfP3=\EN, kfP1=\E1,
        l1=\E[2d, mcd=\E[4i, mc5=\E[5i, ne1=\EE,
        pfx1=\E[\B]1\Bd, prace=\E1, rm=\E[7m,
        ri=\EM, rmacs=\0, rmir=\E[41, rm1n=\E[2p, rmso=\E[m,
        rmu]=\E[m, rs2=\EC[61], sc=\E7,
        sgr=\E[\B]0, smso=\E[m,
        rmu]=\E[m, sms=\E[4m, st]=\E7\E[25; %i%p1%dx,
```

# Types of Capabilities in the Sample Entry

The sample entry shows the formats for the three types of **terminfo** capabilities: Boolean, numeric, and string. All capabilities specified in the **terminfo** source file must be followed by commas, including the last capability in the source file. In **terminfo** source files, capabilities are referenced by their capability names (as shown in the **Capname** column of the previous tables).

#### **Boolean Capabilities**

A boolean capability is true if its **Capname** is present in the entry, and false if its **Capname** is not present in the entry.

The '@' character following a Capname is used to explicitly declare that a boolean capability is false.

#### **Numeric Capabilities**

Numeric capabilities are followed by the character '#' and then a positive integer value. The example assigns the value 80 to the **cols** numeric capability by coding:

```
cols#80
```

Values for numeric capabilities may be specified in decimal, octal or hexadecimal, using normal Clanguage conventions.

#### **String Capabilities**

String-valued capabilities such as **el** (clear to end of line sequence) are listed by the **Capname**, an '=', and a string ended by the next occurrence of a comma.

A delay in milliseconds may appear anywhere in such a capability, preceded by \$ and enclosed in angle brackets, as in **el=\EK\$<3>**. The Curses implementation achieves delays by outputting to the terminal an appropriate number of system-defined padding characters. The *tputs()* function provides delays when used to send such a capability to the terminal.

The delay can be any of the following: a number, a number followed by an asterisk, such as **5***, a number followed by a slash, such as **5/**, or a number followed by both, such as **5***/.

- A '*' shows that the required delay is proportional to the number of lines affected by the operation, and the amount given is the delay required per affected unit. (In the case of insert characters, the factor is still the number of lines affected. This is always 1 unless the device has **in** and the software uses it.) When a '*' is specified, it is sometimes useful to give a delay of the form **3.5** to specify a delay per unit to tenths of milliseconds. (Only one decimal place is allowed.)
- A '/' indicates that the delay is mandatory and padding characters are transmitted regardless of the
  setting of xon. If '/' is not specified or if a device has xon defined, the delay information is advisory and
  is only used for cost estimates or when the device is in raw mode. However, any delay specified for bel
  or flash is treated as mandatory.

The following notation is valid in terminfo source files for specifying special characters:

Notation	Represents Character
^ <b>x</b>	Control-x (for any appropriate x)
\a	Alert
/b	Backspace
<b>\E</b> or <b>\e</b>	An ESCAPE character
\f	Form feed
\l	Linefeed
\n	Newline
\ <b>r</b>	Carriage return
\s	Space
\t	Tab
\^	Caret (^)
\\	Backslash (\)
	Comma (,)
\:	Colon (:)
\0	Null
\nnn	Any character, specified as three octal digits

(See the **XBD** specification, **General Terminal Interface**.)

# **Commented-out Capabilities**

Sometimes individual capabilities must be commented out. To do this, put a period before the capability name. For example, see the second **ind** Note that capabilities are defined in a left-to-right order and, therefore, a prior definition will override a later definition.

# **Device Capabilities**

# **Basic Capabilities**

The number of columns on each line for the device is given by the **cols** numeric capability. If the device has a screen, then the number of lines on the screen is given by the **lines** capability. If the device wraps around to the beginning of the next line when it reaches the right margin, then it should have the **am** capability. If the terminal can clear its screen, leaving the cursor in the home position, then this is given by the **clear** string capability. If the terminal overstrikes (rather than clearing a position when a character is struck over) then it should have the **os** capability. If the device is a printing terminal, with no soft copy unit, specify both **hc** and **os**. If there is a way to move the cursor to the left edge of the current row, specify this as **cr**. (Normally this will be carriage return, control-M.) If there is a way to produce an audible signal (such as a bell or a beep), specify it as **bel**. If, like most devices, the device uses the xon-xoff flow-control protocol, specify **xon**.

If there is a way to move the cursor one position to the left (such as backspace), that capability should be given as **cub1**. Similarly, sequences to move to the right, up, and down should be given as **cuf1**, **cuu1**, and **cud1**, respectively. These local cursor motions must not alter the text they pass over; for example, you would not normally use "**cuf1**=\s" because the space would erase the character moved over.

A very important point here is that the local cursor motions encoded in **terminfo** are undefined at the left and top edges of a screen terminal. Programs should never attempt to backspace around the left edge, unless **bw** is specified, and should never attempt to go up locally off the top. To scroll text up, a program goes to the bottom left corner of the screen and sends the **ind** (index) string. To scroll text down, a program goes to the top left corner of the screen and sends the ri (reverse index) string. The strings **ind** and **ri** are undefined when not on their respective corners of the screen.

Parameterized versions of the scrolling sequences are **indn** and rin. These versions have the same semantics as **ind** and **ri**, except that they take one argument an scroll the number of lines specified by that argument.

They are also undefined except at the appropriate edge of the screen.

The **am** capability tells whether the cursor sticks at the right edge of the screen when text is output, but this does not necessarily apply to a **cuf1** from the last column. Backward motion from the left edge of the screen is possible only when **bw** is specified. In this case, **cub1** will move to the right edge of the previous row. If **bw** is not given, the effect is undefined. This is useful for drawing a box around the edge of the screen, for example. If the device has switch-selectable automatic margins, **am** should be specified in the **terminfo** source file. In this case, initialization strings should turn on this option, if possible. If the device has a command that moves to the first column of the next line, that command can be given as **nel** (newline). It does not matter if the command clears the remainder of the current line, so if the device has no **cr** and If it may still be possible to craft a working **nel** out of one or both of them.

These capabilities suffice to describe hardcopy and screen terminals. Thus the AT&T; 5320 hardcopy terminal is described as follows:

```
5320|att5320|AT&T; 5320 hardcopy terminal,
am, hc, os,
cols#132,
bel=_G, cr=\r, cub1=\b, cnd1=\n,
dch1=\E[P, dl1=\E[M,
ind=\n,
```

while the Lear Siegler ADM-3 is described as

```
adm3|lsi adm3,
am, bel=_G, clear=_Z, cols#80, cr=_M, cub1=_H,
cud1=_J, ind=_J, lines#24,
```

# **Parameterized Strings**

Cursor addressing and other strings requiring arguments are described by a argumentized string capability with escapes in a form (%x) comparable to printf(). For example, to address the cursor, the **cup** capability is given, using two arguments: the row and column to address to. (Rows and columns are numbered from zero and refer to the physical screen visible to the user, not to any unseen memory.) If the terminal has memory relative cursor addressing, that can be indicated by **mrcup**.

The argument mechanism uses a stack and special % codes to manipulate the stack in the manner of Reverse Polish Notation (postfix). Typically a sequence pushes one of the arguments onto the stack and then prints it in some format. Often more complex operations are necessary. Operations are in postfix form with the operands in the usual order. That is, to subtract 5 from the first argument, one would use  $p1\%{5}$ .

The % encodings have the following meanings:

#### %%

Outputs '%'.

### %[[:]flags][width[.precision]][doxXs]

As in printf(); flags are [-+#] and space.

# %с

Print pop() gives %c.

#### %p[1-9]

Push the ith argument.

### %P[a-z]

Set dynamic variable [a-z] to pop().

# %g[a-z]

Get dynamic variable [a-z] and push it.

#### %P[A-Z]

Set static variable [a-z] to pop().

### %g[A-Z]

Get static variable [a-z] and push it.

#### %'c'

Push char constant c.

### %{nn}

Push decimal constant nn.

#### %l

Push strlen(pop()).

# %+ %- %* %/ %m

Arithmetic (%m is mod): push(pop integer2 op pop integer1) where integer1 represents the top of the stack

# **%&; %| %**^

Bit operations: push(pop integer2 op pop integer1)

### %= %> %<

Logical operations: push(pop integer2 op pop integer1)

# %A %0

Logical operations: and, or

# %! %˜

Unary operations: push(op pop())

# %i

(For ANSI terminals) add 1 to the first argument (if one argument present), or first two arguments (if more than one argument present).

### % expr %t thenpart %e elsepart %:

If-then-else, %e elsepart is optional; else-if's are possible ala Algol 68: % c1 %t b1 %e c2 %t b2 %e c3 %t b3 %e c4 %t b4 %e b5%; ci are conditions, bi are bodies.

If the "-" flag is used with "%[doxXs]", then a colon must be placed between the "%" and the "-" to differentiate the flag from the binary "%-" operator. For example: "%:**-16.16s**".

Consider the Hewlett-Packard 2645, which, to get to row 3 and column 12, needs to be sent **\E&a12c03Y** padded for 6 milliseconds. Note that the order of the rows and columns is inverted here, and that the row and column are zero-padded as two digits. Thus its **cup** capability is:

```
cup=\E&a%p2%2;2dc%p1%2.2dY$<6>
```

The Micro-Term ACT-IV needs the current row and column sent preceded by a **^T**, with the row and column simply encoded in binary:

```
cup=_T%p1%c%p2%c
```

Devices that use "%c" need to be able to backspace the cursor (**cub1**), and to move the cursor up one line on the screen (cuu1). This is necessary because it is not always safe to transmit \n, ^D, and \r, as the system may change or discard them. (The library functions dealing with **terminfo** set tty modes so that tabs are never expanded, so \t is safe to send. This turns out to be essential for the Ann Arbor 4080.)

A final example is the LSI ADM-3a, which uses row and column offset by a blank character, thus:

```
cup=\E=%p1%'\s'%+%c%p2%'\s'%+%c
```

After sending "**\E=**", this pushes the first argument, pushes the ASCII value for a space (32), adds them (pushing the sum on the stack in place of the two previous values), and outputs that value as a character. Then the same is done for the second argument. More complex arithmetic is possible using the stack.

### **Cursor Motions**

If the terminal has a fast way to home the cursor (to very upper left corner of screen) then this can be given as **home**; similarly a fast way of getting to the lower left-hand corner can be given as ll; this may involve going up with cuu1 from the home position, but a program should never do this itself (unless ll does) because it can make no assumption about the effect of moving up from the home position. Note that the home position is the same as addressing to (0,0): to the top left corner of the screen, not of memory. (Thus, the **EH** sequence on Hewlett-Packard terminals cannot be used for **home** without losing some of the other features on the terminal.)

If the device has row or column absolute-cursor addressing, these can be given as single argument capabilities **hpa** (horizontal position absolute) and **vpa** (vertical position absolute). Sometimes these are shorter than the more general two-argument sequence (as with the Hewlett-Packard 2645) and can be used in preference to **cup**. If there are argumentized local motions (such as "move n spaces to the right"), these can be given as cud, **cub**, **cuf**, and **cuu** with a single argument indicating how many spaces to move. These are primarily useful if the device does not have **cup**, such as the Tektronix 4025.

If the device needs to be in a special mode when running a program that uses these capabilities, the codes to enter and exit this mode can be given as **smcup** and **rmcup**. This arises, for example, from terminals, such as the Concept, with more than one page of memory. If the device has only memory relative cursor addressing and not screen relative cursor addressing, a one screen-sized window must be fixed into the device for cursor addressing to work properly. This is also used for the Tektronix 4025, where **smcup** sets the command character to be the one used by **terminfo**. If the **rmcup** sequence will not restore the screen after an **smcup** sequence is output (to the state prior to outputting **smcup**), specify **nrrmc**.

### **Area Clears**

If the terminal can clear from the current position to the end of the line, leaving the cursor where it is, this should be given as **el**. If the terminal can clear from the beginning of the line to the current position inclusive, leaving the cursor where it is, this should be given as **el1**. If the terminal can clear from the

current position to the end of the display, then this should be given as **ed**. **ed** is only defined from the first column of a line. (Thus, it can be simulated by a request to delete a large number of lines, if a true **ed** is not available.)

# **Insert/Delete Line**

If the terminal can open a new blank line before the line where the cursor is, this should be given as **il1**; this is done only from the first position of a line. The cursor must then appear on the newly blank line. If the terminal can delete the line which the cursor is on, then this should be given as **dl1**; this is done only from the first position on the line to be deleted. Versions of **il1** and **dl1** which take a single argument and insert or delete that many lines can be given as **il** and **dl**.

If the terminal has a settable destructive scrolling region (like the VT100) the command to set this can be described with the **csr** capability, which takes two arguments: the top and bottom lines of the scrolling region. The cursor position is, alas, undefined after using this command. It is possible to get the effect of insert or delete line using this command - the **sc** and **rc** (save and restore cursor) commands are also useful. Inserting lines at the top or bottom of the screen can also be done using **ri** or **ind** on many terminals without a true insert/delete line, and is often faster even on terminals with those features.

To determine whether a terminal has destructive scrolling regions or non-destructive scrolling regions, create a scrolling region in the middle of the screen, place data on the bottom line of the scrolling region, move the cursor to the top line of the scrolling region, and do a reverse index (ri) followed by a delete line (dl1) or index (ind). If the data that was originally on the bottom line of the scrolling region was restored into the scrolling region by the dl1 or ind, then the terminal has non-destructive scrolling regions. Otherwise, it has destructive scrolling regions. Do not specify csr if the terminal has non-destructive scrolling regions, unless ind, ri, indn, rin, dl, and dl1 all simulate destructive scrolling.

If the terminal has the ability to define a window as part of memory, which all commands affect, it should be given as the argumentized string **wind**. The four arguments are the starting and ending lines in memory and the starting and ending columns in memory, in that order.

If the terminal can retain display memory above, then the **da** capability should be given; if display memory can be retained below, then **db** should be given. These indicate that deleting a line or scrolling a full screen may bring non-blank lines up from below or that scrolling back with **ri** may bring down non-blank lines.

# **Insert/Delete Character**

There are two basic kinds of intelligent terminals with respect to insert/delete character operations which can be described using **terminfo**. The most common insert/delete character operations affect only the characters on the current line and shift characters off the end of the line rigidly. Other terminals, such as the Concept 100 and the Perkin-Elmer Owl, make a distinction between typed and untyped blanks on the screen, shifting upon an insert or delete only to an untyped blank on the screen which is either eliminated, or expanded to two untyped blanks. You can determine the kind of terminal you have by clearing the screen and then typing text separated by cursor motions. Type "**abc def**" using local cursor motions (not spaces) between the **abc** and the **def**. Then position the cursor before the abc and put the terminal in insert mode. If typing characters causes the rest of the line to shift rigidly and characters to fall off the end, then your terminal does not distinguish between blanks and untyped positions. If the **abc** shifts over to the **def** which then move together around the end of the current line and onto the next as you insert, you have the second type of terminal, and should give the capability in, which stands for "insert null." While these are two logically separate attributes (one line versus multiline insert mode, and special treatment of untyped spaces) we have seen no terminals whose insert mode cannot be described with the single attribute.

terminfo can describe both terminals that have an insert mode and terminals which send a simple sequence to open a blank position on the current line. Give as **smir** the sequence to get into insert mode. Give as **rmir** the sequence to leave insert mode. Now give as **ich1** any sequence needed to be sent just before sending the character to be inserted. Most terminals with a true insert mode will not give **ich1**; terminals that send a sequence to open a screen position should give it here. (If your terminal has both, insert mode is usually preferable to **ich1**. Do not give both unless the terminal requires both to be used in combination.) If post-insert padding is needed, give this as a number of milliseconds padding in **ip** (a

string option). Any other sequence which may need to be sent after an insert of a single character may also be given in **ip**. If your terminal needs both to be placed into an "insert mode" and a special code to precede each inserted character, then both **smir/rmir** and **ich1** can be given, and both will be used. The **ich** capability, with one argument, n, will insert n blanks.

If padding is necessary between characters typed while not in insert mode, give this as a number of milliseconds padding in **rmp**.

It is occasionally necessary to move around while in insert mode to delete characters on the same line (for example, if there is a tab after the insertion position). If your terminal allows motion while in insert mode you can give the capability **mir** to speed up inserting in this case. Omitting **mir** will affect only speed. Some terminals (notably Datamedia) must not have **mir** because of the way their insert mode works.

Finally, you can specify **dch1** to delete a single character, dch with one argument, n, to delete n characters, and delete mode by giving **smdc** and **rmdc** to enter and exit delete mode (any mode the terminal needs to be placed in for dch1 to work).

A command to erase n characters (equivalent to outputting n blanks without moving the cursor) can be given as **ech** with one argument.

# Highlighting, Underlining, and Visible Bells

Your device may have one or more kinds of display attributes that allow you to highlight selected characters when they appear on the screen. The following display modes (shown with the names by which they are set) may be available:

- A blinking screen (blink)
- Bold or extra-bright characters (**bold**)
- Dim or half-bright characters (dim)
- Blanking or invisible text (invis)
- Protected text (prot)
- A reverse-video screen (**rev**)
- An alternate character set (**smacs** to enter this mode and **rmacs** to exit it) (If a command is necessary before you can enter alternate character set mode, give the sequence in **enacs** or "enable alternate-character-set" mode.) Turning on any of these modes singly may turn off other modes.

**sgr0** should be used to turn off all video enhancement capabilities. It should always be specified because it represents the only way to turn off some capabilities, such as **dim** or **blink**.

Choose one display method as *standout mode* and use it to highlight error messages and other text to which you want to draw attention. Choose a form of display that provides strong contrast but that is easy on the eyes. (We recommend reverse-video plus half-bright or reverse-video alone.) The sequences to enter and exit standout mode are given as **smso** and **rmso**, respectively. If the code to change into or out of standout mode leaves one or even two blank spaces on the screen, as the TVI 912 and Teleray 1061 do, then **xmc** should be given to tell how many spaces are left.

Sequences to begin underlining and end underlining can be specified as **smul** and **rmul**, respectively. If the device has a sequence to underline the current character and to move the cursor one space to the right (such as the Micro-Term MIME), this sequence can be specified as uc.

Terminals with the "magic cookie" glitch (**xmc**) deposit special "cookies" when they receive mode-setting sequences, which affect the display algorithm rather than having extra bits for each character. Some terminals, such as the Hewlett-Packard 2621, automatically leave standout mode when they move to a new line or the cursor is addressed. Programs using standout mode should exit standout mode before moving the cursor or sending a newline, unless the **msgr** capability, asserting that it is safe to move in standout mode, is present.

If the terminal has a way of flashing the screen to indicate an error quietly (a bell replacement), then this can be given as **flash**; it must not move the cursor. A good flash can be done by changing the screen into reverse video, pad for 200 ms, then return the screen to normal video.

If the cursor needs to be made more visible than normal when it is not on the bottom line (to make, for example, a non-blinking underline into an easier to find block or blinking underline) give this sequence as **cvvis**. The boolean **chts** should also be given. If there is a way to make the cursor completely invisible, give that as **civis**. The capability **cnorm** should be given, which undoes the effects of either of these modes.

If your terminal generates underlined characters by using the underline character (with no special sequences needed) even though it does not otherwise overstrike characters, then specify the capability **ul**. For devices on which a character overstriking another leaves both characters on the screen, specify the capability **os**. If overstrikes are erasable with a blank, then this should be indicated by specifying **eo**.

If there is a sequence to set arbitrary combinations of modes, this should be given as **sgr** (set attributes), taking nine arguments. Each argument is either 0 or non-zero, as the corresponding attribute is on or off. The nine arguments are, in order: standout, underline, reverse, blink, dim, bold, blank, protect, alternate character set. Not all modes need to be supported by **sgr**; only those for which corresponding separate attribute commands exist should be supported. For example, let's assume that the terminal in question needs the following escape sequences to turn on various modes.

tparm Argument	Attribute	Escape Sequence
	none	\E[0m
p1	standout	\E[0;4;7m
p2	underline	\E[0;3m
p3	reverse	\E[0;4m
p4	blink	\E[0;5m
p5	dim	\E[0;7m
p6	bold	\E[0;3;4m
p7	invis	\E[0;8m
p8	protect	not available
p9	altcharset	^O (off) ^N (on)

Note that each escape sequence requires a 0 to turn off other modes before turning on its own mode. Also note that, as suggested above, *standout* is set up to be the combination of *reverse* and *dim*. Also, because this terminal has no *bold* mode, *bold* is set up as the combination of *reverse* and *underline*. In addition, to allow combinations, such as *underline+blink*, the sequence to use would be **E[0;3;5m**. The terminal doesn't have protect mode, either, but that cannot be simulated in any way, so **p8** is ignored. The *altcharset* mode is different in that it is either ^O or ^N, depending on whether it is off or on. If all modes were to be turned on, the sequence would be:

\E[0;3;4;5;7;8m,N

Now look at when different sequences are output. For example, ;3 is output when either **p2** or **p6** is true, that is, if either *underline* or *bold* modes are turned on. Writing out the above sequences, along with their dependencies, gives the following:

Sequence	When to Output	terminfo Translation
\E[0	always	\E[0
;3	if p2 or p6	%%p2%p6% %t;3%;
;4	if p1 or p3 or p6	%%p1%p3% %p6% %t;4%;

Sequence	When to Output	terminfo Translation
;5	if p4	%%p4%t;5%;
;7	if p1 or p5	%%p1%p5% %t;7%;
;8	if p7	%%p7%t;8%;
m	always	m
caret.N or ^O	if p9 ^N, else ^O	%%p9%t^N%e^O%;

Putting this all together into the **sgr** sequence gives:

```
sgr=\E[0%%p2%p6%|%t;3%;%%p1%p3%|%p6%
|%t;4%;%%p5%t;5%;%%p1%p5%
|%t;7%;%%p7%t;8%;m%%p9%t,N%e,0%;,
```

Remember that **sgr** and **sgr0** must always be specified.

# Keypad

If the device has a keypad that transmits sequences when the keys are pressed, this information can also be specified. Note that it is not possible to handle devices where the keypad only works in local (this applies, for example, to the unshifted Hewlett-Packard 2621 keys). If the keypad can be set to transmit or not transmit, specify these sequences as **smkx** and **rmkx**. Otherwise the keypad is assumed to always transmit.

The sequences sent by the left arrow, right arrow, up arrow, down arrow, and home keys can be given as **kcub1**, **kcub1**, **kcub1**, **kcub1** and **khome**, respectively. If there are function keys such as f0, f1, ..., f63, the sequences they send can be specified as **kf0**, **kf1**, ..., **kf63**. If the first 11 keys have labels other than the default f0 through f10, the labels can be given as **lf0**, **lf1**, ..., **lf10**.

The codes transmitted by certain other special keys can be given: **kll** (home down), **kbs** (backspace), **ktbc** (clear all tabs), **kctab** (clear the tab stop in this column), **kclr** (clear screen or erase key), **kdch1** (delete character), **kdl1** (delete line), **krmir** (exit insert mode), **kel** (clear to end of line), **ked** (clear to end of screen), **kich1** (insert character or enter insert mode), **kil1** (insert line), **knp** (next page), **kpp** (previous page), **kind** (scroll forward/down), **kri** (scroll backward/up), **khts** (set a tab stop in this column). In addition, if the keypad has a 3 by 3 array of keys including the four arrow keys, the other five keys can be given as **ka1**, **ka3**, **kb2**, **kc1**, and **kc3**. These keys are useful when the effects of a 3 by 3 directional pad are needed. Further keys are defined above in the capabilities list.

Strings to program function keys can be specified as **pfkey**, **pfloc**, and **pfx**. A string to program screen labels should be specified as **pln**. Each of these strings takes two arguments: a function key identifier and a string to program it with. **pfkey** causes pressing the given key to be the same as the user typing the given string; **pfloc** causes the string to be executed by the terminal in local mode; and **pfx** causes the string to be transmitted to the computer. The capabilities **nlab**, **lw** and **lh** define the number of programmable screen labels and their width and height.

If there are commands to turn the labels on and off, give them in **smln** and **rmln**. **smln** is normally output after one or more pln sequences to make sure that the change becomes visible.

### **Tabs and Initialization**

If the device has hardware tabs, the command to advance to the next tab stop can be given as **ht** (usually control-I). A "backtab" command that moves leftward to the next tab stop can be given as **cbt**. By convention, if tty modes show that tabs are being expanded by the computer rather than being sent to the device, programs should not use **ht** or **cbt** (even if they are present) because the user might not have the

tab stops properly set. If the device has hardware tabs that are initially set every n spaces when the device is powered up, the numeric argument it is given, showing the number of spaces the tabs are set to. This is normally used by *tput* **init** to determine whether to set the mode for hardware tab expansion and whether to set the tab stops. If the device has tab stops that can be saved in nonvolatile memory, the **terminfo** description can assume that they are properly set. If there are commands to set and clear tab stops, they can be given as **tbc** (clear all tab stops) and **hts** (set a tab stop in the current column of every row).

Other capabilities include: **is1**, **is2**, and **is3**, initialization strings for the device; **iprog**, the path name of a program to be run to initialize the device; and if, the name of a file containing long initialization strings. These strings are expected to set the device into modes consistent with the rest of the **terminfo** description. They must be sent to the device each time the user logs in and be output in the following order: run the program **iprog**; output **is1**; output **is2**; set the margins using **mgc**, **smgl** and **smgr**; set the tabs using **tbc** and **hts**; print the file if; and finally output **is3**. This is usually done using the **init** option of *tput*.

Most initialization is done with **is2**. Special device modes can be set up without duplicating strings by putting the common sequences in **is2** and special cases in **is1** and **is3**. Sequences that do a reset from a totally unknown state can be given as **rs1**, **rs2**, **rf**, and **rs3**, analogous to **is1**, **is2**, **is3**, and **if**. (The method using files, **if** and **rf**, is used for a few terminals however, the recommended method is to use the initialization and reset strings.) These strings are output by *tput* **reset**, which is used when the terminal gets into a wedged state. Commands are normally placed in **rs1**, **rs2**, **rs3**, and **rf** only if they produce annoying effects on the screen and are not necessary when logging in. For example, the command to set a terminal into 80-column mode would normally be part of **is2**, but on some terminals it causes an annoying glitch on the screen and is not normally needed because the terminal is usually already in 80-column mode.

If a more complex sequence is needed to set the tabs than can be described by using **tbc** and **hts**, the sequence can be placed in **is2** or **if**.

Any margin can be cleared with **mgc**. (For instructions on how to specify commands to set and clear margins.

# **Delays**

Certain capabilities control padding in the **tty** driver. These are primarily needed by hard-copy terminals, and are used by *tput* **init** to set tty modes appropriately. Delays embedded in the capabilities **cr**, **ind**, **cub1**, **ff**, and **tab** can be used to set the appropriate delay bits to be set in the tty driver. If **pb** (padding baud rate) is given, these values can be ignored at baud rates below the value of **pb**.

# **Status Lines**

If the terminal has an extra "status line" that is not normally used by software, this fact can be indicated. If the status line is viewed as an extra line below the bottom line, into which one can cursor address normally (such as the Heathkit H19's 25th line, or the 24th line of a VT100 which is set to a 23-line scrolling region), the capability **hs** should be given. Special strings that go to a given column of the status line and return from the status line can be given as **tsl** and **fsl**. (**fsl** must leave the cursor position in the same place it was before **tsl**. If necessary, the **sc** and **rc** strings can be included in **tsl** and **fsl** to get this effect.) The capability **tsl** takes one argument, which is the column number of the status line the cursor is to be moved to.

If escape sequences and other special commands, such as tab, work while in the status line, the flag **eslok** can be given. A string which turns off the status line (or otherwise erases its contents) should be given as **dsl**. If the terminal has commands to save and restore the position of the cursor, give them as **sc** and **rc**. The status line is normally assumed to be the same width as the rest of the screen (that is, **cols**). If the status line is a different width (possibly because the terminal does not allow an entire line to be loaded) the width, in columns, can be indicated with the numeric argument **wsl**.

# **Line Graphics**

If the device has a line drawing alternate character set, the mapping of glyph to character would be given in **acsc**. The definition of this string is based on the alternate character set used in the Digital VT100 terminal, extended slightly with some characters from the AT&T; 4410v1 terminal.

Glyph Name	VT100+ Character
arrow pointing right	+
arrow pointing left	,
arrow pointing down	•
solid square block	0
lantern symbol	I
arrow pointing up	-
diamond	•
checker board (stipple)	a
degree symbol	f
plus/minus	g
board of squares	h
lower right corner	j
upper right corner	k
upper left corner	ι
lower left corner	m
plus	n
scan line 1	o
horizontal line	q
scan line 9	s
left tee ( -)	t
right tee (- )	u

Glyph Name	VT100+ Character
bottom tee ( )	V
top tee ( )	W
vertical line	x
bullet	˜

The best way to describe a new device's line graphics set is to add a third column to the above table with the characters for the new device that produce the appropriate glyph when the device is in alternate-character-set mode. For example:

Glyph Name	VT100+ Character	<b>Character Used on New Device</b>
upper left corner	l	R
lower left corner	m	F
upper right corner	k	Т
lower right corner	j	G
horizontal line	q	,
vertical line	x	

Now write down the characters left to right; for example:

```
acsc=1RmFkTjGq\,x.
```

In addition, **terminfo** lets you define multiple character sets.

# **Color Manipulation**

Most color terminals belong to one of two classes of terminal:

### Tektronix-style

The Tektronix method uses a set of N predefined colors (usually 8) from which an application can select "current" foreground and background colors. Thus a terminal can support up to N colors mixed into N*N color-pairs to be displayed on the screen at the same time.

### **Hewlett-Packard-style**

In the HP method, the application cannot define the foreground independently of the background, or viceversa. Instead, the application must define an entire color-pair at once. Up to M color-pairs, made from 2*M different colors, can be defined this way.

The numeric variables **colors** and **pairs** define the number of colors and color-pairs that can be displayed on the screen at the same time. If a terminal can change the definition of a color (for example, the Tektronix 4100 and 4200 series terminals), this should be specified with **ccc** (can change color). To change the definition of a color (Tektronix 4200 method), use **initc** (initialize color). It requires four arguments: color number (ranging from 0 to **colors-1**) and three RGB (red, green, and blue) values or three HLS colors (Hue, Lightness, Saturation). Ranges of RGB and HLS values are terminal-dependent.

Tektronix 4100 series terminals only use HLS color notation. For such terminals (or dual-mode terminals to be operated in HLS mode) one must define a boolean variable **hls**; that would instruct the *init_color*() functions to convert its RGB arguments to HLS before sending them to the terminal. The last three arguments to the **initc** string would then be HLS values.

If a terminal can change the definitions of colors, but uses a color notation different from RGB and HLS, a mapping to either RGB or HLS must be developed.

If the terminal supports ANSI escape sequences to set background and foreground, they should be coded as setab and setaf, respectively. If the terminal supports other escape sequences to set background and foreground, they should be coded as **setb** and **setf**, respectively. The *vidputs*() function and the refresh functions use **setab** and **setaf** if they are defined. Each of these capabilities requires one argument: the number of the color. By convention, the first eight colors (0-7) map to, in order: black, red, green, yellow, blue, magenta, cyan, white. However, color re-mapping may occur or the underlying hardware may not support these colors. Mappings for any additional colors supported by the device (that is, to numbers greater than 7) are at the discretion of the **terminfo** entry writer.

To initialize a color-pair (HP method), use **initp** (initialize pair). It requires seven arguments: the number of a color-pair (range=0 to **pairs-1**), and six RGB values: three for the foreground followed by three for the background. (Each of these groups of three should be in the order RGB.) When **initc** or **initp** are used, RGB or HLS arguments should be in the order "red, green, blue" or "hue, lightness, saturation"), respectively. To make a color-pair current, use **scp** (set color-pair). It takes one argument, the number of a color-pair.

Some terminals (for example, most color terminal emulators for PCs) erase areas of the screen with current background color. In such cases, **bce** (background color erase) should be defined. The variable **op** (original pair) contains a sequence for setting the foreground and the background colors to what they were at the terminal start-up time. Similarly, **oc** (original colors) contains a control sequence for setting all colors (for the Tektronix method) or color-pairs (for the HP method) to the values they had at the terminal start-up time.

Some color terminals substitute color for video attributes. Such video attributes should not be combined with colors. Information about these video attributes should be packed into the ncv (no color video) variable. There is a one-to-one correspondence between the nine least significant bits of that variable and the video attributes. The following table depicts this correspondence.

Attribute	Bit Position	Decimal Value	<b>Characteristic That Sets</b>
WA_ STANDOUT	0	1	<b>sgr,</b> parameter 1
WA_ UNDERLINE	1	2	<b>sgr,</b> parameter 2
WA_ REVERSE	2	4	<b>sgr,</b> parameter 3
WA_ BLINK	3	8	<b>sgr,</b> parameter 4
WA_ DIM	4	16	<b>sgr,</b> parameter 5
WA_ BOLD	5	32	<b>sgr,</b> parameter 6
WA_ INVIS	6	64	<b>sgr,</b> parameter 7
WA_ PROTECT	7	128	<b>sgr,</b> parameter 8
WA_ ALTCHARSET	8	256	<b>sgr,</b> parameter 9
WA_ HORIZONTAL	9	512	<b>sgr1,</b> parameter 1
WA_ LEFT	10	1024	<b>sgr1,</b> parameter 2
WA_ LOW	11	2048	<b>sgr1,</b> parameter 3
WA_ RIGHT	12	4096	<b>sgr1,</b> parameter 4
WA_TOP	13	8192	<b>sgr1,</b> parameter 5
WA_ VERTICAL	14	16384	<b>sgr1,</b> parameter 6

When a particular video attribute should not be used with colors, set the corresponding **ncv bit** to 1; otherwise set it to 0. To determine the information to pack into the **ncv** variable, add the decimal values corresponding to those attributes that cannot coexist with colors. For example, if the terminal uses colors to simulate reverse video (bit number 2 and decimal value 4) and bold (bit number 5 and decimal value 32), the resulting value for **ncv** will be 36 (4 + 32).

### Miscellaneous

If the terminal requires other than a null (zero) character as a pad, then this can be given as **pad**. Only the first character of the **pad** string is used. If the terminal does not have a pad character, specify **npc**.

If the terminal can move up or down half a line, this can be indicated with **hu** (half-line up) and **hd** (half-line down). This is primarily useful for superscripts and subscripts on hardcopy terminals. If a hardcopy terminal can eject to the next page (form feed), give this as **ff** (usually control-L).

If there is a command to repeat a given character a given number of times (to save time transmitting a large number of identical characters) this can be indicated with the argumentized string **rep**. The first argument is the character to be repeated and the second is the number of times to repeat it. Thus, **tparm(repeat_char, 'x', 10)** is the same as **xxxxxxxxxx**.

If the terminal has a settable command character, such as the Tektronix 4025, this can be indicated with **cmdch**. A prototype command character is chosen which is used in all capabilities. This character is given in the **cmdch** capability to identify it. The following convention is supported on some systems: If the environment variable CC exists, all occurrences of the prototype character are replaced with the character in CC.

Terminal descriptions that do not represent a specific kind of known terminal, such as *switch*, *dialup*, *patch*, and *network*, should include the **gn** (generic) capability so that programs can complain that they do not know how to talk to the terminal. (This capability does not apply to virtual terminal descriptions for which the escape sequences are known.) If the terminal is one of those supported by the virtual terminal protocol, the terminal number can be given as **vt**. A line-turn-around sequence to be transmitted before doing reads should be specified in **rfi**.

If the device uses xon/xoff handshaking for flow control, give **xon**. Padding information should still be included so that functions can make better decisions about costs, but actual pad characters will not be transmitted. Sequences to turn on and off xon/xoff handshaking may be given in **smxon** and **rmxon**. If the characters used for handshaking are not **^S** and **^Q**, they may be specified with **xonc** and **xoffc**.

If the terminal has a "meta key" which acts as a shift key, setting the 8th bit of any character transmitted, this fact can be indicated with **km**. Otherwise, software will assume that the 8th bit is parity and it will usually be cleared. If strings exist to turn this "meta mode" on and off, they can be given as **smm** and **rmm**.

If the terminal has more lines of memory than will fit on the screen at once, the number of lines of memory can be indicated with **lm**. A value of **lm#0** indicates that the number of lines is not fixed, but that there is still more memory than fits on the screen.

Media copy strings which control an auxiliary printer connected to the terminal can be given as:

### mc0

Print the contents of the screen

### mc4

Turn off the printer

#### mc5

Turn on the printer

When the printer is on, all text sent to the terminal will be sent to the printer. A variation, **mc5p**, takes one argument, and leaves the printer on for as many characters as the value of the argument, then turns the printer off. The argument should not exceed 255. If the text is not displayed on the terminal screen when the printer is on, specify **mc5i** (silent printer). All text, including **mc4**, is transparently passed to the printer while an **mc5p** is in effect.

# **Special Cases**

The working model used by **terminfo** fits most terminals reasonably well. However, some terminals do not completely match that model, requiring special support by **terminfo**. These are not meant to be construed as deficiencies in the terminals; they are just differences between the working model and the actual hardware. They may be unusual devices or, for some reason, do not have all the features of the **terminfo** model implemented.

### **Source File Syntax**

Terminals that cannot display tilde (˜) characters, such as certain Hazeltine terminals, should indicate **hz**.

Terminals that ignore a linefeed immediately after an **am** wrap, such as the Concept 100, should indicate **xenl**. Those terminals whose cursor remains on the right-most column until another character has been received, rather than wrapping immediately upon receiving the right-most character, such as the VT100, should also indicate **xenl**.

If **el** is required to get rid of standout (instead of writing normal text on top of it), **xhp** should be given.

Those Teleray terminals whose tabs turn all characters moved over to blanks, should indicate **xt** (destructive tabs). This capability is also taken to mean that it is not possible to position the cursor on top of a "magic cookie." Therefore, to erase standout mode, it is necessary, instead, to use delete and insert line.

For Beehive Superbee terminals that do not transmit the escape or control-C characters, specify **xsb**, indicating that the f1 key is to be used for escape and the f2 key for control-C.

# Similar Terminals

If there are two similar terminals, one can be defined as being just like the other with certain exceptions. The string capability **use** can be given with the name of the similar terminal. The capabilities given before use override those in the terminal type invoked by **use**. A capability can be canceled by placing capability-name@ prior to the appearance of the string capability use. For example, the entry:

```
att4424-2|Teletype 4424 in display function group ii, rev@, sgr@, smul@, use=att4424,
```

defines an AT&T; 04424 terminal that does not have the **rev**, **sgr**, and smul capabilities, and hence cannot do highlighting. This is useful for different modes for a terminal, or for different user preferences. More than one **use** capability may be given.

# **Printer Capabilities**

The **terminfo** database lets you define capabilities of printers as well as terminals.

# **Rounding Values**

Because argumentized string capabilities work only with integer values, **terminfo** designers should create strings that expect numeric values that have been rounded. Application designers should note this and should always round values to the nearest integer before using them with a argumentized string capability.

# **Printer Resolution**

A printer's resolution is defined to be the smallest spacing of characters it can achieve. In general, the horizontal and vertical resolutions are independent. Thus the vertical resolution of a printer can be determined by measuring the smallest achievable distance between consecutive printing baselines, while the horizontal resolution can be determined by measuring the smallest achievable distance between the leftmost edges of consecutive printed, identical, characters.

All printers are assumed to be capable of printing with a uniform horizontal and vertical resolution. The view of printing that **terminfo** currently presents is one of printing inside a uniform matrix: All characters are printed at fixed positions relative to each "cell" in the matrix; furthermore, each cell has the same size given by the smallest horizontal and vertical step sizes dictated by the resolution. (The cell size can be changed as will be seen later.)

Many printers are capable of "proportional printing," where the horizontal spacing depends on the size of the character last printed. **terminfo** does not make use of this capability, although it does provide enough capability definitions to allow an application to simulate proportional printing.

A printer must not only be able to print characters as close together as the horizontal and vertical resolutions suggest, but also of "moving" to a position an integral multiple of the smallest distance away from a previous position. Thus printed characters can be spaced apart a distance that is an integral multiple of the smallest distance, up to the length or width of a single page.

Some printers can have different resolutions depending on different "modes." In "normal mode," the existing **terminfo** capabilities are assumed to work on columns and lines, just like a video terminal. Thus the old **lines** capability would give the length of a page in lines, and the **cols** capability would give the width of a page in columns. In "micro mode," many **terminfo** capabilities work on increments of lines and columns. With some printers the micro mode may be concomitant with normal mode, so that all the capabilities work at the same time.

# **Specifying Printer Resolution**

The printing resolution of a printer is given in several ways. Each specifies the resolution as the number of smallest steps per distance:

Characteristic	Number of Smallest Steps
orhi	Steps per inch horizontally
orvi	Steps per inch vertically
orc	Steps per column
orl	Steps per line

When printing in normal mode, each character printed causes movement to the next column, except in special cases described later; the distance moved is the same as the per-column resolution. Some printers cause an automatic movement to the next line when a character is printed in the rightmost position; the distance moved vertically is the same as the per-line resolution. When printing in micro mode, these distances can be different, and may be zero for some printers.

# Automatic Motion after Printing

Normal Mode:

orc Steps moved horizontally

orl Steps moved vertically

Micro Mode:

mcs Steps moved horizontally

**mls** Steps moved vertically

Some printers are capable of printing wide characters. The distance moved when a wide character is printed in normal mode may be different from when a regular width character is printed. The distance moved when a wide character is printed in micro mode may also be different from when a regular character is printed in micro mode, but the differences are assumed to be related: If the distance moved for a regular character is the same whether in normal mode or micro mode (**mcs=orc**), then the distance moved for a wide character is also the same whether in normal mode or micro mode. This doesn't mean

### **Source File Syntax**

the normal character distance is necessarily the same as the wide character distance, just that the distances don't change with a change in normal to micro mode. However, if the distance moved for a regular character is different in micro mode from the distance moved in normal mode (**mcs<orc**), the micro mode distance is assumed to be the same for a wide character printed in micro mode, as the table below shows.

# **Automatic Motion after Printing Wide Character**

Normal Mode or Micro Mode ( <b>mcs = orc</b> ):	
widcs	Steps moved horizontally
Micro Mode (mcs < orc):	
mcs	Steps moved horizontally

There may be control sequences to change the number of columns per inch (the character pitch) and to change the number of lines per inch (the line pitch). If these are used, the resolution of the printer changes, but the type of change depends on the printer:

Changing the Character/Line Pitches	
cpi	Change character pitch
cpix	If set, cpi changes orhi, otherwise changes orc
lpi	Change line pitch
lpix	If set, lpi changes orvi, otherwise changes orl
chr	Change steps per column
cvr	Change steps per line

The **cpi** and **lpi** string capabilities are each used with a single argument, the pitch in columns (or characters) and lines per inch, respectively. The **chr** and **cvr** string capabilities are each used with a single argument, the number of steps per column and line, respectively.

Using any of the control sequences in these strings will imply a change in some of the values of **orc**, **orh**, **orl**, and **orvi**. Also, the distance moved when a wide character is printed, **widcs**, changes in relation to **orc**. The distance moved when a character is printed in micro mode, **mcs**, changes similarly, with one exception: if the distance is 0 or 1, then no change is assumed.

Programs that use **cpi**, **lpi**, **chr**, or **cvr** should recalculate the printer resolution (and should recalculate other values).

# **Capabilities that Cause Movement**

In the following descriptions, "movement" refers to the motion of the "current position." With video terminals this would be the cursor; with some printers, this is the carriage position. Other printers have different equivalents. In general, the current position is where a character would be displayed if printed.

**terminfo** has string capabilities for control sequences that cause movement a number of full columns or lines. It also has equivalent string capabilities for control sequences that cause movement a number of smallest steps.

String Capabilities for Motion	Description
mcub1 mcuf1 mcuu1 mcud1	Move 1 step left Move 1 step right Move 1 step up Move 1 step down
mcub mcuf mcuu mcud	Move N steps left Move N steps right Move N steps up Move N steps down
mhpa mvpa	Move N steps from the left Move N steps from the top

The latter six strings are each used with a single argument, N.

Sometimes the motion is limited to less than the width or length of a page. Also, some printers don't accept absolute motion to the left of the current position. **terminfo** has capabilities for specifying these limits.

Limits to Motion	Description
mjump maddr	Limit on use of mcub1, mcuf1, mcuu1, mcud1 Limit on use of mhpa, mvpa
xhpa xvpa	If set, <b>hpa</b> and <b>mhpa</b> can't move left If set, <b>vpa</b> and <b>mvpa</b> can't move up

If a printer needs to be in a "micro mode" for the motion capabilities described above to work, there are string capabilities defined to contain the control sequence to enter and exit this mode. A boolean is available for those printers where using a carriage return causes an automatic return to normal mode.

Entering/Exiting Micro Mode	Description
smicm rmicm	Enter micro mode Exit micro mode
crxm	Using cr exits micro mode

The movement made when a character is printed in the rightmost position varies among printers. Some make no movement, some move to the beginning of the next line, others move to the beginning of the same line. **terminfo** has boolean capabilities for describing all three cases.

What Happens After Character Printed in Rightmost Position	Description
sam	Automatic move to beginning of same line

### **Source File Syntax**

Some printers can be put in a mode where the normal direction of motion is reversed. This mode can be especially useful when there are no capabilities for leftward or upward motion, because those capabilities can be built from the motion reversal capability and the rightward or downward motion capabilities. It is best to leave it up to an application to build the leftward or upward capabilities, though, and not enter them in the **terminfo** database. This allows several reverse motions to be strung together without intervening wasted steps that leave and reenter reverse mode.

Entering/Exiting Reverse Modes	Description
slm rlm sum rum	Reverse sense of horizontal motions Restore sense of horizontal motions Reverse sense of vertical motions Restore sense of vertical motions
While sense of horizo	ontal motions reversed:
mcub1 mcub mcub mcuf cub1 cuf1 cub cuf	Move 1 step right Move 1 step left Move N steps right Move N steps left Move 1 column right Move 1 column left Move N columns right Move N columns right Move N columns right Move N columns left
mcuu1 mcuu1 mcuu mcud cuu1 cud1 cuu	Move 1 step down Move 1 step up Move N steps down Move N steps up Move 1 line down Move 1 line up Move N lines down Move N lines down

The reverse motion modes should not affect the **mvpa** and **mhpa** absolute motion capabilities. The reverse vertical motion mode should, however, also reverse the action of the line "wrapping" that occurs when a character is printed in the right-most position. Thus printers that have the standard **terminfo** capability **am** defined should experience motion to the beginning of the previous line when a character is printed in the rightmost position in reverse vertical motion mode.

The action when any other motion capabilities are used in reverse motion modes is not defined; thus, programs must exit reverse motion modes before using other motion capabilities.

Two miscellaneous capabilities complete the list of motion capabilities. One of these is needed for printers that move the current position to the beginning of a line when certain control characters, such as *line-feed* or *form-feed*, are used. The other is used for the capability of suspending the motion that normally occurs after printing a character.

Miscellaneous Motion Strings	Description
docr	List of control characters causing cr
zerom	Prevent auto motion after printing next single character

# **Margins**

**terminfo** provides two strings for setting margins on terminals: one for the left and one for the right margin. Printers, however, have two additional margins, for the top and bottom margins of each page. Furthermore, some printers require not using motion strings to move the current position to a margin and then fixing the margin there, but require the specification of where a margin should be regardless of the current position. Therefore **terminfo** offers six additional strings for defining margins with printers.

Setting Margins	Description
smgl smgr smgb smgt	Set left margin at current column Set right margin at current column Set bottom margin at current line Set top margin at current line
smgbp smglp smgrp smgtp	Set bottom margin at line N Set left margin at column N Set right margin at column N Set top margin at line N

The last four strings are used with one or more arguments that give the position of the margin or margins to set. If both of **smglp** and **smgrp** are set, each is used with a single argument, N, that gives the column number of the left and right margin, respectively. If both of **smgtp** and **smgbp** are set, each is used to set the top and bottom margin, respectively: **smgtp** is used with a single argument, N, the line number of the top margin; however, **smgbp** is used with two arguments, N and M, that give the line number of the bottom margin, the first counting from the top of the page and the second counting from the bottom. This accommodates the two styles of specifying the bottom margin in different manufacturers' printers. When coding a **terminfo** entry for a printer that has a settable bottom margin, only the first or second argument should be used, depending on the printer. When writing an application that uses **smgbp** to set the bottom margin, both arguments must be given.

If only one of **smglp** and **smgrp** is set, then it is used with two arguments, the column number of the left and right margins, in that order. Likewise, if only one of **smgtp** and **smgbp** is set, then it is used with two arguments that give the top and bottom margins, in that order, counting from the top of the page. Thus when coding a **terminfo** entry for a printer that requires setting both left and right or top and bottom margins simultaneously, only one of **smglp** and **smgrp** or **smgtp** and **smgbp** should be defined; the other should be left blank. When writing an application that uses these string capabilities, the pairs should be first checked to see if each in the pair is set or only one is set, and should then be used accordingly.

In counting lines or columns, line zero is the top line and column zero is the left-most column. A zero value for the second argument with **smgbp** means the bottom line of the page.

All margins can be cleared with mgc.

# Shadows, Italics, Wide Characters, Superscripts, Subscripts

Five sets of strings describe the capabilities printers have of enhancing printed text.

<b>Enhanced Printing</b>	Description
sshm rshm	Enter shadow-printing mode Exit shadow-printing mode
sitm ritm	Enter italicizing mode Exit italicizing mode
swidm rwidm	Enter wide character mode Exit wide character mode

Enhanced Printing	Description
ssupm rsupm supcs	Enter superscript mode Exit superscript mode List of characters available as superscripts
ssubm rsubm subcs	Enter subscript mode Exit subscript mode List of characters available as subscripts

If a printer requires the **sshm** control sequence before every character to be shadow-printed, the **rshm** string is left blank. Thus programs that find a control sequence in **sshm** but none in rshm should use the **sshm** control sequence before every character to be shadow-printed; otherwise, the sshm control sequence should be used once before the set of characters to be shadow-printed, followed by **rshm**. The same is also true of each of the **sitm/ritm**, **swidm/rwidm**, **ssupm/rsupm**, and **ssubm/rsubm** pairs.

**terminfo** also has a capability for printing emboldened text (**bold**). While shadow printing and emboldened printing are similar in that they "darken" the text, many printers produce these two types of print in slightly different ways. Generally, emboldened printing is done by overstriking the same character one or more times. Shadow printing likewise usually involves overstriking, but with a slight movement up and/or to the side so that the character is "fatter."

It is assumed that enhanced printing modes are independent modes, so that it would be possible, for instance, to shadow print italicized subscripts.

As mentioned earlier, the amount of motion automatically made after printing a wide character should be given in **widcs**.

If only a subset of the printable ASCII characters can be printed as superscripts or subscripts, they should be listed in **supcs** or **subcs** strings, respectively. If the **ssupm** or **ssubm** strings contain control sequences, but the corresponding **supcs** or **subcs** strings are empty, it is assumed that all printable ASCII characters are available as superscripts or subscripts.

Automatic motion made after printing a superscript or subscript is assumed to be the same as for regular characters. Note that the existing **msgr** boolean capability describes whether motion control sequences can be used while in "standout mode." This capability is extended to cover the enhanced printing modes added here. **msgr** should be set for those printers that accept any motion control sequences without affecting shadow, italicized, widened, superscript, or subscript printing. Conversely, if **msgr** is not set, a program should end these modes before attempting any motion.

# **Alternate Character Sets**

In addition to allowing you to define line graphics, **terminfo** lets you define alternate character sets. The following capabilities cover printers and terminals with multiple selectable or definable character sets:

Alternate Character Sets	
scs	Select character set N
scsd	Start definition of character set N, M characters
defc	Define character A, B dots wide, descender D
rcsd	End definition of character set N
csnm	List of character set names
daisy	Printer has manually changed print-wheels
_	

The **scs**, **rcsd**, and **csnm** strings are used with a single argument, N, a number from 0 to 63 that identifies the character set. The **scsd** string is also used with the argument N and another, M, that gives the number of characters in the set. The **defc** string is used with three arguments: A gives the ASCII code representation for the character, B gives the width of the character in dots, and D is zero or one depending

on whether the character is a "descender" or not. The **defc** string is also followed by a string of "imagedata" bytes that describe how the character looks (see below).

Character set 0 is the default character set present after the printer has been initialized. Not every printer has 64 character sets, of course; using **scs** with an argument that doesn't select an available character set should cause a null pointer to be returned by **tparm**.

If a character set has to be defined before it can be used, the **scsd** control sequence is to be used before defining the character set, and the **rcsd** is to be used after. They should also cause a NULL pointer to be returned by **tparm** when used with an argument *N* that doesn't apply. If a character set still has to be selected after being defined, the **scs** control sequence should follow the **rcsd** control sequence. By examining the results of using each of the **scs**, **scsd**, and **rcsd** strings with a character set number in a call to **tparm**, a program can determine which of the three are needed.

Between use of the **scsd** and **rcsd** strings, the **defc** string should be used to define each character. To print any character on printers covered by **terminfo**, the ASCII code is sent to the printer. This is true for characters in an alternate set as well as "normal" characters. Thus the definition of a character includes the ASCII code that represents it. In addition, the width of the character in dots is given, along with an indication of whether the character should descend below the print line (such as the lower case letter "g" in most character sets). The width of the character in dots also indicates the number of image-data bytes that will follow the **defc** string. These image-data bytes indicate where in a dot-matrix pattern ink should be applied to "draw" the character.

It's easiest for the creator of **terminfo** entries to refer to each character set by number; however, these numbers will be meaningless to the application developer. The **csnm** string alleviates this problem by providing names for each number.

When used with a character set number in a call to **tparm**, the **csnm** string will produce the equivalent name. These names should be used as a reference only. No naming convention is implied, although anyone who creates a **terminfo** entry for a printer should use names consistent with the names found in user documents for the printer. Application developers should allow a user to specify a character set by number (leaving it up to the user to examine the **csnm** string to determine the correct number), or by name, where the application examines the **csnm** string to determine the corresponding character set number.

These capabilities are likely to be used only with dot-matrix printers. If they are not available, the strings should not be defined. For printers that have manually changed print-wheels or font cartridges, the boolean **daisy** is set.

# **Dot-Matrix Graphics**

Dot-matrix printers typically have the capability of reproducing raster graphics images. Three numeric capabilities and three string capabilities help a program draw raster-graphics images independent of the type of dot-matrix printer or the number of pins or dots the printer can handle at one time.

Dot-Matrix Graphics		
npins spinv spinh porder sbim rbim	Number of pins, N, in print-head Spacing of pins vertically in pins per inch Spacing of dots horizontally in dots per inch Matches software bits to print-head pins Start printing bit image graphics, B bits wide End printing bit image graphics	

The **sbim** sring is used with a single argument, B, the width of the image in dots.

The model of dot-matrix or raster-graphics that **terminfo** presents is similar to the technique used for most dot-matrix printers: each pass of the printer's print-head is assumed to produce a dot-matrix that is *N* dots high and *B* dots wide. This is typically a wide, squat, rectangle of dots. The height of this rectangle in dots will vary from one printer to the next; this is given in the **npins** numeric capability. The size of the

rectangle in fractions of an inch will also vary; it can be deduced from the **spinv** and **spinh** numeric capabilities. With these three values an application can divide a complete raster-graphics image into several horizontal strips, perhaps interpolating to account for different dot spacing vertically and horizontally.

The **sbim** and **rbim** strings start and end a dot-matrix image, respectively. The **sbim** string is used with a single argument that gives the width of the dot-matrix in dots. A sequence of "image-data bytes" are sent to the printer after the **sbim** string and before the **rbim** string. The number of bytes is a integral multiple of the width of the dot-matrix; the multiple and the form of each byte is determined by the **porder** string as described below.

The **porder** string is a comma separated list of pin numbers optionally followed by an numerical offset. The offset, if given, is separated from the list with a semicolon. The position of each pin number in the list corresponds to a bit in an 8-bit data byte. The pins are numbered consecutively from 1 to **npins**, with 1 being the top pin. Note that the term "pin" is used loosely here; "ink-jet" dot-matrix printers don't have pins, but can be considered to have an equivalent method of applying a single dot of ink to paper. The bit positions in **porder** are in groups of 8, with the first position in each group the most significant bit and the last position the least significant bit. An application produces 8-bit bytes in the order of the groups in **porder**.

An application computes the "image-data bytes" from the internal image, mapping vertical dot positions in each print-head pass into 8-bit bytes, using a 1 bit where ink should be applied and 0 where no ink should be applied. This can be reversed (0 bit for ink, 1 bit for no ink) by giving a negative pin number. If a position is skipped in **porder**, a 0 bit is used. If a position has a lower case 'x' instead of a pin number, a 1 bit is used in the skipped position. For consistency, a lower case 'o' can be used to represent a 0 filled, skipped bit. There must be a multiple of 8 bit positions used or skipped in **porder**; if not, low-order bits of the last byte are set to 0. The offset, if given, is added to each data byte; the offset can be negative.

Some examples may help clarify the use of the **porder** string. The AT&T; 470, AT&T; 475 and C.Itoh 8510 printers provide eight pins for graphics. The pins are identified top to bottom by the 8 bits in a byte, from least significant to most. The **porder** strings for these printers would be **8,7,6,5,4,3,2,1**. The AT&T; 478 and AT&T; 479 printers also provide eight pins for graphics. However, the pins are identified in the reverse order. The **porder** strings for these printers would be **1,2,3,4,5,6,7,8**. The AT&T; 5310, AT&T; 5320, Digital LA100, and Digital LN03 printers provide six pins for graphics. The pins are identified top to bottom by the decimal values 1, 2, 4, 8, 16 and 32. These correspond to the low six bits in an 8-bit byte, although the decimal values are further offset by the value 63. The **porder** string for these printers would be **,,6,5,4,3,2,1;63**, or alternately **0,0,6,5,4,3,2,1;63**.

# **Effect of Changing Printing Resolution**

If the control sequences to change the character pitch or the line pitch are used, the pin or dot spacing may change:

Changing the Character/Line Pitches	
cpi cpix	Change character pitch If set, cpi changes spinh
lpi lpix	Change line pitch If set, lpi changes spinv

**orhi**' and **orhi** are the values of the horizontal resolution in steps per inch, before using **cpi** and after using **cpi**, respectively. Likewise, **orvi**' and **orvi** are the values of the vertical resolution in steps per inch, before using **lpi** and after using **lpi**, respectively. Thus, the changes in the dots per inch for dot-matrix graphics follow the changes in steps per inch for printer resolution.

# **Print Quality**

Many dot-matrix printers can alter the dot spacing of printed text to produce *near-letter-quality* printing or *draft-quality* printing. It is important to be able to choose one or the other because the rate of printing generally decreases as the quality improves. Three strings describe these capabilities:

Print Quality	
snlq snrmq sdrfq	Set near-letter quality print Set normal quality print Set draft quality print

The capabilities are listed in decreasing levels of quality. If a printer doesn't have all three levels, the respective strings should be left blank.

# **Printing Rate and Buffer Size**

Because there is no standard protocol that can be used to keep a program synchronized with a printer, and because modern printers can buffer data before printing it, a program generally cannot determine at any time what has been printed. Two numeric capabilities can help a program estimate what has been printed.

Print Rate/Buffer Size	
cps	Nominal print rate in characters per second
bufsz	Buffer capacity in characters

**cps** is the nominal or average rate at which the printer prints characters; if this value is not given, the rate should be estimated at one-tenth the prevailing baud rate. **bufsz** is the maximum number of subsequent characters buffered before the guaranteed printing of an earlier character, assuming proper flow control has been used. If this value is not given it is assumed that the printer does not buffer characters, but prints them as they are received.

As an example, if a printer has a 1000-character buffer, then sending the letter "a" followed by 1000 additional characters is guaranteed to cause the letter "a" to print. If the same printer prints at the rate of 100 characters per second, then it should take 10 seconds to print all the characters in the buffer, less if the buffer is not full. By keeping track of the characters sent to a printer, and knowing the print rate and buffer size, a program can synchronize itself with the printer.

Note that most printer manufacturers advertise the maximum print rate, not the nominal print rate. A good way to get a value to put in for **cps** is to generate a few pages of text, count the number of printable characters, and then see how long it takes to print the text.

Applications that use these values should recognize the variability in the print rate. Straight text, in short lines, with no embedded control sequences will probably print at close to the advertised print rate and probably faster than the rate in **cps**. Graphics data with a lot of control sequences, or very long lines of text, will print at well below the advertised rate and below the rate in **cps**. If the application is using **cps** to decide how long it should take a printer to print a block of text, the application should pad the estimate. If the application is using **cps** to decide how much text has already been printed, it should shrink the estimate. The application will thus err in favor of the user, who wants, above all, to see all the output in its correct place.

# **Selecting a Terminal**

If the environment variable *TERMINFO* is defined, any program using Curses checks for a local terminal definition before checking in the standard place. For example, if *TERM* is set to **att4424**, then the compiled terminal definition is found in by default the path

### a/att4424

within an implementation-specific directory.

(The a is copied from the first letter of **att4424** to avoid creation of huge directories.) However, if *TERMINFO* is set to **\$HOME/myterms**, Curses first checks

# \$HOME/myterms/a/att4424

If that fails, it then checks the default pathname.

This is useful for developing experimental definitions or when write permission in the implementation-defined default database is not available.

If the *LINES* and *COLUMNS* environment variables are set, or if the program is executing in a window environment, line and column information in the environment will override information read by **terminfo**.

# **Application Usage**

The most effective way to prepare a terminal description is by imitating the description of a similar terminal in **terminfo** and to build up a description gradually, using partial descriptions with a screen-oriented editor, to check that they are correct. To easily test a new terminal description the environment variable *TERMINFO* can be set to the pathname of a directory containing the compiled description, and programs will look there rather than in the **terminfo** database.

# **Conventions for Device Aliases**

Every device must be assigned a name, such as **vt100**. Device names (except the long name) should be chosen using the following conventions. The name should not contain hyphens because hyphens are reserved for use when adding suffixes that indicate special modes.

These special modes may be modes that the hardware can be in, or user preferences. To assign a special mode to a particular device, append a suffix consisting of a hyphen and an indicator of the mode to the device name. For example, the **-w** suffix means *wide mode*; when specified, it allows for a width of 132 columns instead of the standard 80 columns. Therefore, if you want to use a vt100 device set to wide mode, name the device **vt100-w**. Use the following suffixes where possible:

Suffix	Meaning	Example
-w	Wide mode (more than 80 columns)	5410-w
-am	With automatic margins (usually default)	vt100-am
-nam	Without automatic margins	vt100-nam
-n	Number of lines on the screen	2300-40
-na	No arrow keys (leave them in local)	c100-na
-np	Number of pages of memory	c100-4p
-rv	Reverse video	4415-rv

### **Variations of Terminal Definitions**

It is implementation-defined how the entries in terminfo may be created.

There is more than one way to write a **terminfo** entry. A minimal entry may permit applications to use Curses to operate the terminal. If the entry is enhanced to describe more of the terminal's capabilities, applications can use Curses to invoke those features, and can take advantages of optimizations within Curses and thus operate more efficiently. For most terminals, an optimal **terminfo** entry has already been written.

# **Source File Syntax**

# **Notices**

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 United States of America

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for the Knowledge Centers. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation Site Counsel 2455 South Road Poughkeepsie, NY 12601-5400 USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

# Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

# **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

### Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

### **Commercial use**

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

# **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

# **IBM Online Privacy Statement**

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <a href="mailto:ibm.com/privacy/details">ibm.com/privacy/details</a> in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at ibm.com/software/info/product-privacy.

# **Policy for unsupported hardware**

Various z/OS® elements, such as DFSMS, JES2, JES3, and MVS™, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

# **Minimum supported hardware**

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: <a href="IBM Lifecycle Support for z/OS">IBM Lifecycle Support for z/OS</a> (www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

# **Trademarks**

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at Copyright and Trademark information (www.ibm.com/legal/copytrade.shtml).

### background

A property of a window that specifies a character (the background character) and a rendition to be used in a variety of situations.

#### **Curses window**

Data structures, which can be thought of as two-dimensional arrays of characters that represent screen displays. These data structures are manipulated with Curses functions.

# cursor position

The line and column position on the screen denoted by the terminal's cursor.

# empty wide-character string

A wide-character string whose first element is a null wide-character code.

# erase character

A special input character that deletes the last character in the current line, if there is one.

#### kill character

A special input character that deletes all data in the current line, if there are any.

# null chtype

A chtype with all bits set to zero.

### null wide-character code

A wide-character code with all bits set to zero.

### pad

A window that is not necessarily associated with a viewable part of a screen.

### parent window

A window that has subwindows or derived windows associated with it.

### rendition

The rendition of a character displayed on the screen is its attributes !and a color pair.

### **SCREEN**

An opaque Curses data type that is associated with the display screen.

### subwindow

A window, created within another window, but positioned relative to that other window. Changes made to a subwindow do not affect its parent window. A derived window differs from a subwindow only in that it is positioned relative to the origin of its parent window. Changes to a parent window will affect both subwindows and derived windows.

#### touch

To set a flag in a window that indicates that the information in the window could differ from the that displayed on the terminal device.

# wide-character code (C language)

An integer value corresponding to a single graphic symbol or control code.

### wide-character string

A contiguous sequence of wide-character codes terminated by and including the first null wide-character code.

# window

A two-dimensional array of characters representing all or part of the terminal screen. The term window in this document means one of the data structures maintained by the Curses implementation, unless specified otherwise. (This document does not define the interaction between the Curses implementation and other windowing system paradigms.)

# window hierarchy

The aggregate of a parent window and all of its subwindows and derived windows.

# **Index**

### Α

add_wch interface for enhanced curses 16 add_wchnstr interface for enhanced curses 17 addch interface for curses 13 addchstr interface for curses 13 addnstr interface for enhanced curses 14 addnwstr interface for enhanced curses 15 alternate character sets 172 application usage 176 area clears 156 attr_get interface for enhanced curses 18 attroff interface for curses 18

# В

basic capabilities <u>154</u>
baudrate interface for curses <u>19</u>
beep interface for curses <u>20</u>
bkgd interface for enhanced curses <u>21</u>
bkgrnd interface for enhanced curses <u>22</u>
border interface for enhanced curses <u>23</u>
border_set curses for enhanced curses <u>24</u>
box interface for curses <u>25</u>
box_set interface for enhanced curses <u>25</u>
buffer size <u>175</u>

### C

can_change_color interface for enhanced curses 26 capabilities that cause movement 168 cbreak interface for curses 28 chgat interface for enhanced curses 29 clear interface for curses 29 clearok interface for curses 30 clrtobot interface for curses 31 clrtoeol interface for curses 32 color manipulation 163 color_content interface for enhanced curses 32 color pairs interface for enhanced curses 32 cols interface for enhanced curses 33 conventions for device aliases 176 copywin interface for curses 33 cur_term interface for enhanced curses 35 current window structure 8 curs_set interface for enhanced curses 34 curscr interface for curses 34 curses environment, windows 7 curses interfaces 13 curses library 1 curses.h header 121 cursor motions 156

# D

def_prog_mode interface for curses 35

default window structure 7 defined capabilities 139 del_curterm interface for enhanced curses 37 delay_output interface for curses 36 delays 161 delch interface for curses 36 deleteln interface for curses 38 delscreen interface for curses 39 delwin interface for curses 39 derwin interface for curses 40 device capabilities 154 dot-matrix graphics 173 doupdate interface for curses 41 dupwin interface for enhanced curses 42

# Ε

echo interface for curses <u>42</u>
echo_wchar interface for enhanced curses <u>44</u>
echochar interface for enhanced curses <u>43</u>
effect of changing printing resolution <u>174</u>
endwin interface for curses <u>44</u>
erase interface for curses <u>45</u>
erasechar interface for curses 45

# F

filter interface for enhanced curses  $\underline{46}$  flash interface for curses  $\underline{47}$  flushinp interface for curses  $\underline{47}$  formal grammar  $\underline{138}$ 

### G

get_wch interface for enhanced curses  $\frac{54}{56}$  get_wstr interface for enhanced curses  $\frac{56}{56}$  getbegyx interface for curses  $\frac{48}{56}$  getbkgd interface for enhanced curses  $\frac{49}{56}$  getchar interface for enhanced curses  $\frac{49}{56}$  getchar interface for enhanced curses  $\frac{49}{56}$  getmaxys interface for enhanced curses  $\frac{50}{56}$  getmaxys interface for enhanced curses  $\frac{51}{52}$  getnstr interface for curses  $\frac{51}{52}$  getparyx interface for enhanced curses  $\frac{53}{52}$  getstr interface for curses  $\frac{54}{52}$  getwin interface for enhanced curses  $\frac{55}{52}$  getwin interface for curses  $\frac{56}{52}$  getyx interface for curses  $\frac{56}{52}$ 

#### Й

halfdelay interface for enhanced curses <u>56</u> has_colors interface for enhanced curses <u>57</u> has_ic interface for curses <u>57</u> headers <u>121</u> highlighting <u>158</u>

hline interface for enhanced curses <u>58</u>, <u>59</u> hline_set interface for enhanced curses <u>59</u>, 60

### Ι

idcok interface for enhanced curses 60 idlok interface for curses 60 immedok interface for enhanced curses 61 in wch interface for enhanced curses 72 in_wchnstr interface for enhanced curses 73 inch interface for curses 61 inchnstr interface for enhanced curses 62 init_color interface for enhanced curses 63 initializing curses 5 initscr interface for curses 63, 64 innstr interface for enhanced curses 64 innwstr interface for enhanced curses 65 ins nwstr interface for enhanced curses 69 ins wch interface for enhanced curses 70 ins wstr interface for enhanced curses 71 insch interface for curses 66 insdelln interface for enhanced curses 67 insert/delete character 157 insert/delete line 157 insertln interface for curses 67 insnstr interface for enhanced curses 68 insstr interface for enhanced curses 70 instr interface for enhanced curses 70 intrflush-interface for curses 71 inwstr interface for enhanced curses 73 is_linetouched interface for curses 74 isendwin interface for enhanced curses 74

# K

keyname interface for curses  $\underline{75}$  keypad  $\underline{160}$  keypad interface for curses  $\underline{76}$  killchar interface for curses  $\underline{77}$ 

#### L

leaveok interface for curses <u>77</u> line graphics <u>162</u> lines interface for enhanced curses <u>77</u> longname interface for curses 78

### М

mainframe
education xxvi
manipulating window data 11
meta interface for enhanced curses 78
minimum guaranteed limits 138
miscellaneous 165
move interface for curses 79
mv interface for curses 80
mvcur interface for enhanced curses 81
mvderwin interface for enhanced curses 82
mvprintw interface for curses 83
mvscanw interface for curses 83
mvwin interface for curses 84

### N

naming conventions 2
napms interface for curses <u>84</u>
newpad interface for curses <u>85</u>
newterm interface for curses <u>86</u>
newwin interface for curses <u>86</u>
nl interface for curses <u>87</u>
no interface for curses <u>87</u>
nodelay interface for curses <u>88</u>
noqiflush interface for enhanced curses <u>88</u>
notimeout interface for enhanced curses <u>88</u>

### 0

overlay interface for curses 90

### F

pads 8
pair_content interface for enhanced curses 90
parameterized strings 155
pechochar interface for enhanced curses 91
pnoutrefresh interface for curses 91
print quality 175
printer capabilities 166
printer resolution 166
printing rate 175
printwr interface for curses 92
putp interface for enhanced curses 92
putwin interface for enhanced curses 93

# 0

qiflush interface for enhanced curses 93

#### R

raw interface for curses 93
redrawwin interface for enhanced curses 94
refresh interface for curses 94
reset_prog_mode interface for curses 95
resetty interface for curses 95
restartterm interface for enhanced curses 96
ripoffline interface for enhanced curses 96
rounding values 166

### S

sample entry 152
savetty interface for curses 97
scanw interface for curses 97
scr_dump interface for enhanced curses 97
scrl interface for curses 98
scrollok interface for curses 99
selecting a terminal 175
set_curterm interface for enhanced curses 100
set_term interface for curses 100
setccar interface for enhanced curses 99
setscrreg interface for curses 100
setupterm interface for enhanced curses 101
similar terminals 166
slk_attroff interface for enhanced curses 101

source file syntax 137
special cases 165
specifying printer resolution 167
standend interface for curses 103
start_color interface for enhanced curses 104
status lines 161
stdscr interface for enhanced cursor 104
structure of a curses program 3
subpad interface for enhanced curses 104
subwin interface for curses 105
subwindows 8
syncok interface for enhanced curses 105

# Т

tabs and initialization  $\underline{160}$  term.h header for enhanced curses  $\underline{134}$  termattrs interface for enhanced curses  $\underline{106}$  terminfo source format  $\underline{137}$  terminology  $\underline{1}$  terminology  $\underline{1}$  terminame interface for enhanced curses  $\underline{106}$  tgetent interface for enhanced curses  $\underline{107}$  tigetflag interface for enhanced curses  $\underline{108}$  timeout interface for enhanced curses  $\underline{109}$  touchline interface for enhanced curses  $\underline{109}$  touchline interface for enhanced curses  $\underline{109}$  tputs interface for enhanced curses  $\underline{110}$  trademarks  $\underline{182}$  typeahead interface for enhanced curses  $\underline{110}$  types of capabilities in the sample entry  $\underline{152}$ 

# U

unctrl header <u>135</u> unctrl interface for curses <u>111</u> underlining <u>158</u> ungetch interface for enhanced curses <u>111</u> untouchwin interface for enhanced curses <u>112</u> use_env interface for enhanced curses 112

# V

variations of terminal definitions  $\underline{176}$  vidattr interface for enhanced curses  $\underline{113}$  visible bells  $\underline{158}$  vline interface for enhanced curses  $\underline{114}$  vline_set interface for enhanced curses  $\underline{114}$  vw_printw interface for enhanced curses  $\underline{115}$  vw_scanw interface for enhanced curses  $\underline{116}$  vwprintw interface for enhanced curses  $\underline{114}$  vwscanw interface for enhanced curses  $\underline{116}$ 

# W

w interface for curses <u>117</u> wunctrl interface for enhanced curses 119

### Z

z/OS Basic Skills Knowledge Center xxvi

# 

SA38-0690-40

