

# **OpenCL - DX11 Interoperability**

### 1 Overview

1.1 Location \$<AMDAPPSDKSamplesInstallPath>\samples\opencl\cl\1.x

#### 1.2 How to Run

See the Getting Started guide for how to build samples. You first must compile the sample.

Use the command line to change to the directory where the executable is located. The default executables are placed in  $\$  are placed in  $\$  and  $\$  are placed in  $\$  and  $\$  are placed in  $\$  are placed in  $\$  and  $\$  are placed in  $\$  and  $\$  are placed in  $\$ 

Before building this sample:

• Ensure you have the DirectX SDK or the SDK for Windows 8 installed.

Type the following command(s).

- SimpleDX11
   Produces the image of a moving sine wave with a bitmap in the background.
- 2. SimpleDX11 -h
  This prints the help message.

# 1.3 Command Line Options

Table 1 lists, and briefly describes, the command line options.

Table 1 Command Line Options

Short Form	Long Form	Description
-h	help	Display all command options and their respective meanings.
-q	quiet	Quiet mode. Suppresses all text output.
-e	verify	Verify results against reference implementation.
	dump	Dump binary image for all devices.
	load	Load binary image, and execute on device.
	flags	Specify compiler flags to build the kernel.
-р	platformId	Select the platform ID to be used (0 to N-1, where N is the number of available platforms).
-d	deviceId	Select device ID to be used (0 to N-1, where N is the number of available devices).
-A	version	AMD APP SDK version string.

## 2 Implementation Details

You must have a graphics driver and an OpenCL runtime that support the Direct3D 11 media sharing extension. To verify that they are installed, run clinfo from the command line, and check if your device supports the cl khr d3d11 sharing extension.

The following are the key functions of SimpleDX11:

```
clCreateFromD3D11BufferKHR
clEnqueueAcquireD3D11ObjectsKHR
clEnqueueReleaseD3D11ObjectsKHR
clGetDeviceIDsFromD3D11KHR
```

## 3 Algorithm

The following equation is used to compute the sine wave shown in the program:

```
y = \sin(x + t) \times \cos(x + t);
```

where x is the position on the X axis, and t is the time.

## 4 Sample Design

The input of this sample is a .bmp picture. This example reads in the data of the picture, calculates a sine sector using the OpenCL kernel, and renders and shows this picture using D3D11.

#### Steps:

 Create a D3D11 offscreen surface using the D3D11 API D3D11CreateDeviceAndSwapChain, and initialize DirectX11 as shown in Figure 1.




Figure 1 Initializing DX

2. Set up the Opencl environment as shown in Figure 2. Use <code>vetexBufPtr</code> to create an <code>ID3D11Buffer</code> with a pointer. Use <code>IASetVertexBuffers</code> to bind it to the device. Use <code>pfn\_clCreateFromD3D11BufferKHR</code> to create an Opencl buffer with <code>DirectX11</code> for sufrace sharing.




Figure 2 Setting Up CL

3. Run the kernel as shown in Figure 3. Before invoking clenqueueNDRangeKernel, use pfn\_clenqueueAcquireD3D11ObjectsKHR to acquire the D3D11 object. After using clenqueueNDRangeKernel, use pfn\_clenqueueReleaseD3D11ObjectsKHR to release the D3D11 object.






Figure 3 Running the Kernel

- 4. Copy the picture surface into the texture surface, and set the vertex for rendering.
- 5. Call the D3D11 function present to show the picture.

## 5 Sample Effect

The screen shots below show sample effects.





Contact

Advanced Micro Devices, Inc. One AMD Place P.O. Box 3453 Sunnyvale, CA, 94088-3453

Phone: +1.408.749.4000

URL:



The contents of this document are provided in connection with Advanced Micro Devices, Inc. ("AMD") products. AMD makes no representations or warranties with respect to the accuracy or completeness of the contents of this publication and reserves the right to make changes to specifications and product descriptions at any time without notice. The information contained herein may be of a preliminary or advance nature and is subject to change without notice. No license, whether express, implied, arising by estoppel or otherwise, to any intellectual property rights is granted by this publication. Except as set forth in AMD's Standard Terms and Conditions of Sale, AMD assumes no liability whatsoever, and disclaims any express or implied warranty, relating to its products including, but not limited to, the implied warranty of merchantability, fitness for a particular purpose, or infringement of any intellectual property right.

AMD's products are not designed, intended, authorized or warranted for use as components in systems intended for surgical implant into the body, or in other applications intended to support or sustain life, or in any other application in which the failure of AMD's product could create a situation where personal injury, death, or severe property or environmental damage may occur. AMD reserves the right to discontinue or make changes to its products at any time without notice.

For AMD Accelerated Parallel Processing:

Developing: developer.amd.com/

developer.amd.com/appsdk

#### **Copyright and Trademarks**

© 2015 Advanced Micro Devices, Inc. All rights reserved. AMD, the AMD Arrow logo, ATI, the ATI logo, Radeon, FireStream, and combinations thereof are trademarks of Advanced Micro Devices, Inc. OpenCL and the OpenCL logo are trademarks of Apple Inc. used by permission by Khronos. Other names are for informational purposes only and may be trademarks of their respective owners.