

Using the InterSystems Spark Connector

Version 2020.3 2021-02-04

Using the InterSystems Spark Connector
InterSystems IRIS Data Platform Version 2020.3 2021-02-04
Copyright © 2021 InterSystems Corporation
All rights reserved.

InterSystems, InterSystems IRIS, InterSystems Caché, InterSystems Ensemble, and InterSystems HealthShare are registered trademarks of InterSystems Corporation.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Memorial Drive, Cambridge, MA 02142, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)

Tel: +1-617-621-0700 Tel: +44 (0) 844 854 2917 Email: support@InterSystems.com

Table of Contents

| About This Book | 1 |
|---|----|
| 1 Introduction | 3 |
| 1.1 Features | 3 |
| 1.2 Data Source Provider Class Names | 3 |
| 1.3 Requirements and Configuration | 4 |
| 1.3.1 Requirements | 4 |
| 1.3.2 Optional Configuration Settings | 4 |
| 2 Spark Connector Data Source Options | 7 |
| 2.1 Using Spark Connector Generic Options | |
| 2.2 Query Options | |
| 2.3 Standard Save Options | |
| 2.4 InterSystems IRIS Save Options | 9 |
| 2.5 Connection Options | 11 |
| 2.6 Partition Tuning Options | 11 |
| 2.6.1 Implicit Partitioning | 12 |
| 2.6.2 Explicit Partitioning | 12 |
| 3 Using Spark Connector Extension Methods | 13 |
| 3.1 Using Query and Save Extension Methods | |
| 3.1.1 Using the iris() Save Method | |
| 3.1.2 Using the iris() and dataset[T]() Query Methods | 14 |
| 3.1.3 Using the rdd[T]() Query Method | |
| 3.2 Using Extension Methods to Set Data Source Options | 15 |
| 3.2.1 Setting the dbtable Query and Save Options | 15 |
| 3.2.2 Extension Methods for InterSystems IRIS Save Options | 16 |
| 3.2.3 Setting Connection Options with the address() Method | 17 |
| 3.2.4 Setting Partitioning Options with Query Method Parameters | 17 |
| 4 Spark Connector Best Practices | 19 |
| 4.1 Configuration | 19 |
| 4.1.1 Hardware | 20 |
| 4.2 Queries | 20 |
| 4.3 Loading Data | 21 |
| 5 Spark Connector Internals | 23 |
| 5.1 SQL/Spark Datatype Mapping | 23 |
| 5.2 Predicate Pushdown Operators | |
| 5.3 Logging | 25 |
| 5.4 Known Issues | 25 |
| 5.4.1 Pruning Columns with Synthetic Names | 25 |
| 5.4.2 Java 9 Compatibility | 26 |
| 5.4.3 Handling of TINYINT | 26 |
| 5.4.4 JDBC Isolation Levels | 26 |
| 6 Spark Connector Quick Reference | 27 |
| 6.1 Spark Connector Method Reference | |
| 6.1.1 DataFrameReader Extension Methods | 28 |
| 6.1.2 DataFrameWriter Extension Methods | 28 |

| 6.1.3 SparkSession and | SparkContext Extension Methods | 29 |
|------------------------|--------------------------------|----|
| 6.1.4 ml.PipelineModel | Extension Method | 30 |

About This Book

This book describes the InterSystems Spark Connector (com.intersystems.spark), an implementation of the Data Source API for Spark that allows the Spark data processing engine to make optimal use of the InterSystems IRIS ® data platform and its distributed data capabilities.

The following topics are discussed in this book:

- Introduction introduces Apache Spark and the InterSystems Spark Connector, and describes how to configure the Spark Connector on your system.
- Spark Connector Data Source Options provides a detailed description of all Spark Connector data source options.
- Using Spark Connector Extension Methods demonstrates the Spark Connector method interface.
- Spark Connector Best Practices describes ways to optimize Spark Connector hardware and software
- Spark Connector Internals useful information not otherwise covered.
- Spark Connector Quick Reference provides a quick reference to InterSystems-specific Scala extension methods provided by the Spark Connector API.

There is also a detailed Table of Contents.

Related Documents

The following documents contain related material:

- "Apache Spark Support" in the *Implementation Reference for Java Third Party APIs* provides some technical details about the InterSystems Spark Connector.
- Spark Connector API Reference is the online Scala documentation for the com.intersystems.spark API.
- The "Apache Spark" InterSystems overview page lists other resources for the InterSystems Spark Connector.
- *Using Java with InterSystems Software* provides an overview of all InterSystems Java technologies enabled by the InterSystems JDBC driver, and describes how to use the driver.

1

Introduction

The InterSystems IRIS® Spark Connector enables an InterSystems IRIS database to function as an Apache Spark data source. It implements a plug-compatible replacement for the standard Spark jdbc data source. This allows the results of a complex SQL query executed within the database to be retrieved by the Spark program as a Spark Dataset, and for a Dataset to be written back into the database as a SQL table.

1.1 Features

The Spark Connector has an intimate knowledge of —and tight integration with —the underlying database server that provides several advantages over the standard Spark jdbc data source:

• Predicate Push Down

The Connector recognizes a richer set of operators than the standard jdbc data source, allowing more operations to be 'pushed down' into the underlying database for execution.

• Shard Aware

An InterSystems IRIS database can be *sharded*, meaning that tables that are transparently partitioned across multiple servers running on different computers. The Connector allocates compute tasks so that each Spark executor is colocated with the server from which it draws its data. This not only reduces the movement of data across the network, but, more importantly, allows the Spark program's performance to scale linearly with the number of shards, and so size of the data set, on which it operates.

• Implicit Parallelism

The Connector exploits the server's innate ability to automatically parallelize certain queries and so allow large result sets to be returned quickly to the Spark driver program through multiple concurrent network connections. By contrast, the standard jdbc data source requires the user to explicitly specify how the result set is to be partitioned, which in practice is often very difficult to do well.

1.2 Data Source Provider Class Names

Spark data sources are accessed through provider class names. The standard Spark jdbc data source provider class is named org.apache.spark.sql.execution.datasources.jdbc.JdbcRelationProvider, and can be used by specifying it in a call to **format()** as demonstrated in the following example:

```
var df = spark.read
   .format("org.apache.spark.sql.execution.datasources.jdbc.JdbcRelationProvider")
   .option("dbtable","mytable").load()
```

Since the full class name is very awkward to use, it is normally specified with the short alias jdbc:

```
var df = spark.read.format("jdbc").option("dbtable","mytable").load()
```

The InterSystems Spark Connector data source is referenced in exactly the same way, using the full provider class name com.intersystems.spark or the short alias iris:

```
var df = spark.read.format("iris").option("dbtable","mytable").load()
```

Important:

The terms jdbc and iris (lower case, in the same typography as other class names) are used frequently in this book, and always refer specifically to the data source provider class names, never to Java JDBC or InterSystems IRIS.

1.3 Requirements and Configuration

1.3.1 Requirements

The Spark Connector requires the following:

- InterSystems IRIS for more information on configuration, see "Spark Connector Best Practices" later in this book.
- Spark 2.0+ the Connector has been primarily tested against Spark version 2.1.1 under JVM 1.8 u144, using the Spark Standalone cluster manager.
- Java 1.8 InterSystems IRIS does not support earlier versions. Apache Spark does not currently support JVM 1.9.

1.3.2 Optional Configuration Settings

The Connector recognizes a number of configuration settings that parameterize its operation. These are parsed from the Apache Spark SparkConfconfiguration structure at startup and may be specified by:

- the file spark-defaults.conf associated with the Spark cluster.
- values for the --conf option passed on the command line.
- arguments to the SparkConf() constructor or its set() member functions, called from within the driver application itself.

The *url*, *user*, and *password* options specify connection string values for a read or write. The default values are automatically defined using information from the default InterSystems IRIS master instance specified in the SparkConf configuration. Connection options can be explicitly specified in a read or write operation (see "Connection Options") to override the defaults.

spark.iris.master.url

A string of the form "IRIS: //host:port/namespace" that specifies the address of the default Spark master server to connect to if none is.

· spark.iris.master.user

The user account with which to connect to the master server.

spark.iris.master.password

The password for the user account with which to connect to the master server.

Default values are also assigned to the following settings:

spark.iris.master.expires

A positive integral number of seconds after which a connection to an instance is judged to have expired and is automatically closed and garbage collected. Default = 60.

spark.iris.worker.host

An optional string of the form pattern => rewrite where:

- pattern is a regular expression (which may contain parenthesized groups)
- rewrite is a replacement string (which may contain \$ references to those groups)

If specified, this setting describes how to convert the host name of an InterSystems IRIS server into the host name of the preferred Spark worker that should handle requests to read and write dataset partitions to it.

The most common cluster configuration is to arrange that a Spark worker runs on each machine that hosts an InterSystems IRIS server, for then records need not travel across the network. It can happen, however, that the host name by which the master server knows its shard server differs from the host name by which the Spark master knows its worker, even though they are running on the very same machine. Their host names could be aliased by a DNS server, for example, or could be running in separate Docker containers.

This setting offers a means of defining at install time a function that maps between the two host names.

For more information, see the Apache Spark documentation on "Spark Configuration" and the org.apache.spark.SparkConf class.

2

Spark Connector Data Source Options

The Spark Connector iris data source and the standard Spark jdbc data source both use the generic option interface, which sets options by passing option keys and values to the **option()** or **options()** methods. The iris data source supports the same set of options as the Spark jdbc data source, and also includes several options implemented specifically for the InterSystems IRIS® SQL dialect.

The following sections provide detailed information on all supported iris data source options:

- Using Spark Connector Generic Options provides a brief overview of generic data source option support.
- Query Options *dbtable* and *fetchsize* are standard read options. The iris data source also supports the *query* key, which is an optional synonym for *dbtable*.
- Standard Save Options mode, batchsize, and isolationlevel are standard write options.
- InterSystems IRIS Save Options *description*, *publicrowid*, *shard*, and *autobalance* are write options supported only by iris.
- Connection Options *url*, *user*, and *password* are standard options that explicitly specify connection string values for a read or write.
- Partition Tuning Options partitionColumn, lowerBound, upperBound, numPartitions, and mfpi are standard options that specify how a query will be partitioned.

In all of the following examples, *spark* is an instance of SparkSession, and *df* is an instance of DataFrame.

Note: In this book, the terms jdbc and iris (lower case, in the same typography as other class names) are always data source provider class names, not references to Java JDBC or InterSystems IRIS. See "Data Source Provider Class Names" for details.

2.1 Using Spark Connector Generic Options

Both the iris data source and the jdbc data source provide a generic option interface to set data source options. For example, the following code uses the generic Spark jdbc data source with the InterSystems JDBC driver to load a table from the InterSystems IRIS database:

Most options supported by the jdbc data source can also be used in exactly the same way with the iris data source. However, the same table loading code can be much simpler when using the Spark Connector iris data source because most of the corresponding iris options have defaults (see "Requirements and Configuration" for details). For example:

The most important difference in this example is that the **format()** call specifies the Spark Connector's iris data source provider class, rather than the generic jdbc provider class. We omit the *driver* option because the Spark Connector always uses the built-in InterSystems JDBC driver. The *url*, *user*, and *password* options can also be omitted because iris can use default values obtained from Spark configuration settings (see "Connection Options").

2.2 Query Options

The Spark jdbc format and the iris format can both use dbtable and fetchsize when loading a table or performing a query.

dbtable (or query)

The Spark jdbc format and the iris format both use *dbtable* to specify a table name or SQL query. Any string that would be valid in a FROM clause can be used as a *dbtable* value. The *dbtable* key is also a valid write option (see "Standard Save Options").

The iris *query* key is just a synonym for *dbtable*. This optional key can improve code readability by distinguishing a SQL query from a table name. For example:

The Spark Connector also offers several alternative query methods that allow this option to be set as a method parameter (see "Using Query and Save Extension Methods").

fetchsize

The Spark jdbc format and the iris format both use *fetchsize* to specify the number of rows to fetch per server round trip. Defaults to 1000. This option is applied when loading a table or performing a query, and will be ignored by write operations.

2.3 Standard Save Options

The Spark jdbc format and the iris format can both use dbtable, mode, batchsize, and isolationlevel when saving a table.

dbtable

The Spark jdbc format and the iris format both use *dbtable* to specify a table name when saving. This key is also a valid read option (see "Query Options").

This option can also be specified as a parameter of the DataFrameReader.iris() extension method (see "Using Extension Methods to Set Data Source Options").

mode

Describes how to behave if the target table already exists. Can be one of OVERWRITE, APPEND, IGNORE, or ERROR, and defaults to ERROR. These settings correspond to the values defined in the SaveMode enum (see org.apache.spark.sql.SaveMode for more information). This option is applied when saving a table, and will be ignored by read operations.

```
df.write.format("iris")
    .option("mode","OVERWRITE") //overwrite any existing table
    .save()
```

This option can also be set by the standard DataFrameWriter.mode() method.

batchsize

Specifies an integer number of rows to insert per server round trip. Defaults to 1000. This option is applied when saving a table, and will be ignored by read operations.

isolationlevel

Sets the JDBC transaction isolation level. Can READ_UNCOMMITTED (the default) or NONE. These values correspond to the transaction isolation levels defined in java.sql.Connection. This option is applied when saving a table, and will be ignored by read operations.

2.4 InterSystems IRIS Save Options

The *description*, *publicrowid*, *shard*, and *autobalance* options are supported only by the iris data source, and are used to set certain options unique to InterSystems IRIS. These options are applied when saving a table, and will be ignored by read operations.

description

Specifies an optional description to document the newly created table. Will be ignored when appending to a table that already exists. Defaults to " ".

```
df.write.format("iris")
    .option("description", "This is a table of no importance whatsoever.")
    save()
```

See "CREATE TABLE" in the InterSystems SQL Reference for more information on this option.

This option can also be set with the DataFrameReader.description() extension method (see "Setting Save Options with Extension Methods").

publicrowid

Specifies whether the master row ID column for the newly created table is to be made publicly visible. Will be ignored when appending to a table that already exists. Defaults to "false".

```
df.write.format("iris")
    .option("publicrowid","false")
    .save()
```

See "CREATE TABLE" in the InterSystems SQL Reference for more information on this option.

This option can also be set with the DataFrameReader.publicRowID() extension method (see "Setting Save Options with Extension Methods").

shard

Determines sharding for the newly created table. Will be ignored when appending to a table that already exists. The value can be either a boolean indicating whether the newly created table is to be sharded, or a sequence of field name strings (possibly empty) to be used as the user defined shard key.

• A boolean value of "true" indicates that the records of the table are to be distributed across the cluster using a system assigned sharding key. Boolean "false" (the default) indicates that records should be stored locally on the shard master itself (see "Spark Connector Best Practices").

```
df.write.format("iris")
    .option("shard","false") // store locally
    .save()
```

• A field name or sequence of names indicates that the records of the table are to be distributed across the cluster using the given sequence of fields to compute the shard key:

• If the sequence is empty then the table will be sharded on the system assigned key:

This option can also be set with the DataFrameReader.shard() extension method (see "Setting Save Options with Extension Methods").

autobalance

When writing a dataset to a table that is sharded on a system assigned shard key, an *autobalance* value of "true" (the default) specifies that the inserted records are to be evenly distributed amongst the available shards. Value "false" specifies that every dataset partition should attempt to write its records directly into the shard on which its Spark executor also runs.

```
df.write.format("iris")
    .option("autobalance","false") // disable autobalancing)
    .save()
```

In an optimally configured cluster, a Spark worker runs on each shard server (see "Spark Connector Best Practices"). Writing a dataset with the *autobalance* option disabled can be faster in this configuration, since records no longer need to travel across the network to reach their destination shard. However, this shifts the responsibility for balancing to the Spark application, which may be required to partition the dataset appropriately before writing it to the cluster.

This option will be ignored when writing to a table that is not sharded, or when writing to a table sharded on a user defined shard key.

This option can also be set with the DataFrameReader.autobalance() extension method (see "Setting Save Options with Extension Methods").

2.5 Connection Options

The *url*, *user*, and *password* options explicitly specify connection string values for a read or write. If these options are not set, they will be automatically defined using information from the default InterSystems IRIS master instance specified in the SparkConf configuration (see "Default Configuration Settings"). When set, these options override the default for the duration of the current read or write operation.

url, user, and password

The value of *url* is a string of the form "IRIS://[host]:[port]/[namespace]" that names the master InterSystems IRIS instance with which the data is to be loaded or saved. The values of *user* and *password* are strings containing the account and password required to make the connection to *url*.

For example, the following call specifies the connection required to read a table named mytable in the USER namespace:

For more information on constructing a URL string, see "Defining a JDBC Connection URL" in *Using Java with InterSystems Software*.

These options can also be set with the DataFrameReader.address() extension method (see "Setting Connection Options with the address() Method").

Note:

The standard Spark jdbc format also offers the *driver* option, which specifies the class name of the JDBC driver to use. The Spark Connector iris format ignores this option (if specified) because it always uses the InterSystems JDBC driver, which is embedded within the Connector itself.

2.6 Partition Tuning Options

These options determine how a read operation will be partitioned. When reading data, the Connector attempts to negotiate with the server as to how best to partition the resulting Dataset. Depending on how the cluster is configured, each partition can potentially run in parallel within its own Spark executor and establish its own independent connection into the shard from which it draws its data.

Partitioning requests can be either implicit or explicit:

- Implicit Partitioning mfpi specifies the maximum number of partitions to create, and the Connector automatically sets other partitioning parameters.
- Explicit Partitioning partitionColumn, lowerBound, upperBound, and numPartitions provide the Connector with detailed instructions for partitioning.

The Spark Connector also offers several extension methods that allow these options to be set as method parameters (see "Setting Partitioning Options with Query Method Parameters").

2.6.1 Implicit Partitioning

The *mfpi* option (*m*aximum number of *p*artitions *per instance*) specifies an upper limit to the number of partitions that the server will create per queried instance in any implicit query factorization. The default is "1".

This option is applied when reading, and will be ignored by write operations. It is also ignored if a value has been specified for *numPartitions*, which takes precedence over *mfpi* (see "Explicit partitioning").

Implicit partitioning with "mfpi"

Using the *mfpi* option, you could execute a query with the following statement:

2.6.2 Explicit Partitioning

The following options provide an explicit description of how to partition the queries sent to each distinct instance:

- partitionColumn String name of integer valued column in the result set to be used for partitioning.
- lowerBound Long minimum value of partitionColumn.
- upperBound Long maximum value of partitionColumn.
- numPartitions Int number of partitions per instance to create.

These options correspond exactly to the similarly named arguments for the Apache Spark DataFrameReader.jdbc() method. See the documentation on that method for more information.

Explicit partitioning options take precedence over the *mfpi* option (described in the previous section). They are applied when reading, and will be ignored by write operations.

Explicit partitioning with partitionColumn, lowerBound, upperBound, and numPartitions

Using these options, you could execute a query by calling:

3

Using Spark Connector Extension Methods

This chapter discusses a set of InterSystems-specific Scala extension methods provided by the Spark Connector. These methods extend the generic Spark interface with implicit Scala classes and types that provide more convenience and better type safety.

The following topics are discussed:

- Using Query and Save Extension Methods describes extension methods that simplify reading and writing a DataFrame,
 Dataset, or RDD.
- Using Extension Methods to Set Data Source Options describes extension methods and method parameters that
 provide alternate ways to set data source options.

All of the examples in this chapter assume that *spark* is an instance of SparkSession and *df* is an instance of DataFrame.

Note: In this book, the terms jdbc and iris (lower case, in the same typography as other class names) are always data source provider class names, not references to Java JDBC or InterSystems IRIS®. See "Data Source Provider Class Names" for details.

3.1 Using Query and Save Extension Methods

The following topics are discussed:

- Using the iris() Save Method describes an extension method that simplifies saving a DataFrame.
- Using the iris() and dataset[T]() Query Methods describes extension methods that return query results as a DataFrame
 or Dataset.
- Using the rdd[T]() Query Method describes an extension method that returns query results as an RDD.

3.1.1 Using the iris() Save Method

The following example demonstrates a standard way to save an existing DataFrame df to a table named Owls:

```
df.write.format("iris").option("dbtable","Owls").save()
```

The Spark connector provides the DataFrameWriter.iris() extension method, which performs the same task in a much simpler manner. The following code is functionally identical to the previous example:

```
df.write.iris("Owls")
```

In this example, the *dbtable* option is replaced by an argument, the format is automatically set to iris, and the call to **save**() is made internally.

3.1.2 Using the iris() and dataset[T]() Query Methods

The following example demonstrates a standard way to save an existing DataFrame df to a table named Owls, and then query the database to read the table back into new DataFrame df2:

```
val df2 = spark.read.format("iris").option("dbtable","SELECT * FROM Owls").load()
```

The Spark connector provides the DataFrameWriter.iris() method to perform the same task in a much simpler manner. The following code is functionally identical to the previous example:

```
val df2 = spark.read.iris("SELECT * FROM Owls")
```

In this example, the *dbtable* option is replaced by an argument, the format is automatically set to iris, and the call to **load()** is made internally.

Similarly, the SparkSession.dataset[T]() executes a query or loads a table and returns results as a Dataset of the specified type.

3.1.3 Using the rdd[T]() Query Method

SparkContext.rdd[T]() executes a query or loads a table, formats each row of the result set with the provided function, and returns an RDD[T] containing the formatted rows.

Defining a Type Format[T] function

The SparkContext.rdd[T]() method executes a query on the cluster and returns an RDD where each element has been formatted as an instance of the specified type T. Formatting is performed by a user-defined function of type Format[T]. For example, the following code specifies a function pair, which extracts a pair of strings from the first two columns of the current row of a result set:

```
val pair: Format[(String,String)] = r => (r.getString(1),r.getString(2))
```

This function constructs an RDD[(String, String)] from the results of any query of the cluster that includes at least two strings per record.

Using SparkContext.rdd[T]()

The following example calls **rdd**[T]() using the previously defined Format[T] function:

Note: Format functions will be invoked for each and every record requested by the client, and therefore should normally restrict themselves to calling only pure (that is, non side effecting) member functions of the result set (**getInt**, **getDouble**, **getDate** and the like).

3.2 Using Extension Methods to Set Data Source Options

In addition to generic option support (see "Spark Connector Data Source Options"), the Spark Connector also provides a number of methods that allow many of these options to be specified as method arguments. These methods can simplify code and improve type safety by providing alternatives to the generic option interface.

The standard way to set data source options is with the generic option interface (see "Using Spark Connector Generic Options"), but most data source options can also be set with Spark Connector extension methods or method parameters.

- Setting the dbtable Query and Save Options setting dbtable with query methods and the iris() save method.
- Extension Methods for InterSystems IRIS Save Options setting the description, publicrowid, shard, and autobalance options.
- Setting Connection Options with the address() Method setting the url, user, and password options
- Setting Partitioning Options with Query Method Parameters setting the *mpfi*, *partitionColumn*, *lowerBound*, *upperBound*, and *numPartitions* with optional query method parameters.

Note: This chapter does not discuss these options in detail. For complete information on data source option settings, see the descriptions in the previous chapter ("Spark Connector Data Source Options").

3.2.1 Setting the dbtable Query and Save Options

The *dbtable* option is specified as the first argument of all query and save extension methods (see "Using Query and Save Extension Methods" earlier in this chapter), as demonstrated in the following examples

Setting the dbtable query option with query methods

All of the query extension methods (DataFrameReader.iris(), SparkContext.rdd[T](), and SparkSession.dataset[T]()) accept the *dbtable* (alias *query*) option as the first argument. For example, the following code fragments specify *dbtable* as either a table name or an SQL query, and use the DataFrameReader.iris() method to set the format, set the *dbtable* option, and call load():

```
var df = spark.read.iris("mytable")  // Load a table
var df = spark.read.iris("SELECT * FROM mytable")  // Perform a query

rather than:

var df = spark.read.format("iris").option("dbtable","mytable").load()  // Load a table

var df = spark.read.format("iris").option("query","SELECT * FROM mytable").load()  // Perform a query
```

See "Using the iris() and dataset[T]() Query Methods" and "Using the rdd[T]() Query Method" earlier in this chapter for detailed information about the query methods. For more on the *dbtable* query option, see the dbtable entry under Standard Save Options in the previous chapter.

Setting the dbtable save option with DataFrameWriter.iris()

When saving with the DataFrameWriter.iris() extension method, the *dbtable* option is specified as the method parameter. For example, the following code uses DataFrameWriter.iris() to set the format, set the *dbtable* option, and call save():

```
spark.write.iris("mytable")
rather than:
```

See "Using the iris() Save Method" earlier in this chapter for detailed information about this extension method. For more on the *dbtable* save option, see the dbtable (or query) entry under Query Options in the previous chapter.

3.2.2 Extension Methods for InterSystems IRIS Save Options

The save options (*description*, *publicrowid*, *shard*, and *autobalance*) can also be set with DataFrameWriter extension methods. See "InterSystems IRIS Save Options" in the previous chapter for detailed information on these options.

description()

The DataFrameWriter.description() extension method is an alternate way to set the *description* option. For example, you can use the following code:

```
spark.write.description("This is a table.")
rather than:
df.write.format("iris").option("description","This is a table.").save()
```

See description in the previous chapter for more information on this option.

publicRowID()

The DataFrameWriter.publicRowID() extension method is an alternate way to set the *publicrowid* option. For example, you can use the following code:

```
spark.write.publicRowID("false")
rather than:
df.write.format("iris").option("publicrowid","false").save()
```

See publicrowid in the previous chapter for more information on this option.

shard()

The DataFrameWriter.shard() extension method is an alternate way to set the *shard* option. For example, you can use the following code:

```
spark.write.shard("columnA","columnX")
rather than:
df.write.format("iris") .option("shard",Seq("columnA","columnX")).save()
```

Notice that this method call automatically interprets the arguments as a Seq.

See shard in the previous chapter for more information on this option.

autobalance()

The DataFrameWriter.autobalance() extension method is an alternate way to set the *autobalance* option. For example, you can use the following code:

```
spark.write.autobalance("false")
rather than:
```

```
df.write.format("iris").option("autobalance", "false").save()
```

See autobalance in the previous chapter for more information on this option.

3.2.3 Setting Connection Options with the address() Method

The *url*, *user*, and *password* options explicitly specify connection string values for a query or save (see "Connection Options" in the previous chapter for detailed information and examples). These connection options can also be set as parameters of the DataFrameReader.address() and DataFrameWriter.address() extension methods, as demonstrated in the following examples.

Querying with DataFrameReader.address()

The following code uses the DataFrameReader.address() method to set the *url*, *user*, and *password* options, and then uses the DataFrameReader.iris() method to set the format, set the *dbtable* option, and call **load**():

Saving with DataFrameWriter.address()

The following code uses the DataFrameWriter.address() method to set the *url*, *user*, and *password* options, and then uses the DataFrameWriter.iris() method to set the format, set the *dbtable* option, and call save():

3.2.4 Setting Partitioning Options with Query Method Parameters

All of the query extension methods (DataFrameReader.iris(), SparkContext.rdd[T](), and SparkSession.dataset[T]()) accept optional arguments that specify how to partition a query. See "Using Query and Save Extension Methods" earlier in this chapter for a discussion of query methods. The following examples use the iris() method, but all three methods accept the same set of arguments.

Implicit partitioning with the mfpi parameter

The *mfpi* option can be specified as a argument when reading with any of the query extension methods. For example, the following call to DataFrameReader.iris() specifies the first argument as the value for *dbtable* and the second argument as the value for *mfpi*:

```
var df = spark.read.iris("SELECT * FROM table",2)
```

This call is exactly equivalent to the following example:

See "Implicit Partitioning" in the previous chapter for more information on this option.

Explicit partitioning with the partitionColumn, lowerBound, upperBound, and numPartitions parameters

These options can be specified as arguments when reading with any of the query extension methods. For example, the following call to DataFrameReader.iris() specifies the first argument as the value for *dbtable* and the remaining arguments as the values for *partitionColumn*, *lowerBound*, *upperBound*, and *numPartitions*:

```
var df = spark.read.iris("SELECT * FROM mytable", "column", 0,10000, 2)
```

This call is exactly equivalent to the following example:

See "Explicit Partitioning" in the previous chapter for more information on these options.

4

Spark Connector Best Practices

This chapter describes the preferred way to set up a Spark cluster on the InterSystems IRIS® data platform. The following topics are discussed:

- Configuration describes and explains the preferred Spark cluster topology.
- Queries provides examples that demonstrate how to optimize query performance.
- Loading Data discusses how to optimize loading of large datasets into sharded clusters.

Note: Pre-installed Spark in Containers

The InterSystems Cloud Manager (ICM) provides you with a simple, intuitive way to provision cloud infrastructure and deploy services on it. See the "Using ICM" chapter of the *InterSystems Cloud Manager Guide* for instructions on how to configure and deploy containers in a topology similar to the one described in this chapter. The "Deploy and Manage Services" section provides specific instructions for using images that include pre-installed instances of Spark.

4.1 Configuration

An InterSystems IRIS database can be sharded, meaning that tables that are transparently partitioned across multiple servers running on different computers. The Connector allocates compute tasks so that each Spark executor is collocated with the server from which it draws its data. This reduces the movement of data across the network, and more importantly, allows the Spark program's performance to scale linearly with the number of shards (and therefore the size of the data set) on which it operates.

The optimum topology is as follows:

- The Spark cluster runs in what the Spark documentation refers to as Standalone Mode.
- The InterSystems IRIS shard master I0 and Spark master S0 both run on host machine H0.
- A Spark worker w0 also runs on host machine H0.
- Each additional host machine **H***i* hosting an InterSystems IRIS shard server instance **I***i* runs exactly one Spark worker **w***i*
- Optionally, each host machine **H***i* hosting an InterSystems IRIS shard server instance **I***i* also runs exactly one HDFS data node **d***i*.

| Host machines | IRIS shard master/servers | Spark master/workers | HDFS data nodes |
|-----------------------|---------------------------|---------------------------------------|-----------------------|
| H 0 | Io (shard master) | So (Spark master) | D 0 |
| | | wo (Spark worker) | d 0 |
| H 1 H n | I1In (shard servers) | w 1 w n (Spark workers) | d 1 d n |

While other topologies are certainly possible and will produce correct results, this specific topology will generally perform best for the following reasons:

- Each Spark worker is collocated with exactly one InterSystems IRIS shard server, allowing the Connector to ensure
 that each process is executed on the same machine as the data on which it depends. This significantly reduces movement
 of data across the network, and allows performance to scale linearly with the number of shards.
- Each Spark worker creates Spark executor processes running in parallel. The Spark master is aware of the number of
 processing cores available, and distributes tasks to executors accordingly. There is no advantage in running more than
 one Spark worker on each host machine.
- Any tables that are not sharded will be stored on InterSystems IRIS shard master Io. A Spark worker wo should be present on Ho, allowing the processes that use these tables to be collocated with the data.
- When loading large data sets into a cluster, there are significant advantages to installing HDFS on the nodes of the cluster, running one HDFS data node **d***i* on each host machine **H***i*.

4.1.1 Hardware

Hardware configuration generally involves a trade-off between a few powerful host machines and a larger number of less powerful hosts. Given this choice, the optimum configuration will ensure that the largest tables in the database fit comfortably within the collective RAM of all the shard servers in the cluster. In this configuration, the cluster effectively behaves as a scalable cache. This is especially true for large scale analytics of predominantly static or infrequently changing 'data lakes'.

Special consideration should be given to the machine **H**0 that hosts the InterSystems IRIS shard master. Complex queries, particularly those with aggregates, ORDER BY, TOP, or DISTINCT clauses and the like, generally require a non-trivial reduction of the intermediate results returned by the individual shard servers. This computation is staged in temporary tables on the shard master. For a query that returns a large result set that must be sorted, for example, the reduction step on the shard master (the sort) can easily dominate the rest of the computation.

4.2 Queries

When designing an application to run in this environment, there is frequently a choice as to where the aggregation will take place. Consider the following Spark queries, where *A* is a sharded table with a numeric column named *i*. All three queries compute the same single value, namely the maximum value of column *i*, but each one accomplishes this task a different way:

Example 1 — parallelized fetch and aggregate

```
> val q1 = Spark.read.iris("A").selectExpr("MAX(i)")
res1: org.apache.Spark.sql.DataFrame = [max(i): int]
> Spark.read.iris("A").createOrReplaceTempTable("A")
```

Example 2 — using Spark SQL interpreter

```
> val q2 = Spark.sq1("SELECT max(i) FROM A")
res2: org.apache.Spark.sql.DataFrame = [max(i): int]
```

Example 3 — using InterSystems IRIS query optimization

```
> val q3 = Spark.read.iris("SELECT max(i) FROM A")
res3: org.apache.Spark.sql.DataFrame = [max(i): int]
```

Example 1 fetches the entire column i of table A (and only column i, not all of A, thanks to the Connector's ability to automatically prune columns) into the Spark workers. Each worker then computes the maximum value for its portion of the data. These local maximum values are then sent to the Spark master, which picks the single greatest value amongst them and returns it to the driver program in a DataFrame.

To see what's going on, it can be helpful to take a look at the output of the DataFrame's **explain** operator:

Notice:

- the Scan, which corresponds to the parallelized fetch of the data in each of the workers,
- the inner HashAggregate, which corresponds to the work that each worker will perform in parallel in locating its local maximum, and
- the Exchange and subsequent HashAggregate, which corresponds to the transmission of the local maximum values back to the master and subsequent selection of the global maximum.

Example 2 demonstrates the use of Spark's own built-in SQL interpreter. For more complex queries, especially those that are federated across multiple databases or other disparate sources of data, this can be provide a powerful and flexible way of treating the various sources like a single giant database.

However, beneath the covers exactly the same work is performed as in Example 1, as can be seen with the **explain** operator.

Example 3 on the other hand, demonstrates the power of using Spark with InterSystems IRIS: now the entire query is performed within the InterSystems IRIS database, and is thus amenable to the InterSystems IRIS query optimization, the use if indexes, and so on:

```
> q1.explain
== Physical Plan ==
*Scan Relation(select max(i) from B) [Aggregate_1#215] ReadSchema: struct<Aggregate_1:int>
```

4.3 Loading Data

Spark is particularly useful for loading large datasets into sharded InterSystems IRIS clusters.

For best performance and maximum parallelism, you will want to install HDFS on the nodes of the cluster too. In this scenario, each host $\mathbf{H}i$ should also acts as a data node $\mathbf{d}i$.

Example: loading a large CSV file into a sharded table.

```
~> hadoop fs -put x.csv /x.csv
# Copy file "X.csv" into HDFS as /x.csv
```

And now from within Spark:

In this example, each Spark worker reads its own locally available portion of the original file, which was split and distributed to the nodes of the cluster automatically by HDFS in step 1, and writes the parsed records to its own collocated shard. No data moves across the network once the source file has been moved into HDFS.

5

Spark Connector Internals

This chapter covers datatype mapping, predicate pushdown operators, and other useful information not otherwise available.

- SQL/Spark Datatype Mapping a table of SQL datatypes and their corresponding Spark datatypes.
- Predicate Pushdown Operators a list of Spark operators that the Spark Connector recognizes as having direct counterparts within the underlying database.
- Logging the Spark connector, like the Spark system itself, uses Log4J to log events of interest.
- Known Issues problems to be aware of.

5.1 SQL/Spark Datatype Mapping

Internally, the Connector uses the InterSystems JDBC driver to read and write values to and from servers. This constrains the data types that can be serialized in and out of database tables via Spark. The JDBC driver exposes the JDBC data types in the following tables as available projections for InterSystems IRIS® data types, and converts them to and from the listed Spark Catalyst types (members of the org.apache.spark.sql.types package).

This mapping between Spark Catalyst and JDBC data types differs subtly from that used by the standard Spark jdbc data source, as noted in the following sections.

JDBC / Spark Value Type Conversions

The following JDBC value types are exposed, and are converted directly to and from the listed Spark Catalyst types:

| JDBC Value Type | Spark Type |
|-----------------|-------------|
| BIT | BooleanType |
| TINYINT | ByteType |
| BIGINT | LongType |
| INTEGER | IntegerType |
| SMALLINT | ShortType |
| DOUBLE | DoubleType |

Note:

- Value types are all qualified as being NOT NULL when saved to a table.
- Spark Catalyst distinguishes between the different sizes of integer TINYINT, SMALLINT, INTEGER, BIGINT, whereas the Spark jdbc data source does not.
- Spark Catalyst FloatType is mapped to DOUBLE (and deprecated InterSystems class %Library.Float is projected
 as type DOUBLE).

JDBC / Spark Object Type Conversions

The following JDBC object types are exposed, and are represented by the listed Spark Catalyst types. Bidirectional conversion is not supported for LONGVARCHAR, GUID, LONGVARBINARY, and TIME because these JDBC types do not correspond to unique Spark Catalyst types:

| JDBC to Spark Catalyst projections | | Spark Catalyst to JDBC projections | |
|------------------------------------|------------------|------------------------------------|------------------|
| JDBC Object Type | Spark Type | Spark Type | JDBC Object Type |
| VARCHAR, GUID, and LONGVARCHAR | StringType | StringType | VARCHAR |
| VARBINARY and LONGVARBINARY | BinaryType | BinaryType | VARBINARY |
| NUMERIC(p,s) | DecimalType(p,s) | DecimalType(p,s) | NUMERIC(p,s) |
| DATE | DateType | DateType | DATE |
| TIMESTAMP and TIME | TimestampType | TimestampType | TIMESTAMP |

Note:

- In NUMERIC and DecimalType the positive integers *p* and *s* respectively denote the precision and scale of the numeric representation.
- There is no Spark SQL encoder currently available for type java.sql.Time, so JDBC TIME is represented as Spark TimestampType.
- Spark Catalyst (unlike the Spark jdbc data source) recognizes the UNIQUEIDENTIFIER data type, which is not widely supported by all JDBC vendors
- JDBC type GUID is the JDBC representation of Intersystems SQL datatype UNIQUEIDENTIFIER.

See "InterSystems SQL Data Types" for details on how values are represented within InterSystems IRIS, and "DDL Data Types Exposed by InterSystems ODBC / JDBC" for specific information on how they are projected to JDBC.

5.2 Predicate Pushdown Operators

The Spark Connector currently recognizes the following Spark operators as having direct counterparts within the underlying database (see "Overview of Predicates" in the *SQL Reference*):

| EqualTo | LessThanOrEqual | StringStartsWith | IsNull | And |
|-------------|--------------------|------------------|-----------|-----|
| LessThan | GreaterThanOrEqual | StringEndsWith | IsNotNull | Not |
| GreaterThan | StringContains | In | Or | |

5.3 Logging

The connector logs various events of interest using the same infrastructure as the Spark system itself uses, namely Log4J.

The content, format, and destination of the system as a whole is configured by the file \${SPARK_HOME}/conf/log4j-defaults. The connector is implemented in classes that reside in a package named com.intersystems.spark and so can easily be configured by specifying keys of the form:

```
log4j.logger.com.intersystems.spark
log4j.logger.com.intersystems.spark.core
log4j.logger.com.intersystems.spark.core.IRISDataSource = ALL
```

5.4 Known Issues

We hope to address the following issues in a subsequent release:

- Pruning Columns with Synthetic Names
- Java 9 Compatibility
- Handling of TINYINT
- JDBC Isolation Levels

5.4.1 Pruning Columns with Synthetic Names

Consider the following query Spark session:

```
scala> spark.read.iris("select a, min(a) from A")
```

where A is some table that presumably has a column named a.

Notice that no alias is provided for the selection expression min(a). The server synthesizes names for such columns, and in this case might describe the schema for the resulting dataframe as having two columns, named 'a' and 'Aggregate_2' respectively.

No actual field named 'Aggregate_2' exists in the table however, so an attempt to reference it in an enclosing selection would fail:

```
scala> val df = spark.read.iris("select Aggregate_2 from (select a, min(a) from A)")
> SQL ERROR: No such field SQLUSER.A.Aggregate_2 ....
```

This is to be expected in a standard SQL implementation.

The connector uses just such enclosing projection expressions as these however when attempting to prune the columns of a dataframe to those that are actually referenced in subsequent code:

```
scala> spark.read.iris("select a, min(a) from A").select("a")...
```

internally generates the query select a from(select a, min(a) from A) to be executed on the server in order to minimize the motion of data into the spark cluster.

As a result, the connector cannot efficiently prune columns with synthetic names and instead resorts to fetching the entire result set:

```
scala> spark.read.iris("select a, min(a) from A").select("Aggregate_2")
```

internally generates the query select * from(select a, min(a) from A).

For this reason, you should consider modifying the original query by attaching aliases to columns that would otherwise receive server synthesized names.

We hope to address this issue in a subsequent release.

5.4.2 Java 9 Compatibility

Java 9, and the JVM 1.9 on which it runs, became available for general release in September 2017. Neither Apache Spark nor the InterSystems Spark Connector currently run on this version of the JVM. We hope to address this issue in a subsequent release.

5.4.3 Handling of TINYINT

The mapping between Spark Catalyst and JDBC datatypes (see "SQL/Spark Datatype Mapping" earlier in this chapter) differs subtly from that used by the Spark jdbc data source. The Connector achieves this mapping by automatically installing its own subclass of class org.apache.spark.sql.jdbc.JdbcDialect but this also has the side effect of changing the mapping used by Spark JDBC itself.

By and large this is a good thing, but one problem that has been identified recently is that due to a bug in Spark 2.1.1, which neglects to implement a low level reader function for the ByteType, attempting to read an InterSystems IRIS table with a column of type TINYINT using the Spark jdbc data source will fail once the Connector has been loaded.

For now, it is probably best to avoid reading and writing DataFrames using the Spark jdbc data source directly once the Connector has been loaded. We hope to address this issue in a subsequent release.

5.4.4 JDBC Isolation Levels

The InterSystems IRIS server does not currently support the writing of a dataset to a SQL table using JDBC isolation levels other than NONE and READ_UNCOMITTED. We hope to address this issue in a subsequent release.

6

Spark Connector Quick Reference

This chapter is a quick reference to the InterSystems Spark Connector API methods, which define a custom Scala interface for the Spark Connector. It extends the generic Spark interface with a set of implicit Scala classes and types that provide more convenience and better type safety.

Note: This is not a definitive reference for the com.intersystems.spark API. It is intended as a "cheat sheet" containing only short descriptions of members and parameters, plus links to detailed documentation and examples.

For the most complete and up-to-date information, see the online Spark Connector API Reference.

The Spark Connector API provides the following extension methods to Spark Scala classes:

- DataFrameReader Extension Methods:
 - iris() executes a query or loads a table, tunes partitioning, and returns results in a DataFrame.
 - address() specifies the connection details of the cluster to read from
- DataFrameWriter Extension Methods:
 - iris() saves a DataFrame to the given table on the cluster.
 - address() specifies the connection details of the cluster to write to.
 - **description**() specifies an arbitrary description for the newly created table.
 - publicRowID() specifies whether the master RowID field of the newly created table should be publicly visible.
 - **shard()** specifies the shard key for the newly created table.
 - autobalance() specifies how to distribute records saved to a table using a system assigned shard key.
- SparkSession and SparkContext Extension Methods:
 - **rdd[T]()** executes a query or loads a table, tunes partitioning, formats each row of the result set with a specified function, and returns an RDD containing the formatted data.
 - dataset[T]() executes a query or loads a table, tunes partitioning, and returns results in a Dataset with elements of type T.
- ml.Pipeline Extension Method:
 - iscSave() saves a model to an InterSystems IRIS PMML definition class.

6.1 Spark Connector Method Reference

Each entry in this section provides a brief method overview including signatures and parameter descriptions. Most entries also include links to examples and more detailed information.

6.1.1 DataFrameReader Extension Methods

iris()

DataFrameReader.iris() executes a query on the cluster or loads the specified table, tunes partitioning, and returns results in a DataFrame. See "Using the iris() Read and Write Methods" for more information and examples.

```
def iris(text: String,mfpi: N = 1): DataFrame
def iris(text: String,column: String,lo: Long,hi: Long,partitions: N): DataFrame
```

- text text of a query to be executed, or name of a table to load.
- column, lo, hi, partitions— allow you to explicitly specify partitioning parameters.
- *mfpi* allows the server to determine partitioning parameters within certain limits.

See "Partition Tuning Options" for detailed information and examples concerning partitioning parameters (*column*, *lo*, *hi*, *partitions*, and *mfpi*).

address()

DataFrameReader.address() specifies the connection details of the cluster to read from. Overrides the default instance specified in the Spark configuration for the duration of this read operation.

```
def address(url: String,user: String = "",password: String = ""): DataFrameReader
```

• *url*, *user*, *password* — String values used to define a JDBC connection to the master server.

See "Connection Options" for more information and examples.

6.1.2 DataFrameWriter Extension Methods

iris()

DataFrameWriter.iris() saves a DataFrame to the specified table on the cluster. See "Using the iris() Read and Write Methods" for detailed information and examples.

```
def iris(table: String): Unit
```

• table — a String containing the name of the table to write to.

See "CREATE TABLE" in the *InterSystems SQL Reference* for more information on table creation options.

address()

DataFrameWriter.address() specifies the connection details of the cluster to write to. Overrides the default instance specified in the Spark configuration for the duration of this write operation.

```
def address(url: String,user: String = "",password: String = ""): DataFrameWriter[T]
```

url, user, password — String values used to define a JDBC connection to the master server.

See "Connection Options" for more information and examples.

description()

DataFrameWriter.description() specifies a description to document the newly created table.

```
def description(value: String): DataFrameWriter[T]
```

• *value* — a String containing an arbitrary description for the table.

See "InterSystems IRIS Save Options" for more information and examples.

publicRowID()

DataFrameWriter.publicRowID() specifies whether the master RowID field of the newly created table should be publicly visible.

```
def publicRowID(value: Boolean): DataFrameWriter[T]
```

• *value* — a Boolean indicating whether the table should be publicly visible.

See "InterSystems IRIS Save Options" for more information and examples.

shard()

DataFrameWriter.shard() specifies the user defined shard key for the newly created table, or specifies whether the newly created table is to be sharded. Has no effect if the table already exists and the save mode is anything other than OVERWRITE.

```
def shard(fields: String*): DataFrameWriter[T]
def shard(value: Boolean): DataFrameWriter[T]
```

- *fields* A String sequence of field names (possibly empty) to be used as the user defined shard key. If the sequence is empty then the table will be sharded on the system assigned key.
- *value* Boolean value indicating whether the newly created table is to be sharded

See "InterSystems IRIS Save Options" for more information and examples.

autobalance()

Specifies whether or not inserted records should be evenly distributed among the available shards of the cluster when saving to a table that is sharded on a system assigned shard key. Has no effect if the table is not sharded, or is sharded using a custom shard key.

```
def autobalance(value: Boolean): DataFrameWriter[T]
```

• *value* — Boolean true to evenly distribute records amongst the available shards of the cluster, or false to save records into shards that are 'closest' to where the partitions of the dataset reside.

See "InterSystems IRIS Save Options" for more information and examples.

6.1.3 SparkSession and SparkContext Extension Methods

dataset[T]()

SparkSession.dataset[T]() executes a query on the cluster or loads the specified table, optionally tunes partitioning, and returns results in a Dataset[T]s. See "Using the dataset[T]() and rdd[T]() Methods" for more information and examples.

```
def dataset[T](text: String, mfpi: N = 1)(implicit arg0: Encoder[T]): Dataset[T]
def dataset[T](text: String, column: String, lo: Long, hi: Long, partitions: N)(implicit arg0: Encoder[T]): Dataset[T]
```

- text text of a query to be executed, or name of a table to load.
- column, lo, hi, partitions— allow you to explicitly specify partitioning parameters.
- *mfpi* allows the server to determine partitioning parameters within certain limits.

See "Partition Tuning Options" for detailed information and examples concerning partitioning options.

rdd[T]()

SparkContext.rdd[T]() executes a query on the cluster or loads the specified table, optionally tunes partitioning, and computes a suitably partitioned RDD whose elements are formatted by the provided formatting function (an instance of Format[T]). See "Using the dataset[T]() and rdd[T]() Methods" for more information and examples.

```
def rdd[T](text: String, mfpi: N, format: Format[T])(implicit arg0: ClassTag[T]): RDD[T]
def rdd[T](text: String, column: String, lo: Long, hi: Long, partitions: N, format:
Format[T])(implicit arg0: ClassTag[T]): RDD[T]
```

- *text* text of a query to be executed, or name of a table to load.
- column, lo, hi, partitions— allow you to explicitly specify partitioning parameters.
- *mfpi* allows the server to determine partitioning parameters within certain limits.
- format an instance of Format[T] containing the function used to encode each row of the result set.

See "Partition Tuning Options" for concerning partitioning parameters (column, lo, hi, partitions, and mfpi).

See "Defining a Type Format[T] function" for more information on creating and using an instance of Format[T].

6.1.4 ml.PipelineModel Extension Method

iscSave()

ml.PipelineModel.iscSave() saves the PMML definition for the given model as a Class Definition on the master instance identified by *address* for subsequent execution on the cluster. See "Using PMML Models with InterSystems Products" for more information and examples.

```
def iscSave(klass: String,schema: StructType,address: Address = Address()): Unit
```

- klass name of the class definition to create. If this class already exists it will be overwritten.
- *schema* The schema of the model's source Dataset, on which the PMML file's data dictionary will be based.
- address The master instance to which the class will be written.