

Using the Native API for .NET

Version 2020.3 2021-02-04

Using the Native API for .NET InterSystems IRIS Data Platform Version 2020.3 2021-02-04 Copyright © 2021 InterSystems Corporation All rights reserved.

InterSystems, InterSystems IRIS, InterSystems Caché, InterSystems Ensemble, and InterSystems HealthShare are registered trademarks of InterSystems Corporation.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Memorial Drive, Cambridge, MA 02142, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)

Tel: +1-617-621-0700 Tel: +44 (0) 844 854 2917 Email: support@InterSystems.com

Table of Contents

About This Book	1
1 Introduction to the Native API	3
2 Calling ObjectScript Methods and Functions	5
2.1 Class Method Calls	
2.2 Function Calls	7
2.3 Calling Class Library Methods	8
2.3.1 Using Pass-by-reference Arguments	8
2.3.2 Catching %Status Error Codes	9
3 Using .NET Reverse Proxy Objects	11
3.1 Introducing the Object Gateway	11
3.2 Creating Reverse Proxy Objects	12
3.3 Using IRISObject Methods	12
3.4 IRISObject Supported Datatypes	13
4 Working with Global Arrays	15
4.1 Introduction to Global Arrays	15
4.1.1 Glossary of Native API Terms	17
4.1.2 Global Naming Rules	18
4.2 Creating, Accessing, and Deleting Nodes	18
4.2.1 Creating Nodes and Setting Node Values	19
4.2.2 Getting Node Values	
4.2.3 Deleting Nodes	20
4.3 Finding Nodes in a Global Array	
4.3.1 Iterating Over a Set of Child Nodes	
4.3.2 Iteration in Conditional Loops	
4.3.3 Testing for Child Nodes and Node Values	
4.4 Class IRIS Supported Datatypes	24
5 Transactions and Locking	27
5.1 Controlling Transactions	27
5.2 Concurrency Control	28
6 Native API for .NET Quick Reference	31
6.1 Class IRIS	
6.1.1 IRIS Method Details	31
6.2 Class IRISIterator	43
6.2.1 IRISIterator Method and Property Details	
6.3 Class IRISList	
6.3.1 IRISList Constructors	
6.3.2 IRISList Method Details	
6.4 Class IRISObject	
6.4.1 IRISObject Method Details	49

List of Figures

Figure	3-1:	Ob	iect	Gateway	V S	zstem	1

About This Book

The InterSystems *Native API for .NET* is a lightweight interface to powerful InterSystems IRIS® resources that were once available only through ObjectScript:

- *Call ObjectScript classmethods and functions.* Write custom ObjectScript classmethods or functions for any purpose, and call them from your .NET application as easily as you can call native .NET methods.
- *Manipulate ObjectScript class instances* through Object Gateway proxy objects. Call instance methods and get or set property values as easily as you could in an ObjectScript application.
- *Directly access globals*, the tree-based sparse arrays used to implement the InterSystems multidimensional storage model. These native data structures provide very fast, flexible storage and retrieval. InterSystems IRIS uses globals to make data available as objects or relational tables, but you can use the Native API to implement your own data structures.

The following chapters discuss the main features of the Native API:

- Introduction to the Native API gives an overview of Native API abilities and provides some simple code examples.
- Calling ObjectScript Methods and Functions describes how to call user defined ObjectScript class methods and functions.
- Using .NET Reverse Proxy Objects demonstrates how to manipulate ObjectScript objects through Object Gateway reverse proxy objects.
- Working with Global Arrays describes how to create, change, or delete nodes in a multidimensional global array, and demonstrates methods for iteration and data manipulation.
- Transactions and Locking describes how to work with the Native API transaction and concurrency control model.
- Native API Quick Reference provides a brief description of each Native API method mentioned in this book.

There is also a detailed Table of Contents.

More information about globals

Versions of the Native API are also available for Java, Python, and Node.js:

- Using the Native API for Java
- Using the Native API for Python
- Using the Native API for Node.js

The following book is highly recommended for developers who want to master the full power of globals:

Using Globals — describes how to use globals in ObjectScript, and provides more information about how multidimensional storage is implemented on the server.

InterSystems Core APIs for .NET

The Native API is part of a suite that also includes lightweight APIs for object and relational database access. See the following books for more information:

- *Using the InterSystems Managed Provider for .NET* describes how use the InterSystems implementation of the ADO.NET Managed Provider for relational data access and the Entity Framework for object access.
- Persisting .NET Objects with XEP describes how to store and retrieve .NET objects using the InterSystems XEP API.

1

Introduction to the Native API

The *Native API for .NET* is a lightweight interface to powerful InterSystems IRIS® resources that were once available only through ObjectScript. With the Native API, your applications can take advantage of seamless InterSystems IRIS data platform integration:

Implement transparent bidirectional communication between ObjectScript and .NET

The Native API, Object Gateway proxy objects, and ObjectScript applications can all share the same connection and work together in the same context.

Create and use individual instances of an ObjectScript class

The Native API allows you to create instances of ObjectScript classes on InterSystems IRIS and generate Object Gateway proxy objects for them at runtime. Your .NET application can use proxies to work with ObjectScript objects as easily as if they were native .NET objects.

Call ObjectScript classmethods and user-defined functions

You can write custom ObjectScript classmethods or functions for any purpose, and your application can use the Native API to call them just as easily as native .NET methods.

Work with multidimensional global arrays

The Native API provides direct access to the high performance native data structures (global arrays) that underpin the InterSystems IRIS multidimensional storage model. Global arrays can be created, read, changed, and deleted in .NET applications just as they can in ObjectScript.

The following brief examples demonstrate how easy it is to add all of these abilities to your .NET application.

Implement transparent bidirectional communication between ObjectScript and .NET

The Native API for .NET is implemented as an extension to the InterSystems ADO.NET Managed Provider. Connections are created just they would be for any other application using the Managed Provider (see *Using the InterSystems Managed Provider for .NET*). This example opens a connection and then creates an instance of the Native API IRIS class:

This connection can also be used by the InterSystems Object Gateway, allowing your .NET and ObjectScript applications to share the same context and work with the same objects.

Create and use individual instances of an ObjectScript class

Your application can create an instance of an ObjectScript class, immediately generate an Object Gateway proxy for it, and use the proxy to work with the ObjectScript instance (see the chapter on "Using .NET Reverse Proxy Objects").

In this example, the first line calls the **%New()** method of ObjectScript class Demo.dataStore, creating an instance in InterSystems IRIS. In .NET, the call returns a corresponding proxy object named *dataStoreProxy*, which is used to call instance methods and get or set properties of the ObjectScript instance:

```
// use a classmethod call to create an ObjectScript instance and generate a proxy object
   IRISObject dataStoreProxy = (IRISObject)iris.ClassMethodObject("Demo.dataStore","%New");

// use the proxy to call instance methods, get and set properties
   dataStoreProxy.InvokeVoid("ititialize");
   dataStoreProxy.Set("propertyOne","a string property");
   String testString = dataStoreProxy.Get("propertyOne");
   dataStoreProxy.Invoke("updateLog","PropertyOne value changed to "+testString);

// pass the proxy back to ObjectScript method ReadDataStore()
   iris.ClassMethodObject("Demo.useData","ReadDataStore",dataStoreProxy);
```

The last line of this example passes the *dataStoreProxy* proxy to an ObjectScript method named *ReadDataStore()*, which interprets it as a reference to the original ObjectScript instance. From there, the instance could be saved to the database, passed to another ObjectScript application, or even passed back to your .NET application.

Call ObjectScript classmethods and user-defined functions

You can easily call an ObjectScript classmethod or function (see the chapter on "Calling ObjectScript Methods and Functions").

```
String currentNameSpace = iris.ClassMethodString("%SYSTEM.SYS","NameSpace");
```

This example just calls a classmethod to get some system information, but the real power of these calls is their ability to leverage user-written code. You can write custom ObjectScript classmethods or functions for any purpose, and your .NET application can call them as easily as it calls native .NET methods.

Work with multidimensional global arrays

The Native API provides all the methods needed to manipulate global arrays (see the chapter on "Working with Global Arrays"). You can easily access and manipulate globals, traverse multilevel global arrays, and inspect data structures just as you can in ObjectScript. The following example demonstrates how to create, read, change, and delete a simple global array.

```
// Create a global (ObjectScript equivalent: set ^myGlobal("subOne") = 10)
iris.Set(10, "myGlobal", "subOne");

// Change, read, and delete the global
iris.increment(2, "myGlobal", "subOne") // increment value to 12
Console.Write("New number is " + iris.GetInteger("myGlobal", "subOne"));
iris.Kill("myGlobal", "subOne");
```

2

Calling ObjectScript Methods and Functions

This chapter describes methods of class IRIS that allow you to call ObjectScript class methods and user-defined functions directly from your .NET application. See the following sections for details and examples:

- Class Method Calls demonstrates how to call ObjectScript class methods.
- Function Calls demonstrates how to call user defined ObjectScript functions and procedures.
- Calling Class Library Methods demonstrates how to pass arguments by reference and check %Status codes.

2.1 Class Method Calls

The following methods of class IRIS call ObjectScript class methods, returning values of the type indicated by the method name: ClassMethodBool(), ClassMethodBytes(), ClassMethodDouble(), classMethodIRISList(), ClassMethodLong(), ClassMethodObject(), ClassMethodString(), and ClassMethodVoid(). You can also use ClassMethodStatusCode() to retrieve error messages from class methods that return ObjectScript %Status (see "Catching %Status Error Codes").

All of these methods take string arguments for *className* and *methodName*, plus 0 or more method arguments, which may be any of the following types: int?, short?, string, long?, double?, float?, byte[], bool?, DateTime?, IRISList?, or IRISObject. If the connection is bidirectional (see "Using .NET Reverse Proxy Objects"), then any .NET object can be used as an argument.

Trailing arguments may be omitted in argument lists, either by passing fewer than the full number of arguments, or by passing null for trailing arguments. An exception will be thrown if a non-null argument is passed to the right of a null argument.

Calling ObjectScript class methods

The code in this example calls class methods of each supported datatype from ObjectScript test class User.NativeTest (listed immediately after the example). Assume that variable *iris* is a previously defined instance of class IRIS and is currently connected to the server.

```
String className = "User.NativeTest";
String comment = "";
try{
comment = "cmBoolean() tests whether two numbers are equal (true=1,false=0): ";
bool boolVal = iris.ClassMethodBool(className, "cmBoolean",7,7);
Console.WriteLine(comment+boolVal);
```

```
comment = "cmBytes creates byte array [72,105,33]. String value of array: ";
byte[] byteVal = iris.ClassMethodBytes(className, "cmBytes", 72, 105, 33);
Console.WriteLine(comment+ (new String(byteVal)));
comment = "cmString() concatenates \"Hello\" + arg: ";
string stringVal = iris.ClassMethodString(className,"cmString","World");
Console.WriteLine(comment+stringVal);
comment = "cmLong() returns the sum of two numbers: ";
Long longVal = iris.ClassMethodLong(className, "cmLong", 7,8);
Console.WriteLine(comment+longVal);
comment = "cmDouble() multiplies a number by 1.5: ";
Double doubleVal = iris.ClassMethodDouble(className, "cmDouble", 10);
Console.WriteLine(comment+doubleVal);
Console.WriteLine(comment+iris.GetInteger("^cmGlobal"));
iris.Kill("cmGlobal");
comment = "cmList() returns a $LIST containing two values: ";
IRISList listVal = iris.ClassMethodList(className,"cmList","The answer is ",42);
Console.WriteLine(comment+listVal.Get(1)+listVal.Get(2));
} catch (Exception e){
  Console.WriteLine("method failed");
```

ObjectScript Class User.NativeTest

To run the previous example, this ObjectScript class must be compiled and available on the server:

```
Class User.NativeTest Extends %Persistent
ClassMethod cmBoolean(cml As %Integer, cm2 As %Integer) As %Boolean
    Quit (cm1=cm2)
ClassMethod cmBytes(cml As %Integer, cm2 As %Integer, cm3 As %Integer) As %Binary
    Quit $CHAR(cm1,cm2,cm3)
ClassMethod cmString(cm1 As %String) As %String
    Quit "Hello "_cm1
.
ClassMethod cmLong(cml As %Integer, cm2 As %Integer) As %Integer
    Ouit cm1+cm2
ClassMethod cmDouble(cm1 As %Double) As %Double
    Quit cm1 * 1.5
ClassMethod cmVoid(cml As %Integer)
    Set ^cmGlobal=cm1
   Quit ^cmGlobal
ClassMethod cmList(cm1 As %String, cm2 As %Integer)
    Set list = $LISTBUILD(cm1,cm2)
   Quit list
```

You can test these methods by calling them from the Terminal. For example:

```
USER>write ##class(User.NativeTest).cmString("World")
Hello World
```

2.2 Function Calls

Function calls are similar to method calls, but the arguments are in a different order. The function label is specified first, followed by the name of the routine that contains it. This corresponds to the order used in ObjectScript, where function calls have the following form:

```
set result = $$myFunctionLabel^myRoutineName([arguments])
```

Functions are supported because they are necessary for older code bases (see "Callable User-defined Code Modules" in *Using ObjectScript*), but new code should always use method calls if possible. ObjectScript also provides a special keyword to create method wrappers around existing routines without loosing efficiency (see "Call Methods" in the *Orientation Guide for Server-Side Programming*).

The Native API methods in this section call user-defined ObjectScript functions or procedures and return a value of the type indicated by the method name: FunctionBool(), FunctionBytes(), FunctionDouble(), FunctionIRISList(), FunctionObject(), FunctionLong(), FunctionString(), or Procedure() (no return value).

They take String arguments for *functionLabel* and *routineName*, plus 0 or more function arguments, which may be any of the following types: int?, short?, string, long?, double?, float?, byte[], bool?, DateTime?, IRISList?, or IRISObject. If the connection is bidirection (see Using .NET Reverse Proxy Objects), then any .NET object can be used as an argument.

Trailing arguments may be omitted in argument lists, either by passing fewer than the full number of arguments, or by passing null for trailing arguments. An exception will be thrown if a non-null argument is passed to the right of a null argument.

Note: Built-in system functions are not supported

These methods are designed to call functions in user-defined routines. ObjectScript system functions (which start with a \$ character. See "ObjectScript Functions" in the *ObjectScript Reference*) cannot be called directly from your .NET code. However, you can call a system function indirectly by writing an ObjectScript wrapper function that calls the system function and returns the result. For example, the **fnList()** function (at the end of this section in ObjectScript Routine NativeRoutine.mac) calls \$LISTBUILD.

Calling functions of ObjectScript routines with the Native API

The code in this example calls functions of each supported datatype from ObjectScript routine NativeRoutine (File NativeRoutine.mac, listed immediately after this example). Assume that *iris* is an existing instance of class IRIS, and is currently connected to the server.

```
String routineName = "NativeRoutine";
String comment =
comment = "fnBoolean() tests whether two numbers are equal (true=1,false=0): ";
Bool boolVal = iris.FunctionBool("fnBoolean", routineName, 7, 7);
Console.WriteLine(comment+boolVal);
comment = "fnBytes creates byte array [72,105,33]. String value of the array: ";
Byte[] byteVal = new String(iris.FunctionBytes("fnBytes",routineName,72,105,33));
Console.WriteLine(comment+(new String(byteVal)));
comment = "fnString() concatenates \"Hello\" + arg: ";
String stringVal = iris.FunctionString("fnString",routineName,"World");
Console.WriteLine(comment+stringVal);
comment = "fnLong() returns the sum of two numbers: ";
Long longVal = iris.FunctionInt("fnLong",routineName,7,8);
Console.WriteLine(comment+longVal);
comment = "fnDouble() multiplies a number by 1.5: ";
Double doubleVal = iris.FunctionDouble("fnDouble",routineName,5);
Console.WriteLine(comment+doubleVal);
comment = "fnProcedure assigns a value to global array ^fnGlobal: ";
iris.Procedure("fnProcedure", routineName, 88);
```

```
// Read global array ^fnGlobal and then delete it
Console.WriteLine(comment+iris.GetInteger("^fnGlobal")+"\n\n");
iris.Kill("fnGlobal");

comment = "fnList() returns a $LIST containing two values: ";
IRISList listVal = iris.FunctionList("fnList",routineName,"The answer is ",42);
Console.WriteLine(comment+listVal.Get(1)+listVal.Get(2));
```

ObjectScript Routine NativeRoutine.mac

To run the previous example, this ObjectScript routine must be compiled and available on the server:

```
fnBoolean(fn1,fn2) public {
   quit (fn1=fn2)
fnBytes(fn1,fn2,fn3) public {
    quit $CHAR(fn1,fn2,fn3)
fnString(fn1) public {
    quit "Hello "_fn1
fnLong(fn1,fn2) public {
    quit fn1+fn2
fnDouble(fn1) public {
    quit fn1 * 1.5
fnProcedure(fn1) public {
    set ^fnGlobal=fn1
    quit
fnList(fn1,fn2) public {
    set list = $LISTBUILD(fn1,fn2)
    quit list
```

You can test these functions by calling them from the Terminal. For example:

```
USER>write $$fnString^NativeRoutine("World")
Hello World
```

2.3 Calling Class Library Methods

Most of the classes in the InterSystems Class Library use a calling convention where methods only return a %Status value. The actual results are returned in arguments passed by reference. This section describes how to pass by reference and read %Status values.

- Using Pass-by-reference Arguments demonstrates how to use the IRISReference class to pass objects by reference.
- Catching %Status Error Codes describes how to use the ClassMethodStatusCode() method to test and read %Status values..

2.3.1 Using Pass-by-reference Arguments

The Native API supports pass by reference for both methods and functions. To pass an argument by reference, assign the argument value to an instance of class ADO.IRISReference and pass that instance as the argument:

```
IRISReference valueRef = new IRISReference(""); // set inital value to null string
iris.ClassMethodString("%SomeClass","SomeMethod",valueRef);
String myString = valueRef.value; // get the method result
```

Here is a working example:

Using pass-by-reference arguments

This example calls %SYS.DatabaseQuery.**GetDatabaseFreeSpace()** to get the amount of free space (in MB) available in the iristemp database.

```
IRISReference freeMB = new IRISReference(0); // set inital value to 0
String dir = "C:/InterSystems/IRIS/mgr/iristemp"; // directory to be tested
Object status = null;

try {
    Console.Write("\n\nCalling %SYS.DatabaseQuery.GetDatabaseFreeSpace()... ");
    status = iris.ClassMethodObject("%SYS.DatabaseQuery", "GetDatabaseFreeSpace", dir,freeMB);
    Console.WriteLine("\nFree space in " + dir + " = " + freeMB.value + "MB");
}
catch (IRISException e) {
    Console.Write("Call to class method GetDatabaseFreeSpace() returned error:");
    Console.WriteLine(e.getMessage());
}
prints:

Calling %SYS.DatabaseQuery.GetDatabaseFreeSpace()...
Free space in C:/InterSystems/IRIS/mgr/iristemp = 8.9MB
```

2.3.2 Catching %Status Error Codes

When a class method has ObjectScript %Status as the return type, you can use **ClassMethodStatusCode()** to retrieve error messages. When a class method call fails, the resulting IRISException error will contain the %Status error code and message.

In the following example, the **ValidatePassword()** method returns a %Status object. If the password is invalid (for example, password is too short) an exception will be thrown and the %Status message will explain why it failed. Assume that variable *iris* is a previously defined instance of class IRIS and is currently connected to the server.

Using ClassMethodStatusCode() to catch ObjectScript %Status values

This example passes an invalid password to **%SYSTEM.Security.ValidatePassword()** and catches the error message.

```
String className = "%SYSTEM.Security";
String methodName = "ValidatePassword";
String pwd = ""; // an invalid password
try {
// This call will throw an IRISException containing the %Status error message:
    iris.ClassMethodStatusCode(className,methodName,pwd);
// This call would fail silently or throw a generic error message:
    Object status = iris.ClassMethodObject(className,methodName,pwd);
    Console.WriteLine("\nPassword validated!");
} catch (IRISException e) {
    Console.WriteLine("Call to "+methodName+"(\""+pwd+"\") returned error:");
    Console.WriteLine(e.getMessage());
}
```

Notice that this example deliberately calls a method that does not use any pass by reference arguments.

To experiment with a more complex example, you can try catching the status code in the previous example (Using pass-by-reference arguments). Force an exception by passing an invalid directory.

Note: Using IRISObject.InvokeStatusCode() when calling Instance methods

The **ClassMethodStatusCode**() method is used for class method calls. When you are invoking proxy object instance methods (see "Using .NET Reverse Proxy Objects") the IRISObject.**InvokeStatusCode**() method can be used in exactly the same way.

3

Using .NET Reverse Proxy Objects

The Native API works together with the Object Gateway for .NET. Reverse proxy objects are .NET objects that allow you to manipulate ObjectScript objects via the Object Gateway. You can use a reverse proxy object to call the target's instance methods and get or set property values, manipulating the ObjectScript target object as easily as if it were a native .NET object.

This chapter covers the following topics:

- Introducing the Object Gateway provides a brief overview of the Object Gateway.
- Creating Reverse Proxy Objects describes methods used to create reverse proxy objects.
- Using IRISObject Methods demonstrates how reverse proxy objects are used.
- IRIS Object Supported Datatypes describes datatype-specific versions of the reverse proxy methods.

3.1 Introducing the Object Gateway

The Object Gateway allows InterSystems IRIS objects and .NET objects to interact freely, using the same connection and working together in the same context (database, session, and transaction). Object Gateway architecture is described in detail in *Using the Object Gateway for .NET*, but for the purposes of this discussion you can think of it as a simple black box connecting proxy objects on one side to target objects on the other:




Figure 3–1: Object Gateway System

The connection is via TCP/IP if InterSystems IRIS and the host VM are on two different machines. If they are on the same machine, the connection can be either TCP/IP or shared memory.

As the diagram shows, a *forward proxy object* is an ObjectScript proxy for a .NET target object (see "Using Dynamic Object Proxies" in *Using the Object Gateway for .NET* for details). Forward proxies will be mentioned again later, but the focus of this chapter is how to use a .NET reverse proxy to manipulate an ObjectScript target object.

3.2 Creating Reverse Proxy Objects

You can create a reverse proxy object by obtaining the OREF of an ObjectScript class instance (for example, by calling the **%New()** method of the class) and casting it to IRISObject. The following methods can be used to call ObjectScript class methods and functions:

- ADO.IRIS.ClassMethodObject() calls an ObjectScript class method and returns the result as an instance of object.
- ADO.IRIS.FunctionObject() calls an ObjectScript function and returns the result as an instance of object.

In either case, if the returned object is a valid OREF, it will be used to generate and return a proxy for the referenced object.

See "Class Method Calls" in the previous chapter for more information on how to call ObjectScript class methods. The following example uses ClassMethodObject() to create a reverse proxy object:

Creating an instance of IRISObject

- ClassMethodObject() is used to call the %New() method of an ObjectScript class named Demo.Test.
- Since the return value of **%New()** is a valid OREF, **ClassMethodObject()** creates and returns a proxy for the instance.
- In .NET, the proxy is cast to IRISObject, creating reverse proxy object test:

```
IRISObject test = (IRISObject)iris.ClassMethodObject("Demo.Test","%New");
```

Variable *test* is a .NET reverse proxy object for the new instance of Demo.Test. In the following section, *test* will be used to access methods and properties of the ObjectScript Demo.Test instance.

3.3 Using IRISObject Methods

IRISObject provides methods to access the ObjectScript target object. The following example uses **Invoke()** and **InvokeVoid()** to call instance methods, and accessors **Get()** and **Set()** to get and set a property value.

The example in this section uses reverse proxy object methods to access an ObjectScript class named Demo. Test, which includes declarations for methods **initialize()** and **add()**, and property *name*:

ObjectScript Class Demo.Test

```
Class Demo.Test Extends %Persistent
Method initialize(initialVal As %String)
Method add(vall As %Integer, val2 As %Integer) As %Integer
Property name As %String
```

In the following example, the first line creates a reverse proxy object named *test* for an instance of Demo.Test. The rest of the code uses proxy object *test* to access the Demo.Test instance.

.NET code using a Demo.Test reverse proxy object

```
// Create an instance of Demo.Test and return a proxy object for it
   IRISObject test = (IRISObject)iris.ClassMethodObject("Demo.Test","%New");

// instance method test.initialize() is called with one argument, returning nothing.
   test.InvokeVoid("initialize", 42); // sets a mysterious internal variable to 42

// instance method test.add() is called with two arguments, returning an int value.
   int sum = test.Invoke("add",2,3); // adds 2 plus 3, returning 5

// The value of property test.name is set and then returned.
   test.Set("name", "Einstein, Albert"); // sets the property to "Einstein, Albert"
   String name = test.Get("name"); // returns the new property value
```

This example used the following IRISObject methods to access methods and properties of the Demo. Test instance:

- ClassMethodObject() calls Demo.Test class method %New(), which creates an instance of Demo.Test and returns an IRISObject proxy named *test* (as described previously in "Creating Reverse Proxy Objects").
- **InvokeVoid()** invokes the **initialize()** instance method, which initializes an internal variable but does not return a value.
- Invoke() invokes the add() instance method, which accepts two integer arguments and returns the sum as an integer.
- **Set()** sets the *name* property to a new value.
- **Get()** returns the value of property *name*.

There are also datatype-specific versions of these methods, as described in the following section.

3.4 IRISObject Supported Datatypes

The example in the previous section used the generic **Set()**, **Get()**, and **Invoke()** methods, but the IRISObject class also provides datatype-specific methods for other supported datatypes.

IRISObject set() and get() methods

The IRISObject.Set() method accepts any Java object as a property value, including all datatypes supported by IRIS.Set() (see "Class IRIS Supported Datatypes").

In addition to the generic **Get()** method, IRISObject provides the following type-specific methods: **GetBool()**, **GetBytes()**, **GetDouble()**, **GetIRISList()**, **GetLong()**, **GetObject()** and **GetString()**.

IRISObject invoke() methods

The IRISObject invoke methods support the same set of datatypes as the IRIS classmethod calls (see "Class Method Calls").

In addition to the generic <code>Invoke()</code> method, <code>IRISObject</code> provides the following type-specific methods: <code>InvokeBool()</code>, <code>InvokeBytes()</code>, <code>InvokeDouble()</code>, <code>InvokeIRISList()</code>, <code>InvokeLong()</code>, <code>InvokeObject()</code>, <code>InvokeString()</code>, and <code>InvokeVoid()</code>. It also provides <code>InvokeStatusCode()</code>, which gets the contents of an ObjectScript <code>%Status</code> return value (see "Catching <code>%Status</code> Error Codes").

All of the invoke methods take a String argument for *methodName* plus 0 or more method arguments, which may be any of the following types int?, short?, string, long?, double?, float?, byte[], bool?, DateTime?, IRISList?, or IRISObject. If the connection is bidirectional, any Java object can be used as an argument.

Trailing arguments may be omitted in argument lists, either by passing fewer than the full number of arguments, or by passing null for trailing arguments. An exception will be thrown if a non-null argument is passed to the right of a null argument.

4

Working with Global Arrays

This chapter covers the following topics:

- Introduction to Global Arrays introduces global array concepts and provides a simple demonstration of how the Native API is used.
- Creating, Accessing, and Deleting Nodes demonstrates how to create, change, or delete nodes in a global array, and how to retrieve node values.
- Finding Nodes in a Global Array describes the iteration methods that allow rapid access to the nodes of a global array.
- Class IRIS Supported Datatypes provides details on how to retrieve node values as specific datatypes.

Note: IRIS Connection Code

The examples in this chapter assume that an IRIS object named *iris* already exists and is connected to the server. The following code was used to create it:

```
//Open a connection to the server and create an IRIS object
    IRISConnection conn = new IRISConnection();
    conn.ConnectionString = "Server = localhost; "
    + "Port = 1972; " + "Namespace = USER; "
    + "Password = SYS; " + "User ID = _SYSTEM;";
    conn.Open();
    IRIS iris = IRIS.CreateIRIS(conn);
```

4.1 Introduction to Global Arrays

A global array, like all sparse arrays, is a tree structure rather than a sequential list. The basic concept behind global arrays can be illustrated by analogy to a file structure. Each *directory* in the tree is uniquely identified by a *path* composed of a *root directory* identifier followed by a series of *subdirectory* identifiers, and any directory may or may not contain *data*.

Global arrays work the same way: each *node* in the tree is uniquely identified by a *node address* composed of a *global name* identifier and a series of *subscript* identifiers, and a node may or may not contain a *value*. For example, here is a global array consisting of six nodes, two of which contain values:

```
root --> | --> foo --> SubFoo="A" | --> bar --> lowbar --> UnderBar=123
```

Values could be stored in the other possible node addresses (for example, root or root->bar), but no resources are wasted if those node addresses are *valueless*. In InterSystems ObjectScript globals notation, the two nodes with values would be:

```
root("foo","SubFoo")
root("bar","lowbar","UnderBar")
```

The global name (root) is followed by a comma-delimited *subscript list* in parentheses. Together, they specify the entire path to the node.

This global array could be created by two calls to the Native API **Set**() method:

```
irisObject.Set("A", "root", "foo", "SubFoo");
irisObject.Set(123, "root", "bar", "lowbar", "UnderBar");
```

Global array root is created when the first call assigns value "A" to node *root("foo","SubFoo")*. Nodes can be created in any order, and with any set of subscripts. The same global array would be created if we reversed the order of these two calls. The valueless nodes are created automatically, and will be deleted automatically when no longer needed. For details, see "Creating, Accessing, and Deleting Nodes" later in this chapter.

The Native API code to create this array is demonstrated in the following example. An IRISConnection object establishes a connection to the server. The connection will be used by an instance of class IRIS named *iris*. Native API methods are used to create a global array, read the resulting persistent values from the database, and then delete the global array.

The NativeDemo Program

The Native API for .NET is part of the InterSystems.Data.IrisClient.dll library. For detailed information, see the Introduction to *Using the InterSystems Managed Provider for .NET*.

```
using System;
using InterSystems.Data.IRISClient;
using InterSystems.Data.IRISClient.ADO;
namespace NativeSpace
  class NativeDemo
     static void Main(string[] args) {
        try {
//Open a connection to the server and create an IRIS object
           IRISConnection conn = new IRISConnection();
           conn.ConnectionString = "Server = localhost;
+ "Port = 1972; " + "Namespace = USER; "
+ "Password = SYS; " + "User ID = _SYSTEM;";
           conn.Open();
           IRIS iris = IRIS.CreateIRIS(conn);
//Create a global array in the USER namespace on the server
    iris.Set("A", "root", "foo", "SubFoo");
    iris.Set(123, "root", "bar", "lowbar", "UnderBar");
// Read the values from the database and print them
           string subfoo = iris.GetString("root", "foo", "SubFoo");
string underbar = iris.GetString("root", "bar", "lowbar", "UnderBar");
           Console.WriteLine("Created two values: \n"
              + " root(\"foo\",\"SubFoo\")=" + subfoo + "\n"
+ " root(\"bar\",\"lowbar\",\"UnderBar\")=" + underbar);
//Delete the global array and terminate
    iris.Kill("root"); // delete global array root
           iris.Close();
           conn.Close();
        catch (Exception e) {
           Console.WriteLine(e.Message);
     }// end Main()
     // end class NativeDemo
```

NativeDemo prints the following lines:

```
Created two values:
   root("foo","SubFoo")=A
   root("bar","lowbar","UnderBar")=123
```

In this example, an IRISConnection object named *conn* provides a connection to the database associated with the USER namespace. Native API methods perform the following actions:

- IRIS.CreateIRIS() creates a new instance of IRIS named *iris*, which will access the database through *conn*.
- IRIS.Set() creates new persistent nodes in the database.
- IRIS.GetString() queries the database and returns the values of the specified nodes.
- IRIS.Kill() deletes the specified node and all of its subnodes from the database.

The next chapter provides detailed explanations and examples for all of these methods.

4.1.1 Glossary of Native APITerms

See the previous section for an overview of the concepts listed here. Examples in this glossary will refer to the global array structure listed below. The *Legs* global array has ten nodes and three node levels. Seven of the ten nodes contain values:

```
// root node, valueless, 3 child nodes
fish = 0
                            level 1 node, value=0
mammal
                         // level 1 node, valueless
 human = 2
                            level 2 node, value=2
 dog = 4
                            level 2 node, value=4
                            level 1 node, valueless, 3 child nodes
                         // level 2 node, value=6
  insect = 6
  spider = 8
                            level 2 node, value=8
                         // level 2 node, value="Diplopoda", 1 child node
  millipede = Diplopoda
    centipede = 100
                         // level 3 node, value=100
```

Child node

The nodes immediately under a given parent node. The address of a child node is specified by adding exactly one subscript to the end of the parent subscript list. For example, parent node Legs("mammal") has child nodes Legs("mammal","human") and Legs("mammal","dog").

Global name

The identifier for the root node is also the name of the entire global array. For example, root node identifier Legs is the global name of global array *Legs*.

Node

An element of a global array, uniquely identified by a namespace consisting of a global name and an arbitrary number of subscript identifiers. A node must either contain data, have child nodes, or both.

Node level

The number of subscripts in the node address. A 'level 2 node' is just another way of saying 'a node with two subscripts'. For example, Legs("mammal","dog") is a level 2 node. It is two levels under root node Legs and one level under Legs("mammal").

Node address

The complete namespace of a node, including the global name and all subscripts. For example, node address Legs("fish") consists of root node identifier Legs plus a list containing one subscript, "fish". Depending on context, Legs (with no subscript list) can refer to either the root node address or the entire global array.

Root node

The unsubscripted node at the base of the global array tree. The identifier for a root node is its global name with no subscripts.

Subnode

All descendants of a given node are referred to as *subnodes* of that node. For example, node *Legs*("bug") has four different subnodes on two levels. All nine subscripted nodes are subnodes of root node *Legs*.

Subscript / Subscript list

All nodes under the root node are addressed by specifying the global name and a list of one or more subscript identifiers. (The global name plus the subscript list is the node address).

Target address

Many Native API methods require you to specify a valid node address that does not necessarily point to an existing node. For example, the **Set()** method takes a *value* argument and a target address, and stores the value at that address. If no node exists at the target address, a new node is created.

Value

A node can contain a value of any supported type. A node with no child nodes must contain a value; a node that has child nodes can be valueless.

Valueless node

A node must either contain data, have child nodes, or both. A node that has child nodes but does not contain data is called a valueless node. Valueless nodes only exist as pointers to lower level nodes.

4.1.2 Global Naming Rules

Global names and subscripts obey the following rules:

- The length of a node address (totaling the length of the global name and all subscripts) can be up to 511 characters. (Some typed characters may count as more than one encoded character for this limit. For more information, see "Maximum Length of a Global Reference" in *Using Globals*).
- A global name can include letters, numbers, and periods ('.'), and can have a length of up to 31 significant characters. It must begin with a letter, and must not end with a period.
- A subscript can be a number or a string. String subscripts are case-sensitive, and can use all characters (including control and non-printing characters). Length is limited only by the 511 character maximum for the total node address.

4.2 Creating, Accessing, and Deleting Nodes

The Native API provides three methods that can make changes in the database: **Set()** and **Increment()** can create nodes or change node values, and **Kill()** can delete a node or set of nodes. Node values are retrieved by type-specific getter methods such as **GetInteger()** and **GetString()**.

- Creating Nodes and Setting Node Values describes how to use Set() and Increment().
- Getting Node Values lists getter methods for each supported datatype.
- Deleting Nodes describes how to use Kill().

4.2.1 Creating Nodes and Setting Node Values

The **Set()** and **Increment()** methods can be used to create a persistent node with a specified value, or to change the value of an existing node.

IRIS.Set() takes a *value* argument of any supported datatype and stores the value at the specified address. If no node exists at the target address, a new one is created.

Setting and changing node values

In the following example, the first call to **Set()** creates a new node at subnode address *myGlobal("A")* and sets the value of the node to string "first". The second call changes the value of the subnode, replacing it with integer 1.

Set() can create and change values of any supported datatype. To read an existing value, you must use a different getter method for each datatype, as described in the next section.

IRIS.Increment() takes a *number* argument, increments the node value by that amount, and returns the incremented value.

If there is no node at the target address, the method creates one and assigns the *number* argument as the value. This method uses a thread-safe atomic operation to change the value of the node, so the node is never locked.

Incrementing node values

In the following example, the first call to **Increment()** creates new subnode myGlobal("B") with value -2. The next two calls each increment by -2, resulting in a final value of -6:

```
for (int loop = 0; loop < 3; loop++) {
  iris.Increment(-2,"myGlobal", "B");
}</pre>
```

Note: Global naming rules

The second argument for either **Set**() or **Increment**() is a global array name. The name can include letters, numbers, and periods. It must begin with a character, and may not end with a period. The arguments after the global name are subscripts, which can be either numbers or strings (case-sensitive, not restricted to alphanumeric characters). See "Global Naming Rules" for more information.

4.2.2 Getting Node Values

The **Set()** method can be used with all supported datatypes, but each datatype requires a separate getter. Node values can be any of the following datatypes: int?, short?, string, long?, double?, float?, byte[], bool?, DateTime?, IRISList?, and instances of objects that implement System.IO.MemoryStream (stored and retrieved as byte[]). A null value translates to ""

The following methods are used to retrieve node values of these datatypes:

- Numeric datatypes: GetBool(), GetInt16(), GetInt32(), GetInt64(), GetSingle(), GetDouble()
- String datatypes: GetString(), GetBytes(), GetIRISList()
- Other datatypes: **GetDateTime()**, **GetObject()**

For more information on datatypes, see "Class IRIS Supported Datatypes" later in this chapter.

4.2.3 Deleting Nodes

IRIS.Kill() deletes the specified node and all of its subnodes. The entire global array will be deleted if the root node is deleted, or if all nodes with values are deleted.

In the following example, global array myGlobal initially contains the following nodes:

```
myGlobal = <valueless node>
myGlobal("A") = 0
myGlobal("A",1) = 0
myGlobal("A",2) = 0
myGlobal("B") = <valueless node>
myGlobal("B",1) = 0
```

The example will delete the entire global array by calling **Kill**() on two of its subnodes, myGlobal("A") and myGlobal("B",1).

Deleting a node or group of nodes

The first call will delete node *myGlobal("A")* and both of its subnodes:

```
iris.Kill("myGlobal", "A");
// also kills child nodes myGlobal("A",1) and myGlobal("A",2)
```

The second call deletes myGlobal("B",1), the last remaining subnode with a value:

```
iris.Kill("myGlobal", "B",1);
```

Since neither of the remaining nodes has a value, the entire global array is deleted:

- The parent node, myGlobal("B"), is deleted because it is valueless and now has no subnodes.
- Now root node *myGlobal* is valueless and has no subnodes, so the entire global array is deleted from the database.

4.3 Finding Nodes in a Global Array

The Native API provides ways to iterate over part or all of a global array. The following topics describe the various iteration methods:

- Iterating Over a Set of Child Nodes describes how to iterate over all child nodes under a given parent node.
- Iteration in Conditional Loops describes methods and properties that provide more control over iteration.
- Testing for Child Nodes and Node Values describes how to find all subnodes regardless of node level, and identify
 which nodes have values.

4.3.1 Iterating Over a Set of Child Nodes

Child nodes are sets of nodes immediately under the same parent node. Any child node address can be defined by appending one subscript to the subscript list of the parent. For example, the following global array has four child nodes under parent node *heroes("dogs")*:

The heroes global array

This global array uses the names of several heroic dogs (plus a reckless boy and a pioneering sheep) as subscripts. The values are birth years.

```
heroes
                                                     // root node,
                                                                        valueless, 2 child nodes
   heroes("dogs")
                                                     // level 1 node, valueless, 4 child nodes
      heroes("dogs", "Balto") = 1919
                                                     // level 2 node, value=1919
      heroes("dogs", "Hachiko") = 1923
heroes("dogs", "Lassie") = 1940
                                                     // level 2 node, value=1923
                                                     // level 2 node, value=1940, 1 child node
         heroes("dogs", "Lassie", "Timmy") = 1954 // level 3 node, value=1954
      heroes("dogs", "Whitefang") = 1906
                                                        level 2 node, value=1906
   heroes("sheep")
                                                        level 2 node, valueless, 1 child node
      heroes("sheep", "Dolly") = 1996
                                                     // level 2 node, value=1996
```

The following methods are used to create an iterator, define the direction of iteration, and set the starting point of the search:

- IRIS.GetIRISIterator() returns an instance of IRISIterator for the child nodes of the specified target node.
- IRIS.GetIRISReverseIterator() returns an instance of IRISIterator set to backward iteration for the child nodes of the specified target node.
- IRISIterator.**StartFrom()** sets the iterator's starting position to the specified subscript. The subscript is an arbitrary starting point, and does not have to address an existing node.

Read child node values in reverse order

The following code iterates over child nodes of *heroes*("dogs") in reverse collation order, starting with subscript V:

```
// Iterate in reverse, seeking nodes lower than heroes('dogs','V') in collation order
IRISIterator iterDogs = iris.GetIRISReverseIterator("heroes","dogs");
iterDogs.StartFrom("V");
String output = "\nDog birth years: ";
foreach (int BirthYear in iterDogs) {
    output += BirthYear + " ";
};
Console.WriteLine(output);
```

This code prints the following output:

```
Dog birth years: 1940 1923 1919
```

The example does the following:

- GetIRISReverseIterator() returns iterator iterDogs, which will find child nodes of heroes("dogs") in reverse
 collation order.
- StartFrom() specifies subscript V, meaning that the search range will include all child nodes of *heroes("dogs")* with subscripts lower than V in collation order. The iterator will first find subscript Lassie, followed by Hachiko and Balto.

Two subnodes of *heroes("dogs")* are ignored:

- Child node *heroes("dogs","Whitefang")* will not be found because it is outside of the search range (Whitefang is higher than V in collation order).
- Level 3 node heroes("dogs", "Lassie", "Timmy") will not be found because it is a child of Lassie, not dogs.

See the last section in this chapter ("Testing for Child Nodes and Node Values") for a discussion of how to iterate over multiple node levels.

Note: Collation Order

The order in which nodes are retrieved depends on the *collation order* of the subscripts. This is not a function of the iterator. When a node is created, it is automatically stored it in the collation order specified by the storage definition. In this example, the child nodes of heroes("dogs") would be stored in the order shown (Balto, Hachiko, Lassie, Whitefang) regardless of the order in which they were created. For more information, see "Collation of Global Nodes" in *Using Globals*.

4.3.2 Iteration in Conditional Loops

The previous section demonstrated an easy way to make a single pass over a set of child nodes, but in some cases you may want more control than a simple foreach loop can provide. This section demonstrates some methods and properties that allow more control over the iterator and provide easier access to data:

- IRISIterator.MoveNext() implements System.Collections.IEnumerator, allowing you to control exactly when the iterator
 will move to the next node. It returns true if the next node has been found, or false if there are no more nodes in
 the current iteration.
- IRISIterator.Reset() can be called after exiting a loop to reset the iterator to its starting position, allowing it to be used again.
- IRISIterator. Current gets an object containing the value of the node at the current iterator position. This is the same value as the one assigned to the current loop variable in a foreach loop.
- IRISIterator. Current Subscript gets an object containing the lowest level subscript for the node at the current iterator position. For example, if the iterator points to node *myGlobal(23,"somenode")*, the returned object will contain value "somenode".

Like the previous example, this one uses the heroes global array and iterates over the child nodes under *heroes("dogs")*. However, this example uses the same iterator to make several passes over the child nodes, and exits a loop as soon as certain conditions are met.

Search for values that match items in a list

This example scans the child nodes under *heroes("dogs")* until it finds a specific node value or runs out of nodes. Array *targetDates* specifies the list of *targetYear* values to be used in the main foreach loop. Within the main loop, the do while loop finds each child node and compares its value to the current *targetYear*.

```
IRISIterator iterDogs = iris.GetIRISIterator("heroes","dogs");
bool seek;
int[] targetDates = {1906, 1940, 2001};
foreach (int targetYear in targetDates) {
    do {
        seek = iterDogs.MoveNext();
        if (!seek) {
             Console.WriteLine("Could not find a dog born in " + targetYear);
        }
        else if ((int)iterDogs.Current == targetYear) {
             Console.WriteLine(iterDogs.CurrentSubscript + " was born in " + iterDogs.Current);
            seek = false;
        }
        while (seek);
        iterDogs.Reset();
} // end foreach
```

This code prints the following output:

```
Whitefang was born in 1906
Lassie was born in 1940
Could not find a dog born in 2001
```

The example does the following:

- **GetIRISIterator**() returns iterator *iterDogs*, which will find child nodes of *heroes*("dogs") in collation order (as demonstrated in the previous section, "Iterating Over a Set of Child Nodes"). *iterDogs* will be reset and used again in each pass of the foreach loop.
- MoveNext() is called in each pass of the do while loop to find the next child node. It sets *seek* to true if a node is found, or false if there are no more child nodes. If *seek* is false, the do while loop exits after printing a message indicating that the current *targetYear* value was not found.

- The **Current** and **CurrentSubscript** properties of *iterDogs* are set each time a child node is found. **Current** contains the current node value, and **CurrentSubscript** contains the current subscript.
- **Current** is compared to *targetYear*. If there is a match, a message displays both the subscript and the node value, and the do while loop is terminated by setting *seek* to false.
- **Reset()** is called at the end of each do while pass. This returns iterator *iterDogs* to its original starting condition so it can be used again in the next pass.

4.3.3 Testing for Child Nodes and Node Values

In the previous examples, the scope of the search is restricted to child nodes of *heroes("dogs")*. The iterator fails to find two values in global array heroes because they are under different parents:

- Level 3 node heroes("dogs", "Lassie", "Timmy") will not be found because it is a child of Lassie, not dogs.
- Level 2 node heroes("sheep", "Dolly") is not found because it is a child of sheep, not dogs.

To search the entire global array, we need to find all of the nodes that have child nodes, and create an iterator for each one. The **IsDefined()** method provides the necessary information:

- IRIS.IsDefined() can be used to determine if a node has a value, a subnode, or both. It returns one of the following values:
 - 0 the specified node does not exist
 - 1 the node exists and has a value
 - 10 the node is valueless but has a child node
 - 11 the node has both a value and a child node

The returned value can be used to determine several useful boolean values:

The following example consists of two methods:

- **TestNode**() will be called for each node in the *heroes* global array. It calls **IsDefined**() on the current node, and returns a boolean value indicating whether the node has child nodes. It also checks to see if the current subscript is Timmy or Dolly, and prints a message if so.
- **FindAllHeroes**() uses the return value of **TestNode**() to navigate the entire global array. It starts by iterating over the child nodes of root node *heroes*. Whenever **TestNode**() indicates that the current node has child nodes, **FindAllHeroes**() creates a new iterator to test the lower level child nodes.

Method FindAllHeroes()

This example processes a known structure, and traverses the various levels with simple nested calls. In the less common case where a structure has an arbitrary number of levels, a recursive algorithm could be used.

```
public void FindAllHeroes() {
   string root = "heroes";

// Iterate over child nodes of root node heroes
   IRISIterator iterRoot = iris.GetIRISIterator(root);
   foreach (object node in iterRoot) {
     object subl = iterRoot.CurrentSubscript;
     bool hasChild1 = TestNode(iterRoot,subl);

   // Process current child of heroes(subl)
```

```
if (hasChild1) {
    IRISIterator iterOne = iris.GetIRISIterator(root,sub1);
    foreach (object node in iterOne) {
        object sub2 = iterOne.CurrentSubscript;
        bool hasChild2 = TestNode(iterOne,sub1,sub2);

    // Process current child of heroes(sub1,sub2);

    if (hasChild2) {
        IRISIterator iterTwo = iris.GetIRISIterator(root,sub1,sub2);
        foreach (object node in iterTwo) {
            object sub3 = iterTwo.CurrentSubscript;
            TestNode(iterTwo,sub1,sub2,sub3); //no child nodes below level 3
        }
        } //end hasChild1
    } // end main loop
} // end FindAllHeroes()
```

Method TestNode()

```
public bool TestNode(IRISIterator iter, string root, params object[] subscripts) {
// Test for values and child nodes
  int state = iris.IsDefined(root, subscripts);
  bool hasValue = (state%10 > 0); // has value if state is 1 or 11 bool hasChild = (state > 9); // has child if state is 10 or 11
  bool hasChild = (state > 9);
// Look for lost heroes
    string[] lost = {"Timmy", "Dolly"};
  var lost = new List<string> {"Timmy", "Dolly"};
  if (hasValue) { // ignore valueless nodes
    string name = (string)iter.CurrentSubscript;
    int year = (int)iter.Current;
      foreach (string hero in lost) {
        if (hero == name)
    if (lost.Contains(name))
      Console.WriteLine("Hey, we found " + name + " (born in " + year + ")!!!");
        }
  return hasChild;
```

4.4 Class IRIS Supported Datatypes

For simplicity, examples in previous sections of this chapter have always used Integer or String node values, but the IRIS class also provides datatype-specific methods for the following supported datatypes.

IRIS.set()

The IRIS.Set() method supports datatypes bool, byte[], Single, Double, DateTime, Int16, Int32, Int64, String, IRISList, and instances of objects that implement System.IO.MemoryStream. A null value is stored as "".

Class IRIS getters for numeric values

The following IRIS methods assume that the node value is numeric, and attempt to convert it to an appropriate .NET variable: **GetBool()**, **GetSingle()**, **GetDouble()**, **GetInt16()**, **GetInt32()**, or **GetInt64()**. Given an integer node value, all numeric methods return meaningful values. Integer getters cannot reliably retrieve Single or Double values, and may return an inaccurate or meaningless value.

Class IRIS getters for String, byte[], and IRISList

In the InterSystems IRIS database, String, byte[], and IRISList objects are all stored as strings, and no information about the original datatype is preserved. The IRIS **GetString()**, **GetBytes()**, and **GetIRISList()** methods get string data and attempt to coerce it to the desired format.

The string getters assume that a node value is non-numeric, and attempt to convert it appropriately. They return null if the target node is valueless or does not exist. These methods do not perform any type checking, and will not usually throw an exception if the node value is of the wrong datatype.

Class IRIS getters for .NET classes

The IRIS class also supports getters for some .NET classes:

- **GetDateTime()** gets instances of System.DateTime.
- **GetObject()** returns the value of the target node as an object.
- **GetBytes()** can be used to get objects that implement System.IO.MemoryStream. An instance of MemoryStream will be stored as byte[] when set as a node value. Use **GetBytes()** to retrieve the value, then initialize a MemoryStream with the returned byte [] value.

Important: Getter methods do not check for incompatible datatypes

These methods are optimized for speed, and never perform type checking. Your application should never depend on an exception being thrown if one of these methods attempts to fetch a value of the wrong datatype. Although an exception may be thrown, it is more likely that the method will fail silently, returning an inaccurate or meaningless value.

5

Transactions and Locking

The *Native API for .NET* offers an alternative to the standard ADO.NET/SQL transaction model, based on ObjectScript transaction and locking methods. For information on the ObjectScript transaction model, see "Transaction Processing" in *Using ObjectScript*.

The following topics are discussed in this chapter:

- Controlling Transactions describes how transactions are started, nested, rolled back, and committed.
- Concurrency Control describes how to use the various lock methods.

Important: Never Mix IRIS Native and ADO.NET Transaction Models

DO NOT mix the IRIS Native transaction model with the ADO.NET/SQL transaction model.

- If you want to use only IRIS Native commands within a transaction, you should always use IRIS Native transaction methods.
- If you want to use a mix of IRIS Native and ADO.NET/SQL commands within a transaction, you should turn autoCommit OFF and then always use IRIS Native transaction methods.
- If you want to use only ADO.NET/SQL commands within a transaction, you can either always use SQL transaction methods, or turn autocommit OFF and then always use IRIS Native transaction methods.
- Although you can use both models in the same application, you must take care never to start a transaction in one model while a transaction is still running in the other model.

5.1 Controlling Transactions

The methods described here are alternatives to the standard ADO.NET/SQL transaction model. The Native API model for transaction and concurrency control is based on ObjectScript methods, and is not interchangeable with the .NET model. The Native API model must be used if your transactions include Native API method calls.

For more information on the ObjectScript transaction model, see "Transaction Processing" in Using ObjectScript.

The Native API provides the following methods to control transactions:

- IRIS.TCommit() commits one level of transaction.
- IRIS.TStart() starts a transaction (which may be a nested transaction).

- IRIS.GetTLevel() returns an int value indicating the current transaction level (0 if not in a transaction).
- IRIS.TRollback() rolls back all open transactions in the session.
- IRIS.TRollbackOne() rolls back the current level transaction only. If this is a nested transaction, any higher-level transactions will not be rolled back.

The following example starts three levels of nested transaction, setting the value of a different node in each transaction level. All three nodes are printed to prove that they have values. The example then rolls back the second and third levels and commits the first level. All three nodes are printed again to prove that only the first node still has a value.

Controlling Transactions: Using three levels of nested transaction

```
String globalName = "myGlobal";
  iris.TStart();
  // GetTLevel() is 1: create myGlobal(1) = "firstValue"
  iris.Set("firstValue", globalName, iris.GetTLevel());
  iris.TStart();
  // GetTLevel() is 2: create myGlobal(2) = "secondValue"
  iris.Set("secondValue", globalName, iris.GetTLevel());
  iris.TStart();
  // GetTLevel() is 3: create myGlobal(3) = "thirdValue"
  iris.Set("thirdValue", globalName, iris.GetTLevel());
  Console.WriteLine("Node values before rollback and commit:");
  for (int ii=1;ii<4;ii++) {</pre>
    Console.Write(globalName + "(" + ii + ") = ");
    if (iris.isDefined(globalName,ii) > 1) Console.WriteLine(iris.GetString(globalName,ii));
    else Console.WriteLine("<valueless>");
  prints: Node values before rollback and commit:
           myGlobal(1) = firstValue
myGlobal(2) = secondValue
           myGlobal(3) = thirdValue
  iris.TRollbackOne();
                        // roll back 2 levels to GetTLevel 1
  iris.TRollbackOne();
  iris.TCommit(); // GetTLevel() after commit will be 0
  Console.WriteLine("Node values after the transaction is committed:");
  for (int ii=1;ii<4;ii++)
    System.out.print(globalName + "(" + ii + ") = ");
    if (iris.isDefined(globalName,ii) > 1) Console.WriteLine(iris.GetString(globalName,ii));
    else Console.WriteLine("<valueless>");
  prints: Node values after the transaction is committed:
           myGlobal(1) = firstValue
myGlobal(2) = <valueless>
//
//
           myGlobal(3) = <valueless>
```

5.2 Concurrency Control

Concurrency control is a vital feature of multi-process systems such as InterSystems IRIS. It provides the ability to lock specific elements of data, preventing the corruption that would result from different processes changing the same element at the same time. The Native API transaction model provides a set of locking methods that correspond to ObjectScript commands. These methods must not be used with the ADO.NET/SQL transaction model (see the warning at the beginning of this chapter for details).

The following methods of class IRIS are used to acquire and release locks. Both methods take a *lockMode* argument to specify whether the lock is shared or exclusive:

```
Lock(string lockMode, int timeout, string globalName, Object[] subscripts)
Unlock(string lockMode, string globalName, Object[] subscripts)
```

- IRIS.Lock() Takes *lockMode*, *timeout*, *globalName*, and *subscripts* arguments, and locks the node. The *lockMode* argument specifies whether any previously held locks should be released. This method will time out after a predefined interval if the lock cannot be acquired.
- IRIS.Unlock() Takes *lockMode*, *globalName*, and *subscripts* arguments, and releases the lock on a node.

The following argument values can be used:

- *lockMode* combination of the following chars, S for shared lock, E for escalating lock, default is empty string (exclusive and non-escalating)
- timeout amount to wait to acquire the lock in seconds

Note: You can use the Management Portal to examine locks. Go to System Operation > Locks to see a list of the locked items on your system.

There are two ways to release all currently held locks:

- IRIS.ReleaseAllLocks() releases all locks currently held by this connection.
- When the Close() method of the connection object is called, it releases all locks and other connection resources.

Tip: A detailed discussion of concurrency control is beyond the scope of this book. See the following books and articles for more information on this subject:

- "Transaction Processing" and "Lock Management" in Using ObjectScript
- "Locking and Concurrency Control" in the Orientation Guide for Server-Side Programming
- "LOCK" in the *ObjectScript Reference*

6

Native API for .NET Quick Reference

This is a quick reference for the InterSystems IRIS Native API for .NET, providing information on the following extension classes in InterSystems.Data.IRISClient.ADO:

- Class IRIS provides the main functionality of the Native API.
- Class IRISIterator provides methods to navigate a global array.
- Class IRISList provides support for InterSystems \$LIST serialization.
- Class IRISObject provides methods to work with Object Gateway reverse proxy objects.

All of these classes are part of the InterSystems ADO.NET Managed Provider (InterSystems.Data.IRISClient.ADO). They access the database through a standard .NET connection, and can be used without any special setup or installation procedures.

Note: This chapter is intended as a convenience for readers of this book, but it is not the definitive reference for the Native API. For the most complete and up-to-date information, see the online class documentation.

All methods listed in the following sections will throw an exception on encountering any kind of error. Throughout the API, the subscript argument Object[] args is defined as params object[].

6.1 Class IRIS

Class IRIS is a member of InterSystems.Data.IRISClient.ADO (the InterSystems ADO.NET Managed Provider).

IRIS has no public constructors. Instances of IRIS are created by calling static method IRIS. CreateIRIS().

6.1.1 IRIS Method Details

ClassMethodBool()

ADO.IRIS. Class Method Bool() calls an Object Script class method, passing zero or more arguments and returning an instance of bool?.

bool ClassMethodBool(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.

• args — zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodBytes()

ADO.IRIS. ClassMethodBytes() calls an ObjectScript class method, passing zero or more arguments and returning an instance of byte[].

byte[] ClassMethodBytes(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodDouble()

ADO.IRIS. Class Method Double() calls an Object Script class method, passing zero or more arguments and returning an instance of double?.

double ClassMethodDouble(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodIRISList()

ADO.IRIS. ClassMethodIRISList() calls an ObjectScript class method, passing zero or more arguments and returning an instance of IRISList.

```
IRISList ClassMethodIRISList(string className, string methodName, params object[] args)
```

This method is equivalent to newList=(IRISList) ClassMethodBytes(className, methodName, args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodLong()

ADO.IRIS. ClassMethodLong() calls an ObjectScript class method, passing zero or more arguments and returning an instance of long?.

long ClassMethodLong(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodObject()

ADO.IRIS.ClassMethodObject() calls an ObjectScript class method, passing zero or more arguments and returning an instance of object. If the returned object is a valid OREF (for example, if %New() was called),

ClassMethodObject() will generate and return a reverse proxy object (an instance of IRISObject) for the referenced object. See "Using .NET Reverse Proxy Objects" for details and examples.

object ClassMethodObject(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

ClassMethodStatusCode()

ADO.IRIS.ClassMethodStatusCode() tests whether a class method that returns an ObjectScript \$Status object would throw an error if called with the specified arguments. If the call would fail, this method throws an IRISException error containing the ObjectScript \$Status error status number and message.

void ClassMethodStatusCode(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

This is an indirect way to catch exceptions when using ClassMethod[type] calls. If the call would run without error, this method returns without doing anything, meaning that you can safely make the call with the specified arguments.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodString()

ADO.IRIS. ClassMethodString() calls an ObjectScript class method, passing zero or more arguments and returning an instance of string.

string ClassMethodString(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.

• args — zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

ClassMethodVoid()

ADO.IRIS. Class Method Void() calls an Object Script class method with no return value, passing zero or more arguments.

void ClassMethodVoid(string className, string methodName, params object[] args)

parameters:

- className fully qualified name of the class to which the called method belongs.
- methodName name of the class method.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

Close()

ADO.IRIS.Close() closes the IRIS object.

void Close()

CreateIRIS() [static]

ADO.IRIS.CreateIRIS() returns an instance of ADO.IRIS that uses the specified IRISConnection.

static IRIS CreateIRIS(IRISADOConnection conn)

parameters:

• conn — an instance of IRISConnection.

See "Introduction to Global Arrays" for more information and examples.

FunctionBool()

ADO.IRIS.**FunctionBool**() calls an ObjectScript function, passing zero or more arguments and returning an instance of bool?.

bool FunctionBool(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

FunctionBytes()

ADO.IRIS. **FunctionBytes**() calls an ObjectScript function, passing zero or more arguments and returning an instance of byte[].

byte[] FunctionBytes(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

FunctionDouble()

ADO.IRIS.**FunctionDouble()** calls an ObjectScript function, passing zero or more arguments and returning an instance of double?.

double FunctionDouble(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

FunctionInt()

ADO.IRIS.**FunctionInt**() calls an ObjectScript function, passing zero or more arguments and returning an instance of long?.

long FunctionInt(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

FunctionIRISList()

ADO.IRIS.**FunctionIRISList()** calls an ObjectScript function, passing zero or more arguments and returning an instance of IRISList.

```
IRISList FunctionIRISList(string functionName, string routineName, params object[] args)
```

This function is equivalent to newList=(IRISList) FunctionBytes(functionName, routineName, args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

FunctionLong()

ADO.IRIS.**FunctionLong**() calls an ObjectScript function, passing zero or more arguments and returning an instance of Long.

long FunctionLong(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

FunctionObject()

ADO.IRIS.**FunctionObject**() calls an ObjectScript function, passing zero or more arguments and returning an instance of object. If the returned object is a valid OREF, **FunctionObject**() will generate and return a reverse proxy object (an instance of IRISObject) for the referenced object. See "Using .NET Reverse Proxy Objects" for details and examples.

object FunctionObject(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Class IRIS Supported Datatypes" for related information.

FunctionString()

ADO.IRIS.**FunctionString()** calls an ObjectScript function, passing zero or more arguments and returning an instance of string.

string FunctionString(string functionName, string routineName, params object[] args)

parameters:

- functionName name of the function to call.
- routineName name of the routine containing the function.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for details and examples.

GetAPIVersion() [static]

ADO.IRIS.GetAPIVersion() returns the IRIS Native API version string.

```
static String GetAPIVersion()
```

GetBool()

ADO.IRIS.**GetBool**() gets the value of the global as a bool? (or null if node does not exist). Returns false if node value is empty string.

bool GetBool(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetBytes()

ADO.IRIS.GetBytes() gets the value of the global as a byte[] (or null if node does not exist).

byte[] GetBytes(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetDateTime()

ADO.IRIS.GetDateTime() gets the value of the global as a DateTime? (or null if node does not exist).

DateTime GetDateTime(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetDouble()

ADO.IRIS.**GetDouble()** gets the value of the global as a double? (or null if node does not exist). Returns 0.0 if node value is empty string.

Double GetDouble(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetInt16()

ADO.IRIS.**GetInt16**() gets the value of the global as an Int16? (or null if node does not exist). Returns 0 if node value is empty string.

Int16 GetInt16(string globalName, params object[] subscripts)

parameters:

• globalName — global name.

• subscripts — zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetInt32()

ADO.IRIS.**GetInt32**() gets the value of the global as an Int32? (or null if node does not exist). Returns 0 if node value is empty string.

Int32 GetInt32(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetInt64()

ADO.IRIS.**GetInt64**() gets the value of the global as an Int64? (or null if node does not exist). Returns 0 if node value is empty string.

Int64 GetInt64(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetIRISIterator()

ADO.IRIS.**GetIRISIterator**() returns an IRISIterator object (see "Class IRISIterator") for the specified node with search direction set to FORWARD. See "Iterating Over a Set of Child Nodes" for more information and examples.

IRISIterator GetIRISIterator(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetIRISList()

ADO.IRIS.GetIRISList() gets the value of the node as an IRISList (or null if node does not exist).

```
IRISList GetIRISList(String globalName, params object[] subscripts)
```

This is equivalent to calling newList=(IRISList) GetBytes(globalName, subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetIRISReverselterator()

ADO.IRIS.**GetIRISReverseIterator**() returns an IRISIterator object (see "Class IRISIterator") for the specified node with search direction set to BACKWARD. See "Iterating Over a Set of Child Nodes" for more information and examples.

IRISIterator GetIRISReverseIterator(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetObject()

ADO.IRIS.GetObject() gets the value of the global as an Object (or null if node does not exist). See "Using .NET Reverse Proxy Objects" for details and examples.

object GetObject(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetServerVersion()

ADO.IRIS.**GetServerVersion()** returns the server version string for the current connection. This is equivalent to calling \$system.Version.GetVersion() in ObjectScript.

```
String GetServerVersion()
```

GetSingle()

ADO.IRIS.**GetSingle**() gets the value of the global as a Single? (Nullable<float>) or null if node does not exist. Returns 0.0 if node value is an empty string.

Single GetSingle(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetString()

ADO.IRIS.GetString() gets the value of the global as a string (or null if node does not exist).

Empty string and null values require some translation. An empty string " " in .NET is translated to the null string character \$CHAR(0) in ObjectScript. A null in .NET is translated to the empty string in ObjectScript. This translation is consistent with the way .NET handles these values.

string GetString(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

GetTLevel()

ADO.IRIS.**GetTLevel**() gets the level of the current nested IRIS Native transaction. Returns 1 if there is only a single transaction open. Returns 0 if there are no transactions open. This is equivalent to fetching the value of the **\$TLEVEL** special variable.

```
int GetTLevel()
```

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

Increment()

ADO.IRIS.Increment() increments the specified global with the passed value. If there is no node at the specified address, a new node is created with value as the value. A null value is interpreted as 0. Returns the new value of the global node. See "Creating, Accessing, and Deleting Nodes" for more information and examples.

```
long Increment(long? value, string globalName, params object[] subscripts)
```

parameters:

- value long value to which to set this node (null value sets global to 0).
- globalName global name.
- subscripts zero or more subscripts specifying the target node.

IsDefined()

ADO.IRIS.**IsDefined()** returns a value indicating whether the specified node exists and if it contains a value. See "Testing for Child Nodes and Node Values" for more information and examples.

```
int IsDefined(string globalName, params object[] subscripts)
```

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

return values:

- 0 the specified node does not exist
- 1 the node exists and has a value
- 10 the node is valueless but has subnodes
- 11 the node has both a value and subnodes

Kill()

ADO.IRIS.Kill() deletes the global node including any descendants. See "Creating, Accessing, and Deleting Nodes" for more information and examples.

void Kill(string globalName, params object[] subscripts)

parameters:

- globalName global name.
- subscripts zero or more subscripts specifying the target node.

Lock()

ADO.IRIS.Lock() locks the global for an IRIS Native transaction, and returns true on success. Note that this method performs an incremental Lock and not the implicit Unlock before Lock feature that is also offered in ObjectScript.

bool Lock(string lockMode, int timeout, string globalName, params object[] subscripts)

parameters:

- lockMode Character S for shared Lock, E for escalating Lock, or SE for both. Default is empty string (exclusive and non-escalating).
- timeout amount to wait to acquire the Lock in seconds.
- globalName global name.
- subscripts zero or more subscripts specifying the target node.

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

Procedure()

ADO.IRIS.Procedure() calls a procedure, passing zero or more arguments. Does not return a value.

void Procedure(string procedureName, string routineName, params object[] args)

parameters:

- procedureName name of the procedure to call.
- routineName name of the routine containing the procedure.
- args zero or more arguments of supported types.

See "Calling ObjectScript Methods and Functions" for more information and examples.

ReleaseAllLocks()

ADO.IRIS.**ReleaseAllLocks()** is an IRIS Native transaction method that releases all locks associated with the session.

```
void ReleaseAllLocks()
```

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

Set()

ADO.IRIS.Set() sets the current node to a value of a supported datatype (or "" if the value is null). If there is no node at the specified node address, a new node will be created with the specified value. See "Creating, Accessing, and Deleting Nodes" for more information.

```
void Set(bool? value, string globalName, params object[] subscripts)
void Set(byte[] value, string globalName, params object[] subscripts)
void Set(DateTime? value, string globalName, params object[] subscripts)
void Set(Double? value, string globalName, params object[] subscripts)
void Set(Int16? value, string globalName, params object[] subscripts)
void Set(Int32? value, string globalName, params object[] subscripts)
void Set(Int64? value, string globalName, params object[] subscripts)
void Set(IRISList value, String globalName, params object[] subscripts)
void Set(object value, string globalName, params object[] subscripts)
void Set(Single? value, string globalName, params object[] subscripts)
void Set(String value, string globalName, params object[] subscripts)
void Set(System.IO.MemoryStream value, string globalName, params object[] subscripts)
```

parameters:

- value value of a supported datatype (null value sets global to "").
- globalName global name.
- subscripts zero or more subscripts specifying the target node.

See "Class IRIS Supported Datatypes" for related information.

Notes on specific datatypes

The following datatypes have some extra features:

- string empty string and null values require some translation. An empty string " " in .NET is translated to the null string character \$CHAR(0) in ObjectScript. A null in .NET is translated to the empty string in ObjectScript. This translation is consistent with the way .NET handles these values.
- System.IO.MemoryStream an instance of an object that implements MemoryStream will be stored as a byte[] when set as the global value. A null in .NET is translated to the empty string in ObjectScript. Use **getBytes()** to retrieve the value, then initialize a MemoryStream with the returned byte [] value.

TCommit()

ADO.IRIS.TCommit() commits the current IRIS Native transaction.

```
void TCommit()
```

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

TRollback()

ADO.IRIS.TRollback() rolls back all open IRIS Native transactions in the session.

```
void TRollback()
```

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

TRollbackOne()

ADO.IRIS.**TRollbackOne()** rolls back the current level IRIS Native transaction only. If this is a nested transaction, any higher-level transactions will not be rolled back.

```
void TRollbackOne()
```

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

TStart()

ADO.IRIS.TStart() starts/opens an IRIS Native transaction.

```
void TStart()
```

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

Unlock()

ADO.IRIS.Unlock() unlocks the global in an IRIS Native transaction. This method performs an incremental Unlock, not the implicit Unlock-before-Lock feature that is also offered in ObjectScript.

```
void Unlock(string lockMode, string globalName, params object[] subscripts)
```

parameters:

- lockMode Character S for shared Lock, E for escalating Lock, or SE for both. Default is empty string (exclusive and non-escalating).
- globalName global name.
- subscripts zero or more subscripts specifying the target node.

This method uses the IRIS Native transaction model, and is not compatible with ADO.NET/SQL transaction methods. Never mix the two transaction models. See "Transactions and Locking" for more information and examples.

6.2 Class IRISIterator

Class IRISIterator is a member of InterSystems. Data. IRISClient. ADO (the InterSystems ADO. NET Managed Provider).

Instances of IRISIterator are created by calling one of the following IRIS methods:

- ADO.IRIS.GetIRISIterator() Returns an IRISIterator instance set to forward iteration.
- ADO.IRIS.GetIRISReverseIterator() Returns an IRISIterator instance set to backward iteration.

See "Iterating Over a Set of Child Nodes" for more information and examples.

This class implements required IEnumerator method System.Collections.IEnumerator.GetEnumerator(), which is invoked when the iterator is used in a foreach loop.

All methods listed in the following sections will throw an exception on encountering any kind of error.

6.2.1 IRISIterator Method and Property Details

Property Current

ADO.IRISIterator. Current gets the value of the node at the current iterator position. In a foreach loop, this value is also assigned to the current loop variable. See "Iteration in Conditional Loops" for more information and examples.

```
object Current [get]
```

Property CurrentSubscript

ADO.IRISIterator.**CurrentSubscript** gets the lowest level subscript for the node at the current iterator position. For example, if the iterator points to node 'myGlobal(23, "somenode"), the returned value will be "somenode". See "Iteration in Conditional Loops" for more information and examples.

```
object CurrentSubscript [get]
```

MoveNext()

ADO.IRISIterator.MoveNext() implements System.Collections.IEnumerator. It returns true if the next value was retrieved, false if there are no more values. See "Iteration in Conditional Loops" for more information and examples.

```
bool MoveNext()
```

Reset()

ADO.IRISIterator.Reset() can be called after completing a foreach loop to reset the iterator to its starting position, allowing it to be used again. See "Iteration in Conditional Loops" for more information and examples.

```
void Reset()
```

StartFrom()

ADO.IRISIterator.**StartFrom**() sets the iterator's starting position to the specified subscript. The subscript is an arbitrary starting point, and does not have to specify an existing node. See "Iterating Over a Set of Child Nodes" for more information and examples.

```
void StartFrom(Object subscript)
```

6.3 Class IRISList

Class IRISList is a member of InterSystems.Data.IRISClient.ADO (the InterSystems ADO.NET Managed Provider). It implements a .NET interface for InterSystems \$LIST serialization. In addition to the IRISList constructors (described in the following section), it is also returned by the following ADO.IRIS methods: classMethodIRISList(), functionIRISList(), getIRISList().

6.3.1 IRISList Constructors

Constructor ADO.IRISList.IRISList() has the following signatures:

```
public IRISList()
public IRISList(IRISList list)
public IRISList(byte[] buffer, int length)
```

parameters:

- list instance of IRISList to be copied
- buffer buffer to be allocated
- length initial buffer size to be allocated

Instances of IRISList can be created in the following ways:

Create an empty IRISList

```
IRISList list = new IRISList();
```

Create a copy of another IRISList

Create a copy of the IRISList instance specified by argument *list*.

```
IRISList listcopy = new IRISList(myOtherList)
```

Construct an IRISList instance from a byte array

Construct an instance from a \$LIST formatted byte array, such as that returned by IRIS. **GetBytes**(). The constructor takes a *buffer* of size *length*:

```
byte[] listBuffer = myIris.GetBytes("myGlobal",1);
IRISList listFromByte = new IRISList(listBuffer, listBuffer.length);
```

The returned list uses the buffer (not a copy) until changes to the list are visible in the buffer and a resize is required.

6.3.2 IRISList Method Details

Add()

ADO.IRISList.**Add**() appends an Object of any supported type to the end of the IRISList. If *value* is an IRISList, it will be added as a single element (IRISList instances are never concatenated).

```
void Add(Object value)
```

parameters:

• value — Object value. The following types are supported: Int16, Int32, Int64, bool, Single, Double, string, byte[], IRISList.

Adding an IRISList element

Add() always appends an IRISList instance as a single object. However, you can use IRISList.**ToArray()** to convert an IRISList to an array, and then call **Add()** on each element separately.

AddRange()

ADO.IRISList.**AddRange**() appends each element of a collection to the end of the list as it is returned by the collection iterator. An exception will be thrown if any element is not one of the supported types.

```
void AddRange(System.Collections.IList list)
```

parameters:

• list — a collection containing only elements of the following types: Int16, Int32, Int64, bool, Single, Double, string, byte[], IRISList.

See "Class IRIS Supported Datatypes" for related information.

Clear()

ADO.IRISList.Clear() resets the list by removing all elements from the list.

```
void Clear()
```

Count()

ADO.IRISList.Count() iterates over the list and returns the number of elements encountered.

```
int Count()
```

DateToHorolog() [static]

ADO.IRISList.**DateToHorolog()** converts the *date* property of a DateTime value to an int representing the *day* field of a **\$Horolog** string. Also see **HorologToDate()**.

```
static int DateToHorolog(DateTime value)
parameters:
```

value — DateTime value to convert.

DateToPosix() [static]

ADO.IRISList.**DateToPosix**() converts a Time object to the *time* field of a **\$Horolog** string.

```
static long DateToPosix(DateTime Value)
parameters:
```

Value — DateTime value to convert.

Equals()

ADO.IRISList.**Equals**() compares the specified *list* with this instance of IRISList, and returns true if they are identical. To be equal, both lists must contain the same number of elements in the same order with identical serialized values.

```
override bool Equals(Object list)
```

parameters:

• list — instance of IRISList to compare.

Get()

ADO.IRISList. $\mathbf{Get}()$ returns the element at *index* as Object. Throws IndexOutOfRangeException if the index is less than 1 or past the end of the list.

```
Object Get(int index)
```

parameters:

• index — integer specifying the list element to be retrieved.

GetList()

ADO.IRISList. GetList() gets the element at index as an IRISList. Throws IndexOutOfRangeException if the index is less then 1 or past the end of the list

```
IRISList GetList(int index)
```

parameters:

• index — integer specifying the list element to return

Throws IndexOutOfRangeException if the index is less then 1 or past the end of the list.

HorologToDate() [static]

ADO.IRISList.**HorologToDate()** converts the *day* field of a **\$Horolog** string to a DateTime value. Also see **DateToHorolog()**.

```
static DateTime HorologToDate(int HorologValue)
```

parameters:

• HorologValue — int representing the *day* field of a **\$Horolog** string.

HorologToTime() [static]

ADO.IRISList.**HorologToTime()** converts the *time* field of a **\$Horolog** string to a TimeSpan value. Also see **TimeToHorolog()**.

```
static TimeSpan HorologToTime(int HorologValue)
```

parameters:

HorologValue — intrepresenting the *time* field of a \$Horolog string. The *date* field will be zeroed out (set to the epoch), so a TimeSpan with a milliseconds value outside the range 0L to 86399999L does not round trip.

PosixToDate() [static]

ADO.IRISList.PosixToDate() converts a %Library.PosixTime value to a DateTime. Also see DateToPosix().

```
static DateTime PosixToDate(long PosixValue)
```

parameters:

• PosixValue — the %PosixTime value (a 64-bit signed integer).

Remove()

ADO.IRISList.**Remove**() removes the element at *index* from the list. Returns true if the element existed and was removed, false otherwise. This method can be expensive, since it will usually have to reallocate the list.

```
bool Remove(int index)
```

parameters:

• index — integer specifying the list element to remove.

Set()

ADO.IRISList.**Set()** sets or replaces the list element at *index* with *value*. If *value* is an array, each array element is inserted into the list, starting at *index*, and any existing list elements after *index* are shifted to make room for the new values. If *index* is beyond the end of the list, *value* will be stored at *index* and the list will be padded with nulls up to that position.

```
void Set(int index, Object value)
void Set(int index, object[] value)
```

Throws IndexOutOfRangeException if *index* is less than 1. All elements must be of the following types: Int16, Int32, Int64, bool, Single, Double, string, byte[], IRISList.

parameters:

- index integer indicating the list element to be set or replaced
- value Object value or object[] array to insert at *index*

Size()

ADO.IRISList.Size() returns the byte length of the serialized value for this IRISList.

```
int Size()
```

SubList()

ADO.IRISList.**SubList**() returns a new IRISList containing the elements in the closed range [*from*, *to*]. Throws IndexOutOfRangeException if *from* is greater than **Count**() or *to* is less than *from*.

```
IRISList SubList(int from, int to)
```

parameters:

- from index of first element to add to the new list.
- to index of last element to add to the new list.

TimeToHorolog() [static]

ADO.IRISList.**TimeToHorolog()** converts a DateTime value to the *time* field of a **\$Horolog** value. Also see **HorologToTime()**.

```
static int TimeToHorolog(DateTime value)
parameters:
```

• value — DateTime to be converted.

ToArray()

ADO.IRISList.**ToArray**() returns an array of the given type containing all of the elements in this list. If the list is empty, a zero length array will be returned.

IMPORTANT: This method should be used only if all elements can be coerced to be of the same type.

```
Object[] ToArray()
```

ToList()

ADO.IRISList.**ToList**() returns a List of the given type containing all of the elements in this IRISList. If the list is empty, a zero length List will be returned.

```
List<Object> ToList()
```

ToString()

 ${\sf ADO.IRISList.} \textbf{\textit{ToString}} () \ returns \ a \ printable \ representation \ of \ the \ list.$

```
override string ToString()
```

Some element types are represented differently than they would be in ObjectScript:

- An empty list (" " in ObjectScript) is displayed as "\$1b()".
- Empty elements (where \$1b()=\$c(1)) are displayed as "null".
- Strings are not quoted.
- Doubles format with sixteen significant digits

6.4 Class IRISObject

Class IRISObject is a member of InterSystems.Data.IRISClient.ADO (the InterSystems ADO.NET Managed Provider). It provides methods to work with Object Gateway reverse proxy objects (see "Using .NET Reverse Proxy Objects" for details and examples).

IRISObject has no public constructors. Instances of IRISObject can be created by calling one of the following IRIS methods:

- ADO.IRIS.ClassMethodObject()
- ADO.IRIS.FunctionObject()

If the called method or function returns an object that is a valid OREF, a reverse proxy object (an instance of IRISObject) for the referenced object will be generated and returned. For example, **ClassMethodObject()** will return a proxy object for an object created by **%New()**.

See "Using .NET Reverse Proxy Objects" for details and examples.

6.4.1 IRISObject Method Details

Dispose()

ADO.IRISObject. **Dispose()** releases this instance of IRISObject.

```
void Dispose()
```

Get()

ADO.IRISObject.Get() returns a property value of the proxy object as an instance of object.

```
object Get(string propertyName)
```

parameters:

propertyName — name of the property to be returned.

GetBool()

ADO.IRISObject.GetBool() returns a property value of the proxy object as an instance of bool.

```
bool GetBool(string propertyName)
```

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

GetBytes()

ADO.IRISObject.GetBytes() returns a property value of the proxy object as an instance of byte[].

```
byte[] GetBytes(string propertyName)
```

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

GetDouble()

ADO.IRISObject.GetDouble() returns a property value of the proxy object as an instance of double.

```
double GetDouble(string propertyName)
```

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

GetIRISList()

ADO.IRISObject.GetIRISList() returns a property value of the proxy object as an instance of IRISList.

```
IRISList getIRISList(String propertyName)
```

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

GetLong()

ADO.IRISObject.GetLong() returns a property value of the proxy object as an instance of long.

```
Long getLong(String propertyName)
```

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

GetObject()

ADO.IRISObject.GetObject() returns a property value of the proxy object as an instance of object.

```
Object getObject(String propertyName)
```

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

GetString()

ADO.IRISObject.GetString() returns a property value of the proxy object as an instance of string.

String getString(String propertyName)

parameters:

• propertyName — name of the property to be returned.

See "IRISObject Supported Datatypes" for related information.

Invoke()

ADO.IRISObject.Invoke() invokes an instance method of the object, returning value as object.

```
object Invoke(string methodName, params object[] args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

Arguments may be of any of the following types: int?, short?, string, long?, double?, float?, byte[], bool?, DateTime?, IRISList?, or IRISObject. If the connection is bidirection, then any .NET object can be used as an argument.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeBoolean()

ADO.IRISObject.InvokeBool() invokes an instance method of the object, returning value as bool.

```
Boolean invokeBoolean(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeBytes()

ADO.IRISObject.InvokeBytes() invokes an instance method of the object, returning value as byte[].

```
byte[] invokeBytes(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeDouble()

ADO.IRISObject.InvokeDouble() invokes an instance method of the object, returning value as double.

```
Double invokeDouble(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeIRISList()

ADO.IRISObject.InvokeIRISList() invokes an instance method of the object, returning value as IRISList.

```
IRISList invokeIRISList(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeLong()

ADO.IRISObject.InvokeLong() invokes an instance method of the object, returning value as long.

```
Long invokeLong(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeObject()

ADO.IRISObject.InvokeObject() invokes an instance method of the object, returning value as object.

```
Object invokeObject(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeStatusCode()

ADO.IRISObject.InvokeStatusCode() tests whether an invoke method that returns an ObjectScript \$Status object would throw an error if called with the specified arguments. If the call would fail, this method throws a RuntimeException error containing the ObjectScript \$Status error number and message. See "Catching %Status Error Codes" for details and examples.

```
void invokeStatusCode(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeString()

ADO.IRISObject.InvokeString() invokes an instance method of the object, returning value as string.

```
String invokeString(String methodName, Object... args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

InvokeVoid()

ADO.IRISObject.InvokeVoid() invokes an instance method of the object, but does not return a value.

```
void InvokeVoid(string methodName, params object[] args)
```

parameters:

- methodName name of the instance method to be called.
- args zero or more arguments of supported types.

See "IRISObject Supported Datatypes" for valid argument types and related information.

iris [attribute]

jdbc.IRISObject.iris is a public field that provides access to the instance of IRIS associated with this object.

```
public IRIS iris
```

See "IRISObject Supported Datatypes" for related information.

Set()

ADO.IRISObject.Set() sets a property of the proxy object.

```
void Set(string propertyName, Object value)
```

parameters:

- propertyName name of the property to which *value* will be assigned.
- value property value to assign.