# The STklos Virtual Machine

Jeronimo Pellegrini

# **Table of Contents**

1. The bytecode	2
2. Value register	3
3. Stack	6
4. Local variables	7
5. Deep variables	9
6. Global variables	10
7. Operations	11
7.1. Arithmetic	11
7.2. Increment and decrement val.	13
7.3. Comparisons	13
7.4. Constructors	14
7.5. Structure references	15
8. Control flow	17
9. Closures, let, and related	18
9.1. let	18
10. Miscelannea	19
10.1. Creating closures and procedures	20
10.2. Procedure calls	21
11. Modules	25
12. vm.c	27
12.1. The global lock	27
12.2.run_vm(vm_thread *vm)	28
13 Continuations	20

This is the documentation for the opcodes of the STklos virtual machine. The VM implementation is contained in the files src/vm.h and src/vm.c.

The VM has a stack, which in the source code is accessed using the C functions push(elt) and pop(). Each VM thread also has:

- STk\_instr \*pc, the program counter
- SCM \*fp, the frame pointer
- SCM \*sp, the Scheme stack pointer
- SCM \*stack, the Scheme stack
- int stack\_len, the length of the stack
- SCM val, a register for the current value
- SCM vals[], a register for multiple values
- int valc, the number of multiple values
- SCM r1, r2 two registers
- SCM env, the current environment
- SCM current\_module, the current module
- SCM iport, oport, eport, the current input, output and error ports
- SCM scheme\_thread, the Scheme thread associated with this thread

Of these, only a few are relevant to understanding the bytecode – these are the value registers and the stack.

## Chapter 1. The bytecode

STklos bytecode is a sequence of 16-bit integers. You can see the opcodes of a compiled thunk with

```
(disassemble (lambda () ...))
```

and the opcodes of an expression with

```
(disassemble-expr 'expr)
```

With an extra #t argument, dissasemble-proc will show constants:

```
(disassemble-expr "abc")

000: CONSTANT 0
002:
```

```
(disassemble-expr "abc" #t)
```

When we make a closure with the lambda, we'll always see a RETURN at the end of the output:

```
stklos> (disassemble (lambda () '() ))
```

```
000: IM-NIL
001: RETURN
```

In the above example, one opcode loads the NIL value to the register and another opcode `RETURN`s. This return is from the lambda.

## Chapter 2. Value register

The simpler opcodes are those that carry with them an immediate value. These operations will copy their value to the val register in the VM.

```
IM_FALSE
IM_TRUE
IM_NIL
IM_MINUS1
IM_ZERO
IM_ONE
IM_VOID
```

Examples:

```
(disassemble-expr 1)

000: IM-ONE

(disassemble (lambda () #f 1) )

000: IM-FALSE
001: IM-ONE
002: RETURN
```

Opcodes for small integers and constants do the same, but they take a little longer to execute, since they need to perform some small operations.

```
SMALL_INT
CONSTANT
```

```
(disassemble-expr 5)
```

```
000: SMALL-INT 5
```

Small integers are *not* the same as fixnums! A small integer is an integer number that fits in 16 bits (that is, in one bytecode element). The fixnum range depends on the size of long in the platform being used.

Suppose STklos has been compiled on a 64 bit system and also ona 32 bit system. The ranges for

small ints and fixnums are:

```
small integer (on both): [ -2^15, +2^15 - 1 ]
fixnum (long is 32-bit): [ -2^29, +2^29 - 1 ]
fixnum (long is 64-bit): [ -2^61, +2^61 - 1 ]
```

The expression above, 5, is compiled into the bytes

```
00 08 00 05
```

where 00 08 is the opcode for 'small int'', and '00 05 is the argument (the small integer, 5).

Small integers are compiled *into* the bytecode. Fixnums, bignums, strings are stored *outside* of the bytecode, and the instruction CONSTANT takes as argument an index into the constants vector.

The expression 50000 is not a small integer, so it is compiled as a constant:

```
(disassemble-expr 50000 #t)
000: CONSTANT 0
002:

Constants:
0: 50000
```

Zero is the index of 50000 in the constants vector.

The above code is compiled into bytecode as

```
00 09 00 00
```

where 00 09 means CONSTANT and 00 00 is the index into the constants vector.

Another clarifying example:

(disassemble-expr '(values 50000 ``abc'') #t)

```
000: PREPARE-CALL
001: CONSTANT-PUSH 0
003: CONSTANT-PUSH 1
005: GREF-INVOKE 2 2
008:

Constants:
0: 50000
1: "abc"
```

2: values

The bytecode is

37 85 0 85 1 86 2 2

#### Here,

- 85 0 is CONSTANT-PUSH 0 (0 = first element of the vector)
- 85 1 is CONSTANT-PUSH 1 (1 = second element)
- 86 2 2 is GREF-INVOKE 2 2 (2 = number, arg to `values, next 2 = third element of vector)

# Chapter 3. Stack

The following opcodes are similar to the immediate-value ones, except that, instead of copying their values to the val register, they push the value on the stack.

```
FALSE_PUSH
TRUE_PUSH
NIL_PUSH
MINUS1_PUSH
ZERO_PUSH
ONE_PUSH
VOID_PUSH
INT_PUSH
CONSTANT_PUSH
```

The POP and PUSH move objects between stack and value register.

```
POP ; move top of stack to val register
PUSH ; store val register on top of stack
```

# Chapter 4. Local variables

The LOCAL\_REF opcodes will load the values of variables from the current environment (the `local'' variables) on the `val register.

```
LOCAL_REF0
LOCAL_REF1
LOCAL_REF2
LOCAL_REF3
LOCAL_REF4
LOCAL_REF
```

#### Examples:

```
(disassemble (lambda (a) a))
```

```
000: LOCAL-REF0
001: RETURN
```

```
(disassemble (lambda (a b) a))
```

```
000: LOCAL-REF1
001: RETURN
```

There are opcodes for five fixed positions only, so after that another opcode, LOCAL\_REF, needs an argument:

```
(disassemble (lambda (a b c d e f) a))
```

```
000: LOCAL-REF 5
002: RETURN
```

The following opcodes are similar to the local reference ones, except that, instead of copying their values to the val register, they push the value on the stack.

```
LOCAL_REF0_PUSH
LOCAL_REF1_PUSH
LOCAL_REF3_PUSH
LOCAL_REF4_PUSH
```

The following opcodes are analogous to the local reference ones, but instead of loading values, they store the value of the val register on the local variables



## Chapter 5. Deep variables

Variables which are visible but not in the immediately accessible environment are accessed with the DEEP opcodes.

```
DEEP_LOCAL_REF
DEEP_LOCAL_SET
DEEP_LOC_REF_PUSH
```

#### Examples:

```
(disassemble
  (let ((a 10))
      (lambda () a)))
```

```
000: DEEP-LOCAL-REF 256
002: RETURN
```

```
000: SMALL-INT 20
002: DEEP-LOCAL-SET 256
004: RETURN
```

In the following example, the value of a is fetched from a deep environment and pushed onto the stack, so it can be used by the comparison opcode IN-NUMEQ:

```
(disassemble
  (let ((a 10))
        (lambda ()
        (= a 20))))
```

```
000: DEEP-LOC-REF-PUSH 256
002: SMALL-INT 20
004: IN-NUMEQ
005: RETURN
```

# Chapter 6. Global variables

Global variables can be read and set with the following opcodes:

```
GLOBAL-REF
GLOBAL-SET
```

### Examples:

```
(disassemble-expr 'my-cool-global-variable) #t)
```

000: GLOBAL-REF 0

Constants:

0: my-cool-global-variable

(disassemble-expr '(set! my-cool-global-variable #f) #t)

000: IM-FALSE

001: GLOBAL-SET 0

Constants:

0: my-cool-global-variable

# **Chapter 7. Operations**

### 7.1. Arithmetic

The operations take the top of stack and val as operands, and leave the result on val.

```
IN_ADD2
IN_SUB2
IN_MUL2
IN_DIV2
```

```
(disassemble-expr '(+ a 3) #t)
```

```
000: GLOBAL-REF    0
002: IN-SINT-ADD2    3

Constants:
0: a
```

First the value of a (which is the zero-th local variable) is pushed onto the stack. Then, DEEP-LOCAL-REF brings the value of x, and IM-ADD2 adds the two values, leaving the result on the local variable register.

For fixnums, the analogous opcodes are:

```
IN_FXADD2
IN_FXSUB2
IN_FXMUL2
IN_FXDIV2
```

```
(disassemble-expr '(fx+ v 3))
```

```
000: GLOBAL-REF    0
002: IN-SINT-FXADD2    3

Constants:
0: v
```

The following variant of those opcodes do not use the stack. They operate on val and an argument:

```
IN_SINT_ADD2
```

```
IN_SINT_SUB2
IN_SINT_MUL2
IN_SINT_DIV2
```

#### Example:

```
(disassemble-expr '(+ a 2))
```

000: GLOBAL-REF 0 002: IN-SINT-ADD2 2

Constants:

0: a

With a as a local variable:

```
(disassemble (lambda (a) (+ a 2)))
```

000: LOCAL-REF0 001: IN-SINT-ADD2 2

003: RETURN

First, the value of a is put on val; then it is summed with 2, which comes as an argument to the opcode IN-SINT-ADD2.

These also have fixnum variants:

```
IN_SINT_FXADD2
IN_SINT_FXSUB2
IN_SINT_FXMUL2
IN_SINT_FXDIV2
```

#### Example:

### (disassemble-expr '(fx+ a 2))

000: GLOBAL-REF 0
002: IN-SINT-FXADD2 2

Constants:

0: a

### 7.2. Increment and decrement val

```
IN_INCR
IN_DECR
```

## 7.3. Comparisons

These compare the top of stack with val, and leave a boolean on val.

```
IN_NUMEQ  ; pop() == val ?
IN_NUMDIFF  ; ! pop() == val ?
IN_NUMLT  ; pop < val ?
IN_NUMGT  ; pop > val ?
IN_NUMLE  ; pop <= val ?
IN_NUMGE  ; pop >= val ?
```

Example:

```
(disassemble-expr ' (>= a 2))
```

```
000: GLOBAL-REF-PUSH  0
002: SMALL-INT  2
004: IN-NUMGE

Constants:
0: a
```

There are also opcodes for equal?, eqv? and eq?:

```
IN_EQUAL
IN_EQV
IN_EQ
```

Example:

```
(disassemble-expr '(eq? a 2))
```

```
000: GLOBAL-REF-PUSH 0
002: SMALL-INT 2
004: IN-EQ
Constants:
```

```
0: a
```

The dissassemble procedures will not, however, show the names of symbols or values of strings (disassemble-expr does, when passed the extra #t argument).

```
(disassemble (lambda (a) (eq? a 'hello-i-am-a-symbol)))
```

```
000: LOCAL-REF0-PUSH
001: CONSTANT 0
003: IN-EQ
004: RETURN
```

```
(disassemble-expr '(eq? a 'hello-i-am-a-symbol) #t)
```

```
000: GLOBAL-REF-PUSH  0
002: CONSTANT     1
004: IN-EQ
005:

Constants:
0: a
1: hello-i-am-a-symbol
```

### 7.4. Constructors

These will build structures with the value in val and store the structure (that is, the tagged word representing it) again on val.

```
IN_CONS
IN_CAR
IN_CDR
IN_LIST
```

Examples:

```
(disassemble-expr '(cons "a" "b") #t)
```

```
000: CONSTANT-PUSH 0
002: CONSTANT 1
004: IN-CONS
005:
```

```
Constants:
0: "a"
1: "b"
```

```
(disassemble (lambda (a b) (cons a b)))
```

```
000: LOCAL-REF1-PUSH
001: LOCAL-REF0
002: IN-CONS
003: RETURN
```

The element to be consed is pushed on the stack; then the second element is loaded on val, and then IN-CONS is called.

```
(disassemble (lambda (a) (list a)))
```

```
000: LOCAL-REF0-PUSH
001: IN-LIST 1
003: RETURN
```

```
(disassemble-expr '(car a) #t)
```

## 7.5. Structure references

The following opcodes access and set elements of strings and vectors.

```
IN_VREF
IN_SREF
IN_VSET
IN_SSET
```

V stands for vector, S stands for string; then, REF and SET mean reference' and set".

The instructions will use the object in the stack and the index from the val register.

#### Examples

```
(disassemble
  (let ((a #(0 1 2 3)))
        (lambda () (vector-ref a 2))))
```

```
000: DEEP-LOC-REF-PUSH 256
002: SMALL-INT 2
004: IN-VREF
005: RETURN
```

In the following example, the CONSTANT-PUSH is including a reference to the string on the stack.

```
(disassemble-expr '(string-ref "abcde" 3) #t)
```

```
000: CONSTANT-PUSH 0
002: SMALL-INT 3
004: IN-SREF
005:

Constants:
0: "abcde"
```

When setting a value, the reference to the vector or string and the index go on the stack (index below the reference to the object – the index is popped first), and the value goes on val, then the setting opcode is used:

```
(disassemble
  (let ((v (vector #\a #\b #\c)))
     (lambda () (vector-set! v 2 10))))
```

```
000: DEEP-LOC-REF-PUSH 256 ; push ref. to vector
002: INT-PUSH 2 ; push index
004: SMALL-INT 10 ; put new value in val
006: IN-VSET ; set it!
007: RETURN
```

## Chapter 8. Control flow

The following opcodes have an argument, which is the offset to be added to the program counter.

```
; unconditionally jump
GOT0
JUMP_TRUE
                  ; jump if val is true
JUMP_FALSE
                 ; jump if val is false
JUMP_NUMDIFF
                 ; jump if ! pop() = val (for numbers)
                 ; jump if pop() = val (for numbers)
JUMP_NUMEQ
JUMP_NUMLT
                 ; jump of pop() < val
JUMP_NUMLE
                 ; jump of pop() <= val
JUMP_NUMGT ; jump of pop() > val
JUMP_NUMGE ; jump of pop() >= val
JUMP_NOT_EQ ; jump if pop() not eq? val
JUMP_NOT_EQV ; jump if pop() not eqv? val
JUMP_NOT_EQUAL ; jump if pop() not equal? val
```

Example:

```
(disassemble
(lambda () (if #t 2 4)))
```

```
000: IM-TRUE
001: JUMP-FALSE 3 ;; ==> 006
003: SMALL-INT 2
005: RETURN
006: SMALL-INT 4
008: RETURN
```

STklos' disassemble is nice enough to tell you the line number where a jump goes!

# Chapter 9. Closures, let, and related

### 9.1. let

The opcodes for 'entering 'let[]' create new environments and push them on the stack, but do not update activation records, since there is no procedure call happening. Then, the 'LEAVE\_LET opcode removes the environment from the stack.

```
ENTER_LET
ENTER_LET_STAR
ENTER_TAIL_LET
ENTER_TAIL_LET_STAR
LEAVE_LET
```

Examples:

When the let is in tail position, then the opcode used is the ordinary ENTER\_TAIL\_LET, and no LEAVE\_LET is needed:

```
(disassemble
  (lambda ()
       (let ((x 1))
       x)))
```

```
000: PREPARE-CALL
001: INT-PUSH 4
002: ENTER-TAIL-LET 1
004: LOCAL-REF0
005: RETURN
```

# Chapter 10. Miscelannea

The following opcode does nothing:

```
NOP
```

The following sets the docstring and the formal parameter list documentation for a procedure:

```
DOCSTRG
FORMALS
```

**Examples:** 

```
(disassemble-expr '(define (f) "A well-documented function" 5) #t)
```

```
(disassemble
  (lambda ()
      (define (f) "A well-documented function" 5)
      10))
```

Here, DOCSTRG seems to have a zero argument because it uses a constant string, and disassemble does

not show values of strings and symbol names.

The FORMALS opcode is similar to DOCSTRG, except that it expects a list instead of a string.

```
000: CREATE-CLOSURE
                          5 -3;; ==> 007
003: LOCAL-REF2
004: IN-SINT-MUL2
                          3
006: RETURN
007: FORMALS
                          0
009: DOCSTRG
                          1
011: DEFINE-SYMBOL
013:
Constants:
0: (a b . c)
1: "A well-documented function"
2: f
```

## 10.1. Creating closures and procedures

The following opcode creates a closure.

```
CREATE_CLOSURE
```

This opcode fetches two parameters:

- the number of instructions ahead that the VM needs to jump to (because what follows is the code of a closure being created, and it should *not* be executed, so the VM wull jump over it)
- the closure arity.

Examples:

```
(disassemble
(lambda ()
(lambda () "Hello")))
```

```
000: CREATE-CLOSURE 4 0 ;; ==> 006
```

```
003: CONSTANT 0
005: RETURN
006: RETURN
```

```
(disassemble
(lambda ()
(lambda (x) (* 2 x))))
```

```
000: CREATE-CLOSURE 5 1 ;; ==> 007
003: LOCAL-REF0
004: IN-SINT-MUL2 2
006: RETURN
007: RETURN
```

```
(disassemble
  (lambda ()
     (define (g a b c) 10)
     g))
```

### 10.2. Procedure calls

The following opcodes are used to make procedure calls:

```
PREPARE-CALL ( PREP_CALL() in vm.c )
INVOKE
TAIL_INVOKE
GREF-INVOKE
GREF-TAIL-INVOKE
PUSH_GREF_INVOKE
PUSH_GREF_TAIL_INV
```

- PREPARE-CALL pushes an activation record on the stack.
- INVOKE opcodes call procedures local or global; in tail position or not. The ones with the PUSH\_

prefix also push an argument onto the stack.

These are handled in the VM as states in the state machine (they are labels used in the CASE's in 'vm/.c).

In vm.c, all these instructions end up sending the control to the FUNCALL: label, which will then check what to do depending on the type of call (tc\_instance, tc\_closure, tc\_next\_method, tc\_apply, or some primitive, tc\_subr···)

The peephole optimizer will combine PUSH, GLOBAL-REF INVOKE instructions, yielding combined instructions. The following is an excerpt from peephole.stk where these transformations are documented:

```
;; [GLOBAL-REF, PUSH] => GLOBAL-REF-PUSH
;; [PUSH GLOBAL-REF] => PUSH-GLOBAL-REF
;; [PUSH-GLOBAL-REF, INVOKE] => PUSH-GREF-INVOKE
;; [PUSH-GLOBAL-REF, TAIL-INVOKE] => PUSH-GREF-TAIL-INV
;; [PUSH, PREPARE-CALL] => PUSH-PREPARE-CALL
;; [GLOBAL-REF, INVOKE] => GREF-INVOKE
;; [GLOBAL-REF, INVOKE] => GREF-INVOKE
;; [GLOBAL-REF, TAIL-INVOKE] => GREF-TAIL-INVOKE
;; [GLOBAL-REFx, PUSH] => LOCAL-REFx-PUSH
```

The arguments to the INVOKE-like instructions are:

- INVOKE: n\_args (the procedure address is the first item on the stack, so it is not passed as argument in the code)
- GREF-INVOKE: proc\_addr, n\_args
- PUSH-GREF-INVOKE: first\_arg, proc\_addr, n\_args (pushes the first and calls the procedure with n\_args arguments form the stack

```
(disassemble (lambda () (f)))
```

```
000: PREPARE-CALL
001: GREF-TAIL-INVOKE 0 0
004: RETURN
```

```
(disassemble (lambda () (f 3)))
```

```
000: PREPARE-CALL
001: INT-PUSH 3
003: GREF-TAIL-INVOKE 0 1
006: RETURN
```

In the next example, GREF-INVOKE is called with arguments 0 and 0. The **first** value 0 is the address of the procedure in the stack. The IN-SINT-ADD2 procedure is called afterwards to sum 3 with the return from f.

```
(disassemble (lambda () (+ 3 (f))))
```

```
000: PREPARE-CALL
001: GREF-INVOKE 0 0
004: IN-SINT-ADD2 3
006: RETURN
```

In the next example, GREF-INVOKE is called with arguments 0 and 2. The value 0 is the address of the procedure in the stack; 2 is the number of arguments given in this procedure call. The IN-SINT-ADD2 procedure is called afterwards to sum 5 with the return from f.

```
(disassemble
  (lambda (x)
        (+ 5 (f x #f))))
```

```
000: PREPARE-CALL
001: LOCAL-REF0-PUSH
002: FALSE-PUSH
003: GREF-INVOKE 0 2
006: IN-SINT-ADD2 5
008: RETURN
```

Now the next example shows how INVOKE is used to call a procedure that is non-global (it is in the local environment). The INVOKE instruction will use the first value on the stack as the address of the procedure (it's DEEP-LOCAL-REF 256, since f is defined inside the let). The other two arguments to be popped from the stack are #f (pushed by the FALSE-PUSH instruction) and the global variable y (pushed by the instruction GLOBAL-REF-PUSH 0). After INVOKE calls f, the instruction IN-SINT-ADD2 3 will sum 3 to the result.

```
(let ((f (lambda (x) x)))
  (disassemble
    (lambda ()
        (+ 3 (f y #f)))))
```

```
000: PREPARE-CALL
001: GLOBAL-REF-PUSH 0
003: FALSE-PUSH
004: DEEP-LOCAL-REF 256
006: INVOKE 2
```

008: IN-SINT-ADD2 3

010: RETURN

## Chapter 11. Modules

The following opcode enters a given module.

```
SET_CUR_MOD
```

An SCM object of type module must be in the val resgister.

Example:

```
(disassemble-expr '(select-module m) #t)
```

In the above example, the constants were two symbols: m and find-module. The find-module procedure, which is called, will leave module m in the val register, which is then used by SET\_CUR\_MOD.

The following opcode defines a variable in a module.

```
DEFINE_SYMBOL
```

It will define a variable with name set as symbol fetched after the opcode, and value in the val register.

```
(disassemble-expr '(define a "abc") #t)
```

```
000: CONSTANT 0
002: DEFINE-SYMBOL 1
004:

Constants:
0: "abc"
1: a
```

## (disassemble-expr '(define a #f) #t)

000: IM-FALSE

001: DEFINE-SYMBOL 0

003:

Constants:

0: a

## Chapter 12. vm.c

An important observation:

• apply: there is a DEFINE\_PRIMITIVE("apply", ...), but it is not used. It is necessary just so there is a primitive of the type tc\_apply. When the VM finds a primitive of this kind, it'll treat it differently.

Some basic functions in the VM:

- push(v): pushes v on the stack (the stack pointer is decreased)
- pop(): pops a value from the stack (the stack pointer is increased)
- fetch\_next() fetches the next opcode, increasing the PC
- fetch\_const() fetches the **next** opcode and uses it as index for a constant
- look\_const() looks at the current opcode and uses it as index for a constant
- fetch\_global() fetches the next opcode and uses it as index for a global variable
- add\_global(ref) adds ref to the list of global variables, and returns its index. If it was already
  there, the old index is returned. If it was not, a place is allocated for it, and the new index is
  returned.

Already covered before:

- SCM STk\_C\_apply(SCM func, int nargs, ...): applies func, with nargs arguments
- SCM STk\_C\_apply\_list(SCM func, SCM 1): applies func, with a list of arguments
- SCM STk\_n\_values(int n, ···): prepares n values in the VM (for the next instruction), and returns a pointer to the vm→val register
- SCM STk\_values2vector(SCM obj, SCM vect): turns a values object into an array with the values

## 12.1. The global lock

There is one global mutex lock for STklos, called global\_lock, declared in vm.c:

```
MUT_DECL(global_lock); /* the lock to access checked_globals */
```

As per the comment, its purpose is to discipline access to global variables.

Three macros are used to control the global lock (a mutex):

- LOCK\_AND\_RESTART will acquire the lock, and decrease the program counter. It will also set a flag that signals that the lock has been acquired by this thread, and then call NEXT. The name "AND\_RESTART" reflects the fact that it decreases the PC and calls NEXT (for the next instruction) so the effect is to start again operating on this instruction, but this time with the lock.
- RELEASE\_LOCK will release the lock, regardless of the thread having it or not. The flag indicating ownership by this thread is cleared.

• RELEASE\_POSSIBLE\_LOCK will release the lock **if** this thread has it.

## 12.2. run\_vm(vm\_thread \*vm)

After some initial setup, this function will operate as a state machine. Its basic structure is shown below.

The CASE symbol is defined differently, depending on the system, but CASE(x) semantically simialar to case x: (if computed GOTOs are better, then it's defined as a label instead — see its definition in vm.c).

# **Chapter 13. Continuations**

There are undocumented primitives in vm.c that can be used to capture and restore continuations. They are listed here with their undocumented Scheme counterparts:

- STk\_make\_continuation() (%make-continuation)
- STk\_restore\_cont(SCM cont, SCM value) (%restore-continuation cont value)
- STk\_continuationp(SCM obj) (%continuation? obj)
- STk\_fresh\_continuationp(SCM obj) (%fresh-continuation? obj)

Continuation is a native type (tc\_continuation). A continuation object (defined in vm.h) contains pointers to the C stack, the Scheme stack and several other data.

Capturing a continuation is carried ou tby the following step (these are the actual comments in the function STk\_make\_continuation):

- 1. Determine the size of the C stack and the start address
- 2. Determine the size of the Scheme stack
- 3. Allocate a continuation object
- 4. Save the Scheme stack
- 5. Save the C stack

Restoring is easier:

- 1. Restore the Scheme stack
- 2. Restore the C stack

And, when the C stack is restored, the Vm is back to its original state, except for the global variables.