# Cygwin/X Contributor's Guide

Harold L Hunt, II

Jon Turney

#### Cygwin/X Contributor's Guide

by Harold L Hunt, II

by Jon Turney

Copyright (C) 2004 Harold L Hunt II. Copyright (C) 2009 Jon Turney. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation; with no Invariant Sections, with no Front-Cover Texts, and with no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

# **Table of Contents**

1. Overview	1
2. Programming	2
Overview	2
Source Code Tree Layout	2
Cygwin/X X Server Architecture	
Server Privates	4
Macros	4
Engine System	5
Shadow FB Engines	5
Native GDI Engine	5
Primary FB Engine	6
User Input	6
Keyboard	7
Mouse	8
Prerequisites for Building the Source Code	9
Required Packages for Building	9
Compilation environment setup	9
libXfont linkage issue	9
Obtaining the Source Code	10
Obtaining via Cygwin setup	10
Obtaining from subversion	11
Obtaining from X.Org	11
Native Compiling	12
Compiling the Source Code	12
Standard Build	12
Debug Build	12
Running a local build	13
Installing a local build	
Keeping your source code tree updated	14
Cross Compiling	14
Obtaining binutils and gcc Source	14
Obtaining Cygwin Headers and Libs	
Building binutils and gcc	
Creating Links for binutils and gcc	
Building Cygwin/X	
Packaging a Cygwin/X Distribution	
Reference Documentation	
X.Org documents	
Further reading	
X server porting documents	20
3. Documentation	22
Overview	22
Obtaining the Source Code	22
Source of latest cygwin-x-doc release	22
Source from CVS	22

	Setting Up a DocBook Build Environment	22
	Required Packages for building documentation	22
	Building the Documentation	23
	Packaging a Documentation Distribution	24
4. V	Veb Site Maintenance	25
	Updating the documentation on the web site	25
Bibl	liography	26
	ssary	
<b>A.</b> (	SNU Free Documentation License	31
	0. PREAMBLE	31
	1. APPLICABILITY AND DEFINITIONS	31
	2. VERBATIM COPYING	32
	3. COPYING IN QUANTITY	32
	4. MODIFICATIONS	33
	5. COMBINING DOCUMENTS	34
	6. COLLECTIONS OF DOCUMENTS	34
	7. AGGREGATION WITH INDEPENDENT WORKS	35
	8. TRANSLATION	35
	9. TERMINATION	35
	10. FUTURE REVISIONS OF THIS LICENSE	35
	How to use this License for your documents	36

# **Chapter 1. Overview**

The Cygwin/X project can use your help! We will do everything we can to make experienced contributors productive as soon as possible. We also want to make it as easy as possible for new contributers to make Cygwin/X their first open source project.

Anyone who despaired of touching the monolithic tree will find things much easier now with modular X. If you want to see Cygwin/X stay current and add new features, then WE NEED YOU.

We need programmers, documentation writers, and website maintainers.

## **Chapter 2. Programming**

## **Overview**

This chapter provides a consolidated overview of all of the information needed to begin making source code contributions to Cygwin/X. Creating a source code contribution for Cygwin/X requires an amazingly small amount of information; however, prior to this document that tiny amount of information was difficult to obtain, as it was scattered across several documents and source code files. New programmers with no open source project experience, as well as programming gurus, will be able to make source code contributions to Cygwin/X after reading this chapter. Programming gurus are great; our intention is to create more of them.

This document is primarily focused on the Cygwin/X server; most other components are extremely stable and work out-of-the-box on Cygwin

The primary source of information on developing for X is the X.Org developer startpage (http://www.x.org/wiki/DeveloperStart)

Downloading the X Window System source code tree can take anywhere from 10 minutes to 10 hours, depending upon the speed of your network connection. If you have an active network connection at your disposal you may want to skip ahead to the Section called *Obtaining the Source Code* and start downloading the source code tree now. You will find it advantageous to have a source code tree as you read the other sections.

## **Source Code Tree Layout**

#### Descriptions of Important xserver Directories and Subdirectories

- cfb\* contains deprecated color framebuffer drawing procedures that are not compatible with the Shadow drawing system that Cygwin/X depends upon. This directory is of no interest to Cygwin/X programmers.
- dix contains [drawing] *device independent X* routines. main.c contains the main entry-point function for the Cygwin/X X Server. The X Server startup procedure can be followed by examining main.
- fb contains the modern framebuffer drawing procedures used by Cygwin/X. This directory is maintained by Keith Packard and is only of interest to Cygwin/X programmers when it fails to build.
- · hw contains [drawing] hardware dependent functions.
  - vfb contains the Virtual Framebuffer X Server. The vfb server draws to a system memory
    framebuffer with the primary purpose of allowing X clients to run on a machine that does not have
    display hardware.
  - xfree86 contains source code for the X Window System servers that run on various operating
    systems that generally have low-level access to the graphics hardware. Cygwin/X does not have
    low-level access to the graphics hardware, thus Cygwin/X is not able to utilize the X Window
    System server.

- xnest contains source code for the Nested X Server which runs inside of another X Server. xnest is not generally of interest to Cygwin/X programmers.
- xwin contains the source code for the Cygwin/X X Server. This is the primary directory that Cygwin/X programmers are interested in.
- include contains header files specific to the X Server program, such as graphics context structures.
   This directory is useful to Cygwin/X programmers when they need to lookup the name or data type of members of various X Server structures.
- mi contains machine independent drawing routines. These drawing routines are used by the Cygwin/X Native GDI X Server engine. In turn, the machine independent routines depend in winGetSpans, winFillSpans, and winSetSpans, which are implemented in the Native GDI engine.
- miext contains various machine independent X extensions.
  - layer contains source code for the layer extension. This extension is supported by Cygwin/X, however, this directory will be of interest only when layer fails to build.
  - shadow contains source code for the shadow extension that the Cygwin/X X Server depends upon.
     This directory is of primary importance to Cygwin/X, but it is maintained by other programmers and is only of direct interest to Cygwin/X programmers when it fails to build. The shadow extension does three things:
    - 1. Allows the fb graphics routines to draw to an offscreen framebuffer.
    - 2. Keeps track of the regions of the offscreen framebuffer that have been drawn on.
    - 3. Calls one of Cygwin/X's engine dependent ShadowUpdate () functions to transfer the updated regions of the offscreen framebuffer to the screen.
- os contains *operating system dependent* X Server functions. However, the functions in the os have been written in such a way that they are actually compatible with most UNIX-style operating systems, include Cygwin.

#### Other components of interest

- doc
  - hardcopy contains precompiled PostScript documentation for various components of the X
    Window System. Cygwin/X-specific documentation is not contained in this directory. This directory
    is of little interest to Cygwin/X programmers.
  - specs contains the sources to build the documents in hardcopy. This directory is of little interest to Cygwin/X programmers.
- fonts contains font definition files used to compile fonts. This directory is of little interest to Cygwin/X programmers.
- include contains various X Window System headers that are not generally specific to any one client or library (i.e. X.h, Xproto.h, and keysymdef.h).

• 1ib contains both X client and X Server libraries. Cygwin/X does not generally call any functions in these libraries directly; however, we do have to link to several of these libraries to get our X Server to build. These libraries are maintained by various developers from the X Window System project and there are occasional synchronizations with The Open Group (http://www.opengroup.org/)'s X.org (http://www.x.org/). Cygwin/X programmers occasionally need to fix Cygwin-related build errors that occur in these libraries.

## Cygwin/X X Server Architecture

Cygwin/X's X Server architecture was heavily inspired by Angebranndt94, the Definition of the Porting Layer for the X v11 Sample Server.

#### **Server Privates**

X Servers use various structures to pass information around to functions. Some of those structures are colormaps, *graphics contexts* (GCs), *pixmaps*, and *screens*. The X protocol defines the contents of each of these structures, however, the X Server implementation and various X Server libraries (*MI*, *FB*, *Shadow*, etc.) may require additional information to be associated with these internal structures. For example, the Cygwin/X X Server must associate a Windows window handle (hwnd) with each X Server screen that is open.

Privates are the mechanism provided by the X protocol for associating additional information with internal X Server structures. Privates originally consisted of a single pointer member contained in each structure, usually named <code>devPrivate</code> or <code>devPriv</code>. This original specification only allowed one of the X Server layers (mi, fb, shadow, etc.) to have privates associated with an internal structure. Privates have since been revised.

The current privates implementation requires that each X Server layer call a function on startup to indicate that that layer will require privates and to obtain an index into the array of privates that that layer's privates will be stored at. Modern privates are generally stored in an array of type DevUnion pointed to by a structure member named <code>devPrivates</code>; DevUnion is defined in <code>xserver/include/miscstruct.h</code>. There are two different memory allocation schemes for <code>devPrivates</code>.

Memory for privates structures can either be preallocated or allocated upon use. Preallocation, the preferred method for GCs, pixmaps, and windows, requires that the size of the privates memory needed be specified during X Server initialization. Preallocation allows the *DIX* layer to allocate all memory needed for a given internal structure, including all privates memory, as a single contiguous block of memory; this greatly reduces memory fragmentation. Allocation upon use, used by screens, requires the *DDX* structure creation function to allocate memory for the privates; winScreenInit calling winAllocatePrivates, which allocates screen privates memory directly, is an example of this. Allocation upon use can optionally and non-optimally be used by GCs, pixmaps, and windows.

#### **Macros**

Three macros are provided for each class of privates that make setting up and using the privates easier. The macros for screen privates are examined as an example.

```
winPrivScreenPtr winGetScreenPriv (ScreenPtr pScreen );
```

winGetScreenPriv takes a non-NULL pointer to a screen, a ScreenPtr, and returns the pointer stored in the DDX privates for that screen. Passing a NULL or invalid ScreenPtr to winGetScreenPriv will cause an access violation, crashing the Cygwin/X X Server.

```
void winSetScreenPriv (ScreenPtr pScreen , void * pvPrivates );
```

winSetScreenPriv takes a non-NULL pointer to a screen, a ScreenPtr, and sets the DDX privates pointer to the value of the *pvPrivates* parameter. Passing a NULL or invalid ScreenPtr to winSetScreenPriv will cause an access violation, crashing the Cygwin/X X Server.

```
void winScreenPriv (ScreenPtr pScreen );
```

winScreenPriv takes a non-NULL pointer to a screen, a ScreenPtr, and declares a local variable in the calling function named pScreenPriv. winScreenPriv may only be called at the top of a C function within the variable declaration block; calling the function elsewhere will break the ANSI C rule that all variables must be declared at the top of a scope block. Passing a NULL or invalid ScreenPtr to winScreenPriv will cause an access violation, crashing the Cygwin/X X Server.

### **Engine System**

The Cygwin/X X Server uses several methods of drawing graphics on the display device; each of these different drawing methods is referred to as an engine. Each of the engines can be classified as either a Shadow FB engine, a Native GDI engine, or as a Primary FB engine. It should be noted that the Primary FB engine is deprecated and is discussed here only for completeness. The engines are discussed in the following sections, in order of importance.

#### Shadow FB Engines

The Shadow FB engines use Keith Packard's *FB* drawing procedures wrapped with his *Shadow* layer that allows drawing to an *offscreen framebuffer* with periodic updates of the *primary framebuffer*.

#### **Native GDI Engine**

The Native GDI engine will eventually translate individual X graphics calls into their GDI equivalent. Some X graphics calls do not translate directly to a GDI call so they may be passed through the MI layer to change them into a serious of lower level calls that are supported. Currently, the Native GDI engine passes all X graphics calls through the MI layer to convert them into three functions: FillSpans, GetSpans, and SetSpans. The functionality of those three functions, as of 2001-10-28, is limited to the functionality needed to draw the familiar X background pattern upon X Server startup.

#### **Primary FB Engine**

The Primary FB engine is deprecated. Primary FB works in the same manner that the original Cygwin/X X Server worked, namely, it uses <code>IDirectDrawSurface\_Lock</code> to obtain a pointer to the *primary framebuffer* memory at server startup. This memory pointer is held until the X Server shuts down. This technique does not work on all versions of Windows.

Locking the primary framebuffer on Windows 95/98/Me causes the Win16Mutex to be obtained by the program that locks the primary framebuffer; the Win16Mutex is not released until the primary framebuffer is unlocked. The Win16Mutex is a semaphore introduced in Windows 95 that prevents 16 bit Windows code from being reentered by different threads or processes. For compatibility reasons, all GDI operations in Windows 95/98/Me are written in 16 bit code, thus requiring that the Win16Mutex be obtained before performing those operations. All of this leads to the following situation on Windows 95/98/Me:

- 1. The primary framebuffer is locked, causing the Cygwin/X X Server to hold the Win16Mutex.
- 2. Windows switches the Cygwin/X X Server out of the current process slot; another process is switched in.
- 3. The newly selected process makes a GDI function call.
- 4. The GDI function call must wait for the Win16Mutex to be released, but the Win16Mutex cannot be released until the Cygwin/X X Server releases the Win16Mutex. However, the Cygwin/X X Server will not release the Win16Mutex until it exits. The end result is that the Win16Mutex has been deadlocked and the Windows machine is frozen with no way to recover.

Windows NT/2000/XP do not contain any 16 bit code, so the Win16Mutex is not an issue; thus, the Primary FB engine works fine on those operating systems. However, drawing directly to the primary framebuffer suffers performance problems. For example, on some systems writing to the primary framebuffer requires doing memory reads and writes across the PCI bus which is only 32 bits wide and features a clock speed of 33 MHz, as opposed to accessing system memory, which is attached to a 64 bit wide bus that runs at between 100 and 266 (effective) MHz. Furthermore, accessing the primary framebuffer memory requires several synchronization steps that take many clock cycles to complete. The end result is that the Primary FB engine is several times slower than the Shadow FB engines.

The Primary FB engine also has several unique issues that are difficult to program around. Development of the Primary FB engine has ceased, due to the difficulty of maintaining it, coupled with the fact that Primary FB does not run on Windows 95/98/Me and with the poor performance of Primary FB. The Primary FB source code has been left in place so that future programmers can enable it and see the poor performance of the engine for themselves.

## **User Input**

User input is processed using the MI layer's user input system. Any queued Win32 user input messages, as well as other Win32 messages, are handled when hw/xwin/winwakeup.c's winWakeupHandler function is called by the OS layer os/WaitFor.c's WaitForSomething function and when the DIX layer dix/dispatch.c's Dispatch function calls hw/xwin/InitInput.c's ProcessInputEvents function. Each Win32 user input message typically queues an input event, or several input events, using the MI layer's mi/mieq.c's mieqEnqueue function. Enqueued MI input events are processed in

ProcessInputEvents by calling mi/mieq.c's mieqProcessInputEvents; the cursor position is updated on the screen by calling mipointer.c's miPointerUpdate.

#### Keyboard

Win32 keyboard messages are processed in winwndproc.c's winWindowProc. The messages processed are:

- WM\_SYSKEYDOWN
- WM\_KEYDOWN
- WM\_SYSKEYUP
- · WM KEYUP

The WM\_SYSKEY\* messages are generated when the user presses a key while holding down the **Alt** key or when the user presses a key after pressing and releasing the **F10** key. Processing for WM\_SYSKEYDOWN and WM\_KEYDOWN (respectively WM\_SYSKEYUP, WM\_KEYUP) messages are identical because the X Server does not distinguish between a normal key press and a key press when the **Alt** key is down.

Win32 uses virtual key codes to identify which key is being pressed or released. Virtual key codes follow the idea that the same virtual key code will be sent for keys with the same label printed on them. For example, the left and right **Ctrl** keys both generate the VK\_CONTROL virtual key code. Virtual key codes are accompanied by other state information, such as the extended flag, that distinguishes between the multiple keys with the same label. For example, the left **Ctrl** key does not have the extended flag asserted, while the right **Ctrl** key does have the extended flag asserted. However, virtual key codes are not the way that key presses have traditionally been identified on personal computers and in the X Protocol.

Personal computers and the X Protocol use scan codes to identify which key is being pressed. Each key on the keyboard generates a specified number when that key is pressed or released; this number is called the scan code. Scan codes are always distinct for distinct keys. For example, the left and right **Ctrl** keys generate distinct scan codes, even though their functionality is the same. Scan codes do not have additional state information, as the multiple keys with the same label will each generate a unique scan code. There is some debate as to which of virtual key codes or scan codes is the better system.

The X Protocol expects that keyboard input will be based on a scan code system. There are two methods of sending a scan codes from a virtual key code message. The first method is to create a static table that links the normal and extended state of each virtual key code to a scan code. This method seems valid, but the method does not work reliably for users with non-U.S. keyboard layouts. The second method simply pulls the scan code out of the param of the keyboard messages; this method works reliably for non-U.S. keyboard layouts. However, there are further concerns for non-U.S. keyboard layouts.

Non-U.S. keyboard layouts typically use the right **Alt** key as a sort of shift key to access an additional row of symbols from the ', 1, 2, ..., 0 keys, as well as accented forms of standard alphabetic characters, such as á, ä, å, ú and additional alphabetic characters, such as ß. Non-U.S. keyboards typically label the right **Alt** key as **AltGr** or **AltLang**; the Gr is short for "grave", which is the name of one of the accent symbols. The X Protocol and Win32 methods of handling the **AltGr** key are not directly compatible with one another.

The X Protocol handles **AltGr** presses and releases in much the same way as any other key press and release. Win32, however, generates a fake **Ctrl** press and release for each **AltGr** press and release. The X

Protocol does not expect this fake **Ctrl** press and release, so care must be taken to discard the fake **Ctrl** press and release. Fake **Ctrl** presses and releases are detected and discarded by passing each keyboard message to winkeybd.c's winlsfakeCtrl\_L function.winlsfakeCtrl\_L detects the fake key presses and releases by comparing the timestamps of the **AltGr** message with the timestamp of any preceding or trailing **Ctrl** message. Two real key events will never have the same timestamp, but the fake key events have the same timestamp as the **AltGr** messages, so the fake messages can be easily identified.

Special keyboard considerations must be handled the Cygwin/X X Server losses or gains the keyboard focus. For example, the user can switch out of Cygwin/X, toggle the **Num Lock** key, then switch back into Cygwin/X; in this case Cygwin/X would not have received the **Num Lock** toggle message, so it will continue to function as if **Num Lock** was in its previous state. Thus, the state of any mode keys such as **Num Lock**, **Caps Lock**, **Scroll Lock**, and **Kana Lock** must be stored upon loss of keyboard focus; the stored state of each mode key must then be compared to that key's current state, toggling the key if its state has changed.

#### Mouse

Win32 mouse messages are processed in winwndproc.c's winWindowProc. The messages processed are:

- WM\_MOUSEMOVE
- WM\_NCMOUSEMOVE
- WM\_LBUTTON\*
- WM\_MBUTTON\*
- WM RBUTTON\*
- WM MOUSEWHEEL

Handling mouse motion is relatively straight forward, with the special consideration that the Windows mouse cursor must be hidden when the mouse is moving over the client area of a Cygwin/X window; the Windows mouse cursor must be redisplayed when the mouse is moving over the non-client area of a Cygwin/X window. Win32 sends the absolute coordinates of the mouse, so we call miPointerAbsoluteCursor to change the position of the mouse.

Three-button mouse emulation is supported for users that do not have a three button mouse. When three-button mouse emulation is disabled, mouse button presses and releases are handled trivially in winmouse.c's winMouseButtonsHandle by simply passing the event to mieqEnqueue. Three-button mouse emulation is quite complicated.

Three-button mouse emulation is handled by starting a timer when the left or right mouse buttons are pressed; the button event is sent as a left or right mouse button event if the other button is not pressed before the timer expires. The button event is sent as an emulated middle button event if the other mouse button is pressed before the timer runs out.

The mouse wheel is handled in winmouse.c's winMouseWheel by generating sequences of button 4 and button 5 presses and releases corresponding to how much the mouse wheel has moved. Win32 uses variable resolution for the mouse wheel and passes the mouse wheel motion as a delta from the wheel's previous position. The number of button clicks to send is determined by dividing the wheel delta by the

distance that is considered by Win32 to be one unit of motion for the mouse wheel; any remainder of the wheel delta must be preserved and added to the next mouse wheel message.

## **Prerequisites for Building the Source Code**

### **Required Packages for Building**

Many developer libraries and developer tools are required to build Cygwin/X. Several packages are required in addition to the default packages installed by the Cygwin installer. Following is a list of additional packages that are required to compile Cygwin/X natively in Cygwin. Note that some of these packages are meta packages that will automatically cause several other packages to be selected for installation; do not unselect any of these automatically selected packages.

- · Required tools:
  - autoconf, automake, binutils, bison, bzip2, cygport, diffutils, fileutils, findutils, flex, gawk, gcc, git, libtool, make, patch, pkg-config, sed, subversion, tar
- · Required protocol headers:
  - bigreqsproto, compositeproto, damageproto, evieext, fixesproto, fontsproto, glproto, inputproto, kbproto, randrproto, recordproto, renderproto, resourceproto, scrnsaverproto, xcmiscproto, xextproto, xineramaproto, xproto
- · Required development libraries:
  - libfontenc-devel, libfreetype2-devel, libGL-devel, libpixman1-devel, libX11-devel, libXau-devel, libXdmcp-devel, libXfont-devel, libXinerama-devel, libxkbfile-devel, minires-devel, openssl-devel, zlib
- Other miscellaneous required pacakges:
  - xorg-util-macros, xtrans

**Note:** The /usr/share/doc/Cygwin/xorg-server-n.n.n.README file installed with the X server binary package lists up-to-date runtime and build requirements.

## **Compilation environment setup**

#### libXfont linkage issue

libXfont must be statically linked for the server to start correctly, otherwise it fails with errors loading all fonts, including the mandatory fixed font.

This is due to limitations of Cygwin's current weak symbol handling which requires static linking to work correctly. For example, in libXfont the RegisterFPEFunctions function is defined weak and should be overloaded with RegisterFPEFunctions defined in dix/dixfont.c in the xserver. However, such overloading will only currently work for Cygwin when libXfont is statically linked with the X server, and not as a shared libary.

We can't ship a static-only libXfont in Cygwin because xfs requires it shared, otherwise you get multiple definitions during linking, thanks to the xtrans code. So when building the X server, you must prepare your compilation environment so that the libXfont shared libary is not linked with.

A quick and dirty way of achieving this is to move libXFont.la and libXfont.dll.a aside whilst building the X server.

```
mv /usr/lib/libXFont.la /usr/lib/libXFont.la.old
mv /usr/lib/libXFont.dll.a /usr/lib/libXFont.dll.a.old
```

A cleaner way is to generate customized .pc file for libXfont and arrange for that to be in your PKG\_CONFIG\_PATH when ./configuring the X server. See the .cygport file for an example of how to achieve that.

## **Obtaining the Source Code**

## **Obtaining via Cygwin setup**

The source code for the packages distributed via Cygwin setup is also available via Cygwin setup. To install the source for the X server, run Cygwin setup and tick the 'Src?' check-box for the 'xorg-server' package.

This may have multiple patches applied on top of the X Window System source code, and should be the starting point for new developers.

On installing the source code package, setup will unpack it under /usr/src. You should find the stock X.Org xorg-server-n.n.n.tar.bz2 archive, plus a number of .patch files, and a .cygport file which automates the distribution build and packaging tasks.

The sources can unpacked and prepared using cygport as follows:

```
Username@CygwinHost ~

$ cd /usr/src

Username@CygwinHost /usr/src

$ cygport xorg-server-n.n.n-n.cygport prep
[lots of output as archive is unpacked and patches applied]

Username@CygwinHost /usr/src

$ cd xorg-server-n.n.n-n/src/xorg-server-n.n.n/
```

```
Username@CygwinHost /usr/src/xorg-server-n.n.n-n/src/xorg-server-n.n.n/
$ ./autogen.sh -V
[more output as autoconfiguration scripts are regenerated]
```

Note: Alternatively you may manually untar the archive and apply the patches (in the correct order).

**Note:** It is necessary to run the package's autogen.sh script to regenerate the configure script and Makefiles if the patches modify the autoconf or automake source files

**Note:** For details of using cygport to generate packages for distribution, see the Section called *Packaging a Cygwin/X Distribution* 

### Obtaining from subversion

The patches applied to the stock X.Org archive and the packaging script for the packages distributed via Cygwin setup are held in a subversion repository. Intermediate versions between released packages can be obtained from there.

```
Username@CygwinHost ~
$ svn checkout https://cygwin-ports.svn.sourceforge.net/svnroot/cygwin-ports/ports/trunk
Username@CygwinHost ~
$ cd xorg-server
```

This will obtain the .patch files, and a .cygport file. You can then add the stock X.Org xorg-server-n.n.n.tar.bz2 archive, either by downloading it with 'cygport xorg-server-n.n.n-n.cygport download' or by copying it into that directory if you have already downloaded it, and proceed as in the Section called *Obtaining via Cygwin setup* 

## **Obtaining from X.Org**

Cygwin/X source code is contained in, and distributed with, the X Window System source code releases (http://xorg.freedesktop.org/wiki/Releases/Download).

Read-only access to the  $\,X\,$  Window System git source (http://cgit.freedesktop.org/xorg/xserver/). tree hosted on freedesktop.org (http://freedesktop.org/Software/xorg) is also available.

```
$ git clone git://git.freedesktop.org/git/xorg/xserver
```

The CYGWIN branch exists in git for historical reasons. Current development follows the mainline (called the *master* branch in git terminology).

If you just want to look at the Cygwin/X source, use the cgit interface to the X.Org tree (http://cgit.freedesktop.org/xorg/xserver/). Most of the Cygwin/X-specific code is in the xserver/hw/xwin (http://cgit.freedesktop.org/xorg/xserver/tree/hw/xwin) directory.

## **Native Compiling**

### **Compiling the Source Code**

Compiling Cygwin/X doesn't have to be hard, although the X Window System source code tree is reasonably large. There are a few simple techniques that make building the source code, keeping the source code up to date, and keeping the source code organized much easier.

#### Standard Build

Follow these steps to create a standard, non-debug, build:

1. Change the current directory to your X Window System development directory:

```
Username@CygwinHost ~
$ cd ~/xserver

Username@CygwinHost ~/xserver
$ ./configure --prefix=/usr --with-log-dir=/var/log --disable-xv
[lots of output]
$ make
[lots more output]
```

Standard build is now complete.

**Note:** You may wish to consult the .cygport file for the current ./configure flags used in distributed packages

**Note:** The unpacked source occupies approximately 80MB of disk space. Building the source requires approximately an additional 160MB. On my ageing 2.2MHz Athlon64 3500+, a full build takes about 20 minutes.

Note: XXX: Describe how to configure using a builddir

#### **Debug Build**

Follow these steps to create a build with debugging information:

1. Change the current directory to your X Window System development directory:

```
Username@CygwinHost ~
$ cd ~/xserver

Username@CygwinHost ~/xserver
$ ./configure --prefix=/usr --with-log-dir=/var/log --disable-xv --enable-debug CFLAG
[lots of output]
$ make
[lots more output]
Debug build is now complete.
```

### Running a local build

Follow these steps to run the built X server:

1. Change the current directory to your X Window System development directory:

```
Username@CygwinHost ~
$ cd xserver
Username@CygwinHost ~/xserver
$
```

2. Invoke the hw/xwin/Xwin executable:

```
Username@CygwinHost ~/xserver
$ hw/xwin/XWin
```

The X server you have built will now attempt to run.

## Installing a local build

Installing a local build installs the built X server(s) and associated man pages.

1. Change the current directory to your desired X Window System build directory:

```
Username@CygwinHost ~
$ cd ~/xserver/build/build-prefix
Username@CygwinHost ~/xserver/build/build-prefix
$
```

2. Make the **install** target, which installs everything:

```
Username@CygwinHost ~/xserver/build/build-prefix
$ make install
Username@CygwinHost ~/xserver/build/build-prefix
```

### Keeping your source code tree updated

git makes keeping your source code tree up to date easy. Consult the git documentation for details.

## **Cross Compiling**

Note: XXX: THIS SECTION NEEDS UPDATING

Cross compiling is the act of the building source code on one system, the build host, into executables or libraries to be run on a different host, the native host. The build host and the native host may differ in operating system and/or processor type. Cross compiling is done for several reasons:

- The native host is grossly under powered, such as a handheld computer.
- The user happens to have greatly more compiling power available on a platform other than the native host. For example, the user may have access to a 32 processor machine while their desktop machine may only be a uni-processor machine.

Cross compiling is much trickier than building on the native host. There are a whole new class of problems that can happen when cross compiling that are simply not an issue when building on Cygwin. You should be familiar with building Cygwin/X on Cygwin, as described in the Section called *Native Compiling*, before attempting to cross compile Cygwin/X.

## Obtaining binutils and gcc Source

binutils and gcc source code releases that are known to compile on Cygwin are distributed by the Cygwin project. Therefore, it is highly recommended that you obtain the binutils and gcc sources from the Cygwin mirror network (http://cygwin.com/mirrors.html).

Follow these steps to download Cygwin/X binaries:

- 1. Create a directory to store the binutils and gcc sources in, such as /home/my\_login/cygwin/src/
- 2. Visit the Cygwin mirrors page (http://cygwin.com/mirrors.html) to find your closest mirror
- 3. The ftp url for your mirror site should take you to the cygwin/ directory on the mirror
- 4. Change current ftp directory to cygwin/release/.
- 5. Download the following files from cygwin/release/, saving them to /home/my\_login/cygwin/src/ The compressed file size appears after each file in the list below.

**Downloading with a Web Browser:** Some web browsers automatically decompress saved files when you use the left mouse button to follow the link to a file; bunzip2 will report, "Data integrity

error when decompressing.", when attempting to decompress a file that has been decompressed by your web browser. Prevent your files from being automatically decompressed by clicking the right mouse button on a file link and choosing a command such as Save Target As... or Save Link As... from the context sensitive menu. Better yet, download your files with a stand alone ftp client.

- binutils/binutils-20030901-1-src.tar.bz2 (10.5 MiB; required, necessary to build gcc and Cygwin/X)
- gcc/gcc-3.3.1-1-src.tar.bz2 (21.9 MiB; required, necessary to build Cygwin/X)

### **Obtaining Cygwin Headers and Libs**

The simplest method of building a cross compiler for Cygwin requires that you have the Cygwin headers and libraries available at the time of building the cross compiler. Cygwin headers and libraries are installed when Cygwin is installed, so the headers and libraries can be obtained from an existing Cygwin installation.

**Don't simply copy the headers and libraries:** Some of the headers and libraries are symbolic links to other headers or libraries. Copying these files using a program that is not aware of Cygwin's symlink emulation will result in some of the header and library files being broken. The method described below will preserve the symbolic links used by the header and library files.

1. Launch your Cygwin environment, using either the icon on your Desktop, the icon in your Start Menu, or by running cygwin.bat from your Cygwin directory (e.g. c:\cygwin); you should see a window like the following:

```
Username@CygwinHost ~
```

2. Change the current directory to Cygwin root directory:

```
Username@CygwinHost ~
$ cd /
Username@CygwinHost /
$
```

3. Create an archive of the contents of the /lib directory:

```
Username@CygwinHost /
$ tar czf cygwin-lib.tgz lib/
Username@CygwinHost /
$
```

4. Change the current directory to the usr directory in your Cygwin root directory:

```
Username@CygwinHost /
$ cd /usr
Username@CygwinHost /usr
$
```

5. Create an archive of the contents of the /usr/include directory:

```
Username@CygwinHost /usr
$ tar czf cygwin-include.tgz include/
Username@CygwinHost /usr
$
```

6. Transfer cygwin-lib.tgz and cygwin-include.tgz to your build host using any method that you have available (e.g. ftp, samba, diskette, etc.). Save the files in the /home/my\_login/cygwin/i686-pc-cygwin/ directory.

7. Open a shell on your cross compiling build host; you should see a window like the following:

```
[harold@CrossHost harold]$
```

8. Change the current directory to the /home/my\_login/cygwin/i686-pc-cygwin/ directory in your build host root directory:

```
[harold@CrossHost harold]$ cd /home/my_login/cygwin/i686-pc-cygwin/
[harold@CrossHost /home/my_login/cygwin/i686-pc-cygwin/]$
```

9. Extract the cygwin-lib.tgz and cygwin-include.tgz archives:

```
[harold@CrossHost /home/my_login/cygwin/i686-pc-cygwin/]$ tar xzf cygwin-lib.tgz
[harold@CrossHost /home/my_login/cygwin/i686-pc-cygwin/]$ tar xzf cygwin-include.tgz
```

10. Obtaining Cygwin headers and libs is now complete.

## **Building binutils and gcc**

1. Open a shell on your cross compiling build host; you should see a window like the following:

```
[harold@CrossHost harold]$
```

2. Change the current directory to the /home/my\_login/cygwin/src/ directory in your build host root directory:

```
[harold@CrossHost harold]$ cd /home/my_login/cygwin/src/
[harold@CrossHost src]$
```

3. Extract the binutils-20030901-1-src.tar.bz2 and gcc-3.3.1-1-src.tar.bz2 archives:

```
[harold@CrossHost src]$ bunzip2 binutils-20030901-1-src.tar.bz2 [harold@CrossHost src]$ tar xf binutils-20030901-1-src.tar
```

```
[harold@CrossHost src]$ bunzip2 gcc-3.3.1-1-src.tar.bz2
   [harold@CrossHost src]$ tar xf gcc-3.3.1-1-src.tar
4. Change the current directory to the /home/my_login/cygwin/src/binutils-20030901-1
  directory:
   [harold@CrossHost src]$ cd binutils-20030901-1
   [harold@CrossHost binutils-20030901-1]$
5. Create a build directory and change the current directory to that directory:
   [harold@CrossHost binutils-20030901-1]$ mkdir build
   [harold@CrossHost binutils-20030901-1]$ cd build
   [harold@CrossHost build]$
6. Configure binutils:
   [harold@CrossHost build]$ ../configure
  --prefix=/home/my_login/cygwin --exec-prefix=/home/my_login/cygwin
  --target=i686-pc-cygwin --host=i686-pc-linux > configure.log 2>&1
  [harold@CrossHost build]$
7. Build binutils:
   [harold@CrossHost build]$ make all > all.log 2>&1
   [harold@CrossHost build]$
8. Install binutils:
   [harold@CrossHost build]$ make install > install.log 2>&1
   [harold@CrossHost build]$
9. Modify the PATH environment variable to include the directories that the binutils executables were
  installed in:
  [harold@CrossHost build]$
  PATH=$PATH:/home/my_login/cygwin/bin:/home/my_login/cygwin/i686-pc-cygwin/bin
   [harold@CrossHost build]$
10. Change the current directory to the /home/my_login/cygwin/src/gcc-3.3.1-1 directory:
   [harold@CrossHost build]$ cd ../../gcc-3.3.1-1
   [harold@CrossHost gcc-3.3.1-1]$
11. Create a build directory and change the current directory to that directory:
   [harold@CrossHost gcc-3.3.1-1]$ mkdir build
   [harold@CrossHost gcc-3.3.1-1]$ cd build
   [harold@CrossHost build]$
```

#### 12. Configure gcc:

```
[harold@CrossHost build]$ ../configure
   --prefix=/home/my_login/cygwin --exec-prefix=/home/my_login/cygwin
   --target=i686-pc-cygwin --host=i686-pc-linux
   --enable-haifa > configure.log 2>&1
   [harold@CrossHost build]$

13. Build gcc:
   [harold@CrossHost build]$ make all > all.log 2>&1
   [harold@CrossHost build]$

14. Install gcc:
   [harold@CrossHost build]$ make install > install.log 2>&1
   [harold@CrossHost build]$
```

### Creating Links for binutils and gcc

15. Building binutils and gcc is now complete.

Links to the executables in /home/my\_login/cygwin/bin must be created in the /home/my\_login/cygwin/i686-pc-cygwin/bin directory; these are required for the build system to find the build executables (e.g. gcc, cpp, etc.). Each of the build executables in /home/my\_login/cygwin/bin is prefixed with i686-pc-cygwin (e.g. i686-pc-cygwin-cpp) whereas the build system expects the executables to have no prefix (e.g. cpp).

Creating links to the build executables and dropping the prefix from the name of each build executables link is done by a script that was provided by the XFree86 cross-compiling community and slightly modified by Alexander Gottwald. The text of this script is below, save it in a file on your cross compiling host called cross-links.sh. Note that the location of the script does not matter, since it contains a reference to the location of the build tools in the CYGROOT variable.

Finally, run the cross-links.sh script. There should now be several links in the /home/my\_login/cygwin/i686-pc-cygwin/bin directory.

## **Building Cygwin/X**

Building the source code when cross compiling X Window System is nearly identical to the process described below in the Section called *Native Compiling* of the Native Compiling section. One divergence from the aforementioned instructions is that you will be using a **bash** shell on your cross compiling host, rather than on your native Cygwin host; other divergences follow.

Note: XXX: THIS IS UNTESTED

- 1. When configuring, you must pass —target=i686-pc-cygwin to ./configure to cause the build system to build for the target, Cygwin, platform:
- 2. When configuring, you must pass —prefix=/stagingdir to ./configure to cause the build system to be configured to install the target platform build into /stagingdir.

OR, when installing a build, you must pass **DESIDIR** to **make install** to install the target platform build into /stagingdir.

**Tip:** Never run **make install** on your host platform without the DESIDER parameter, as that will cause the Cygwin build of X Window System to be installed over top of your local X Window System installation, which would completely destroy your host system's X Window System installation.

## Packaging a Cygwin/X Distribution

Cygwin/X uses a cygport build and packaging script that automates all of the tasks required to build, create binary packages, and source code packages.

**Note:** These instructions assume that you want to build a distribution from the source packages available from Cygwin's **setup.exe**.

You can a similar technique to build a distribution from locally modified sources, cygports svn or a X.Org release tarball instead.

- Use Cygwin setup to install the xorg-server source package, it will be automatically unpacked under /usr/src
- 2. Invoke cygport on the .cygport file contained in the source package installed above. This will create the source and binary packages xorg-server-n.n.n-X-src.tar.bz2 and

```
xorg-server-n.n.n-X.tar.bz2
Username@CygwinHost /usr/src
$ cygport xorg-server-x.x.x-x.cygport all
```

#### **Reference Documentation**

X developer reference documentation.

### X.Org documents

Offical X.Org documentation.

Print versions of various X Window System Manuals also exist.

 Definition of the Porting Layer for the X V11 Sample Server (http://www.x.org/releases/X11R7.5/doc/core/Xserver-spec.pdf)

Essential reading.

The current version of this document is available in the xorg-docs package.

- Xlib C Language X Interface (http://www.x.org/docs/X11/xlib.pdf)
   The current version of this document is available in the libX11 runtime package.
- X Protocol (http://www.x.org/docs/XProtocol/proto.pdf)
- X Inter-Client Communication Conventions (http://www.x.org/docs/ICCCM/icccm.pdf)
- X Logical Font Description Conventions (http://www.x.org/docs/XLFD/xlfd.pdf)

## **Further reading**

Other documents of interest.

- The X Selection Mechanism or, How to Cut and Paste in 1000 lines or more (http://www.msu.edu/~huntharo/xwin/docs/xwindows/selection.pdf) (40 KiB, 13 pages)
  - 1990 Good information/tutorial about the X selection mechanism. From Papers and Talks by Keith Packard (http://keithp.com/~keithp/talks/) converted to PDF

### X server porting documents

Other documents about X server porting.

- Strategies for Porting the X V11 Sample Server (http://www.msu.edu/~huntharo/xwin/docs/xwindows/strat.pdf) (77 KiB, 22 pages)
  - 1998 Mainly of historical interest now, but might give you some insight
- Godzilla's Guide to Porting the X V11 Sample Server (http://www.msu.edu/~huntharo/xwin/docs/xwindows/gdz.pdf) (38 KiB, 11 pages)
  - 1990 Old and thin, but relevant
- Design of eXcursion Version 2 for Windows, Windows NT, and Windows 95
   (http://www.msu.edu/~huntharo/xwin/docs/xwindows/eXcursion2.pdf) (301 KiB, 14 pages)
  - 1996 Discusses some of the difficulties in creating an X Server for Microsoft Windows. More geared towards implementing a server that translates X raster ops into Windows GDI raster ops. Cygwin/X does not currently translate raster ops, though the framework to do so is in place, and development on raster op translation could be resumed in the future.
- Writing a Graphics Device Driver and DDX for the Digital UNIX X Server (http://www.msu.edu/~huntharo/xwin/docs/xwindows/xikdoc.pdf) (602 KiB, 272 pages)
  - 1997 Contains some good hints in the DDX section

## **Chapter 3. Documentation**

#### **Overview**

Cygwin/X documentation is written in XML according to the DocBook (http://docbook.org/) document type definition (DTD). These XML input files are then compiled using an autoconf and automake build system. We currently build the following output formats: HTML, PDF, PS, RTF, and TXT.

## **Obtaining the Source Code**

### Source of latest cygwin-x-doc release

To obtain the source of the latest release of the cygwin-x-doc package start the cygwin setup, select directories and mirror and select the package cygwin-x-doc from the category X11. Mark the checkbox labelled src and install. This will install the documentation source in /usr/src/cygwin-x-doc.

#### Source from CVS

The documentation source code is available from sourceware.org CVS. To obtain them please use the follow commands:

```
$ cvs -d :pserver:anoncvs@sourceware.org:/cvs/cygwin-xfree login
CVS password: <hit return>
$ cvs -d :pserver:anoncvs@sourceware.org:/cvs/cygwin-xfree co doc
[output as files are checked out]
$ (cd doc && autoreconf)
[output as autoconfiguration scripts are regenerated]
```

You should now have the sources in an directory called doc.

If you just want to look at the Cygwin/X documentation source, use the CVSweb interface to the Cygwin/X documentation tree (http://sourceware.org/cgi-bin/cvsweb.cgi/doc/?cvsroot=cygwin-xfree).

## **Setting Up a DocBook Build Environment**

Setup a DocBook build environment on Cygwin

### **Required Packages for building documentation**

- · openjade
- jadetex (no offical package for this)
- · docbook-dsssl (no offical package for this and getting the stylesheets set up properly is a black art)

**Note:** A useful, if slightly dated, introduction to setting up a docbook build environment and editing tools can be found in the SGML for Windows NT: Setting up a free SGML editing and publishing system on Windows NT/Cygwin

(http://web.archive.org/web/20050320030737/http://ourworld.compuserve.com/homepages/hoenicka\_markus/cygbodocument.

## **Building the Documentation**

Follow these instructions to build the Cygwin/X documentation source code:

1. Open a shell on your documentation build host; you should see a window like the following:

```
Username@CygwinHost ~ $
```

2. Change the current directory to the documentation source code directory:

```
Username@CygwinHost ~
$ cd cygwin-x-doc-1.0.0

Username@CygwinHost ~/cygwin-x-doc-1.0.0
$
```

3. Create a build directory and change the current directory to that directory:

```
Username@CygwinHost ~/cygwin-x-doc-1.0.0
$ mkdir build

Username@CygwinHost ~/cygwin-x-doc-1.0.0
$ cd build

Username@CygwinHost ~/cygwin-x-doc-1.0.0/build
$
```

4. Configure the documentation source code:

```
Username@CygwinHost ~/cygwin-x-doc-1.0.0/build
$ ../configure

Username@CygwinHost ~/cygwin-x-doc-1.0.0/build
$
```

**Note:** Use **./configure --enable-hardcopy** to enable building of all documentation formats, otherwise just HTML will be built

5. Build the documentation:

```
Username@CygwinHost ~/cygwin-x-doc-1.0.0/build
$ make all
```

6. Building the documentation is now complete.

## **Packaging a Documentation Distribution**

Follow these instructions to build a Cygwin/X documentation source code distribution:

1. Edit the version tag in the third line of the file configure.ac to indicated a new version, or to add a branch name to the distribution. The line containing the version tag should look like:

```
AC_INIT(cygwin-x-doc, 1.0.0)
```

2. Open a shell on your documentation build host; you should see a window like the following:

```
Username@CygwinHost ~ $
```

3. Change the current directory to the documentation source code build directory:

```
Username@CygwinHost ~
$ cd cygwin-x-doc-1.0.0/build

Username@CygwinHost ~/cygwin-x-doc-1.0.0/build
$
```

4. Build the documentation source code distribution:

```
Username@CygwinHost ~/cygwin-x-doc-1.0.0/build
$ make distcheck
```

- 5. The documentation source code distribution should now be contained in the current directory in a file called cygwin-x-doc-1.0.0.tar.gz.
- 6. Building the documentation is now complete.

## **Chapter 4. Web Site Maintenance**

The Cygwin/X web site is stored in sourceware.org CVS. The CVSROOT is :ext:sourceware.org:/cvs/cygwin/, and the path is htdocs/xfree/

## Updating the documentation on the web site

A simple way of updating the documentation from the cywin-x-doc package shown on the web site is to build the documentation directly into a CVS checkout of web-site and then check it in.

```
$ export CVS_RSH=ssh
$ cvs -z9 -d :ext:user@sourceware.org:/cvs/cygwin/ co htdocs/xfree
[...]
$ cd htdocs/xfree/docs
$ path-to-cygwin-x-doc/configure --enable-hardcopy
$ make
$ cvs up
[...]
$ cvs ci
```

## **Bibliography**

### **Articles**

[Angebranndt94] *Definition of the Porting Layer for the X v11 Sample Server*, Angebranndt94, Susan Angebranndt, Raymond Drewry, Philip Karlton, Todd Newman, Robert W. Scheifler, Keith Packard, and David P. Wiggins, 1994.

#### **Books**

- [ScheiflerGettys92] Robert W. Scheifler, James Gettys, Jim Flowers, and David Rosenthal, 1992, 1-55558-088-2, Butterworth-Heinemann, *X Window System: The Complete Reference to Xlib, X Protocol, ICCCM, and XLFD*.
- [Richter99] Jeffrey Richter, 1999, 1-57231-996-8, Microsoft Press, *Programming Applications for Microsoft Windows: Mastering the critical building blocks of 32-bit and 64-bit Windows-based applications.*
- [Petzold99] Charles Petzold, 1999, 1-57231-995-X, Microsoft Press, *Programming Windows: The definitive guide to the Win32 API*.
- [McKay99] Everett N. McKay, 1999, 0-7356-0586-6, Microsoft Press, Developing User Interfaces for Microsoft Windows: Practical and effective methods for improving the user experience.
- [JonesOhlund99] Anthony Jones and Jim Ohlund, 1999, 0-7356-0560-2, Microsoft Press, *Network Programming for Microsoft Windows: Clear, practical guide to Microsoft's networking APIs.*
- [Yuan01] Feng Yuan, 2001, 0-13-086985-6, Prentice Hall PTR, Windows Graphics Programming: Win32 GDI and DirectDraw.
- [CohenWoodring98] Aaron Cohen and Mike Woodring, 1998, 1-56592-296-4, O'Reilly & Associates, Inc., *Win32 Multithreaded Programming: Building Thread-Safe Applications*.
- [CameronRosenblattRaymond96] Debra Cameron, Bill Rosenblatt, and Eric Raymond, 1996, 1991, 1-56592-152-6, O'Reilly & Associates, Inc., *Learning GNU Emacs: UNIX Text Processing*.
- [Lewine91] Edited by Dale Dougherty, Donald A. Lewine, 1991, 0-937175-73-0, O'Reilly & Associates, Inc., *POSIX Programmer's Guide: Writing Portable UNIX Programs*.
- [KernighanRitchie88] Brian W. Kernighan and Dennis M. Ritchie, 1988, 1978, 0-13-110370-9, Prentice Hall PTR, *The C Programming Language: ANSI C*.

## **Glossary**

B

#### Bitmap (Win32)

Windows pixel map.

#### Bitmap (X)

X pixel map with bit depth equal to one. X pixel maps of bit depth not equal to one are called *pixmaps*.

C

#### **Color Framebuffer Layer**

Deprecated X Server layer providing implementations of the X graphics functions to draw on an antiquated framebuffer device. CFB is optimized to minimize CPU instructions at the expense of additional memory accesses; this does not work well on modern machines because memory access is the system performance bottle neck. CFB can only be initialized to draw on one depth of framebuffer per instantiation; this was done to eliminate CPU instructions that checked the current framebuffer depth, thus saving processing time on early machines.

#### Colormap

X Server colormap. Contains a table translating index values to red, green, blue 3-tuples that will be displayed on the screen when a given index value is contained in a bitmap.

D

#### **Device Dependent X Layer**

X Server layer that depends on the hardware; but not the operating system.

#### **Device Independent X Layer**

X Server layer that does not depend on the hardware layer, nor the operating system.

## F

#### Framebuffer Layer

X Server layer providing implementations of the X graphics functions to draw on a modern framebuffer device. FB is optimized to minimize memory accesses at the expense of additional CPU instructions; this works well on modern machines because memory access is the system performance bottle neck.

## G

#### **Graphics Context**

X Server graphics context. Stores information describing a graphics operation to perform, such as the foreground and background colors, fill style, stipple, and tile.

#### git

git is an open source distributed version control system. More information can be found at the git project homepage (http://git.or.cz/).

## M

#### **Machine Independent Layer**

X Server layer providing user input and graphics display functions that are independent of the machine used by the DDX layer. The MI drawing functions depend on only three DDX functions: FillSpans, GetSpans, and SetSpans.

O

#### Offscreen Framebuffer

Essentially a *bitmap*, in the Windows sense, of size and color format that can be displayed on the screen. An offscreen framebuffer may be identical in size and color format to the *primary framebuffer*, but this is not always required.

#### **OS Layer**

X Server layer that depends on the operating system; but not the hardware.

P

#### **Pixmap**

X pixel map with bit depth not equal to one. X pixel maps of bit depth one are called bitmaps.

#### **Primary Framebuffer**

The block of memory, essentially a *bitmap*, that describes what is currently being displayed on the screen. Any updates to the primary framebuffer will be displayed on the screen after the next screen refresh.

#### **Privates**

Additional information associated with internal X Server structures, such as *colormaps*, *GCs*, *pixmaps*, or *screens*.

S

#### Screen

X Server screen. A screen usually corresponds to a display device; however, Cygwin/X's X Server corresponds each screen to one Windows window. A single instance of the Cygwin/X X Server may have several screens.

#### **Shadow**

X Server shadow layer that allows FB to draw to an offscreen framebuffer and occasionally call a DDX function that transfers the updated regions to the screen.



#### X Display Manager

An X Display Manager presents a graphical login screen to X users. Often an XDM will allow the user to select a desktop environment or window manager to be for their login session. Some X Display Managers are xdm, gdm (Gnome Display Manager), and kdm (KDE Display Manager).

#### **X Display Manager Control Protocol**

XDMCP allows XDM to process logins for users remote to the machine that XDM is running on; login sessions will be run on the machine running XDM. For example, at a university you may use XDMCP to login to an X session running on an engineering department computer from your dorm room.

See Also: X Display Manager.

## **Appendix A. GNU Free Documentation License**

Version 1.1, March 2000

Copyright (C) 2000 Free Software Foundation, Inc. 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other written document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you".

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (For example, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, whose contents can be viewed and edited directly and straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup has been designed to thwart or discourage subsequent modification by readers is not Transparent. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML designed for human modification. Opaque formats include PostScript, PDF, proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

### 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

### 3. COPYING IN QUANTITY

If you publish printed copies of the Document numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a publicly-accessible computer-network location containing a complete Transparent copy of the Document, free of added material, which the general network-using public has access to download

anonymously at no charge using public-standard network protocols. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has less than five).
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section entitled "History", and its title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.

- K. In any section entitled "Acknowledgements" or "Dedications", preserve the section's title, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section as "Endorsements" or to conflict in title with any Invariant Section.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections entitled "History" in the various original documents, forming one section entitled "History"; likewise combine any sections entitled "Acknowledgements", and any sections entitled "Dedications". You must delete all sections entitled "Endorsements."

### 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

#### 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, does not as a whole count as a Modified Version of the Document, provided no compilation copyright is claimed for the compilation. Such a compilation is called an "aggregate", and this License does not apply to the other self-contained works thus compiled with the Document, on account of their being thus compiled, if they are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one quarter of the entire aggregate, the Document's Cover Texts may be placed on covers that surround only the Document within the aggregate. Otherwise they must appear on covers around the whole aggregate.

#### 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License provided that you also include the original English version of this License. In case of a disagreement between the translation and the original English version of this License, the original English version will prevail.

### 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

### 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (c) YEAR YOUR NAME. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation; with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have no Invariant Sections, write "with no Invariant Sections" instead of saying which ones are invariant. If you have no Front-Cover Texts, write "no Front-Cover Texts" instead of "Front-Cover Texts being LIST"; likewise for Back-Cover Texts.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.