Managing File Permissions

Note

All labs rely on previous courseware and lab information.

Objectives

In this lab, you will:

- · Change all folder and file permissions to match the appropriate group structure
- · Modify file permissions for a user
- · Update the company folder structure

Duration

This lab will require approximately 35 minutes to complete.

AWS service restrictions

In this lab environment, access to AWS services and service actions might be restricted to the ones that you need to complete the lab instructions. You might encounter errors if you attempt to access other services or perform actions beyond the ones that this lab describes.

Accessing the AWS Management Console

1. At the top of these instructions, choose Start Lab to launch your lab.

A Start Lab panel opens, and it displays the lab status.

Tip: If you need more time to complete the lab, choose the Start Lab button again to restart the timer for the environment.

- 2. Wait until you see the message Lab status: ready, then close the Start Lab panel by choosing the X.
- 3. At the top of these instructions, choose AWS.

 This opens the AWS Management Console in a new browser tab. The system will automatically log you in.

Tip: If a new browser tab does not open, a banner or icon is usually at the top of your browser with a message that your browser is preventing the site from opening pop-up windows. Choose the banner or icon and then choose **Allow pop ups**.

4. Arrange the AWS Management Console tab so that it displays along side these instructions. Ideally, you will be able to see both browser tabs at the same time so that you can follow the lab steps more easily.

Task 1: Use SSH to connect to an Amazon Linux EC2 instance

In this task, you will connect to a Amazon Linux EC2 instance. You will use an SSH utility to perform all of these operations. The following instructions vary slightly depending on whether you are using Windows or Mac/Linux.

Windows Users: Using SSH to Connect

These instructions are specifically for Windows users. If you are using macOS or Linux, <u>skip to the next section</u>.

- 5. Select the Details drop-down menu above these instructions you are currently reading, and then select Show . A Credentials window will be presented.
- 6. Select the **Download PPK** button and save the **labsuser.ppk** file. *Typically your browser will save it to the Downloads directory.*
- 7. Make a note of the **PublicIP** address.
- 8. Then exit the Details panel by selecting the X.
- 9. Download **PuTTY** to SSH into the Amazon EC2 instance. If you do not have PuTTY installed on your computer, <u>download it here</u>.
- 10. Open putty.exe
- 11. Configure PuTTY timeout to keep the PuTTY session open for a longer period of time.:
 - Select Connection
 - Set Seconds between keepalives to 30
- 12. Configure your PuTTY session:
 - Select Session
 - Host Name (or IP address): Paste the Public DNS or IPv4 address of the instance you made a note of earlier.
 - Alternatively, return to the EC2 Console and select **Instances**. Check the box next to the instance you want to connect to and in the *Description* tab copy the **IPv4 Public IP** value.
 - Back in PuTTY, in the Connection list, expand SSH
 - Select Auth (don't expand it)
 - Select Browse
 - Browse to and select the lab#.ppk file that you downloaded
 - Select Open to select it
 - Select Open again.
- 13. Select **Yes**, to trust and connect to the host.
- 14. When prompted **login as**, enter: ec2-user This will connect you to the EC2 instance.

15. Windows Users: Select here to skip ahead to the next task.

macOS and Linux Users

These instructions are specifically for Mac/Linux users. If you are a Windows user, <u>skip ahead to the next task.</u>

- 16. Select the Details drop-down menu above these instructions you are currently reading, and then select Show. A Credentials window will be presented.
- 17. Select the **Download PEM** button and save the **labsuser.pem** file.
- 18. Make a note of the PublicIP address.
- 19. Then exit the Details panel by selecting the X.
- 20. Open a terminal window, and change directory cd to the directory where the *labsuser.pem* file was downloaded. For example, if the *labuser.pem* file was saved to your Downloads directory, run this command:

```
cd ~/Downloads
```

21. Change the permissions on the key to be read-only, by running this command:

```
chmod 400 labsuser.pem
```

22. Run the below command (replace <public-ip> with the PublicIP address you copied earlier).

Alternatively, return to the EC2 Console and select Instances. Check the box next to the instance you want to connect to and in the Description tab copy the IPv4 Public IP value.:

```
ssh -i labsuser.pem ec2-user@<public-ip>
```

23. Type yes when prompted to allow the first connection to this remote SSH server.

Because you are using a key pair for authentication, you will not be prompted for a password.

Task 2: Change file and folder ownership

In this exercise, you will change the following ownership:

- 24. companyA folder ownership to the CEO and group ownership to Personnel
- 25. HR folder ownership to the HR manager and group ownership to HR
- 26. Finance folder ownership to the finance manager and group ownership to Finance
- 27. To validate that you are in the /home/ec2-user/companyA folder, enter pwd and press Enter.

 If you are not in this folder, enter cd companyA and press Enter.

28. To change the ownership of the **companyA** folder structure to the CEO mjackson and the group ownership to Personnel, enter sudo chown -R mjackson:Personnel /home/ec2-user/companyA and press Enter.

- 29. To change the ownership of the HR folder to the HR manager ctee, enter sudo chown -R 1juan:HR HR and press Enter.
- 30. To change the ownership of the HR/Finance folder to the finance manager, enter sudo chown -R mmajor: Finance HR/Finance and press Enter.
- 31. To validate your work by using the recursive feature of the **Is** command, enter 1s -1ar and press Enter.

```
[ec2-user@ip-10-0-10-253 ~]$ cd companyA
[ec2-user@ip-10-0-10-253 companyA]$ sudo chown -R emcbath:Personnel /home/ec2-user/companyA
[ec2-user@ip-10-0-10-253 companyA]$ sudo chown -R ctee:HR HR
[ec2-user@ip-10-0-10-253 companyA]$ sudo chown -R dolberdi:Finance HR/Finance
[ec2-user@ip-10-0-10-253 companyA]$ ls -laR
.:
total 0
drwxr-xr-x 9 emcbath Personnel 136 Aug 24 23:15 .
drwxr-xr-x 2 emcbath Personnel 6 Aug 24 23:15 .
drwxr-xr-x 2 emcbath Personnel 6 Aug 24 23:15 Employees
drwxr-xr-x 2 emcbath Personnel 6 Aug 24 23:15 Management
-rw-r-r-- 1 emcbath Personnel 6 Aug 24 23:15 Soles
drwxr-xr-x 2 emcbath Personnel 6 Aug 24 23:15 Soles
drwxr-xr-x 2 emcbath Personnel 6 Aug 24 23:15 SharedFolders
drwxr-xr-x 2 emcbath Personnel 6 Aug 24 23:15 Shipping
```

Figure: When using the command Is -laR the output shows the ownership permissions of the entire companyA folder structure. This folder structure includes the following: Documents, Employees, HR, Management, Roster.csv, Sales, SharedFolders, and Shipping.

Task 3: Change permission modes

In this task, you change permission modes. You create and change permissions using the **chomd** command.

Recall that the **chmod** command changes the permissions of your files. There are two modes: symbolic and absolute. Symbolic mode uses both letters and symbols to manipulate permissions, and absolute mode uses only numbers to represent permissions.

- 32. To validate that you are in the /home/ec2-uer/companyA folder, enter pwd and press Enter.
- 33. Use vim to create a file called **symbolic_mode_file**. To create this file, enter sudo vi symbolic_mode_file and press Enter.
- 34. To save and close the file, press ESC. Then enter :wq and press Enter.
- 35. To use the symbolic mode for **chmod** to change the file permissions, enter sudo chmod g+w symbolic_mode_file and press Enter.

 You just gave the group owner write permissions to **symbolic mode file**.
- 36. Use vim to create a file called **absolute_mode_file**. To create this file, enter sudo vi absolute_mode_file and press Enter.
- 37. To save and close the file, press ESC. Then enter :wq and press Enter.
- 38. To use the absolute mode for **chmod** to change the file permissions, enter sudo chmod 764 absolute_mode_file and press Enter.

764 means that the user has read, write, and execute permissions on the absolute mode file.

39. To confirm this information, enter the 1s -1 command and press Enter. You should see the two files that you created with the correlating read, write, and execute permissions.

```
[ec2-user@ip-10-0-10-100 companyA]$ vi symbolic_mode_file
[ec2-user@ip-10-0-10-100 companyA]$ chmod g+w symbolic_mode_file
[ec2-user@ip-10-0-10-100 companyA]$ vi absolute_mode_file
[ec2-user@ip-10-0-10-100 companyA]$ chmod 764 absolute_mode_file
[ec2-user@ip-10-0-10-100 companyA]$ ls -1
total 8
-rwxrw-r-- 1 ec2-user ec2-user 27 Sep 7 17:09 absolute_mode_file
drwxr-xr-x 2 ec2-user Personnel 6 Sep 7 16:59 CE0
drwxr-xr-x 2 ec2-user Personnel 6 Sep 7 16:59 Documents
drwxr-xr-x 2 ec2-user Personnel 6 Sep 7 16:59 Employees
drwxr-xr-x 6 ec2-user Personnel 6 Sep 7 16:59 HR
drwxr-xr-x 2 ec2-user Personnel 6 Sep 7 16:59 Management
-rw-r---- 1 ec2-user Personnel 6 Sep 7 16:59 Sales
drwxr-xr-x 2 ec2-user Personnel 24 Sep 7 16:59 Sales
drwxr-xr-x 2 ec2-user Personnel 24 Sep 7 16:59 SharedFolders
drwxr-xr-x 2 ec2-user Shipping 6 Sep 7 16:59 Shipping
-rw-rw-r-- 1 ec2-user ec2-user 23 Sep 7 17:09 symbolic_mode_file
```

Figure: When using the command sudo chmod 764 absolute_mode_file, the user in the file will have read, write, and execute permissions for the absolute_mode_file. This is confirmed by running the command Is -I which lists the read, write, and execute permissions of the user.

Task 4: Assign permissions

In this exercise, you assign the appropriate permissions to the **Shipping** and **Sales** folders.

- 40. To validate that you are in the /home/ec2-user/companyA folder, enter pwd and press Enter.
- 41. To change the ownership of the **Shipping** folder to eowusu, the current shipping manager, and the group ownership to Shipping, enter sudo chown -R eowusu:Shipping Shipping and press Enter.
- 42. To change the ownership of the **Sales** folder to nwolf, the current sales manager, and the group ownership to Sales, enter sudo chown -R nwolf:Sales sales and press Enter.
- 43. To validate your work, use the 1s command on the folders that you just created.
 - To validate the changes to the Shipping folder, enter 1s -laR Shipping and press Enter.
 - To validate the changes to the Sales folder, enter and 1s -1aR Sales and press Enter.

```
ec2-user@ip-10-0-10-253:~/companyA|$ sudo chown -R eleonard:Shipping Shipping [ec2-user@ip-10-0-10-253 companyA]$ ls -laR Shipping Shipping Shipping:
total 0 drwxr-xr-x 2 eleonard Shipping 6 Aug 24 23:15 ...
[ec2-user@ip-10-0-10-253 companyA]$ sudo chown -R isteinke:Sales Sales [ec2-user@ip-10-0-10-253 companyA]$ sudo chown -R isteinke:Sales Sales
[ec2-user@ip-10-0-10-253 companyA]$ ls -laR Sales
Sales:
total 0 drwxr-xr-x 2 isteinke Sales 6 Aug 24 23:15 ...
drwxr-xr-x 9 emcbath Personnel 136 Aug 24 23:15 ...
[ec2-user@ip-10-0-10-253 companyA]$ [ ec2-user@ip-10-0-10-253 companyA]$ [ ec2-user@ip-1
```

Figure: The command prompt shows the output of changing the ownership of the Shipping folder and its group to the user eleonard. This is confirmed by using the Is command. The same change of ownership is done for the Sales folder and its group to the user isteinke.

Lab Complete

Congratulations! You have completed the lab.

44. Select End Lab at the top of this page and then select Yes to confirm that you want to end the lab.

A panel will appear, indicating that "DELETE has been initiated... You may close this message box now."

45. Select the **X** in the top right corner to close the panel.

About the AWS component

Amazon EC2 provides a wide selection of *instance types* optimized to fit different use cases. Instance types comprise varying combinations of CPU, memory, storage, and networking capacity and give you the flexibility to choose the appropriate mix of resources for your applications. Each instance type includes one or more *instance sizes* so that you can scale your resources to the requirements of your target workload.

This lab uses a **t3.micro** instance, which should be selected by default. This instance type has 1 virtual CPU and 1 GiB of memory.

Additional resources

- Amazon EC2 Instance Types
- Amazon Machine Images (AMI)
- Status Checks for Your Instances
- Amazon EC2 Service Quotas
- <u>Terminate Your Instance</u>

For more information about AWS Training and Certification, see https://aws.amazon.com/training/.

Your feedback is welcome and appreciated.

If you would like to share any suggestions or corrections, please provide the details in our <u>AWS Training</u> and Certification Contact Form.

© 2022 Amazon Web Services, Inc. and its affiliates. All rights reserved. This work may not be reproduced or redistributed, in whole or in part, without prior written permission from Amazon Web Services, Inc. Commercial copying, lending, or selling is prohibited.