# Lecture 8: Abstraction II - Special Member Functions

#### Introduction

Special member functions are class methods defined by the compiler during compilation if not explicitly defined that help manage resources and ensure objects are properly initialized, copied, and cleaned up.

#### Constructors

Constructors are methods that initialize the instance fields of a class and perform any required setup. They have no return type, return nothing, and are called when an object is instantiated (created). Their general syntax is

```
[explicit] class (parameter-list) [:member-initialization-list] {body}
```

**Object Declaration** When an object is instantiated, it can invoke a constructor using any one of the following syntaxes:

- 1. class identifier(argument-list);
  - parentheses must be omitted to invoke the default constructor.
- 2. class identifier = {argument-list};
  - cannot be used to invoke the default constructor.
  - curly braces can be omitted to invoke a constructor with a single parameter.
- 3. class identifier = class(argument-list);

where the second format is prohibited if the constructor is defined with the explicit keyword.

Member Initialization List The member initialization list either allows the initialization of instance fields or an invocation of another constructor, a process called *constructor delegation* executing the constructor's body. The field initialization syntax within the list is

- Variable syntax: field(argument-list)
  where argument-list are arguments for a constructor of field.
- Array syntax: field { argument-list }

Furthermore, constructor delegation can invoke either another constructor of the class or a constructor of its base classes if any [elaboration of base classes is in the inheritance lecture] with the syntax is

```
class(argument-list)
```

which is an anonymous object.

In addition, the list can contain both constructor delegations followed by field initializations if they are initializing members of different classes.

**Default Constructor** The *default constructor* is the primary constructor and a special member function. It is invoked whenever a standard variable declaration is used. Its syntax is

```
[explicit] class()[:member-initialization-list]{body}
```

All other constructors are considered overloaded constructors.

Copy Constructor Another special member function constructor is called the *copy constructor*. It creates a new object as a copy of an existing object. Its syntax is

```
[explicit] class (const class & identifier) [: member-initialization-list] {body}
```

The copying procedure can either be a *shallow copy* [memberwise copy] or a deep copy. A shallow copy copies field content from the parameter to the object, which may lead to shared resources among objects when dealing with pointers since the content of a pointer is an address.

Whereas, a deep copy copies resources, which means its pointer fields allocate new memory and then copy the dereferenced content.

#### Example:

Two versions using different copy procedures including all possible object instantiation formats.

```
class SV
                                                               class DV
{
                                                               {
 public:
                                                                 public:
 int *x;
                                                                 int *x;
 char id;
                                                                 char id;
 SV():SV(0) {}
                                                                 DV() : DV(0) \{ \}
 explicit SV(int y) : (new int(y)), id('x') {}
                                                                 explicit DV(int y) : (new int(y)), id('x') {}
 SV(int x,char id) : SV(x) {this->id = id;}
                                                                 DV(int x,char id) : DV(x) {this->id = id;}
 SV(const SV& obj) : id(obj.id)
                                                                 DV(const DV& obj) : id(obj.id), x(new int)
                                                                 {
   //shallow copy
                                                                  //deep copy
   x = obj.x;
                                                                  *x = *(obj.x);
 }
};
                                                               };
int main()
                                                               int main()
 //default constructor
                                                                 //default constructor
 SV a1, a3 = SV();
                                                                 DV a1, a3 = DV();
 //1st overloaded constructor
                                                                 //1st overloaded constructor
 SV b1(4), b3 = SV(4);
                                                                DV b1(4), b3 = DV(4);
 //2nd overloaded constructor
                                                                 //2nd overloaded constructor
 SV c1(8, 't'), c2 = \{8, 't'\}, c3 = SV(8, 't'),;
                                                                 DV c1(8,'t'), c2 = \{8,'t'\}, c3 = DV(8,'t'),;
 //copy constructor
                                                                 //copy constructor
 SV d1(c1), d2 = c2, d3 = SV(c3);
                                                                 DV d1(c1), d2 = c2, d3 = DV(c3);
 return 0;
                                                                 return 0;
}
```

### Destructor

The destructor is a special member function used for resource cleanup (garbage collection). It deals with memory deallocation, stream closures, and other termination operations. Its syntax is

```
~class(){body}
```

It is invoked whenever the object's scope ends or when the object is explicitly deallocated if it was explicitly allocated.

## Example:

Destructors of the classes from the previous example.

Using the current destructor, SV objects that use the copy constructor may have issues with field x since it performs a shallow copy.

## **Assignment Operator**

The assignment operator is the last of the special member function. It copies the content of another object to the object. Its syntax is

```
class& operator=(const class& identifier){body}
```

It is invoked when its object is assigned another class object after being instantiated; hence, its definition normally confirms that the argument and the object are different before performing the copy as illustrated in the template code below

```
class & operator=(const class & identifier)
{
   if(this != &identifier)
   {
      body
   }
   return *this;
}
```

Anyway, the copy procedure is identical to the copy constructor, except sometimes with pointers; it needs to deallocate memory before allocating new memory to prevent memory leaks. Furthermore, it always returns the dereferenced this pointer.

#### Example:

Assignment operator of the classes from the previous examples.

```
class SV
                                                              class DV
                                                               public:
 public:
 //previous code
                                                                //previous code
                                                               DV& operator=(const DV& rhs)
 SV& operator=(const SV& rhs)
   if(this != &rhs)
                                                                 if(this != &rhs)
     //shallow copy
                                                                   //deep copy
    delete x;
                                                                   delete x;
     x = rhs.x;
                                                                   x = new int;
    id = rhs.id:
                                                                   *x = *(rhs.x);
                                                                   id = rhs.id;
   return *this;
                                                                 return *this;
                                                                }
};
                                                              };
int main()
                                                              int main()
 //previous code
                                                                //previous code
 SV *s = new SV(6);
                                                               DV *s = new DV(6);
 a1 = SV(81); //assignment operator call
                                                                a1 = DV(81); //assignment operator call
 delete s; //destructor call
                                                                delete s; //destructor call
 return 0;
                                                               return 0;
}
                                                              }
```