Composing an SIR model from individual transitions using AlgebraicPetri.jl

Simon Frost (@sdwfrost) 2023-06-13

Introduction

This example serves as a 'Hello World' to composing Petri net models, where models are 'glued' together using the shared states of the individual submodels.

Libraries

```
using AlgebraicPetri,AlgebraicPetri.TypedPetri
using Catlab, Catlab.CategoricalAlgebra, Catlab.Programs
using Catlab.WiringDiagrams, Catlab.Graphics
using AlgebraicDynamics.UWDDynam
using LabelledArrays
using OrdinaryDiffEq
using Plots
```

Transitions

We first define a labelled Petri net that has the different types of transition in our models. The first argument is an array of state names as symbols (here, a generic :Pop), followed by the transitions in the model. Transitions are given as transition_name=>((input_states)=>(output_states)).

```
epi_lpn = LabelledPetriNet(
  [:Pop],
  :infection=>((:Pop, :Pop)=>(:Pop, :Pop)),
  :recovery=>(:Pop=>:Pop)
);
```

Labelled Petri nets contain four types of fields; S, states or species; T, transitions; I, inputs; and O, outputs.

Next, we define the transmission model (from susceptibles, S to infecteds, I) as an undirected wiring diagram using the @relation macro, referring to the transitions in our labelled Petri net above (infection). We include a reference to Pop in the definition of the state variables to allow us to do this.

```
si_uwd = @relation (S, I) where (S::Pop, I::Pop) begin
    infection(S, I, I, I)
end;
```

We then use <code>oapply_typed</code>, which takes in a labelled Petri net (here, <code>epi_lpn</code>) and an undirected wiring diagram (<code>si_uwd</code>), where each of the boxes is labeled by a symbol that matches the label of a transition in the Petri net, in addition to an array of symbols for each of the rates in the wiring diagram. This produces a Petri net given by colimiting the transitions together, and returns the <code>ACSetTransformation</code> from that Petri net to the type system.


```
si_acst = oapply_typed(epi_lpn, si_uwd, [:]);
```

To obtain the labelled Petri net, we extract the domain of the ACSetTransformation using dom.

```
si_lpn = dom(si_acst);
```


We can obtain a GraphViz representation of the labelled Petri net using to graphviz.

```
to_graphviz(si_lpn)
```



We repeat for the recovery (I to R) transition.

```
ir_uwd = @relation (I, R) where (I::Pop, R::Pop) begin
    recovery(I, R)
end
ir_acst = oapply_typed(epi_lpn, ir_uwd, [:])
ir_lpn = dom(ir_acst)
to_graphviz(ir_lpn)
```



To glue the SI and IR models together to make an SIR model, we first define an undirected wiring diagram which contains all our states, and two transitions.


```
sir_uwd = @relation (S, I, R) where (S::Pop, I::Pop, R::Pop) begin
    si(S, I)
    ir(I, R)
end;
```

We then create a StructuredMulticospan using this wiring diagram, telling oapply that si in the wiring diagram corresponds to the si_lpn labelled Petri net, etc.. Open converts a PetriNet to an OpenPetriNet where each state is exposed as a leg of the cospan, allowing it to be composed over an undirected wiring diagram.

```
sir_smc = oapply(sir_uwd, Dict(
    :si => Open(si_lpn),
    :ir => Open(ir_lpn),
));
```

We extract the labelled Petri net by extracting the object that is the codomain of all the legs, using the apex function.

```
sir_lpn = apex(sir_smc)
to_graphviz(sir_lpn)
```



Running the model

To run an ODE model from the labelled Petri net, we generate a function that can be passed to SciML's ODEProblem using vectorfield.

```
sir_vf = vectorfield(sir_lpn);
```

The initial conditions and parameter values are written as labelled arrays.

```
u0 = @LArray [990.0, 10.0, 0.0] Tuple(snames(sir_lpn))

3-element LArray{Float64, 1, Vector{Float64}, (:S, :I, :R)}:
    :S => 990.0
    :I => 10.0
    :R => 0.0

p = @LArray [0.5/1000, 0.25] Tuple(tnames(sir_lpn))

2-element LArray{Float64, 1, Vector{Float64}, (:, :)}:
    : => 0.0005
    : => 0.25

tspan = (0.0, 40.0);
```

We can now use the initial conditions, the time span, and the parameter values to simulate the system.

```
sir_prob = ODEProblem(sir_vf, u0, tspan, p)
sir_sol = solve(sir_prob, Rosenbrock32())
plot(sir_sol)
```

