
# Operating System Concepts

**Tenth Edition** 

Silberschatz, Galvin and Gagne

### Chapter 3

**Processes** 





### Chapter 3: Processes

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- Examples of IPC Systems
- Communication in Client-Server Systems





### Objectives

- To introduce the notion of a process a program in execution, which forms the basis of all computation
- To describe the various features of processes, including scheduling, creation and termination, and communication
- To explore interprocess communication using shared memory and message passing
- To describe communication in client-server systems





### Process Concept

- An operating system executes a variety of programs:
  - Batch system **jobs**
  - Time-shared systems user programs or tasks
- Textbook uses the terms *job* and *process* almost interchangeably
- **Process** a program in execution; process execution must progress in sequential fashion






### Process Concept 1

- Multiple parts
  - The program code, also called text section
  - Current activity including program counter, processor registers
  - Stack containing temporary data
    - Function parameters, return addresses, local variables
  - Data section containing global variables
  - Heap containing memory dynamically allocated during run time





## Process in Memory








#### Process State

- As a process executes, it changes **state** 
  - new: The process is being created
  - running: Instructions are being executed
  - waiting: The process is waiting for some event to occur
  - ready: The process is waiting to be assigned to a processor
  - terminated: The process has finished execution





### Diagram of Process State







### Process Control Block (PCB)

Information associated with each process (also called **task control block**)


- Process state running, waiting, etc.
- Program counter location of instruction to next execute
- CPU registers contents of all process-centric registers
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information memory allocated to the process
- Accounting information CPU used, clock time elapsed since start, time limits
- I/O status information I/O devices allocated to process, list of open files

process state process number program counter registers memory limits list of open files





#### **CPU Switch From Process to Process**







#### **Threads**

- So far, process has a single thread of execution
- Consider having multiple program counters per process
  - Multiple locations can execute at once
    - Multiple threads of control -> <u>threads</u>
- Must then have storage for thread details, <u>multiple</u> <u>program counters in PCB</u>
- See next chapter






#### Process Representation in Linux

Represented by the C structure task struct

```
pid t_pid; /* process identifier */
long state; /* state of the process */
unsigned int time_slice /* scheduling information */
struct task_struct *parent; /* this process's parent */
struct list_head children; /* this process's children */
struct files_struct *files; /* list of open files */
struct mm_struct *mm; /* address space of this process */
```








### **Process Scheduling**

- Maximize CPU use, quickly switch processes onto CPU for time sharing
- Process scheduler selects among available processes for next execution on CPU
- Maintains scheduling queues of processes
  - **Job queue** set of all processes in the system
  - Ready queue set of all processes residing in main memory, ready and waiting to execute
  - **Device queues** set of processes waiting for an I/O device
  - Processes migrate among the various queues






#### Ready Queue And Various I/O Device Queues





### Representation of Process Scheduling

• Queueing diagram represents queues, resources, flows







#### Schedulers


- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU
  - Sometimes the only scheduler in a system
  - Short-term scheduler is invoked frequently (milliseconds)  $\Rightarrow$  (must be fast)
- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
  - Long-term scheduler is invoked infrequently (seconds, minutes) ⇒ (may be slow)
  - The long-term scheduler controls the **degree of multiprogramming**
- Processes can be described as either:
  - <u>I/O-bound process</u> spends more time doing I/O than computations, many short CPU bursts
  - <u>CPU-bound process</u> spends more time doing computations; few very long CPU bursts
- Long-term scheduler strives for good *process mix*





### Addition of Medium Term Scheduling

- Medium-term scheduler can be added if degree of multiple programming needs to decrease
  - Remove process from memory, store on disk, bring back in from disk to continue execution: **swapping**







### Multitasking in Mobile Systems

- Some mobile systems (e.g., early version of iOS) allow only one process to run, others suspended
- Due to screen real estate, user interface limits iOS provides for a
  - Single foreground process- controlled via user interface
  - <u>Multiple background processes</u>— in memory, running, but not on the display, and with limits
  - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
  - Background process uses a **service** to perform tasks
  - Service can keep running even if background process is suspended
  - Service has no user interface, small memory use





#### Context Switch

- When CPU <u>switches to another process</u>, the system must <u>save the</u>

  <u>state of the old process</u> and <u>load the saved state for the new process</u>

  via a <u>context switch</u>
- Context of a process represented in the PCB
- Context-switch time is <u>overhead</u>; the system does no useful work while switching
  - The more complex the OS and the PCB  $\rightarrow$  the longer the context switch
- Time dependent on hardware support
  - Some hardware provides multiple sets of registers per CPU → multiple contexts loaded at once





### Operations on Processes

- System must provide mechanisms for:
  - process creation,
  - process termination,
  - and so on as detailed next






#### Process Creation

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a <u>process identifier</u>
   (pid)
- Resource sharing options
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution options
  - Parent and children execute concurrently
  - Parent waits until children terminate






#### A Tree of Processes in Linux





#### Process Creation 2

- Address space
  - Child duplicate of parent
  - Child has a program loaded into it
- UNIX examples
  - **fork()** system call creates new process
  - <u>exec()</u> system call used after a **fork()** to replace the process' memory space with a new program







### C Program Forking Separate Process

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid_t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
   else if (pid == 0) { /* child process */
      execlp("/bin/ls", "ls", NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait (NULL);
      printf("Child Complete");
   return 0;
```





#### Creating a Separate Process via Windows API

```
#include <stdio.h>
#include <windows.h>
int main(VOID)
STARTUPINFO si;
PROCESS_INFORMATION pi;
   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));
   /* create child process */
   if (!CreateProcess(NULL, /* use command line */
    "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE, /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
    &si,
    &pi))
      fprintf(stderr, "Create Process Failed");
      return -1;
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");
   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
```





#### Process Termination 1

- Process executes last statement and then asks the operating system to delete it using the exit() system call.
  - Returns status data from child to parent (via wait())
  - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the abort() system call. Some reasons for doing so:
  - Child has exceeded allocated resources
  - Task assigned to child is no longer required
  - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates





#### Process Termination 2

- Some operating systems do not allow child to exists if its parent has terminated. If a process terminates, then all its children must also be terminated.
  - cascading termination. All children, grandchildren, etc. are terminated.
  - The termination is initiated by the operating system.
- The parent process may wait for termination of a child process by using the wait() system call. The call returns status information and the pid of the terminated process

```
pid = wait(&status);
```

- If no parent waiting (did not invoke wait ()) process is a zombie
- If parent terminated without invoking wait, process is an orphan





#### Multiprocess Architecture – Chrome Browser

- Many web browsers ran as single process (some still do)
  - If one web site causes trouble, entire browser can hang or crash
- Google Chrome Browser is multiprocess with 3 different types of processes:
  - **Browser** process manages user interface, disk and network I/O
  - Renderer process renders web pages, deals with HTML, Javascript. A new renderer created for each website opened
    - Runs in **sandbox** restricting disk and network I/O, minimizing effect of security exploits
  - Plug-in process for each type of plug-in







### Interprocess Communication


- Processes within a system may be <u>independent</u> or <u>cooperating</u>
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing
  - Computation speedup
  - Modularity
  - Convenience
- Cooperating processes need <u>interprocess communication</u> (IPC)
- Two models of IPC
  - Shared memory
  - Message passing





#### Communications Models

(a) Message passing. (b) shared memory.





#### Producer-Consumer Problem

- Paradigm for cooperating processes, *producer* process produces information that is consumed by a *consumer* process
  - <u>unbounded-buffer</u> places no practical limit on the size of the buffer
  - **bounded-buffer** assumes that there is a fixed buffer size





#### Bounded-Buffer – Shared-Memory Solution

Shared data

```
#define BUFFER_SIZE 10
typedef struct {
    . . .
} item;
item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```

• Solution is correct, but can only use <u>BUFFER\_SIZE-1</u> elements





#### Bounded-Buffer – Producer

```
item next_produced;
while (true) {
    /* produce an item in next produced */
    while (((in + 1) % BUFFER_SIZE) == out)
        ; /* do nothing */
    buffer[in] = next_produced;
    in = (in + 1) % BUFFER_SIZE;
}
```





#### Bounded Buffer – Consumer

```
item next_consumed;
while (true) {
    while (in == out)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;

    /* consume the item in next consumed */
}
```





#### Interprocess Communication – Shared Memory

- An area of <u>memory shared among the processes</u> that wish to communicate
- The communication is <u>under the control of the users</u> <u>processes not the operating system.</u>
- Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.
- Synchronization is discussed in great details in Chapters 6 and 7.





### Examples of IPC Systems – POSIX

- POSIX Shared Memory
  - Process first creates shared memory segment
     shm\_fd = shm\_open(name, O CREAT | O RDWR, 0666);
  - Also used to open an existing segment to share it
  - Set the size of the object ftruncate(shm fd, 4096);
  - Now the process could write to the shared memory sprintf(shared memory, "Writing to shared memory");





### IPC POSIX Producer

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";
/* shared memory file descriptor */
int shm fd;
/* pointer to shared memory obect */
void *ptr;
   /* create the shared memory object */
   shm_fd = shm_open(name, O_CREAT | O_RDWR, 0666);
   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);
   /* write to the shared memory object */
   sprintf(ptr, "%s", message_0);
   ptr += strlen(message_0);
   sprintf(ptr, "%s", message_1);
   ptr += strlen(message_1);
   return 0;
```





#### IPC POSIX Consumer

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm fd;
/* pointer to shared memory obect */
void *ptr;
   /* open the shared memory object */
   shm_fd = shm_open(name, O_RDONLY, 0666);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);
   /* read from the shared memory object */
   printf("%s",(char *)ptr);
   /* remove the shared memory object */
   shm_unlink(name);
   return 0;
```





### Interprocess Communication – Message Passing

- Mechanism for processes to communicate and to synchronize their actions
- Message system processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - <u>send</u>(message)
  - receive(message)
- The *message* size is either <u>fixed or variable</u>





## Message Passing

- If processes P and Q wish to communicate, they need to:
  - Establish a *communication link* between them
  - Exchange messages via send/receive
- Implementation issues:
  - How are links established?
  - Can a link be associated with more than two processes?
  - How many links can there be between every pair of communicating processes?
  - What is the capacity of a link?
  - Is the size of a message that the link can accommodate fixed or variable?
  - Is a link unidirectional or bi-directional?





# Message Passing 2

- Implementation of communication link
  - Physical:
    - Shared memory
    - Hardware bus
    - Network
  - <u>Logical</u>:
    - Direct or indirect
    - Synchronous or asynchronous
    - Automatic or explicit buffering





#### **Direct Communication**

- Processes must name each other explicitly:
  - <u>send (P, message)</u> send a message to process P
  - receive(Q, message) receive a message from process Q
- Properties of communication link
  - Links are <u>established automatically</u>
  - A link is <u>associated with exactly one pair</u> of communicating processes
  - Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional





#### Indirect Communication

- <u>Messages are directed and received from mailboxes</u> (also referred to as ports)
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established <u>only if processes share a common mailbox</u>
  - A link may be <u>associated with many processes</u>
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional





#### Indirect Communication 2

- Operations
  - <u>create</u> a new mailbox (port)
  - send and receive messages through mailbox
  - <u>destroy</u> a mailbox
- Primitives are defined as:

**send**(*A*, *message*) – send a message to mailbox A **receive**(*A*, *message*) – receive a message from mailbox A





### Indirect Communication 3

- Mailbox sharing
  - $P_1$ ,  $P_2$ , and  $P_3$  share mailbox A
  - $P_1$ , sends;  $P_2$  and  $P_3$  receive
  - Who gets the message?
- Solutions
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation
  - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.





# Synchronization 1

- Message passing may be either blocking or non-blocking
- Blocking is considered synchronous
  - **Blocking send** -- the sender is blocked until the message is received
  - Blocking receive -- the receiver is blocked until a message is available
- Non-blocking is considered asynchronous
  - Non-blocking send -- the sender sends the message and continue
  - **Non-blocking receive** -- the receiver receives:
    - A valid message, or
    - Null message
- Different combinations possible
  - If both send and receive are blocking, we have a **rendezvous**





## Synchronization 2

Producer-consumer becomes trivial

```
message next produced;
while (true) {
      /* produce an item in next produced */
      send(next produced);
message next consumed;
while (true) {
      receive (next consumed);
      /* consume the item in next consumed */
```



# Buffering

- Queue of messages attached to the link.
- implemented in one of three ways
  - 1. Zero capacity no messages are queued on a link. Sender must wait for receiver (rendezvous)
  - 2. Bounded capacity finite length of *n* messages Sender must wait if link full
  - 3. Unbounded capacity infinite length Sender never waits





### Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls
- Pipes
- Remote Method Invocation (Java)





### Multiple-Choice Question

- Which of the following contains dynamically allocated data during program run time?
  - A) text section
  - B) data section
  - C) heap section
  - D) stack section





### Multiple-Choice Question 2

- Which of the following process state will be switched from "running" state when an I/O event occurs?
  - A) ready
  - B) terminated
  - C) waiting
  - D) new





### Multiple-Choice Question 3

- Which of the following cases could force a process removed from the CPU?
  - A) I/O request
  - B) fork a child
  - C) interrupt or time slice expired
  - D) all of the above



## **Essay Questions**

- Name and describe the different states that a process can exist in at any given time.
- Ordinarily the exec() system call follows the fork(). Explain what would happen if a programmer were to inadvertently place the call to exec() before the call to fork().
- Explain why Google Chrome uses multiple processes.