CS 110 Computer Architecture

An Introduction to Operating Systems

Instructors:


Chundong Wang & Siting Liu

https://toast-lab.sist.shanghaitech.edu.cn/courses/CS110@ShanghaiTech/Spring-2023/index.html

School of Information Science and Technology SIST


ShanghaiTech University

Slides based on UC Berkeley's CS61C




So how is this any different?





Raspberry Pi



It's a real computer!




But wait...

- That's not the same! Our CS 110 experience isn't like the real world. When we run VENUS, it only executes one program and then stops.
- When I switch on my computer, I get this:



Yes, but that's just software! The Operating System (OS)

Well, "just software"



What does the OS do?

- One of the first things that runs when your computer starts (right after firmware/ bootloader)
- Loads, runs and manages programs:
 - Multiple programs at the same time (time-sharing)
 - Isolate programs from each other (isolation)
 - Multiplex resources between applications (e.g., devices)
- Services: File System, Network stack, printer, etc.
- Finds and controls all the devices in the machine in a general way (using "device drivers")

What does the core of OS need to do?

- Provide interaction with the outside world
 - Interact with "devices"
 - Disk, screen, keyboard, mouse, network, etc.
- Provide isolation between running programs (processes)
 - Each program runs in its own little world
 - Virtual memory

Agenda


- OS Boot Sequence and Operation
- Devices and I/O, interrupt and traps
- Application, Multiprogramming/time-sharing

Agenda

- OS Boot Sequence and Operation
- Devices and I/O, interrupt and traps
- Application, Multiprogramming/time-sharing

What happens at boot?

 When the computer switches on, it does the same as Venus: the CPU executes instructions from some start address (stored in Flash ROM)




• Bootstrapping:

https://en.wikipedia.org/wiki/Bootstrapping


What happens at boot?

 When the computer switches on, it does the same as Venus: the CPU executes instructions from some start address (stored in Flash ROM)

1. BIOS: Find a storage device and load first sector (block of data)



2. Bootloader (stored on, e.g., disk): Load the OS *kernel* from disk into a location in memory and jump into it.




The state of the

4. Init: Launch an application that waits for input in loop (e.g., Terminal/Desktop/...

UEFI

Unified Extensible Firmware Interface

- Successor of BIOS
- Much more powerful and complex
- E.g. graphics menu; networking; browsers
- All modern Intel & AMD based computer use UEFI



Agenda

- OS Boot Sequence and Operation
- Devices and I/O, interrupt and traps
- Application, Multiprogramming/time-sharing

How to interact with devices?


Assume a program running on a CPU. How does it interact with the outside world?
 Operating System

 Need I/O interface for Keyboards, Network, Mouse, Screen, etc.

Connect to many types of devices

 Control these devices, respond to them, and transfer data

Present them to user programs so they are useful




cntrl reg.

Instruction Set Architecture for I/O

- What must the processor do for I/O?
 - Input: reads a sequence of bytes
 - Output: writes a sequence of bytes
- Interface options
 - Some processors have special input/output instructions
 - Memory Mapped Input/Output (used by RISC-V):
 - Use normal load/store instructions, e.g., lw/sw, for input/output
 - In small pieces
 - A portion of the address space dedicated to IO
 - I/O device registers there (no memory there)

Memory Mapped I/O

- Certain addresses are not regular memory
- Instead, they correspond to registers in I/O devices



Processor-I/O Speed Mismatch

- 1GHz microprocessor can execute 1 billion load or store instructions per second, or 4,000,000 KB/s data rate
 - I/O data rates range from 0.01 KB/s to 1,250,000 KB/s
- Input: device may not be ready to send data as fast as the processor loads it
 - Also, might be waiting for human to act
- Output: device not be ready to accept data as fast as processor stores it
- What to do?

Processor Checks Status before Acting

- Path to a device generally has 2 registers:
 - Control Register, says it's OK to read/write (I/O ready) [think of a flagman on a road]
 - Data Register, contains data
- Processor reads from Control Register in loop, waiting for device to set Ready bit in Control reg (0 => 1) to say it's OK
- Processor then loads from (input) or writes to (output) data register
 - Load from or Store into Data Register resets Ready bit (1 => 0) of Control Register
- This is called "Polling"

I/O Example (polling)

Input: Read from keyboard into a0

```
li t0, 0xffff00000 #ffff00000

Waitloop:

lw t1, 0(t0) #control

andi t1, t1,0x1

beq t1, zero, Waitloop

lw a0, 4(t0) #data
```

Output: Write to display from a0

```
li t0, 0xffff0000 #ffff0000

Waitloop:

lw t1, 8(t0) #control

andi t1, t1,0x1

beq t1, zero, Waitloop

sw a0, 12(t0) #data
```

"Ready" bit is from processor's point of view!

Cost of Polling?

- Assume for a processor with a 1GHz clock it takes 400 clock cycles for a polling operation (call polling routine, accessing the device, and returning).
 Determine % of processor time for polling
 - Mouse: polled 30 times/sec so as not to miss user movement

% Processor time to poll

- Mouse Polling [clocks/sec]
 - = 30 [polls/s] * 400 [clocks/poll] = 12K [clocks/s]
- % Processor for polling:

```
12*10^3 [clocks/s] / 1*10^9 [clocks/s] = 0.0012%
```

=> Polling mouse little impact on processor

What is the alternative to polling?

- Wasteful to have processor spend most of its time "spin-waiting" for I/O to be ready
- Would like an unplanned procedure call that would be invoked only when I/O device is ready
- Solution: use exception mechanism to help I/O.
 - Interrupt program when I/O ready, return when done with data transfer
- Allow to register (post) interrupt handlers: functions that are called when an interrupt is triggered

Interrupt-driven I/O

Incoming interrupt suspends instruction stream Handler Execution Looks up the vector (function address) of a handler in an interrupt vector table stored within the CPU Perform a jal to the handler (needs to store any state) Stack Frame Handler run on current stack and returns on finish (thread doesn't notice that a handler was run) li t0, 0xffff0000 Stack Frame handler: t1, 0(t0)andi t1, t1,0 \times 1 a0, 4(t0)t1, 8(t0)Stack Frame ret Label: sll t1,s3,2 addu t1, t1, s5 t1,0(t1)lw **CPU Interrupt Table** s1, s1, t1 add addu s3, s3, s4 Interrupt(SPIO) handler SPI0 s3,s2,abel bne • • •


Terminology

In CA (you'll see other definitions in use elsewhere):

- <u>Interrupt</u> caused by an event *external* to current running program (e.g. key press, mouse activity)
 - Asynchronous to current program, can handle interrupt on any convenient instruction
- <u>Exception</u> caused by some event during execution of one instruction of current running program (e.g., page fault, bus error, illegal instruction)
 - Synchronous, must handle exception on instruction that causes exception
- <u>Trap</u> action of servicing interrupt or exception by hardware jump to "trap handler" code

Traps/Interrupts/Exceptions

altering the normal flow of control




An external or internal event that needs to be processed - by another program - the OS. The event is often unexpected from original program's point of view.

Precise Traps

Supervisor exception program counter


- Trap handler's view of machine state is that every instruction prior to the trapped one has completed, and no instruction after the trap has executed.
- Implies that handler can return from an interrupt by restoring user registers and jumping back to interrupted instruction (SEPC register will hold the instruction address)
 - Interrupt handler software doesn't need to understand the pipeline of the machine, or what program was doing!
 - More complex to handle trap caused by an exception than interrupt
- Providing precise traps is tricky in a pipelined superscalar out-of-order processor!
 - But handling imprecise interrupts in software is even worse.

Trap Handling in 5-Stage Pipeline



- How to handle multiple simultaneous exceptions in different pipeline stages?
- How and where to handle external asynchronous interrupts?

Save Exceptions Until Commit



Handling Traps in In-Order Pipeline

- Hold exception flags in pipeline until commit point (M stage)
- Exceptions in earlier instructions override exceptions in later instructions
- Exceptions in earlier pipe stages override later exceptions for a given instruction
- Inject external interrupts at commit point
- If exception/interrupt at commit: update Cause and SEPC registers, kill all stages, inject handler PC into fetch stage

Trap Pipeline Diagram

Agenda

- OS Boot Sequence and Operation
- Devices and I/O, interrupt and trap
- Application, Multiprogramming/time-sharing

Launching Applications

- Applications are called "processes" in most OSs.
 - Process: separate memory space;
 - Thread: shared memory space.
- Created by another process calling into an OS routine (using a "syscall", more details later).
 - Depends on OS, but Linux uses fork to create a new process, and execve to load application.
- Loads executable file from disk (using the file system service) and puts instructions & data into memory (.text, .data sections), prepare stack and heap.
- Set argc and argv, jump into the main function.

Supervisor Mode

- If something goes wrong in an application, it could crash the entire machine.
 - And what about malware, etc.?
- The OS may need to enforce resource constraints to applications (e.g., access to devices).
- To help protect the OS from the application, CPUs have a supervisor mode bit.
 - When not in supervisor mode (user mode), a process can only access a subset of instructions and (physical) memory.
 - Process can enter the supervisor mode by using an interrupt, and change out of supervisor mode using a special instruction.

Syscalls

- What if we want to call into an OS routine? (e.g., to read a file, launch a new process, send data, etc.)
 - Need to perform a syscall: set up function arguments in registers, and then raise software interrupt
 - OS will perform the operation and return to user mode
- This way, the OS can mediate access to all resources, including devices and the CPU itself.

Multiprogramming

- The OS runs multiple applications at the same time.
- But not really (unless you have a core per process)
 - Time-sharing processor
- When jumping into process, set timer interrupt.
 - When it expires, store PC, registers, etc. (process state).
 - Pick a different process to run and load its state.
 - Set timer, change to user mode, jump to the new PC.
- Switches between processes very quickly. This is called a "context switch".
- Deciding what process to run is called scheduling.

Protection, Translation, Paging

- Supervisor mode does not fully isolate applications from each other or from the OS.
 - Application could overwrite another application's memory.
 - Also, may want to address more memory than we actually have (e.g., for sparse data structures).
- Solution: Virtual Memory. Gives each process the illusion of a full memory address space that it has completely for itself.

In Conclusion

- Once we have a basic machine, it's mostly up to the OS to use it and define application interfaces.
- Hardware helps by providing the right abstractions and features (e.g., Virtual Memory, I/O).