Section 2: Electromagnetics AE435

AE435 Spring 2018

In this section, we will review the basics of charge, electricity, magnetism, and Maxwell equations.

2 Electrostatics with Dielectric Media

Contents

| 2 | 2 Electrostatics with Dielectric Media | | 11 |
|---|--|---|----|
| | 2.1 | Polarization | 12 |
| | 2.2 | Surface and Volume Charge Density | 15 |
| | 2.3 | Gauss' Law for Dielectrics | 17 |
| | 2.4 | Susceptibility, Permittivity, & Dielectric Constant | 19 |
| | 2.5 | Boundary Conditions at Interfaces | 23 |
| | 2.6 | Poisson & Laplace's Eqns. for Dielectrics | 24 |

2.1 Polarization

Many molecules have a positive end and a negative end.

Water, H₂O, for example is a "polar molecule".

Figure 4

Oxygen gets slightly more than its share of the electron cloud while hydrogen gets less.

Water is an example of a "polar molecule". It is always polarized, even without any electric field present. But even non-polar atoms/molecules can become polarized in an electric field. Polarized, meaning a redistribution of the electron cloud creating an asymmetric charge distribution that aligns with the electric field.

We model this by thinking of each polarized atom/molecule as a dipole.

Polarization (how skewed the electron cloud is) depends on \vec{E} . However, part of \vec{E} is produced by polarization. In addition, the redistribution of charge in a dielectric (insulator) can affect the external charge distribution, which changes \vec{E} . In short, we have a non-linear system!

A dipole is two equal and opposite charges, $\pm q$, separated by small distance, \vec{l} .

Figure 6

We start by defining the dipole potential field.

Dipole Potential Field

$$\phi(\vec{r}) = \frac{q}{4\pi\epsilon_0} \frac{(\vec{r} - \vec{r}')}{|\vec{r} - \vec{r}'|^3} \cdot \vec{l}$$
 (23)

Note: We ignore the higher order terms in \vec{l} .

This equation is exact for a point dipole, where $|\vec{l}| \to 0$ as $q \to 0$. All nonlinear terms vanish for a point dipole, which has no net charge or spatial extent, and has a constant dipole moment.

$$\vec{p} = \lim_{l \to 0} q \vec{l} = \text{constant} \tag{24}$$

For dielectric media, we can generalize this to

$$\Delta \vec{p} = \int_{V} \vec{r} \, \mathrm{d}q$$

which is the dipole moment of charge distribution in a small volume.

Usually, it is more convenient to work with the dipole moment per unit volume

Polarization of the Dielectric

$$\vec{P} = \lim_{\Delta V \to 0} \frac{\Delta \vec{p}}{\Delta V} \tag{25}$$

This is a point property, $\overrightarrow{P}(\overrightarrow{r})$ unit [C/m3], called the Polarization of the dielectric. It's a vector with direction defined by charge separation.

Figure 7

Another way to think of this is through physical molecules, rather than just point dipoles:

$$\overrightarrow{p_m}$$
 = Polarization of a Molecule
$$\overrightarrow{P} = N\overrightarrow{p_m} \quad \left[\frac{\#}{m^3}\right]$$
 (26)

where N is the number density of molecules in a dielectric.

2.2 Surface and Volume Charge Density

Charge displacement due to induced dipoles results in a net surface charge density

Net Surface Charge Density

$$\sigma_p = \vec{P} \cdot \hat{n} \qquad \left[\frac{c}{m^2} \right] \tag{27}$$

and a net volume charge density.

Net Volume Charge Density

$$\rho_p = -\nabla \cdot \vec{P} \qquad \left[\frac{c}{m^3}\right] \tag{28}$$

The rest of this section will be spend proving Equation 27 and Equation 28.

Consider the boundary of a dielectric shown below. Assume all positive charges in the slab move a displacement vector \overrightarrow{S} in response to an applied electric field, \overrightarrow{E} , and that negative charges are stationary.

We find that the differential volume defined by displacement \vec{S} and projected area $d\vec{A} = \hat{n} d\vec{A}$ is:

$$dV = \vec{s} \cdot d\vec{A}$$

If N is the number of positive charges per unit volume in the medium, the charge crossing $d\vec{A}$ is:

$$dq = Nq\vec{s} \cdot d\vec{A}$$

Recall polarization per molecule (Equation 24) $\overrightarrow{p_m} = q \overrightarrow{s}$

And polarization per unit volume (Equation 26) $\overrightarrow{P} = N \overrightarrow{p_m}$

So charge crossing $d\vec{A}$,

$$dq = \vec{P} \cdot d\vec{A}$$

Then the **Net Surface Charge** is the charge per unit area:

$$\frac{\mathrm{d}q}{\mathrm{d}A} = \sigma_p = \vec{P} \cdot \hat{n} \tag{29}$$

So whenever \overrightarrow{P} and \hat{n} are in the same direction, we get a net positive (+) surface charge. Whenever \overrightarrow{P} and \hat{n} are in the opposite direction, we get a net negative (-) surface charge.

Similar for Volume Charge Density

Again, the charge flow out of any surface dA with normal \hat{n} is:

$$dq = \vec{P} \cdot d\vec{A} = \vec{P} \cdot \hat{n} \, dA$$

So the net flow out of a differential volume equals the total flux integrated over the surface,

$$\int_{S} \vec{P} \cdot d\vec{A} = \int_{S} \frac{dq}{dA} dA$$

No charge is created or destroyed, so the differential loss of charge within dV is:

$$-\int_{S} dq = \int_{V} \rho_{p} dV = -\int_{S} \vec{P} \cdot d\vec{A} = -\int_{V} \nabla \cdot \vec{P} dV$$

Thus, similar to Gauss' Law, you get a differential form valid for any arbitrary volume.

Then the **Net Volume Charge** is the charge per unit volume:

$$\rho_p = -\nabla \cdot \vec{P} \tag{30}$$

So, a negative gradient in polarization creates a positive volumetric charge. Meanwhile, a positive gradient in polarization creates a negative volumetric charge.

2.3 Gauss' Law for Dielectrics

Starting with the free-space Gauss's law, we add dielectric charges

Gauss' Law with Dielectric Charges

$$\oint_{S} \vec{E} \cdot d\vec{A} = \int_{V} \nabla \cdot \vec{E} \, dV = \frac{\sum q}{\epsilon_{0}} = \frac{1}{\epsilon_{0}} \int_{V} (\rho_{f} + \rho_{p}) \, dV$$
(31)

Where:

 ρ_f = volume charge density of free charges

 ρ_p = volume charge density of charge due to dielectric polarization

The differential form is then (compare with 2.13):

$$\nabla \cdot \vec{E} = \frac{1}{\epsilon_0} \left(\rho_f + \rho_p \right) \tag{32}$$

Total electric field is due to free charges AND polarization "charges".

E is due to ALL charges, but usually don't care about, ρ_p .

What we'd like is an equation in terms of free charge as a source term. Recall (2.30), so that

$$\rho_p = -\nabla \cdot \vec{P}$$

$$\nabla \cdot \overrightarrow{E} = \frac{1}{\epsilon_0} \left(\rho_f - \nabla \cdot \overrightarrow{P} \right)$$

Then:

$$\nabla \cdot \left(\epsilon_0 \vec{E} + \vec{P} \right) = \rho_f \tag{33}$$

Define Electric Displacement

$$\vec{D} = \epsilon_0 \vec{E} + \vec{P} \tag{34}$$

The above equation (2.33) becomes:

$$\nabla \cdot \vec{D} = \rho_f \tag{35}$$

Which is the most common form of Poisson's equation seen in Maxwell equations.

Free charge is the source of displacement . In integral form,

$$\oint_{S} \vec{D} \cdot d\vec{A} = \int_{V} \rho_{f} dV \tag{36}$$

In contrast, total charge is the source of the Electric Field.

$$\left(
ho _{f}+
ho _{p}
ight)$$

2.4 Susceptibility, Permittivity, & Dielectric Constant

Material properties are characterized by constitutive relations (a relationship between two physical quantities that is specific to a material). For isotropic materials,

Equation Name

$$\vec{P} = \chi(E) \, \vec{E} \tag{37}$$

Where:

 $\chi = \text{Electrical Susceptibility of the Material}$

Can define permittivity as:

$$\epsilon(E) = \epsilon_0 + \chi(E) \tag{38}$$

So that

$$\vec{D} = \epsilon(E) \vec{E} \tag{39}$$

More generally, for time-varying fields, permittivity is a function of both the wave number and frequency.

$$\vec{D}(\vec{K}, w) = \epsilon(\vec{K}, w) \vec{E}(\vec{K}, w)$$

Often χ and ϵ are independent of \vec{E} , these materials are called linear dielectrics.

$$\vec{P} = \chi \vec{E} \tag{40}$$

$$\vec{D} = \epsilon \vec{E}$$

For these, can also specify material's electrical behavior by dielectric constant.

$$\epsilon = K \,\epsilon_0 \tag{41}$$

So

Relative Permitivity
$$\epsilon_r = K = \frac{\epsilon}{\epsilon_0} = 1 + \frac{\chi}{\epsilon_0} \eqno(42)$$

Most materials have a defined dielectric constant and strength. The table below list a few example materials.

Note 1. The dielectric constant, K, is ≈ 1 for most gasses.

| | Dielectric Constant | Dielectric Strength |
|-----------------------------|---------------------|---|
| Material | K | $\mathrm{E}_{\mathrm{max}}\left[\frac{V}{m}\right]$ |
| Al ₂ O (Alumina) | 4.5 | 6×10^{6} |
| Glass | 5-10 | 9×10^{6} |
| Nylon | 3.5 | 19×10^{6} |
| Ethanol (0° C) | 28.4 | - |
| $H_2O (0^{\circ} C)$ | 87.8 | - |
| Air, 1atm | 1.00059 | 3×10^{6} |
| CO ₂ , 1atm | 1.000985 | - |
| BN (Boron Nitride) | 4.3 | 2.4×10^{6} |

To analyze problems involving dielectrics, you need:

- 1. Boundary Conditions
- 2. Governing Equations

We found that the field of a polarized object is identival to the field produced by a distribution of "bound charges" or as we call it, "polarization" charges, ρ_p , σ_p such that

$$\sigma_p = \vec{P} \cdot \hat{n}$$

$$\rho_p = -\nabla \cdot \vec{P}$$

Where \overrightarrow{P} is the dipole moment per unit volume. "Dipole" refers to the separation of positive and negative charges.

The strength of the polarization, (or how polarized a molecule is) is called the "Dipole Moment". It is expressed such that...

$$p = q d$$

Where:

q = Amount of charge

d = Displaced distance

 \overrightarrow{P} is the sum of dipole moments of all atoms/molecules

$$\vec{P} = N \vec{p_m}$$

Polarization of a material results in "bound" or "polarization" charges.

Figure 9

Figure 9 shows that:

- A net charge at the end, at the surface, this is "bound" charge or as we will refer to it, "Polarization" charge. This is σ_p .
- ρ_p comes about due to $\nabla \cdot \vec{P}$, for example, in an inhomogeneous material. This \vec{P} field shows us that polarization is dependent on the material.

$$\overrightarrow{P}=\chi(E)\,\overrightarrow{E}$$

Electric Displacement,
$$\vec{D} = \epsilon_0 \vec{E} + \vec{P}$$
 and $\nabla \cdot \vec{D} = \rho_f$

Which is a useful way to express Gauss' law since it only depends on free charge, ρ_f . Often times, we don't care about "polarization" charges (we don't care about what is going on inside the material). Typically, we know ρ_f but we don't know ρ_p

Example: A wire carrying line charge $\lambda\left[\frac{c}{m}\right]$ is surrounded by an insulator with radius, a. Determine the Electric Displacement, \overrightarrow{D} .

Figure 10

All we need to calculate \overrightarrow{D} is the free charge. The free charge is in the wire and we also have some polarization charge in the insulator. A cylindrical surface with length, L, and radius, S. Using Gauss' Law in integral form, we get...

$$\oint_{S} \vec{D} \cdot d\vec{A} = \int_{V} \rho_{f} dV \quad \Rightarrow \quad D(2 \pi s L) = \lambda L$$

Solving for D and then including the radial direction vector, \hat{s} , we get

$$\vec{D} = \frac{\lambda}{2\pi s} \,\hat{s}$$

which is true inside and outside of the insulator.

Now let's say we have a free charge moving around outside the surface. What is the force acting on that charge. Now we need to know the electric field.

$$\vec{F}_q = q \vec{E}$$

From Equation 34 which states $\vec{D} = \epsilon_0 \vec{E} + \vec{P}$ and since we are outside the insulator (s > a) meaning $\vec{P} = 0$ therefore...

$$\vec{E} = \frac{1}{\epsilon_0} \vec{D} = \frac{\lambda}{2 \pi \epsilon_0 s} \hat{s}$$

Finally, what is the electric field inside the insulator. Normally, this is not needed but there is a chance that the electric field is so strong that it breaks the insulator. In this situation we must know \vec{P} since it is no longer equal to zero. As a result, we must know the susceptibility of the insulator, χ which is dependent on the material (Equation 27).

2.5 Boundary Conditions at Interfaces

Consider a generalized surface with external surface charge density, σ_e . This does NOT include polarization charge, σ_p .

Figure 11

Where

 $\overrightarrow{D}_1=$ The Electric Displacement just below the surface

 \overrightarrow{D}_2 = The Electric Displacement just above the surface

Note that \overrightarrow{D}_2 changes only because of the effect of the external electric field. The change is related to the charge on the surface.

From the figure, it can be shown that...

The difference in the vertical components of the Electric Displacement above and below the generalized surface is equal to the external surface charge density.

$$(D_{\perp})_1 - (D_{\perp})_2 = \sigma_e \tag{43}$$

The perpendicular component of Electric Displacement changes proportional to σ

If we apply Gauss' law to a small volume slightly above and slightly below the surface and then loot at the field around the surface, we can derive Equation 44.

The horizontal components of Electric Displacement above and below the generalized surface are equal. Since we did not include Polarization, \vec{P} , our equation for electric displacement, $\vec{D} = \epsilon_0 \vec{E} + \vec{P}$, becomes $\vec{D} = \epsilon_0 \vec{E}$ and so...

$$\left(E_{\parallel}\right)_{1} = \left(E_{\parallel}\right)_{2} \tag{44}$$

The parallel components of the Electric Field, \vec{E} , do not change above and below the surface.

2.6 Poisson & Laplace's Eqns. for Dielectrics

When we include dielectric media, the divergence equation is: (Derived earlier in Equation 35)

$$\nabla \cdot \vec{D} = \rho_f \tag{45}$$

where ρ_f is the volume density of free charges, and the displacement is

$$\vec{D} = \epsilon \, \vec{E} \tag{46}$$

So, in dielectric media, the divergence of the electric field is given by:

$$\nabla \cdot \vec{E} = \frac{\rho_f}{\epsilon} \tag{47}$$

Which is just what we had for Gauss' Law except now it includes dielectrics. But we still have electrostatic fields, so can put in terms of scalar potential as:

$$\nabla^2 \phi = -\frac{\rho_f}{\epsilon} \tag{48}$$

which is Poisson's Equation for dielectrics.

In most cases, there is no free charge distributed through the dielectric, it concentrates either on the surface or (more rarely) concentrates in clumps within the dielectric. As a result, you can usually use Laplace's Equation for Dielectrics

$$\nabla^2 \phi = 0 \tag{49}$$

in the body of a dielectric.