# A pre\_main function that runs before static initialization that precedes main

Document #: D9999 Date: 2014-12-10

Project: Programming Language C++

Evolution Working Group

Reply-to: Daniel Gutson

<daniel.gutson@tallertechnologies.com>

Christopher Kormanyos <e\_float@yahoo.com>

#### 1 Motivation

#### Overview

Many systems require user-specific initialization. In particular, deeply embedded environments may have user-specific initialization that should be executed as soon as possible following power-on-reset of the microcontroller. Examples thereof include initialization of I/O ports, watchdog timers, clock systems, *etc.* For these environments, postponing user-specific initialization until main may detract from quality of design.

## 2 Proposed Solution

This document proposes changes in the standard text reflecting the specification of a new pre\_main function that is called prior to static initialization that precedes main.

#### Modification to the standard text

#### 1. [basic.start.main] Add a new paragraph §3.6.1p6

The pre\_main function shall be called prior to *static initialization* (§3.6.2) that precedes main. The linkage (3.5) of pre\_main is implementation-defined. The pre\_main function is parameter-free. The return value of pre\_main is void. The pre\_main function lacks side-effects. The mechanism ensuring that pre\_main lacks side-effects is implementation-defined.

### 3 Existing mechanisms and workarounds

We will now investigate existing mechanisms and workarounds that implement a pre\_main-style mechanism.

#### Custom startup code

Many embedded systems developers write custom startup code that supports a kind of pre\_main function. For example, we will now look at sample startup code that shows how an implementation could potentially provide a call mechanism for pre\_main.

```
void __my_startup()
  // Load the sreg register.
  asm volatile("eor r1, r1");
  asm volatile("out 0x3F, r1");
  // Set the stack pointer.
  asm volatile("ldi r28, lo8(__initial_stack_pointer)");
  asm volatile("ldi r29, hi8(__initial_stack_pointer)");
  // Load the stack pointer high and low registers.
  asm volatile("out 0x3E, r29");
  asm volatile ("out 0x3D, r28");
  // A potential call mechanism for pre_main.
  pre_main();
  // Initialize statics from ROM to RAM.
  // Initialize default-initialized static RAM.
  crt::init_ram();
  // Call all ctor initializations.
  crt::init_ctors();
  // Call main (and never return).
  asm volatile("call main");
  // Catch an unexpected return from main.
  for(;;)
    // Replace with a loud error if desired.
    mcal::wdg::secure::trigger();
}
```

This example has been taken from a low-level initialization sequence for a popular 8-bit microcontroller. The code has been compiled and tested with GCC 4.8.1. After setting a CPU register, the stack pointer is initialized. Immediately following stack setup, pre\_main is called. Note that pre\_main is called prior to static initialization.

#### Commercially available microcontroller compilers

Some commercially available microcontroller compilers provide a custom hook (in the sense of pre\_main) that is called before static initialization that precedes main. The IAR Systems C/C++ compiler, for instance, uses an implementation-specific function called \_\_low\_level\_init for this purpose. The user is responsible for the content (if any) of \_\_low\_level\_init.

#### 4 Future Work

The motivation and justification for a potential pre\_main is analogous in C and C++. Specifying pre\_main could potentially be addressed in WG14 as well as WG21.

Along these lines, do we need two versions of pre\_main? In particular,

```
void ::pre_main(void); // Intended for C
void std::pre_main(); // Intended for C++
```

What is the proper name of a potential pre\_main? Is pre\_init a better name because it more clearly reflects when the function is called?

Despite the proposal that pre\_main is to lack side-effects, it could be beneficial to allow pre\_main to initialize certain *clearly identifiable* non-local variables having static storage duration. Embedded systems tool chains for C/C++ typically provide special linker sections with implementation-specific names such as .noinit, .noclear, *etc*. These are meant to store non-local variables having static storage duration that are not intended to undergo static initialization. Attributes such as [[noclear]] or [[noinit]] could be used to clearly identify these.

Consider, for example, the reset\_reason in the following code.

```
typedef enum enum_reset_reason
{
   power_on_reset,
   watchdog_reset,
   software_reset
}
reset_reason_type;
[[noclear]] reset_reason_type reset_reason;
```

Here, reset\_reason is intended to be initialized by pre\_main in the application, not via conventional static initialization.

### 5 Discussion

TBD: Summarize the discussion regarding when pre\_main should be called and why.

TBD: Summarize the discussion regarding the dangers of offering an open user-interface that precedes main. Will users run into inordinate amounts of trouble with this proposed interface?

## 6 Acknowledgments

TBD: Acknowledge the participants.

## 7 References

TBD: Any references?