L4 Quantum information and computing (QIC) 2020-21

Lecture 4: Rotation operators and the Rabi solution

October 14, 2021

Aims of Lecture 4: To introduce the concept of single-qubit gates (qubit rotations) and then how they are implemented using external fields.

Qubit rotation

We can use the terms single-qubit gates and qubit rotation interchangeably, because apart from the global phase factor, all unitary single-qubit operations can be represented as a rotation of the Bloch vector. In quantum mechanics, the **rotation operator** (also called a generator of rotation) for a rotation by an angle Θ (not, in general, the same as the polar angle θ) about an axis defined by the unit vector $\hat{\boldsymbol{n}} = (n_x, n_y, n_z)$ is given by

$$R_{\hat{n}} = e^{-i \boldsymbol{J} \cdot \hat{\boldsymbol{n}} \Theta / \hbar} = e^{-i \boldsymbol{\sigma} \cdot \hat{\boldsymbol{n}} \Theta / 2}$$

where for a two-level system (equivalent to a spin-1/2), the angular momentum is given by $J=\frac{1}{2}\hbar\sigma$. To use this expression we need to evaluate the exponential of a matrix. Using a Taylor expansion and grouping even and odd terms we find that¹

$$\mathsf{R}_{\hat{\boldsymbol{n}}} = \mathrm{e}^{-\mathrm{i}\boldsymbol{\sigma}\cdot\hat{\boldsymbol{n}}(\Theta/2)} = \sigma_0 \cos\left(\frac{\Theta}{2}\right) - \mathrm{i}\boldsymbol{\sigma}\cdot\hat{\boldsymbol{n}}\sin\left(\frac{\Theta}{2}\right) \;.$$

Using this result we can write a general rotation matrix

$$\mathsf{R}_{\hat{\boldsymbol{n}}} = \left[\begin{array}{cc} \cos\frac{\Theta}{2} - \mathrm{i} n_z \sin\frac{\Theta}{2} & (-\mathrm{i} n_x - n_y) \sin\frac{\Theta}{2} \\ (-\mathrm{i} n_x + n_y) \sin\frac{\Theta}{2} & \cos\frac{\Theta}{2} + \mathrm{i} n_z \sin\frac{\Theta}{2} \end{array} \right] \ . \ (4.1)$$

¹For any Pauli spin matrix, σ_j , using $\sigma_j^{2m}=\sigma_0$ for any integer m, the Taylor expansion is

$$e^{-i\sigma_{j}(\Theta/2)} = \sigma_{0} - i\sigma_{j} \left(\frac{\Theta}{2}\right) - \frac{\sigma_{j}^{2}}{2!} \left(\frac{\Theta}{2}\right)^{2}$$

$$+i\frac{\sigma_{j}^{3}}{3!} \left(\frac{\Theta}{2}\right)^{3} + \frac{\sigma_{j}^{4}}{4!} \left(\frac{\Theta}{2}\right)^{4} + \dots$$

$$= \sigma_{0} - \frac{\sigma_{j}^{2}}{2!} \left(\frac{\Theta}{2}\right)^{2} + \frac{\sigma_{j}^{4}}{4!} \left(\frac{\Theta}{2}\right)^{4} + \dots$$

$$-i \left[\sigma_{j} \left(\frac{\Theta}{2}\right) - \frac{\sigma_{j}^{3}}{3!} \left(\frac{\Theta}{2}\right)^{3} + \dots\right]$$

$$= \sigma_{0} \cos \left(\frac{\Theta}{2}\right) - i\sigma_{j} \sin \left(\frac{\Theta}{2}\right),$$

where in the second line we rearranged the terms into even and odd series which correspond to cosine and sine respectively. Note that $R_{\hat{n}}$ is **unitary**, i.e. $R_{\hat{n}}R_{\hat{n}}^{\dagger} = \sigma_0$ and the operator $|\psi'\rangle = R|\psi\rangle$ preserves the norm of the state vector. The special case of rotation about the x, y, and z axes (see also Nielsen and Chang, Sec. 4.2) are given by

$$\begin{array}{rcl} \mathsf{R}_x(\Theta) & = & \mathrm{e}^{-\mathrm{i}(\Theta/2)\mathsf{X}} = \cos\frac{\Theta}{2}\mathsf{I} - \mathrm{i}\sin\frac{\Theta}{2}\mathsf{X} \\ & = & \left(\begin{array}{cc} \cos\frac{\Theta}{2} & -\mathrm{i}\sin\frac{\Theta}{2} \\ -\mathrm{i}\sin\frac{\Theta}{2} & \cos\frac{\Theta}{2} \end{array}\right) \; . \end{array}$$

$$\begin{array}{rcl} \mathsf{R}_y(\Theta) & = & \mathrm{e}^{-\mathrm{i}(\Theta/2)\mathsf{Y}} = \cos\frac{\Theta}{2}\mathsf{I} - \mathrm{i}\sin\frac{\Theta}{2}\mathsf{Y} \\ & = & \left(\begin{array}{cc} \cos\frac{\Theta}{2} & -\sin\frac{\Theta}{2} \\ \sin\frac{\Theta}{2} & \cos\frac{\Theta}{2} \end{array}\right) \; . \end{array}$$

$$\begin{array}{rcl} \mathsf{R}_z(\Theta) & = & \mathrm{e}^{-\mathrm{i}(\Theta/2)\mathsf{Z}} = \cos\frac{\Theta}{2}\mathsf{I} - \mathrm{i}\sin\frac{\Theta}{2}\mathsf{Z} \\ & = & \left(\begin{array}{cc} \mathrm{e}^{-\mathrm{i}\frac{\Theta}{2}} & 0 \\ 0 & \mathrm{e}^{\mathrm{i}\frac{\Theta}{2}} \end{array}\right) \,. \end{array}$$

Next, we shall look at how to implement these rotation using oscillatory electromagnetic (EM) fields.

Qubits in EM fields: the interaction Hamiltonian

In practice, qubit rotations are implemented by applying EM fields (lasers and microwaves) with angular frequency, ω , either resonant or detuned by $\Delta = \omega - \omega_0$ with respect to the qubit resonance, $\omega_0 = (E_1 - E_0)/\hbar$. The external field has the form

$$\mathcal{E} = \mathcal{E}_0 \cos(\phi_L - \omega t)$$
.

where $\phi_{\rm L} = \mathbf{k} \cdot \mathbf{r} + \phi_0$ is the phase. Note that this depends on the position of the qubit, \mathbf{r} , which is a problem if the qubit is delocalised or moves.

The field changes the coefficients, a and b, appearing in the state vector. The time evolution of the state vector is given by solving the Schrödinger equation, (see Appendix for derivation)

$$i\hbar \frac{\partial}{\partial t} |\psi\rangle = \mathcal{H}_{\rm int} |\psi\rangle ,$$

where $\mathcal{H}_{\rm int}$ is known as the interaction Hamiltonian.² For a two-level system, using the vector form, the interaction Hamiltonian is a 2×2 matrix

$${\cal H}_{\rm int} \ = \ \frac{\hbar}{2} \left(\begin{array}{cc} \Delta & \Omega e^{-i\phi_L} \\ \Omega e^{i\phi_L} & -\Delta \end{array} \right) \; , \label{eq:Hint}$$

where Ω is known as the Rabi frequency (proportional to the amplitude of the EM field, $\Omega = \langle 1| - \mathbf{d} \cdot \mathbf{\mathcal{E}}_0 |0\rangle/\hbar$, where \mathbf{d} is the dipole moment of the qubit). The next step is to write this interaction in the form of a rotation.

The Rabi solution:

If the interaction Hamiltonian is time-independent then the solution to the Schrödinger equation is

$$|\psi(t)\rangle = \exp(-i\mathcal{H}_{int}t/\hbar)|\psi(0)\rangle = \mathsf{R}|\psi(0)\rangle$$
,

where R has the form of a rotation matrix. To find the rotation matrix we rewrite the interaction in the form

$$R = \exp(-i\mathcal{H}_{int}t/\hbar) = \exp(-i\frac{1}{2}\boldsymbol{\sigma}\cdot\hat{\boldsymbol{n}}\Theta) .$$

By writing the interaction Hamiltonian in terms of spin matrices

$$\mathcal{H}_{\rm int} = \frac{\hbar}{2} \left[\Delta \sigma_z + \Omega (\cos \phi_{\rm L} \sigma_x + \sin \phi_{\rm L} \sigma_y) \right] .$$

We construct the unit vector by normalising the coefficients of the Pauli matrices.

$$\hat{m{n}} = rac{1}{(\Omega^2 + \Delta^2)^{1/2}} [\Omega\cos\phi_{
m L}, \Omega\sin\phi_{
m L}, \Delta] \; ,$$

 $\Omega_{\rm eff}=(\Omega^2+\Delta^2)^{1/2}$ is the normalisation factor. In this case the interaction Hamiltonian becomes

$$\mathcal{H}_{\mathrm{int}} = \frac{\hbar}{2} \Omega_{\mathrm{eff}} \hat{\boldsymbol{n}} \cdot \boldsymbol{\sigma} .$$

By comparing the solution to the Schrödinger equation to a rotation matrix

$$e^{-i\mathcal{H}_{\rm int}t/\hbar} = e^{-i\Omega_{\rm eff}\hat{\boldsymbol{n}}\cdot\boldsymbol{\sigma}t/2} = e^{-i\Theta\hat{\boldsymbol{n}}\cdot\boldsymbol{\sigma}/2}$$

we find that the rotation angle is

$$\Theta = (\Omega^2 + \Delta^2)^{1/2}t \ .$$

The factor $\Omega_{\rm eff} = (\Omega^2 + \Delta^2)^{1/2}$ is known as the **effective Rabi frequency**. Substituting

$$\begin{array}{rcl} n_x & = & (\Omega/\Omega_{\rm eff})\cos\phi_{\rm L} \; , \\ n_y & = & (\Omega/\Omega_{\rm eff})\sin\phi_{\rm L} \; , \\ n_z & = & \Delta/\Omega_{\rm eff} \; , \end{array}$$

into the rotation matrix, eqn (4.1), we obtain³

$$\label{eq:Rate} \mathsf{R}_{\boldsymbol{\hat{n}}}(\boldsymbol{\Theta}) \ \ = \ \ \left[\begin{array}{ccc} \cos\frac{\boldsymbol{\Theta}}{2} - \mathrm{i}\frac{\Delta}{\Omega_{\mathrm{eff}}}\sin\frac{\boldsymbol{\Theta}}{2} & -\mathrm{i}\frac{\Omega}{\Omega_{\mathrm{eff}}}\mathrm{e}^{-\mathrm{i}\phi_L}\sin\frac{\boldsymbol{\Theta}}{2} \\ -\mathrm{i}\frac{\Omega}{\Omega_{\mathrm{eff}}}\mathrm{e}^{+\mathrm{i}\phi_L}\sin\frac{\boldsymbol{\Theta}}{2} & \cos\frac{\boldsymbol{\Theta}}{2} + \mathrm{i}\frac{\Delta}{\Omega_{\mathrm{eff}}}\sin\frac{\boldsymbol{\Theta}}{2} \end{array} \right] \ .$$

This is known as the **Rabi solution**. The three key parameters for driven qubits are: the Rabi frequency Ω , which characterises the strength of the coupling between the qubit and the field, the detuning, $\Delta = \omega - \omega_0$, and a phase of the field, ϕ_L .⁴

For the special case of zero detuning $(\Delta = 0)$, the Rabi solution reduces to

$$\mathsf{R}(\theta_{\mathrm{L}},\phi_{\mathrm{L}}) = \left[\begin{array}{cc} \cos(\Omega t/2) & -\mathrm{i}\mathrm{e}^{-\mathrm{i}\phi_{\mathrm{L}}}\sin(\Omega t/2) \\ -\mathrm{i}\mathrm{e}^{+\mathrm{i}\phi_{\mathrm{L}}}\sin(\Omega t/2) & \cos(\Omega t/2) \end{array} \right] \; ,$$

which corresponds to a rotation about a vector in the equatorial plane in the Bloch sphere. Note that we have switched to the notation $R(\theta_L, \phi_L)$, where $\theta_L = \Omega t$ is the rotation angle and ϕ_L determines the direction in the xy plane about which we rotate. We shall explore this further in Lecture 5.

Summary:

What do you need to be able to do?

- 1. Write an identity for the rotation operator in terms of cosine and sine term.
- 2. Derive matrices for rotations about the x, y and z axes.
- 3. Rewrite the interaction Hamiltonian in terms of spin matrices.
- 4. Understand the significance of the terms in the Rabi solution.

²Note that Hamiltonians are **Hermitian** $\mathcal{H} = \mathcal{H}^{\dagger}$ but not usually unitary, so behave differently to rotation matrices. Any Hermitian matrix can be converted to a diagonal matrix with real eigenvalues, $D = U^{\dagger} \mathcal{H} U$, where U is a unitary operator.

³Note the sign of ϕ_L depends on whether $|0\rangle$ or $|1\rangle$ has higher energy. Other texts may use different sign conventions.

⁴Note that the sign of Ω term depends on our choice of field phase. Rather than $+\Omega$ at $\phi_L = 0$, some texts have $-\Omega$.

Appendix: Derivation of \mathcal{H}_{int}

The Schrödinger equation describing the interaction between the qubit and the external field is,

$$i\hbar\partial_t|\psi\rangle = (\mathcal{H}_0 + \mathcal{H}')|\psi\rangle$$
,

where \mathcal{H}_0 is the Hamiltonian for the quantum system and \mathcal{H}' is the perturbation due to the EM field. We substitute a state vector of the form

$$|\psi(t)\rangle = a(t)|0\rangle e^{-iE_0t/\hbar} + b(t)|1\rangle e^{-iE_1t/\hbar}$$
.

Using $\mathcal{H}_0|k\rangle = E_k|k\rangle$ we can cancel some terms on the left and right leaving

$$\begin{split} \mathrm{i}\hbar \left(\dot{a}(t)|0\rangle \mathrm{e}^{-\mathrm{i}E_{0}t/\hbar} + \dot{b}(t)|1\rangle \mathrm{e}^{-\mathrm{i}E_{1}t/\hbar} \right) = \\ \mathcal{H}'|0\rangle a(t) \mathrm{e}^{-\mathrm{i}E_{0}t/\hbar} + \mathcal{H}'|1\rangle b(t) \mathrm{e}^{-\mathrm{i}E_{1}t/\hbar} \ . \end{split}$$

Next, we take the inner product with $\langle 0|\mathrm{e}^{\mathrm{i}E_0t/\hbar}$ (or $\langle 1|\mathrm{e}^{\mathrm{i}E_1t/\hbar}\rangle$), and use the fact that the field couples states $|0\rangle$ and $|1\rangle$, i.e. $\langle 0|\mathcal{H}'|0\rangle = \langle 1|H'|1\rangle = 0$, we find

$$\begin{split} \mathrm{i}\hbar\dot{a}(t) &= \langle 0|\mathcal{H}'|1\rangle\mathrm{e}^{-\mathrm{i}\omega_0t}\ b(t)\ ,\\ \mathrm{i}\hbar\dot{b}(t) &= \langle 1|\mathcal{H}'|0\rangle\mathrm{e}^{\mathrm{i}\omega_0t}\ a(t)\ . \end{split}$$

The interaction is of the form $\mathcal{H}' = -\mathbf{d} \cdot \boldsymbol{\mathcal{E}}$ where $\mathbf{d} = -e\mathbf{r}$ is the electric dipole operator, and $\boldsymbol{\mathcal{E}} = \boldsymbol{\mathcal{E}}_0 \cos(\phi_L - \omega t)$ is the electric part of the EM field. If the phase is zero at t = 0 then the laser is, $\phi_L = \mathbf{k} \cdot \mathbf{r}$. We define a **Rabi frequency** (as a measure of the coupling between the field and the qubit) as $\Omega = -\langle 1|\mathbf{d} \cdot \boldsymbol{\mathcal{E}}_0|0\rangle/\hbar^5$. If the state vectors are real such that $\Omega = -\langle 0|\mathbf{d} \cdot \boldsymbol{\mathcal{E}}_0|1\rangle/\hbar$ as well, then we can rewrite the coupled equations as

$$i\dot{a}(t) = \Omega \cos(\phi_{\rm L} - \omega t) e^{-i\omega_0 t} b(t)$$

$$i\dot{b}(t) = \Omega \cos(\phi_{\rm L} - \omega t) e^{i\omega_0 t} a(t)$$

where $\omega_0 = (E_1 - E_0)/\hbar$. Now we expand the cosine and use that for $\omega \sim \omega_0$, we can neglect terms in $\omega + \omega_0$ (known as **rotating wave approximation**) Integrating $e^{i(\omega + \omega_0)t} + e^{i(\omega - \omega_0)t}$ we get

$$\frac{\mathrm{e}^{\mathrm{i}(\omega+\omega_0)t}}{\mathrm{i}(\omega+\omega_0)} + \frac{\mathrm{e}^{\mathrm{i}(\omega-\omega_0)t}}{\mathrm{i}(\omega-\omega_0)} \ .$$

As $\omega+\omega_0\sim 10^{15}$ and $\omega-\omega_0\sim 10^7$ we can neglect the $\omega+\omega_0$ term, giving

$$\begin{split} &\mathrm{i}\dot{a}(t) &=& \frac{1}{2}\Omega\mathrm{e}^{-\mathrm{i}\phi_\mathrm{L}}\mathrm{e}^{\mathrm{i}\Delta t}\ b(t)\\ &\mathrm{i}\dot{b}(t) &=& \frac{1}{2}\Omega\mathrm{e}^{\mathrm{i}\phi_\mathrm{L}}\mathrm{e}^{-\mathrm{i}\Delta t}\ a(t)\ . \end{split}$$

where $\Delta = \omega - \omega_0$ is the **detuning**.

Finally, we transform into a **rotating frame** by make a change of variable, $\tilde{a} = a \mathrm{e}^{-\mathrm{i}(\Delta/2)t}$, $\tilde{b} = b \mathrm{e}^{\mathrm{i}(\Delta/2)t}$. This removes the explicit time dependence and we obtain,

$$\begin{array}{rcl} \mathrm{i}\dot{\tilde{a}} & = & \frac{1}{2}\Delta\tilde{a} + \frac{1}{2}\Omega\mathrm{e}^{-\mathrm{i}\phi_\mathrm{L}}\ \tilde{b} \\ \mathrm{i}\dot{\tilde{b}} & = & \frac{1}{2}\Omega\mathrm{e}^{\mathrm{i}\phi_\mathrm{L}}\ \tilde{a} - \frac{1}{2}\Delta\tilde{b}\ . \end{array}$$

We can rewrite these coupled equations in the form of a Schrödinger equation,

$$i\hbar \frac{\partial}{\partial t} |\psi\rangle = \mathcal{H}_{\rm int} |\psi\rangle$$

with

$$\mathcal{H}_{\rm int} \ = \ \frac{\hbar}{2} \left(\begin{array}{cc} \Delta & \Omega e^{-i\phi_L} \\ \Omega e^{i\phi_L} & -\Delta \end{array} \right) \ , \label{eq:Hint}$$

and

$$|\psi\rangle \ = \ \left(\begin{array}{c} \tilde{a} \\ \tilde{b} \end{array}\right) \ .$$

We shall omit the tildes from now on.

⁵As d = -er the real frequency is positive.