

EMI REGISTRY MANUAL

EMIR Product Team

Document Version:	1.2.0
Component Version:	1.2.0
Date:	12 07 2012

This work is co-funded by the EC EMI project under the FP7 Collaborative Projects Grant Agreement Nr. INFSO-RI-261611.



Contents

1	Ove	rview	1
2	Insta	allation	1
	2.1	Installation using the RPM bundle (RedHat Distributions)	2
	2.2	Installation using the Debian bundle (Centos/Debian Distributions)	2
	2.3	Database Installation	2
	2.4	Installation from the self-contained archive (tar.gz)	3
3	Con	figuration	3
	3.1	General Configuration	3
	3.2	PKI Trust Settings Configuration	4
	3.3	Configuring the Credentials	9
	3.4	ACL Based Authorization	10
	3.5	Policy Based Authorization with XACML	11
	3.6	MongoDB Database Configuration	13
	3.7	Building EMIR Network	13
	3.8	Service Endpoint Record (SER) Management	16
	3.9	Logging Configuration	17
	3.10	Advanced HTTP Server Settings	17
4	EMI	R Service Endpoint Record Publisher (EMIR-SERP) Client	19
	4.1	About the EMIRD	19
	4.2	Installation	20
	4.3	Configuration	20
5	How	to use EMIR API	23
	5.1	Register new Services	24
	5.2	Updating the Service information	24
	5.3	Delete existing Services	25
	5 4	Ouerving the EMIR	25

EMI Registry Manual

7	App	endix II	30
6	App	endix I	28
	5.9	Monitoring the Registry	28
	5.8	Viewing the Service information template	27
	5.7	Rich Querying the EMIR for GLUE 2.0 XML Documents	27
	5.6	Querying the EMIR for GLUE 2.0 XML Documents	27
	5.5	Rich Querying in EMIR	26

1 Overview

EMI Service Registry is a Service Endpoint Registry conceived during the EMI project. Its main goal is to discover all the Service Endpoints that exist. It consists of a collection of services that enables storing service records in a federated manner. Each of the record is a Service Endpoint Record (SER) complying with the OGF's GLUE 2.0 standard. The deployment of EMIR (which implies building an EMIR network over WAN) is bipartite: 1) Building a rooted hierarchy with a single EMIR server aggregating all the information within a federation 2) Sharing the information at the root level among peered EMIR servers (using P2P), thus enabling intra-federation discovery.

Feature Highlights:

- the service endpoint record registration includes the management of the services' endpoint information.
- Powerful data back-end based on MongoDB
- Schema-free information model based on JSON (using GLUE2 entity names for specific attributes)
- REST-ful API to browse the service registrations
- Security
 - PKI governed authentication
 - Policy based authorisation

For more information about EMIR, visit EMI's TWiki[https://twiki.cern.ch/twiki/bin/view/-EMI/EMIRegistry].

2 Installation

In order to install EMIR, it is required to install the SUN or OpenJDK Java 6 (JRE or SDK). If not installed on the target system, it can be downloaded from http://java.oracle.com

- · Linux based operating system
- MongoDB

EMIR is distributed in the following formats:

- Platform independent format, provided in "tar.gz" format
- RPM package, suitable SL5/SL6 and other Fedora based Linux derivatives (RedHat, CentOS etc...)

Debian package

IMPORTANT NOTE ON PATHS

The location of the installation and configuration files differ depending on the type of bundle (see the above section).

If RPM bundle is being installed, the following paths will be used:

```
CONF=/etc/emi/emir
BIN=/usr/sbin
LOG=/var/log/emi/emir
```

The platform independent binary places all the files under single directory. The contents will be:

```
CONF=INST/conf/
BIN=INST/bin/
LOG=INST/logs/
```

The above variables (CONF, BIN and LOG) will be used throughout the rest of this manual.

2.1 Installation using the RPM bundle (RedHat Distributions)

Download EMIR Server's RPM distribution from the EMI's emisoft and install it using the rpm or yum command.

Example

```
yum install -y emi-emir
```

2.2 Installation using the Debian bundle (Centos/Debian Distributions)

Download EMIR DEB distribution from the EMI's emisoft and install it using the apt-get command.

2.3 Database Installation

EMIR server uses MongoDB database as a backbone to store and indexe SER collections. The database dependency will automatically be fetched from the **emisoft** repository, while installing the EMIR Server. Otherwise it should be installed and configured before installing the EMIR. The installation and configuration instructions to setup the MongoDB database can be found on MongoDB's Web site.

2.4 Installation from the self-contained archive (tar.gz)

In order to generate, build and install the self contained binary it is required to follow the steps written below:

CREATING THE BUNDLE

- 1. check out the source code from git://github.com/eu-emi/emiregistry.git
- 2. go to SOURCE_ROOT/emir-dist directory
- 3. run mvn assembly:assembly -DskipTests

The archive can be found inside the **SOURCE_ROOT/target/emir-distribution-x.y.z-a-all.(tar.gz/zip)**, that contains all the necessary files for installation thus no special actions will be required except extraction to the target folder.

3 Configuration

The EMIR server comes with a well documented configuration file (CONF/emir.config), containing a number of options to setup registry hierarchy, p2p, security, http server, and database. The settings in the configuration file are pre-defined to start-up the server in a non-production environment, however the administrator needs to review before deploying on the production Grid environments.

3.1 General Configuration

The server configuration options in the CONF/emir.config are:

- Server address (plain or SSL)
- Settings of the type of the registry node, i.e. whether the current EMIR server instance is a child of some other (a parent) EMIR server node or a top/global registry in a hierarchy.

Property name	Type	Default value	Description		
Server general settings					

Property name	Type	Default value	Description
emir.address	string	http://localh	The address/URL of the
			EMIR server on which
			it receives registration
			and query requests. It
			should either start with
			http or https (SSL/TLS)
			mode, if "https" mode
			is selected the
			Authentication and
			Authorisation
			properties must be
			properly configured
emir.anonymousPort	Unsigned	9127	The anonymous http
	Integer		port number. Setting
			the property will start
			an additional http server
			(without SSL/TLS)
			only if the above server
			address is <i>https</i> (with
			SSL/TLS). It will
			provide anonymous
			access to the query
			interface (i.e. /services
			REST Web Service).

3.2 PKI Trust Settings Configuration

EMIR endorses Public Key Infrastructure (PKI) trust settings to validate certificates using EMI's caNL (JAVA version). The validation is performed when a connection with a remote peer is initiated over the network, using the SSL (or TLS) protocol, i.e. emir.address value has https scheme.

Certificates validation is primarily configured using a set of initially trusted certificates of so called Certificate Authorities (CAs). Those trusted certificates are also known as *trust anchors* and their collection is called as a *truststore*.

The validation mechanism except the *trust anchors* can use additional input for checking if a certificate being checked was not revoked and if its subject is in a permitted namesapce.

EMIR allows different types of truststores. All of them are configured using a set of specific properties in *CONF/emir.config* file.

3.2.1 OpenSSL Truststore

It allows using a directory with CA certificates stored in PEM format, with precisely defined names: Certificate Authorities (CA), Certificate Revocation List (CRL), signing policy and

namespaces files are named as <hash>.0, <hash>.r0, <hash>.signing_policy and <hash>.namespaces respectively. Hash is the old hash of the trusted CA certificate subject name - in OpenSSL version newer than 1.0.0 use -suject_hash_old switch to generate it. If multiple certificates have the same hash then the default zero number must be incremented. It is suggested when a common truststore with EMI (and Globus) middlewares is needed.

3.2.2 Directory Truststore

It allows to use a list of wildcard expressions, concrete paths of files, or URLs to remote files as a set of trusted CAs and CRLs. The truststore is configured as a directory containing all the trusted certificates (or with a specified extension). The directory with stored IGTF trust anchors can be set as a EMIR truststore for instance.

3.2.3 Java Keystore (JKS) Truststore

A single repository (or a binary file) of X.509 public key certificates with (optionally) accompanying private key certificates. The Java JDK already bundles keytool utility - a certificate manage utility to create JKS truststores.

3.2.4 PKCS#12 Truststore

Similar to JKS trustore, single binary file can be used to store X.509 public with (optionally) accompanying private key certificates. The **OpenSSL pkcs12** command can be used to parse, read, and create these files; the extension for PKCS#12 files is ".p12".

Property name	Type	Default	Description		
		value /			
		mandatory			
emir.security.tru	s [Askb@W, allow	P A rbkýW	controls whether proxy		
	DENY]		certificates are supported		
emir.security.tru	s įkeystore, type	mandatory	The truststore type.		
	openssl,	to be set			
	directory]				
emir.security.tru	s inseger aumber at	e 6 0terval	how often the truststore		
			should be reloaded, in		
			seconds.		
	Directory				
emir.security.tru	s inseger aundber e o	tb5ryConnec	tCommection timeout for		
			fetching the remote CA		
			certificates in seconds.		

Property name	Туре	Default value /	Description
		mandatory	
emir.security.tru	s fikes vstem obáthe o		CDirectory where CA
1	The state of the	1	certificates should be
			cached, after downloading
			them from a remote source.
			Can be left undefined if no
			disk cache should be used.
			Note that directory should
			be secured, i.e. normal
			users should not be allowed
			to write to it.
emir.security.tru	s tREMrÐER1 red	tPEWEncodi	
		1 - 1	controls whether
			certificates are encoded in
			PEM or DER.
emir.security.tru	s tis ttofre.dired	t-oryLocati	ohist. of CA certificates
_	properties with	_	locations. Can contain
	a common		URLs, local files and
	prefix		wildcard expressions.
	Key	store	
emir.security.tru	s tsing re.keyst	o-reFormat	The keystore type (jks,
			pkcs12) in case of truststore
			of keystore type.
emir.security.tru	s tsing re.keyst	o-rePasswor	
			keystore type truststore.
emir.security.tru	s tsing re.keyst	o-rePath	The keystore path in case of
		_	truststore of keystore type.
		enssl	
emir.security.tru		KEH DIKSWITA IQIEMA	_
	EU-	DIIG	truststore, controls which
	GRIDPMA_GLC	BUS,	(and in which order)
	GLOBUS,		namespace checking rules
	EUGRIDPMA,		should be applied
	GLOBUS_EUGF EU-	RIDPMA_REQ	UIRE,
	GRIDPMA_GLC	BUS_REQUIF	E,
	GLOBUS_REQU		
	EU-		
	GRIDPMA_REQ	UIRE,	
	EU-		
	GRIDPMA_ANI	_GLOBUS,	
	EU-	_ ′	
	GRIDPMA_ANI	GLOBUS R	EQUIRE,
	IGNORE]		

Property name	Type	Default	Description
		value /	
	C1-1	mandatory	1:
emir.security.tru	s nesystem opte ns	s leach gria	
	D		opeenssl truststore
		cation	
emir.security.tru	smetgeraumberCo	nhectionTi	m©onntection timeout for
			fetching the remote CRLs
			in seconds (not used for
- <u></u>			Openssl truststores).
emir.security.tru	striketsysatem opathDi	s-kCachePat	ļ — — — — — — — — — — — — — — — — — — —
			should be cached, after
			downloading them from
			remote source. Can be left
			undefined if no disk cache
			should be used. Note that
			directory should be
			secured, i.e. normal users
			should not be allowed to
			write to it. Not used for
			Openssl truststores.
emir.security.tru		cations.*	List of CRLs locations. Can
	properties with		contain URLs, local files
	a common		and wildcard expressions.
	prefix		Not used for Openssl
			truststores.
emir.security.tru		def_VALID	General CRL handling
	IF_VALID,		mode. The IF_VALID
	IGNORE]		setting turns on CRL
			checking only in case the
			CRL is present.
emir.security.tru	s inseger aumbe rUp	d @t@ Interv	аНоw often CRLs should be
			updated, in seconds.
emir.security.tru	s inseger aumber p0	a& h@O tl	For how long the OCSP
			responses should be locally
			cached in seconds (this is a
			maximum value, responses
			won't be cached after
			expiration)
emir.security.tru	s fiketsystem pathpl	i-skCache	If this property is defined
			then OCSP responses will
			be cached on disk in the

Property name	Type	Default	Description
		value /	_
		mandatory	
emir.security.tru	s tis ttofre.ocspI	ocalRespon	deptsonal limber Rocal OCSP
	properties with		responders
	a common		
	prefix		
emir.security.tru			BGeneral OCSP ckecking
	IF_AVAILABLE		mode. REQUIRE should
	IGNORE]		not be used unless it is
			guaranteed that for all
			certificates an OCSP
			responder is defined.
emir.security.tru	s inseger aumber pl	i1m@oout	Timeout for OCSP
			connections in miliseconds.
emir.security.tru	s tGRb<u>r</u>@CSB ,voo	attish <u>o</u> tkibr	Controls overal revocation
	OCSP_CRL]		sources order
emir.security.tru	s [trute;) faelse] evoc	afabseAl	1Controls whether all
			defined revocation sources
			should be always checked,
			even if one the first one
			already confirmed that a
			checked certificate is not
			revoked.

3.2.5 Examples

Directory truststore, with a minimal set of options:

```
truststore.type=directory
truststore.directoryLocations=/trust/dir/*.pem
truststore.crlLocations=/trust/dir/*.crl
```

Directory truststore, with complete set of options:

```
emir.security.truststore.type=directory
emir.security.truststore.allowProxy=DENY
emir.security.truststore.updateInterval=1234
emir.security.truststore.directoryLocations=/trust/dir/*.pem http://caserver/ca.pe
emir.security.truststore.directoryEncoding=PEM
emir.security.truststore.directoryConnectionTimeout=100
emir.security.truststore.directoryDiskCachePath=/tmp
emir.security.truststore.crlLocations=/trust/dir/*.crl http://caserver/crl.pem
emir.security.truststore.crlUpdateInterval=400
```

```
emir.security.truststore.crlMode=REQUIRE
emir.security.truststore.crlConnectionTimeout=200
emir.security.truststore.crlDiskCachePath=/tmp
```

Openssl truststore:

```
emir.security.truststore.type=openssl
emir.security.truststore.opensslPath=path/to/truststores/openssl
emir.security.truststore.opensslNsMode=EUGRIDPMA_GLOBUS_REQUIRE
emir.security.truststore.allowProxy=ALLOW
emir.security.truststore.updateInterval=1234
emir.security.truststore.crlMode=IF_VALID
```

Java keystore used as a truststore:

```
emir.security.truststore.type=keystore
emir.security.truststore.keystorePath=path/to/truststores/emir-truststore.jks
emir.security.truststore.keystoreFormat=JKS
emir.security.truststore.keystorePassword=xxxxxx
```

3.3 Configuring the Credentials

EMIR uses private key and a corresponding certificate (called together as a *credential*) to identify clients and servers. The credentials can be provided in several formats. The following table list all possible variants and corresponding parameters.

Property name	Type	Default	Description
		value /	
		mandatory	
emir.security.cre	d @ks,pkcs.12 orma	t-	format of the credential
	der, pem]		
emir.security.cre	d stninģ al.keyAl	i-as	keystore alias of the key
			entry to be used (can be
			ignored if the keystore
			contains only one key
			entry)
emir.security.cre	d stninģ al.keyPa	s-sword	private key password in
			keystore (if different from
			the main credential
			password)
emir.security.cre	d etning al.keyPa	t-h	location of the private key
			if stored separately from
			the main credential

Property name	Туре	Default value /	Description
		mandatory	
emir.security.cre	d etninģ al.passv	o-rd	password required to load
			the credential
emir.security.cre	d files yistelm pathh	mandatory	credential location
		to be set	

3.3.1 Examples

Credential as a pair of DER files:

```
credential.format=der
credential.password=emi
credential.path=path/to/credentials/cert-1.der
credential.keyPath=path/to/credentials/pk-1.der
```

Credential as a JKS file (type can be autodetected in almost every case):

```
credential.path=path/to/credentials/server1.jks
credential.password=xxxxxx
```

3.4 ACL Based Authorization

The EMIR offers two alternative options to authorise its' clients.

- Using Access Control List (ACL)
- XACML Policy based authorization

This is the default mechanism to access control the *Create,Update*, and *Delete* operations on EMIR's SER database. The client SERP or child DSR registering SERPs with a parent DSR/GSR get authorised while matching it's distinguished name (DN) against the pre-defined ACL file (CONF/emir.acl). Whereas the file contains a list of DN and role pairs, separated by :: symbol, see the example below:

the property in the CONF/emir.config file

Property name	Type		Description
emir.security.access	ofdestystem.	a CD NF/emir.acl	The location of the
	path		ACL file

Example ACL file contents

```
emailAddress=emiregistry@user.eu,CN=EMIRegistry-Demo-User,OU=JSC,O= ← Forschungszentrum Juelich GmbH,L=Juelich,C=DE :: serviceowner emailAddress=emiregistry@user.eu-admin,CN=EMIRegistry-Demo-User- ← Admin,OU=JSC,O=Forschungszentrum Juelich GmbH,L=Juelich,C=DE :: ← admin
```

The public key certificate or DN should be sent to the DSR administrator for successfull SER registrations.

Roles: There are only two pre-defined roles within the scope of ACL file:

- the admin is a super user who can change any registration, owned by anyone, and
- the serviceowner is only allowed to create new or modify his created SERPs.



Important

The ACL based authorisation is only activated when the DSR/GSR is running on SSL/TLS mode

3.5 Policy Based Authorization with XACML

Using XACML 2.0 is an alternative way to authorize clients (User, EMIR-SERP, DSR, or GSR) in a fine grained manner. The administrator should review the policies defined in the CONF/xacml2Policies/ folder and change them according to her infrastructure needs. However the already defined policies provides a good starting point to the administrators to define/modify the policies.



Important

the XACML policy based authorization will be ignored, if the ACL based authorisation is activated

In order to enable the XACML based authorization: attribute sources and policies must be configured.

3.5.1 Setting Attribute Sources

EMIR only supports file based attribute sources; the client DNs can be included in the attributes file.

Table 1: File Attribute Source Settings

Property name	Type	Default value	Description
emir.security.attri	u string ord	efile	This property is a space
			separated list of
			attribute source names,
			which are then
			configured in detail
			below. The named
			attribute sources are
			queried in the given
			order.
emir.security.attri	ustrėnsg. FIL	E ealæms i.emir.a	ponfigurationroifulmeteSourc
			FILE attribute source
emir.security.attri	u (steisct ,FIL	E.matching	Specifies the matching
	regexp]		or client DNs
emir.security.attri	uftlessystemL	ECONF∉users/te	s tTthe pathnio the film 1
	path	or	containing subjects'
		CONF/users/te	s t DNs. iTeng efitepsutfixted
			with strict use strict
			checking of DNs,
			whereas the file
			suffixed with regexp
			contain entries using
			regualr expressions

3.5.2 Setting XACML Policies

Table 2: Policy settings

Property name	Type	Default value	Description
emir.security.access	cfdestystem.	p apa fikiagm12.co	rThe path to the
	path		XACML2
			configuration,
			containing the rules of
			executing the policies
emir.security.access	estrintgrol.	p ep. unicore.ua	s Tool parame of the polp al Herasaf PDP
			class to endorse, for the
			xacml2 policies
			execution

The CONF/xacml2.config file contains raw xacml polices, enable EMIR (DSR or GSR) administrators to write their own rules.

3.6 MongoDB Database Configuration

The EMIR uses MongoDB to store and index the SER collections. It must be configured and running before deploying any EMIR (DSR or GSR) server.

Property name	Type	Default value	Description		
Connection Settings					
mongodb.hostName	string	localhost	Fully qualified host		
			name of the machine on		
			which MongoDB is		
			setup		
mongodb.port	Integer	27017	The port number		
	Datab	ase Settings			
mongodb.dbName	string	emiregistry	The name of the		
			database to store the		
			SERP records		
mongodb.colName	string	services	The name of the		
			collection (of the		
			database) in which the		
			records will be stored		
Login Settings					
mongodb.userName	string	_	The username to access		
			the MongoDB database		
mongodb.password	string	_	The password to access		
			the MongoDB database		

For high loads, especially at the GSR level, it is recommended to setup MongoDB replication for enhanced scalability and performance.

3.7 Building EMIR Network

EMIR allows building a network of registries participating in a Grid infrastructure or federation. The network can be of type hierarchical or Peer-to-Peer (P2P). In an hierarchical network, the SER collections are propagated from leaf DSR node to the top level root node, called GSR. Each DSR has only one parent, either DSR or GSR to which it pushes it's SER collections. At the root level the P2P network of GSR is formed to replicate the SER collections among multiple GSRs by referring a pre-configured Global list. The global list contains a listing of URLs of all the GSRs, each of which should be able to access the URLs.

3.7.1 How to Setup DSR?

In order to build hierarchy of DSRs must be able to propagate the SER collections to any **single** parent DSR or a GSR.

Table 3: Parent DSR Settings

Property name	Type	Default value	Description
	EMIR's	DSR settings	
emir.parentAddress	string	http://localho	The address/URL (http
			or https) of the EMIR
			DSR server to which it
			propagates its SER
			collection



Important

Add DN of child DSR into the parent DSRs CONF/emir.acl or CONF/users/testUd-(strict \mid regsexp).xml

3.7.2 How to Setup GSR?

The root level GSR has two primary functions:

- aggregation of children DSR SER collections
- replicating the SER collections among other GSRs (visible of Global List)

Table 4: GSR Settings

Property name	Type	Default value	Description		
General GSR Settings					

Table 4: (continued)

Property name	Type	Default value	Description
emir.global.enable	boolean	false	If set to true, indicating
			the registry node is
			global. It will then
			replicate the state
			among peer global
			registries (GSRs), the
			emir.parentAddress
			property will be
			ignored (if enabled), as
			the root registry should
			not contain any parent.
emir.global.sparsity	Unsigned	2	It determines the
	Integer		number of neighbors as
			a function of the actual
			number of member
			nodes of the network.
emir.global.retry	Unsigned	5	It specifies a number of
	Integer		attempts if
			communication to
			another GSR is failed.
emir.global.etValid	Unsigned	12	Specifies period in
	Integer		hours for checking the
			entries in the soft state
			database and strip the
			expired entries (but still
			keeps them).
emir.global.softStat	elintegery	2	Extend the expiration
			time with this time
			delay in hours.
emir.global.etRemove	Integer	24	Specifies period in
			hours for checking the
			entries in the soft state
			database and remove
			the expired entries.
		List Settings	.
emir.global.provider	LURE or	_	Link to the document
	filesys-		listing GSR URLs. The
	tem		URL(s) is/are important
	path		for building the GSR's
			DOD . 11
			P2P network at the



Important

Add DN of child DSR into the GSRs CONF/emir.acl or CONF/users/testUd-(strict | regsexp).xml

3.8 Service Endpoint Record (SER) Management

3.8.1 Setting Service Endpoint Records (SER) Lifetime

In EMIR, every SER has associated lifetime or (Time-To-Live) TTL. The settings can be defined in DSR or GSR to restrict the maximum assignable lifetime and assign default lifetime if missing from the registration.

Property name	Type	Default value	Description
emir.record.expiryMa	×Unsigned	_	Maximum assignable
	Integer		lifetime for the SERs
	(in days)		containing the
			Service_ExpireOn
			property, defined in
			days, minimum value:
			1.
emir.record.expiryDe	funsigned	_	The default lifetime
	Integer		will be set from the
			given property if the
			incoming registration is
			without the
			Service_ExpireOn
			attribute

Table 5: SER TTL Settings

3.8.2 Filtering Service Endpoint Records (SER)

EMIR offers a way to block

- SERs from being registered via DSR or EMIR-SERP
- SERs from being propagated to it's parent DSR or GSR

Description **Property name Default value** Type emir.record.blockListfilesystemingONF/inputfilteThe file containing list path of SER IDs, matching services will be blocked from registration to it's index emir.record.blockListfilesystemin@ONF/outputfilfdhesfile containing list path of SER IDs, matching services will be blocked from propagation to it's parent DSR

Table 6: SER Filter Settings

3.9 Logging Configuration

The EMIR server uses log4j to provide log facilities to record all but some of the server activities. In order to change the logging configuration, CONF/log4j.properties should be reviewed by the administrator.

Property name	Type	Default value	Description
log4j.configuration	filesystem	STARTUP_SCRIP	The log4j configuration
	path		

3.10 Advanced HTTP Server Settings

EMIR uses Eclipse's Jetty server to host REST Web services. Following table lists the important properties.



Important

Do not set **emir.jetty.requireClientAuthn** and **emir.jetty.wantClientAuthn** in CON-F/emir.config file, as they are automatically set by the EMIR server on start-up.

Property name	Туре	Default value / mandatory	Description
emir.jetty.disabl	e dding herSuite	sempty string	Space separated list of SSL cipher suites to be disabled.

Property name	Туре	Default value / mandatory	Description
emir.jetty.fastRa		false	Use insecure, but fast pseudo random generator to generate session ids instead of slow and secure generator for SSL sockets. Useful for testing.
emir.jetty.gzip.e		false	Controls whether to enable compression of HTTP responses.
emir.jetty.gzip.r	ni instegep siumber	100000	Specifies the minimal size of message that should be compressed.
emir.jetty.highLo			If the number of connections exceeds this amount, then connector is put into a special <i>low on resources</i> state. Existing connections will be closed faster. Note that this value is honored only for NIO connectors. Legacy connectors go into low resources mode when no more threads are available.
emir.jetty.lowRes	so ıntœge M≽xiidle'i	Iim⊕O	In low resource conditions, time (in ms.) before an idle connection will time out.
emir.jetty.maxId		200000	Time (in ms.) before an idle connection will time out. It should be large enough not to expire connections with slow clients, values below 30s are getting quite risky.
emir.jetty.maxTh	e indeger > 1	255	Maximum number of threads to have in the Jetty thread pool for connections serving.
emir.jetty.minTh	eindeger > 1	1	Minimum number of threads to have in the Jetty thread pool for connections serving.

Property name	Type	Default	Description
		value /	
		mandatory	
emir.jetty.requir	e(tiluie; fatse), thn	true	Controls whether the SSL
			socket requires client-side
			authentication.
emir.jetty.soLing	e inTegee number	-1	Socket linger time.
emir.jetty.useNIO	[true, false]	false	Controls whether the NIO
			connector be used. NIO is
			best suited under high-load,
			when lots of connections
			exist that are idle for long
			periods.
emir.jetty.wantCl	i (trute), fatlsen	true	Controls whether the SSL
			socket accepts client-side
			authentication.

4 EMIR Service Endpoint Record Publisher (EMIR-SERP) Client

4.1 About the EMIRD

The UMD services need to be registered into the EMI Registry service infrastructure to be discoverable for the clients. Most of the services or even the containers executing them provide a way to do this but not all of them. For those that are unable to register themselves automatically and periodically the EMIRD is available.

The EMIRD is a daemon like (background) service that can be executed next to these services (preferably on the same machine) and able to perform the automatic and periodical registration and update against the configured EMI Registry service on behalf of the service itself. This client uses exactly the same, standard RESTful API as the other clients do.

Most of the parameters of these registrations and updates can be configured. For the details see the Configuration section!

After the successful registration until the termination of the daemon, the EMIRD client do the periodical updates then finally, when the execution of the daemon is over, it attempts to delete the service entries from the remote database.

The service entries can be simple or advanced ones.

The simple service entries contain only the mandatory and easily configurable attributes that are the following: Service_Name, Service_Type, Service_Endpoint_URL, Service_Endpoint_InterfaceName. Here, the single mandatory element is the Service_Endpoint_URL.

The advanced entries can contains any kind of key value pairs that are accepted by the EMI Regisrty services and can be configured in the form of whole, formatted **json** documents.

4.2 Installation

The installation of the EMIRD client is trivial. The only thing to do is to install the emir-daemon package from the EMI repository by executing:

```
yum instlal emir-daemon
```

4.3 Configuration

The configuration of EMIRD can be performed by editing its configuration file or files. The configuration can be found basically in one file that default location is /etc/emi/emird.ini.

This file contains every configuration options that can be the EMIRD daemon control by, like service url, logging verbosity, credential location, etc.

The advanced service entries to be propagated can be described in separated configuration files preferably also under this directory and use to have .json extension.

The main configuration file has INI format. The emir section contains the daemon scoped options while the others are to describe the different service entries to be registered. In these cases the exact name is indifferent, they just have to differ from eachother and must avoid the emir name as well.

4.3.1 Configuration options

Note: The option names are case-insensitives.

url

Location: emir section

Default value: No default value

Mandatory: Yes Description:

URL of the EMIR service to connect in a protocol://domain:port format.

The protocol part is not mandatory if https (default) The port part is not mandatory if 54321 (default) The domain part is mandatory

Examples: url = emiregistry2.grid.niif.hu url = https://emiregistry2.grid.niif.hu url

period

Location: emir section

Default value: No default value

Mandatory: Yes
Description:

The period of the registration/update messages. Its value is given in minutes.

validity

Location: emir section

Default value: No default value

Mandatory: Yes
Description:

The validity of the registration entries. Its value is given in minutes.

cert

Location: emir section

Default value: /etc/grid-security/hostcert.pem

Mandatory: No Description:

User certificate file location in PEM format. Only used and checked if the protocol in the url option is *https*.

key

Location: emir section

Default value: /etc/grid-security/hostkey.pem

Mandatory: No Description:

User key file location in PEM format. Only used and checked if the protocol in the url option is *https*.

cadir

Location: emir section

Default value: /etc/grid-security/certificates

Mandatory: No Description:

A path pointing to the store where the PEM certificate of the trusted Certificate Authorities can be found. Only used and checked if the protocol in the url option is *https*.

verbosity

Location: emir section
Default value: error

Mandatory: No Description:

Logging verbosity. The parameter is optional. If missing or an invalid value is given, the default value will be used. The logs are written into the log file that can be found in the <code>/var/log/emi/emird</code> directory by default.

Service_Endpoint_URL

Location: simple service entry section

Default value: No default value

Mandatory: Yes
Description:

The Service Endpoint URL to be propagated. If this option is missing an error message will be raised.

Service_Name

Location: simple service entry section

Default value: No default value

Mandatory: No
Description:

The Service Name to be propagated. If this option is missing then the service entry will contains no such component.

Service_Type

Location: simple service entry section

Default value: No default value

Mandatory: No Description:

The Service Type to be propagated. If this option is missing then the service entry will contains no such component.

Service Endpoint InterfaceName

Location: simple service entry section

Default value: No default value

Mandatory: No
Description:

The Service Endpoint Interface Name to be propagated. If this option is missing then the service entry will contains no such component.

json_file_location

Location: advanced service entry section

Default value: No default value

Mandatory: Yes Description:

The service entry can be also defined in a single external json formatted file per service. Any allowed json attributes are allowed in this way. The location of this file must be defined in this ini variable. The recommended place for these files is under the /etc/emi/emird/directory and naming them after the name of the given service with .json extension.

5 How to use EMIR API

The EMI Registry allows Services to register/publish their capabilities while the Service Consumers are able to find the deployed services.

This section contains the description of the REST-ful interface, that allows the management of the service information (or entries) by exposing the individual URIs. The normative description of the API cab also be defined as Web Application Description Language (WADL) document WADL Section 7.

5.1 Register new Services

HTTP Method: POST

URI: /serviceadmin

Content Type: application/json

Security Implications: Requires authenticated "and" authorized user access to per-

form this operation

5.1.1 Request

The message body contain a JSON Array containing the JSON objects (see below), each of which would be a service entry in the EMI registry.

Service description is defined as a Section 6 document.



Important

The only mandatory attribute is Service_Endpoint_URL, which should be unique

5.1.2 Response

The response contains similar array of JSON Objects as it was in sent request, confirming the successful update.

Status Code: OK/200

5.2 Updating the Service information

 $\mathop{\mathtt{HTTP}} \;\; \mathop{\mathtt{Method}} : PUT$

URI:/serviceadmin

Content Type: application/json

Security Implications: Requires an authenticated "and" authorized user access to

perform this operation

5.2.1 Request

The request body contain a similar JSON array object as defined POST method that contains the description of the Services to be updated. The Service Entries identified by the *Service_Endpoint_URL* key in the individual JSON objects will be updated respectively.

5.2.2 Response

The response contains similar array of JSON Objects as it was in sent request, confirming the successful update.

Status Code: OK/200

5.3 Delete existing Services

HTTP Method: DELETE

URI: /serviceadmin

Security Implications: Requires an authenticated "and" authorized user access to

perform this operation

5.3.1 Request

The Service Entry matching the Endpoint ID will be deleted from the registry only if the client executing the action has authorised access and the method is allowed by the security plugins.

Query Parameters: Service_Endpoint_ID= < Service unique Endpoint ID>

Example:/serviceadmin?Service_Endpoint_ID=urn:endpoint:emi1

5.3.2 Response

Status Code: OK/200

5.4 Querying the EMIR

HTTP Method: GET

URI:/services

Content Type: application/json

5.4.1 Request

The request contains the key-value pairs separated by ampers and $\ensuremath{\&}$

Query Parameters: AttributeName=<Attribute_Value>&AttributeName=<Attribute_Value>&...

Example: /services?Service_Type=eu.emi.es&Service_Endpoint_HealthState=ok

The additional parameters can also be added to restrict and/or paginate the result

Additional Query Parameters:

skip=Integer value

skip returns the result skipping the given number of entries

limit=Integer value

limit defines the maximum number of result containing the service entries

Response+Additional Query Parameters+:

skip=Integer value

skip returns the result skipping the given number of entries

limit=Integer value

limit defines the maximum number of result containing the service entries

The response contains an array of service entries packed in a JSON array object

Status Code: OK/200

5.5 Rich Querying in EMIR

HTTP Method: GET

URI:/services

Content Type: application/json

5.5.1 Request

The request contains the JSON document including with support for defining advanced clauses, the http://www.mongodb.org/display/DOCS/Advanced+Queries, MongoDB Advanced Queries[MongoDB JSON Query Language] describes the various types of queries

Additional keys (skip, limit) can also be added to paginate the returning results.

5.5.2 Response

The response contains the array of service entries packed in a JSON array object

Status Code: OK/200

5.6 Querying the EMIR for GLUE 2.0 XML Documents

HTTP Method: GET

URI:/services

Content Type: application/xml

5.6.1 Request

The request contains the key-value pairs separated by ampersand &

Query Parameters: AttributeName=<Attribute_Value>&AttributeName=<Attribute_Value>&...

Example:/services?Service_Type=eu.emi.es&Service_Endpoint_HealthState=ok

The additional parameters can also be added to restrict and/or paginate the result

Additional Query Parameters:

skip=Integer value

skip returns the result skipping the given number of entries

limit=Integer value

limit defines the maximum number of result containing the service entries

5.6.2 Response

The response contains an XML document containing service entries in GLUE 2.0 format

Status Code: OK/200

5.7 Rich Querying the EMIR for GLUE 2.0 XML Documents

The request and response interface is same as defined above, however the content type must be defined as **application/xml** instead.

5.8 Viewing the Service information template

This To view the GLUE 2.0's JSON flavored service model.

HTTP Method: GET

URI:/model

Content Type: application/json

5.8.1 Request

N/A

5.8.2 Response

JSON document, as described in the /serviceadmin POST method

Status Code: OK/200

5.9 Monitoring the Registry

Allows registry users to view the registry status

```
HTTP Method: GET
URI:/ping
```

5.9.1 Request

N/A

5.9.2 Response

Status Code: OK/200

6 Appendix I

The service record JSON template of EMIR interface.

```
[ //Example Service Endpoints Records (belonging to the same \( \to \) service]

{
    "Service_ID":"s1",
    "Service_Name":"ComputingService",
    "Service_CreationTime":{"$date":"2011-07-21T11 \( \to \) :47:24Z"},
    "Service_Type":"job-management",
    "Service_Contact": [{"ContactType":"sysadmin", " \( \to \) Detail":"http://contactlink"},{"ContactType":" \( \to \) developer", "Detail":"http://contactlink"}],
    "Service_Endpoint_ID":"se1", //this should be \( \to \) unique
    "Service_Endpoint_URL":"http://1",
```

```
"Service_Endpoint_Capability":["capability1"," ←
            capability2"],
        "Service_Endpoint_Technology":"technology",
        "Service_Endpoint_InterfaceName": "interface",
        "Service_Endpoint_InterfaceVersion":["version1"," \leftarrow
            version2"],
        "Service_Endpoint_InterfaceExtension":["extension1 \leftarrow
            ", "extension2"],
        "Service_Endpoint_WSDL": "http//1.wsdl",
        "Service_Endpoint_SupportedProfile":["profile1"," \leftarrow
            profile2"],
        "Service_Endpoint_Semantics":["semantic1"," \leftarrow
            semantic2"],
        "Service_Endpoint_HealthState": "ok",
        "Service_Endpoint_HealthStateInfo": "state info",
        "Service_Endpoint_ServingState": "production",
        "Service_Endpoint_StartTime":{"$date":"2011-07-21 \leftrightarrow
            T11:47:24Z"},
        "Service_Endpoint_DowntimeAnnounce":{ "$date \leftarrow
            ":"2011-07-21T11:47:24Z"},
        "Service_Endpoint_DowntimeStart":{ "$date ←
            ":"2011-07-21T11:47:24Z"},
        "Service_Endpoint_DowntimeEnd":{"$date":"2011-07-21 ←
            T11:47:24Z"},
        "Service_Endpoint_QualityLevel": "production",
        "Service_Location_Address": "A Street 1",
        "Service_Location_Place": "Bonn",
        "Service_Location_Country": "Germany",
        "Service_Location_PostCode": "53119",
        "Service_Location_Latitude":53.3,
        "Service_Location_Longitude":4,
        "Service_ExpireOn": { "$date": "2020-07-21T11:47:24Z"}
},
        "Service_ID":"s1",
        "Service_Name": "ComputingService",
        "Service_CreationTime":{"$date":"2011-07-21T11 \leftrightarrow
            :47:24Z"},
        "Service_Type": "job-management",
        "Service_Contact": [{"ContactType":"sysadmin", " \leftrightarrow
            Detail":"http://contactlink"}, {"ContactType":" ←
            developer", "Detail":"http://contactlink"}],
        "Service_Endpoint_ID":"se2", //this should be \leftarrow
            unique
        "Service_Endpoint_URL": "http://1",
        "Service_Endpoint_Capability":["capability1"," \leftarrow
            capability2"],
        "Service_Endpoint_Technology":"technology",
        "Service_Endpoint_InterfaceName": "interface",
```

```
"Service_Endpoint_InterfaceVersion":["version1"," \leftarrow
           version2"],
        "Service_Endpoint_InterfaceExtension":["extension1 \leftarrow
            ", "extension2"],
        "Service_Endpoint_WSDL":"http//1.wsdl",
        "Service_Endpoint_SupportedProfile":["profile1"," \leftarrow
            profile2"],
        "Service_Endpoint_Semantics":["semantic1"," \leftarrow
            semantic2"],
        "Service_Endpoint_HealthState": "ok",
        "Service_Endpoint_HealthStateInfo": "state info",
        "Service_Endpoint_ServingState": "production",
        "Service_Endpoint_StartTime":{"$date":"2011-07-21 ←
            T11:47:24Z"},
        "Service_Endpoint_DowntimeAnnounce":{ "$date ←
            ":"2011-07-21T11:47:24Z"},
        "Service_Endpoint_DowntimeStart":{"$date \leftarrow
            ":"2011-07-21T11:47:24Z"},
        "Service_Endpoint_DowntimeEnd":{"$date":"2011-07-21 ←
            T11:47:24Z"},
        "Service_Endpoint_QualityLevel": "production",
        "Service_Location_Address": "A Street 1",
        "Service_Location_Place": "Berlin",
        "Service_Location_Country": "Germany",
        "Service_Location_PostCode": "53011",
        "Service_Location_Latitude":53.5,
        "Service_Location_Longitude":4,
        "Service_ExpireOn":{"$date":"2020-07-21T11:47:24Z"}
}
```

7 Appendix II

The EMIR WADL document to define the REST-ful API

```
</method>
    <method id="checkin" name="POST">
            <representation mediaType="*/*"/>
        </response>
    </method>
</resource>
<resource path="/neighbors">
    <method id="childDSRs" name="GET">
        <response>
            <representation mediaType="*/*"/>
        </response>
    </method>
</resource>
<resource path="/parent">
    <method id="childDSRs" name="GET">
        <response>
            <representation mediaType="*/*"/>
        </response>
    </method>
</resource>
<resource path="/serviceadmin">
    <method id="getServicebyUrl" name="GET">
            <representation mediaType="application/json"/>
        </response>
    </method>
    <method id="registerServices" name="POST">
        <request>
            <representation mediaType="application/json"/>
        </request>
        <response>
            <representation mediaType="application/json"/>
        </response>
    </method>
    <method id="updateServices" name="PUT">
        <request>
            <representation mediaType="application/json"/>
        </request>
        <response>
            <representation mediaType="application/json"/>
        </response>
    </method>
    <method id="deleteService" name="DELETE">
            <representation mediaType="*/*"/>
        </response>
    </method>
</resource>
<resource path="/services">
```

```
<method id="queryWithParams" name="GET">
    <response>
        <representation mediaType="application/json"/>
    </response>
</method>
<method id="queryWithJSON" name="POST">
    <request>
        <representation mediaType="application/json"/>
    </request>
    <response>
        <representation mediaType="application/json"/>
    </response>
</method>
<method id="queryXMLWithJSON" name="POST">
    <request>
        <representation mediaType="application/json"/>
    </request>
    <response>
        <representation mediaType="application/xml"/>
    </response>
</method>
<method id="queryXMLWithParams" name="GET">
        <representation mediaType="application/xml"/>
        <representation mediaType="text/xml"/>
    </response>
</method>
<resource path="/urls">
    <method id="getServiceEndPoints" name="GET">
        <response>
            <representation mediaType="application/json \leftarrow
        </response>
    </method>
</resource>
<resource path="/types">
    <method id="getServiceTypes" name="GET">
        <response>
            <representation mediaType="application/json \leftarrow
                "/>
        </response>
    </method>
</resource>
<resource path="/query.xml">
    <method id="queryXml" name="GET">
        <response>
            <representation mediaType="application/xml \leftarrow
                "/>
            <representation mediaType="text/xml"/>
        </response>
```

```
</method>
            </resource>
            <resource path="/pagedquery">
                <method id="pagedQuery" name="GET">
                    <response>
                        <representation mediaType="*/*"/>
                    </response>
                </method>
            </resource>
        </resource>
        <resource path="/model">
            <method id="getModel" name="GET">
                <response>
                    <representation mediaType="text/html"/>
                    <representation mediaType="application/json"/>
                </response>
            </method>
        </resource>
        <resource path="/ping">
            <method id="ping" name="GET">
                <response>
                    <representation mediaType="application/json"/>
                    <representation mediaType="text/plain"/>
                </response>
            </method>
        </resource>
    </resources>
</application>
```