


Lab - Implement CoPP

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask
R1	G0/0/0	172.16.12.1	255.255.255.252
	G0/0/1	10.10.1.1	255.255.255.0
R2	G0/0/0	172.16.12.2	255.255.255.252
A1	VLAN 1	10.10.1.4	255.255.255.0

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Verify Initial Connectivity

Part 3: Implement a CoPP Policy on R1

Part 4: Verify the CoPP Policy on R1

Part 5: (Challenge) Further Classify Default Traffic

Background / Scenario

Control Plane Policing (CoPP) is a protection feature for the router's control plane CPU. CoPP can granularly permit, drop, or rate-limit traffic to or from the CPU using a Modular QoS CLI (MQC) policy. The CoPP policy is applied to a dedicated control-plane interface which protects the CPU from unexpected extreme rates of traffic that could impact the stability of the router.

CoPP handles all process-switched traffic, such as packets logged by an ACL or IP packets with header (TTL) options. Other types of traffic directed to the control plane include routing updates, (OSPF, EIGRP and BGP) as well as management traffic, including Telnet, SNMP, SSH, NTP, and HTTP etc.

The focus of this lab is using the Cisco IOS Modular QoS CLI (MQC) to implement CoPP.

Note: This lab is an exercise in configuring CoPP policies and does not necessarily reflect network best practices.

Note: The routers used with CCNP hands-on labs are Cisco 4221 with Cisco IOS XE Release 16.9.4 (universalk9 image). The switch used in the lab is a Cisco Catalyst 2960 with Cisco IOS Release 15.2(2)

(lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

Note: Make sure that the routers and switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

Required Resources

- 2 Routers (Cisco 4221 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 1 Switch (Cisco 2960 with Cisco IOS Release 15.2(2) lanbasek9 image or comparable)
- 1 PC (Choice of operating system with terminal emulation program and a packet capture utility installed)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings and interface addressing on devices.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

Step 2: Configure basic settings for each device.

a. Console into each device, enter global configuration mode, and apply the basic settings. The startup configurations for each device are provided below.

Router R1

```
hostname R1
no ip domain lookup
ip domain name CCNPv8.CoPP.Lab
username admin privilege 15 algorithm-type scrypt secret cisco123
banner motd # R1, Control Plane Policing
line con 0
 exec-timeout 0 0
logging synchronous
exit
interface q0/0/1
 ip address 10.10.1.1 255.255.255.0
no shutdown
 exit
interface q0/0/0
 ip address 172.16.12.1 255.255.255.252
 no shutdown
 exit
router eigrp 123
  eigrp router-id 0.0.0.1
  network 172.16.12.0 0.0.0.3
```

network 10.10.1.0 0.0.0.255

```
exit
   line vty 0 4
   login local
   transport input telnet ssh
   exit
   crypto key generate rsa modulus 1024
Router R2
   hostname R2
   no ip domain lookup
   ip domain name CCNPv8.CoPP.Lab
   username admin privilege 15 algorithm-type scrypt secret cisco123
  banner motd # R2, Control Plane Policing
   line con 0
    exec-timeout 0 0
   logging synchronous
   exit
   interface g0/0/0
   ip address 172.16.12.2 255.255.255.252
   no shutdown
   exit.
   router eigrp 123
     eigrp router-id 0.0.0.2
    network 172.16.12.0 0.0.0.3
     exit
   line vty 0 4
   login local
   transport input telnet ssh
   crypto key generate rsa modulus 1024
    end
Switch A1
  hostname A1
   no ip domain lookup
   username admin privilege 15 algorithm-type scrypt secret cisco123
   ip domain name CCNPv8.COPP.LAB
  banner motd # A1, Control Plane Policing #
   spanning-tree mode rapid-pvst
   line con 0
   exec-timeout 0 0
   logging synchronous
   exit
   line vty 0 15
```

```
login local
 transport input telnet ssh
interface range f0/1-24, g0/1-2
 shutdown
 exit
interface range f0/1
switchport mode access
 no shutdown
 exit.
interface vlan 1
 ip address 10.10.1.4 255.255.255.0
no shut
 exit
 ip default-gateway 10.10.1.1
 crypto key generate rsa modulus 1024
 end
```

- b. Set the clock on each device to UTC time.
- c. Save the running configuration to startup-config.
- d. Verify ICMP connectivity between the devices.

Part 2: Verify Initial Connectivity

It is always advisable to test network connectivity and services before applying any policies. This ensures that the network is fully functional, and that the loss of connectivity or functionality is due to the applied policy and not a pre-existing network issue.

When testing TCP connectivity, some services will prompt for a username/password. The pre-configured username is **admin** and password is **cisco123**.

Step 1: Test Telnet connectivity.

From A1, test Telnet connectivity to R1 and R2. When prompted for a username / password use **admin** and **cisco123**. You should be successful. Troubleshoot as needed.

Step 2: Test SSH connectivity.

From A1, test SSH connectivity to R1 and R2. When prompted for a username / password use **admin** and **cisco123**. You should be successful. Troubleshoot as needed.

Part 3: Implement a CoPP Policy on R1

In this part, you will configure ACLs to identify traffic flows. You will then use these ACLs in class maps to classify the traffic for CoPP. Next, you will bind the class maps to a CoPP policy map. This policy map will apply the policing and actions to take for each class map. Finally, you will apply the policy map to the control plane.

Step 1: Configure named ACLs to identify traffic flows.

Understanding what is needed for traffic classification can be achieved from network protocol analysis. Cisco NetFlow and Embedded Packet Capture (EPC) can be used to classify network traffic.

After the traffic has been identified, ACLs can be built for matching the identified traffic. The definition of these ACLs is one of the most critical steps in the CoPP process. MQC uses these ACLs to define the traffic classes. Appropriate granularity in the classification of these protocols within these ACLs allows for better protection of the control plane CPU.

a. Configure an extended ACL using the name **TELNET** to identify Telnet traffic.

```
R1(config)# ip access-list extended TELNET
R1(config-ext-nacl)# permit tcp any any eq 23
R1(config-ext-nacl)# exit
```

b. Configure an extended ACL using the name EIGRP to identify all EIGRP traffic.

```
R1(config)# ip access-list extended EIGRP
R1(config-ext-nacl)# permit eigrp any any
R1(config-ext-nacl)# exit
```

c. Configure an extended ACL using the name **SSH** to identify all SSH traffic.

```
R1(config)# ip access-list extended SSH
R1(config-ext-nacl)# permit tcp any any eq 22
R1(config-ext-nacl)# exit
```

d. Configure an extended ACL using the name ICMP to identify ICMP traffic.

```
R1(config)# ip access-list extended ICMP
R1(config-ext-nacl)# permit icmp any any
R1(config-ext-nacl)# exit
```

Note: Packets not matching any permit statements will be sent to the control plane CPU on R1.

Step 2: Configure class maps for CoPP on R1.

Class maps are used to classify traffic for CoPP. The ACLs defined previously specify which IP packets belong to which classes. The mapping of ACLs to class maps completes the traffic classification process.

Class maps support multiple match criteria; however, in this configuration a single-match criteria will satisfy basic functionality.

a. Configure a class map named **CM-TELNET** to match IP packets that should be dropped and never reach the control plane CPU.

```
R1(config)# class-map match-all CM-TELNET
R1(config-cmap)# match access-group name TELNET
R1(config-cmap)# exit
```

b. Configure a class map named **CM-EIGRP** to match EIGRP packets. This will allow you to apply a policy to these routing packets. The same could be done for OSPF or BGP packets if those routing protocols were active.

```
R1(config) # class-map match-all CM-EIGRP
R1(config-cmap) # match access-group name EIGRP
R1(config-cmap) # exit
```

c. Configure a class map named **CM-SSH** to match IP packets in the ACL named SSH. These IP packets are SSH packets destined to the management plane.

```
R1(config)# class-map match-all CM-SSH
R1(config-cmap)# match access-group name SSH
```

```
R1(config-cmap)# exit
```

d. Configure a class map named **CM–ICMP** to match IP packets in the ACL named **ICMP**. These IP packets are ICMP packets destined to the router.

```
R1(config) # class-map match-all CM-ICMP
R1(config-cmap) # match access-group name ICMP
R1(config-cmap) # exit
```

Step 3: Configure a policy map for CoPP on R1.

The policy map defines the "baseline" service policy for each traffic classification. For each traffic class previously configured, the policy map applies the control plane policing rates and actions.

Finding the optimal police rate without impacting network stability requires understanding traffic flows over time. To guarantee that CoPP does not introduce stability issues, the violate action should be set to transmit for all vital classes. When the CoPP policy is confirmed to be operationally effective, that would be the time to convert the appropriate "exceed-action" transmit actions to drop actions.

a. Configure a policy map named PM-COPP on R1.

```
R1(config) # policy-map PM-COPP
```

- b. Associate the traffic class maps to the policy map and configure the following policing and action policies:
 - For Telnet packets, configure policing at 8 kbps. Then set the conform action to drop and the exceed action to drop. This will effectively drop all Telnet packets that match the class map.
 - For EIGRP packets, configure policing at 20 packets per second (pps). Then set the conform action to transmit and the exceed action to drop.
 - For SSH packets, configure the policing at 50 kbps, set the conform action to transmit and the exceed action to transmit. This will effectively transmit all SSH packets that match the class map.
 - For ICMP packet, configure policing at 10pps. Then set the conform action to transmit and the exceed action to drop.

```
R1(config-pmap) # class CM-TELNET
R1(config-pmap-c) # police 8000 conform-action drop exceed-action drop
R1(config-pmap-c-police) # exit
R1(config-pmap-c) # class CM-EIGRP
R1(config-pmap-c) # police rate 10 pps conform-action transmit exceed-action transmit
R1(config-pmap-c-police) # exit
R1(config-pmap-c) # class CM-SSH
R1(config-pmap-c) # police 50000 conform-action transmit exceed-action transmit
R1(config-pmap-c-police) # exit
R1(config-pmap-c) # class CM-ICMP
R1(config-pmap-c) # police rate 10 pps conform-action transmit exceed-action drop
R1(config-pmap-c-police) # exit
```

c. Associate the default class map with the traffic policy. Set the class to **class-default** and configure policing at 12 kbps. Then set the conform action to transmit and the exceed action to transmit.

```
R1(config-pmap-c)# class class-default
R1(config-pmap-c)# police 12000 conform-action transmit exceed-action transmit
R1(config-pmap-c-police)# end
```

Note: The class **class-default** is automatically placed at the end of the policy map. By the nature of CoPP-matching mechanisms, certain traffic types will always end up falling into the default class. This includes Layer 2 keepalives and non-IP traffic. Because these traffic types are required to maintain the network control plane, the **class-default** should never be policed with both conform and exceed actions set to drop.

Step 4: Apply the CoPP policy to the control plane virtual interface on R1.

The policy map is applied to the control plane virtual interface in the inbound direction using the **service-policy** command. Only traffic destined for the router's control plane will be affected by the CoPP policy.

a. Enter control plane configuration mode to apply a CoPP policy.

```
R1# conf t
R1(config)# control-plane
```

b. Next, attach the policy map to the control plane interface using the **service-policy input** command and specify the policy map named PM–COPP on the control plane virtual interface.

```
R1(config-cp)# service-policy input PM-COPP
R1(config-cp)# end
```

Part 4: Verify the CoPP Policy on R1.

Within a few moments of the CoPP policy being applied, dynamic information can be seen about the actual policy including rate information and the number of bytes and packets that conformed to or exceeded the configured policies.

Step 1: Issue the show access-list command.

The **show access-list** command identifies specific traffic for each ACL.

R1# show access-lists

```
Extended IP access list EIGRP

10 permit eigrp any any
Extended IP access list ICMP

10 permit icmp any any
Extended IP access list SSH

10 permit tcp any any eq 22
Extended IP access list TELNET

10 permit tcp any any eq telnet
```

Step 2: Issue the show class-map command.

The only class maps configured are those used for CoPP. Notice the **match-any** statement under the **class-default** class map. The **match** statement was automatically added when the class map was included in the policy map configuration.

R1# show class-map

```
Class Map match-all CM-TELNET (id 1)
Match access-group name TELNET

Class Map match-any class-default (id 0)
Match any

Class Map match-all CM-ICMP (id 5)
Match access-group name ICMP

Class Map match-all CM-EIGRP (id 2)
Match access-group name EIGRP

Class Map match-all CM-SSH (id 3)
```

Match access-group name SSH

Step 3: Issue the show policy-map command.

Notice the policy map shows the policing rates that were configured for each class map, including the **class-default** class map.

R1# show policy-map

```
Policy Map PM-COPP
 Class CM-TELNET
   police cir 8000 bc 1500
     conform-action drop
     exceed-action drop
 Class CM-EIGRP
  police rate 10 pps
     conform-action transmit
     exceed-action transmit
 Class CM-SSH
   police cir 50000 bc 1562
     conform-action transmit
     exceed-action transmit
     Class CM-ICMP
   police rate 10 pps
     conform-action transmit
     exceed-action drop
      Class class-default
   police cir 12000 bc 1500
     conform-action transmit
     exceed-action transmit
```

Step 4: Issue the show policy-map control-plane command.

This is the most useful command for verifying CoPP functionality. Notice that the EIGRP packets conform to the policing rule. Because no packets exceeded the defined rates for the EIGRP class map, all packets are transmitted to the control plane for processing. Note that your packet count will vary from the example below.

R1# show policy-map control-plane

```
Control Plane

Service-policy input: PM-COPP

Class-map: CM-TELNET (match-all)
        0 packets, 0 bytes
        5 minute offered rate 0000 bps, drop rate 0000 bps
Match: access-group name TELNET
    police:
        cir 8000 bps, bc 1500 bytes
        conformed 0 packets, 0 bytes; actions:
        drop
        exceeded 0 packets, 0 bytes; actions:
        drop
        conformed 0000 bps, exceeded 0000 bps
```

```
Class-map: CM-EIGRP (match-all)
  34 packets, 2516 bytes
  5 minute offered rate 0000 bps, drop rate 0000 bps
 Match: access-group name EIGRP
  police:
      rate 10 pps, burst 2 packets
    conformed 34 packets, 2516 bytes; actions:
      transmit
    exceeded 0 packets, 0 bytes; actions:
      transmit
    conformed 0 pps, exceeded 0 pps
Class-map: CM-SSH (match-all)
  0 packets, 0 bytes
  5 minute offered rate 0000 bps, drop rate 0000 bps
 Match: access-group name SSH
  police:
      cir 50000 bps, bc 1562 bytes
    conformed 0 packets, 0 bytes; actions:
      transmit
    exceeded 0 packets, 0 bytes; actions:
      transmit
    conformed 0000 bps, exceeded 0000 bps
Class-map: CM-ICMP (match-all)
  0 packets, 0 bytes
  5 minute offered rate 0000 bps, drop rate 0000 bps
 Match: access-group name ICMP
  police:
      rate 10 pps, burst 2 packets
    conformed 0 packets, 0 bytes; actions:
      transmit
    exceeded 0 packets, 0 bytes; actions:
      drop
    conformed 0 pps, exceeded 0 pps
Class-map: class-default (match-any)
  333 packets, 19788 bytes
  5 minute offered rate 0000 bps, drop rate 0000 bps
 Match: any
  police:
      cir 12000 bps, bc 1500 bytes
    conformed 333 packets, 19788 bytes; actions:
      transmit
    exceeded 0 packets, 0 bytes; actions:
      transmit
    conformed 0000 bps, exceeded 0000 bps
```

Step 5: From R2, ping R1.

From R2, use the command **ping 172.16.12.1 repeat 20** to simulate a DoS attach on the control plane on R1. Notice the success rate of 70 percent and the failed pings as indicated by the period symbol (.) among the (successful) exclamation marks. From the output above, this indicates that R1 is dropping every third ICMP packet, based on the policy for rate limiting ICMP traffic to the control plane on R1.

```
R2# ping 172.16.12.1 repeat 20

Type escape sequence to abort.

Sending 20, 100-byte ICMP Echos to 172.16.12.1, timeout is 2 seconds:
!!.!!.!!.!!.!!

Success rate is 70 percent (14/20), round-trip min/avg/max = 1/1/2 ms
```

Step 6: From R2, access R1 via Telnet.

From R2 enter the **telnet 172.17.12.1** command. Notice that all Telnet traffic to R1 is not successful. This is because our policy is to drop all Telnet traffic directed to the control plane on R1.

```
R2# telnet 172.16.12.1
Trying 172.16.12.1 ...
% Connection timed out; remote host not responding
```

Step 7: From R2, access A1 via Telnet.

From R2, enter the **telnet 10.10.1.4** command. When prompted for a username / password enter **admin** and **cisco123**. Notice that Telnet traffic from R2 through R1 to A1 is successful.

```
R2# telnet 10.10.1.4

Trying 10.10.1.4 ... Open
A1, Control Plane Policing

User Access Verification

Username: admin
Password:
A1# exit

[Connection to 10.10.1.4 closed by foreign host]
```

Step 8: SSH from R2 to R1.

From R2 SSH into R1 using the **ssh -l admin 172.16.12.1** command. When prompted for a password enter **cisco123**. Then enter the **show running-config** command to generate SSH packets.

```
R2# ssh -l admin 172.16.12.1
Password:
R1, Control Plane Policing
R1# show running-config
Building configuration...
(output omitted)
R1# exit
```

[Connection to 172.16.12.1 closed by foreign host]

Step 9: Investigate the CoPP policy on R1.

a. On R1, repeat the **show policy-map control-plane** command to investigate policing of ICMP, Telnet, SSH, EIGRP and other packets.

Note: Your packet counts will vary from the following output.

```
R1# show policy-map control-plane
Control Plane
 Service-policy input: PM-COPP
   Class-map: CM-TELNET (match-all)
      4 packets, 232 bytes
      5 minute offered rate 0000 bps, drop rate 0000 bps
     Match: access-group name TELNET
     police:
          cir 8000 bps, bc 1500 bytes
        conformed 4 packets, 232 bytes; actions:
          drop
        exceeded 0 packets, 0 bytes; actions:
          drop
        conformed 0000 bps, exceeded 0000 bps
   Class-map: CM-EIGRP (match-all)
      487 packets, 36038 bytes
      5 minute offered rate 0000 bps, drop rate 0000 bps
     Match: access-group name EIGRP
      police:
          rate 10 pps, burst 2 packets
        conformed 487 packets, 36038 bytes; actions:
          transmit
        exceeded 0 packets, 0 bytes; actions:
          transmit
        conformed 0 pps, exceeded 0 pps
   Class-map: CM-SSH (match-all)
      68 packets, 5776 bytes
      5 minute offered rate 0000 bps, drop rate 0000 bps
     Match: access-group name SSH
      police:
          cir 50000 bps, bc 1562 bytes
        conformed 68 packets, 5776 bytes; actions:
          transmit
        exceeded 0 packets, 0 bytes; actions:
          transmit
        conformed 0000 bps, exceeded 0000 bps
   Class-map: CM-ICMP (match-all)
```

```
10 packets, 1000 bytes
  5 minute offered rate 0000 bps, drop rate 0000 bps
 Match: access-group name ICMP
  police:
      rate 10 pps, burst 2 packets
    conformed 7 packets, 700 bytes; actions:
      transmit
    exceeded 3 packets, 300 bytes; actions:
    conformed 0 pps, exceeded 0 pps
Class-map: class-default (match-any)
  4701 packets, 281816 bytes
  5 minute offered rate 0000 bps, drop rate 0000 bps
 Match: any
  police:
      cir 12000 bps, bc 1500 bytes
    conformed 4701 packets, 281816 bytes; actions:
      transmit
    exceeded 0 packets, 0 bytes; actions:
      transmit
    conformed 0000 bps, exceeded 0000 bps
```

- b. From the output above note the following:
 - Notice that all four Telnet packets were dropped.
 - All EIGRP packets conform to the policing rule and are forwarded the control plane for processing.
 - All SSH packets also conform to the policing rule and are forwarded to the control plane for processing.
 - Ping packets are rate limited to 10 pps. This allows a "burst" of two packets, with every third packet being dropped.

Part 5: (Challenge) Further Classify Default Traffic

Notice in the output of the **show policy-map control-plane** command that there is a substantial number of packets that are being matched to the **class-default** class map. One solution to help identify the source of these packets would be to configure a "CATCH-ALL" class map. This new class map would collect any remaining traffic that have not matched previous class maps and are destined to the device's control plane. This CATCH-ALL class would prevent packets from ending up in the **class-default** class map. For example, an ACL called CATCH-ALL could be defined as follows:

```
R1(config)# ip access-list extended CATCH-ALL
R1(config-ext-nacl)# permit icmp any any
R1(config-ext-nacl)# permit udp any any
R1(config-ext-nacl)# permit tcp any any
R1(config-ext-nacl)# permit ip any any
R1(config-ext-nacl)# exit
```

This ACL could be matched to a class map called CM-CATCH-ALL that could be policed to 50 kbps with a confirm action of transmit and an exceed action of drop.

Implement this new class map in your policy map, repeat the verifications in Part 4, and then view the output of the **show policy-map control-plane** command to see where this default traffic is classified.

Reflection Questions

- 1. Why is R2 able to use Telnet through R1 to A1?
- 2. When initially deploying CoPP, how can you prevent disruption of legitimate control plane traffic?

Router Interface Summary Table

Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
4221	Gigabit Ethernet 0/0/0 (G0/0/0)	Gigabit Ethernet 0/0/1 (G0/0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
4300	Gigabit Ethernet 0/0/0 (G0/0/0)	Gigabit Ethernet 0/0/1 (G0/0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.