

OASE Operation Autonomy Support Engine Online installation

******"Operation Autonomy Support Engine" is referred to as "OASE" in this manual.

Table of contents

1. Introduction	4. OAS	SE operation check	
1.1 About this manual	4.1	Operation check	(1/4)
	4.2	Operation check	(2/4)
2. System configuration	4.3	Operation check	(3/4)
2.1 Requirements(1/2)	4.4	Operation check	(4/4)
2.2 Requirements(2/2)			
3. OASE environment construction p	rocedure		

Online installation 3.1 3.2 Preparation (1/2) 3.3 OASE environment construction flow 3.4 Environment construction (1/11) 3.5 (2/11)Environment construction 3.6 Environment construction (3/11) 3.7 (4/11)Environment construction 3.8 **Environment construction** (5/11)3.9 **Environment construction** (6/11)(7/11)3.10 Environment construction (8/11)3.11 Environment construction 3.12 Environment construction (9/11)3.13 Environment construction (10/11)(11/11)

3.14 Environment construction

1. Introduction



1.1 About this manual

About this manual

• This manual describes the procedure to construct OASE in all-in-one configuration(described later) with installer using external repository.



2. System configuration



2.1 Environment · Conditions

- Environment necessary to use OASE.
 - For details regarding the environment needed in order to use OASE, please refer to the "Exastro-OASE_Environment_Construction_manual_Basics"


3. OASE environment construction procedure



3.1 Online installation

About the installation procedure

 If the OASE server is in online environment, the system configuration is performed by installing required library from internet and executing OASE installer.



3.2 Preparation

OASE Environment Construction tools


• The tools used to construct OASE Environments are listed below.

Description	File	Storage path
OASE Installer	oase_installer.sh	/(installation file storage)/oase/oase_install_package/install_scripts/
Answer File	oase_answers.txt	/(installation file storage)/oase/oase_install_package/install_scripts/

3.4 OASE environment construction flow

Environment construction flow (Online)

The flow of environment construction is as follows.



3.5 Environment construction (1/11)

- Download file from Github
 - Download file via the following command.

```
$ wget https://github.com/exastro-suite/oase/archive/vx.x.x.tar.gz
```

- **Please install wget command beforehand.
- ※Please change the version(x.x.x) properly.

Change the privilege of installation script

Extract zip file and change the privilege of installation script

```
$ tar zxf vx.x.x.tar.gz
$ find ./oase-x.x.x/oase_install_package/install_scripts/ -type f -name *.sh | xargs chmod 755
```

- Edit answers file
 - •/oase-x.x.x/oase_install_package/install_scripts/oase_answers.txt

3.6 Environment construction (2/7)

Edit answers file(1/3)

 The following list shows how to edit the OASE Environment Setting file (oase_answers.txt).

Item	Required	Default value	Description
install_mode	0	Install_Online	Choose between one of the following modes. (Install_Online, Install_Offline, Gather_Library, Versionup_All, Versionup_OASE, Uninstall)
RabbitMQ_username	0	administrator	Username of RabbitMQ
RabbitMQ_password	0	password	Password of RabbitMQ
RabbitMQ_queuename	0	oase	Queue name of RabbitMQ (Since it will be generated, any desired name is OK)
RabbitMQ_ipaddr	0		IP address of RabbitMQ
db_root_password	0	password	Root password of MySQL
db_name	0	OASE_DB	Name of the MySQL database for OASE
db_username	0	OASE_USER	Username of the MySQL database for OASE
db_password	0	OASE_PASSWD	Password of the MySQL database for OASE
db_erase	0	-	Erase or keep the database when uninstalling OASE
jboss_root_directory	0	/Exastro/WildFl y	Installation path of Jboss
rhdm_adminname	0	admin000	Administrator name of RHDM

3.7 Environment construction (3/7)

Edit answers file(2/3)

 The following list shows how to edit the OASE Environment Setting file (oase_answers.txt).

Item	Required	Default value	Description
rhdm_password	0	password@1	Password of RHDM
dm_ipaddrport	0	localhost:8080	IP address and port number of RHDM
rulefile_rootpath	0	/exastro/rule	Root path of RHDM rule setting file (Since it will be generated, any desired path is OK)
apply_ipaddrport	0	127.0.0.1:50001	IP address and port to start Apply service
mavenrep_path	0	/root/.m2/repository/com/o ase/	Storage path of RHDM Maven jar file
oasemail_smtp	0	"{'IPADDR':'127.0.0.1','POR T':25,'AUTH':False}"	Setting of OASE mail server
oase_directory	0	/exastro	Installation target directory of OASE
oase_session_engine	0	-	The way to keep OASE session
ev_location	0	-	IP address to execute clone job when connected with ActiveDirectory
oase_language	0	en	Language of OASE
oase_os	0	-	Environment OS

3.7 Environment construction (4/11)

Edit answers file(3/3)

 The following list shows how to edit the OASE Environment Setting file (oase_answers.txt).

Item	Required	Default value	Description
oase_domain	0	exastro-oase.local	OASE Domain name
certificate_path	Optional	_	File path for user specified SSL server Certificate. (Enter only when using an user specified SSL certificate. Specify an absolute path)
private_key_path	Optional	_	File path for user specified SSL Private keys. (enter only when using an user specified SSL private key. Specify an absolute path)

3.8 環境構築 (5/11)

- User specified server certificates and private keys.
 - It is possible to use files prepared by users as server certificates and private keys. If you want to use them, please prepare both a server certificate and a private key and input their file paths to "Certificate_path" and "private_key_path" respectively in the answer file. It is not possible to use only either server certificates or private keys.
 - If the server certificate includes an intermediate certificate, Create a file that connects the two and set the path of the file to "certificate_path" Example of Creation command #cat(Server certificate file)(Intermediate certificate file)->(Linked server certificate file).
 - If nothing is input for "certificate_path" and "private_key_path",
 The ITA installer will use the value of "ita_domain" in the answer file to create and install the self-certificate.
 - (**The "ita_domain" is used as the common name when creating the self-certificate. It is also the file name for the self-certificate and the private key.

3.9 環境構築(6/11)

- When installing, the server certificate and private key are placed in the (/etc/pki/tls/certs). However, since they will be removed from that directory when uninstalled, please manage the original server certificate and private key files with care when using user-specified server certificates and private keys.
- When uninstalling, if both "certificate_path" and "private_key_path" in the answer file (oase_answers.txt) are specified, the specified files will be deleted. If no file is specified, the name specified in "oase_domain" will be used to delete the used file.

16

3.10 環境構築 (7/11)

Answer file example.(oase_answers.txt) 1/4

• The following shows an example of the answer file(oase_answers.txt):

```
("Install_Online", "Install_Offline", "Gather_Library", "Versionup_All", "Versionup_QASE", "Uninstall")
#e.g) install_mode:Install_Online
install_mode:Install_Online
RabbitMO
====================================
# Decide the RabbitMQ_username.
#e.g) RabbitMQ_username:sample_rabbitmq_username
abbitMQ_username:admin
# Decide the RabbitMO_password.
# e.g) RabbitMQ_password:sample_rabbitmq_password
CabbitMO password:password
# Decide the RabbitMO_queuename.
#e.g) RabbitMQ_queuename:oase
 abbitMO_queuename:oase
# Enter IP address for RabbitM0.
e.g) RabbitMQ_ipaddr:127.0.0.1
RabbitMQ_ipaddr:
===============================
# MariaDB
# Enter the MariaDB root user's password
e.g) db_root_password;sample_root_password
db_root_password:password
# Decide the database name, username, and password for OASE.
 e.g) db_name:sample_db_name
db_name:OASE_DB
e.g) db_username:sample_db_username
db_username: OASE_USER
# e.g) db_password:sample_db_password
db_password:OASE_PASSHD
 In uninstall mode.
  Select "erase" or "leave" oase database
```

3.11 環境構築(8/11)

Answer file (oase_answers.txt) description sample 2/4

```
Select "erase" or "leave" oase database
 e.g) db_erase:erase
db_erase:erase
################################
‡ JBoss EAP
.
Enter JBoss install directory.
 e.g) jboss_root_directory:/exastro/JBossEAP
iboss_root_directory:/exastro/JBossEAP
#################################
**********************
 Decide the Administrator name, password.
# e.g) rhdm_adminname:admin0000
rhdm_adminname:admin0000
# e.g) rhdm password:password@1
rhdm password:password@1
# Enter IP address & port for Decision Manager.
e.g) dm_ipaddrport:localhost:8080
dm_ipaddrport:localhost:8080
********************
 RULEFILE
!#################################
 Enter root path for RULEFILE.
‡e.g) rulefile_rootpath:/exastro/rule
rulefile_rootpath:/exastro/rule
##############################
Enter IP address & port for APPLY SERVICE.
e.g) apply_ipaddrport:127.0.0.1:50001
apply_ipaddrport:127.0.0.1:50001
```

3.12 環境構築 (9/11)

Answer file (oase_answers.txt) description sample 3/4

```
#################################
# Maven
###############################
# Enter repository path for Maven.
e.g) mavenrep_path:/root/.m2/repository/com/oase/
mavenrep_path:/root/.m2/repository/com/oase/
##############################
# OASEメールSMTP設定
# Enter smtp settings.
 e.g) oasemail_smtp:"{'IPADDR':'127.0.0.1','PORT':25,'AUTH':False}"
oasemail smtp:"{'IPADDR':'127.0.0.1','PORT':25,'AUTH':False}"
################################
‡ OASEインストールディレクトリ
# Enter OASE install directory.
e.g) oase directory:/exastro
oase directory:/exastro
###################################
 settings.py
# Decide the EVTIMER SERVER location
e.g) ev_location:127.0.0.1
ev_location:127.0.0.1
Select language. ("ja")
#e.g) oase_language:ja
oase_language:ja
Select Operation System. ("CentOS7" or "RHEL7" or "RHEL8")
 e.g) oase_os:RHEL7
oase_os:RHEL8
```

3.13 環境構築(10/11)

Answer file (oase_answers.txt) description sample 4/4

```
##############################
Enter the oase domain name.
 e.g) oase_domain:exastro-oase.local
oase domain:exastro-oase.local
 Enter when using user-specified certificates and private keys.
 If no file path is entered for both "certificate_path" and "private_key_path",
 the OASE installer creates and installs a self-certificate and private key
 using the values entered in "oase_domain".
 Enter the file path where the certificate to be install.
 e.g) certificate_path:/temp/etc_pki_tls_certs/exastro-oase.crt
certificate_path:
Enter the file path where the private key to be install.
 e.g) private_key_path:/temp/etc_pki_tls_certs/exastro-oase.key
private_key_path:
```

3.11 Environment construction (7/7)

Change directory

 Move to the directory which contains the settings file and shell for environment construction

```
$ cd oase-x.x.x/oase_install_package/install_scripts
```

- Execute environment construction tool(online version)
 - Execute environment construction tool with the following command.

```
$ sh oase online installer.sh
```

• The installation of OASE is completed.

4. OASE operation check



4.1 Operation check (1/4)

Access URL

- Please access the login screen from the following URL.
- URL : https://exastro-oase/oase_web/top/login
- ****Accessing from both HTTP and HTTPS are available after installation.**

Since HTTP is insecure, accessing from HTTPS is recommended.

Please check from Operation check(3/7) for the method to access from HTTP.


Login

- Please enter the specific Login ID and default password then click the [Login] button when the login screen of OASE is displayed.
 - Login ID : administrator
 - Default password : oaseoaseoase
- The screen will move to [Change password screen] if it is the first login after installation.
- Please change the default password from the change password screen.

4.4 Operation check (2/4)

OASE login screen

• If OASE is installed properly, the following login screen will be displayed.



4.5 Operation check (3/4)

- Check contents according to the display of each menu
 - Please check if the following menu are displayed after login.

Function	Menu
OASE screen	DashBoard
	Rule
	System
	Management

4.4 Operation check (4/4)

Preparation for accessing with HTTPS.

- Register the host set in the Answer file's "oase_domain" to the environment's DNS Server or the operator device's "hosts".
- Import the certificate to the Operator device (Windows)
 If you are not using user specified server certificates, the server certificate can be found in the following path in the OASE install package.

Directory	File name
/etc/pki/tls/certs	[Host name set in the Answer file's "oase_domain"].crt

If you are using user certificates, please use the certificate file set in the Answer file's "Certificate_path".

Import the certificate to your Web browser.

Access URL via HTTP

- Please access the login screen via the following URL
- URL : http:// (IP address of server)
- ※ You can also access through the server's IP Address.

The steps after connection is the same as HTTPS.

