## **StarPU Handbook**

for StarPU 1.2.0rc5

This manual documents the usage of StarPU version 1.2.0rc5. Its contents was last updated on 17 December 2015.

Copyright © 2009-2013 Université de Bordeaux

Copyright © 2010-2015 CNRS Copyright © 2011, 2012 INRIA

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

## **Contents**

1 Introduction				3
	1.1	Motivat	tion	3
	1.2	StarPU	J in a Nutshell	3
		1.2.1	Codelet and Tasks	3
		1.2.2	StarPU Data Management Library	4
	1.3	Applica	ation Taskification	4
	1.4	Glossa	ıry	4
	1.5	Resear	rch Papers	5
	1.6	StarPU	J Applications	5
	1.7	Further	r Reading	5
ı	Star	rPU Ba	asics	7
2	Buil	ding and	d Installing StarPU	9
	2.1	Installir	ng a Binary Package	9
	2.2	Installir	ng from Source	9
		2.2.1	Optional Dependencies	9
		2.2.2	Getting Sources	9
		2.2.3	Configuring StarPU	10
		2.2.4	Building StarPU	10
		2.2.5	Installing StarPU	10
	2.3	Setting	up Your Own Code	11
		2.3.1	Setting Flags for Compiling, Linking and Running Applications	11
		2.3.2	Running a Basic StarPU Application	11
		2.3.3	Running a Basic StarPU Application on Microsoft Visual C	11
		2.3.4	Kernel Threads Started by StarPU	12
		2.3.5	Enabling OpenCL	12
	2.4	Benchr	marking StarPU	12
		2.4.1	Task Size Overhead	13
		2.4.2	Data Transfer Latency	13
		2.4.3	Matrix-Matrix Multiplication	13

iv CONTENTS

	2.4.4 Cholesky Factorization		13
	2.4.5 LU Factorization		13
	2.4.6 Simulated benchmarks		13
Basi	sic Examples		15
3.1	Hello World Using The C Extension		15
3.2	Hello World Using StarPU's API		16
	3.2.1 Required Headers		16
	3.2.2 Defining A Codelet		16
	3.2.3 Submitting A Task		16
	3.2.4 Execution Of Hello World		17
	3.2.5 Passing Arguments To The Codelet		17
	3.2.6 Defining A Callback		18
	3.2.7 Where To Execute A Codelet		18
3.3	Vector Scaling Using the C Extension		19
	3.3.1 Adding an OpenCL Task Implementation		20
	3.3.2 Adding a CUDA Task Implementation		21
3.4	Vector Scaling Using StarPU's API		21
	3.4.1 Source Code of Vector Scaling		22
	3.4.2 Execution of Vector Scaling		23
3.5	Vector Scaling on an Hybrid CPU/GPU Machine		23
	3.5.1 Definition of the CUDA Kernel		23
	3.5.2 Definition of the OpenCL Kernel		23
	3.5.3 Definition of the Main Code		24
	3.5.4 Execution of Hybrid Vector Scaling		26
Sta	arPU Quick Programming Guide		27
Adva	vanced Examples		29
Chec	eck List When Performance Are Not There		31
5.1	Data Related Features That May Improve Performance		31
5.2	Task Related Features That May Improve Performance		31
5.3	Scheduling Related Features That May Improve Performance		31
5.4	CUDA-specific Optimizations		31
5.5	OpenCL-specific Optimizations		32
5.6	Detection Stuck Conditions		32
5.7	How to limit memory used by StarPU and cache buffer allocations		32
5.8	How To Reduce The Memory Footprint Of Internal Data Structures		33
5.9	How to reuse memory		33
5.10	Performance Model Calibration		34
	3.1 3.2 3.3 3.4 3.5 <b>Sta</b> <b>Adv</b> <b>Che</b> 5.1 5.2 5.3 5.4 5.5 5.6 5.7 5.8 5.9	2.4.5 LU Factorization 2.4.6 Simulated benchmarks  Basic Examples  3.1 Hello World Using The C Extension 3.2 Hello World Using StarPUs API 3.2.1 Required Headers 3.2.2 Defining A Codelet 3.2.3 Submitting A Task 3.2.4 Execution Of Hello World 3.2.5 Passing Arguments To The Codelet 3.2.6 Defining A Callback 3.2.7 Where To Execute A Codelet 3.3 Vector Scaling Using the C Extension 3.3.1 Adding an OpenCL Task Implementation 3.3.2 Adding a CUDA Task Implementation 3.3.2 Adding a CUDA Task Implementation 3.4.1 Source Code of Vector Scaling 3.4.2 Execution of Vector Scaling 3.5 Vector Scaling on an Hybrid CPU/GPU Machine 3.5.1 Definition of the CUDA Kernel 3.5.2 Definition of the CUDA Kernel 3.5.3 Definition of the Main Code 3.5.4 Execution of Hybrid Vector Scaling  StarPU Quick Programming Guide  Advanced Examples  Check List When Performance Are Not There 5.1 Data Related Features That May Improve Performance 5.2 Task Related Features That May Improve Performance 5.3 Scheduling Related Features That May Improve Performance 5.4 CUDA-specific Optimizations 5.5 OpenCL-specific Optimizations 5.6 Detection Stuck Conditions 5.7 How to limit memory used by StarPU and cache buffer allocations 5.8 How To Reduce The Memory Footprint Of Internal Data Structures 5.9 How to reuse memory	2.4.5 LU Factorization 2.4.6 Simulated benchmarks  Basic Examples  3.1 Hello World Using The C Extension 3.2 Hello World Using StarPU's API 3.2.1 Required Headers 3.2.2 Defining A Codelet 3.2.3 Submitting A Task 3.2.4 Execution Of Hello World 3.2.5 Passing Arguments To The Codelet 3.2.6 Defining A Callback 3.2.7 Where To Execute A Codelet 3.2.8 Vector Scaling Using the C Extension 3.3.1 Adding an OpenCL Task Implementation 3.3.2 Adding a CUDA Task Implementation 3.3.1 Source Code of Vector Scaling 3.4.1 Source Code of Vector Scaling 3.4.2 Execution of Vector Scaling 3.5 Vector Scaling on an Hybrid CPU/GPU Machine 3.5.1 Definition of the CUDA Kernel 3.5.2 Definition of the CUDA Kernel 3.5.3 Definition of the Main Code 3.5.4 Execution of Hybrid Vector Scaling  StarPU Quick Programming Guide  Advanced Examples  Check List When Performance Are Not There 5.1 Data Related Features That May Improve Performance 5.2 Task Related Features That May Improve Performance 5.3 Scheduling Related Features That May Improve Performance 5.4 CUDA-specific Optimizations 5.5 OpenCL-specific Optimizations 5.6 Detection Stuck Conditions 5.7 How to limit memory used by StarPU and cache buffer allocations 5.8 How To Reduce The Memory Footprint Of Internal Data Structures 5.9 How to ruse memory .

CONTENTS

	5.11	Profiling	36						
Ш	Sta	arPU Inside	37						
6	Task	Tasks In StarPU							
	6.1	Task Granularity	39						
	6.2	Task Submission	39						
	6.3	Task Priorities	39						
	6.4	Setting The Data Handles For A Task	39						
	6.5	Using Multiple Implementations Of A Codelet	40						
	6.6	Enabling Implementation According To Capabilities	41						
	6.7	Insert Task Utility	42						
	6.8	Getting Task Children	43						
	6.9	Parallel Tasks	43						
		6.9.1 Fork-mode Parallel Tasks	44						
		6.9.2 SPMD-mode Parallel Tasks	44						
		6.9.3 Parallel Tasks Performance	45						
		6.9.4 Combined Workers	45						
		6.9.5 Concurrent Parallel Tasks	45						
		6.9.6 Synchronization tasks	45						
7	Data	n Management	47						
7	<b>Data</b> 7.1	Management  Data Management	<b>47</b> 47						
7									
7	7.1	Data Management	47						
7	7.1 7.2	Data Management	47 48						
7	7.1 7.2 7.3	Data Management	47 48 48						
7	7.1 7.2 7.3 7.4	Data Management	47 48 48 49						
7	7.1 7.2 7.3 7.4 7.5	Data Management	47 48 48 49 50						
7	7.1 7.2 7.3 7.4 7.5 7.6	Data Management	47 48 48 49 50 51						
7	7.1 7.2 7.3 7.4 7.5 7.6 7.7	Data Management	47 48 48 49 50 51 52						
7	7.1 7.2 7.3 7.4 7.5 7.6 7.7	Data Management	47 48 48 49 50 51 52 53						
7	7.1 7.2 7.3 7.4 7.5 7.6 7.7	Data Management	477 488 489 500 511 522 533						
7	7.1 7.2 7.3 7.4 7.5 7.6 7.7 7.8 7.9	Data Management	477 488 489 500 511 522 533 533						
7	7.1 7.2 7.3 7.4 7.5 7.6 7.7 7.8 7.9	Data Management	47 48 48 49 50 51 52 53 53 53						
7	7.1 7.2 7.3 7.4 7.5 7.6 7.7 7.8 7.9	Data Management	477 488 489 500 511 522 533 533 534						
	7.1 7.2 7.3 7.4 7.5 7.6 7.7 7.8 7.9 7.10 7.11 7.12	Data Management  Data Prefetch  Partitioning Data  Asynchronous Partitioning  Manual Partitioning  Data Reduction  Commute Data Access  Concurrent Data accesses  Temporary Buffers  7.9.1 Temporary Data  7.9.2 Scratch Data  The Multiformat Interface  Defining A New Data Interface  Specifying a target node for task data	47 48 48 49 50 51 52 53 53 53 54 55 56						
8	7.1 7.2 7.3 7.4 7.5 7.6 7.7 7.8 7.9 7.10 7.11 7.12 Sche	Data Management  Data Prefetch  Partitioning Data  Asynchronous Partitioning  Manual Partitioning  Data Reduction  Commute Data Access  Concurrent Data accesses  Temporary Buffers  7.9.1 Temporary Data  7.9.2 Scratch Data  The Multiformat Interface  Defining A New Data Interface  Specifying a target node for task data	47 48 48 49 50 51 52 53 53 53 54 55 56						
	7.1 7.2 7.3 7.4 7.5 7.6 7.7 7.8 7.9 7.10 7.11 7.12	Data Management  Data Prefetch  Partitioning Data  Asynchronous Partitioning  Manual Partitioning  Data Reduction  Commute Data Access  Concurrent Data accesses  Temporary Buffers  7.9.1 Temporary Data  7.9.2 Scratch Data  The Multiformat Interface  Defining A New Data Interface  Specifying a target node for task data	47 48 48 49 50 51 52 53 53 53 54 55 56						

vi CONTENTS

	8.4	Static Scheduling	60
	8.5	Defining A New Scheduling Policy	61
	0.0	Defining A New Concouning Folicy	01
9	Sche	eduling Contexts	63
	9.1	General Ideas	63
	9.2	Creating A Context	63
	9.3	Modifying A Context	64
	9.4	Submitting Tasks To A Context	64
	9.5	Deleting A Context	64
	9.6	Emptying A Context	65
	9.7	Contexts Sharing Workers	65
10	Sche	duling Context Hypervisor	67
	10.1	What Is The Hypervisor	67
	10.2	Start the Hypervisor	67
	10.3	Interrogate The Runtime	67
	10.4	Trigger the Hypervisor	67
	10.5	Resizing Strategies	68
	10.6	Defining A New Hypervisor Policy	69
44	Made	ularized Scheduler	71
"			71
		Introduction	
	11.2	Using Modularized Schedulers	71
		11.2.1 Existing Modularized Schedulers	71
		11.2.2 An Example : The Tree-Eager-Prefetching Strategy	72
		11.2.3 Interface	72
	11.3	Build a Modularized Scheduler	73
		11.3.1 Pre-implemented Components	73
		11.3.2 Progression And Validation Rules	73
		11.3.3 Implement a Modularized Scheduler	73
	11.4	Write a Scheduling Component	75
		11.4.1 Generic Scheduling Component	75
		11.4.2 Instantiation : Redefine the Interface	75
		11.4.3 Detailed Progression and Validation Rules	75
10	Dobi	reging Tools	77
12		Ugging Tools  Ulaing The Temperais Tools Debugger	
	12.1	Using The Temanejo Task Debugger	77
13	Onlir	ne Performance Tools	79
	13.1	On-line Performance Feedback	79
		13.1.1 Enabling On-line Performance Monitoring	79
		13.1.2 Per-task Feedback	79

CONTENTS vii

		13.1.3 Per-codelet Feedback	79
		13.1.4 Per-worker Feedback	80
		13.1.5 Bus-related Feedback	80
		13.1.6 StarPU-Top Interface	80
	13.2	Task And Worker Profiling	81
	13.3	Performance Model Example	82
	13.4	Data trace and tasks length	84
14	Offlii	ne Performance Tools	85
•		Off-line Performance Feedback	85
		14.1.1 Generating Traces With FxT	85
		14.1.2 Creating a Gantt Diagram	86
		14.1.3 Creating a DAG With Graphviz	87
		14.1.4 Getting task details	87
		14.1.5 Monitoring Activity	87
		14.1.6 Getting modular schedular animation	87
	14.2	Performance Of Codelets	88
		Trace statistics	93
	14.4	Theoretical Lower Bound On Execution Time	95
	14.5	Theoretical Lower Bound On Execution Time Example	95
	14.6	Memory Feedback	95
	14.7	Data Statistics	96
15	Eroa	uently Asked Questions	99
13		How To Initialize A Computation Library Once For Each Worker?	99
			100
		On-GPU Rendering	
		Using StarPU With MKL 11 (Intel Composer XE 2013)	
		Thread Binding on NetBSD	
		Interleaving StarPU and non-StarPU code	
	10.0	The first wing start of the first start of start	
IV	Sta	arPU Extensions	103
16		Of Core	105
			105
		Use a new disk memory	
		Disk functions	
		Examples: disk_copy	
	16.5	Examples: disk_compute	107
17	MPI :	Support	111

viii CONTENTS

	17.1	Simple Example	111
	17.2	Point To Point Communication	112
	17.3	Exchanging User Defined Data Interface	113
	17.4	MPI Insert Task Utility	114
	17.5	MPI cache support	116
	17.6	MPI Data migration	117
	17.7	MPI Collective Operations	117
18	FET	Support	119
		Compilation	_
	10.1	Compliation	110
19	MIC/	SCC Support	121
	19.1	Compilation	121
	19.2	Porting Applications To MIC Xeon Phi / SCC	121
	19.3	Launching Programs	121
20	C Ex	ctensions	123
	20.1	Defining Tasks	123
	20.2	Initialization, Termination, and Synchronization	125
	20.3	Registered Data Buffers	125
	20.4	Using C Extensions Conditionally	126
		Comy of Extendionic Conditionally	120
•			
21		CL OpenCL Extensions	129
	soc		
	SOC	CL OpenCL Extensions	129 131
	<b>Sim</b> (22.1	CL OpenCL Extensions  Grid Support	<b>129 131</b> 131
	Sim( 22.1 22.2	CL OpenCL Extensions  Grid Support  Preparing your application for simulation	129 131 131 131
	Sim( 22.1 22.2 22.3	Calibration	129 131 131 131 132
	Sim( 22.1 22.2 22.3 22.4	Calibration	129 131 131 131 132 132
	SOC Sim( 22.1 22.2 22.3 22.4 22.5	Calibration	129 131 131 131 132 132
	Sim( 22.1 22.2 22.3 22.4 22.5 22.6	Calibration	129 131 131 132 132 132 132
	Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7	Calibration	129 131 131 131 132 132 132 133
22	Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8	CL OpenCL Extensions  Grid Support  Preparing your application for simulation.  Calibration.  Simulation  Simulation On Another Machine.  Simulation examples  simulation.  applications.	129 131 131 131 132 132 132 133
22	Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper	Calibration	129 131 131 132 132 132 133 133
22	Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper	Grid Support  Preparing your application for simulation.  Calibration.  Simulation  Simulation On Another Machine.  Simulation examples  simulation  applications  applications  nMP Runtime Support	129 131 131 132 132 132 133 133 135
22	Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper	Calibration  Simulation  Simulation On Another Machine  Simulation  applications  applications  applications  nMP Runtime Support  Implementation Details and Specificities	129 131 131 132 132 132 133 133 135 135
22	Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper 23.1	Calibration Simulation Simulation On Another Machine Simulation applications applications applications applications applications applications application Details and Specificities 23.1.1 Main Thread	129 131 131 132 132 132 133 133 133 135 135
22	SOC Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper 23.1	Grid Support Preparing your application for simulation. Calibration. Simulation Simulation On Another Machine. Simulation examples simulation applications. applications. applications. applications applications application Details and Specificities 23.1.1 Main Thread. 23.1.2 Extended Task Semantics	129 131 131 132 132 132 133 133 135 135 135 135
22	SOC Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper 23.1	Grid Support Preparing your application for simulation. Calibration Simulation Simulation On Another Machine Simulation examples simulation applications applications IMP Runtime Support Implementation Details and Specificities 23.1.1 Main Thread 23.1.2 Extended Task Semantics Configuration	129 131 131 132 132 132 133 133 135 135 135 135
22	SOC Sim( 22.1 22.2 22.3 22.4 22.5 22.6 22.7 22.8 Oper 23.1	Grid Support Preparing your application for simulation. Calibration Simulation Simulation On Another Machine Simulation examples simulation applications applications applications applications applications Implementation Details and Specificities 23.1.1 Main Thread 23.1.2 Extended Task Semantics Configuration Initialization and Shutdown	129 131 131 132 132 132 133 133 135 135 135 135 135 136

CONTENTS

		23.4.2 Parallel For	136
		23.4.3 Sections	137
		23.4.4 Single	138
	23.5	Tasks	138
		23.5.1 Explicit Tasks	138
		23.5.2 Data Dependencies	139
		23.5.3 TaskWait and TaskGroup	139
	23.6	Synchronization Support	140
		23.6.1 Simple Locks	140
		23.6.2 Nestable Locks	140
		23.6.3 Critical Sections	141
		23.6.4 Barriers	141
V	Sta	rPU Reference API	143
	_		445
24		cution Configuration Through Environment Variables	145
		Configuring Workers	
		Configuring The Scheduling Engine	
		Miscellaneous And Debug	
		Configuring The Hypervisor	
	24.3	Configuring The Hypervisor	130
25	Com	pilation Configuration	151
	25.1	Common Configuration	151
	25.2	Configuring Workers	152
	25.3	Extension Configuration	153
	25.4	Advanced Configuration	153
26	Mod	ule Index	155
20			155
	20.1	woulds	100
27	Mod	ule Documentation a.k.a StarPU's API	157
	27.1	Versioning	157
		27.1.1 Detailed Description	157
		27.1.2 Macro Definition Documentation	157
		27.1.2.1 STARPU_MAJOR_VERSION	157
		27.1.2.2 STARPU_MINOR_VERSION	157
		27.1.2.3 STARPU_RELEASE_VERSION	157
		27.1.3 Function Documentation	157
		27.1.3.1 starpu_get_version	157
	27.2	Initialization and Termination	158

CONTENTS

	27.2.1	Detailed I	Description	158
	27.2.2	Data Stru	cture Documentation	158
		27.2.2.1	struct starpu_driver	158
		27.2.2.2	union starpu_driver.id	158
		27.2.2.3	struct starpu_conf	158
	27.2.3	Function	Documentation	161
		27.2.3.1	starpu_init	161
		27.2.3.2	starpu_initialize	161
		27.2.3.3	starpu_conf_init	161
		27.2.3.4	starpu_shutdown	161
		27.2.3.5	starpu_pause	161
		27.2.3.6	starpu_resume	161
		27.2.3.7	starpu_asynchronous_copy_disabled	162
		27.2.3.8	starpu_asynchronous_cuda_copy_disabled	162
		27.2.3.9	starpu_asynchronous_opencl_copy_disabled	162
		27.2.3.10	starpu_asynchronous_mic_copy_disabled	162
		27.2.3.11	starpu_topology_print	162
27.3	Standa	rd Memory	y Library	162
	27.3.1	Detailed I	Description	163
	27.3.2	Macro De	efinition Documentation	163
		27.3.2.1	starpu_data_malloc_pinned_if_possible	163
		27.3.2.2	starpu_data_free_pinned_if_possible	163
		27.3.2.3	STARPU_MALLOC_PINNED	163
		27.3.2.4	STARPU_MALLOC_COUNT	163
		27.3.2.5	STARPU_MALLOC_NORECLAIM	163
		27.3.2.6	STARPU_MEMORY_WAIT	163
		27.3.2.7	STARPU_MEMORY_OVERFLOW	163
	27.3.3	Function	Documentation	163
		27.3.3.1	starpu_malloc_flags	163
		27.3.3.2	starpu_malloc_set_align	164
		27.3.3.3	starpu_malloc	164
		27.3.3.4	starpu_free	164
		27.3.3.5	starpu_free_flags	164
		27.3.3.6	starpu_memory_pin	164
		27.3.3.7	starpu_memory_unpin	164
		27.3.3.8	starpu_memory_get_total	164
		27.3.3.9	starpu_memory_get_available	164
		27.3.3.10	starpu_memory_allocate	164
			starpu_memory_deallocate	
		27.3.3.12	starpu_memory_wait_available	165

CONTENTS xi

27.4	Toolbox	165
	27.4.1	Detailed Description
	27.4.2	Macro Definition Documentation
		27.4.2.1 STARPU_GNUC_PREREQ
		27.4.2.2 STARPU_UNLIKELY
		27.4.2.3 STARPU_LIKELY
		27.4.2.4 STARPU_ATTRIBUTE_UNUSED
		27.4.2.5 STARPU_ATTRIBUTE_INTERNAL
		27.4.2.6 STARPU_ATTRIBUTE_MALLOC
		27.4.2.7 STARPU_ATTRIBUTE_WARN_UNUSED_RESULT
		27.4.2.8 STARPU_ATTRIBUTE_PURE
		27.4.2.9 STARPU_ATTRIBUTE_ALIGNED
		27.4.2.10 STARPU_WARN_UNUSED_RESULT
		27.4.2.11 STARPU_POISON_PTR
		27.4.2.12 STARPU_MIN
		27.4.2.13 STARPU_MAX
		27.4.2.14 STARPU_ASSERT
		27.4.2.15 STARPU_ASSERT_MSG
		27.4.2.16 STARPU_ABORT
		27.4.2.17 STARPU_ABORT_MSG
		27.4.2.18 STARPU_CHECK_RETURN_VALUE
		27.4.2.19 STARPU_CHECK_RETURN_VALUE_IS
		27.4.2.20 STARPU_RMB
		27.4.2.21 STARPU_WMB
	27.4.3	Function Documentation
		27.4.3.1         starpu_get_env_number         168
27.5	Thread	s
	27.5.1	Detailed Description
	27.5.2	Macro Definition Documentation
		27.5.2.1 STARPU_PTHREAD_CREATE_ON
		27.5.2.2 STARPU_PTHREAD_CREATE
		27.5.2.3 STARPU_PTHREAD_MUTEX_INIT
		27.5.2.4 STARPU_PTHREAD_MUTEX_DESTROY
		27.5.2.5 STARPU_PTHREAD_MUTEX_LOCK
		27.5.2.6 STARPU_PTHREAD_MUTEX_UNLOCK
		27.5.2.7 STARPU_PTHREAD_KEY_CREATE
		27.5.2.8 STARPU_PTHREAD_KEY_DELETE
		27.5.2.9 STARPU_PTHREAD_SETSPECIFIC
		27.5.2.10 STARPU_PTHREAD_GETSPECIFIC
		27.5.2.11 STARPU_PTHREAD_RWLOCK_INIT

xii CONTENTS

	27.5.2.12 STARPU_PTHREAD_RWLOCK_RDLOCK	170
	27.5.2.13 STARPU_PTHREAD_RWLOCK_WRLOCK	170
	27.5.2.14 STARPU_PTHREAD_RWLOCK_UNLOCK	170
	27.5.2.15 STARPU_PTHREAD_RWLOCK_DESTROY	171
	27.5.2.16 STARPU_PTHREAD_COND_INIT	171
	27.5.2.17 STARPU_PTHREAD_COND_DESTROY	171
	27.5.2.18 STARPU_PTHREAD_COND_SIGNAL	171
	27.5.2.19 STARPU_PTHREAD_COND_BROADCAST	171
	27.5.2.20 STARPU_PTHREAD_COND_WAIT	171
	27.5.2.21 STARPU_PTHREAD_BARRIER_INIT	171
	27.5.2.22 STARPU_PTHREAD_BARRIER_DESTROY	171
	27.5.2.23 STARPU_PTHREAD_BARRIER_WAIT	171
	27.5.2.24 STARPU_PTHREAD_MUTEX_INITIALIZER	171
	27.5.2.25 STARPU_PTHREAD_COND_INITIALIZER	171
27.5.3	Function Documentation	171
	27.5.3.1 starpu_pthread_create	172
	27.5.3.2 starpu_pthread_join	172
	27.5.3.3 starpu_pthread_exit	172
	27.5.3.4 starpu_pthread_attr_init	172
	27.5.3.5 starpu_pthread_attr_destroy	172
	27.5.3.6 starpu_pthread_attr_setdetachstate	172
	27.5.3.7 starpu_pthread_mutex_init	172
	27.5.3.8 starpu_pthread_mutex_destroy	172
	27.5.3.9 starpu_pthread_mutex_lock	172
	27.5.3.10 starpu_pthread_mutex_unlock	173
	27.5.3.11 starpu_pthread_mutex_trylock	173
	27.5.3.12 starpu_pthread_mutexattr_gettype	173
	27.5.3.13 starpu_pthread_mutexattr_settype	173
	27.5.3.14 starpu_pthread_mutexattr_destroy	173
	27.5.3.15 starpu_pthread_mutexattr_init	173
	27.5.3.16 starpu_pthread_key_create	173
	27.5.3.17 starpu_pthread_key_delete	173
	27.5.3.18 starpu_pthread_setspecific	173
	27.5.3.19 starpu_pthread_getspecific	173
	27.5.3.20 starpu_pthread_cond_init	173
	27.5.3.21 starpu_pthread_cond_signal	174
	27.5.3.22 starpu_pthread_cond_broadcast	174
	27.5.3.23 starpu_pthread_cond_wait	174
	27.5.3.24 starpu_pthread_cond_timedwait	174
	27.5.3.25 starpu_pthread_cond_destroy	174

CONTENTS xiii

	27.5.3.26 starpu_pthread_rwlock_init	74
	27.5.3.27 starpu_pthread_rwlock_destroy	74
	27.5.3.28 starpu_pthread_rwlock_rdlock	74
	27.5.3.29 starpu_pthread_rwlock_tryrdlock	74
	27.5.3.30 starpu_pthread_rwlock_wrlock	74
	27.5.3.31 starpu_pthread_rwlock_trywrlock	75
	27.5.3.32 starpu_pthread_rwlock_unlock	75
	27.5.3.33 starpu_pthread_barrier_init	75
	27.5.3.34 starpu_pthread_barrier_destroy	75
	27.5.3.35 starpu_pthread_barrier_wait	75
	27.5.3.36 starpu_pthread_spin_init	75
	27.5.3.37 starpu_pthread_spin_destroy	75
	27.5.3.38 starpu_pthread_spin_lock	75
	27.5.3.39 starpu_pthread_spin_trylock	75
	27.5.3.40 starpu_pthread_spin_unlock	75
27.6 Bitmap	o	75
27.6.1	Detailed Description	76
27.6.2	Function Documentation	76
	27.6.2.1 starpu_bitmap_create	76
	27.6.2.2 starpu_bitmap_destroy	76
	27.6.2.3 starpu_bitmap_set	76
	27.6.2.4 starpu_bitmap_unset	76
	27.6.2.5 starpu_bitmap_unset_all	76
	27.6.2.6 starpu_bitmap_get	76
	27.6.2.7 starpu_bitmap_unset_and	76
	27.6.2.8 starpu_bitmap_or	77
	27.6.2.9 starpu_bitmap_and_get	77
	27.6.2.10 starpu_bitmap_cardinal	77
	27.6.2.11 starpu_bitmap_first	77
	27.6.2.12 starpu_bitmap_last	77
	27.6.2.13 starpu_bitmap_next	77
	27.6.2.14 starpu_bitmap_has_next	77
27.7 Worke	rs' Properties	77
27.7.1	Detailed Description	78
27.7.2	Data Structure Documentation	78
	27.7.2.1 struct starpu_worker_collection	78
	27.7.2.2 struct starpu_sched_ctx_iterator	79
27.7.3	Macro Definition Documentation	79
	27.7.3.1 STARPU_NMAXWORKERS	
27.7.4	Enumeration Type Documentation	79

XIV

		27.7.4.1	starpu_node_kind	180
		27.7.4.2	starpu_worker_archtype	180
		27.7.4.3	starpu_worker_collection_type	180
	27.7.5	Function	Documentation	180
		27.7.5.1	starpu_worker_get_count	180
		27.7.5.2	starpu_worker_get_count_by_type	180
		27.7.5.3	starpu_cpu_worker_get_count	180
		27.7.5.4	starpu_cuda_worker_get_count	181
		27.7.5.5	starpu_mic_worker_get_count	181
		27.7.5.6	starpu_mic_device_get_count	181
		27.7.5.7	starpu_scc_worker_get_count	181
		27.7.5.8	starpu_opencl_worker_get_count	181
		27.7.5.9	starpu_worker_get_id	181
		27.7.5.10	starpu_worker_get_ids_by_type	181
		27.7.5.11	starpu_worker_get_by_type	181
		27.7.5.12	starpu_worker_get_by_devid	181
		27.7.5.13	starpu_worker_get_devid	182
			starpu_worker_get_type	
		27.7.5.15	starpu_worker_get_name	182
			starpu_worker_get_memory_node	
			starpu_node_get_kind	
			starpu_worker_get_type_as_string	
27.8			nt	
			Description	
	27.8.2	Macro De	finition Documentation	184
			STARPU_DATA_ACQUIRE_CB	
	27.8.3	Typedef E	Occumentation	184
		27.8.3.1	starpu_data_handle_t	184
		27.8.3.2	starpu_arbiter_t	184
	27.8.4	Enumerat	tion Type Documentation	184
		27.8.4.1		184
	27.8.5	Function	Documentation	185
		27.8.5.1	starpu_data_register	185
		27.8.5.2	starpu_data_ptr_register	185
		27.8.5.3	starpu_data_register_same	185
		27.8.5.4	starpu_data_unregister	
		27.8.5.5	starpu_data_unregister_no_coherency	
		27.8.5.6	starpu_data_unregister_submit	
		27.8.5.7	starpu_data_invalidate	
		27.8.5.8	starpu_data_invalidate_submit	186

CONTENTS xv

	27.8.5.9	starpu_data_set_wt_mask	86
	27.8.5.10	starpu_data_fetch_on_node	86
	27.8.5.11	starpu_data_prefetch_on_node	86
	27.8.5.12	starpu_data_idle_prefetch_on_node	86
	27.8.5.13	3 starpu_data_wont_use	86
	27.8.5.14	starpu_data_lookup	86
	27.8.5.15	starpu_data_request_allocation	86
	27.8.5.16	starpu_data_query_status	87
	27.8.5.17	starpu_data_advise_as_important	87
	27.8.5.18	3 starpu_data_set_reduction_methods	87
	27.8.5.19	starpu_data_get_interface_ops	87
	27.8.5.20	starpu_data_acquire	87
	27.8.5.21	starpu_data_acquire_cb	87
	27.8.5.22	starpu_data_acquire_cb_sequential_consistency	87
	27.8.5.23	3 starpu_data_acquire_on_node	88
	27.8.5.24	starpu_data_acquire_on_node_cb1	88
	27.8.5.25	starpu_data_acquire_on_node_cb_sequential_consistency 1	88
	27.8.5.26	starpu_data_release	88
	27.8.5.27	starpu_data_release_on_node1	88
	27.8.5.28	3 starpu_arbiter_create	88
	27.8.5.29	starpu_data_assign_arbiter	88
	27.8.5.30	starpu_arbiter_destroy	88
27.9 Data Ir	nterfaces		88
27.9.1	Detailed	Description	92
27.9.2	Data Stru	ucture Documentation	92
	27.9.2.1	struct starpu_data_interface_ops	92
	27.9.2.2	struct starpu_data_copy_methods	94
	27.9.2.3	struct starpu_variable_interface	97
	27.9.2.4	struct starpu_vector_interface	97
	27.9.2.5	struct starpu_matrix_interface	98
	27.9.2.6	struct starpu_block_interface	98
	27.9.2.7	struct starpu_bcsr_interface	98
	27.9.2.8	struct starpu_csr_interface	99
	27.9.2.9	struct starpu_coo_interface	99
27.9.3	Macro De	efinition Documentation	99
	27.9.3.1	STARPU_VARIABLE_GET_PTR	00
	27.9.3.2	STARPU_VARIABLE_GET_ELEMSIZE	00
	27.9.3.3	STARPU_VARIABLE_GET_DEV_HANDLE	00
	27.9.3.4	STARPU_VARIABLE_GET_OFFSET	00
	27.9.3.5	STARPU_VECTOR_GET_PTR	00

xvi CONTENTS

27.9.3.6 STARPU_VECTOR_GET_DEV_HANDLE
27.9.3.7 STARPU_VECTOR_GET_OFFSET
27.9.3.8 STARPU_VECTOR_GET_NX
27.9.3.9 STARPU_VECTOR_GET_ELEMSIZE
27.9.3.10 STARPU_VECTOR_GET_SLICE_BASE
27.9.3.11 STARPU_MATRIX_GET_PTR
27.9.3.12 STARPU_MATRIX_GET_DEV_HANDLE
27.9.3.13 STARPU_MATRIX_GET_OFFSET
27.9.3.14 STARPU_MATRIX_GET_NX
27.9.3.15 STARPU_MATRIX_GET_NY
27.9.3.16 STARPU_MATRIX_GET_LD
27.9.3.17 STARPU_MATRIX_GET_ELEMSIZE
27.9.3.18 STARPU_BLOCK_GET_PTR
27.9.3.19 STARPU_BLOCK_GET_DEV_HANDLE
27.9.3.20 STARPU_BLOCK_GET_OFFSET
27.9.3.21 STARPU_BLOCK_GET_NX
27.9.3.22 STARPU_BLOCK_GET_NY
27.9.3.23 STARPU_BLOCK_GET_NZ
27.9.3.24 STARPU_BLOCK_GET_LDY
27.9.3.25 STARPU_BLOCK_GET_LDZ
27.9.3.26 STARPU_BLOCK_GET_ELEMSIZE
27.9.3.27 STARPU_BCSR_GET_NNZ
27.9.3.28 STARPU_BCSR_GET_NZVAL
27.9.3.29 STARPU_BCSR_GET_NZVAL_DEV_HANDLE
27.9.3.30 STARPU_BCSR_GET_COLIND
27.9.3.31 STARPU_BCSR_GET_COLIND_DEV_HANDLE
27.9.3.32 STARPU_BCSR_GET_ROWPTR
27.9.3.33 STARPU_BCSR_GET_ROWPTR_DEV_HANDLE
27.9.3.34 STARPU_BCSR_GET_OFFSET
27.9.3.35 STARPU_CSR_GET_NNZ
27.9.3.36 STARPU_CSR_GET_NROW
27.9.3.37 STARPU_CSR_GET_NZVAL
27.9.3.38 STARPU_CSR_GET_NZVAL_DEV_HANDLE
27.9.3.39 STARPU_CSR_GET_COLIND
27.9.3.40 STARPU_CSR_GET_COLIND_DEV_HANDLE
27.9.3.41 STARPU_CSR_GET_ROWPTR
27.9.3.42 STARPU_CSR_GET_ROWPTR_DEV_HANDLE
27.9.3.43 STARPU_CSR_GET_OFFSET
27.9.3.44 STARPU_CSR_GET_FIRSTENTRY
27.9.3.45 STARPU_CSR_GET_ELEMSIZE

CONTENTS xvii

	27.9.3.46 STARPU_COO_GET_COLUMNS	04
	27.9.3.47 STARPU_COO_GET_COLUMNS_DEV_HANDLE	04
	27.9.3.48 STARPU_COO_GET_ROWS	04
	27.9.3.49 STARPU_COO_GET_ROWS_DEV_HANDLE	04
	27.9.3.50 STARPU_COO_GET_VALUES	04
	27.9.3.51 STARPU_COO_GET_VALUES_DEV_HANDLE	04
	27.9.3.52 STARPU_COO_GET_OFFSET	04
	27.9.3.53 STARPU_COO_GET_NX	04
	27.9.3.54 STARPU_COO_GET_NY	04
	27.9.3.55 STARPU_COO_GET_NVALUES	04
	27.9.3.56 STARPU_COO_GET_ELEMSIZE	04
27.9.4	Enumeration Type Documentation	05
	27.9.4.1 starpu_data_interface_id	05
27.9.5	Function Documentation	05
	27.9.5.1 starpu_void_data_register	205
	27.9.5.2 starpu_variable_data_register	05
	27.9.5.3 starpu_variable_ptr_register	05
	27.9.5.4 starpu_vector_data_register	205
	27.9.5.5 starpu_vector_ptr_register	206
	27.9.5.6 starpu_matrix_data_register	206
	27.9.5.7 starpu_matrix_ptr_register	206
	27.9.5.8 starpu_block_data_register	206
	27.9.5.9 starpu_block_ptr_register	206
	27.9.5.10 starpu_bcsr_data_register	07
	27.9.5.11 starpu_csr_data_register	207
	27.9.5.12 starpu_coo_data_register	207
	27.9.5.13 starpu_data_get_interface_on_node	207
	27.9.5.14 starpu_data_handle_to_pointer	207
	27.9.5.15 starpu_data_get_local_ptr	207
	27.9.5.16 starpu_data_get_interface_id	207
	27.9.5.17 starpu_data_get_size	207
	27.9.5.18 starpu_data_pack	207
	27.9.5.19 starpu_data_unpack	208
	27.9.5.20 starpu_variable_get_elemsize	208
	27.9.5.21 starpu_variable_get_local_ptr	208
	27.9.5.22 starpu_vector_get_nx	208
	27.9.5.23 starpu_vector_get_elemsize	208
	27.9.5.24 starpu_vector_get_local_ptr	208
	27.9.5.25 starpu_matrix_get_nx	208
	27.9.5.26 starpu_matrix_get_ny	208

xviii **CONTENTS** 

27.9.5.27 starpu_matrix_get_local_ld
27.9.5.28 starpu_matrix_get_local_ptr
27.9.5.29 starpu_matrix_get_elemsize
27.9.5.30 starpu_block_get_nx
27.9.5.31 starpu_block_get_ny
27.9.5.32 starpu_block_get_nz
27.9.5.33 starpu_block_get_local_ldy
27.9.5.34 starpu_block_get_local_ldz
27.9.5.35 starpu_block_get_local_ptr
27.9.5.36 starpu_block_get_elemsize
27.9.5.37 starpu_bcsr_get_nnz
27.9.5.38 starpu_bcsr_get_nrow
27.9.5.39 starpu_bcsr_get_firstentry
27.9.5.40 starpu_bcsr_get_local_nzval
27.9.5.41 starpu_bcsr_get_local_colind
27.9.5.42 starpu_bcsr_get_local_rowptr
27.9.5.43 starpu_bcsr_get_r
27.9.5.44 starpu_bcsr_get_c
27.9.5.45 starpu_bcsr_get_elemsize
27.9.5.46 starpu_csr_get_nnz
27.9.5.47 starpu_csr_get_nrow
27.9.5.48 starpu_csr_get_firstentry
27.9.5.49 starpu_csr_get_local_nzval
27.9.5.50 starpu_csr_get_local_colind
27.9.5.51 starpu_csr_get_local_rowptr
27.9.5.52 starpu_csr_get_elemsize
27.9.5.53 starpu_malloc_on_node_flags
27.9.5.54 starpu_free_on_node_flags
27.9.5.55 starpu_malloc_on_node
27.9.5.56 starpu_free_on_node
27.9.5.57 starpu_malloc_on_node_set_default_flags
27.9.5.58 starpu_interface_copy
27.9.5.59 starpu_hash_crc32c_be_n
27.9.5.60 starpu_hash_crc32c_be
27.9.5.61 starpu_hash_crc32c_string
27.9.5.62 starpu_data_interface_get_next_id
Data Partition
27.10.1 Detailed Description
27.10.2 Data Structure Documentation
27.10.2.1 struct starpu_data_filter

27.10Data

CONTENTS xix

27.10.3 Function Documentation	214
27.10.3.1 starpu_data_partition	214
27.10.3.2 starpu_data_unpartition	214
27.10.3.3 starpu_data_get_nb_children	214
27.10.3.4 starpu_data_get_child	214
27.10.3.5 starpu_data_get_sub_data	215
27.10.3.6 starpu_data_vget_sub_data	215
27.10.3.7 starpu_data_map_filters	215
27.10.3.8 starpu_data_vmap_filters	215
27.10.3.9 starpu_data_partition_plan	215
27.10.3.10starpu_data_partition_submit	215
27.10.3.11starpu_data_partition_readonly_submit	216
27.10.3.12starpu_data_partition_readwrite_upgrade_submit	216
27.10.3.13starpu_data_unpartition_submit	216
27.10.3.14starpu_data_unpartition_readonly_submit	216
27.10.3.15starpu_data_partition_clean	216
27.10.3.16starpu_vector_filter_block	216
27.10.3.17starpu_vector_filter_block_shadow	217
27.10.3.18starpu_vector_filter_list	217
27.10.3.19starpu_vector_filter_divide_in_2	217
27.10.3.20starpu_matrix_filter_block	217
27.10.3.21starpu_matrix_filter_block_shadow	217
27.10.3.22starpu_matrix_filter_vertical_block	217
27.10.3.23starpu_matrix_filter_vertical_block_shadow	217
27.10.3.24starpu_block_filter_block	218
27.10.3.25starpu_block_filter_block_shadow	218
27.10.3.26starpu_block_filter_vertical_block	218
27.10.3.27starpu_block_filter_vertical_block_shadow	218
27.10.3.28starpu_block_filter_depth_block	218
27.10.3.29starpu_block_filter_depth_block_shadow	218
27.10.3.30starpu_bcsr_filter_canonical_block	218
27.10.3.31starpu_csr_filter_vertical_block	218
27.11 Out Of Core	219
27.11.1 Detailed Description	219
27.11.2 Data Structure Documentation	219
27.11.2.1 struct starpu_disk_ops	219
27.11.3 Function Documentation	
27.11.3.1 starpu_disk_register	
27.11.3.2 starpu_disk_open	
27.11.3.3 starpu_disk_close	221

CONTENTS

27.11.4 Variable Documentation	221
27.11.4.1 starpu_disk_stdio_ops	221
27.11.4.2 starpu_disk_unistd_ops	222
27.11.4.3 starpu_disk_unistd_o_direct_ops	222
27.11.4.4 starpu_disk_leveldb_ops	222
27.12Multiformat Data Interface	222
27.12.1 Detailed Description	222
27.12.2 Data Structure Documentation	222
27.12.2.1 struct starpu_multiformat_data_interface_ops	222
27.12.2.2 struct starpu_multiformat_interface	223
27.12.3 Macro Definition Documentation	223
27.12.3.1 STARPU_MULTIFORMAT_GET_CPU_PTR	223
27.12.3.2 STARPU_MULTIFORMAT_GET_CUDA_PTR	223
27.12.3.3 STARPU_MULTIFORMAT_GET_OPENCL_PTR	223
27.12.3.4 STARPU_MULTIFORMAT_GET_MIC_PTR	224
27.12.3.5 STARPU_MULTIFORMAT_GET_NX	224
27.12.4 Function Documentation	224
27.12.4.1 starpu_multiformat_data_register	224
27.13Codelet And Tasks	224
27.13.1 Detailed Description	225
27.13.2 Data Structure Documentation	226
27.13.2.1 struct starpu_codelet	226
27.13.2.2 struct starpu_data_descr	229
27.13.2.3 struct starpu_task	229
27.13.3 Macro Definition Documentation	234
27.13.3.1 STARPU_NOWHERE	235
27.13.3.2 STARPU_CPU	235
27.13.3.3 STARPU_CUDA	235
27.13.3.4 STARPU_OPENCL	235
27.13.3.5 STARPU_MIC	235
27.13.3.6 STARPU_SCC	235
27.13.3.7 STARPU_MAIN_RAM	235
27.13.3.8 STARPU_MULTIPLE_CPU_IMPLEMENTATIONS	235
27.13.3.9 STARPU_MULTIPLE_CUDA_IMPLEMENTATIONS	235
27.13.3.10STARPU_MULTIPLE_OPENCL_IMPLEMENTATIONS	236
27.13.3.11STARPU_NMAXBUFS	236
27.13.3.12STARPU_VARIABLE_NBUFFERS	236
27.13.3.13STARPU_TASK_INITIALIZER	236
27.13.3.14STARPU_TASK_GET_NBUFFERS	236
27.13.3.15STARPU_TASK_GET_HANDLE	236

CONTENTS xxi

	27.13.3.16STARPU_TASK_SET_HANDLE	236
	27.13.3.17STARPU_CODELET_GET_MODE	236
	27.13.3.18STARPU_CODELET_SET_MODE	236
	27.13.3.19STARPU_TASK_GET_MODE	237
	27.13.3.20STARPU_TASK_SET_MODE	237
	27.13.3.21STARPU_TASK_INVALID	237
27.13.4	Typedef Documentation	237
	27.13.4.1 starpu_cpu_func_t	237
	27.13.4.2 starpu_cuda_func_t	237
	27.13.4.3 starpu_opencl_func_t	237
	27.13.4.4 starpu_mic_func_t	237
	27.13.4.5 starpu_scc_func_t	237
	27.13.4.6 starpu_mic_kernel_t	237
	27.13.4.7 starpu_scc_kernel_t	237
27.13.5	5 Enumeration Type Documentation	238
	27.13.5.1 starpu_codelet_type	238
	27.13.5.2 starpu_task_status	238
27.13.6	Function Documentation	238
	27.13.6.1 starpu_codelet_init	238
	27.13.6.2 starpu_task_init	238
	27.13.6.3 starpu_task_create	238
	27.13.6.4 starpu_task_dup	238
	27.13.6.5 starpu_task_clean	239
	27.13.6.6 starpu_task_destroy	239
	27.13.6.7 starpu_task_wait	239
	27.13.6.8 starpu_task_submit	239
	27.13.6.9 starpu_task_submit_to_ctx	239
	27.13.6.10starpu_task_wait_for_all	239
	27.13.6.11starpu_task_wait_for_all_in_ctx	239
	27.13.6.12starpu_task_wait_for_n_submitted	239
	27.13.6.13starpu_task_wait_for_n_submitted_in_ctx	240
	27.13.6.14starpu_task_nready	240
	27.13.6.15starpu_task_nsubmitted	240
	27.13.6.16starpu_task_get_current	240
	27.13.6.17starpu_codelet_display_stats	240
	27.13.6.1&starpu_task_wait_for_no_ready	240
	27.13.6.19starpu_task_set_implementation	240
	27.13.6.20starpu_task_get_implementation	240
	27.13.6.21starpu_create_sync_task	
27.14Insert_	Task	240

xxii CONTENTS

27.14.1 Detailed Description	41
27.14.2 Macro Definition Documentation	41
27.14.2.1 STARPU_VALUE	41
27.14.2.2 STARPU_CALLBACK	41
27.14.2.3 STARPU_CALLBACK_WITH_ARG	41
27.14.2.4 STARPU_CALLBACK_ARG	41
27.14.2.5 STARPU_PRIORITY	41
27.14.2.6 STARPU_DATA_ARRAY	41
27.14.2.7 STARPU_DATA_MODE_ARRAY	42
27.14.2.8 STARPU_EXECUTE_ON_WORKER	42
27.14.2.9 STARPU_WORKER_ORDER	42
27.14.2.10STARPU_TAG	42
27.14.2.11STARPU_TAG_ONLY	42
27.14.2.12STARPU_NAME	42
27.14.2.13STARPU_FLOPS	42
27.14.2.14STARPU_SCHED_CTX	42
27.14.3 Function Documentation	42
27.14.3.1 starpu_insert_task	42
27.14.3.2 starpu_task_insert	42
27.14.3.3 starpu_codelet_pack_args	43
27.14.3.4 starpu_codelet_unpack_args	43
27.14.3.5 starpu_task_build	43
27.15Explicit Dependencies	43
27.15.1 Detailed Description	44
27.15.2 Typedef Documentation	44
27.15.2.1 starpu_tag_t	44
27.15.3 Function Documentation	44
27.15.3.1 starpu_task_declare_deps_array	44
27.15.3.2 starpu_task_get_task_succs	44
27.15.3.3 starpu_tag_declare_deps	44
27.15.3.4 starpu_tag_declare_deps_array	44
27.15.3.5 starpu_tag_wait	45
27.15.3.6 starpu_tag_wait_array	45
27.15.3.7 starpu_tag_restart	45
27.15.3.8 starpu_tag_remove	45
27.15.3.9 starpu_tag_notify_from_apps	45
27.16Implicit Data Dependencies	45
27.16.1 Detailed Description	46
27.16.2 Function Documentation	46
27.16.2.1 starpu_data_set_default_sequential_consistency_flag	46

CONTENTS xxiii

27.16.2.2 starpu_data_get_default_sequential_consistency_flag	246
27.16.2.3 starpu_data_set_sequential_consistency_flag	246
27.16.2.4 starpu_data_get_sequential_consistency_flag	246
27.17Performance Model	246
27.17.1 Detailed Description	247
27.17.2 Data Structure Documentation	247
27.17.2.1 struct starpu_perfmodel	247
27.17.2.2 struct starpu_perfmodel_regression_model	248
27.17.2.3 struct starpu_perfmodel_per_arch	249
27.17.2.4 struct starpu_perfmodel_history_list	249
27.17.2.5 struct starpu_perfmodel_history_entry	250
27.17.3 Enumeration Type Documentation	250
27.17.3.1 starpu_perfmodel_type	250
27.17.4 Function Documentation	250
27.17.4.1 starpu_perfmodel_init	250
27.17.4.2 starpu_perfmodel_free_sampling_directories	250
27.17.4.3 starpu_perfmodel_load_file	250
27.17.4.4 starpu_perfmodel_load_symbol	250
27.17.4.5 starpu_perfmodel_unload_model	251
27.17.4.6 starpu_perfmodel_debugfilepath	251
27.17.4.7 starpu_perfmodel_get_archtype_name	251
27.17.4.8 starpu_perfmodel_get_arch_name	251
27.17.4.9 starpu_worker_get_perf_archtype	251
27.17.4.10starpu_perfmodel_list	251
27.17.4.11starpu_perfmodel_directory	251
27.17.4.12starpu_perfmodel_print	251
27.17.4.13starpu_perfmodel_print_all	251
27.17.4.14starpu_bus_print_bandwidth	251
27.17.4.15starpu_bus_print_affinity	251
27.17.4.16starpu_perfmodel_update_history	252
27.17.4.17starpu_transfer_bandwidth	252
27.17.4.18starpu_transfer_latency	252
27.17.4.19starpu_transfer_predict	252
27.17.4.20starpu_perfmodel_history_based_expected_perf	252
27.18Profiling	252
27.18.1 Detailed Description	253
27.18.2 Data Structure Documentation	253
27.18.2.1 struct starpu_profiling_task_info	253
27.18.2.2 struct starpu_profiling_worker_info	253
27.18.2.3 struct starpu_profiling_bus_info	254

xxiv CONTENTS

27.18.3 Macro Definition Documentation	254
27.18.3.1 STARPU_PROFILING_DISABLE	254
27.18.3.2 STARPU_PROFILING_ENABLE	254
27.18.4 Function Documentation	254
27.18.4.1 starpu_profiling_status_set	254
27.18.4.2 starpu_profiling_status_get	254
27.18.4.3 starpu_profiling_init	254
27.18.4.4 starpu_profiling_set_id	254
27.18.4.5 starpu_profiling_worker_get_info	255
27.18.4.6 starpu_bus_get_profiling_info	255
27.18.4.7 starpu_bus_get_count	255
27.18.4.8 starpu_bus_get_id	255
27.18.4.9 starpu_bus_get_src	255
27.18.4.10starpu_bus_get_dst	255
27.18.4.11starpu_timing_timespec_delay_us	255
27.18.4.12starpu_timing_timespec_to_us	255
27.18.4.13starpu_profiling_bus_helper_display_summary	255
27.18.4.14starpu_profiling_worker_helper_display_summary	255
27.18.4.15starpu_data_display_memory_stats	255
27.19Theoretical Lower Bound on Execution Time	256
27.19.1 Detailed Description	256
27.19.2 Function Documentation	256
27.19.2.1 starpu_bound_start	256
27.19.2.2 starpu_bound_stop	256
27.19.2.3 starpu_bound_print_dot	256
27.19.2.4 starpu_bound_compute	256
27.19.2.5 starpu_bound_print_lp	256
27.19.2.6 starpu_bound_print_mps	256
27.19.2.7 starpu_bound_print	256
27.20CUDA Extensions	257
27.20.1 Detailed Description	257
27.20.2 Macro Definition Documentation	257
27.20.2.1 STARPU_USE_CUDA	257
27.20.2.2 STARPU_MAXCUDADEVS	257
27.20.2.3 STARPU_CUDA_REPORT_ERROR	257
27.20.2.4 STARPU_CUBLAS_REPORT_ERROR	257
27.20.3 Function Documentation	257
27.20.3.1 starpu_cuda_get_local_stream	257
27.20.3.2 starpu_cuda_get_device_properties	258
27.20.3.3 starpu_cuda_report_error	258

CONTENTS xxv

27.20.3.4 starpu_cuda_copy_async_sync	258
27.20.3.5 starpu_cuda_set_device	258
27.20.3.6 starpu_cublas_init	258
27.20.3.7 starpu_cublas_shutdown	258
27.20.3.8 starpu_cublas_report_error	258
27.21 OpenCL Extensions	258
27.21.1 Detailed Description	260
27.21.2 Data Structure Documentation	260
27.21.2.1 struct starpu_opencl_program	260
27.21.3 Macro Definition Documentation	260
27.21.3.1 STARPU_USE_OPENCL	260
27.21.3.2 STARPU_MAXOPENCLDEVS	260
27.21.3.3 STARPU_OPENCL_DATADIR	260
27.21.3.4 STARPU_OPENCL_DISPLAY_ERROR	260
27.21.3.5 STARPU_OPENCL_REPORT_ERROR	260
27.21.3.6 STARPU_OPENCL_REPORT_ERROR_WITH_MSG	260
27.21.4 Function Documentation	260
27.21.4.1 starpu_opencl_get_context	261
27.21.4.2 starpu_opencl_get_device	261
27.21.4.3 starpu_opencl_get_queue	261
27.21.4.4 starpu_opencl_get_current_context	261
27.21.4.5 starpu_opencl_get_current_queue	261
27.21.4.6 starpu_opencl_set_kernel_args	261
27.21.4.7 starpu_opencl_load_opencl_from_file	261
27.21.4.8 starpu_opencl_load_opencl_from_string	261
27.21.4.9 starpu_opencl_unload_opencl	261
27.21.4.10starpu_opencl_load_program_source	262
27.21.4.11starpu_opencl_compile_opencl_from_file	262
27.21.4.12starpu_opencl_compile_opencl_from_string	262
27.21.4.13starpu_opencl_load_binary_opencl	262
27.21.4.14starpu_opencl_load_kernel	262
27.21.4.15starpu_opencl_release_kernel	262
27.21.4.16starpu_opencl_collect_stats	262
27.21.4.17starpu_opencl_error_string	262
27.21.4.18starpu_opencl_display_error	263
27.21.4.19starpu_opencl_report_error	263
27.21.4.20starpu_opencl_allocate_memory	263
27.21.4.21starpu_opencl_copy_ram_to_opencl	263
27.21.4.22starpu_opencl_copy_opencl_to_ram	
27.21.4.23starpu_opencl_copy_opencl_to_opencl	263

XXVI

27.21.4.24starpu_opencl_copy_async_sync	63
27.22OpenMP Runtime Support	64
27.22.1 Detailed Description	66
27.22.2 Data Structure Documentation	66
27.22.2.1 struct starpu_omp_lock_t	66
27.22.2.2 struct starpu_omp_nest_lock_t	66
27.22.2.3 struct starpu_omp_parallel_region_attr	67
27.22.2.4 struct starpu_omp_task_region_attr	67
27.22.3 Macro Definition Documentation	68
27.22.3.1 STARPU_OPENMP	68
27.22.4 Enumeration Type Documentation	68
27.22.4.1 starpu_omp_sched_value	68
27.22.4.2 starpu_omp_proc_bind_value	68
27.22.5 Function Documentation	69
27.22.5.1 starpu_omp_init	69
27.22.5.2 starpu_omp_shutdown	69
27.22.5.3 starpu_omp_parallel_region	69
27.22.5.4 starpu_omp_master	69
27.22.5.5 starpu_omp_master_inline	69
27.22.5.6 starpu_omp_barrier	69
27.22.5.7 starpu_omp_critical	70
27.22.5.8 starpu_omp_critical_inline_begin	70
27.22.5.9 starpu_omp_critical_inline_end	70
27.22.5.10starpu_omp_single	70
27.22.5.11starpu_omp_single_inline	70
27.22.5.12starpu_omp_single_copyprivate	70
27.22.5.13starpu_omp_single_copyprivate_inline_begin	71
27.22.5.14starpu_omp_single_copyprivate_inline_end	71
27.22.5.15starpu_omp_for	71
27.22.5.16starpu_omp_for_inline_first	71
27.22.5.17starpu_omp_for_inline_next	72
27.22.5.18starpu_omp_for_alt	72
27.22.5.19starpu_omp_for_inline_first_alt	72
27.22.5.20starpu_omp_for_inline_next_alt	73
27.22.5.21starpu_omp_ordered	73
27.22.5.22starpu_omp_ordered_inline_begin	73
27.22.5.23starpu_omp_ordered_inline_end	73
27.22.5.24starpu_omp_sections	73
27.22.5.25starpu_omp_sections_combined	74
27.22.5.26starpu_omp_task_region	74

CONTENTS xxvii

27.22.5.27starpu_omp_taskwait
27.22.5.28starpu_omp_taskgroup
27.22.5.29starpu_omp_taskgroup_inline_begin
27.22.5.30starpu_omp_taskgroup_inline_end
27.22.5.31starpu_omp_set_num_threads
27.22.5.32starpu_omp_get_num_threads
27.22.5.33starpu_omp_get_thread_num         275
27.22.5.34starpu_omp_get_max_threads
27.22.5.35starpu_omp_get_num_procs
27.22.5.36starpu_omp_in_parallel
27.22.5.37starpu_omp_set_dynamic
27.22.5.38starpu_omp_get_dynamic
27.22.5.39starpu_omp_set_nested
27.22.5.40starpu_omp_get_nested
27.22.5.41starpu_omp_get_cancellation
27.22.5.42starpu_omp_set_schedule
27.22.5.43starpu_omp_get_schedule
27.22.5.44starpu_omp_get_thread_limit
27.22.5.45starpu_omp_set_max_active_levels
27.22.5.46starpu_omp_get_max_active_levels
27.22.5.47starpu_omp_get_level
27.22.5.48starpu_omp_get_ancestor_thread_num
27.22.5.49starpu_omp_get_team_size
27.22.5.50starpu_omp_get_active_level
27.22.5.51starpu_omp_in_final
27.22.5.52starpu_omp_get_proc_bind
27.22.5.53starpu_omp_set_default_device
27.22.5.54starpu_omp_get_default_device
27.22.5.55starpu_omp_get_num_devices         280
27.22.5.56starpu_omp_get_num_teams
27.22.5.57starpu_omp_get_team_num       280
27.22.5.58starpu_omp_is_initial_device
27.22.5.59starpu_omp_init_lock
27.22.5.60starpu_omp_destroy_lock
27.22.5.61starpu_omp_set_lock
27.22.5.62starpu_omp_unset_lock
27.22.5.63starpu_omp_test_lock
27.22.5.64starpu_omp_init_nest_lock
27.22.5.65starpu_omp_destroy_nest_lock
27.22.5.66starpu_omp_set_nest_lock

xxviii CONTENTS

27.22.5.67starpu_omp_unset_nest_lock	83
27.22.5.68starpu_omp_test_nest_lock	83
27.22.5.69starpu_omp_atomic_fallback_inline_begin	83
27.22.5.70starpu_omp_atomic_fallback_inline_end	83
27.22.5.71starpu_omp_get_wtime	84
27.22.5.72starpu_omp_get_wtick	84
27.22.5.73starpu_omp_vector_annotate	84
27.23MIC Extensions	84
27.23.1 Detailed Description	85
27.23.2 Macro Definition Documentation	85
27.23.2.1 STARPU_USE_MIC	85
27.23.2.2 STARPU_MAXMICDEVS	85
27.23.3 Typedef Documentation	85
27.23.3.1 starpu_mic_func_symbol_t	85
27.23.4 Function Documentation	85
27.23.4.1 starpu_mic_register_kernel	85
27.23.4.2 starpu_mic_get_kernel	85
27.24SCC Extensions	85
27.24.1 Detailed Description	86
27.24.2 Macro Definition Documentation	86
27.24.2.1 STARPU_USE_SCC	86
27.24.2.2 STARPU_MAXSCCDEVS	86
27.24.3 Typedef Documentation	86
27.24.3.1 starpu_scc_func_symbol_t	86
27.24.4 Function Documentation	86
27.24.4.1 starpu_scc_register_kernel	86
27.24.4.2 starpu_scc_get_kernel	86
27.25Miscellaneous Helpers	86
27.25.1 Detailed Description	86
27.25.2 Function Documentation	86
27.25.2.1 starpu_data_cpy	86
27.25.2.2 starpu_execute_on_each_worker	87
27.25.2.3 starpu_execute_on_each_worker_ex	87
27.25.2.4 starpu_execute_on_specific_workers	87
27.25.2.5 starpu_timing_now	87
27.26FxT Support	87
27.26.1 Detailed Description	87
27.26.2 Data Structure Documentation	87
27.26.2.1 struct starpu_fxt_codelet_event	87
27.26.2.2 struct starpu_fxt_options	88

CONTENTS xxix

27.26.3 Function Documentation	288
27.26.3.1 starpu_fxt_options_init	288
27.26.3.2 starpu_fxt_generate_trace	288
27.26.3.3 starpu_fxt_start_profiling	289
27.26.3.4 starpu_fxt_stop_profiling	289
27.26.3.5 starpu_fxt_write_data_trace	289
27.26.3.6 starpu_fxt_trace_user_event	289
27.27FFT Support	289
27.27.1 Detailed Description	289
27.27.2 Function Documentation	289
27.27.2.1 starpufft_malloc	289
27.27.2.2 starpufft_free	289
27.27.2.3 starpufft_plan_dft_1d	289
27.27.2.4 starpufft_plan_dft_2d	290
27.27.2.5 starpufft_start	290
27.27.2.6 starpufft_start_handle	290
27.27.2.7 starpufft_execute	290
27.27.2.8 starpufft_execute_handle	290
27.27.2.9 starpufft_cleanup	290
27.27.2.10starpufft_destroy_plan	290
27.28MPI Support	290
27.28.1 Detailed Description	292
27.28.2 Macro Definition Documentation	292
27.28.2.1 STARPU_USE_MPI	292
27.28.2.2 starpu_mpi_data_register	292
27.28.2.3 starpu_data_set_tag	292
27.28.2.4 starpu_mpi_data_set_rank	292
27.28.2.5 starpu_data_set_rank	293
27.28.2.6 starpu_data_get_rank	293
27.28.2.7 starpu_data_get_tag	293
27.28.2.8 STARPU_EXECUTE_ON_NODE	293
27.28.2.9 STARPU_EXECUTE_ON_DATA	293
27.28.3 Function Documentation	293
27.28.3.1 starpu_mpi_init_comm	293
27.28.3.2 starpu_mpi_init	293
27.28.3.3 starpu_mpi_initialize	293
27.28.3.4 starpu_mpi_initialize_extended	293
27.28.3.5 starpu_mpi_shutdown	294
27.28.3.6 starpu_mpi_comm_amounts_retrieve	294
27.28.3.7 starpu_mpi_send	294

CONTENTS

27.28.3.8 starpu_mpi_recv
27.28.3.9 starpu_mpi_isend
27.28.3.10starpu_mpi_irecv
27.28.3.11starpu_mpi_isend_detached
27.28.3.12starpu_mpi_irecv_detached
27.28.3.13starpu_mpi_irecv_detached_sequential_consistency
27.28.3.14starpu_mpi_issend
27.28.3.15starpu_mpi_issend_detached
27.28.3.16starpu_mpi_wait
27.28.3.17starpu_mpi_test
27.28.3.18starpu_mpi_barrier
27.28.3.19starpu_mpi_isend_detached_unlock_tag
27.28.3.20starpu_mpi_irecv_detached_unlock_tag
27.28.3.21starpu_mpi_isend_array_detached_unlock_tag
27.28.3.22starpu_mpi_irecv_array_detached_unlock_tag
27.28.3.23starpu_mpi_get_communication_tag
27.28.3.24starpu_mpi_set_communication_tag
27.28.3.25starpu_mpi_datatype_register
27.28.3.26starpu_mpi_datatype_unregister
27.28.3.27starpu_mpi_cache_is_enabled
27.28.3.28starpu_mpi_cache_set
27.28.3.29starpu_mpi_cache_flush
27.28.3.30starpu_mpi_cache_flush_all_data
27.28.3.31starpu_mpi_data_register_comm
27.28.3.32starpu_mpi_data_set_tag
27.28.3.33starpu_mpi_data_set_rank_comm
27.28.3.34starpu_mpi_data_get_rank
27.28.3.35starpu_mpi_data_get_tag
27.28.3.36starpu_mpi_insert_task
27.28.3.37starpu_mpi_task_insert
27.28.3.38starpu_mpi_task_build
27.28.3.39starpu_mpi_task_post_build
27.28.3.40starpu_mpi_get_data_on_node
27.28.3.41starpu_mpi_get_data_on_node_detached
27.28.3.42starpu_mpi_node_selection_get_current_policy
27.28.3.43starpu_mpi_node_selection_set_current_policy
27.28.3.44starpu_mpi_node_selection_register_policy
27.28.3.45starpu_mpi_node_selection_unregister_policy
27.28.3.46starpu_mpi_redux_data
27.28.3.47starpu_mpi_scatter_detached

CONTENTS xxxi

27.28.3.4&starpu_mpi_gather_detached
27.29Task Bundles
27.29.1 Detailed Description
27.29.2 Typedef Documentation
27.29.2.1 starpu_task_bundle_t
27.29.3 Function Documentation
27.29.3.1 starpu_task_bundle_create
27.29.3.2 starpu_task_bundle_insert
27.29.3.3 starpu_task_bundle_remove
27.29.3.4 starpu_task_bundle_close
27.29.3.5 starpu_task_bundle_expected_length
27.29.3.6 starpu_task_bundle_expected_power
27.29.3.7 starpu_task_bundle_expected_data_transfer_time
27.30Task Lists
27.30.1 Detailed Description
27.30.2 Data Structure Documentation
27.30.2.1 struct starpu_task_list
27.30.3 Function Documentation
27.30.3.1 starpu_task_list_init
27.30.3.2 starpu_task_list_push_front
27.30.3.3 starpu_task_list_push_back
27.30.3.4 starpu_task_list_front
27.30.3.5 starpu_task_list_back
27.30.3.6 starpu_task_list_empty
27.30.3.7 starpu_task_list_erase
27.30.3.8 starpu_task_list_pop_front
27.30.3.9 starpu_task_list_pop_back
27.30.3.10starpu_task_list_begin
27.30.3.11starpu_task_list_next
27.31 Parallel Tasks
27.31.1 Detailed Description
27.31.2 Function Documentation
27.31.2.1 starpu_combined_worker_get_size
27.31.2.2 starpu_combined_worker_get_rank
27.31.2.3 starpu_combined_worker_get_count
27.31.2.4 starpu_combined_worker_get_id
27.31.2.5 starpu_combined_worker_assign_workerid
27.31.2.6 starpu_combined_worker_get_description
27.31.2.7 starpu_combined_worker_can_execute_task
27.31.2.8 starpu_parallel_task_barrier_init

xxxii CONTENTS

27.31.2.9 starpu_parallel_task_barrier_init_n
27.32Running Drivers
27.32.1 Detailed Description
27.32.2 Function Documentation
27.32.2.1 starpu_driver_run
27.32.2.2 starpu_driver_init
27.32.2.3 starpu_driver_run_once
27.32.2.4 starpu_driver_deinit
27.32.2.5 starpu_drivers_request_termination
27.33Expert Mode
27.33.1 Detailed Description
27.33.2 Function Documentation
27.33.2.1 starpu_wake_all_blocked_workers
27.33.2.2 starpu_progression_hook_register
27.33.2.3 starpu_progression_hook_deregister
27.34StarPU-Top Interface
27.34.1 Detailed Description
27.34.2 Data Structure Documentation
27.34.2.1 struct starpu_top_data
27.34.2.2 struct starpu_top_param
27.34.3 Enumeration Type Documentation
27.34.3.1 starpu_top_data_type
27.34.3.2 starpu_top_param_type
27.34.3.3 starpu_top_message_type
27.34.4 Function Documentation
27.34.4.1 starpu_top_add_data_boolean
27.34.4.2 starpu_top_add_data_integer
27.34.4.3 starpu_top_add_data_float
27.34.4.4 starpu_top_register_parameter_boolean
27.34.4.5 starpu_top_register_parameter_float
27.34.4.6 starpu_top_register_parameter_integer
27.34.4.7 starpu_top_register_parameter_enum
27.34.4.8 starpu_top_init_and_wait
27.34.4.9 starpu_top_update_parameter
27.34.4.10starpu_top_update_data_boolean
27.34.4.11starpu_top_update_data_integer
27.34.4.12starpu_top_update_data_float
27.34.4.13starpu_top_task_prevision
27.34.4.14starpu_top_debug_log
27.34.4.15starpu_top_debug_lock

CONTENTS xxxiii

27.35Scheduling Contexts	10
27.35.1 Detailed Description	11
27.35.2 Data Structure Documentation	11
27.35.2.1 struct starpu_sched_ctx_performance_counters	11
27.35.3 Macro Definition Documentation	12
27.35.3.1 STARPU_SCHED_CTX_POLICY_NAME	12
27.35.3.2 STARPU_SCHED_CTX_POLICY_STRUCT	12
27.35.3.3 STARPU_SCHED_CTX_POLICY_MIN_PRIO	12
27.35.3.4 STARPU_SCHED_CTX_POLICY_MAX_PRIO	12
27.35.3.5 STARPU_MIN_PRIO	12
27.35.3.6 STARPU_MAX_PRIO	12
27.35.3.7 STARPU_DEFAULT_PRIO	13
27.35.4 Function Documentation	13
27.35.4.1 starpu_sched_ctx_create	13
27.35.4.2 starpu_sched_ctx_create_inside_interval	13
27.35.4.3 starpu_sched_ctx_register_close_callback	13
27.35.4.4 starpu_sched_ctx_add_workers	13
27.35.4.5 starpu_sched_ctx_remove_workers	13
27.35.4.6 starpu_sched_ctx_display_workers	13
27.35.4.7 starpu_sched_ctx_delete	13
27.35.4.8 starpu_sched_ctx_set_inheritor	14
27.35.4.9 starpu_sched_ctx_set_context	14
27.35.4.10starpu_sched_ctx_get_context	14
27.35.4.11starpu_sched_ctx_stop_task_submission	14
27.35.4.12starpu_sched_ctx_finished_submit	14
27.35.4.13starpu_sched_ctx_get_workers_list	14
27.35.4.14starpu_sched_ctx_get_nworkers	14
27.35.4.15starpu_sched_ctx_get_nshared_workers	14
27.35.4.16starpu_sched_ctx_contains_worker	14
27.35.4.17starpu_sched_ctx_worker_get_id	14
27.35.4.18starpu_sched_ctx_overlapping_ctxs_on_worker	14
27.35.4.19starpu_sched_ctx_set_min_priority	15
27.35.4.20starpu_sched_ctx_set_max_priority	15
27.35.4.21starpu_sched_ctx_get_min_priority	15
27.35.4.22starpu_sched_ctx_get_max_priority	15
27.35.4.23starpu_sched_ctx_min_priority_is_set	
27.35.4.24starpu_sched_ctx_max_priority_is_set	
27.35.4.25starpu_sched_ctx_create_worker_collection	
27.35.4.26starpu_sched_ctx_delete_worker_collection	
27.35.4.27starpu_sched_ctx_get_worker_collection	

CONTENTS

27.35.4.28starpu_sched_ctx_set_perf_counters	315
27.35.4.2%starpu_sched_ctx_call_pushed_task_cb	316
27.35.4.30starpu_sched_ctx_notify_hypervisor_exists	316
27.35.4.31starpu_sched_ctx_check_if_hypervisor_exists	316
27.35.4.32starpu_sched_ctx_set_policy_data	316
27.35.4.33starpu_sched_ctx_get_policy_data	316
27.35.4.34starpu_sched_ctx_exec_parallel_code	316
27.35.4.35starpu_sched_ctx_get_nready_tasks	316
27.35.4.36starpu_sched_ctx_get_nready_flops	316
27.36Scheduling Policy	316
27.36.1 Detailed Description	317
27.36.2 Data Structure Documentation	317
27.36.2.1 struct starpu_sched_policy	317
27.36.3 Function Documentation	318
27.36.3.1 starpu_sched_get_predefined_policies	319
27.36.3.2 starpu_worker_get_sched_condition	319
27.36.3.3 starpu_sched_set_min_priority	319
27.36.3.4 starpu_sched_set_max_priority	319
27.36.3.5 starpu_sched_get_min_priority	319
27.36.3.6 starpu_sched_get_max_priority	319
27.36.3.7 starpu_push_local_task	319
27.36.3.8 starpu_push_task_end	319
27.36.3.9 starpu_worker_can_execute_task	319
27.36.3.10starpu_worker_can_execute_task_impl	320
27.36.3.11starpu_worker_can_execute_task_first_impl	320
27.36.3.12starpu_task_footprint	320
27.36.3.13starpu_task_data_footprint	320
27.36.3.14starpu_task_expected_length	320
27.36.3.15starpu_worker_get_relative_speedup	320
27.36.3.16starpu_task_expected_data_transfer_time	320
27.36.3.17starpu_data_expected_transfer_time	320
27.36.3.18starpu_task_expected_power	320
27.36.3.19starpu_task_expected_conversion_time	320
27.36.3.20starpu_get_prefetch_flag	321
27.36.3.21starpu_prefetch_task_input_on_node	321
27.36.3.22starpu_idle_prefetch_task_input_on_node	321
27.36.3.23starpu_sched_ctx_worker_shares_tasks_lists	321
27.37Tree	321
27.37.1 Detailed Description	321
27.37.2 Data Structure Documentation	321

CONTENTS XXXV

27.37.2.1 struct starpu_tree	321
27.37.3 Function Documentation	322
27.37.3.1 starpu_tree_reset_visited	322
27.37.3.2 starpu_tree_insert	322
27.37.3.3 starpu_tree_get	322
27.37.3.4 starpu_tree_get_neighbour	322
27.37.3.5 starpu_tree_free	322
27.38Scheduling Context Hypervisor - Regular usage	322
27.38.1 Detailed Description	323
27.38.2 Macro Definition Documentation	323
27.38.2.1 SC_HYPERVISOR_MAX_IDLE	323
27.38.2.2 SC_HYPERVISOR_PRIORITY	323
27.38.2.3 SC_HYPERVISOR_MIN_WORKERS	323
27.38.2.4 SC_HYPERVISOR_MAX_WORKERS	323
27.38.2.5 SC_HYPERVISOR_GRANULARITY	323
27.38.2.6 SC_HYPERVISOR_FIXED_WORKERS	323
27.38.2.7 SC_HYPERVISOR_MIN_TASKS	324
27.38.2.8 SC_HYPERVISOR_NEW_WORKERS_MAX_IDLE	324
27.38.2.9 SC_HYPERVISOR_TIME_TO_APPLY	324
27.38.2.10SC_HYPERVISOR_ISPEED_W_SAMPLE	324
27.38.2.11SC_HYPERVISOR_ISPEED_CTX_SAMPLE	324
27.38.2.126C_HYPERVISOR_NULL	324
27.38.3 Function Documentation	324
27.38.3.1 sc_hypervisor_init	324
27.38.3.2 sc_hypervisor_shutdown	324
27.38.3.3 sc_hypervisor_register_ctx	325
27.38.3.4 sc_hypervisor_unregister_ctx	325
27.38.3.5 sc_hypervisor_resize_ctxs	325
27.38.3.6 sc_hypervisor_stop_resize	325
27.38.3.7 sc_hypervisor_start_resize	325
27.38.3.8 sc_hypervisor_get_policy	325
27.38.3.9 sc_hypervisor_add_workers_to_sched_ctx	325
27.38.3.10sc_hypervisor_remove_workers_from_sched_ctx	325
27.38.3.11sc_hypervisor_move_workers	325
27.38.3.12sc_hypervisor_size_ctxs	325
27.38.3.13sc_hypervisor_set_type_of_task	325
27.38.3.14sc_hypervisor_update_diff_total_flops	326
27.38.3.15sc_hypervisor_update_diff_elapsed_flops	326
27.38.3.16sc_hypervisor_ctl	326
27.39Scheduling Context Hypervisor - Building a new resizing policy	326

xxxvi CONTENTS

27.39.1 Detailed Description	326
27.39.2 Data Structure Documentation	326
27.39.2.1 struct sc_hypervisor_policy	326
27.39.2.2 struct sc_hypervisor_policy_config	328
27.39.2.3 struct sc_hypervisor_wrapper	328
27.39.2.4 struct sc_hypervisor_resize_ack	329
27.39.2.5 struct sc_hypervisor_policy_task_pool	329
27.39.3 Function Documentation	330
27.39.3.1 sc_hypervisor_post_resize_request	330
27.39.3.2 sc_hypervisor_get_size_req	330
27.39.3.3 sc_hypervisor_save_size_req	330
27.39.3.4 sc_hypervisor_free_size_req	330
27.39.3.5 sc_hypervisor_can_resize	330
27.39.3.6 sc_hypervisor_get_config	330
27.39.3.7 sc_hypervisor_set_config	330
27.39.3.8 sc_hypervisor_get_sched_ctxs	330
27.39.3.9 sc_hypervisor_get_nsched_ctxs	330
27.39.3.10sc_hypervisor_get_wrapper	330
27.39.3.11sc_hypervisor_get_elapsed_flops_per_sched_ctx 3	330
27.40 Modularized Scheduler Interface	331
27.40.1 Detailed Description	333
27.40.2 Data Structure Documentation	333
27.40.2.1 struct starpu_sched_component	333
27.40.2.2 struct starpu_sched_tree	336
27.40.2.3 struct starpu_sched_component_fifo_data	336
27.40.2.4 struct starpu_sched_component_prio_data	336
27.40.2.5 struct starpu_sched_component_mct_data	336
27.40.2.6 struct starpu_sched_component_perfmodel_select_data	336
27.40.2.7 struct starpu_sched_component_composed_recipe	337
27.40.2.8 struct starpu_sched_component_specs	337
27.40.3 Macro Definition Documentation	337
27.40.3.1 STARPU_SCHED_COMPONENT_IS_HOMOGENEOUS	337
27.40.3.2 STARPU_SCHED_COMPONENT_IS_SINGLE_MEMORY_NODE 3	337
27.40.4 Enumeration Type Documentation	337
27.40.4.1 starpu_sched_component_properties	337
27.40.5 Function Documentation	38
27.40.5.1 starpu_sched_tree_create	38
27.40.5.2 starpu_sched_tree_destroy	338
27.40.5.3 starpu_sched_tree_update_workers	38
27.40.5.4 starpu_sched_tree_update_workers_in_ctx	338

**CONTENTS** xxxvii

	27.40.5.5 starpu_sched_tree_push_task	338
	27.40.5.6 starpu_sched_tree_add_workers	338
	27.40.5.7 starpu_sched_tree_remove_workers	338
	27.40.5.8 starpu_sched_component_connect	338
	27.40.5.9 starpu_sched_component_destroy	338
	27.40.5.10starpu_sched_component_destroy_rec	339
	27.40.5.11starpu_sched_component_can_execute_task	339
	27.40.5.12starpu_sched_component_execute_preds	339
	27.40.5.13starpu_sched_component_transfer_length	339
	27.40.5.14starpu_sched_component_worker_get	339
	27.40.5.15starpu_sched_component_worker_get_workerid	339
	27.40.5.16starpu_sched_component_is_worker	339
	27.40.5.17starpu_sched_component_is_simple_worker	339
	27.40.5.18starpu_sched_component_is_combined_worker	339
	27.40.5.19starpu_sched_component_worker_pre_exec_hook	339
	27.40.5.20starpu_sched_component_worker_post_exec_hook	340
	27.40.5.21starpu_sched_component_fifo_create	340
	27.40.5.22starpu_sched_component_is_fifo	340
	27.40.5.23starpu_sched_component_prio_create	340
	27.40.5.24starpu_sched_component_is_prio	340
	27.40.5.25starpu_sched_tree_work_stealing_push_task	340
	27.40.5.26starpu_sched_component_is_work_stealing	340
	27.40.5.27starpu_sched_component_is_random	340
	27.40.5.28starpu_sched_component_is_eager	340
	27.40.5.29starpu_sched_component_is_eager_calibration	340
	27.40.5.30starpu_sched_component_mct_create	340
	27.40.5.31starpu_sched_component_is_mct	341
	27.40.5.32starpu_sched_component_heft_create	341
	27.40.5.33starpu_sched_component_is_heft	341
	27.40.5.34starpu_sched_component_perfmodel_select_create	341
	27.40.5.35starpu_sched_component_is_perfmodel_select	341
	27.40.5.36starpu_sched_component_composed_recipe_create	341
	27.40.5.37starpu_sched_component_composed_recipe_create_singleton	341
	27.40.5.38starpu_sched_component_composed_recipe_add	341
	27.40.5.39starpu_sched_component_composed_recipe_destroy	341
	27.40.5.40starpu_sched_component_composed_component_create	341
	27.40.5.41starpu_sched_component_make_scheduler	342
Eilo Indox		240
File Index		343
∠ö.ı File List	1	343

28 File Index

xxxviii CONTENTS

29	File I	Documentation	345
	29.1	starpu.h File Reference	345
		29.1.1 Detailed Description	346
	29.2	starpu_bitmap.h File Reference	346
		29.2.1 Detailed Description	346
	29.3	starpu_bound.h File Reference	346
		29.3.1 Detailed Description	347
	29.4	starpu_config.h File Reference	347
		29.4.1 Detailed Description	348
	29.5	starpu_cublas.h File Reference	348
		29.5.1 Detailed Description	349
	29.6	starpu_cuda.h File Reference	349
		29.6.1 Detailed Description	349
	29.7	starpu_data.h File Reference	349
		29.7.1 Detailed Description	351
	29.8	starpu_data_filters.h File Reference	351
		29.8.1 Detailed Description	353
	29.9	starpu_data_interfaces.h File Reference	353
		29.9.1 Detailed Description	357
	29.10	Ostarpu_deprecated_api.h File Reference	357
		29.10.1 Detailed Description	357
	29.1	1 starpu_disk.h File Reference	357
		29.11.1 Detailed Description	
	29.12	2starpu_driver.h File Reference	358
		29.12.1 Detailed Description	
	29.13	3starpu_expert.h File Reference	358
		29.13.1 Detailed Description	
	29.14	4starpu_fxt.h File Reference	
		29.14.1 Detailed Description	
	29.15	5starpu_hash.h File Reference	
		29.15.1 Detailed Description	
	29.16	6starpu_mic.h File Reference	
		29.16.1 Detailed Description	
	29.17	7starpu_opencl.h File Reference	
		29.17.1 Detailed Description	
	29.18	8starpu_openmp.h File Reference	
		29.18.1 Detailed Description	
	29.19	9starpu_perfmodel.h File Reference	
		29.19.1 Detailed Description	
		29.19.2 Data Structure Documentation	365

CONTENTS xxxix

29.19.2.1 struct starpu_perfmodel_device
29.19.2.2 struct starpu_perfmodel_arch
29.20starpu_profiling.h File Reference
29.20.1 Detailed Description
29.21starpu_rand.h File Reference
29.21.1 Detailed Description
29.22starpu_scc.h File Reference
29.22.1 Detailed Description
29.23starpu_sched_ctx.h File Reference
29.23.1 Detailed Description
29.24starpu_sched_ctx_hypervisor.h File Reference
29.24.1 Detailed Description
29.25starpu_scheduler.h File Reference
29.25.1 Detailed Description
29.26starpu_sink.h File Reference
29.26.1 Detailed Description
29.27starpu_stdlib.h File Reference
29.27.1 Detailed Description
29.28starpu_task.h File Reference
29.28.1 Detailed Description
29.28.2 Macro Definition Documentation
29.28.2.1 STARPU_CUDA_ASYNC
29.28.2.2 STARPU_OPENCL_ASYNC
29.29starpu_task_bundle.h File Reference
29.29.1 Detailed Description
29.30starpu_task_list.h File Reference
29.30.1 Detailed Description
29.31 starpu_task_util.h File Reference
29.31.1 Detailed Description
29.32starpu_thread.h File Reference
29.32.1 Detailed Description
29.32.2 Data Structure Documentation
29.32.2.1 struct starpu_pthread_barrier_t
29.32.2.2 struct starpu_pthread_spinlock_t
29.33starpu_thread_util.h File Reference
29.33.1 Detailed Description
29.34starpu_top.h File Reference
29.34.1 Detailed Description
29.35starpu_tree.h File Reference
29.35.1 Detailed Description

CONTENTS 1

	29.36starpu_util.h File Reference	379
	29.36.1 Detailed Description	381
	29.37starpu_worker.h File Reference	381
	29.37.1 Detailed Description	382
	29.38starpu_mpi.h File Reference	382
	29.38.1 Detailed Description	384
	29.39starpufft.h File Reference	384
	29.39.1 Detailed Description	385
	29.40sc_hypervisor.h File Reference	385
	29.40.1 Detailed Description	386
	29.41 sc_hypervisor_config.h File Reference	386
	29.41.1 Detailed Description	387
	29.42sc_hypervisor_lp.h File Reference	387
	29.42.1 Detailed Description	387
	29.43sc_hypervisor_monitoring.h File Reference	387
	29.43.1 Detailed Description	388
	29.44sc_hypervisor_policy.h File Reference	388
	29.44.1 Detailed Description	389
	29.44.2 Data Structure Documentation	389
	29.44.2.1 struct types_of_workers	389
30	Deprecated List	391
VI	Appendix	393
31	Full Source Code for the 'Scaling a Vector' Example	395
	31.1 Main Application	395
	31.2 CPU Kernel	396
	31.3 CUDA Kernel	397
	31.4 OpenCL Kernel	397
	31.4.1 Invoking the Kernel	397
	31.4.2 Source of the Kernel	398
32	GNU Free Documentation License	399
	32.1 ADDENDUM: How to use this License for your documents	403
VII	I Index	405

2 **CONTENTS** 

### **Chapter 1**

### Introduction

#### 1.1 Motivation

The use of specialized hardware such as accelerators or coprocessors offers an interesting approach to overcome the physical limits encountered by processor architects. As a result, many machines are now equipped with one or several accelerators (e.g. a GPU), in addition to the usual processor(s). While a lot of efforts have been devoted to offload computation onto such accelerators, very little attention as been paid to portability concerns on the one hand, and to the possibility of having heterogeneous accelerators and processors to interact on the other hand.

StarPU is a runtime system that offers support for heterogeneous multicore architectures, it not only offers a unified view of the computational resources (i.e. CPUs and accelerators at the same time), but it also takes care of efficiently mapping and executing tasks onto an heterogeneous machine while transparently handling low-level issues such as data transfers in a portable fashion.

#### 1.2 StarPU in a Nutshell

StarPU is a software tool aiming to allow programmers to exploit the computing power of the available CPUs and GPUs, while relieving them from the need to specially adapt their programs to the target machine and processing units.

At the core of StarPU is its run-time support library, which is responsible for scheduling application-provided tasks on heterogeneous CPU/GPU machines. In addition, StarPU comes with programming language support, in the form of extensions to languages of the C family (C Extensions), as well as an OpenCL front-end (SOCL OpenCL Extensions).

StarPU's run-time and programming language extensions support a task-based programming model. Applications submit computational tasks, with CPU and/or GPU implementations, and StarPU schedules these tasks and associated data transfers on available CPUs and GPUs. The data that a task manipulates are automatically transferred among accelerators and the main memory, so that programmers are freed from the scheduling issues and technical details associated with these transfers.

StarPU takes particular care of scheduling tasks efficiently, using well-known algorithms from the literature (Task Scheduling Policy). In addition, it allows scheduling experts, such as compiler or computational library developers, to implement custom scheduling policies in a portable fashion (Defining A New Scheduling Policy).

The remainder of this section describes the main concepts used in StarPU.

#### 1.2.1 Codelet and Tasks

One of the StarPU primary data structures is the **codelet**. A codelet describes a computational kernel that can possibly be implemented on multiple architectures such as a CPU, a CUDA device or an OpenCL device.

Another important data structure is the task. Executing a StarPU task consists in applying a codelet on a data set,

4 Introduction

on one of the architectures on which the codelet is implemented. A task thus describes the codelet that it uses, but also which data are accessed, and how they are accessed during the computation (read and/or write). StarPU tasks are asynchronous: submitting a task to StarPU is a non-blocking operation. The task structure can also specify a **callback** function that is called once StarPU has properly executed the task. It also contains optional fields that the application may use to give hints to the scheduler (such as priority levels).

By default, task dependencies are inferred from data dependency (sequential coherency) by StarPU. The application can however disable sequential coherency for some data, and dependencies can be specifically expressed. A task may be identified by a unique 64-bit number chosen by the application which we refer as a **tag**. Task dependencies can be enforced either by the means of callback functions, by submitting other tasks, or by expressing dependencies between tags (which can thus correspond to tasks that have not yet been submitted).

#### 1.2.2 StarPU Data Management Library

Because StarPU schedules tasks at runtime, data transfers have to be done automatically and "just-in-time" between processing units, relieving application programmers from explicit data transfers. Moreover, to avoid unnecessary transfers, StarPU keeps data where it was last needed, even if was modified there, and it allows multiple copies of the same data to reside at the same time on several processing units as long as it is not modified.

#### 1.3 Application Taskification

**TODO** 

#### 1.4 Glossary

A **codelet** records pointers to various implementations of the same theoretical function.

A memory node can be either the main RAM, GPU-embedded memory or a disk memory.

A bus is a link between memory nodes.

A **data handle** keeps track of replicates of the same data (**registered** by the application) over various memory nodes. The data management library manages to keep them coherent.

The **home** memory node of a data handle is the memory node from which the data was registered (usually the main memory node).

A task represents a scheduled execution of a codelet on some data handles.

A **tag** is a rendez-vous point. Tasks typically have their own tag, and can depend on other tags. The value is chosen by the application.

A **worker** execute tasks. There is typically one per CPU computation core and one per accelerator (for which a whole CPU core is dedicated).

A **driver** drives a given kind of workers. There are currently CPU, CUDA, and OpenCL drivers. They usually start several workers to actually drive them.

A **performance model** is a (dynamic or static) model of the performance of a given codelet. Codelets can have execution time performance model as well as power consumption performance models.

A data **interface** describes the layout of the data: for a vector, a pointer for the start, the number of elements and the size of elements; for a matrix, a pointer for the start, the number of elements per row, the offset between rows, and the size of each element; etc. To access their data, codelet functions are given interfaces for the local memory node replicates of the data handles of the scheduled task.

**Partitioning** data means dividing the data of a given data handle (called **father**) into a series of **children** data handles which designate various portions of the former.

A **filter** is the function which computes children data handles from a father data handle, and thus describes how the partitioning should be done (horizontal, vertical, etc.)

1.5 Research Papers 5

**Acquiring** a data handle can be done from the main application, to safely access the data of a data handle from its home node, without having to unregister it.

#### 1.5 Research Papers

Research papers about StarPU can be found at <a href="http://runtime.bordeaux.inria.fr/Publis/-Keyword/STARPU.html">http://runtime.bordeaux.inria.fr/Publis/-Keyword/STARPU.html</a>.

A good overview is available in the research report at http://hal.archives-ouvertes.fr/inria-00467677.

#### 1.6 StarPU Applications

You can first have a look at the chapters Basic Examples and Advanced Examples. A tutorial is also installed in the directory <code>share/doc/starpu/tutorial/</code>.

Many examples are also available in the StarPU sources in the directory examples /. Simple examples include:

incrementer/ Trivial incrementation test.

basic\_examples/ Simple documented Hello world and vector/scalar product (as shown in Basic Examples), matrix product examples (as shown in Performance Model Example), an example using the blocked matrix data interface, an example using the variable data interface, and an example using different formats on CPUs and GPUs.

matvecmult/ OpenCL example from NVidia, adapted to StarPU.

axpy/ AXPY CUBLAS operation adapted to StarPU.

fortran/ Example of Fortran bindings.

More advanced examples include:

filters/ Examples using filters, as shown in Partitioning Data.

lu/ LU matrix factorization, see for instance xlu\_implicit.c

cholesky/ Cholesky matrix factorization, see for instance cholesky\_implicit.c.

#### 1.7 Further Reading

The documentation chapters include

- Part 1: StarPU Basics
  - Building and Installing StarPU
  - Basic Examples
- Part 2: StarPU Quick Programming Guide
  - Advanced Examples
  - Check List When Performance Are Not There
- Part 3: StarPU Inside
  - Tasks In StarPU
  - Data Management

6 Introduction

- Scheduling
- Scheduling Contexts
- Scheduling Context Hypervisor
- Debugging Tools
- Online Performance Tools
- Offline Performance Tools
- Frequently Asked Questions
- Part 4: StarPU Extensions
  - Out Of Core
  - MPI Support
  - FFT Support
  - MIC Xeon Phi / SCC Support
  - C Extensions
  - SOCL OpenCL Extensions
  - SimGrid Support
- Part 5: StarPU Reference API
  - Execution Configuration Through Environment Variables
  - Compilation Configuration
  - Module Documentation
  - File Documentation
  - Deprecated List
- · Part: Appendix
  - Full source code for the 'Scaling a Vector' example
  - The GNU Free Documentation License

Make sure to have had a look at those too!

# Part I StarPU Basics

# **Chapter 2**

# **Building and Installing StarPU**

#### 2.1 Installing a Binary Package

One of the StarPU developers being a Debian Developer, the packages are well integrated and very uptodate. To see which packages are available, simply type:

```
$ apt-cache search starpu
```

To install what you need, type for example:

```
$ sudo apt-get install libstarpu-1.2 libstarpu-dev
```

#### 2.2 Installing from Source

StarPU can be built and installed by the standard means of the GNU autotools. The following chapter is intended to briefly remind how these tools can be used to install StarPU.

#### 2.2.1 Optional Dependencies

The hwloc (http://www.open-mpi.org/software/hwloc) topology discovery library is not mandatory to use StarPU but strongly recommended. It allows for topology aware scheduling, which improves performance. hwloc is available in major free operating system distributions, and for most operating systems.

If hwloc is not available on your system, the option --without-hwloc should be explicitly given when calling the configure script. If hwloc is installed with a pkg-config file, no option is required, it will be detected automatically, otherwise --with-hwloc should be used to specify its location.

#### 2.2.2 Getting Sources

StarPU's sources can be obtained from the download page of the StarPU website (http://runtime.-bordeaux.inria.fr/StarPU/files/).

All releases and the development tree of StarPU are freely available on INRIA's gforge under the LGPL license. Some releases are available under the BSD license.

The latest release can be downloaded from the INRIA's gforge (http://gforge.inria.fr/frs/?group-\_id=1570) or directly from the StarPU download page (http://runtime.bordeaux.inria.fr/Star-PU/files/).

The latest nightly snapshot can be downloaded from the StarPU gforge website (http://starpu.gforge.-inria.fr/testing/).

```
$ wget http://starpu.gforge.inria.fr/testing/starpu-nightly-latest.tar.gz
```

And finally, current development version is also accessible via svn. It should be used only if you need the very latest changes (i.e. less than a day!). Note that the client side of the software Subversion can be obtained from http-://subversion.tigris.org. If you are running on Windows, you will probably prefer to use TortoiseSVN (http://tortoisesvn.tigris.org/).

```
$ svn checkout svn://scm.gforge.inria.fr/svn/starpu/trunk StarPU
```

#### 2.2.3 Configuring StarPU

Running autogen.sh is not necessary when using the tarball releases of StarPU. If you are using the source code from the svn repository, you first need to generate the configure scripts and the Makefiles. This requires the availability of autoconf and automake >= 2.60.

```
$ ./autogen.sh
```

You then need to configure StarPU. Details about options that are useful to give to ./configure are given in Compilation Configuration.

```
$ ./configure
```

If configure does not detect some software or produces errors, please make sure to post the content of config.log when reporting the issue.

By default, the files produced during the compilation are placed in the source directory. As the compilation generates a lot of files, it is advised to put them all in a separate directory. It is then easier to cleanup, and this allows to compile several configurations out of the same source tree. For that, simply enter the directory where you want the compilation to produce its files, and invoke the configure script located in the StarPU source directory.

```
$ mkdir build
$ cd build
$ ../configure
```

By default, StarPU will be installed in /usr/local/bin, /usr/local/lib, etc. You can specify an installation prefix other than /usr/local using the option -prefix, for instance:

```
$ ../configure --prefix=$HOME/starpu
```

#### 2.2.4 Building StarPU

```
$ make
```

Once everything is built, you may want to test the result. An extensive set of regression tests is provided with Star-PU. Running the tests is done by calling make check. These tests are run every night and the result from the main profile is publicly available (http://starpu.gforge.inria.fr/testing/).

```
$ make check
```

#### 2.2.5 Installing StarPU

In order to install StarPU at the location that was specified during configuration:

```
$ make install
```

Libtool interface versioning information are included in libraries names (libstarpu-1.2.so, libstarpumpi-1.-2.so and libstarpufft-1.2.so).

#### 2.3 Setting up Your Own Code

#### 2.3.1 Setting Flags for Compiling, Linking and Running Applications

StarPU provides a pkg-config executable to obtain relevant compiler and linker flags. As compiling and linking an application against StarPU may require to use specific flags or libraries (for instance CUDA or libspe2).

If StarPU was not installed at some standard location, the path of StarPU's library must be specified in the environment variable PKG\_CONFIG\_PATH so that pkg-config can find it. For example if StarPU was installed in \$STARPU PATH:

```
$ PKG_CONFIG_PATH=$PKG_CONFIG_PATH:$STARPU_PATH/lib/pkgconfig
```

The flags required to compile or link against StarPU are then accessible with the following commands:

```
$ pkg-config --cflags starpu-1.2 # options for the compiler
$ pkg-config --libs starpu-1.2 # options for the linker
```

Note that it is still possible to use the API provided in the version 1.0 of StarPU by calling pkg-config with the starpu-1.0 package. Similar packages are provided for starpumpi-1.0 and starpufft-1.0. It is also possible to use the API provided in the version 0.9 of StarPU by calling pkg-config with the libstarpu package. Similar packages are provided for libstarpumpi and libstarpufft.

Make sure that pkg-config -libs starpu-1.2 actually produces some output before going further: PK-G\_CONFIG\_PATH has to point to the place where starpu-1.2.pc was installed during make install.

Also pass the option -static if the application is to be linked statically.

It is also necessary to set the environment variable LD\_LIBRARY\_PATH to locate dynamic libraries at runtime.

```
$ LD_LIBRARY_PATH=$STARPU_PATH/lib:$LD_LIBRARY_PATH
```

When using a Makefile, the following lines can be added to set the options for the compiler and the linker:

#### 2.3.2 Running a Basic StarPU Application

Basic examples using StarPU are built in the directory examples/basic\_examples/ (and installed in \$ST-ARPU\_PATH/lib/starpu/examples/). You can for example run the example vector\_scal.

```
$ ./examples/basic_examples/vector_scal
BEFORE: First element was 1.000000
AFTER: First element is 3.140000
```

When StarPU is used for the first time, the directory  $STARPU_HOME/.starpu/is$  created, performance models will be stored in that directory (STARPU\_HOME).

Please note that buses are benchmarked when StarPU is launched for the first time. This may take a few minutes, or less if hwloc is installed. This step is done only once per user and per machine.

#### 2.3.3 Running a Basic StarPU Application on Microsoft Visual C

Batch files are provided to run StarPU applications under Microsoft Visual C. They are installed in \$STARPU\_PA-TH/bin/msvc.

To execute a StarPU application, you first need to set the environment variable STARPU\_PATH.

```
c:\....> cd c:\cygwin\home\ci\starpu\
c:\....> set STARPU_PATH=c:\cygwin\home\ci\starpu\
c:\....> cd bin\msvc
c:\....> starpu_open.bat starpu_simple.c
```

The batch script will run Microsoft Visual C with a basic project file to run the given application.

The batch script starpu\_clean.bat can be used to delete all compilation generated files.

The batch script starpu\_exec.bat can be used to compile and execute a StarPU application from the command prompt.

```
c:\....> cd c:\cygwin\home\ci\starpu\
c:\....> set STARPU_PATH=c:\cygwin\home\ci\starpu\
c:\....> cd bin\msvc
c:\....> starpu_exec.bat ..\..\..\examples\basic_examples\hello_world.c

MSVC StarPU Execution
...
/out:hello_world.exe
...
Hello world (params = {1, 2.00000})
Callback function got argument 0000042
c:\....>
```

#### 2.3.4 Kernel Threads Started by StarPU

StarPU automatically binds one thread per CPU core. It does not use SMT/hyperthreading because kernels are usually already optimized for using a full core, and using hyperthreading would make kernel calibration rather random.

Since driving GPUs is a CPU-consuming task, StarPU dedicates one core per GPU.

While StarPU tasks are executing, the application is not supposed to do computations in the threads it starts itself, tasks should be used instead.

TODO: add a StarPU function to bind an application thread (e.g. the main thread) to a dedicated core (and thus disable the corresponding StarPU CPU worker).

#### 2.3.5 Enabling OpenCL

When both CUDA and OpenCL drivers are enabled, StarPU will launch an OpenCL worker for NVIDIA GPUs only if CUDA is not already running on them. This design choice was necessary as OpenCL and CUDA can not run at the same time on the same NVIDIA GPU, as there is currently no interoperability between them.

To enable OpenCL, you need either to disable CUDA when configuring StarPU:

```
$ ./configure --disable-cuda
or when running applications:
$ STARPU_NCUDA=0 ./application
```

OpenCL will automatically be started on any device not yet used by CUDA. So on a machine running 4 GPUS, it is therefore possible to enable CUDA on 2 devices, and OpenCL on the 2 other devices by doing so:


```
$ STARPU_NCUDA=2 ./application
```

#### 2.4 Benchmarking StarPU

Some interesting benchmarks are installed among examples in \$STARPU\_PATH/lib/starpu/examples/. Make sure to try various schedulers, for instance STARPU\_SCHED=dmda.

#### 2.4.1 Task Size Overhead

This benchmark gives a glimpse into how long a task should be (in  $\mu$ s) for StarPU overhead to be low enough to keep efficiency. Running tasks\_size\_overhead.sh generates a plot of the speedup of tasks of various sizes, depending on the number of CPUs being used.



#### 2.4.2 Data Transfer Latency

local\_pingpong performs a ping-pong between the first two CUDA nodes, and prints the measured latency.

#### 2.4.3 Matrix-Matrix Multiplication

sgemm and dgemm perform a blocked matrix-matrix multiplication using BLAS and cuBLAS. They output the obtained GFlops.

#### 2.4.4 Cholesky Factorization

 $\verb|cholesky| x perform a Cholesky factorization (single precision). They use different dependency primitives.$ 

#### 2.4.5 LU Factorization

lu\_\* perform an LU factorization. They use different dependency primitives.

#### 2.4.6 Simulated benchmarks

It can also be convenient to try simulated benchmarks, if you want to give a try at CPU-GPU scheduling without actually having a GPU at hand. This can be done by using the simgrid version of StarPU: first install the simgrid simulator from http://simgrid.gforge.inria.fr/, then configure StarPU with --enable-simgrid and

rebuild and install it, and then you can simulate the performance for a few virtualized systems shipped along StarP-U: attila, mirage and idgraf.

#### For instance:

```
$ export STARPU_PERF_MODEL_DIR=$STARPU_PATH/share/starpu/perfmodels/sampling
$ export STARPU_HOSTNAME=attila
$ $STARPU_PATH/lib/starpu/examples/cholesky_implicit -size $((960*20)) -nblocks 20
```

Will show the performance of the cholesky factorization with the attila system. It will be interesting to try with different matrix sizes and schedulers.

Performance models are available for cholesky\_\*, lu\_\*, \*gemm, with block sizes 320, 640, or 960, and for stencil with block size 128x128x128, 192x192x192, and 256x256x256.

# **Chapter 3**

# **Basic Examples**

#### 3.1 Hello World Using The C Extension

This section shows how to implement a simple program that submits a task to StarPU using the StarPU C extension (C Extensions). The complete example, and additional examples, is available in the directory gcc-plugin/examples of the StarPU distribution. A similar example showing how to directly use the StarPU's API is shown in Hello World Using StarPU's API.

GCC from version 4.5 permit to use the StarPU GCC plug-in (C Extensions). This makes writing a task both simpler and less error-prone. In a nutshell, all it takes is to declare a task, declare and define its implementations (for CPU, OpenCL, and/or CUDA), and invoke the task like a regular C function. The example below defines my\_task which has a single implementation for CPU:

```
#include <stdio.h>
/* Task declaration. */
static void my_task (int x) __attribute__ ((task));
/* Definition of the CPU implementation of 'my_task'. */
static void my_task (int x)
 printf ("Hello, world! With x = dn', x);
int main ()
 /* Initialize StarPU. */
#pragma starpu initialize
  /* Do an asynchronous call to 'my_task'. */
 my_task (42);
  /\star Wait for the call to complete. \star/
#pragma starpu wait
  /* Terminate. */
#pragma starpu shutdown
  return 0;
```

The code can then be compiled and linked with GCC and the flag -fplugin:

```
$ gcc 'pkg-config starpu-1.2 --cflags' hello-starpu.c \
   -fplugin='pkg-config starpu-1.2 --variable=gccplugin' \
   'pkg-config starpu-1.2 --libs'
```

The code can also be compiled without the StarPU C extension and will behave as a normal sequential code.

16 Basic Examples

As can be seen above, the C extensions allows programmers to use StarPU tasks by essentially annotating "regular" C code.

#### 3.2 Hello World Using StarPU's API

This section shows how to achieve the same result as in the previous section using StarPU's standard C API.

#### 3.2.1 Required Headers

The header starpu.h should be included in any code using StarPU.

```
#include <starpu.h>
```

#### 3.2.2 Defining A Codelet

A codelet is a structure that represents a computational kernel. Such a codelet may contain an implementation of the same kernel on different architectures (e.g. CUDA, x86, ...). For compatibility, make sure that the whole structure is properly initialized to zero, either by using the function starpu\_codelet\_init(), or by letting the compiler implicitly do it as examplified above.

The field starpu\_codelet::nbuffers specifies the number of data buffers that are manipulated by the codelet: here the codelet does not access or modify any data that is controlled by our data management library.

We create a codelet which may only be executed on the CPUs. When a CPU core will execute a codelet, it will call the function cpu func, which *must* have the following prototype:

```
void (*cpu_func)(void *buffers[], void *cl_arg);
```

In this example, we can ignore the first argument of this function which gives a description of the input and output buffers (e.g. the size and the location of the matrices) since there is none. We also ignore the second argument which is a pointer to optional arguments for the codelet.

```
void cpu_func(void *buffers[], void *cl_arg)
{
    printf("Hello world\n");
}
struct starpu_codelet cl =
{
    .cpu_funcs = { cpu_func },
    .nbuffers = 0
};
```

#### 3.2.3 Submitting A Task

Before submitting any tasks to StarPU, starpu\_init() must be called. The NULL argument specifies that we use the default configuration. Tasks cannot be submitted after the termination of StarPU by a call to starpu\_shutdown().

In the example above, a task structure is allocated by a call to <a href="starpu\_task\_create">starpu\_task\_create</a>(). This function only allocates and fills the corresponding structure with the default settings, but it does not submit the task to StarPU.

The field <a href="mailto:starpu\_task::cl">starpu\_task::cl</a> is a pointer to the codelet which the task will execute: in other words, the codelet structure describes which computational kernel should be offloaded on the different architectures, and the task structure is a wrapper containing a codelet and the piece of data on which the codelet should operate.

If the field starpu\_task::synchronous is non-zero, task submission will be synchronous: the function starpu\_task\_submit() will not return until the task has been executed. Note that the function starpu\_shutdown() does not guarantee that asynchronous tasks have been executed before it returns, starpu\_task\_wait\_for\_all() can be used to that effect, or data can be unregistered (starpu\_data\_unregister()), which will implicitly wait for all the tasks scheduled to work on it, unless explicitly disabled thanks to starpu\_data\_set\_default\_sequential\_consistency\_flag() or starpu\_data\_set\_sequential\_consistency\_flag().

```
int main(int argc, char **argv)
{
    /* initialize StarPU */
    starpu_init(NULL);

    struct starpu_task *task = starpu_task_create(
    );

    task->cl = &cl; /* Pointer to the codelet defined above */
    /* starpu_task_submit will be a blocking call. If unset,
    starpu_task_wait() needs to be called after submitting the task. */
    task->synchronous = 1;

    /* submit the task to StarPU */
    starpu_task_submit(task);

    /* terminate StarPU */
    starpu_shutdown();

    return 0;
}
```

#### 3.2.4 Execution Of Hello World

```
$ make hello_world
cc $(pkg-config --cflags starpu-1.2) hello_world.c -o hello_world $(pkg-config --libs starpu-1.2)
$ ./hello_world
Hello world
```

#### 3.2.5 Passing Arguments To The Codelet

The optional field starpu\_task::cl\_arg field is a pointer to a buffer (of size starpu\_task::cl\_arg\_size) with some parameters for the kernel described by the codelet. For instance, if a codelet implements a computational kernel that multiplies its input vector by a constant, the constant could be specified by the means of this buffer, instead of registering it as a StarPU data. It must however be noted that StarPU avoids making copy whenever possible and rather passes the pointer as such, so the buffer which is pointed at must be kept allocated until the task terminates, and if several tasks are submitted with various parameters, each of them must be given a pointer to their own buffer.

```
struct params
{
    int i;
    float f;
};

void cpu_func(void *buffers[], void *cl_arg)
{
    struct params *params = cl_arg;
    printf("Hello world (params = {%i, %f} )\n", params->i, params->f);
}
```

As said before, the field <a href="mailto:starpu\_codelet::nbuffers">starpu\_codelet::nbuffers</a> specifies the number of data buffers that are manipulated by the codelet. It does not count the argument — the parameter <code>cl\_arg</code> of the function <code>cpu\_func</code> — since it is not managed by our data management library, but just contains trivial parameters.

Be aware that this may be a pointer to a *copy* of the actual buffer, and not the pointer given by the programmer: if the codelet modifies this buffer, there is no guarantee that the initial buffer will be modified as well: this for instance implies that the buffer cannot be used as a synchronization medium. If synchronization is needed, data has to be registered to StarPU, see Vector Scaling Using StarPU's API.

```
int main(int argc, char **argv)
{
    /* initialize StarPU */
    starpu_init(NULL);

    struct starpu_task *task = starpu_task_create(
    );

    task->cl = &cl; /* Pointer to the codelet defined above */
    struct params params = { 1, 2.0f };
```

18 Basic Examples

```
task->cl_arg = &params;
task->cl_arg_size = sizeof(params);

/* starpu_task_submit will be a blocking call */
task->synchronous = 1;

/* submit the task to StarPU */
starpu_task_submit(task);

/* terminate StarPU */
starpu_shutdown();

return 0;
}

$ make hello_world
cc $(pkg-config --cflags starpu-1.2) hello_world.c -o hello_world $(pkg-config --libs starpu-1.2)
$ ./hello_world
Hello world (params = {1, 2.000000})
```

#### 3.2.6 Defining A Callback

Once a task has been executed, an optional callback function starpu\_task::callback\_func is called when defined. While the computational kernel could be offloaded on various architectures, the callback function is always executed on a CPU. The pointer starpu\_task::callback\_arg is passed as an argument of the callback function. The prototype of a callback function must be:

```
void (*callback_function) (void *);
void callback_func(void *callback_arg)
    printf("Callback function (arg %x)\n", callback_arg);
int main(int argc, char **argv)
    /* initialize StarPU */
    starpu_init(NULL);
    struct starpu_task *task = starpu_task_create(
    task \rightarrow cl = &cl; /* Pointer to the codelet defined above */
    task->callback_func = callback_func;
    task->callback\_arg = 0x42;
    /* starpu_task_submit will be a blocking call */
    task->synchronous = 1;
    /\star submit the task to StarPU \star/
    starpu_task_submit(task);
    /* terminate StarPU */
    starpu_shutdown();
    return 0;
}
$ make hello_world
cc $(pkg-config --cflags starpu-1.2) hello_world.c -o hello_world $(pkg-config --libs starpu-1.2)
$ ./hello_world
Hello world
Callback function (arg 42)
```

#### 3.2.7 Where To Execute A Codelet

```
struct starpu_codelet cl =
{
    .where = STARPU_CPU,
    .cpu_funcs = { cpu_func },
    .cpu_funcs_name = { "cpu_func" },
    .nbuffers = 0
};
```

We create a codelet which may only be executed on the CPUs. The optional field starpu\_codelet::where is a bitmask that defines where the codelet may be executed. Here, the value STARPU\_CPU means that only CPUs can execute this codelet. When the optional field starpu\_codelet::where is unset, its value is automatically set based on the availability of the different fields XXX\_funcs.

TODO: explain starpu\_codelet::cpu\_funcs\_name

#### 3.3 Vector Scaling Using the C Extension

The previous example has shown how to submit tasks. In this section, we show how StarPU tasks can manipulate data.

We will first show how to use the C language extensions provided by the GCC plug-in (C Extensions). The complete example, and additional examples, is available in the directory gcc-plugin/examples of the StarPU distribution. These extensions map directly to StarPU's main concepts: tasks, task implementations for CPU, OpenCL, or CUDA, and registered data buffers. The standard C version that uses StarPU's standard C programming interface is given in Vector Scaling Using StarPU's API.

First of all, the vector-scaling task and its simple CPU implementation has to be defined:

Next, the body of the program, which uses the task defined above, can be implemented:

The function main above does several things:

- · It initializes StarPU.
- It allocates vector in the heap; it will automatically be freed when its scope is left. Alternatively, good old malloc and free could have been used, but they are more error-prone and require more typing.
- It registers the memory pointed to by vector. Eventually, when OpenCL or CUDA task implementations are
  added, this will allow StarPU to transfer that memory region between GPUs and the main memory. Removing
  this pragma is an error.

20 Basic Examples

• It invokes the task vector\_scal. The invocation looks the same as a standard C function call. However, it is an asynchronous invocation, meaning that the actual call is performed in parallel with the caller's continuation.

- It waits for the termination of the asynchronous call vector\_scal.
- · Finally, StarPU is shut down.

The program can be compiled and linked with GCC and the flag -fplugin:

```
$ gcc 'pkg-config starpu-1.2 --cflags' vector_scal.c
   -fplugin='pkg-config starpu-1.2 --variable=gccplugin'
   'pkg-config starpu-1.2 --libs'
```

And voilà!

#### 3.3.1 Adding an OpenCL Task Implementation

Now, this is all fine and great, but you certainly want to take advantage of these newfangled GPUs that your lab just bought, don't you?

So, let's add an OpenCL implementation of the task <code>vector\_scal</code>. We assume that the OpenCL kernel is available in a file, <code>vector\_scal\_opencl\_kernel.cl</code>, not shown here. The OpenCL task implementation is similar to that used with the standard C API (Definition of the OpenCL Kernel). It is declared and defined in our C file like this:

```
/\star The OpenCL programs, loaded from 'main' (see below). \star/
static struct starpu_opencl_program cl_programs;
static void vector_scal_opencl (unsigned size, float vector[size],
                                 float factor)
  __attribute__ ((task_implementation ("opencl", vector_scal)));
static void
vector scal opencl (unsigned size, float vector[size], float factor)
  int id, devid, err;
  cl_kernel kernel;
  cl_command_queue queue;
  cl event event:
  /* VECTOR is GPU memory pointer, not a main memory pointer. */
  cl_mem val = (cl_mem) vector;
  id = starpu_worker_get_id ();
  devid = starpu_worker_get_devid (id);
  /* Prepare to invoke the kernel. In the future, this will be largely
      automated. */
  err = starpu_opencl_load_kernel (&kernel, &queue, &
      cl_programs,
                                   "vector_mult_opencl", devid);
  if (err != CL SUCCESS)
   STARPU_OPENCL_REPORT_ERROR (err);
  err = clSetKernelArg (kernel, 0, sizeof (size), &size);
  err |= clSetKernelArg (kernel, 1, sizeof (val), &val);
  err |= clSetKernelArg (kernel, 2, sizeof (factor), &factor);
  if (err)
   STARPU_OPENCL_REPORT_ERROR (err);
  size_t global = 1, local = 1;
  err = clEnqueueNDRangeKernel (queue, kernel, 1, NULL, &global,
                                &local, 0, NULL, &event);
  if (err != CL SUCCESS)
   STARPU_OPENCL_REPORT_ERROR (err);
  clFinish (queue);
  starpu_opencl_collect_stats (event);
  clReleaseEvent (event);
  /* Done with KERNEL. */
  starpu_opencl_release_kernel (kernel);
```

The OpenCL kernel itself must be loaded from main, sometime after the pragma initialize:

And that's it. The task  $vector\_scal$  now has an additional implementation, for OpenCL, which StarPU's scheduler may choose to use at run-time. Unfortunately, the  $vector\_scal\_opencl$  above still has to go through the common OpenCL boilerplate; in the future, additional extensions will automate most of it.

#### 3.3.2 Adding a CUDA Task Implementation

Adding a CUDA implementation of the task is very similar, except that the implementation itself is typically written in CUDA, and compiled with nvcc. Thus, the C file only needs to contain an external declaration for the task implementation:

The actual implementation of the CUDA task goes into a separate compilation unit, in a .cu file. It is very close to the implementation when using StarPU's standard C API (Definition of the CUDA Kernel).

```
/* CUDA implementation of the 'vector_scal' task, to be compiled with 'nvcc'.
#include <starpu.h>
#include <stdlib.h>
static __global__ void
vector_mult_cuda (unsigned n, float *val, float factor)
 unsigned i = blockIdx.x * blockDim.x + threadIdx.x;
  if (i < n)
    val[i] *= factor;
/\star Definition of the task implementation declared in the C file. \star/
vector_scal_cuda (size_t size, float vector[], float factor)
  unsigned threads_per_block = 64;
 unsigned nblocks = (size + threads_per_block - 1) / threads_per block;
  vector_mult_cuda <<< nblocks, threads_per_block, 0,
    starpu_cuda_get_local_stream () >>> (size,
      vector, factor);
  cudaStreamSynchronize (starpu cuda get local stream
       ());
```

The complete source code, in the directory gcc-plugin/examples/vector\_scal of the StarPU distribution, also shows how an SSE-specialized CPU task implementation can be added.

For more details on the C extensions provided by StarPU's GCC plug-in, see C Extensions.

#### 3.4 Vector Scaling Using StarPU's API

This section shows how to achieve the same result as explained in the previous section using StarPU's standard C API.

The full source code for this example is given in Full source code for the 'Scaling a Vector' example.

22 Basic Examples

#### 3.4.1 Source Code of Vector Scaling

Programmers can describe the data layout of their application so that StarPU is responsible for enforcing data coherency and availability across the machine. Instead of handling complex (and non-portable) mechanisms to perform data movements, programmers only declare which piece of data is accessed and/or modified by a task, and StarPU makes sure that when a computational kernel starts somewhere (e.g. on a GPU), its data are available locally.

Before submitting those tasks, the programmer first needs to declare the different pieces of data to StarPU using the functions starpu\_\*\_data\_register. To ease the development of applications for StarPU, it is possible to describe multiple types of data layout. A type of data layout is called an **interface**. There are different predefined interfaces available in StarPU: here we will consider the **vector interface**.

The following lines show how to declare an array of NX elements of type float using the vector interface:

The first argument, called the **data handle**, is an opaque pointer which designates the array in StarPU. This is also the structure which is used to describe which data is used by a task. The second argument is the node number where the data originally resides. Here it is STARPU\_MAIN\_RAM since the array vector is in the main memory. Then comes the pointer vector where the data can be found in main memory, the number of elements in the vector and the size of each element. The following shows how to construct a StarPU task that will manipulate the vector and a constant factor.

Since the factor is a mere constant float value parameter, it does not need a preliminary registration, and can just be passed through the pointer starpu\_task::cl\_arg like in the previous example. The vector parameter is described by its handle. starpu\_task::handles should be set with the handles of the data, the access modes for the data are defined in the field starpu\_codelet::modes (STARPU\_R for read-only, STARPU\_W for write-only and STARPU\_RW for read and write access).

The definition of the codelet can be written as follows:

```
void scal_cpu_func(void *buffers[], void *cl_arg)
{
    unsigned i;
    float *factor = cl_arg;

    /* length of the vector */
    unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* CPU copy of the vector pointer */
    float *val = (float *)STARPU_VECTOR_GET_PTR(buffers[0]);

    for (i = 0; i < n; i++)
        val[i] *= *factor;
}

struct starpu_codelet cl = {
    .cpu_funcs = { scal_cpu_func },
    .cpu_funcs_name = { "scal_cpu_func" },
    .nbuffers = 1,
    .modes = { STARPU_RW }
};</pre>
```

The first argument is an array that gives a description of all the buffers passed in the array starpu\_task::handles. The size of this array is given by the field starpu\_codelet::nbuffers. For the sake of genericity, this array contains pointers to the different interfaces describing each buffer. In the case of the **vector interface**, the location of the vector (resp. its length) is accessible in the starpu\_vector\_interface::ptr (resp. starpu\_vector\_interface::nx) of this interface. Since the vector is accessed in a read-write fashion, any modification will automatically affect future accesses to this vector made by other tasks.

The second argument of the function scal\_cpu\_func contains a pointer to the parameters of the codelet (given in starpu\_task::cl\_arg), so that we read the constant factor from this pointer.

#### 3.4.2 Execution of Vector Scaling

```
$ make vector_scal
cc $(pkg-config --cflags starpu-1.2) vector_scal.c -o vector_scal $(pkg-config --libs starpu-1.2)
$ ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
```

#### 3.5 Vector Scaling on an Hybrid CPU/GPU Machine

Contrary to the previous examples, the task submitted in this example may not only be executed by the CPUs, but also by a CUDA device.

#### 3.5.1 Definition of the CUDA Kernel

The CUDA implementation can be written as follows. It needs to be compiled with a CUDA compiler such as nvcc, the NVIDIA CUDA compiler driver. It must be noted that the vector pointer returned by STARPU\_VECTOR\_GET\_-PTR is here a pointer in GPU memory, so that it can be passed as such to the kernel call vector\_mult\_cuda.

```
#include <starpu.h>
static __global__ void vector_mult_cuda(unsigned n, float *val,
                                        float factor)
        unsigned i = blockIdx.x*blockDim.x + threadIdx.x;
        if (i < n)
               val[i] *= factor;
}
extern "C" void scal_cuda_func(void *buffers[], void *_args)
        float *factor = (float *)_args;
        /* length of the vector */
        unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
        /* local copy of the vector pointer */
                    (float *)STARPU_VECTOR_GET_PTR(
      buffers[0]);
        unsigned threads_per_block = 64;
        unsigned nblocks = (n + threads_per_block-1) / threads_per_block;
        vector_mult_cuda << nblocks, threads_per_block, 0,
       starpu_cuda_get_local_stream()>>>
                        (n, val, *factor);
        cudaStreamSynchronize(starpu_cuda_get_local_stream
      ());
}
```

#### 3.5.2 Definition of the OpenCL Kernel

The OpenCL implementation can be written as follows. StarPU provides tools to compile a OpenCL kernel stored in a file.

```
__kernel void vector_mult_opencl(int nx, __global float* val, float factor) {
```

24 Basic Examples

Contrary to CUDA and CPU, STARPU\_VECTOR\_GET\_DEV\_HANDLE has to be used, which returns a cl\_mem (which is not a device pointer, but an OpenCL handle), which can be passed as such to the OpenCL kernel. The difference is important when using partitioning, see Partitioning Data.

```
#include <starpu.h>
extern struct starpu_opencl_program programs;
void scal_opencl_func(void *buffers[], void *_args)
    float *factor = _args;
    int id, devid, err;
                                           /* OpenCL specific code */
    cl_kernel kernel;
                                            /* OpenCL specific code */
    cl_command_queue queue;
                                            /* OpenCL specific code */
   cl_event event;
                                           /* OpenCL specific code */
    /* length of the vector */
    unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* OpenCL copy of the vector pointer */
    cl_mem val = (cl_mem)STARPU_VECTOR_GET_DEV_HANDLE
      (buffers[0]);
    { /* OpenCL specific code */
        id = starpu_worker_get_id();
         devid = starpu_worker_get_devid(id);
         err = starpu_opencl_load_kernel(&kernel, &
      queue,
                                           &programs,
                                            vector_mult_opencl", /* Name of the
       codelet */
                                           devid);
         if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR
      (err);
         err = clSetKernelArg(kernel, 0, sizeof(n), &n);
         err |= clSetKernelArg(kernel, 1, sizeof(val), &val);
err |= clSetKernelArg(kernel, 2, sizeof(*factor), factor);
         if (err) STARPU_OPENCL_REPORT_ERROR(err);
       /* OpenCL specific code */
       size_t global=n;
size_t local;
        size_t s;
        cl_device_id device;
        starpu_opencl_get_device(devid, &device);
        err = clGetKernelWorkGroupInfo (kernel, device,
      CL_KERNEL_WORK_GROUP_SIZE,
                                          sizeof(local), &local, &s);
        if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR
      (err);
        if (local > global) local=global;
        err = clEnqueueNDRangeKernel(queue, kernel, 1, NULL, &global, &local, 0
                                      NULL, &event);
        if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR
      (err);
    {    /* OpenCL specific code */
         clFinish(queue);
         starpu_opencl_collect_stats(event);
         clReleaseEvent(event);
         starpu_opencl_release_kernel(kernel);
```

#### 3.5.3 Definition of the Main Code

The CPU implementation is the same as in the previous section.

Here is the source of the main application. You can notice that the fields <a href="starpu\_codelet::cuda\_funcs">starpu\_codelet::cuda\_funcs</a> and <a href="starpu\_codelet::cu

```
\star This example demonstrates how to use StarPU to scale an array by a factor.
 \star It shows how to manipulate data with StarPU's data management library.
 * 1- how to declare a piece of data to StarPU (starpu_vector_data_register)
 \star 2- how to describe which data are accessed by a task (task->handles[0])
   3- how a kernel can manipulate the data (buffers[0].vector.ptr)
#include <starpu.h>
#define NX
                 2048
extern void scal_cpu_func(void *buffers[], void *_args);
extern void scal_sse_func(void *buffers[], void *_args);
extern void scal_cuda_func(void *buffers[], void *_args);
extern void scal_opencl_func(void *buffers[], void *_args);
static struct starpu_codelet cl = {
   .where = STARPU_CPU | STARPU_CUDA | STARPU_OPENCL
    /* CPU implementation of the codelet \star/
    .cpu_funcs = { scal_cpu_func, scal_sse_func },
    .cpu_funcs_name = { "scal_cpu_func", "scal_sse_func" },
#ifdef STARPU_USE_CUDA
    /\star CUDA implementation of the codelet \star/
    .cuda_funcs = { scal_cuda_func },
#endif
#ifdef STARPU_USE_OPENCL
    /\star OpenCL implementation of the codelet \star/
    .opencl_funcs = { scal_opencl_func },
#endif
    .nbuffers = 1,
    .modes = { STARPU_RW }
#ifdef STARPU_USE_OPENCL
struct starpu_opencl_program programs;
#endif
int main(int argc, char **argv)
    /* We consider a vector of float that is initialized just as any of C
      * data */
    float vector[NX]:
    unsigned i;
    for (i = 0; i < NX; i++)
        vector[i] = 1.0f;
    fprintf(stderr, "BEFORE: First element was %f\n", vector[0]);
    /* Initialize StarPU with default configuration */
    starpu_init(NULL);
#ifdef STARPU_USE_OPENCL
        starpu_opencl_load_opencl_from_file(
                "examples/basic_examples/vector_scal_opencl_kernel.cl", &
      programs, NULL);
#endif
    /\star Tell StaPU to associate the "vector" vector with the "vector_handle"
     \star identifier. When a task needs to access a piece of data, it should
     * refer to the handle that is associated to it.
* In the case of the "vector" data interface:
     \star - the first argument of the registration method is a pointer to the
          handle that should describe the data
     \star - the second argument is the memory node where the data (ie. "vector")
         resides initially: STARPU_MAIN_RAM stands for an address in main
      memory, as
         opposed to an adress on a GPU for instance.
     \star\, — the third argument is the adress of the vector in RAM
       - the fourth argument is the number of elements in the vector
        - the fifth argument is the size of each element.
    starpu_data_handle_t vector_handle;
    {\tt starpu\_vector\_data\_register\,(\&vector\_handle,}
      STARPU_MAIN_RAM, (uintptr_t) vector,
                                  NX, sizeof(vector[0]));
    float factor = 3.14;
    /* create a synchronous task: any call to starpu_task_submit will block
      * until it is terminated */
    struct starpu_task *task = starpu_task_create(
```

26 Basic Examples

```
task->synchronous = 1;
    task->cl = &cl;
    /\star the codelet manipulates one buffer in RW mode \star/
    task->handles[0] = vector handle;
    /\star an argument is passed to the codelet, beware that this is a
     \star READ-ONLY buffer and that the codelet may be given a pointer to a
     * COPY of the argument */
    task->cl_arg = &factor;
    task->cl_arg_size = sizeof(factor);
    /\star execute the task on any eligible computational ressource \star/
    /* \ {\tt StarPU \ does \ not \ need \ to \ manipulate \ the \ array \ anymore \ so \ we \ can \ stop}
      * monitoring it */
    starpu_data_unregister(vector_handle);
#ifdef STARPU_USE_OPENCL
    starpu_opencl_unload_opencl(&programs);
#endif
    /* terminate StarPU, no task can be submitted after */
    starpu_shutdown();
    fprintf(stderr, "AFTER First element is fn", vector[0]);
    return 0:
```

#### 3.5.4 Execution of Hybrid Vector Scaling

The Makefile given at the beginning of the section must be extended to give the rules to compile the CUDA source code. Note that the source file of the OpenCL kernel does not need to be compiled now, it will be compiled at run-time when calling the function starpu\_opencl\_load\_opencl\_from\_file().

and to execute it, with the default configuration:

```
$ ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
```

or for example, by disabling CPU devices:

```
$ STARPU_NCPU=0 ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
```

or by disabling CUDA devices (which may permit to enable the use of OpenCL, see Enabling OpenCL):

```
$ STARPU_NCUDA=0 ./vector_scal
0.000000 3.000000 6.000000 9.000000 12.000000
```

# Part II StarPU Quick Programming Guide

# **Chapter 4**

# **Advanced Examples**

TODO

30 Advanc
-----------

# **Chapter 5**

# **Check List When Performance Are Not There**

TODO: improve!

Simply encapsulating application kernels into tasks already permits to seamlessly support CPU and GPUs at the same time. To achieve good performance, we give below a list of features which should be checked.

#### 5.1 Data Related Features That May Improve Performance

link to Data Management
link to Data Prefetch

#### 5.2 Task Related Features That May Improve Performance

link to Task Granularity link to Task Submission link to Task Priorities

#### 5.3 Scheduling Related Features That May Improve Performance

link to Task Scheduling Policy
link to Task Distribution Vs Data Transfer
link to Power-based Scheduling
link to Static Scheduling

#### 5.4 CUDA-specific Optimizations

Due to CUDA limitations, StarPU will have a hard time overlapping its own communications and the codelet computations if the application does not use a dedicated CUDA stream for its computations instead of the default stream, which synchronizes all operations of the GPU. StarPU provides one by the use of starpu\_cuda\_get\_local\_stream() which can be used by all CUDA codelet operations to avoid this issue. For instance:

Unfortunately, some CUDA libraries do not have stream variants of kernels. That will lower the potential for overlapping.

Calling starpu\_cublas\_init() makes StarPU already do appropriate calls for the CUBLAS library. Some libraries like Magma may however change the current stream, one then has to call cublasSetKernelStream(starpu\_cuda\_get\_local\_stream()); at the beginning of the codelet to make sure that CUBLAS is really using the proper stream.

If the kernel can be made to only use this local stream or other self-allocated streams, i.e. the whole kernel submission can be made asynchronous, then one should enable asynchronous execution of the kernel. That means setting the flag STARPU\_CUDA\_ASYNC in the corresponding field starpu\_codelet::cuda\_flags, and dropping the cudaStreamSynchronize() call at the end of the cuda\_func function, so that it returns immediately after having queued the kernel to the local stream. That way, StarPU will be able to submit and complete data transfers while kernels are executing, instead of only at each kernel submission. The kernel just has to make sure that StarPU can use the local stream to synchronize with the kernel startup and completion.

Using the flag STARPU\_CUDA\_ASYNC also permits to enable concurrent kernel execution, on cards which support it (Kepler and later, notably). This is enabled by setting the environment variable STARPU\_NWORKER\_PER\_C-UDA to the number of kernels to execute concurrently. This is useful when kernels are small and do not feed the whole GPU with threads to run.

#### 5.5 OpenCL-specific Optimizations

If the kernel can be made to only use the StarPU-provided command queue or other self-allocated queues, i.e. the whole kernel submission can be made asynchronous, then one should enable asynchronous execution of the kernel. This means setting the flag STARPU\_OPENCL\_ASYNC in the corresponding field starpu\_codelet::opencl\_flags and dropping the clFinish() and starpu\_opencl\_collect\_stats() calls at the end of the kernel, so that it returns immediately after having queued the kernel to the provided queue. That way, StarPU will be able to submit and complete data transfers while kernels are executing, instead of only at each kernel submission. The kernel just has to make sure that StarPU can use the command queue it has provided to synchronize with the kernel startup and completion.

#### 5.6 Detection Stuck Conditions

It may happen that for some reason, StarPU does not make progress for a long period of time. Reason are sometimes due to contention inside StarPU, but sometimes this is due to external reasons, such as stuck MPI driver, or CUDA driver, etc.

```
export STARPU_WATCHDOG_TIMEOUT=10000 (STARPU_WATCHDOG_TIMEOUT)
```

allows to make StarPU print an error message whenever StarPU does not terminate any task for 10ms. In addition to that,

```
export STARPU_WATCHDOG_CRASH=1 (STARPU WATCHDOG CRASH)
```

raises SIGABRT in that condition, thus allowing to catch the situation in gdb. It can also be useful to type "handle SIGABRT nopass" in gdb to be able to let the process continue, after inspecting the state of the process.

#### 5.7 How to limit memory used by StarPU and cache buffer allocations

By default, StarPU makes sure to use at most 90% of the memory of GPU devices, moving data in and out of the device as appropriate and with prefetch and writeback optimizations. Concerning the main memory, by default it will not limit its consumption, since by default it has nowhere to push the data to when memory gets tight. This also means that by default StarPU will not cache buffer allocations in main memory, since it does not know how much of the system memory it can afford.

In the case of GPUs, the STARPU\_LIMIT\_CUDA\_MEM, STARPU\_LIMIT\_CUDA\_devid\_MEM, STARPU\_LIMIT\_-OPENCL\_MEM, and STARPU\_LIMIT\_OPENCL\_devid\_MEM environment variables can be used to control how

much (in MiB) of the GPU device memory should be used at most by StarPU (their default values are 90% of the available memory).

In the case of the main memory, the STARPU\_LIMIT\_CPU\_MEM environment variable can be used to specify how much (in MiB) of the main memory should be used at most by StarPU for buffer allocations. This way, StarPU will be able to cache buffer allocations (which can be a real benefit if a lot of bufferes are involved, or if allocation fragmentation can become a problem), and when using Out Of Core, StarPU will know when it should evict data out to the disk.

It should be noted that by default only buffer allocations automatically done by StarPU are accounted here, i.e. allocations performed through <a href="mailoc\_on\_node">starpu\_malloc\_on\_node</a>() which are used by the data interfaces (matrix, vector, etc.). This does not include allocations performed by the application through e.g. malloc(). It does not include allocations performed through <a href="mailoc">starpu\_malloc</a>() either, only allocations performed explicitly with the STARPU\_MALLOC\_COUNT) are taken into account. If the application wants to make StarPU aware of its own allocations, so that StarPU knows precisely how much data is allocated, and thus when to evict allocation caches or data out to the disk, starpu\_memory\_allocate can be used to specify an amount of memory to be accounted for. <a href="mailocate">starpu\_memory\_deallocate</a> can be used to account freed memory back. Those can for instance be used by data interfaces with dynamic data buffers: instead of using starpu\_malloc\_on\_node, they would dynamically allocate data with malloc/realloc, and notify starpu of the delta thanks to starpu memory allocate and starpu memory deallocate calls.

starpu\_memory\_get\_total and starpu\_memory\_get\_available can be used to get an estimation of how much memory is available. starpu\_memory\_wait\_available can also be used to block until an amount of memory becomes available (but it may be preferrable to use starpu\_memory\_allocate(STARPU\_MEMORY\_WAIT) to reserve that amount immediately).

## 5.8 How To Reduce The Memory Footprint Of Internal Data Structures

It is possible to reduce the memory footprint of the task and data internal structures of StarPU by describing the shape of your machine and/or your application at the configure step.

To reduce the memory footprint of the data internal structures of StarPU, one can set the --enable-maxcpus, --enable-maxcudadev, --enable-maxopencidev and --enable-maxnodes configure parameters to give StarPU the architecture of the machine it will run on, thus tuning the size of the structures to the machine.

To reduce the memory footprint of the task internal structures of StarPU, one can set the --enable-maxbuffers configure parameter to give StarPU the maximum number of buffers that a task can use during an execution. For example, in the Cholesky factorization (dense linear algebra application), the GEMM task uses up to 3 buffers, so it is possible to set the maximum number of task buffers to 3 to run a Cholesky factorization on StarPU.

#### 5.9 How to reuse memory

When your application needs to allocate more data than the available amount of memory usable by StarPU (given by starpu\_memory\_get\_available()), the allocation cache system can reuse data buffers used by previously executed tasks. For that system to work with MPI tasks, you need to submit tasks progressively instead of as soon as possible, because in the case of MPI receives, the allocation cache check for reusing data buffers will be done at submission time, not at execution time.

You have two options to control the task submission flow. The first one is by controlling the number of submitted tasks during the whole execution. This can be done whether by setting the environment variables STARPU\_LIMIT\_MAX\_NSUBMITTED\_TASKS and STARPU\_LIMIT\_MIN\_NSUBMITTED\_TASKS to tell StarPU when to stop submitting tasks and when to wake up and submit tasks again, or by explicitely calling starpu\_task\_wait\_for\_n\_submitted() in your application code for finest grain control (for example, between two iterations of a submission loop).

The second option is to control the memory size of the allocation cache. This can be done in the application by using jointly starpu\_memory\_get\_available() and starpu\_memory\_wait\_available() to submit tasks only when there is enough memory space to allocate the data needed by the task, i.e when enough data are available for reuse in the allocation cache.

#### 5.10 Performance Model Calibration

Most schedulers are based on an estimation of codelet duration on each kind of processing unit. For this to be possible, the application programmer needs to configure a performance model for the codelets of the application (see Performance Model Example for instance). History-based performance models use on-line calibration. StarPU will automatically calibrate codelets which have never been calibrated yet, and save the result in \$STARPU\_HOM-E/.starpu/sampling/codelets. The models are indexed by machine name. To share the models between machines (e.g. for a homogeneous cluster), use export STARPU\_HOSTNAME=some\_global\_name (STA-RPU\_HOSTNAME). To force continuing calibration, use export STARPU\_CALIBRATE=1 (STARPU\_CALIBRATE). This may be necessary if your application has not-so-stable performance. StarPU will force calibration (and thus ignore the current result) until 10 (\_STARPU\_CALIBRATION\_MINIMUM) measurements have been made on each architecture, to avoid badly scheduling tasks just because the first measurements were not so good. Details on the current performance model status can be obtained from the command starpu\_perfmodel\_display: the -1 option lists the available performance models, and the -s option permits to choose the performance model to be displayed. The result looks like:


```
$ starpu_perfmodel_display -s starpu_slu_lu_model_11
performance model for cpu_impl_0

# hash size flops mean dev n
914f3bef 1048576 0.000000e+00 2.503577e+04 1.982465e+02 8
3e921964 65536 0.000000e+00 5.527003e+02 1.848114e+01 7
e5a07e31 4096 0.000000e+00 1.717457e+01 5.190038e+00 14
...
```

Which shows that for the LU 11 kernel with a 1MiB matrix, the average execution time on CPUs was about 25ms, with a 0.2ms standard deviation, over 8 samples. It is a good idea to check this before doing actual performance measurements.

A graph can be drawn by using the tool  $starpu\_perfmodel\_plot$ :

```
$ starpu_perfmodel_plot -s starpu_slu_lu_model_11
4096 16384 65536 262144 1048576 4194304
$ gnuplot starpu_starpu_slu_lu_model_11.gp
$ gv starpu_starpu_slu_lu_model_11.eps
```



If a kernel source code was modified (e.g. performance improvement), the calibration information is stale and should be dropped, to re-calibrate from start. This can be done by using export STARPU\_CALIBRATE=2 (STARPU\_CALIBRATE).

Note: history-based performance models get calibrated only if a performance-model-based scheduler is chosen.

The history-based performance models can also be explicitly filled by the application without execution, if e.g. the application already has a series of measurements. This can be done by using <a href="mailto:starpu\_perfmodel\_update\_history">starpu\_perfmodel\_update\_history</a>(), for instance:

```
static struct starpu_perfmodel perf_model = {
    .type = STARPU_HISTORY_BASED,
    .symbol = "my_perfmodel",
struct starpu_codelet cl = {
    .cuda_funcs = { cuda_func1, cuda_func2 },
    .nbuffers = 1,
    .modes = {STARPU_W},
.model = &perf_model
};
void feed(void) {
    struct my_measure *measure;
    struct starpu_task task;
    starpu_task_init(&task);
    task.cl = &cl;
    for (measure = &measures[0]; measure < measures[last]; measure++) {</pre>
        starpu_data_handle_t handle;
        starpu_vector_data_register(&handle, -1, 0,
      measure->size, sizeof(float));
        task.handles[0] = handle;
        starpu_perfmodel_update_history(&
      perf_model, &task,
                                          STARPU_CUDA_DEFAULT + measure->cudadev,
       0.
                                          measure->implementation, measure->time)
        starpu_task_clean(&task);
        starpu_data_unregister(handle);
```

```
}
```

Measurement has to be provided in milliseconds for the completion time models, and in Joules for the energy consumption models.

## 5.11 Profiling

A quick view of how many tasks each worker has executed can be obtained by setting <code>export STARPU\_WO-RKER\_STATS=1</code> (STARPU\_WORKER\_STATS). This is a convenient way to check that execution did happen on accelerators, without penalizing performance with the profiling overhead.

A quick view of how much data transfers have been issued can be obtained by setting <code>export STARPU\_BUS\_-STATS=1</code> (STARPU\_BUS\_STATS).

More detailed profiling information can be enabled by using <code>export STARPU\_PROFILING=1</code> (STARPU\_PROFILING=0 (STARPU\_PROFILING) or by calling starpu\_profiling\_status\_set() from the source code. Statistics on the execution can then be obtained by using <code>export STARPU\_BUS\_STATS=1</code> and <code>export STARPU\_WORKER\_STATS=1</code>. More details on performance feedback are provided in the next chapter.

Part III

**StarPU Inside** 

## **Chapter 6**

## Tasks In StarPU

## 6.1 Task Granularity

Like any other runtime, StarPU has some overhead to manage tasks. Since it does smart scheduling and data management, that overhead is not always neglectable. The order of magnitude of the overhead is typically a couple of microseconds, which is actually quite smaller than the CUDA overhead itself. The amount of work that a task should do should thus be somewhat bigger, to make sure that the overhead becomes neglectible. The offline performance feedback can provide a measure of task length, which should thus be checked if bad performance are observed. To get a grasp at the scalability possibility according to task size, one can run tests/microbenchs/tasks-\_size\_overhead.sh which draws curves of the speedup of independent tasks of very small sizes.

The choice of scheduler also has impact over the overhead: for instance, the scheduler dmda takes time to make a decision, while eager does not. tasks\_size\_overhead.sh can again be used to get a grasp at how much impact that has on the target machine.

#### 6.2 Task Submission

To let StarPU make online optimizations, tasks should be submitted asynchronously as much as possible. Ideally, all the tasks should be submitted, and mere calls to <a href="starpu\_task\_wait\_for\_all(">starpu\_data\_unregister(</a>) be done to wait for termination. StarPU will then be able to rework the whole schedule, overlap computation with communication, manage accelerator local memory usage, etc.

#### 6.3 Task Priorities

By default, StarPU will consider the tasks in the order they are submitted by the application. If the application programmer knows that some tasks should be performed in priority (for instance because their output is needed by many other tasks and may thus be a bottleneck if not executed early enough), the field starpu\_task::priority should be set to transmit the priority information to StarPU.

## 6.4 Setting The Data Handles For A Task

The number of data a task can manage is fixed by the environment variable STARPU\_NMAXBUFS which has a default value which can be changed through the configure option --enable-maxbuffers.

However, it is possible to define tasks managing more data by using the field <a href="starpu\_task::dyn\_handles">starpu\_task::dyn\_handles</a> when defining a task and the field <a href="starpu\_codelet::dyn\_modes">starpu\_codelet::dyn\_modes</a> when defining the corresponding codelet.

40 Tasks In StarPU

```
STARPU_R, STARPU_R, ...
};
struct starpu_codelet dummy_big_cl =
        .cuda_funcs = { dummy_big_kernel },
        .opencl_funcs = { dummy_big_kernel },
        .cpu_funcs = { dummy_big_kernel },
        .cpu_funcs_name = { "dummy_big_kernel" },
        .nbuffers = STARPU_NMAXBUFS+1,
        .dyn_modes = modes
};
task = starpu_task_create();
task->cl = &dummy_big_cl;
task->dyn_handles = malloc(task->cl->nbuffers * sizeof(
      starpu_data_handle_t));
for(i=0 ; i<task->cl->nbuffers ; i++)
        task->dyn_handles[i] = handle;
starpu_task_submit(task);
starpu_data_handle_t *handles = malloc(dummy_big_cl.
      nbuffers * sizeof(starpu_data_handle_t));
for(i=0 ; i<dummy_big_cl.nbuffers ; i++)</pre>
        handles[i] = handle;
starpu_task_insert(&dummy_big_cl,
                STARPU_VALUE, &dummy_big_cl.nbuffers,
      sizeof(dummy_big_cl.nbuffers),
                STARPU_DATA_ARRAY, handles, dummy_big_cl.
      nbuffers,
                 0):
```

The whole code for this complex data interface is available in the directory examples/basic\_-examples/dynamic\_handles.c.

## 6.5 Using Multiple Implementations Of A Codelet

One may want to write multiple implementations of a codelet for a single type of device and let StarPU choose which one to run. As an example, we will show how to use SSE to scale a vector. The codelet can be written as follows:

```
#include <xmmintrin.h>
void scal_sse_func(void *buffers[], void *cl_arg)
    float *vector = (float *) STARPU_VECTOR_GET_PTR(
      buffers[0]);
    unsigned int n = STARPU_VECTOR_GET_NX(buffers[0]);
    unsigned int n_iterations = n/4;
    if (n % 4 != 0)
        n_iterations++;
     m128 * VECTOR = ( m128*) vector;
      _m128 factor __attribute__((aligned(16)));
    factor = _mm_set1_ps(*(float *) cl_arg);
    unsigned int i;
for (i = 0; i < n_iterations; i++)</pre>
        VECTOR[i] = _mm_mul_ps(factor, VECTOR[i]);
struct starpu_codelet cl = {
    .cpu_funcs = { scal_cpu_func, scal_sse_func },
.cpu_funcs_name = { "scal_cpu_func", "scal_sse_func" },
    .nbuffers = 1,
    .modes = { STARPU_RW }
```

Schedulers which are multi-implementation aware (only dmda and pheft for now) will use the performance models of all the implementations it was given, and pick the one that seems to be the fastest.

## 6.6 Enabling Implementation According To Capabilities

Some implementations may not run on some devices. For instance, some CUDA devices do not support double floating point precision, and thus the kernel execution would just fail; or the device may not have enough shared memory for the implementation being used. The field <a href="mailto:starpu\_codelet::can\_execute">starpu\_codelet::can\_execute</a> permits to express this. For instance:

```
static int can_execute(unsigned workerid, struct starpu_task
      *task, unsigned nimpl)
  const struct cudaDeviceProp *props;
  if (starpu_worker_get_type(workerid) ==
     STARPU_CPU_WORKER)
    return 1:
  /* Cuda device */
  props = starpu_cuda_get_device_properties(
      workerid);
  if (props->major >= 2 || props->minor >= 3)
    /* At least compute capability 1.3, supports doubles */
    return 1;
  /* Old card, does not support doubles */
struct starpu_codelet cl = {
    .can_execute = can_execute,
    .cpu_funcs = { cpu_func },
    .cpu_funcs_name = { "cpu_func" },
    .cuda_funcs = { gpu_func }
    .nbuffers = 1,
    .modes = { STARPU_RW }
}:
```

This can be essential e.g. when running on a machine which mixes various models of CUDA devices, to take benefit from the new models without crashing on old models.

Note: the function starpu\_codelet::can\_execute is called by the scheduler each time it tries to match a task with a worker, and should thus be very fast. The function starpu\_cuda\_get\_device\_properties() provides a quick access to CUDA properties of CUDA devices to achieve such efficiency.

Another example is to compile CUDA code for various compute capabilities, resulting with two CUDA functions, e.g. scal\_gpu\_13 for compute capability 1.3, and scal\_gpu\_20 for compute capability 2.0. Both functions can be provided to StarPU by using starpu\_codelet::cuda\_funcs, and starpu\_codelet::can\_execute can then be used to rule out the scal\_gpu\_20 variant on a CUDA device which will not be able to execute it:

```
static int can_execute(unsigned workerid, struct starpu_task
       *task, unsigned nimpl)
  const struct cudaDeviceProp *props;
  if (starpu_worker_get_type(workerid) ==
      STARPU_CPU_WORKER)
    return 1;
  /* Cuda device */
  if (nimpl == 0)
    /\star Trying to execute the 1.3 capability variant, we assume it is ok in all
      cases.
    return 1:
  /\star Trying to execute the 2.0 capability variant, check that the card can do
  props = starpu_cuda_get_device_properties(
      workerid);
  if (props->major >= 2 || props->minor >= 0)
    /\star At least compute capability 2.0, can run it \star/
    return 1;
  /\star Old card, does not support 2.0, will not be able to execute the 2.0
       variant. */
  return 0:
struct starpu_codelet cl = {
    .can_execute = can_execute,
    .cpu_funcs = { cpu_func },
    .cpu_funcs_name = { "cpu_func" },
    .cuda_funcs = { scal_gpu_13, scal_gpu_20 },
    .nbuffers = 1,
    .modes = { STARPU_RW }
};
```

42 Tasks In StarPU

Another example is having specialized implementations for some given common sizes, for instance here we have a specialized implementation for 1024x1024 matrices:

```
static int can_execute(unsigned workerid, struct starpu_task
        *task, unsigned nimpl)
  const struct cudaDeviceProp *props;
  if (starpu_worker_get_type(workerid) ==
      STARPU_CPU_WORKER)
    return 1;
  /* Cuda device */
  switch (nimpl)
    case 0:
     /* Trying to execute the generic capability variant. */
      return 1;
    case 1:
      /* Trying to execute the size == 1024 specific variant.   
*/struct starpu_matrix_interface *interface =
       starpu_data_get_interface_on_node(task->
      handles[0]);
       return STARPU_MATRIX_GET_NX(interface) == 1024 &&
      STARPU_MATRIX_GET_NY(interface == 1024);
 }
struct starpu_codelet cl = {
    .can_execute = can_execute,
.cpu_funcs = { cpu_func },
.cpu_funcs_name = { "cpu_func" },
    .cuda_funcs = { potrf_gpu_generic, potrf_gpu_1024 },
    .nbuffers = 1,
    .modes = { STARPU_RW }
};
```

Note: the most generic variant should be provided first, as some schedulers are not able to try the different variants.

## 6.7 Insert Task Utility

StarPU provides the wrapper function starpu\_task\_insert() to ease the creation and submission of tasks.

Here the implementation of the codelet:

```
void func_cpu(void *descr[], void *_args)
        int *x0 = (int *)STARPU_VARIABLE_GET_PTR(descr[0
      1);
        float *x1 = (float *)STARPU_VARIABLE_GET_PTR(
      descr[1]);
        int ifactor;
        float ffactor;
        starpu codelet unpack args ( args, &ifactor, &
      ffactor);
        *x0 = *x0 * ifactor;
*x1 = *x1 * ffactor;
struct starpu_codelet mycodelet = {
        .cpu_funcs = { func_cpu },
        .cpu_funcs_name = { "func_cpu" },
        .nbuffers = 2,
        .modes = { STARPU_RW, STARPU_RW }
};
```

And the call to the function starpu\_task\_insert():

The call to starpu\_task\_insert() is equivalent to the following code:

Here a similar call using STARPU\_DATA\_ARRAY.

If some part of the task insertion depends on the value of some computation, the macro STARPU\_DATA\_ACQUIRE\_CB can be very convenient. For instance, assuming that the index variable i was registered as handle  $A_{n}$  and I is I in the index variable I in the index variable I in the index variable I is I in the index variable I in the index variable I in the index variable I is I in the index variable I in t

The macro STARPU\_DATA\_ACQUIRE\_CB submits an asynchronous request for acquiring data i for the main application, and will execute the code given as third parameter when it is acquired. In other words, as soon as the value of i computed by the codelet which\_index can be read, the portion of code passed as third parameter of STARPU\_DATA\_ACQUIRE\_CB will be executed, and is allowed to read from i to use it e.g. as an index. Note that this macro is only avaible when compiling StarPU with the compiler gcc.

### 6.8 Getting Task Children

It may be interesting to get the list of tasks which depend on a given task, notably when using implicit dependencies, since this list is computed by StarPU. starpu\_task\_get\_task\_succs() provides it. For instance:

#### 6.9 Parallel Tasks

StarPU can leverage existing parallel computation libraries by the means of parallel tasks. A parallel task is a task which gets worked on by a set of CPUs (called a parallel or combined worker) at the same time, by using an existing parallel CPU implementation of the computation to be achieved. This can also be useful to improve the load balance between slow CPUs and fast GPUs: since CPUs work collectively on a single task, the completion time of tasks on CPUs become comparable to the completion time on GPUs, thus relieving from granularity discrepancy concerns. hwloc support needs to be enabled to get good performance, otherwise StarPU will not know how to better group cores.

Two modes of execution exist to accomodate with existing usages.

44 Tasks In StarPU

#### 6.9.1 Fork-mode Parallel Tasks

In the Fork mode, StarPU will call the codelet function on one of the CPUs of the combined worker. The codelet function can use <a href="starpu\_combined\_worker\_get\_size">starpu\_combined\_worker\_get\_size</a>() to get the number of threads it is allowed to start to achieve the computation. The CPU binding mask for the whole set of CPUs is already enforced, so that threads created by the function will inherit the mask, and thus execute where StarPU expected, the OS being in charge of choosing how to schedule threads on the corresponding CPUs. The application can also choose to bind threads by hand, using e.g. sched getaffinity to know the CPU binding mask that StarPU chose.

For instance, using OpenMP (full source is available in examples/openmp/vector\_scal.c):

```
void scal cpu func(void *buffers[], void * args)
    unsigned i;
    float *factor = _args;
    struct starpu_vector_interface *vector = buffers[0];
    unsigned n = STARPU_VECTOR_GET_NX(vector);
    float *val = (float *)STARPU_VECTOR_GET_PTR(vector);
#pragma omp parallel for num_threads(starpu_combined_worker_get_size())
       val[i] *= *factor;
static struct starpu_codelet cl =
    .modes = { STARPU_RW },
    .where = STARPU_CPU,
    .type = STARPU_FORKJOIN.
    .max_parallelism = INT MAX,
    .cpu funcs = {scal cpu func},
    .cpu_funcs_name = {"scal_cpu_func"},
    .nbuffers = 1,
};
```

Other examples include for instance calling a BLAS parallel CPU implementation (see examples/mult/xgemm.-c).

#### 6.9.2 SPMD-mode Parallel Tasks

In the SPMD mode, StarPU will call the codelet function on each CPU of the combined worker. The codelet function can use <a href="mailto:starpu\_combined\_worker\_get\_size">starpu\_combined\_worker\_get\_size</a>() to get the total number of CPUs involved in the combined worker, and thus the number of calls that are made in parallel to the function, and <a href="mailto:starpu\_combined\_worker\_get\_rank">starpu\_combined\_worker\_get\_rank</a>() to get the rank of the current CPU within the combined worker. For instance:

```
static void func(void *buffers[], void *args)
    unsigned i;
    float *factor = _args;
    struct starpu_vector_interface *vector = buffers[0];
    unsigned n = STARPU_VECTOR_GET_NX(vector);
    float *val = (float *)STARPU VECTOR GET PTR(vector);
    /* Compute slice to compute */
    unsigned m = starpu_combined_worker_get_size
    unsigned j = starpu_combined_worker_get_rank
    unsigned slice = (n+m-1)/m;
    for (i = j * slice; i < (j+1) * slice && i < n; i++)</pre>
        val[i] *= *factor;
static struct starpu_codelet cl =
    .modes = { STARPU_RW },
    .type = STARPU_SPMD,
    .max_parallelism = INT_MAX,
    .cpu_funcs = { func },
.cpu_funcs_name = { "func" },
    .nbuffers = 1,
```

6.9 Parallel Tasks 45

Of course, this trivial example will not really benefit from parallel task execution, and was only meant to be simple to understand. The benefit comes when the computation to be done is so that threads have to e.g. exchange intermediate results, or write to the data in a complex but safe way in the same buffer.

#### 6.9.3 Parallel Tasks Performance

To benefit from parallel tasks, a parallel-task-aware StarPU scheduler has to be used. When exposed to codelets with a flag STARPU\_FORKJOIN or STARPU\_SPMD, the schedulers pheft (parallel-heft) and peager (parallel eager) will indeed also try to execute tasks with several CPUs. It will automatically try the various available combined worker sizes (making several measurements for each worker size) and thus be able to avoid choosing a large combined worker if the codelet does not actually scale so much.

#### 6.9.4 Combined Workers

By default, StarPU creates combined workers according to the architecture structure as detected by hwloc. It means that for each object of the hwloc topology (NUMA node, socket, cache, ...) a combined worker will be created. If some nodes of the hierarchy have a big arity (e.g. many cores in a socket without a hierarchy of shared caches), StarPU will create combined workers of intermediate sizes. The variable STARPU\_SYNTHESIZE\_ARITY COMBINED WORKER permits to tune the maximum arity between levels of combined workers.

The combined workers actually produced can be seen in the output of the tool starpu\_machine\_display (the environment variable STARPU\_SCHED has to be set to a combined worker-aware scheduler such as pheft or peager).

#### 6.9.5 Concurrent Parallel Tasks

Unfortunately, many environments and librairies do not support concurrent calls.

For instance, most OpenMP implementations (including the main ones) do not support concurrent pragma omp parallel statements without nesting them in another pragma omp parallel statement, but StarPU does not yet support creating its CPU workers by using such pragma.

Other parallel libraries are also not safe when being invoked concurrently from different threads, due to the use of global variables in their sequential sections for instance.

The solution is then to use only one combined worker at a time. This can be done by setting the field starpu\_conf::single\_combined\_worker to 1, or setting the environment variable STARPU\_SINGLE\_COMBINED\_WORKER to 1. StarPU will then run only one parallel task at a time (but other CPU and GPU tasks are not affected and can be run concurrently). The parallel task scheduler will however still however still try varying combined worker sizes to look for the most efficient ones.

#### 6.9.6 Synchronization tasks

For the application conveniency, it may be useful to define tasks which do not actually make any computation, but wear for instance dependencies between other tasks or tags, or to be submitted in callbacks, etc.

The obvious way is of course to make kernel functions empty, but such task will thus have to wait for a worker to become ready, transfer data, etc.

A much lighter way to define a synchronization task is to set its cl field to NULL. The task will thus be a mere synchronization point, without any data access or execution content: as soon as its dependencies become available, it will terminate, call the callbacks, and release dependencies.

An intermediate solution is to define a codelet with its where field set to STARPU\_NOWHERE, for instance this:

```
struct starpu_codelet {
    .where = STARPU_NOWHERE,
    .nbuffers = 1,
    .modes = { STARPU_R },
}
```

46 Tasks In StarPU

```
task = starpu_task_create();
task->cl = starpu_codelet;
task->handles[0] = handle;
starpu_task_submit(task);
```

will create a task which simply waits for the value of handle to be available for read. This task can then be depended on, etc.

## **Chapter 7**

# **Data Management**

intro qui parle de coherency entre autres

### 7.1 Data Management

When the application allocates data, whenever possible it should use the <a href="starpu\_malloc">starpu\_malloc</a>() function, which will ask CUDA or OpenCL to make the allocation itself and pin the corresponding allocated memory, or to use the <a href="starpu\_memory\_pin">starpu\_memory\_pin</a>() function to pin memory allocated by other ways, such as local arrays. This is needed to permit asynchronous data transfer, i.e. permit data transfer to overlap with computations. Otherwise, the trace will show that the <a href="mailto:DriverCopyAsync">DriverCopyAsync</a> state takes a lot of time, this is because CUDA or OpenCL then reverts to synchronous transfers.

By default, StarPU leaves replicates of data wherever they were used, in case they will be re-used by other tasks, thus saving the data transfer time. When some task modifies some data, all the other replicates are invalidated, and only the processing unit which ran that task will have a valid replicate of the data. If the application knows that this data will not be re-used by further tasks, it should advise StarPU to immediately replicate it to a desired list of memory nodes (given through a bitmask). This can be understood like the write-through mode of CPU caches.

```
starpu_data_set_wt_mask(img_handle, 1<<0);</pre>
```

will for instance request to always automatically transfer a replicate into the main memory (node 0), as bit 0 of the write-through bitmask is being set.

```
starpu_data_set_wt_mask(img_handle, ~0U);
```

will request to always automatically broadcast the updated data to all memory nodes.

Setting the write-through mask to  $\sim$ 0U can also be useful to make sure all memory nodes always have a copy of the data, so that it is never evicted when memory gets scarse.

Implicit data dependency computation can become expensive if a lot of tasks access the same piece of data. If no dependency is required on some piece of data (e.g. because it is only accessed in read-only mode, or because write accesses are actually commutative), use the function starpu\_data\_set\_sequential\_consistency\_flag() to disable implicit dependencies on that data.

In the same vein, accumulation of results in the same data can become a bottleneck. The use of the mode STA-RPU\_REDUX permits to optimize such accumulation (see Data Reduction). To a lesser extent, the use of the flag STARPU\_COMMUTE keeps the bottleneck (see Commute Data Access), but at least permits the accumulation to happen in any order.

Applications often need a data just for temporary results. In such a case, registration can be made without an initial value, for instance this produces a vector data:

48 Data Management

StarPU will then allocate the actual buffer only when it is actually needed, e.g. directly on the GPU without allocating in main memory.

In the same vein, once the temporary results are not useful any more, the data should be thrown away. If the handle is not to be reused, it can be unregistered:

```
starpu_data_unregister_submit(handle);
```

actual unregistration will be done after all tasks working on the handle terminate.

If the handle is to be reused, instead of unregistering it, it can simply be invalidated:

```
starpu_data_invalidate_submit(handle);
```

the buffers containing the current value will then be freed, and reallocated only when another task writes some value to the handle.

### 7.2 Data Prefetch

The scheduling policies heft, dmda and pheft perform data prefetch (see STARPU\_PREFETCH): as soon as a scheduling decision is taken for a task, requests are issued to transfer its required data to the target processing unit, if needed, so that when the processing unit actually starts the task, its data will hopefully be already available and it will not have to wait for the transfer to finish.

The application may want to perform some manual prefetching, for several reasons such as excluding initial data transfers from performance measurements, or setting up an initial statically-computed data distribution on the machine before submitting tasks, which will thus guide StarPU toward an initial task distribution (since StarPU will try to avoid further transfers).

This can be achieved by giving the function starpu\_data\_prefetch\_on\_node() the handle and the desired target memory node. The starpu\_data\_idle\_prefetch\_on\_node() variant can be used to issue the transfer only when the bus is idle.

Conversely, one can advise StarPU that some data will not be useful in the close future by calling starpu\_data\_wont\_use. StarPU will then write its value back to its home node, and evict it from GPUs when room is needed.

## 7.3 Partitioning Data

An existing piece of data can be partitioned in sub parts to be used by different tasks, for instance:

The task submission then uses the function starpu\_data\_get\_sub\_data() to retrieve the sub-handles to be passed as tasks parameters.

```
/* Get subdata number i (there is only 1 dimension) */
starpu_data_handle_t sub_handle =
    starpu_data_get_sub_data(handle, 1, i);
struct starpu_task *task = starpu_task_create(
    );

task->handles[0] = sub_handle;
task->cl = &cl;
task->synchronous = 1;
task->cl_arg = &factor;
task->cl_arg_size = sizeof(factor);

starpu_task_submit(task);
}
```

Partitioning can be applied several times, see examples/basic\_examples/mult.c and examples/filters/.

Wherever the whole piece of data is already available, the partitioning will be done in-place, i.e. without allocating new buffers but just using pointers inside the existing copy. This is particularly important to be aware of when using OpenCL, where the kernel parameters are not pointers, but handles. The kernel thus needs to be also passed the offset within the OpenCL buffer:

```
void opencl_func(void *buffers[], void *cl_arg)
{
    cl_mem vector = (cl_mem) STARPU_VECTOR_GET_DEV_HANDLE
        (buffers[0]);
    unsigned offset = STARPU_BLOCK_GET_OFFSET(buffers[0]);
    ...
    clSetKernelArg(kernel, 0, sizeof(vector), &vector);
    clSetKernelArg(kernel, 1, sizeof(offset), &offset);
    ...
}
```

And the kernel has to shift from the pointer passed by the OpenCL driver:

```
__kernel void opencl_kernel(__global int *vector, unsigned offset)
{
    block = (__global void *)block + offset;
    ...
```

StarPU provides various interfaces and filters for matrices, vectors, etc., but applications can also write their own data interfaces and filters, see <code>examples/interface</code> and <code>examples/filters/custom\_mf</code> for an example.

## 7.4 Asynchronous Partitioning

The partitioning functions described in the previous section are synchronous: starpu\_data\_partition and starpu\_data unpartition both wait for all the tasks currently working on the data. This can be a bottleneck for the application.

An asynchronous API also exists, it works only on handles with sequential consistency. The principle is to first plan the partitioning, which returns data handles of the partition, which are not functional yet. Along other task submission, one can submit the actual partitioning, and then use the handles of the partition. Before using the handle of the whole data, one has to submit the unpartitioning. fmultiple\_submit is a complete example using this technique.

In short, we first register a matrix and plan the partitioning:

50 Data Management

starpu\_data\_partition\_plan returns the handles for the partition in vert\_handle.

One can submit tasks working on the main handle, but not yet on the vert\_handle handles. Now we submit the partitioning:

And now we can submit tasks working on vert\_handle handles (and not on the main handle any more). Eventually we want to work on the main handle again, so we submit the unpartitioning:

```
starpu_data_unpartition_submit(handle, PARTS, vert_handle, -1);
```

And now we can submit tasks working on the main handle again.

All this code is asynchronous, just submitting which tasks, partitioning and unpartitioning should be done at runtime.

Planning several partitioning of the same data is also possible, one just has to submit unpartitioning (to get back to the initial handle) before submitting another partitioning.

It is also possible to activate several partitioning at the same time, in read-only mode, by using starpu\_data\_-partition\_readonly\_submit. A complete example is available in examples/filters/fmultiple\_submit\_readonly.c.

## 7.5 Manual Partitioning

One can also handle partitioning by hand, by registering several views on the same piece of data. The idea is then to manage the coherency of the various views through the common buffer in the main memory. fmultiple\_-manual is a complete example using this technique.

In short, we first register the same matrix several times:

Since StarPU is not aware that the two handles are actually pointing to the same data, we have a danger of inadvertently submitting tasks to both views, which will bring a mess since StarPU will not guarantee any coherency between the two views. To make sure we don't do this, we invalidate the view that we will not use:

```
for (i = 0; i < PARTS; i++)
    starpu_data_invalidate(vert_handle[i]);</pre>
```

Then we can safely work on handle.

When we want to switch to the vertical slice view, all we need to do is bring coherency between them by running an empty task on the home node of the data:

7.6 Data Reduction 51

The execution of the switch task will get back the matrix data into the main memory, and thus the vertical slices will get the updated value there.

Again, we prefer to make sure that we don't accidentally access the matrix through the whole-matrix handle:

```
starpu_data_invalidate_submit(handle);
```

And now we can start using vertical slices, etc.

#### 7.6 Data Reduction

In various cases, some piece of data is used to accumulate intermediate results. For instances, the dot product of a vector, maximum/minimum finding, the histogram of a photograph, etc. When these results are produced along the whole machine, it would not be efficient to accumulate them in only one place, incurring data transmission each and access concurrency.

StarPU provides a mode STARPU\_REDUX, which permits to optimize that case: it will allocate a buffer on each memory node, and accumulate intermediate results there. When the data is eventually accessed in the normal mode STARPU\_R, StarPU will collect the intermediate results in just one buffer.

For this to work, the user has to use the function <a href="mailto:starpu\_data\_set\_reduction\_methods">starpu\_data\_set\_reduction\_methods</a>() to declare how to initialize these buffers, and how to assemble partial results.

For instance, cg uses that to optimize its dot product: it first defines the codelets for initialization and reduction:

```
struct starpu_codelet bzero_variable_cl =
        .cpu_funcs = { bzero_variable_cpu },
        .cpu_funcs_name = { "bzero_variable_cpu" },
        .cuda_funcs = { bzero_variable_cuda },
        .nbuffers = 1.
}
static void accumulate_variable_cpu(void *descr[], void *cl_arg)
        double *v_dst = (double *)STARPU_VARIABLE_GET_PTR
      (descr[0]);
        double *v_src = (double *)STARPU_VARIABLE_GET_PTR
      (descr[1]);
        *v_dst = *v_dst + *v_src;
static void accumulate_variable_cuda(void *descr[], void *cl_arg)
        double *v dst = (double *) STARPU VARIABLE GET PTR
      (descr[0]);
        double *v_src = (double *)STARPU_VARIABLE_GET_PTR
        cublasaxpy(1, (double)1.0, v_src, 1, v_dst, 1);
        cudaStreamSynchronize(starpu_cuda_get_local_stream
      ());
}
struct starpu_codelet accumulate_variable_cl =
        .cpu_funcs = { accumulate_variable_cpu },
.cpu_funcs_name = { "accumulate_variable_cpu" },
        .cuda_funcs = { accumulate_variable_cuda },
        .nbuffers = 1,
```

and attaches them as reduction methods for its handle dtq:

```
starpu_variable_data_register(&dtq_handle, -1,
    NULL, sizeof(type));
starpu_data_set_reduction_methods(dtq_handle,
    &accumulate_variable_cl, &bzero_variable_cl);
```

and dtq\_handle can now be used in mode STARPU\_REDUX for the dot products with partitioned vectors:

```
for (b = 0; b < nblocks; b++)
```

52 Data Management

```
starpu_task_insert(&dot_kernel_cl,
    STARPU_REDUX, dtq_handle,
    STARPU_R, starpu_data_get_sub_data(v1,
1, b),
    STARPU_R, starpu_data_get_sub_data(v2,
1, b),
    ():
```

During registration, we have here provided NULL, i.e. there is no initial value to be taken into account during reduction. StarPU will thus only take into account the contributions from the tasks  $dot_kernel_cl$ . Also, it will not allocate any memory for  $dtq_handle$  before tasks  $dot_kernel_cl$  are ready to run.

If another dot product has to be performed, one could unregister  $dtq\_handle$ , and re-register it. But one can also call starpu\_data\_invalidate\_submit() with the parameter  $dtq\_handle$ , which will clear all data from the handle, thus resetting it back to the initial status register (NULL).

The example cg also uses reduction for the blocked gemv kernel, leading to yet more relaxed dependencies and more parallelism.

STARPU\_REDUX can also be passed to starpu\_mpi\_task\_insert() in the MPI case. That will however not produce any MPI communication, but just pass STARPU\_REDUX to the underlying starpu\_task\_insert(). It is up to the application to call starpu\_mpi\_redux\_data(), which posts tasks that will reduce the partial results among MPI nodes into the MPI node which owns the data. For instance, some hypothetical application which collects partial results into data res, then uses it for other computation, before looping again with a new reduction:

#### 7.7 Commute Data Access

By default, the implicit dependencies computed from data access use the sequential semantic. Notably, write accesses are always serialized in the order of submission. In some applicative cases, the write contributions can actually be performed in any order without affecting the eventual result. In that case it is useful to drop the strictly sequential semantic, to improve parallelism by allowing StarPU to reorder the write accesses. This can be done by using the STARPU\_COMMUTE data access flag. Accesses without this flag will however properly be serialized against accesses with this flag. For instance:

```
starpu_task_insert(&cl1,
    STARPU_R, h,
    STARPU_RW, handle,
    O);
starpu_task_insert(&cl2,
    STARPU_R, handle1,
    STARPU_RW|STARPU_COMMUTE, handle,
    O);
starpu_task_insert(&cl2,
    STARPU_RW|STARPU_COMMUTE, handle,
    O);
starpu_task_insert(&cl3,
    STARPU_RW, starpu_task_insert(&cl3,
    STARPU_R, g,
    STARPU_RW, handle,
    O);
```

The two tasks running cl2 will be able to commute: depending on whether the value of handle1 or handle2 becomes available first, the corresponding task running cl2 will start first. The task running cl1 will however always be run before them, and the task running cl3 will always be run after them.

If a lot of tasks use the commute access on the same set of data and a lot of them are ready at the same time, it may become interesting to use an arbiter, see Concurrent Data accesses .

#### 7.8 Concurrent Data accesses

When several tasks are ready and will work on several data, StarPU is faced with the classical Dining Philosophers problem, and has to determine the order in which it will run the tasks.

Data accesses usually use sequential ordering, so data accesses are usually already serialized, and thus by default StarPU uses the Dijkstra solution which scales very well in terms of overhead: tasks will just acquire data one by one by data handle pointer value order.

When sequential ordering is disabled or the STARPU\_COMMUTE flag is used, there may be a lot of concurrent accesses to the same data, and the Dijkstra solution gets only poor parallelism, typically in some pathological cases which do happen in various applications. In that case, one can use a data access arbiter, which implements the classical centralized solution for the Dining Philosophers problem. This is more expensive in terms of overhead since it is centralized, but it opportunistically gets a lot of parallelism. The centralization can also be avoided by using several arbiters, thus separating sets of data for which arbitration will be done. If a task accesses data from different arbiters, it will acquire them arbiter by arbiter, in arbiter pointer value order.

See the tests/datawizard/test\_arbiter.cpp example.

Arbiters however do not support the STARPU\_REDUX flag yet.

### 7.9 Temporary Buffers

There are two kinds of temporary buffers: temporary data which just pass results from a task to another, and scratch data which are needed only internally by tasks.

#### 7.9.1 Temporary Data

Data can sometimes be entirely produced by a task, and entirely consumed by another task, without the need for other parts of the application to access it. In such case, registration can be done without prior allocation, by using the special memory node number -1, and passing a zero pointer. StarPU will actually allocate memory only when the task creating the content gets scheduled, and destroy it on unregistration.

In addition to that, it can be tedious for the application to have to unregister the data, since it will not use its content anyway. The unregistration can be done lazily by using the function <a href="mailto:starpu\_data\_unregister\_submit(">starpu\_data\_unregister\_submit()</a>, which will record that no more tasks accessing the handle will be submitted, so that it can be freed as soon as the last task accessing it is over.

The following code examplifies both points: it registers the temporary data, submits three tasks accessing it, and records the data for automatic unregistration.

The application may also want to see the temporary data initialized on the fly before being used by the task. This can be done by using <a href="mailto:starpu\_data\_set\_reduction\_methods">starpu\_data\_set\_reduction\_methods</a>() to set an initialization codelet (no redux codelet is needed).

#### 7.9.2 Scratch Data

Some kernels sometimes need temporary data to achieve the computations, i.e. a workspace. The application could allocate it at the start of the codelet function, and free it at the end, but that would be costly. It could also allocate one buffer per worker (similarly to How To Initialize A Computation Library Once For Each Worker?), but that would make them systematic and permanent. A more optimized way is to use the data access mode STARPU\_SCRATCH, as examplified below, which provides per-worker buffers without content consistency.

54 Data Management

StarPU will make sure that the buffer is allocated before executing the task, and make this allocation per-worker: for CPU workers, notably, each worker has its own buffer. This means that each task submitted above will actually have its own workspace, which will actually be the same for all tasks running one after the other on the same worker. Also, if for instance GPU memory becomes scarce, StarPU will notice that it can free such buffers easily, since the content does not matter.

The example examples/pi uses scratches for some temporary buffer.

#### 7.10 The Multiformat Interface

It may be interesting to represent the same piece of data using two different data structures: one that would only be used on CPUs, and one that would only be used on GPUs. This can be done by using the multiformat interface. StarPU will be able to convert data from one data structure to the other when needed. Note that the scheduler dmda is the only one optimized for this interface. The user must provide StarPU with conversion codelets:

```
#define NX 1024
struct point array_of_structs[NX];
starpu_data_handle_t handle;
\star The conversion of a piece of data is itself a task, though it is created,
\star submitted and destroyed by StarPU internals and not by the user. Therefore,
 * we have to define two codelets.
 * Note that for now the conversion from the CPU format to the GPU format has
 \star be executed on the GPU, and the conversion from the GPU to the CPU has to be
 * executed on the CPU.
#ifdef STARPU USE OPENCL
void cpu_to_opencl_opencl_func(void *buffers[], void *args);
struct starpu_codelet cpu_to_opencl_cl = {
    .where = STARPU_OPENCL,
    .opencl_funcs = { cpu_to_opencl_opencl_func },
    .nbuffers = 1.
    .modes = { STARPU_RW }
};
void opencl_to_cpu_func(void *buffers[], void *args);
struct starpu_codelet opencl_to_cpu_cl = {
    .where = STARPU CPU.
    .cpu_funcs = { opencl_to_cpu_func },
    .cpu_funcs_name = { "opencl_to_cpu_func" },
    .nbuffers = 1,
    .modes = { STARPU_RW }
#endif
struct starpu multiformat data interface ops
       format_ops = {
#ifdef STARPU_USE_OPENCL
    .opencl_elemsize = 2 * sizeof(float),
    .cpu_to_opencl_cl = &cpu_to_opencl_cl,
.opencl_to_cpu_cl = &opencl_to_cpu_cl,
#endif
    .cpu elemsize = 2 * sizeof(float),
starpu_multiformat_data_register(handle,
      STARPU MAIN RAM, &array of structs, NX, &format ops);
```

Kernels can be written almost as for any other interface. Note that STARPU\_MULTIFORMAT\_GET\_CPU\_PTR shall only be used for CPU kernels. CUDA kernels must use STARPU\_MULTIFORMAT\_GET\_CUDA\_PTR, and OpenCL kernels must use STARPU\_MULTIFORMAT\_GET\_OPENCL\_PTR. STARPU\_MULTIFORMAT\_GET\_NX may be used in any kind of kernel.

static void

```
multiformat_scal_cpu_func(void *buffers[], void *args)
{
    struct point *aos;
    unsigned int n;

    aos = STARPU_MULTIFORMAT_GET_CPU_PTR(buffers[
        0]);
    n = STARPU_MULTIFORMAT_GET_NX(buffers[0]);
    ...
}

extern "C" void multiformat_scal_cuda_func(void *buffers[], void *_args)
{
    unsigned int n;
    struct struct_of_arrays *soa;

    soa = (struct struct_of_arrays *) STARPU_MULTIFORMAT_GET_CUDA_PTR
        (buffers[0]);
    n = STARPU_MULTIFORMAT_GET_NX(buffers[0]);
    ...
}
```

A full example may be found in examples/basic\_examples/multiformat.c.

## 7.11 Defining A New Data Interface

Let's define a new data interface to manage complex numbers.

```
/* interface for complex numbers */
struct starpu_complex_interface
{
          double *real;
          double *imaginary;
          int nx;
};
```

Registering such a data to StarPU is easily done using the function starpu\_data\_register(). The last parameter of the function, interface\_complex\_ops, will be described below.

Different operations need to be defined for a data interface through the type starpu\_data\_interface\_ops. We only define here the basic operations needed to run simple applications. The source code for the different functions can be found in the file examples/interface/complex\_interface.c.

```
static struct starpu_data_interface_ops
    interface_complex_ops =
{
          .register_data_handle =
          complex_register_data_handle,
          .allocate_data_on_node = complex_allocate_data_on_node,
          .copy_methods = &complex_copy_methods,
          .get_size = complex_get_size,
```

56 Data Management

```
.footprint = complex_footprint,
.interfaceid = STARPU_UNKNOWN_INTERFACE_ID,
.interface_size = sizeof(struct starpu_complex_interface),
};
```

Functions need to be defined to access the different fields of the complex interface from a StarPU data handle.

Similar functions need to be defined to access the different fields of the complex interface from a void \* pointer to be used within codelet implementations.

Complex data interfaces can then be registered to StarPU.

and used by codelets.

The whole code for this complex data interface is available in the directory examples/interface/.

## 7.12 Specifying a target node for task data

When executing a task on a GPU for instance, StarPU would normally copy all the needed data for the tasks on the embedded memory of the GPU. It may however happen that the task kernel would rather have some of the datas kept in the main memory instead of copied in the GPU, a pivoting vector for instance. This can be achieved by setting the <a href="starpu\_codelet::specific\_nodes">starpu\_codelet::specific\_nodes</a> flag to 1, and then fill the <a href="starpu\_codelet::nodes">starpu\_codelet::nodes</a> array (or <a href="starpu\_codelet::nodes">starpu\_codelet::nodes</a> array (or <a href="starpu\_nodes">starpu\_codelet::nodes</a> array (or <a href="starpu\_nodes">starpu\_codelet::nodes</a> array (or <a href="starpu\_nodes">starpu\_nodes</a> when <a href="starpu\_nodes">starpu\_codelet::nodes</a> array (or <a href="starpu\_nodes">starpu\_nodes</a> when <a href="starpu\_nodes">sta

```
struct starpu_codelet cl =
{
    .cuda_funcs = { kernel },
    .nbuffers = 2,
    .modes = {STARPU_RW, STARPU_RW},
    .specific_nodes = 1,
    .nodes = {STARPU_MAIN_RAM, -1},
};
```

the first data of the task will be kept in the main memory, while the second data will be copied to the CUDA GPU as usual.

58 **Data Management** 

## **Chapter 8**

# **Scheduling**

## 8.1 Task Scheduling Policy

The basics of the scheduling policy are that

- The scheduler gets to schedule tasks (push operation) when they become ready to be executed, i.e. they are not waiting for some tags, data dependencies or task dependencies.
- Workers pull tasks (pop operation) one by one from the scheduler.

This means scheduling policies usually contain at least one queue of tasks to store them between the time when they become available, and the time when a worker gets to grab them.

By default, StarPU uses the simple greedy scheduler <code>eager</code>. This is because it provides correct load balance even if the application codelets do not have performance models. If your application codelets have performance models (Performance Model Example), you should change the scheduler thanks to the environment variable STARPU\_SCHED. For instance <code>export STARPU\_SCHED=dmda</code>. Use <code>help</code> to get the list of available schedulers.

The **eager** scheduler uses a central task queue, from which all workers draw tasks to work on concurrently. This however does not permit to prefetch data since the scheduling decision is taken late. If a task has a non-0 priority, it is put at the front of the queue.

The prio scheduler also uses a central task queue, but sorts tasks by priority (between -5 and 5).

The **random** scheduler uses a queue per worker, and distributes tasks randomly according to assumed worker overall performance.

The **ws** (work stealing) scheduler uses a queue per worker, and schedules a task on the worker which released it by default. When a worker becomes idle, it steals a task from the most loaded worker.

The **lws** (locality work stealing) scheduler uses a queue per worker, and schedules a task on the worker which released it by default. When a worker becomes idle, it steals a task from neighbour workers. It also takes into account priorities.

The **dm** (deque model) scheduler uses task execution performance models into account to perform a HEFT-similar scheduling strategy: it schedules tasks where their termination time will be minimal. The difference with HEFT is that **dm** schedules tasks as soon as they become available, and thus in the order they become available, without taking priorities into account.

The dmda (deque model data aware) scheduler is similar to dm, but it also takes into account data transfer time.

The **dmdar** (deque model data aware ready) scheduler is similar to dmda, but it also sorts tasks on per-worker queues by number of already-available data buffers on the target device.

The **dmdas** (deque model data aware sorted) scheduler is similar to dmdar, except that it sorts tasks by priority order, which allows to become even closer to HEFT by respecting priorities after having made the scheduling decision (but it still schedules tasks in the order they become available).

60 Scheduling

The heft (heterogeneous earliest finish time) scheduler is a deprecated alias for dmda.

The **pheft** (parallel HEFT) scheduler is similar to dmda, it also supports parallel tasks (still experimental). Should not be used when several contexts using it are being executed simultaneously.

The **peager** (parallel eager) scheduler is similar to eager, it also supports parallel tasks (still experimental). Should not be used when several contexts using it are being executed simultaneously.

TODO: describe modular schedulers

#### 8.2 Task Distribution Vs Data Transfer

Distributing tasks to balance the load induces data transfer penalty. StarPU thus needs to find a balance between both. The target function that the scheduler dmda of StarPU tries to minimize is alpha \* T\_execution + beta \* T\_data\_transfer, where T\_execution is the estimated execution time of the codelet (usually accurate), and T\_data\_transfer is the estimated data transfer time. The latter is estimated based on bus calibration before execution start, i.e. with an idle machine, thus without contention. You can force bus re-calibration by running the tool starpu\_calibrate\_bus. The beta parameter defaults to 1, but it can be worth trying to tweak it by using export STARPU\_SCHED\_BETA=2 for instance, since during real application execution, contention makes transfer times bigger. This is of course imprecise, but in practice, a rough estimation already gives the good results that a precise estimation would give.

## 8.3 Power-based Scheduling

If the application can provide some power performance model (through the field starpu\_codelet::power\_model), StarPU will take it into account when distributing tasks. The target function that the scheduler  $\tt dmda$  minimizes becomes  $\tt alpha * T_execution + beta * T_data_transfer + gamma * Consumption, where Consumption is the estimated task consumption in Joules. To tune this parameter, use <code>export STARPU_S-CHED_GAMMA=3000</code> for instance, to express that each Joule (i.e kW during 1000us) is worth 3000us execution time penalty. Setting <code>alpha</code> and <code>beta</code> to zero permits to only take into account power consumption.$ 

This is however not sufficient to correctly optimize power: the scheduler would simply tend to run all computations on the most energy-conservative processing unit. To account for the consumption of the whole machine (including idle processing units), the idle power of the machine should be given by setting  $export STARPU\_IDLE\_POW-ER=200$  for 200W, for instance. This value can often be obtained from the machine power supplier.

The power actually consumed by the total execution can be displayed by setting export STARPU\_PROFILING=1 STARPU\_WORKER\_STATS=1.

On-line task consumption measurement is currently only supported through the CL\_PROFILING\_POWER\_CONSUMED OpenCL extension, implemented in the MoviSim simulator. Applications can however provide explicit measurements by using the function starpu\_perfmodel\_update\_history() (examplified in Performance Model Example with the power\_model performance model). Fine-grain measurement is often not feasible with the feedback provided by the hardware, so the user can for instance run a given task a thousand times, measure the global consumption for that series of tasks, divide it by a thousand, repeat for varying kinds of tasks and task sizes, and eventually feed StarPU with these manual measurements through starpu\_perfmodel\_update\_history(). For instance, for CUDA devices, nvidia-smi-q-d POWER can be used to get the current consumption in Watt. Multiplying that value by the average duration of a single task gives the consumption of the task in Joules, which can be given to starpu\_perfmodel\_update\_history().

## 8.4 Static Scheduling

In some cases, one may want to force some scheduling, for instance force a given set of tasks to GPU0, another set to GPU1, etc. while letting some other tasks be scheduled on any other device. This can indeed be useful to guide StarPU into some work distribution, while still letting some degree of dynamism. For instance, to force execution of a task on CUDA0:

One can also specify the order in which tasks must be executed by setting the <a href="starpu\_task::workerorder">starpu\_task::workerorder</a> field. If this field is set to a non-zero value, it provides the per-worker consecutive order in which tasks will be executed, starting from 1. For a given of such task, the worker will thus not execute it before all the tasks with smaller order value have been executed, notably in case those tasks are not available yet due to some dependencies. This eventually gives total control of task scheduling, and StarPU will only serve as a "self-timed" task runtime. Of course, the provided order has to be runnable, i.e. a task should should not depend on another task bound to the same worker with a bigger order.

Note however that using scheduling contexts while statically scheduling tasks on workers could be tricky. Be careful to schedule the tasks exactly on the workers of the corresponding contexts, otherwise the workers' corresponding scheduling structures may not be allocated or the execution of the application may deadlock. Moreover, the hypervisor should not be used when statically scheduling tasks.

## 8.5 Defining A New Scheduling Policy

A full example showing how to define a new scheduling policy is available in the StarPU sources in the directory examples/scheduler/.

#### See Scheduling Policy

```
static struct starpu_sched_policy dummy_sched_policy = {
    .init_sched = init_dummy_sched,
    .deinit_sched = deinit_dummy_sched,
    .add_workers = dummy_sched_add_workers,
    .remove_workers = dummy_sched_remove_workers,
    .push_task = push_task_dummy,
    .push_prio_task = NULL,
    .pop_task = pop_task_dummy,
    .post_exec_hook = NULL,
    .pop_every_task = NULL,
    .policy_name = "dummy",
    .policy_description = "dummy scheduling strategy"
};
```

62 Scheduling

# **Chapter 9**

# **Scheduling Contexts**

TODO: improve!

#### 9.1 General Ideas

Scheduling contexts represent abstracts sets of workers that allow the programmers to control the distribution of computational resources (i.e. CPUs and GPUs) to concurrent parallel kernels. The main goal is to minimize interferences between the execution of multiple parallel kernels, by partitioning the underlying pool of workers using contexts.

## 9.2 Creating A Context

By default, the application submits tasks to an initial context, which disposes of all the computation resources available to StarPU (all the workers). If the application programmer plans to launch several parallel kernels simultaneously, by default these kernels will be executed within this initial context, using a single scheduler policy(see Task Scheduling Policy). Meanwhile, if the application programmer is aware of the demands of these kernels and of the specificity of the machine used to execute them, the workers can be divided between several contexts. These scheduling contexts will isolate the execution of each kernel and they will permit the use of a scheduling policy proper to each one of them.

Scheduling Contexts may be created in two ways: either the programmers indicates the set of workers corresponding to each context (providing he knows the identifiers of the workers running within StarPU), or the programmer does not provide any worker list and leaves the Hypervisor assign workers to each context according to their needs (Scheduling Context Hypervisor)

Both cases require a call to the function <code>starpu\_sched\_ctx\_create</code>, which requires as input the worker list (the exact list or a NULL pointer) and the scheduling policy. The latter one can be a character list corresponding to the name of a StarPU predefined policy or the pointer to a custom policy. The function returns an identifier of the context created which you will use to indicate the context you want to submit the tasks to.

64 Scheduling Contexts

Note: Parallel greedy and parallel heft scheduling policies do not support the existence of several disjoint contexts on the machine. Combined workers are constructed depending on the entire topology of the machine, not only the one belonging to a context.

## 9.3 Modifying A Context

A scheduling context can be modified dynamically. The applications may change its requirements during the execution and the programmer can add additional workers to a context or remove if no longer needed. In the following example we have two scheduling contexts sched\_ctx1 and sched\_ctx2. After executing a part of the tasks some of the workers of sched\_ctx1 will be moved to context sched\_ctx2.

## 9.4 Submitting Tasks To A Context

The application may submit tasks to several contexts either simultaneously or sequnetially. If several threads of submission are used the function <code>starpu\_sched\_ctx\_set\_context</code> may be called just before <code>starpu\_task\_submit</code>. Thus StarPU considers that the current thread will submit tasks to the coresponding context.

When the application may not assign a thread of submission to each context, the id of the context must be indicated by using the function starpu\_task\_submit\_to\_ctx or the field STARPU\_SCHED\_CTX for starpu\_task\_insert().

## 9.5 Deleting A Context

When a context is no longer needed it must be deleted. The application can indicate which context should keep the resources of a deleted one. All the tasks of the context should be executed before doing this. Thus, the programmer may use either a barrier and then delete the context directly, or just indicate that other tasks will not be submitted later on to the context (such that when the last task is executed its workers will be moved to the inheritor) and delete the context at the end of the execution (when a barrier will be used eventually).

## 9.6 Emptying A Context

A context may have no resources at the begining or at a certain moment of the execution. Task can still be submitted to these contexts and they will be executed as soon as the contexts will have resources. A list of tasks pending to be executed is kept and when workers are added to the contexts these tasks start being submitted. However, if resources are never allocated to the context the program will not terminate. If these tasks have low priority the programmer can forbid the application to submit them by calling the function  $starpu\_sched\_ctx\_stop\_-task\_submission()$ .

## 9.7 Contexts Sharing Workers

Contexts may share workers when a single context cannot execute efficiently enough alone on these workers or when the application decides to express a hierarchy of contexts. The workers apply an alogrithm of "Round-Robin" to chose the context on which they will "pop" next. By using the function starpu\_sched\_ctx\_set\_turn\_to\_other\_ctx, the programmer can impose the workerid to "pop" in the context sched\_ctx\_id next.

66	Scheduling Contexts

## **Chapter 10**

# **Scheduling Context Hypervisor**

## 10.1 What Is The Hypervisor

StarPU proposes a platform to construct Scheduling Contexts, to delete and modify them dynamically. A parallel kernel, can thus be isolated into a scheduling context and interferences between several parallel kernels are avoided. If the user knows exactly how many workers each scheduling context needs, he can assign them to the contexts at their creation time or modify them during the execution of the program.

The Scheduling Context Hypervisor Plugin is available for the users who do not dispose of a regular parallelism, who cannot know in advance the exact size of the context and need to resize the contexts according to the behavior of the parallel kernels.

The Hypervisor receives information from StarPU concerning the execution of the tasks, the efficiency of the resources, etc. and it decides accordingly when and how the contexts can be resized. Basic strategies of resizing scheduling contexts already exist but a platform for implementing additional custom ones is available.

## 10.2 Start the Hypervisor

The Hypervisor must be initialized once at the beginning of the application. At this point a resizing policy should be indicated. This strategy depends on the information the application is able to provide to the hypervisor as well as on the accuracy needed for the resizing procedure. For example, the application may be able to provide an estimation of the workload of the contexts. In this situation the hypervisor may decide what resources the contexts need. However, if no information is provided the hypervisor evaluates the behavior of the resources and of the application and makes a guess about the future. The hypervisor resizes only the registered contexts.

#### 10.3 Interrogate The Runtime

The runtime provides the hypervisor with information concerning the behavior of the resources and the application. This is done by using the performance\_counters which represent callbacks indicating when the resources are idle or not efficient, when the application submits tasks or when it becomes to slow.

## 10.4 Trigger the Hypervisor

The resizing is triggered either when the application requires it (sc\_hypervisor\_resize\_ctxs) or when the initials distribution of resources alters the performance of the application (the application is to slow or the resource are idle for too long time). If the environment variable SC\_HYPERVISOR\_TRIGGER\_RESIZE is set to speed the monitored speed of the contexts is compared to a theoretical value computed with a linear program, and the resizing is triggered whenever the two values do not correspond. Otherwise, if the environment variable is set to idle the

hypervisor triggers the resizing algorithm whenever the workers are idle for a period longer than the threshold indicated by the programmer. When this happens different resizing strategy are applied that target minimizing the total execution of the application, the instant speed or the idle time of the resources.

## 10.5 Resizing Strategies

The plugin proposes several strategies for resizing the scheduling context.

The **Application driven** strategy uses the user's input concerning the moment when he wants to resize the contexts. Thus, the users tags the task that should trigger the resizing process. We can set directly the field starpu\_task::hypervisor\_tag or use the macro ::STARPU\_HYPERVISOR\_TAG in the function starpu\_task\_insert().

Then the user has to indicate that when a task with the specified tag is executed the contexts should resize.

```
sc_hypervisor_resize(sched_ctx, 2);
```

The user can use the same tag to change the resizing configuration of the contexts if he considers it necessary.

The **Idleness** based strategy moves workers unused in a certain context to another one needing them. (see Users' Input In The Resizing Process)

The **Gflops rate** based strategy resizes the scheduling contexts such that they all finish at the same time. The speed of each of them is computed and once one of them is significantly slower the resizing process is triggered. In order to do these computations the user has to input the total number of instructions needed to be executed by the parallel kernels and the number of instruction to be executed by each task.

The number of flops to be executed by a context are passed as parameter when they are registered to the hypervisor, (sc\_hypervisor\_register\_ctx(sched\_ctx\_id, flops)) and the one to be executed by each task are passed when the task is submitted. The corresponding field is starpu\_task::flops and the corresponding macro in the function starpu\_task\_insert() is STARPU\_FLOPS (Caution: but take care of passing a double, not an integer, otherwise parameter passing will be bogus). When the task is executed the resizing process is triggered.

The **Feft** strategy uses a linear program to predict the best distribution of resources such that the application finishes in a minimum amount of time. As for the **Gflops rate** strategy the programmers has to indicate the total number of flops to be executed when registering the context. This number of flops may be updated dynamically during the execution of the application whenever this information is not very accurate from the beginning. The function sc\_hypervisor\_update\_diff\_total\_flop is called in order add or remove a difference to the flops left to be executed. Tasks are provided also the number of flops corresponding to each one of them. During the execution of the application the hypervisor monitors the consumed flops and recomputes the time left and the number of resources to use. The speed of each type of resource is (re)evaluated and inserter in the linear program in order to better adapt to the needs of the application.

The **Teft** strategy uses a linear program too, that considers all the types of tasks and the number of each of them and it tries to allocates resources such that the application finishes in a minimum amount of time. A previous calibration of StarPU would be useful in order to have good predictions of the execution time of each type of task.

The types of tasks may be determines directly by the hypervisor when they are submitted. However there are applications that do not expose all the graph of tasks from the beginning. In this case in order to let the hypervisor know about all the tasks the function sc\_hypervisor\_set\_type\_of\_task will just inform the hypervisor about future tasks without submitting them right away.

The **Ispeed** strategy divides the execution of the application in several frames. For each frame the hypervisor computes the speed of the contexts and tries making them run at the same speed. The strategy requires less contribution from the user as the hypervisor requires only the size of the frame in terms of flops.

The **Throughput** strategy focuses on maximizing the throughput of the resources and resizes the contexts such that the machine is running at its maximum efficiency (maximum instant speed of the workers).

# 10.6 Defining A New Hypervisor Policy

While Scheduling Context Hypervisor Plugin comes with a variety of resizing policies (see Resizing Strategies), it may sometimes be desirable to implement custom policies to address specific problems. The API described below allows users to write their own resizing policy.

Here an example of how to define a new policy

```
struct sc_hypervisor_policy dummy_policy =
{
    .handle_poped_task = dummy_handle_poped_task,
    .handle_pushed_task = dummy_handle_pushed_task,
    .handle_idle_cycle = dummy_handle_idle_cycle,
    .handle_idle_end = dummy_handle_idle_end,
    .handle_post_exec_hook = dummy_handle_post_exec_hook,
    .custom = 1,
    .name = "dummy"
};
```


Scheduling	Context	Hγ	perviso

# **Chapter 11**

# **Modularized Scheduler**

## 11.1 Introduction

StarPU's Modularized Schedulers are made of individual Scheduling Components Modularizedly assembled as a Scheduling Tree. Each Scheduling Component has an unique purpose, such as prioritizing tasks or mapping tasks over resources. A typical Scheduling Tree is shown below.



When a task is pushed by StarPU in a Modularized Scheduler, the task moves from a Scheduling Component to an other, following the hierarchy of the Scheduling Tree, and is stored in one of the Scheduling Components of the strategy. When a worker wants to pop a task from the Modularized Scheduler, the corresponding Worker Component of the Scheduling Tree tries to pull a task from its parents, following the hierarchy, and gives it to the worker if it succeeded to get one.

# 11.2 Using Modularized Schedulers

## 11.2.1 Existing Modularized Schedulers

StarPU is currently shipped with the following pre-defined Modularized Schedulers :

Eager-based Schedulers (with/without prefetching) :

72 Modularized Scheduler

Naive scheduler, which tries to map a task on the first available resource it finds.

Prio-based Schedulers (with/without prefetching):
 Similar to Eager-Based Schedulers. Can handle tasks which have a defined priority and schedule them accordingly.


Random-based Schedulers (with/without prefetching):
 Selects randomly a resource to be mapped on for each task.

#### · HEFT Scheduler:

Heterogeneous Earliest Finish Time Scheduler. This scheduler needs that every task submitted to StarPU have a defined performance model (Performance Model Calibration) to work efficiently, but can handle tasks without a performance model.

It is currently needed to set the environment variable STARPU\_SCHED to use those Schedulers. Modularized Schedulers' naming is tree-\*

## 11.2.2 An Example: The Tree-Eager-Prefetching Strategy



#### 11.2.3 Interface

Each Scheduling Component must follow the following pre-defined Interface to be able to interact with other Scheduling Components.

- Push (Caller\_Component, Child\_Component, Task)

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component

  The calling Scheduling Component transfers a task to its Child Component transfer to the task to its Child Component transfers a task to its Child Component transfer to the task
  - The calling Scheduling Component transfers a task to its Child Component. When the Push function returns, the task no longer belongs to the calling Component. The Modularized Schedulers' model relies on this function to perform prefetching.
- Pull (Caller\_Component, Parent\_Component) -> Task
   The calling Scheduling Component requests a task from its Parent Component. When the Pull function ends, the returned task belongs to the calling Component.

- Can\_Push (Caller\_Component, Parent\_Component)
   The calling Scheduling Component notifies its Parent Component that it is ready to accept new tasks.
- Can\_Pull (Caller\_Component, Child\_Component)
   The calling Scheduling Component notifies its Child Component that it is ready to give new tasks.

## 11.3 Build a Modularized Scheduler

## 11.3.1 Pre-implemented Components

StarPU is currently shipped with the following four Scheduling Components:

- Flow-control Components : Fifo, Prio
  - Components which store tasks. They can also prioritize them if they have a defined priority. It is possible to define a threshold for those Components following two criterias: the number of tasks stored in the Component, or the sum of the expected length of all tasks stored in the Component.
- Resource-Mapping Components: Mct, Heft, Eager, Random, Work-Stealing
   "Core" of the Scheduling Strategy, those Components are the ones who make scheduling choices.
- Worker Components: Worker
   Each Worker Component modelize a concrete worker.
- Special-Purpose Components: Perfmodel\_Select, Best\_Implementation
   Components dedicated to original purposes. The Perfmodel\_Select Component decides which Resource-Mapping Component should be used to schedule a task. The Best\_Implementation Component chooses which implementation of a task should be used on the choosen resource.

## 11.3.2 Progression And Validation Rules

Some rules must be followed to ensure the correctness of a Modularized Scheduler:

- At least one Flow-control Component without threshold per Worker Component is needed in a Modularized Scheduler, to store incoming tasks from StarPU and to give tasks to Worker Components who asks for it. It is possible to use one Flow-control Component per Worker Component, or one for all Worker Components, depending on how the Scheduling Tree is defined.
- At least one Resource-Mapping Component is needed in a Modularized Scheduler. Resource-Mapping Components are the only ones who can make scheduling choices, and so the only ones who can have several child.

## 11.3.3 Implement a Modularized Scheduler

The following code shows how the Tree-Eager-Prefetching Scheduler shown in Section An Example: The Tree-Eager-Prefetching Strategy is implemented:

```
#define _STARPU_SCHED_NTASKS_THRESHOLD_DEFAULT 2
#define _STARPU_SCHED_EXP_LEN_THRESHOLD_DEFAULT 1000000000.0

static void initialize_eager_prefetching_center_policy(unsigned sched_ctx_id)
{
    unsigned ntasks_threshold = _STARPU_SCHED_NTASKS_THRESHOLD_DEFAULT;
    double exp_len_threshold = _STARPU_SCHED_EXP_LEN_THRESHOLD_DEFAULT;
```

74 Modularized Scheduler

```
\verb|starpu_sched_ctx_create_worker_collection||\\
    (sched_ctx_id, STARPU_WORKER_LIST);
  /* Create the Scheduling Tree */
  struct starpu_sched_tree * t :
    starpu_sched_tree_create(sched_ctx_id);
  /* The Root Component is a Flow-control Fifo Component */
  t->root = starpu_sched_component_fifo_create
      (NULT.):
  /\star The Resource-mapping Component of the strategy is an Eager Component
  struct starpu_sched_component * eager_component =
    starpu_sched_component_eager_create(NULL);
  /* Create links between Components : the Eager Component is the child
     of the Root Component */
  t->root->add_child
    (t->root, eager_component);
  eager_component->add father
    (eager_component, t->root);
  /\star A task threshold is set for the Flow-control Components which will
     be connected to Worker Components. By doing so, this Modularized
     Scheduler will be able to perform some prefetching on the resources
  struct starpu sched component fifo data
      fifo data :
    .ntasks_threshold = ntasks_threshold,
    .exp_len_threshold = exp_len_threshold,
  unsigned i;
  for(i = 0;
    i < starpu_worker_get_count() +</pre>
    starpu_combined_worker_get_count();
    i++)
    /* Each Worker Component has a Flow-control Fifo Component as
      father */
    struct starpu_sched_component * worker_component =
         starpu_sched_component_worker_get(i)
    struct starpu_sched_component * fifo_component =
         starpu_sched_component_fifo_create(
      &fifo_data);
    fifo_component->add_child
      (fifo_component, worker_component);
    worker_component->add_father
      (worker_component, fifo_component);
    /* Each Flow-control Fifo Component associated to a Worker
       Component is linked to the Eager Component as one of its
       children */
    eager_component->add_child
    (eager_component, fifo_component);
fifo_component->add_father
      (fifo_component, eager_component);
  starpu_sched_tree_update_workers(t);
  {\tt starpu\_sched\_ctx\_set\_policy\_data}
    (sched_ctx_id, (void*)t);
/\star Properly destroy the Scheduling Tree and all its Components \star/
static void deinitialize_eager_prefetching_center_policy(unsigned sched_ctx_id)
 struct starpu_sched_tree * tree =
       (struct starpu_sched_tree*)
      starpu_sched_ctx_get_policy_data(sched_ctx_id);
  starpu_sched_tree_destroy(tree);
  starpu_sched_ctx_delete_worker_collection
    (sched_ctx_id);
/\star Initializing the starpu_sched_policy struct associated to the Modularized
   Scheduler : only the init_sched and deinit_sched needs to be defined to
   implement a Modularized Scheduler */
struct starpu_sched_policy
      _starpu_sched_tree_eager_prefetching_policy =
{
```

# 11.4 Write a Scheduling Component

## 11.4.1 Generic Scheduling Component

Each Scheduling Component is instantiated from a Generic Scheduling Component, which implements a generic version of the Interface. The generic implementation of Pull, Can\_Pull and Can\_Push functions are recursive calls to their parents (respectively to their children). However, as a Generic Scheduling Component do not know how much children it will have when it will be instantiated, it does not implement the Push function.


#### 11.4.2 Instantiation: Redefine the Interface

A Scheduling Component must implement all the functions of the Interface. It is so necessary to implement a Push function to instantiate a Scheduling Component. The implemented Push function is the "fingerprint" of a Scheduling Component. Depending on how functionalities or properties the programmer wants to give to the Scheduling Component he is implementing, it is possible to reimplement all the functions of the Interface. For example, a Flow-control Component reimplements the Pull and the Can\_Push functions of the Interface, allowing him to catch the generic recursive calls of these functions. The Pull function of a Flow-control Component can, for example, pop a task from the local storage queue of the Component, and give it to the calling Component which asks for it.


# 11.4.3 Detailed Progression and Validation Rules

- A Reservoir is a Scheduling Component which redefines a Push and a Pull function, in order to store tasks into it. A Reservoir delimit Scheduling Areas in the Scheduling Tree.
- A Pump is the engine source of the Scheduler: it pushes/pulls tasks to/from a Scheduling Component to
  an other. Native Pumps of a Scheduling Tree are located at the root of the Tree (incoming Push calls from
  StarPU), and at the leafs of the Tree (Pop calls coming from StarPU Workers). Pre-implemented Scheduling Components currently shipped with Pumps are Flow-Control Components and the Resource-Mapping
  Component Heft, within their defined Can\_Push functions.
- · A correct Scheduling Tree requires a Pump per Scheduling Area and per Execution Flow.

The Tree-Eager-Prefetching Scheduler shown in Section An Example : The Tree-Eager-Prefetching Strategy follows the previous assumptions :



76 Modularized Scheduler



# **Chapter 12**

# **Debugging Tools**

StarPU provides several tools to help debugging applications. Execution traces can be generated and displayed graphically, see Generating Traces With FxT.

Some gdb helpers are also provided to show the whole StarPU state:

```
(gdb) source tools/gdbinit
(gdb) help starpu
```

Valgrind can be used on StarPU: valgrind.h just needs to be found at ./configure time, to tell valgrind about some known false positives and disable host memory pinning. Other known false positives can be suppressed by giving the suppression files in tools/valgrind/ \*.suppr to valgrind's –suppressions option.

The environment variable STARPU\_DISABLE\_KERNELS can also be set to 1 to make StarPU do everything (schedule tasks, transfer memory, etc.) except actually calling the application-provided kernel functions, i.e. the computation will not happen. This permits to quickly check that the task scheme is working properly.


The Temanejo task debugger can also be used, see Using The Temanejo Task Debugger.

# 12.1 Using The Temanejo Task Debugger

StarPU can connect to Temanejo >= 1.0rc2 (see <a href="http://www.hlrs.de/temanejo">http://www.hlrs.de/temanejo</a>), to permit nice visual task debugging. To do so, build Temanejo's libayudame.so, install Ayudame.h to e.g. /usr/local/include, apply the tools/patch-ayudame to it to fix C build, re-./configure, make sure that it found it, rebuild StarPU. Run the Temanejo GUI, give it the path to your application, any options you want to pass it, the path to libayudame.so.

It permits to visualize the task graph, add breakpoints, continue execution task-by-task, and run gdb on a given task, etc.

78 Debugging Tools



Make sure to specify at least the same number of CPUs in the dialog box as your machine has, otherwise an error will happen during execution. Future versions of Temanejo should be able to tell StarPU the number of CPUs to use.

# Chapter 13

# **Online Performance Tools**

# 13.1 On-line Performance Feedback

#### 13.1.1 Enabling On-line Performance Monitoring

In order to enable online performance monitoring, the application can call starpu\_profiling\_status\_set() with the parameter STARPU\_PROFILING\_ENABLE. It is possible to detect whether monitoring is already enabled or not by calling starpu\_profiling\_status\_get(). Enabling monitoring also reinitialize all previously collected feedback. The environment variable STARPU\_PROFILING can also be set to 1 to achieve the same effect. The function starpu\_profiling\_init() can also be called during the execution to reinitialize performance counters and to start the profiling if the environment variable STARPU\_PROFILING is set to 1.

Likewise, performance monitoring is stopped by calling starpu\_profiling\_status\_set() with the parameter STARPU\_-PROFILING\_DISABLE. Note that this does not reset the performance counters so that the application may consult them later on.

More details about the performance monitoring API are available in Profiling.

#### 13.1.2 Per-task Feedback

If profiling is enabled, a pointer to a structure starpu\_profiling\_task\_info is put in the field starpu\_task::profiling\_info when a task terminates. This structure is automatically destroyed when the task structure is destroyed, either automatically or by calling starpu\_task\_destroy().

The structure starpu\_profiling\_task\_info indicates the date when the task was submitted (starpu\_profiling\_task\_info::submit\_time), started (starpu\_profiling\_task\_info::start\_time), and terminated (starpu\_profiling\_task\_info::end\_time), relative to the initialization of StarPU with starpu\_init(). It also specifies the identifier of the worker that has executed the task (starpu\_profiling\_task\_info::workerid). These date are stored as timespec structures which the user may convert into micro-seconds using the helper function starpu\_timing\_timespec\_to\_us().

It it worth noting that the application may directly access this structure from the callback executed at the end of the task. The structure starpu\_task associated to the callback currently being executed is indeed accessible with the function starpu\_task get current().

#### 13.1.3 Per-codelet Feedback

The field starpu\_codelet::per\_worker\_stats is an array of counters. The i-th entry of the array is incremented every time a task implementing the codelet is executed on the i-th worker. This array is not reinitialized when profiling is enabled or disabled.

80 Online Performance Tools

#### 13.1.4 Per-worker Feedback

The second argument returned by the function starpu\_profiling\_worker\_get\_info() is a structure starpu\_profiling\_worker\_info that gives statistics about the specified worker. This structure specifies when StarPU started collecting profiling information for that worker (starpu\_profiling\_worker\_info::start\_time), the duration of the profiling measurement interval (starpu\_profiling\_worker\_info::total\_time), the time spent executing kernels (starpu\_profiling\_worker\_info::executing\_time), the time spent sleeping because there is no task to execute at all (starpu\_profiling\_worker\_info::sleeping\_time), and the number of tasks that were executed while profiling was enabled. These values give an estimation of the proportion of time spent do real work, and the time spent either sleeping because there are not enough executable tasks or simply wasted in pure StarPU overhead.

Calling starpu profiling worker get info() resets the profiling information associated to a worker.

When an FxT trace is generated (see Generating Traces With FxT), it is also possible to use the tool  $starpu\_-workers\_activity$  (see Monitoring Activity) to generate a graphic showing the evolution of these values during the time, for the different workers.

#### 13.1.5 Bus-related Feedback

TODO: ajouter STARPU\_BUS\_STATS

The bus speed measured by StarPU can be displayed by using the tool starpu\_machine\_display, for instance:

```
StarPU has found:
       3 CUDA devices
              CUDA 0 (Tesla C2050 02:00.0)
               CUDA 1 (Tesla C2050 03:00.0)
              CUDA 2 (Tesla C2050 84:00.0)
from
      to RAM
                      to CUDA 0
                                      to CUDA 1
                                                     to CUDA 2
       0.000000
                      5176.530428
                                      5176.492994
                                                     5191.710722
                                                    2417.379201
CUDA 0 4523.732446
                     0.000000
                                      2414.074751
CUDA 1 4523.718152
                      2414.078822
                                      0.000000
                                                     2417.375119
CUDA 2 4534.229519
                      2417.069025
                                     2417.060863
                                                     0.000000
```

## 13.1.6 StarPU-Top Interface

StarPU-Top is an interface which remotely displays the on-line state of a StarPU application and permits the user to change parameters on the fly.

Variables to be monitored can be registered by calling the functions starpu\_top\_add\_data\_boolean(), starpu\_top\_add\_data\_float(), e.g.:

The application should then call starpu\_top\_init\_and\_wait() to give its name and wait for StarPU-Top to get a start request from the user. The name is used by StarPU-Top to quickly reload a previously-saved layout of parameter display.

```
starpu_top_init_and_wait("the application");
```

The new values can then be provided thanks to starpu\_top\_update\_data\_boolean(), starpu\_top\_update\_data\_integer(), starpu\_top\_update\_data\_float(), e.g.:

```
starpu_top_update_data_integer(data, mynum);
```

Updateable parameters can be registered thanks to starpu\_top\_register\_parameter\_boolean(), starpu\_top\_register\_parameter\_integer(), starpu\_top\_register\_parameter\_float(), e.g.:

modif\_hook is a function which will be called when the parameter is being modified, it can for instance print the new value:

```
void modif_hook(struct starpu_top_param *d) {
    fprintf(stderr,"%s has been modified: %f\n", d->name, alpha);
}
```

Task schedulers should notify StarPU-Top when it has decided when a task will be scheduled, so that it can show it in its Gantt chart, for instance:

```
starpu_top_task_prevision(task, workerid, begin, end);
```

Starting StarPU-Top (StarPU-Top is started via the binary starpu\_top.) and the application can be done two ways:

- The application is started by hand on some machine (and thus already waiting for the start event). In the Preference dialog of StarPU-Top, the SSH checkbox should be unchecked, and the hostname and port (default is 2011) on which the application is already running should be specified. Clicking on the connection button will thus connect to the already-running application.
- StarPU-Top is started first, and clicking on the connection button will start the application itself (possibly on a remote machine). The SSH checkbox should be checked, and a command line provided, e.g.:

```
\ ssh myserver STARPU_SCHED=dmda ./application
```

If port 2011 of the remote machine can not be accessed directly, an ssh port bridge should be added:

```
$ ssh -L 2011:localhost:2011 myserver STARPU_SCHED=dmda ./application
```

and "localhost" should be used as IP Address to connect to.

# 13.2 Task And Worker Profiling

A full example showing how to use the profiling API is available in the StarPU sources in the directory examples/profiling/.

```
struct starpu task *task = starpu task create();
task->cl = &cl;
task->synchronous = 1;
/* We will destroy the task structure by hand so that we can
   query the profiling info before the task is destroyed. \star
task->destroy = 0;
/\star Submit and wait for completion (since synchronous was set to 1) \star/
starpu_task_submit(task);
/\star The task is finished, get profiling information \star/
struct starpu_profiling_task_info *info = task->
      profiling_info;
/\star How much time did it take before the task started ? \star/
double delay += starpu_timing_timespec_delay_us(
      &info->submit_time, &info->start_time);
/* How long was the task execution ? */
double length += starpu_timing_timespec_delay_us
      (&info->start_time, &info->end_time);
/* We don't need the task structure anymore */
starpu_task_destroy(task);
```

```
/* Display the occupancy of all workers during the test */
for (worker = 0; worker < starpu_worker_get_count();</pre>
      worker++)
        struct starpu profiling worker info
      worker_info;
         int ret = starpu_profiling_worker_get_info
       (worker, &worker_info);
        STARPU ASSERT (!ret);
        double total_time = starpu_timing_timespec_to_us
       (&worker info.total time);
        double executing_time = starpu_timing_timespec_to_us
       (&worker_info.executing_time);
        double sleeping_time = starpu_timing_timespec_to_us
       (&worker_info.sleeping_time);
        double overhead_time = total_time - executing_time - sleeping_time
        float executing_ratio = 100.0*executing_time/total_time;
         float sleeping_ratio = 100.0*sleeping_time/total_time;
        float overhead_ratio = 100.0 - executing_ratio - sleeping_ratio;
        char workername[128];
        starpu_worker_get_name(worker, workername, 128);
        fprintf(stderr, "Worker %s:\n", workername);
fprintf(stderr, "\ttotal time: %.21f ms\n", total_time*1e-3);
fprintf(stderr, "\texec time: %.21f ms (%.2f %%)\n",
        executing_time*1e-3, executing_ratio); fprintf(stderr, "\tblocked time: %.21f ms (%.2f %%)\n",
                  sleeping_time*1e-3, sleeping_ratio);
                           "\toverhead time: %.21f ms (%.2f %%)\n",
                  overhead_time *1e-3, overhead_ratio);
}
```

# 13.3 Performance Model Example

To achieve good scheduling, StarPU scheduling policies need to be able to estimate in advance the duration of a task. This is done by giving to codelets a performance model, by defining a structure starpu\_perfmodel and providing its address in the field starpu\_codelet::model. The fields starpu\_perfmodel::symbol and starpu\_perfmodel::type are mandatory, to give a name to the model, and the type of the model, since there are several kinds of performance models. For compatibility, make sure to initialize the whole structure to zero, either by using explicit memset(), or by letting the compiler implicitly do it as examplified below.

• Measured at runtime (model type STARPU\_HISTORY\_BASED). This assumes that for a given set of data input/output sizes, the performance will always be about the same. This is very true for regular kernels on GPUs for instance (<0.1% error), and just a bit less true on CPUs (~=1% error). This also assumes that there are few different sets of data input/output sizes. StarPU will then keep record of the average time of previous executions on the various processing units, and use it as an estimation. History is done per task size, by using a hash of the input and ouput sizes as an index. It will also save it in \$STARP-U\_HOME/.starpu/sampling/codelets for further executions, and can be observed by using the tool starpu\_perfmodel\_display, or drawn by using the tool starpu\_perfmodel\_plot (Performance Model Calibration). The models are indexed by machine name. To share the models between machines (e.g. for a homogeneous cluster), use export STARPU\_HOSTNAME=some\_global\_name. Measurements are only done when using a task scheduler which makes use of it, such as dmda. Measurements can also be provided explicitly by the application, by using the function starpu\_perfmodel\_update\_history().

The following is a small code example.

If e.g. the code is recompiled with other compilation options, or several variants of the code are used, the symbol string should be changed to reflect that, in order to recalibrate a new model from zero. The symbol string can even be constructed dynamically at execution time, as long as this is done before submitting any task using it.

```
static struct starpu_perfmodel mult_perf_model = {
    .type = STARPU_HISTORY_BASED,
    .symbol = "mult_perf_model"
};
```

```
struct starpu_codelet cl = {
    .cpu_funcs = { cpu_mult },
    .cpu_funcs_name = { "cpu_mult" },
    .nbuffers = 3,
    .modes = { STARPU_R, STARPU_R, STARPU_W },
    /* for the scheduling policy to be able to use performance models */
    .model = &mult_perf_model
};
```

Measured at runtime and refined by regression (model types STARPU\_REGRESSION\_BASED and STARPU\_NL\_REGRESSION\_BASED). This still assumes performance regularity, but works with various data input sizes, by applying regression over observed execution times. STARPU\_REGRESSION\_BASED uses an a\*n^b regression form, STARPU\_NL\_REGRESSION\_BASED uses an a\*n^b+c (more precise than STARPU\_REGRESSION\_BASED, but costs a lot more to compute).

For instance, tests/perfmodels/regression\_based.c uses a regression-based performance model for the function memset().

Of course, the application has to issue tasks with varying size so that the regression can be computed. StarPU will not trust the regression unless there is at least 10% difference between the minimum and maximum observed input size. It can be useful to set the environment variable STARPU\_CALIBRATE to 1 and run the application on varying input sizes with STARPU\_SCHED set to dmda scheduler, so as to feed the performance model for a variety of inputs. The application can also provide the measurements explictly by using the function starpu\_perfmodel\_update\_history(). The tools starpu\_perfmodel\_display and starpu\_perfmodel\_plot can be used to observe how much the performance model is calibrated (Performance Model Calibration); when their output look good, STARPU\_CALIBRATE can be reset to 0 to let StarPU use the resulting performance model without recording new measures, and STARPU\_SCHED can be set to dmda to benefit from the performance models. If the data input sizes vary a lot, it is really important to set STARPU\_CALIBRATE to 0, otherwise StarPU will continue adding the measures, and result with a very big performance model, which will take time a lot of time to load and save.

For non-linear regression, since computing it is quite expensive, it is only done at termination of the application. This means that the first execution of the application will use only history-based performance model to perform scheduling, without using regression.

- Provided as an estimation from the application itself (model type STARPU\_COMMON and field starpu\_perfmodel::cost\_function), see for instance examples/common/blas\_model.h and examples/common/blas\_model.c.
- Provided explicitly by the application (model type STARPU\_PER\_ARCH): the fields .per\_arch[arch] [nimpl].cost\_function have to be filled with pointers to functions which return the expected duration of the task in micro-seconds, one per architecture.

For STARPU\_HISTORY\_BASED, STARPU\_REGRESSION\_BASED, and STARPU\_NL\_REGRESSION\_BASED, the dimensions of task data (both input and output) are used as an index by default. STARPU\_HISTORY\_BASED uses a CRC hash of the dimensions as an index to distinguish histories, and STARPU\_REGRESSION\_BASED and STARPU\_NL\_REGRESSION\_BASED use the total size as an index for the regression.

The starpu\_perfmodel::size\_base and starpu\_perfmodel::footprint fields however permit the application to override that, when for instance some of the data do not matter for task cost (e.g. mere reference table), or when using sparse structures (in which case it is the number of non-zeros which matter), or when there is some hidden parameter such as the number of iterations, or when the application actually has a very good idea of the complexity of the algorithm, and just not the speed of the processor, etc. The example in the directory <code>examples/pi</code> uses this to include the number of iterations in the base size. <code>starpu\_perfmodel::size\_base</code> should be used when the variance of the actual performance is known (i.e. bigger returned value is longer execution time), and thus particularly useful for <code>STARPU\_REGRESSION\_BASED</code> or <code>STARPU\_NL\_REGRESSION\_BASED</code>. <code>starpu\_perfmodel::footprint</code> can be used when the variance of the actual performance is unknown (irregular performance behavior, etc.), and thus only useful for <code>STARPU\_HISTORY\_BASED</code>. <code>starpu\_task\_data\_footprint()</code> can be used as a base and combined with other parameters through <code>starpu\_hash\_crc32c\_be</code> for instance.

StarPU will automatically determine when the performance model is calibrated, or rather, it will assume the performance model is calibrated until the application submits a task for which the performance can not be predicted. For STARPU\_HISTORY\_BASED, StarPU will require 10 (STARPU\_CALIBRATE\_MINIMUM) measurements for a given size before estimating that an average can be taken as estimation for further executions with the same size.

For STARPU\_REGRESSION\_BASED and STARPU\_NL\_REGRESSION\_BASED, StarPU will require 10 (STARP-U\_CALIBRATE\_MINIMUM) measurements, and that the minimum measured data size is smaller than 90% of the maximum measured data size (i.e. the measurement interval is large enough for a regression to have a meaning). Calibration can also be forced by setting the STARPU\_CALIBRATE environment variable to 1, or even reset by setting it to 2.

How to use schedulers which can benefit from such performance model is explained in Task Scheduling Policy.

The same can be done for task power consumption estimation, by setting the field <a href="mailto:starpu\_codelet::power\_model">starpu\_codelet::power\_model</a> the same way as the field <a href="mailto:starpu\_codelet::model">starpu\_codelet::model</a>. Note: for now, the application has to give to the power consumption performance model a name which is different from the execution time performance model.


The application can request time estimations from the StarPU performance models by filling a task structure as usual without actually submitting it. The data handles can be created by calling any of the functions  $starpu_*-data_register$  with a NULL pointer and -1 node and the desired data sizes, and need to be unregistered as usual. The functions  $starpu_task_expected_length()$  and  $starpu_task_expected_power()$  can then be called to get an estimation of the task cost on a given arch.  $starpu_task_footprint()$  can also be used to get the footprint used for indexing history-based performance models.  $starpu_task_destroy()$  needs to be called to destroy the dummy task afterwards. See  $tests/perfmodels/regression_based.c$  for an example.

# 13.4 Data trace and tasks length

It is possible to get statistics about tasks length and data size by using:

```
$ starpu_fxt_data_trace filename [codelet1 codelet2 ... codeletn]
```

Where filename is the FxT trace file and codeletX the names of the codelets you want to profile (if no names are specified, starpu\_fxt\_data\_trace will profile them all). This will create a file, data\_trace.gp which can be executed to get a .eps image of these results. On the image, each point represents a task, and each color corresponds to a codelet.



# **Chapter 14**

# **Offline Performance Tools**

To get an idea of what is happening, a lot of performance feedback is available, detailed in this chapter. The various informations should be checked for.

- What does the Gantt diagram look like? (see Creating a Gantt Diagram)
  - If it's mostly green (tasks running in the initial context) or context specific color prevailing, then the
    machine is properly utilized, and perhaps the codelets are just slow. Check their performance, see
    Performance Of Codelets.
  - If it's mostly purple (FetchingInput), tasks keep waiting for data transfers, do you perhaps have far more communication than computation? Did you properly use CUDA streams to make sure communication can be overlapped? Did you use data-locality aware schedulers to avoid transfers as much as possible?
  - If it's mostly red (Blocked), tasks keep waiting for dependencies, do you have enough parallelism? It might be a good idea to check what the DAG looks like (see Creating a DAG With Graphviz).
  - If only some workers are completely red (Blocked), for some reason the scheduler didn't assign tasks to them. Perhaps the performance model is bogus, check it (see Performance Of Codelets). Do all your codelets have a performance model? When some of them don't, the schedulers switches to a greedy algorithm which thus performs badly.

You can also use the Temanejo task debugger (see Using The Temanejo Task Debugger) to visualize the task graph more easily.

## 14.1 Off-line Performance Feedback

#### 14.1.1 Generating Traces With FxT

StarPU can use the FxT library (see https://savannah.nongnu.org/projects/fkt/) to generate traces with a limited runtime overhead.

You can either get a tarball:

```
\ wget http://download.savannah.gnu.org/releases/fkt/fxt-0.2.11.tar.gz
```

or use the FxT library from CVS (autotools are required):

Compiling and installing the FxT library in the \$FXTDIR path is done following the standard procedure:

```
$ ./configure --prefix=$FXTDIR
$ make
$ make install
```

In order to have StarPU to generate traces, StarPU should be configured with the option --with-fxt:

```
$ ./configure --with-fxt=$FXTDIR
```

Or you can simply point the PKG\_CONFIG\_PATH to FXTDIR/lib/pkgconfig and pass --with-fxt to ./configure

When FxT is enabled, a trace is generated when StarPU is terminated by calling starpu\_shutdown(). The trace is a binary file whose name has the form  $prof_file_XXX_YYY$  where XXX is the user name, and YYY is the pid of the process that used StarPU. This file is saved in the /tmp/ directory by default, or by the directory specified by the environment variable STARPU\_FXT\_PREFIX.

The additional configure option --enable-fxt-lock can be used to generate trace events which describes the locks behaviour during the execution.

#### 14.1.2 Creating a Gantt Diagram

When the FxT trace file prof\_file\_something has been generated, it is possible to generate a trace in the Paje format by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

Or alternatively, setting the environment variable STARPU\_GENERATE\_TRACE to 1 before application execution will make StarPU do it automatically at application shutdown.

This will create a file paje.trace in the current directory that can be inspected with the ViTE (http://vite.-gforge.inria.fr/) trace visualizing open-source tool. It is possible to open the file paje.trace with ViTE by using the following command:

```
$ vite paje.trace
```

To get names of tasks instead of "unknown", fill the optional starpu\_codelet::name, or use a performance model for them. Details of the codelet execution can be obtained by passing --enable-paje-codelet-details when configuring StarPU and using a recent enough version of ViTE (at least r1430).

In the MPI execution case, collect the trace files from the MPI nodes, and specify them all on the command  $starpu\_fxt\_tool$ , for instance:

```
$ starpu_fxt_tool -i /tmp/prof_file_something1 -i /tmp/prof_file_something2
```

By default, all tasks are displayed using a green color. To display tasks with varying colors, pass option -c to starpu\_fxt\_tool.

To identify tasks precisely, the application can set the starpu\_task::tag\_id field of the task (or use STARPU\_TAG\_ONLY when using starpu\_task\_insert()), and with a recent enough version of vite (>= r1430) and the --enable-paje-codelet-details StarPU configure option, the value of the tag will show up in the trace.

It can also set the starpu\_task::name field of the task (or use STARPU\_NAME) when using starpu\_task\_insert()), to replace in traces the name of the codelet with an arbitrarily chosen name.

Traces can also be inspected by hand by using the tool fxt\_print, for instance:

```
$ fxt_print -o -f /tmp/prof_file_something
```

Timings are in nanoseconds (while timings as seen in vite are in milliseconds).

#### 14.1.3 Creating a DAG With Graphviz

When the FxT trace file prof\_file\_something has been generated, it is possible to generate a task graph in the DOT format by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

This will create a dag. dot file in the current directory. This file is a task graph described using the DOT language. It is possible to get a graphical output of the graph by using the graphviz library:

```
$ dot -Tpdf dag.dot -o output.pdf
```

#### 14.1.4 Getting task details

When the FxT trace file prof\_file\_something has been generated, details on the executed tasks can be retrieved by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

This will create a tasks.rec file in the current directory. This file is in the recutils format, i.e. Field: value lines, and empty lines to separate each task. This can be used as a convenient input for various ad-hoc analysis tools. The performance models can be opened for instance by using starpu\_perfmodel\_load\_symbol and then using starpu perfmodel history based expected perf

#### 14.1.5 Monitoring Activity

When the FxT trace file  $prof_file\_something$  has been generated, it is possible to generate an activity trace by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

This will create a file activity.data in the current directory. A profile of the application showing the activity of StarPU during the execution of the program can be generated:

```
$ starpu_workers_activity activity.data
```

This will create a file named activity.eps in the current directory. This picture is composed of two parts. The first part shows the activity of the different workers. The green sections indicate which proportion of the time was spent executed kernels on the processing unit. The red sections indicate the proportion of time spent in StartPU: an important overhead may indicate that the granularity may be too low, and that bigger tasks may be appropriate to use the processing unit more efficiently. The black sections indicate that the processing unit was blocked because there was no task to process: this may indicate a lack of parallelism which may be alleviated by creating more tasks when it is possible.

The second part of the picture activity.eps is a graph showing the evolution of the number of tasks available in the system during the execution. Ready tasks are shown in black, and tasks that are submitted but not schedulable yet are shown in grey.

## 14.1.6 Getting modular schedular animation

When using modular schedulers (i.e. schedulers which use a modular architecture, and whose name start with "modular-"), the command

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

will also produce a trace.html file which can be viewed in a javascript-enabled web browser. It shows the flow of tasks between the components of the modular scheduler.

#### 14.2 Performance Of Codelets

The performance model of codelets (see Performance Model Example) can be examined by using the tool starpu\_perfmodel\_display:

```
$ starpu_perfmodel_display -1
file: <malloc_pinned.hannibal>
file: <starpu_slu_lu_model_21.hannibal>
file: <starpu_slu_lu_model_11.hannibal>
file: <starpu_slu_lu_model_22.hannibal>
file: <starpu_slu_lu_model_12.hannibal>
```

Here, the codelets of the example 1u are available. We can examine the performance of the kernel 22 (in microseconds), which is history-based:


We can see that for the given size, over a sample of a few hundreds of execution, the GPUs are about 20 times faster than the CPUs (numbers are in us). The standard deviation is extremely low for the GPUs, and less than 10% for CPUs.

This tool can also be used for regression-based performance models. It will then display the regression formula, and in the case of non-linear regression, the same performance log as for history-based performance models:

```
$ starpu_perfmodel_display -s non_linear_memset_regression_based
performance model for cpu_impl_0
Regression: \#sample = 1400
Linear: y = alpha size ^ beta
alpha = 1.335973e-03
beta = 8.024020e-01
Non-Linear: y = a size ^b + c
a = 5.429195e-04
b = 8.654899e - 01
c = 9.009313e-01
# hash size mean stddev n
a3d3725e 4096 4.763200e+00 7.650928e-01
                                                         100
                        1.827970e+00 2.037181e-01
870a30aa 8192
                                                        100
48e988e9 16384
                       2.652800e+00 1.876459e-01
4.255530e+00 3.518025e-01
                                                         100
961e65d2 32768
                                                         100
```

The same can also be achieved by using StarPU's library API, see Performance Model and notably the function starpu\_perfmodel\_load\_symbol(). The source code of the tool starpu\_perfmodel\_display can be a useful example.


The tool starpu\_perfmodel\_plot can be used to draw performance models. It writes a .gp file in the current directory, to be run with the tool gnuplot, which shows the corresponding curve.



When the field starpu\_task::flops is set,  $starpu_perfmodel_plot$  can directly draw a GFlops curve, by simply adding the -f option:

\$ starpu\_perfmodel\_plot -f -s chol\_model\_11

This will however disable displaying the regression model, for which we can not compute GFlops.




When the FxT trace file  $prof\_file\_something$  has been generated, it is possible to get a profiling of each codelet by calling:

```
$ starpu_fxt_tool -i /tmp/prof_file_something
```

This will create profiling data files, and a distrib.data.gp file in the current directory, which draws the distribution of codelet time over the application execution, according to data input size.

<sup>\$</sup> starpu\_codelet\_profile distrib.data codelet\_name




This is also available in the tool starpu\_perfmodel\_plot, by passing it the fxt trace:

\$ starpu\_perfmodel\_plot -s non\_linear\_memset\_regression\_based -i /tmp/prof\_file\_foo\_0

It will produce a . gp file which contains both the performance model curves, and the profiling measurements.

Offline Performance Tools



If you have the statistical tool  $\ensuremath{\mathbb{R}}$  installed, you can additionally use


92

\$ starpu\_codelet\_histo\_profile distrib.data

Which will create one .pdf file per codelet and per input size, showing a histogram of the codelet execution time distribution.

14.3 Trace statistics 93

# Histogram of val[val > quantile(val, 0.01) & val < quantile(val, 0.99)]



# 14.3 Trace statistics

More than just codelet performance, it is interesting to get statistics over all kinds of StarPU states (allocations, data transfers, etc.). This is particularly useful to check what may have gone wrong in the accurracy of the simgrid simulation.

This requires the R statistical tool, with the plyr, ggplot2 and data.table packages. If your system distribution does not have packages for these, one can fetch them from CRAN:

```
$ R
> install.packages("plyr")
> install.packages("ggplot2")
> install.packages("data.table")
> install.packages("knitr")
```


The pj\_dump tool from pajeng is also needed (see https://github.com/schnorr/pajeng)

One can then get textual or .csv statistics over the trace states:

```
$ starpu_paje_state_stats -v native.trace simgrid.trace
"Value"
               "Events_native.csv" "Duration_native.csv"
                                                          "Events_simgrid.csv" "Duration_simgrid.csv"
"Callback"
               220
                                                                                Ω
                                   0.075978
                                                          220
"chol_model_11" 10
                                    565.176
                                                                                572.8695
"chol_model_21" 45
                                                                                9170.719
                                    9184.828
                                                          45
"chol_model_22" 165
                                    64712.07
                                                          165
                                                                                64299.203
$ starpu_paje_state_stats native.trace simgrid.trace
```

And one can plot histograms of execution times, of several states for instance:

\$ starpu\_paje\_draw\_histogram -n chol\_model\_11,chol\_model\_21,chol\_model\_22 native.trace simgrid.trace
and see the resulting pdf file:



A quick statistical report can be generated by using:

```
$ starpu_paje_summary native.trace simgrid.trace
```

it includes gantt charts, execution summaries, as well as state duration charts and time distribution histograms.

Other external Pajé analysis tools can be used on these traces, one just needs to sort the traces by timestamp order (which not guaranteed to make recording more efficient):

\$ starpu\_paje\_sort paje.trace

#### 14.4 Theoretical Lower Bound On Execution Time

StarPU can record a trace of what tasks are needed to complete the application, and then, by using a linear system, provide a theoretical lower bound of the execution time (i.e. with an ideal scheduling).

The computed bound is not really correct when not taking into account dependencies, but for an application which have enough parallelism, it is very near to the bound computed with dependencies enabled (which takes a huge lot more time to compute), and thus provides a good-enough estimation of the ideal execution time.

Theoretical Lower Bound On Execution Time Example provides an example on how to use this.

# 14.5 Theoretical Lower Bound On Execution Time Example

For kernels with history-based performance models (and provided that they are completely calibrated), StarPU can very easily provide a theoretical lower bound for the execution time of a whole set of tasks. See for instance  $examples/lu/lu_example.c$ : before submitting tasks, call the function  $starpu_bound_start()$ , and after complete execution, call  $starpu_bound_stop()$ .  $starpu_bound_print_p()$  or  $starpu_bound_print_mps()$  can then be used to output a Linear Programming problem corresponding to the schedule of your tasks. Run it through  $lp_solve$  or any other linear programming solver, and that will give you a lower bound for the total execution time of your tasks. If StarPU was compiled with the library glpk installed,  $starpu_bound_compute()$  can be used to solve it immediately and get the optimized minimum, in ms. Its parameter integer allows to decide whether integer resolution should be computed and returned

Data transfer time can only be taken into account when deps is set. Only data transfers inferred from implicit data dependencies between tasks are taken into account. Other data transfers are assumed to be completely overlapped.

Setting deps to 0 will only take into account the actual computations on processing units. It however still properly takes into account the varying performances of kernels and processing units, which is quite more accurate than just comparing StarPU performances with the fastest of the kernels being used.

The prio parameter tells StarPU whether to simulate taking into account the priorities as the StarPU scheduler would, i.e. schedule prioritized tasks before less prioritized tasks, to check to which extend this results to a less optimal solution. This increases even more computation time.

## 14.6 Memory Feedback

It is possible to enable memory statistics. To do so, you need to pass the option --enable-memory-stats when running configure. It is then possible to call the function starpu\_data\_display\_memory\_stats() to display statistics about the current data handles registered within StarPU.

Moreover, statistics will be displayed at the end of the execution on data handles which have not been cleared out. This can be disabled by setting the environment variable STARPU MEMORY STATS to 0.

For example, if you do not unregister data at the end of the complex example, you will get something similar to:

```
$ STARPU_MEMORY_STATS=0 ./examples/interface/complex
Complex[0] = 45.00 + 12.00 i
Complex[0] = 78.00 + 78.00 i
Complex[0] = 45.00 + 12.00 i
Complex[0] = 45.00 + 12.00 i
$ STARPU_MEMORY_STATS=1 ./examples/interface/complex
Complex[0] = 45.00 + 12.00 i
Complex[0] = 78.00 + 78.00 i
Complex[0] = 45.00 + 12.00 i
Complex[0] = 45.00 + 12.00 i
Memory stats:
#----
Data on Node #3
#----
Data : 0x553ff40
Size : 16
Data access stats
/!\ Work Underway
Node #0
Direct access : 4
Loaded (Owner) : 0
Loaded (Shared) : 0
Invalidated (was Owner) : 0
Node #3
Direct access : 0
Loaded (Owner) : 0
Loaded (Shared): 1
Invalidated (was Owner) : 0
Data : 0x5544710
Size : 16
Data access stats
/!\ Work Underway
Node #0
Direct access : 2
Loaded (Owner) : 0
Loaded (Shared): 1
Invalidated (was Owner) : 1
Node #3
Direct access : 0
Loaded (Owner): 1
Loaded (Shared) : 0
Invalidated (was Owner) : 0
```

#### 14.7 Data Statistics


Different data statistics can be displayed at the end of the execution of the application. To enable them, you need to pass the option --enable-stats when calling configure. When calling starpu\_shutdown() various statistics will be displayed, execution, MSI cache statistics, allocation cache statistics, and data transfer statistics. The display can be disabled by setting the environment variable STARPU\_STATS to 0.

```
$ ./examples/cholesky/cholesky_tag
Computation took (in ms)
518.16
Synthetic GFlops : 44.21
#------
MSI cache stats :
TOTAL MSI stats hit 1622 (66.23 %) miss 827 (33.77 %)
...
```

14.7 Data Statistics 97

\$ STARPU\_STATS=0 ./examples/cholesky\_tag
Computation took (in ms)
518.16

Synthetic GFlops : 44.21



# **Chapter 15**

# **Frequently Asked Questions**

# 15.1 How To Initialize A Computation Library Once For Each Worker?

Some libraries need to be initialized once for each concurrent instance that may run on the machine. For instance, a C++ computation class which is not thread-safe by itself, but for which several instanciated objects of that class can be used concurrently. This can be used in StarPU by initializing one such object per worker. For instance, the libstarpufft example does the following to be able to use FFTW on CPUs.

Some global array stores the instanciated objects:

```
fftw_plan plan_cpu[STARPU_NMAXWORKERS];
```

At initialisation time of libstarpu, the objects are initialized:

And in the codelet body, they are used:

```
static void fft(void *descr[], void *_args)
{
   int workerid = starpu_worker_get_id();
   fftw_plan plan = plan_cpu[workerid];
   ...
   fftw_execute(plan, ...);
}
```

This however is not sufficient for FFT on CUDA: initialization has to be done from the workers themselves. This can be done thanks to starpu\_execute\_on\_each\_worker(). For instance libstarpufft does the following.

# 15.2 Using The Driver API

#### **Running Drivers**

```
int ret;
struct starpu_driver = {
    .type = STARPU_CUDA_WORKER,
    .id.cuda_id = 0
};
ret = starpu_driver_init(&d);
if (ret != 0)
    error();
while (some_condition) {
    ret = starpu_driver_run_once(&d);
    if (ret != 0)
        error();
}
ret = starpu_driver_deinit(&d);
if (ret != 0)
    error();
```

To add a new kind of device to the structure starpu\_driver, one needs to:

- 1. Add a member to the union starpu driver::id
- 2. Modify the internal function \_starpu\_launch\_drivers() to make sure the driver is not always launched.
- 3. Modify the function starpu\_driver\_run() so that it can handle another kind of architecture.
- 4. Write the new function \_starpu\_run\_foobar() in the corresponding driver.

# 15.3 On-GPU Rendering

Graphical-oriented applications need to draw the result of their computations, typically on the very GPU where these happened. Technologies such as OpenGL/CUDA interoperability permit to let CUDA directly work on the OpenGL buffers, making them thus immediately ready for drawing, by mapping OpenGL buffer, textures or renderbuffer objects into CUDA. CUDA however imposes some technical constraints: peer memcpy has to be disabled, and the thread that runs OpenGL has to be the one that runs CUDA computations for that GPU.

To achieve this with StarPU, pass the option --disable-cuda-memcpy-peer to ./configure (TODO: make it dynamic), OpenGL/GLUT has to be initialized first, and the interoperability mode has to be enabled by using the field starpu\_conf::cuda\_opengl\_interoperability, and the driver loop has to be run by the application, by using the field starpu\_conf::not\_launched\_drivers to prevent StarPU from running it in a separate thread, and by using starpu\_driver\_run() to run the loop. The examples <code>gl\_interop</code> and <code>gl\_interop\_idle</code> show how it articulates in a simple case, where rendering is done in task callbacks. The former uses <code>glutMainLoopEvent</code> to make GLUT progress from the StarPU driver loop, while the latter uses <code>glutIdleFunc</code> to make StarPU progress from the GLUT main loop.

Then, to use an OpenGL buffer as a CUDA data, StarPU simply needs to be given the CUDA pointer at registration, for instance:

```
/* The handle can now be used as usual */
starpu_task_insert(&cl, STARPU_RW, handle, 0);
/* ... */
/* This gets back data into the OpenGL buffer */
starpu_data_unregister(handle);
```

and display it e.g. in the callback function.

# 15.4 Using StarPU With MKL 11 (Intel Composer XE 2013)

Some users had issues with MKL 11 and StarPU (versions 1.1rc1 and 1.0.5) on Linux with MKL, using 1 thread for MKL and doing all the parallelism using StarPU (no multithreaded tasks), setting the environment variable MKL\_N-UM\_THREADS to 1, and using the threaded MKL library, with iomp5.

Using this configuration, StarPU uses only 1 core, no matter the value of STARPU\_NCPU. The problem is actually a thread pinning issue with MKL.

The solution is to set the environment variable KMP\_AFFINITY to disabled (http://software.intel.-com/sites/products/documentation/studio/composer/en-us/2011Update/compiler-\_c/optaps/common/optaps\_openmp\_thread\_affinity.htm).

# 15.5 Thread Binding on NetBSD

When using StarPU on a NetBSD machine, if the topology discovery library hwloc is used, thread binding will fail. To prevent the problem, you should at least use the version 1.7 of hwloc, and also issue the following call:

```
$ sysctl -w security.models.extensions.user_set_cpu_affinity=1
Or add the following line in the file /etc/sysctl.conf
security.models.extensions.user_set_cpu_affinity=1
```

# 15.6 Interleaving StarPU and non-StarPU code

If your application only partially uses StarPU, and you do not want to call starpu\_init() / starpu\_shutdown() at the beginning/end of each section, StarPU workers will poll for work between the sections. To avoid this behavior, you can "pause" StarPU with the starpu\_pause() function. This will prevent the StarPU workers from accepting new work (tasks that are already in progress will not be frozen), and stop them from polling for more work.

Note that this does not prevent you from submitting new tasks, but they won't execute until starpu\_resume() is called. Also note that StarPU must not be paused when you call starpu\_shutdown(), and that this function pair works in a push/pull manner, ie you need to match the number of calls to these functions to clear their effect.

One way to use these functions could be:

Frequently Asked Question
---------------------------

# Part IV StarPU Extensions

# **Out Of Core**

### 16.1 Introduction

When using StarPU, one may need to store more data than what the main memory (RAM) can store. This part describes the method to add a new memory node on a disk and to use it.

The principle is that one first registers a disk location, seen by StarPU as a void\*, which can be for instance a Unix path for the stdio or unistd case, or a database file path for a leveldb case, etc. The disk backend opens this place with the plug method.

If the disk backend provides an alloc method, StarPU can then start using it to allocate room and store data there with the write method, without user intervention.

The user can also use starpu\_disk\_open to explicitly open an object within the disk, e.g. a file name in the stdio or unistd cases, or a database key in the leveldb case, and then use starpu\_\*\_register functions to turn it into a StarPU data handle. StarPU will then automatically read and write data as appropriate.

### 16.2 Use a new disk memory

To use a disk memory node, you have to register it with this function:

Here, we use the unistd library to realize the read/write operations, i.e. fread/fwrite. This structure must have a path where to store files, as well as the maximum size the software can afford storing on the disk.

Don't forget to check if the result is correct!

This can also be achieved by just setting environment variables:

```
export STARPU_DISK_SWAP=/tmp
export STARPU_DISK_SWAP_BACKEND=unistd
export STARPU_DISK_SWAP_SIZE=$((200*1024*1024))
```

When the register function is called, StarPU will benchmark the disk. This can take some time.

#### Warning: the size thus has to be at least 1 MB!

StarPU will automatically try to evict unused data to this new disk. One can also use the standard StarPU memory node API, see the Standard Memory Library and the Data Interfaces.

The disk is unregistered during the starpu\_shutdown().

106 Out Of Core

#### 16.3 Disk functions

There are various ways to operate a disk memory node, described by the structure starpu\_disk\_ops. For instance, the variable starpu\_disk\_unistd\_ops uses read/write functions.

All structures are in Out Of Core .

# 16.4 Examples: disk\_copy

```
/* Try to write into disk memory
* Use mechanism to push datas from main ram to disk ram
#include <starpu.h>
#include <stdlib.h>
#include <stdio.h>
#include <math.h>
/* size of one vector */
int main(int argc, char **argv)
       double * A. *B. *C. *D. *E. *F;
       /* limit main ram to force to push in disk */
setenv("STARPU_LIMIT_CPU_MEM", "160", 1);
        /* Initialize StarPU with default configuration */
       int ret = starpu_init(NULL);
        if (ret == -ENODEV) goto enodev;
        /* register a disk */
       int new_dd = starpu_disk_register(&
     starpu_disk_unistd_ops, (void *) "/tmp/", 1024*1024*200);
/* can't write on /tmp/ */
        if (new_dd == -ENOENT) goto enoent;
        /* allocate two memory spaces */
        starpu_malloc_flags((void **)&A, NX*sizeof(double),
      STARPU MALLOC COUNT);
        starpu_malloc_flags((void **)&F, NX*sizeof(double),
      STARPU_MALLOC_COUNT);
       FPRINTF(stderr, "TEST DISK MEMORY \n");
       unsigned int j;
        /* initialization with bad values */
        for(j = 0; j < NX; ++j)
                A[j] = j;
               F[j] = -j;
       }
       starpu data handle t vector handleA, vector handleB
      , vector_handleC, vector_handleD, vector_handleE, vector_handleF;
        /* register vector in starpu */
        starpu_vector_data_register(&vector_handleA,
      STARPU_MAIN_RAM, (uintptr_t)A, NX, sizeof(double));
       starpu_vector_data_register(&vector_handleB,
       -1, (uintptr_t) NULL, NX, sizeof(double));
       starpu_vector_data_register(&vector_handleC,
       -1, (uintptr_t) NULL, NX, sizeof(double));
        starpu_vector_data_register(&vector_handleD,
       -1, (uintptr_t) NULL, NX, sizeof(double));
       starpu_vector_data_register(&vector_handleE,
       -1, (uintptr_t) NULL, NX, sizeof(double));
        starpu_vector_data_register(&vector_handleF,
      STARPU_MAIN_RAM, (uintptr_t)F, NX, sizeof(double));
        /* copy vector A->B, B->C... */
        starpu_data_cpy(vector_handleB, vector_handleA, 0, NULL,
      NULL);
       starpu_data_cpy(vector_handleC, vector_handleB, 0, NULL,
      NULL);
```

```
starpu_data_cpy(vector_handleD, vector_handleC, 0, NULL,
        starpu_data_cpy(vector_handleE, vector_handleD, 0, NULL,
       NULL);
        starpu_data_cpy(vector_handleF, vector_handleE, 0, NULL,
       NULL);
        /\star {\tt StarPU} does not need to manipulate the array anymore so we can stop
         * monitoring it */
        /* free them */
        starpu_data_unregister(vector_handleA);
        starpu_data_unregister(vector_handleB);
        starpu_data_unregister(vector_handleC);
        starpu_data_unregister(vector_handleD);
        starpu_data_unregister(vector_handleE);
        starpu_data_unregister(vector_handleF);
        /\star check if computation is correct \star/
        int try = 1;
for (j = 0; j < NX; ++j)
                 if (A[j] != F[j])
                         printf("Fail A %f != F %f n", A[j], F[j]);
                         try = 0;
                }
        /* free last vectors */
      starpu_free_flags(A, NX*sizeof(double),
STARPU_MALLOC_COUNT);
        starpu_free_flags(F, NX*sizeof(double),
      STARPU_MALLOC_COUNT);
        /\star terminate StarPU, no task can be submitted after \star/
        starpu_shutdown();
        if(try)
                FPRINTF(stderr, "TEST SUCCESS\n");
                 FPRINTF(stderr, "TEST FAIL\n");
        return (try ? EXIT_SUCCESS : EXIT_FAILURE);
enodev:
        return 77;
enoent:
        return 77;
```

# 16.5 Examples: disk\_compute

```
/★ Try to write into disk memory
\star Use mechanism to push datas from main ram to disk ram
#include <starpu.h>
#include <stdlib.h>
#include <stdio.h>
#include <sys/types.h>
#include <unistd.h>
#include <math.h>
#define NX (1024)
int main(int argc, char **argv)
         /* Initialize StarPU with default configuration */ int ret = starpu\_init(NULL);
         if (ret == -ENODEV) goto enodev;
         /\star Initialize path and name \star/
         char pid_str[16];
         int pid = getpid();
         snprintf(pid_str, 16, "%d", pid);
         const char *name_file_start = "STARPU_DISK_COMPUTE_DATA_";
const char *name_file_end = "STARPU_DISK_COMPUTE_DATA_RESULT_";
         char * path_file_start = malloc(strlen(base) + 1 + strlen(
      name_file_start) + 1);
strcpy(path_file_start, base);
         strcat(path_file_start, "/");
```

108 Out Of Core

```
strcat(path_file_start, name_file_start);
  char * path_file_end = malloc(strlen(base) + 1 + strlen(name_file_end)
+ 1);
 strcpy(path_file_end, base);
strcat(path_file_end, "/");
  strcat(path_file_end, name_file_end);
  /* register a disk */
  int new_dd = starpu_disk_register(&
starpu_disk_unistd_ops, (void *) base, 1024*1024*1);
/* can't write on /tmp/ */
if (new_dd == -ENOENT) goto encent;
  unsigned dd = (unsigned) new_dd;
  printf("TEST DISK MEMORY \n");
  /* Imagine, you want to compute datas */
  int *A;
  starpu_malloc_flags((void **)&A, NX*sizeof(int),
STARPU_MALLOC_COUNT);
starpu_malloc_flags((void **)&C, NX*sizeof(int),
STARPU_MALLOC_COUNT);
  unsigned int j;
  /* you register them in a vector */
  for(j = 0; j < NX; ++j)
          A[j] = j;
C[j] = 0;
  /\star you create a file to store the vector ON the disk \star/
  FILE * f = fopen(path_file_start, "wb+");
  if (f == NULL)
          goto enoent2;
  /* store it in the file */
  fwrite(A, sizeof(int), NX, f);
  /* close the file */
  fclose(f);
  /* create a file to store result */
f = fopen(path_file_end, "wb+");
  if (f == NULL)
          goto enoent2;
  /* replace all datas by 0 */
  fwrite(C, sizeof(int), NX, f);
  /* close the file */
  fclose(f);
  /* And now, you want to use your datas in StarPU *//* Open the file ON the disk */
  void * data = starpu_disk_open(dd, (void *)
name_file_start, NX*sizeof(int));
  void * data_result = starpu_disk_open(dd, (void *)
name_file_end, NX*sizeof(int));
  starpu_data_handle_t vector_handleA, vector_handleC
  /* register vector in starpu */
  starpu_vector_data_register(&vector_handleA,
 dd, (uintptr_t) data, NX, sizeof(int));
  /\star and do what you want with it, here we copy it into an other vector
  starpu_vector_data_register(&vector_handleC,
 dd, (uintptr_t) data_result, NX, sizeof(int));
  starpu_data_cpy(vector_handleC, vector_handleA, 0, NULL,
 NULL);
  /* free them */
  starpu_data_unregister(vector_handleA);
  starpu_data_unregister(vector_handleC);
```

```
/* close them in StarPU */
         starpu_disk_close(dd, data, NX*sizeof(int));
         starpu_disk_close(dd, data_result, NX*sizeof(int));
         /* check results */
f = fopen(path_file_end, "rb+");
         if (f == NULL)
          /* take datas */
         int size = fread(C, sizeof(int), NX, f);
         /* close the file */
         fclose(f);
         int try = 1;
for (j = 0; j < NX; ++j)</pre>
                  if (A[j] != C[j])
                  {
                            printf("Fail A %d != C %d \n", A[j], C[j]);
                            try = 0;
       starpu_free_flags(A, NX*sizeof(int),
STARPU_MALLOC_COUNT);
starpu_free_flags(C, NX*sizeof(int),
STARPU_MALLOC_COUNT);
         unlink(path_file_start);
         unlink(path_file_end);
         free(path_file_start);
         free(path_file_end);
         /\star terminate StarPU, no task can be submitted after \star/
         starpu_shutdown();
         if(try)
                  printf("TEST SUCCESS\n");
                   printf("TEST FAIL\n");
         return (try ? EXIT_SUCCESS : EXIT_FAILURE);
enodev:
         return 77;
         starpu_free_flags(A, NX*sizeof(int),
       STARPU_MALLOC_COUNT);
       starpu_free_flags(C, NX*sizeof(int),
STARPU_MALLOC_COUNT);
enoent:
         unlink(path_file_start);
         unlink(path_file_end);
         free(path_file_start);
free(path_file_end);
         starpu_shutdown();
         return 77;
```



# **MPI Support**

The integration of MPI transfers within task parallelism is done in a very natural way by the means of asynchronous interactions between the application and StarPU. This is implemented in a separate libstarpumpi library which basically provides "StarPU" equivalents of MPI\_\* functions, where void \* buffers are replaced with starpu\_data\_handle\_t, and all GPU-RAM-NIC transfers are handled efficiently by StarPU-MPI. The user has to use the usual mpirun command of the MPI implementation to start StarPU on the different MPI nodes.

An MPI Insert Task function provides an even more seamless transition to a distributed application, by automatically issuing all required data transfers according to the task graph and an application-provided distribution.

# 17.1 Simple Example

The flags required to compile or link against the MPI layer are accessible with the following commands:

```
$ pkg-config --cflags starpumpi-1.2 # options for the compiler
$ pkg-config --libs starpumpi-1.2 # options for the linker
```

You also need pass the option -static if the application is to be linked statically.

```
void increment token (void)
    struct starpu_task *task = starpu_task_create(
    task->cl = &increment_cl;
    task->handles[0] = token_handle;
    starpu_task_submit(task);
int main(int argc, char **argv)
    int rank, size:
    starpu_init(NULL);
    starpu_mpi_initialize_extended(&rank, &size);
    starpu_vector_data_register(&token_handle,
      STARPU_MAIN_RAM, (uintptr_t) &token, 1, sizeof(unsigned));
    unsigned nloops = NITER;
    unsigned loop;
    unsigned last_loop = nloops - 1;
unsigned last_rank = size - 1;
    for (loop = 0; loop < nloops; loop++) {</pre>
        int tag = loop*size + rank;
        if (loop == 0 && rank == 0)
            fprintf(stdout, "Start with token value dn, token);
```

112 MPI Support

```
starpu_mpi_irecv_detached(token_handle, (
 increment_token();
   if (loop == last_loop && rank == last_rank)
       starpu_data_acquire(token_handle, STARPU_R
 );
       fprintf(stdout, "Finished: token value %d\n", token);
       starpu_data_release(token_handle);
   else
       starpu_mpi_isend_detached(token_handle, (
  rank+1)%size, tag+1,
              MPI_COMM_WORLD, NULL, NULL);
starpu_task_wait_for_all();
starpu_mpi_shutdown();
starpu_shutdown();
if (rank == last rank)
   fprintf(stderr, "[%d] token = %d == %d * %d ?\n", rank, token, nloops,
   STARPU_ASSERT(token == nloops*size);
```

#### 17.2 Point To Point Communication

The standard point to point communications of MPI have been implemented. The semantic is similar to the MPI one, but adapted to the DSM provided by StarPU. A MPI request will only be submitted when the data is available in the main memory of the node submitting the request.

There is two types of asynchronous communications: the classic asynchronous communications and the detached communications. The classic asynchronous communications (starpu\_mpi\_isend() and starpu\_mpi\_irecv()) need to be followed by a call to starpu\_mpi\_wait() or to starpu\_mpi\_test() to wait for or to test the completion of the communication. Waiting for or testing the completion of detached communications is not possible, this is done internally by StarPU-MPI, on completion, the resources are automatically released. This mechanism is similar to the pthread detach state attribute which determines whether a thread will be created in a joinable or a detached state.

Internally, all communication are divided in 2 communications, a first message is used to exchange an envelope describing the data (i.e its tag and its size), the data itself is sent in a second message. All MPI communications submitted by StarPU uses a unique tag which has a default value, and can be accessed with the functions starpu\_mpi\_get\_communication\_tag() and starpu\_mpi\_set\_communication\_tag(). The matching of tags with corresponding requests is done within StarPU-MPI.

For any userland communication, the call of the corresponding function (e.g starpu\_mpi\_isend()) will result in the creation of a StarPU-MPI request, the function starpu\_data\_acquire\_cb() is then called to asynchronously request StarPU to fetch the data in main memory; when the data is ready and the corresponding buffer has already been received by MPI, it will be copied in the memory of the data, otherwise the request is stored in the *early requests list*. Sending requests are stored in the *ready requests list*.

While requests need to be processed, the StarPU-MPI progression thread does the following:

- 1. it polls the *ready requests list*. For all the ready requests, the appropriate function is called to post the corresponding MPI call. For example, an initial call to starpu\_mpi\_isend() will result in a call to MPI\_Isend. If the request is marked as detached, the request will then be added in the *detached requests list*.
- 2. it posts a MPI\_Irecv() to retrieve a data envelope.

- 3. it polls the *detached requests list*. For all the detached requests, it tests its completion of the MPI request by calling MPI\_Test. On completion, the data handle is released, and if a callback was defined, it is called.
- 4. finally, it checks if a data envelope has been received. If so, if the data envelope matches a request in the *early requests list* (i.e the request has already been posted by the application), the corresponding MPI call is posted (similarly to the first step above).

If the data envelope does not match any application request, a temporary handle is created to receive the data, a StarPU-MPI request is created and added into the *ready requests list*, and thus will be processed in the first step of the next loop.

Communication gives the list of all the point to point communications defined in StarPU-MPI.

# 17.3 Exchanging User Defined Data Interface

New data interfaces defined as explained in Defining A New Data Interface can also be used within StarPU-M-PI and exchanged between nodes. Two functions needs to be defined through the type starpu\_data\_interface\_ops. The function starpu\_data\_interface\_ops::pack\_data takes a handle and returns a contiguous memory buffer allocated with starpu\_malloc\_flags(ptr, size, 0) along with its size where data to be conveyed to another node should be copied. The reversed operation is implemented in the function starpu\_data\_interface\_ops::unpack\_data which takes a contiguous memory buffer and recreates the data handle.

```
static int complex_pack_data(starpu_data_handle_t handle,
     unsigned node, void **ptr, ssize t *count)
  STARPU_ASSERT(starpu_data_test_if_allocated_on_node(handle, node
  struct starpu_complex_interface *complex interface =
    (struct starpu_complex_interface *) starpu_data_get_interface_on_node
      (handle, node);
  *count = complex_get_size(handle);
  starpu_malloc_flags(ptr, *count, 0);
 memcpy(*ptr, complex_interface->real, complex_interface->nx*sizeof(double));
 memcpy(*ptr+complex_interface->nx*sizeof(double), complex_interface->
      imaginary,
        complex_interface->nx*sizeof(double));
 return 0;
static int complex_unpack_data(starpu_data_handle_t handle,
      unsigned node, void *ptr, size_t count)
  STARPU_ASSERT(starpu_data_test_if_allocated_on_node(handle, node
  struct starpu complex interface *complex interface =
    (struct starpu_complex_interface *) starpu_data_get_interface_on_node
      (handle, node);
 memcpy(complex_interface->real, ptr, complex_interface->nx*sizeof(double));
 memcpy(complex_interface->imaginary, ptr+complex_interface->nx*sizeof(double)
        complex_interface->nx*sizeof(double));
  return 0;
}
static struct starpu data interface ops
     interface complex ops =
  .pack_data = complex_pack_data,
  .unpack_data = complex_unpack_data
```

Instead of defining pack and unpack operations, users may want to attach a MPI type to their user defined data interface. The function <a href="mailto:starpu\_mpi\_datatype\_register">starpu\_mpi\_datatype\_register</a>() allows to do so. This function takes 3 parameters: the data handle for which the MPI datatype is going to be defined, a function's pointer that will create the MPI datatype, and a function's pointer that will free the MPI datatype.

114 MPI Support

The functions to create and free the MPI datatype are defined as follows.

```
void starpu_complex_interface_datatype_allocate(starpu_data_handle_t
      handle, MPI_Datatype *mpi_datatype)
       int ret;
        int blocklengths[2];
        MPI_Aint displacements[2];
       MPI_Datatype types[2] = {MPI_DOUBLE, MPI_DOUBLE};
       struct starpu_complex_interface *complex_interface =
          (struct starpu_complex_interface *) starpu_data_get_interface_on_node
      (handle, STARPU_MAIN_RAM);
       {\tt MPI\_Address\,(complex\_interface,\ displacements);}
        MPI_Address(&complex_interface->imaginary, displacements+1);
       displacements[1] -= displacements[0];
displacements[0] = 0;
       blocklengths[0] = complex_interface->nx;
        blocklengths[1] = complex_interface->nx;
       ret = MPI_Type_create_struct(2, blocklengths, displacements, types,
      mpi_datatype);
        STARPU_ASSERT_MSG(ret == MPI_SUCCESS, "
      MPI_Type_contiguous failed");
        ret = MPI_Type_commit(mpi_datatype);
        STARPU_ASSERT_MSG(ret == MPI_SUCCESS, "MPI_Type_commit
      failed");
}
void starpu_complex_interface_datatype_free(MPI_Datatype *mpi_datatype)
        MPI_Type_free(mpi_datatype);
}
```

Note that it is important to make sure no communication is going to occur before the function <a href="mailto:starpu\_mpi\_datatype\_register">starpu\_mpi\_datatype\_register</a>() is called. That would produce an undefined result as the data may be received before the function is called, and so the MPI datatype would not be known by the StarPU-MPI communication engine, and the data would be processed with the pack and unpack operations.

# 17.4 MPI Insert Task Utility

To save the programmer from having to explicit all communications, StarPU provides an "MPI Insert Task Utility". The principe is that the application decides a distribution of the data over the MPI nodes by allocating it and notifying StarPU of that decision, i.e. tell StarPU which MPI node "owns" which data. It also decides, for each handle, an MPI tag which will be used to exchange the content of the handle. All MPI nodes then process the whole task graph, and StarPU automatically determines which node actually execute which task, and trigger the required MPI transfers.

The list of functions is described in MPI Insert Task.

Here an stencil example showing how to use <a href="starpu\_mpi\_task\_insert">starpu\_mpi\_task\_insert</a>(). One first needs to define a distribution function which specifies the locality of the data. Note that the data needs to be registered to MPI by calling <a href="starpu\_mpi\_data\_register">starpu\_mpi\_data\_register</a>(). This function allows to set the distribution information and the MPI tag which should be used when communicating the data. It also allows to automatically clear the MPI communication cache when unregistering the data.

```
/* Returns the MPI node number where data is */
int my_distrib(int x, int y, int nb_nodes) {
    /* Block distrib */
    return ((int)(x / sqrt(nb_nodes) + (y / sqrt(nb_nodes)) * sqrt(nb_nodes))) %
        nb_nodes;

    // /* Other examples useful for other kinds of computations */
    // /* / distrib */
    // return (x+y) % nb_nodes;

    // /* Block cyclic distrib */
    // unsigned side = sqrt(nb_nodes);
    // return x % side + (y % side) * size;
}
```

Now the data can be registered within StarPU. Data which are not owned but will be needed for computations can be registered through the lazy allocation mechanism, i.e. with a home\_node set to -1. StarPU will automatically allocate the memory when it is used for the first time.

One can note an optimization here (the else if test): we only register data which will be needed by the tasks that we will execute.

```
unsigned matrix[X][Y];
starpu_data_handle_t data_handles[X][Y];
for(x = 0; x < X; x++)  {
    for (y = 0; y < Y; y++) {
        int mpi_rank = my_distrib(x, y, size);
        if (mpi_rank == my_rank)
            /* Owning data */
            starpu variable data register(&
      data_handles[x][y], STARPU_MAIN_RAM,
                                            (uintptr_t)&(matrix[x][y]), sizeof(
        else if (my_rank == my_distrib(x+1, y, size) || my_rank == my_distrib(x
      -1, y, size)
              \mid \mid my_rank == my_distrib(x, y+1, size) \mid \mid my_rank == my_distrib(x
      , y-1, size))
              \star I don't own that index, but will need it for my computations \star/
            starpu_variable_data_register(&
      data_handles[x][y], -1,
                                            (uintptr_t) NULL, sizeof(unsigned));
            /* I know it's useless to allocate anything for this */
            data_handles[x][y] = NULL;
        if (data_handles[x][y]) {
            starpu_mpi_data_register(data_handles[x][y]
        x*X+y, mpi_rank);
    }
}
```

Now starpu\_mpi\_task\_insert() can be called for the different steps of the application.

I.e. all MPI nodes process the whole task graph, but as mentioned above, for each task, only the MPI node which owns the data being written to (here,  $data_handles[x][y]$ ) will actually run the task. The other MPI nodes will automatically send the required data.

This can be a concern with a growing number of nodes. To avoid this, the application can prune the task for loops according to the data distribution, so as to only submit tasks on nodes which have to care about them (either to execute them, or to send the required data).

A way to do some of this quite easily can be to just add an if like this:

116 MPI Support

This permits to drop the cost of function call argument passing and parsing.

If the my\_distrib function can be inlined by the compiler, the latter can improve the test.

If the size can be made a compile-time constant, the compiler can considerably improve the test further.

If the distribution function is not too complex and the compiler is very good, the latter can even optimize the for loops, thus dramatically reducing the cost of task submission.

A function starpu\_mpi\_task\_build() is also provided with the aim to only construct the task structure. All MPI nodes need to call the function, only the node which is to execute the task will return a valid task structure, others will return NULL. That node must submit that task. All nodes then need to call the function starpu\_mpi\_task\_post\_build() – with the same list of arguments as starpu\_mpi\_task\_build() – to post all the necessary data communications.

#### 17.5 MPI cache support

StarPU-MPI automatically optimizes duplicate data transmissions: if an MPI node B needs a piece of data D from MPI node A for several tasks, only one transmission of D will take place from A to B, and the value of D will be kept on B as long as no task modifies D.

If a task modifies D, B will wait for all tasks which need the previous value of D, before invalidating the value of D. As a consequence, it releases the memory occupied by D. Whenever a task running on B needs the new value of D, allocation will take place again to receive it.

Since tasks can be submitted dynamically, StarPU-MPI can not know whether the current value of data D will again be used by a newly-submitted task before being modified by another newly-submitted task, so until a task is submitted to modify the current value, it can not decide by itself whether to flush the cache or not. The application can however explicitly tell StarPU-MPI to flush the cache by calling starpu\_mpi\_cache\_flush() or starpu\_mpi\_cache\_flush\_all\_data(), for instance in case the data will not be used at all any more (see for instance the cholesky example in mpi/examples/matrix\_decomposition), or at least not in the close future. If a newly-submitted task actually needs the value again, another transmission of D will be initiated from A to B. A mere starpu\_mpi\_cache\_flush\_all\_data() can for instance be added at the end of the whole algorithm, to express that no data will be reused after that (or at least that it is not interesting to keep them in cache). It may however be interesting to add fine-graph starpu\_mpi\_cache\_flush() calls during the algorithm; the effect for the data deallocation will be the same, but it will additionally release some pressure from the StarPU-MPI cache hash table during task submission.

The whole caching behavior can be disabled thanks to the STARPU\_MPI\_CACHE environment variable. The variable STARPU\_MPI\_CACHE\_STATS can be set to 1 to enable the runtime to display messages when data are added or removed from the cache holding the received data.

17.6 MPI Data migration 117

# 17.6 MPI Data migration

The application can dynamically change its mind about the data distribution, to balance the load over MPI nodes for instance. This can be done very simply by requesting an explicit move and then change the registered rank. For instance, we here switch to a new distribution function my\_distrib2: we first register any data that wasn't registered already and will be needed, then migrate the data, and register the new location.

```
for (x = 0; x < X; x++) {
    for (y = 0; y < Y; y++) {
   int mpi_rank = my_distrib2(x, y, size);
        if (!data_handles[x][y] && (mpi_rank == my_rank
               || my_rank == my_distrib(x+1, y, size) || my_rank == my_distrib(x
      -1, y, size)
               || my_rank == my_distrib(x, y+1, size) || my_rank == my_distrib(x
      , y-1, size)))
             /* Register newly-needed data */
             starpu_variable_data_register(&
      data_handles[x][y], -1,
                                             (uintptr_t) NULL, sizeof(unsigned));
        if (data_handles[x][y]) {
             /\star Migrate the data \star/
             starpu_mpi_get_data_on_node_detached
      (MPI_COMM_WORLD, data_handles[x][y], mpi_rank, NULL, NULL);
              \star And register the new rank of the matrix \star/
             starpu_mpi_data_set_rank(data_handles[x][y]
      , mpi_rank);
    }
}
```

From then on, further tasks submissions will use the new data distribution, which will thus change both MPI communications and task assignments.

Very importantly, since all nodes have to agree on which node owns which data so as to determine MPI communications and task assignments the same way, all nodes have to perform the same data migration, and at the same point among task submissions. It thus does not require a strict synchronization, just a clear separation of task submissions before and after the data redistribution.

Before data unregistration, it has to be migrated back to its original home node (the value, at least), since that is where the user-provided buffer resides. Otherwise the unregistration will complain that it does not have the latest value on the original home node.

```
for(x = 0; x < X; x++) {
    for (y = 0; y < Y; y++) {
        if (data_handles[x][y]) {
            int mpi_rank = my_distrib(x, y, size);
            /* Get back data to original place where the user-provided buffer
        is. */
            starpu_mpi_get_data_on_node_detached
        (MPI_COMM_WORLD, data_handles[x][y], mpi_rank, NULL, NULL);
            /* And unregister it */
            starpu_data_unregister(data_handles[x][y]);
        }
}</pre>
```

# 17.7 MPI Collective Operations

The functions are described in MPI Collective Operations.

118 MPI Support

```
data_handles = malloc(nblocks*sizeof(starpu_data_handle_t
for (x = 0; x < nblocks; x++)
    int mpi_rank = my_distrib(x, nodes);
    if (rank == root) {
    starpu_vector_data_register(&data_handles[x])
      , STARPU_MAIN_RAM, (uintptr_t)vector[x],
                                       blocks_size, sizeof(float));
    else if ((mpi_rank == rank) || ((rank == mpi_rank+1 || rank == mpi_rank-1))
      ) {    /* I own that index, or i will need it for my computations */  
        starpu_vector_data_register(&data_handles[x]
      , -1, (uintptr_t) NULL,
                                      block_size, sizeof(float));
    else {
    /* I know it's useless to allocate anything for this */
    if (data_handles[x]) {
        starpu\_mpi\_data\_register(data\_handles[x], \ x*
     nblocks+y, mpi_rank);
/\star Scatter the matrix among the nodes \star/
starpu_mpi_scatter_detached(data_handles, nblocks,
    root, MPI_COMM_WORLD);
/* Calculation */
for (x = 0; x < nblocks; x++) {
    if (data_handles[x]) {
        int owner = starpu_data_get_rank(data_handles[x]);
if (owner == rank) {
             starpu_task_insert(&cl, STARPU_RW,
      data_handles[x], 0);
    }
}
/\star Gather the matrix on main node \star/
starpu_mpi_gather_detached(data_handles, nblocks, 0,
      MPI_COMM_WORLD);
```

# **FFT Support**

StarPU provides libstarpufft, a library whose design is very similar to both fftw and cufft, the difference being that it takes benefit from both CPUs and GPUs. It should however be noted that GPUs do not have the same precision as CPUs, so the results may different by a negligible amount.

Different precisions are available, namely float, double and long double precisions, with the following fftw naming conventions:

- double precision structures and functions are named e.g. starpufft\_execute()
- float precision structures and functions are named e.g. starpufftf\_execute()
- long double precision structures and functions are named e.g. starpufftl\_execute()

The documentation below is given with names for double precision, replace starpufft\_ with starpufftf\_ or starpufftl\_ as appropriate.

Only complex numbers are supported at the moment.

The application has to call starpu\_init() before calling starpufft functions.

Either main memory pointers or data handles can be provided.

- To provide main memory pointers, use starpufft\_start() or starpufft\_execute(). Only one FFT can be performed at a time, because StarPU will have to register the data on the fly. In the starpufft\_start() case, starpufft\_cleanup() needs to be called to unregister the data.
- To provide data handles (which is preferrable), use starpufft\_start\_handle() (preferred) or starpufft\_execute\_handle(). Several FFTs tasks can be submitted for a given plan, which permits e.g. to start a series of FFT with just one plan. starpufft\_start\_handle() is preferrable since it does not wait for the task completion, and thus permits to enqueue a series of tasks.

All functions are defined in FFT Support.

## 18.1 Compilation

The flags required to compile or link against the FFT library are accessible with the following commands:

```
$ pkg-config --cflags starpufft-1.2 # options for the compiler
$ pkg-config --libs starpufft-1.2 # options for the linker
```

Also pass the option -static if the application is to be linked statically.

120 **FFT Support** 

# **MIC/SCC Support**

# 19.1 Compilation

SCC support just needs the presence of the RCCE library.

MIC Xeon Phi support actually needs two compilations of StarPU, one for the host and one for the device. The PATH environment variable has to include the path to the cross-compilation toolchain, for instance /usr/linux-klom-4.7/bin The script mic-configure can then be used to achieve the two compilations: it basically calls configure as appropriate from two new directories: build\_mic and build\_host. make and make install can then be used as usual and will recurse into both directories. If different configuration options are needed for the host and for the mic, one can use -with-host-param=-with-fxt for instance to specify the -with-fxt option for the host only, or -with-mic-param=-with-fxt for the mic only.

## 19.2 Porting Applications To MIC Xeon Phi / SCC

The simplest way to port an application to MIC Xeon Phi or SCC is to set the field starpu\_codelet::cpu\_funcs\_name, to provide StarPU with the function name of the CPU implementation. StarPU will thus simply use the existing CPU implementation (cross-rebuilt in the MIC Xeon Phi case). The functions have to be globally-visible (i.e. not static) for StarPU to be able to look them up, and -rdynamic must be passed to gcc (or -export-dynamic to ld) so that symbols of the main program are visible.

For SCC execution, the function starpu\_initialize() also has to be used instead of starpu\_init(), so as to pass argc and argv.

### 19.3 Launching Programs

SCC programs are started through RCCE.

MIC programs are started from the host. StarPU automatically starts the same program on MIC devices. It however needs to get the MIC-cross-built binary. It will look for the file given by the environment variable ST-ARPU\_MIC\_SINK\_PROGRAM\_NAME or in the directory given by the environment variable STARPU\_MIC\_SINK\_PROGRAM\_PATH, or in the field starpu\_conf::mic\_sink\_program\_path. It will also look in the current directory for the same binary name plus the suffix -mic or \_mic.

The testsuite can be started by simply running make check from the top directory. It will recurse into both build\_host to run tests with only the host, and

122 MIC/SCC Support

into build\_mic to run tests with both the host and the MIC devices. Single tests with the host and the MIC can be run by starting ./loader-cross.sh ./the\_test from build\_mic/tests.

# **C** Extensions

When GCC plug-in support is available, StarPU builds a plug-in for the GNU Compiler Collection (GCC), which defines extensions to languages of the C family (C, C++, Objective-C) that make it easier to write StarPU code. This feature is only available for GCC 4.5 and later; it is known to work with GCC 4.5, 4.6, and 4.7. You may need to install a specific -dev package of your distro, such as gcc-4.6-plugin-dev on Debian and derivatives. In addition, the plug-in's test suite is only run when GNU Guile (http://www.gnu.org/software/guile/) is found at configure-time. Building the GCC plug-in can be disabled by configuring with --disable-gcc-extensions.

Those extensions include syntactic sugar for defining tasks and their implementations, invoking a task, and manipulating data buffers. Use of these extensions can be made conditional on the availability of the plug-in, leading to valid C sequential code when the plug-in is not used (Using C Extensions Conditionally).

When StarPU has been installed with its GCC plug-in, programs that use these extensions can be compiled this way:

```
$ gcc -c -fplugin='pkg-config starpu-1.2 --variable=gccplugin' foo.c
```

When the plug-in is not available, the above pkg-config command returns the empty string.

In addition, the -fplugin-arg-starpu-verbose flag can be used to obtain feedback from the compiler as it analyzes the C extensions used in source files.

This section describes the C extensions implemented by StarPU's GCC plug-in. It does not require detailed knowledge of the StarPU library.

Note: this is still an area under development and subject to change.

# 20.1 Defining Tasks

The StarPU GCC plug-in views tasks as "extended" C functions:

- tasks may have several implementations—e.g., one for CPUs, one written in OpenCL, one written in CUDA;
- tasks may have several implementations of the same target—e.g., several CPU implementations;
- when a task is invoked, it may run in parallel, and StarPU is free to choose any of its implementations.

Tasks and their implementations must be declared. These declarations are annotated with attributes (http-://gcc.gnu.org/onlinedocs/gcc/Attribute-Syntax.html#Attribute-Syntax): the declaration of a task is a regular C function declaration with an additional task attribute, and task implementations are declared with a task\_implementation attribute.

The following function attributes are provided:

124 C Extensions

task Declare the given function as a StarPU task. Its return type must be void. When a function declared as task has a user-defined body, that body is interpreted as the implicit definition of the task's CPU implementation (see example below). In all cases, the actual definition of a task's body is automatically generated by the compiler.

Under the hood, declaring a task leads to the declaration of the corresponding <code>codelet</code> (Codelet and Tasks). If one or more task implementations are declared in the same compilation unit, then the codelet and the function itself are also defined; they inherit the scope of the task.

Scalar arguments to the task are passed by value and copied to the target device if need be—technically, they are passed as the buffer starpu\_task::cl\_arg (Codelet and Tasks).

Pointer arguments are assumed to be registered data buffers—the handles argument of a task (starpu\_task::handles); const-qualified pointer arguments are viewed as read-only buffers (STARPU\_R), and non-const-qualified buffers are assumed to be used read-write (STARPU\_RW). In addition, the output type attribute can be as a type qualifier for output pointer or array parameters (STARPU\_W).

task\_implementation (target, task) Declare the given function as an implementation of task to run on target. target must be a string, currently one of "cpu", "opencl", or "cuda".

Here is an example:

```
#define __output __attribute__ ((output))
static void matmul (const float *A, const float *B,
                     output float *C.
                    unsigned nx, unsigned ny, unsigned nz)
   _attribute__ ((task));
static void matmul_cpu (const float *A, const float *B,
                          _output float *C,
                        unsigned nx, unsigned ny, unsigned nz)
   _attribute__ ((task_implementation ("cpu", matmul)));
static void
\verb|matmul_cpu| (const float *A, const float *B, \__output float *C,
           unsigned nx, unsigned ny, unsigned nz)
 unsigned i, j, k;
  for (j = 0; j < ny; j++)
    for (i = 0; i < nx; i++)
       for (k = 0; k < nz; k++)
         C[j * nx + i] += A[j * nz + k] * B[k * nx + i];
```

A matmult task is defined; it has only one implementation, matmult\_cpu, which runs on the CPU. Variables A and B are input buffers, whereas C is considered an input/output buffer.

For convenience, when a function declared with the task attribute has a user-defined body, that body is assumed to be that of the CPU implementation of a task, which we call an implicit task CPU implementation. Thus, the above snippet can be simplified like this:

Use of implicit CPU task implementations as above has the advantage that the code is valid sequential code when StarPU's GCC plug-in is not used (Using C Extensions Conditionally).

CUDA and OpenCL implementations can be declared in a similar way:

The CUDA and OpenCL implementations typically either invoke a kernel written in CUDA or OpenCL (for similar code, CUDA Kernel, and OpenCL Kernel), or call a library function that uses CUDA or OpenCL under the hood, such as CUBLAS functions:

A task can be invoked like a regular C function:

This leads to an asynchronous invocation, whereby matmult's implementation may run in parallel with the continuation of the caller.

The next section describes how memory buffers must be handled in StarPU-GCC code. For a complete example, see the qcc-pluqin/examples directory of the source distribution, and Vector Scaling Using the C Extension.

# 20.2 Initialization, Termination, and Synchronization

The following pragmas allow user code to control StarPU's life time and to synchronize with tasks.

**#pragma starpu initialize** Initialize StarPU. This call is compulsory and is *never* added implicitly. One of the reasons this has to be done explicitly is that it provides greater control to user code over its resource usage.

**#pragma starpu shutdown** Shut down StarPU, giving it an opportunity to write profiling info to a file on disk, for instance (Off-line Performance Feedback).

#pragma starpu wait Wait for all task invocations to complete, as with starpu\_task\_wait\_for\_all().

### 20.3 Registered Data Buffers

Data buffers such as matrices and vectors that are to be passed to tasks must be registered. Registration allows StarPU to handle data transfers among devices—e.g., transferring an input buffer from the CPU's main memory to a task scheduled to run a GPU (StarPU Data Management Library).

The following pragmas are provided:

126 C Extensions

- **#pragma starpu unregister ptr** Unregister the previously-registered memory area pointed to by ptr.

  As a side-effect, ptr points to a valid copy in main memory.
- **#pragma starpu acquire ptr** Acquire in main memory an up-to-date copy of the previously-registered memory area pointed to by ptr, for read-write access.
- #pragma starpu release ptr Release the previously-register memory area pointed to by ptr, making it available to the tasks.

Additionally, the following attributes offer a simple way to allocate and register storage for arrays:

- registered This attributes applies to local variables with an array type. Its effect is to automatically register the array's storage, as per #pragma starpu register. The array is automatically unregistered when the variable's scope is left. This attribute is typically used in conjunction with the heap\_allocated attribute, described below.
- heap\_allocated This attributes applies to local variables with an array type. Its effect is to automatically allocate the array's storage on the heap, using <a href="mailto:starpu\_malloc">starpu\_malloc</a>() under the hood. The heap-allocated array is automatically freed when the variable's scope is left, as with automatic variables.

The following example illustrates use of the heap\_allocated attribute:

```
extern void cholesky(unsigned nblocks, unsigned size,
                    float mat[nblocks][nblocks][size])
  __attribute__ ((task));
int
main (int argc, char *argv[])
#pragma starpu initialize
  /* ... */
  int nblocks, size;
  parse_args (&nblocks, &size);
  /\star Allocate an array of the required size on the heap,
     and register it.
    float matrix[nblocks][nblocks][size]
      __attribute__ ((heap_allocated, registered));
    cholesky (nblocks, size, matrix);
#pragma starpu wait
    /* MATRIX is automatically unregistered & freed here. */
#pragma starpu shutdown
  return EXIT_SUCCESS;
```

## 20.4 Using C Extensions Conditionally

The C extensions described in this chapter are only available when GCC and its StarPU plug-in are in use. Yet, it is possible to make use of these extensions when they are available—leading to hybrid CPU/GPU code—and discard them when they are not available—leading to valid sequential code.

To that end, the GCC plug-in defines the C preprocessor macro — STARPU\_GCC\_PLUGIN — when it is being used. When defined, this macro expands to an integer denoting the version of the supported C extensions.

The code below illustrates how to define a task and its implementations in a way that allows it to be compiled without the GCC plug-in:

```
/* This program is valid, whether or not StarPU's GCC plug-in
   is being used. */
#include <stdlib.h>
/* The attribute below is ignored when GCC is not used. */
static void matmul (const float *A, const float *B, float * C,
                     unsigned nx, unsigned ny, unsigned nz)
  __attribute__ ((task));
static void
matmul (const float *A, const float *B, float * C,
        unsigned nx, unsigned ny, unsigned nz)
  /\star Code of the CPU kernel here...
#ifdef STARPU_GCC_PLUGIN
/* Optional OpenCL task implementation. */
static void matmul_opencl (const float *A, const float *B, float * C,
   unsigned nx, unsigned ny, unsigned nz)
_attribute__ ((task_implementation ("opencl", matmul)));
static void
matmul_opencl (const float *A, const float *B, float * C,
                unsigned nx, unsigned ny, unsigned nz)
 /* Code that invokes the OpenCL kernel here... */
#endif
int
main (int argc, char *argv[])
  /\star The pragmas below are simply ignored when StarPU-GCC
     is not used. */
#pragma starpu initialize
  float A[123][42][7], B[123][42][7], C[123][42][7];
#pragma starpu register A
#pragma starpu register B
#pragma starpu register C
  /* When StarPU-GCC is used, the call below is asynchronous;
 otherwise, it is synchronous. */
matmul ((float *) A, (float *) B, (float *) C, 123, 42, 7);
#pragma starpu wait
#pragma starpu shutdown
  return EXIT_SUCCESS;
```

The above program is a valid StarPU program when StarPU's GCC plug-in is used; it is also a valid sequential program when the plug-in is not used.

Note that attributes such as task as well as starpu pragmas are simply ignored by GCC when the StarPU plug-in is not loaded. However, gcc -Wall emits a warning for unknown attributes and pragmas, which can be inconvenient. In addition, other compilers may be unable to parse the attribute syntax (In practice, Clang and several proprietary compilers implement attributes.), so you may want to wrap attributes in macros like this:



# **SOCL OpenCL Extensions**

SOCL is an OpenCL implementation based on StarPU. It gives a unified access to every available OpenCL device: applications can now share entities such as Events, Contexts or Command Queues between several OpenCL implementations.

In addition, command queues that are created without specifying a device provide automatic scheduling of the submitted commands on OpenCL devices contained in the context to which the command queue is attached.

Note: this is still an area under development and subject to change.

When compiling StarPU, SOCL will be enabled if a valid OpenCL implementation is found on your system. To be able to run the SOCL test suite, the environment variable SOCL\_OCL\_LIB\_OPENCL needs to be defined to the location of the file libOpenCL.so of the OCL ICD implementation. You should for example add the following line in your file .bashrc

```
export SOCL_OCL_LIB_OPENCL=/usr/lib/x86_64-linux-gnu/libOpenCL.so
```

You can then run the test suite in the directory <code>socl/examples</code>.

\$

The environment variable OCL\_ICD\_VENDORS has to point to the directory where the socl.icd ICD file is installed. When compiling StarPU, the files are in the directory <code>socl/vendors</code>. With an installed version of StarPU, the files are installed in the directory <code>sprefix/share/starpu/opencl/vendors</code>.

To run the tests by hand, you have to call for example,

```
$ LD_PRELOAD=$SOCL_OCL_LIB_OPENCL OCL_ICD_VENDORS=socl/vendors/ socl/examples/clinfo/clinfo
Number of platforms: 2
Plaform Profile: FULL_PROFILE
Plaform Version: OpenCL 1.1 CUDA 4.2.1
Plaform Name: NVIDIA CUDA
Plaform Vendor: NVIDIA Corporation
Plaform Extensions: cl_khr_byte_addressable_store cl_khr_icd cl_khr_gl_sharing cl_nv_compiler_options cl_nv_
Plaform Profile: FULL_PROFILE
Plaform Version: OpenCL 1.0 SOCL Edition (0.1.0)
Plaform Name: SOCL Platform
Plaform Vendor: INRIA
Plaform Extensions: cl_khr_icd
....
```

To enable the use of CPU cores via OpenCL, one can set the STARPU\_OPENCL\_ON\_CPUS environment variable to 1 and STARPU\_NCPUS to 0 (to avoid using CPUs both via the OpenCL driver and the normal CPU driver).

# **SimGrid Support**

StarPU can use Simgrid in order to simulate execution on an arbitrary platform.

# 22.1 Preparing your application for simulation.

There are a few technical details which need to be handled for an application to be simulated through Simgrid.

If the application uses <code>gettimeofday</code> to make its performance measurements, the real time will be used, which will be bogus. To get the simulated time, it has to use <code>starpu\_timing\_now()</code> which returns the virtual timestamp in us.

For some technical reason, the application's .c file which contains main() has to be recompiled with starpu\_simgrid\_wrap.h, which in the simgrid case will # define main() into starpu\_main(), and it is libstarpu which will provide the real main() and will call the application's main().

To be able to test with crazy data sizes, one may want to only allocate application data if STARPU\_SIMGRID is not defined. Passing a NULL pointer to starpu\_data\_register functions is fine, data will never be read/written to by StarPU in Simgrid mode anyway.

To be able to run the application with e.g. CUDA simulation on a system which does not have CUDA installed, one can fill the cuda\_funcs with (void\*)1, to express that there is a CUDA implementation, even if one does not actually provide it. StarPU will never actually run it in Simgrid mode anyway.

#### 22.2 Calibration

The idea is to first compile StarPU normally, and run the application, so as to automatically benchmark the bus and the codelets.

```
$ ./configure && make
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
[starpu][_starpu_load_history_based_model] Warning: model matvecmult
   is not calibrated, forcing calibration for this run. Use the
    STARPU_CALIBRATE environment variable to control this.
$ ...
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
TEST PASSED
```

Note that we force to use the scheduler dmda to generate performance models for the application. The application may need to be run several times before the model is calibrated.

132 SimGrid Support

#### 22.3 Simulation

Then, recompile StarPU, passing --enable-simgrid to ./configure.

```
$ ./configure --enable-simgrid
```

To specify the location of SimGrid, you can either set the environment variables SIMGRID\_CFLAGS and SIMG-RID\_LIBS, or use the configure options --with-simgrid-dir, --with-simgrid-include-dir and --with-simgrid-lib-dir, for example

```
$ ./configure --with-simgrid-dir=/opt/local/simgrid
```

You can then re-run the application.

```
$ make
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
TEST FAILED !!!
```

It is normal that the test fails: since the computation are not actually done (that is the whole point of simgrid), the result is wrong, of course.

If the performance model is not calibrated enough, the following error message will be displayed

```
$ STARPU_SCHED=dmda ./examples/matvecmult/matvecmult
[starpu][_starpu_load_history_based_model] Warning: model matvecmult
    is not calibrated, forcing calibration for this run. Use the
    STARPU_CALIBRATE environment variable to control this.
[starpu][_starpu_simgrid_execute_job][assert failure] Codelet
    matvecmult does not have a perfmodel, or is not calibrated enough
```

The number of devices can be chosen as usual with STARPU\_NCPU, STARPU\_NCUDA, and STARPU\_NOPENCL, and the amount of GPU memory with STARPU\_LIMIT\_CUDA\_MEM, STARPU\_LIMIT\_CUDA\_devid\_MEM, STARPU\_LIMIT\_OPENCL\_MEM, and STARPU\_LIMIT\_OPENCL\_devid\_MEM.

#### 22.4 Simulation On Another Machine

The simgrid support even permits to perform simulations on another machine, your desktop, typically. To achieve this, one still needs to perform the Calibration step on the actual machine to be simulated, then copy them to your desktop machine (the \$STARPU\_HOME/.starpu directory). One can then perform the Simulation step on the desktop machine, by setting the environment variable STARPU\_HOSTNAME to the name of the actual machine, to make StarPU use the performance models of the simulated machine even on the desktop machine.

If the desktop machine does not have CUDA or OpenCL, StarPU is still able to use simgrid to simulate execution with CUDA/OpenCL devices, but the application source code will probably disable the CUDA and OpenCL codelets in thatcd sc case. Since during simgrid execution, the functions of the codelet are actually not called, one can use dummy functions such as the following to still permit CUDA or OpenCL execution:

### 22.5 Simulation examples

StarPU ships a few performance models for a couple of systems: attila and mirage. See section Simulated benchmarks for the details.

#### 22.6 simulation

The simulation can be tweaked, to be able to tune it between a very accurate simulation and a very simple simulation (which is thus close to scheduling theory results), see the STARPU\_SIMGRID\_CUDA\_MALLOC\_COST and STARPU\_SIMGRID\_CUDA\_QUEUE\_COST environment variables.

22.7 applications 133

## 22.7 applications

StarPU-MPI applications can also be run in simgrid mode. It needs to be compiled with smpicc, and run using the starpu smpirun script, for instance:

```
$ STARPU_SCHED=dmda starpu_smpirun -platform cluster.xml -hostfile hostfile ./mpi/tests/pingpong
```

Where cluster.xml is a Simgrid-MPI platform description, and hostfile the list of MPI nodes to be used. StarPU currently only supports homogeneous MPI clusters: for each MPI node it will just replicate the architecture referred by STARPU\_HOSTNAME.

# 22.8 applications

By default, simgrid uses its own implementation of threads, which prevents gdb from being able to inspect stacks of all threads. To be able to fully debug an application running with simgrid, pass the -cfg=contexts/factory-:thread option to the application, to make simgrid use system threads, which gdb will be able to manipulate as usual.

SimGrid Support 134

# **OpenMP Runtime Support**

StarPU provides the necessary routines and support to implement an OpenMP (http://www.openmp.org/) runtime compliant with the revision 3.1 of the language specification, and compliant with the task-related data dependency functionalities introduced in the revision 4.0 of the language. This StarPU OpenMP Runtime Support (SORS) has been designed to be targetted by OpenMP compilers such as the Klang-OMP compiler. Most supported OpenMP directives can both be implemented inline or as outlined functions.

All functions are defined in OpenMP Runtime Support.

# 23.1 Implementation Details and Specificities

### 23.1.1 Main Thread

When using the SORS, the main thread gets involved in executing OpenMP tasks just like every other threads, in order to be compliant with the specification execution model. This contrasts with StarPU's usual execution model where the main thread submit tasks but does not take part in executing them.

#### 23.1.2 Extended Task Semantics

The semantics of tasks generated by the SORS are extended with respect to regular StarPU tasks in that SORS' tasks may block and be preempted by SORS call, whereas regular StarPU tasks cannot. SORS tasks may coexist with regular StarPU tasks. However, only the tasks created using SORS API functions inherit from extended semantics.

### 23.2 Configuration

The SORS can be compiled into libstarpu through the configure option --enable-openmp. Conditional compiled source codes may check for the availability of the OpenMP Runtime Support by testing whether the C preprocessor macro STARPU\_OPENMP is defined or not.

### 23.3 Initialization and Shutdown

The SORS needs to be executed/terminated by the starpu\_omp\_init() / starpu\_omp\_shutdown() instead of starpu\_init() / starpu\_shutdown(). This requirement is necessary to make sure that the main thread gets the proper execution environment to run OpenMP tasks. These calls will usually be performed by a compiler runtime. Thus, they can be executed from a constructor/destructor such as this:

```
static void omp_constructor(void)
{
    int ret = starpu_omp_init();
        STARPU_CHECK_RETURN_VALUE(ret, "
        starpu_omp_init");
}
__attribute__((destructor))
static void omp_destructor(void)
{
        starpu_omp_shutdown();
}

See Also
        starpu_omp_init()
        starpu_omp_shutdown()
```

# 23.4 Parallel Regions and Worksharing

The SORS provides functions to create OpenMP parallel regions as well as mapping work on participating workers. The current implementation does not provide nested active parallel regions: Parallel regions may be created recursively, however only the first level parallel region may have more than one worker. From an internal point-of-view, the SORS' parallel regions are implemented as a set of implicit, extended semantics StarPU tasks, following the execution model of the OpenMP specification. Thus the SORS' parallel region tasks may block and be preempted, by SORS calls, enabling constructs such as barriers.

#### 23.4.1 Parallel Regions

Parallel regions can be created with the function starpu\_omp\_parallel\_region() which accepts a set of attributes as parameter. The execution of the calling task is suspended until the parallel region completes. The field starpu\_omp\_parallel\_region\_attr::cl is a regular StarPU codelet. However only CPU codelets are supported for parallel regions. Here is an example of use:

#### See Also

```
struct starpu_omp_parallel_region_attr
starpu_omp_parallel_region()
```

#### 23.4.2 Parallel For

OpenMP for loops are provided by the starpu\_omp\_for() group of functions. Variants are available for inline or outlined implementations. The SORS supports static, dynamic, and guided loop scheduling clauses. The

auto scheduling clause is implemented as static. The runtime scheduling clause honors the scheduling mode selected through the environment variable OMP\_SCHEDULE or the starpu\_omp\_set\_schedule() function. For loops with the ordered clause are also supported. An implicit barrier can be enforced or skipped at the end of the worksharing construct, according to the value of the nowait parameter.

The canonical family of starpu\_omp\_for() functions provide each instance with the first iteration number and the number of iterations (possibly zero) to perform. The alternate family of starpu\_omp\_for\_alt() functions provide each instance with the (possibly empty) range of iterations to perform, including the first and excluding the last.

The family of starpu\_omp\_ordered() functions enable to implement OpenMP's ordered construct, a region with a parallel for loop that is guaranteed to be executed in the sequential order of the loop iterations.

```
void for_g(unsigned long long i, unsigned long long nb_i, void *arg)
         (void) arg;
         for (; nb_i > 0; i++, nb_i--)
                 array[i] = 1;
}
void parallel_region_f(void *buffers[], void *args)
         (void) buffers;
         (void) args;
      starpu_omp_for(for_g, NULL, NB_ITERS, CHUNK,
starpu_omp_sched_static, 0, 0);
See Also
    starpu omp for()
    starpu_omp_for_inline_first()
    starpu_omp_for_inline_next()
    starpu_omp_for_alt()
    starpu omp for inline first alt()
    starpu_omp_for_inline_next_alt()
    starpu_omp_ordered()
    starpu_omp_ordered_inline_begin()
    starpu omp ordered inline end()
```

#### 23.4.3 Sections

OpenMP sections worksharing constructs are supported using the set of starpu\_omp\_sections() variants. The general principle is either to provide an array of per-section functions or a single function that will redirect to execution to the suitable per-section functions. An implicit barrier can be enforced or skipped at the end of the worksharing construct, according to the value of the nowait parameter.

```
void parallel_region_f(void *buffers[], void *args)
{
     (void) buffers;
     (void) args;

     section_funcs[0] = f;
     section_funcs[1] = g;
     section_funcs[2] = h;
     section_funcs[3] = i;

     section_args[0] = arg_f;
     section_args[1] = arg_g;
     section_args[2] = arg_h;
     section_args[3] = arg_i;

     starpu_omp_sections(4, section_f, section_args, 0);
}

See Also

starpu_omp_sections()
    starpu_omp_sections_combined()
```

#### 23.4.4 Single

OpenMP single workharing constructs are supported using the set of starpu\_omp\_single() variants. An implicit barrier can be enforced or skipped at the end of the worksharing construct, according to the value of the nowait parameter.

```
void single_f(void *arg)
{
      (void) arg;
      pthread_t tid = pthread_self();
      int worker_id = starpu_worker_get_id();
      printf("[tid %p] task thread = %d -- single\n", (void *)tid, worker_id)
      ;
}

void parallel_region_f(void *buffers[], void *args)
{
      (void) buffers;
      (void) args;
      starpu_omp_single(single_f, NULL, 0);
}
```

The SORS also provides dedicated support for single sections with copyprivate clauses through the starpu-\_omp\_single\_copyprivate() function variants. The OpenMP master directive is supported as well using the starpu-\_omp\_master() function variants.

#### See Also

```
starpu_omp_master()
starpu_omp_master_inline()
starpu_omp_single()
starpu_omp_single_inline()
starpu_omp_single_copyprivate()
starpu_omp_single_copyprivate_inline_begin()
starpu_omp_single_copyprivate_inline_end()
```

#### 23.5 Tasks

The SORS implements the necessary support of OpenMP 3.1 and OpenMP 4.0's so-called explicit tasks, together with OpenMP 4.0's data dependency management.

#### 23.5.1 Explicit Tasks

Explicit OpenMP tasks are created with the SORS using the starpu\_omp\_task\_region() function. The implementation supports if, final, untied and mergeable clauses as defined in the OpenMP specification. Unless specified otherwise by the appropriate clause(s), the created task may be executed by any participating worker of the current parallel region.

The current SORS implementation requires explicit tasks to be created within the context of an active parallel region. In particular, an explicit task cannot be created by the main thread outside of a parallel region. Explicit OpenMP tasks created using <a href="mailto:starpu\_omp\_task\_region">starpu\_omp\_task\_region</a>() are implemented as StarPU tasks with extended semantics, and may as such be blocked and preempted by SORS routines.

The current SORS implementation supports recursive explicit tasks creation, to ensure compliance with the Open-MP specification. However, it should be noted that StarPU is not designed nor optimized for efficiently scheduling of recursive task applications.

The code below shows how to create 4 explicit tasks within a parallel region.

```
void task_region_g(void *buffers[], void *args)
{
          (void) buffers;
          (void) args;
```

23.5 Tasks 139

```
pthread tid = pthread_self();
        int worker_id = starpu_worker_get_id();
       printf("[tid %p] task thread = %d: explicit task \"g\"\n", (void *)tid,
      worker_id);
void parallel_region_f(void *buffers[], void *args)
        (void) buffers;
        (void) args;
       struct starpu_omp_task_region_attr attr;
       memset(&attr, 0, sizeof(attr));
       attr.cl.cpu_funcs[0] = task_region_g;
        attr.cl.where
                         = STARPU_CPU;
                             = 1;
       attr.if_clause
       attr.final clause
                             = 1;
       attr.untied clause
       attr.mergeable_clause = 0;
       starpu_omp_task_region(&attr);
       starpu_omp_task_region(&attr);
       starpu_omp_task_region(&attr);
       starpu_omp_task_region(&attr);
```

#### See Also

```
struct starpu_omp_task_region_attr
starpu_omp_task_region()
```

#### 23.5.2 Data Dependencies

The SORS implements inter-tasks data dependencies as specified in OpenMP 4.0. Data dependencies are expressed using regular StarPU data handles (starpu\_data\_handle\_t) plugged into the task's attr.cl codelet. The family of starpu\_vector\_data\_register() -like functions and the starpu\_data\_lookup() function may be used to register a memory area and to retrieve the current data handle associated with a pointer respectively. The testcase ./tests/openmp/task\_02.c gives a detailed example of using OpenMP 4.0 tasks dependencies with the SORS implementation.

Note: the OpenMP 4.0 specification only supports data dependencies between sibling tasks, that is tasks created by the same implicit or explicit parent task. The current SORS implementation also only supports data dependencies between sibling tasks. Consequently the behaviour is unspecified if dependencies are expressed beween tasks that have not been created by the same parent task.

#### 23.5.3 TaskWait and TaskGroup

The SORS implements both the taskwait and taskgroup OpenMP task synchronization constructs specified in OpenMP 4.0, with the starpu\_omp\_taskwait() and starpu\_omp\_taskgroup() functions respectively.

An example of starpu omp taskwait() use, creating two explicit tasks and waiting for their completion:

```
void task_region_g(void *buffers[], void *args)
         (void) buffers;
        (void) args;
        printf("Hello, World!\n");
}
void parallel region f(void *buffers[], void *args)
         (void) buffers;
         (void) args;
        struct starpu_omp_task_region_attr attr;
        memset(&attr, 0, sizeof(attr));
attr.cl.cpu_funcs[0] = task_region_g;
                                = STARPU_CPU;
        attr.cl.where
        attr.if clause
        attr.final_clause
        attr.untied_clause
        attr.mergeable_clause = 0;
        starpu_omp_task_region(&attr);
        starpu_omp_task_region(&attr);
        starpu_omp_taskwait();
```

An example of starpu\_omp\_taskgroup() use, creating a task group of two explicit tasks:

```
void task_region_g(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        printf("Hello, World!\n");
void taskgroup_f(void *arg)
        (void) arg;
        struct starpu_omp_task_region_attr attr;
        memset(&attr, 0, sizeof(attr));
        attr.cl.cpu_funcs[0] = task_region_g;
                             = STARPU_CPU;
        attr.cl.where
        attr.if clause
        attr.final clause
        attr.untied_clause
        attr.mergeable_clause = 0;
        starpu_omp_task_region(&attr);
        starpu_omp_task_region(&attr);
}
void parallel_region_f(void *buffers[], void *args)
        (void) buffers;
        (void) args;
        starpu_omp_taskgroup(taskgroup_f, (void *)NULL);
See Also
    starpu omp task region()
    starpu omp taskwait()
    starpu_omp_taskgroup()
    starpu_omp_taskgroup_inline_begin()
    starpu_omp_taskgroup_inline_end()
```

# 23.6 Synchronization Support

The SORS implements objects and method to build common OpenMP synchronization constructs.

#### 23.6.1 Simple Locks

The SORS Simple Locks are opaque starpu\_omp\_lock\_t objects enabling multiple tasks to synchronize with each others, following the Simple Lock constructs defined by the OpenMP specification. In accordance with such specification, simple locks may not by acquired multiple times by the same task, without being released in-between; otherwise, deadlocks may result. Codes requiring the possibility to lock multiple times recursively should use Nestable Locks (Nestable Locks). Codes NOT requiring the possibility to lock multiple times recursively should use Simple Locks as they incur less processing overhead than Nestable Locks.

#### See Also

```
starpu_omp_lock_t
starpu_omp_init_lock()
starpu_omp_destroy_lock()
starpu_omp_set_lock()
starpu_omp_unset_lock()
starpu_omp_test_lock()
```

#### 23.6.2 Nestable Locks

The SORS Nestable Locks are opaque starpu\_omp\_nest\_lock\_t objects enabling multiple tasks to synchronize with each others, following the Nestable Lock constructs defined by the OpenMP specification. In accordance with

such specification, nestable locks may by acquired multiple times recursively by the same task without deadlocking. Nested locking and unlocking operations must be well parenthesized at any time, otherwise deadlock and/or undefined behaviour may occur. Codes requiring the possibility to lock multiple times recursively should use Nestable Locks. Codes NOT requiring the possibility to lock multiple times recursively should use Simple Locks (Simple Locks) instead, as they incur less processing overhead than Nestable Locks.

#### See Also

```
starpu_omp_nest_lock_t
starpu_omp_init_nest_lock()
starpu_omp_destroy_nest_lock()
starpu_omp_set_nest_lock()
starpu_omp_unset_nest_lock()
starpu_omp_test_nest_lock()
```

#### 23.6.3 Critical Sections

The SORS implements support for OpenMP critical sections through the family of starpu\_omp\_critical functions. Critical sections may optionally be named. There is a single, common anonymous critical section. Mutual exclusion only occur within the scope of single critical section, either a named one or the anonymous one.

#### See Also

```
starpu_omp_critical()
starpu_omp_critical_inline_begin()
starpu_omp_critical_inline_end()
```

#### 23.6.4 Barriers

The SORS provides the starpu\_omp\_barrier() function to implement barriers over parallel region teams. In accordance with the OpenMP specification, the starpu\_omp\_barrier() function waits for every implicit task of the parallel region to reach the barrier and every explicit task launched by the parallel region to complete, before returning.

#### See Also

```
starpu_omp_barrier()
```

# Part V StarPU Reference API

# **Chapter 24**

# **Execution Configuration Through Environment Variables**

The behavior of the StarPU library and tools may be tuned thanks to the following environment variables.

#### 24.1 Configuring Workers

- **STARPU\_NCPU** Specify the number of CPU workers (thus not including workers dedicated to control accelerators). Note that by default, StarPU will not allocate more CPU workers than there are physical CPUs, and that some CPUs are used to control the accelerators.
- **STARPU\_NCPUS** This variable is deprecated. You should use **STARPU\_NCPU**.
- **STARPU\_NCUDA** Specify the number of CUDA devices that StarPU can use. If STARPU\_NCUDA is lower than the number of physical devices, it is possible to select which CUDA devices should be used by the means of the environment variable STARPU\_WORKERS\_CUDAID. By default, StarPU will create as many CUDA workers as there are CUDA devices.
- **STARPU\_NWORKER\_PER\_CUDA** Specify the number of workers per CUDA device, and thus the number of kernels which will be concurrently running on the devices. The default value is 1.
- **STARPU\_CUDA\_PIPELINE** Specify how many asynchronous tasks are submitted in advance on CUDA devices. This for instance permits to overlap task management with the execution of previous tasks, but it also allows concurrent execution on Fermi cards, which otherwise bring spurious synchronizations. The default is 2. Setting the value to 0 forces a synchronous execution of all tasks.
- STARPU\_NOPENCL OpenCL equivalent of the environment variable STARPU\_NCUDA.
- **STARPU\_OPENCL\_PIPELINE** Specify how many asynchronous tasks are submitted in advance on OpenCL devices. This for instance permits to overlap task management with the execution of previous tasks, but it also allows concurrent execution on Fermi cards, which otherwise bring spurious synchronizations. The default is 2. Setting the value to 0 forces a synchronous execution of all tasks.
- **STARPU\_OPENCL\_ON\_CPUS** By default, the OpenCL driver only enables GPU and accelerator devices. By setting the environment variable STARPU\_OPENCL\_ON\_CPUS to 1, the OpenCL driver will also enable CPU devices.
- **STARPU\_OPENCL\_ONLY\_ON\_CPUS** By default, the OpenCL driver enables GPU and accelerator devices. By setting the environment variable STARPU\_OPENCL\_ONLY\_ON\_CPUS to 1, the OpenCL driver will ONLY enable CPU devices.
- **STARPU\_NMIC** MIC equivalent of the environment variable STARPU\_NCUDA, i.e. the number of MIC devices to
- STARPU NMICCORES Number of cores to use on the MIC devices.

- **STARPU\_NSCC** SCC equivalent of the environment variable STARPU\_NCUDA.
- **STARPU\_WORKERS\_NOBIND** Setting it to non-zero will prevent StarPU from binding its threads to CPUs. This is for instance useful when running the testsuite in parallel.
- STARPU\_WORKERS\_CPUID Passing an array of integers in STARPU\_WORKERS\_CPUID specifies on which logical CPU the different workers should be bound. For instance, if STARPU\_WORKERS\_CPUID = "0 1 4 5", the first worker will be bound to logical CPU #0, the second CPU worker will be bound to logical CPU #1 and so on. Note that the logical ordering of the CPUs is either determined by the OS, or provided by the library hwloc in case it is available. Ranges can be provided: for instance, STARPU\_WORKERS\_CPUID = "1-3 5" will bind the first three workers on logical CPUs #1, #2, and #3, and the fourth worker on logical CPU #5. Unbound ranges can also be provided: STARPU\_WORKERS\_CPUID = "1-" will bind the workers starting from logical CPU #1 up to last CPU.

Note that the first workers correspond to the CUDA workers, then come the OpenCL workers, and finally the CPU workers. For example if we have STARPU\_NCUDA=1, STARPU\_NOPENCL=1, STARPU\_NCPU=2 and STARPU\_WORKERS\_CPUID = "0 2 1 3", the CUDA device will be controlled by logical CPU #0, the OpenCL device will be controlled by logical CPU #2, and the logical CPUs #1 and #3 will be used by the CPU workers.

If the number of workers is larger than the array given in STARPU\_WORKERS\_CPUID, the workers are bound to the logical CPUs in a round-robin fashion: if STARPU\_WORKERS\_CPUID = "0 1", the first and the third (resp. second and fourth) workers will be put on CPU #0 (resp. CPU #1).

This variable is ignored if the field starpu\_conf::use\_explicit\_workers\_bindid passed to starpu\_init() is set.

STARPU\_WORKERS\_CUDAID Similarly to the STARPU\_WORKERS\_CPUID environment variable, it is possible to select which CUDA devices should be used by StarPU. On a machine equipped with 4 GPUs, setting STARPU\_WORKERS\_CUDAID = "1 3" and STARPU\_NCUDA=2 specifies that 2 CUDA workers should be created, and that they should use CUDA devices #1 and #3 (the logical ordering of the devices is the one reported by CUDA).

This variable is ignored if the field starpu\_conf::use\_explicit\_workers\_cuda\_gpuid passed to starpu\_init() is set.

**STARPU\_WORKERS\_OPENCLID** OpenCL equivalent of the STARPU\_WORKERS\_CUDAID environment variable

This variable is ignored if the field starpu\_conf::use\_explicit\_workers\_opencl\_gpuid passed to starpu\_init() is set.

- STARPU\_WORKERS\_MICID MIC equivalent of the STARPU\_WORKERS\_CUDAID environment variable.
  - This variable is ignored if the field starpu\_conf::use\_explicit\_workers\_mic\_deviceid passed to starpu\_init() is set.
- STARPU WORKERS SCCID SCC equivalent of the STARPU WORKERS CUDAID environment variable.

This variable is ignored if the field starpu\_conf::use\_explicit\_workers\_scc\_deviceid passed to starpu\_init() is set.

- STARPU\_SINGLE\_COMBINED\_WORKER If set, StarPU will create several workers which won't be able to work concurrently. It will by default create combined workers which size goes from 1 to the total number of CPU workers in the system. STARPU\_MIN\_WORKERSIZE and STARPU\_MAX\_WORKERSIZE can be used to change this default.
- **STARPU\_MIN\_WORKERSIZE** STARPU\_MIN\_WORKERSIZE permits to specify the minimum size of the combined workers (instead of the default 2)
- **STARPU\_MAX\_WORKERSIZE** STARPU\_MAX\_WORKERSIZE permits to specify the minimum size of the combined workers (instead of the number of CPU workers in the system)
- STARPU\_SYNTHESIZE\_ARITY\_COMBINED\_WORKER Let the user decide how many elements are allowed between combined workers created from hwloc information. For instance, in the case of sockets with 6 cores without shared L2 caches, if STARPU\_SYNTHESIZE\_ARITY\_COMBINED\_WORKER is set to 6, no combined worker will be synthesized beyond one for the socket and one per core. If it is set to 3, 3 intermediate combined workers will be synthesized, to divide the socket cores into 3 chunks of 2 cores. If it set to 2, 2

intermediate combined workers will be synthesized, to divide the the socket cores into 2 chunks of 3 cores, and then 3 additional combined workers will be synthesized, to divide the former synthesized workers into a bunch of 2 cores, and the remaining core (for which no combined worker is synthesized since there is already a normal worker for it).

The default, 2, thus makes StarPU tend to building a binary trees of combined workers.

- **STARPU\_DISABLE\_ASYNCHRONOUS\_COPY** Disable asynchronous copies between CPU and GPU devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- **STARPU\_DISABLE\_ASYNCHRONOUS\_CUDA\_COPY** Disable asynchronous copies between CPU and CUDA devices.
- **STARPU\_DISABLE\_ASYNCHRONOUS\_OPENCL\_COPY** Disable asynchronous copies between CPU and OpenCL devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- **STARPU\_DISABLE\_ASYNCHRONOUS\_MIC\_COPY** Disable asynchronous copies between CPU and MIC devices.
- **STARPU\_ENABLE\_CUDA\_GPU\_DIRECT** Enable (1) or Disable (0) direct CUDA transfers from GPU to GPU, without copying through RAM. The default is Enabled. This permits to test the performance effect of GPU-Direct.
- **STARPU\_DISABLE\_PINNING** Disable (1) or Enable (0) pinning host memory allocated through starpu\_malloc, starpu\_memory\_pin and friends. The default is Enabled. This permits to test the performance effect of memory pinning.

#### 24.2 Configuring The Scheduling Engine

**STARPU\_SCHED** Choose between the different scheduling policies proposed by StarPU: work random, stealing, greedy, with performance models, etc.

Use STARPU\_SCHED=help to get the list of available schedulers.

**STARPU\_CALIBRATE** If this variable is set to 1, the performance models are calibrated during the execution. If it is set to 2, the previous values are dropped to restart calibration from scratch. Setting this variable to 0 disable calibration, this is the default behaviour.

Note: this currently only applies to dm and dmda scheduling policies.

- **STARPU\_CALIBRATE\_MINIMUM** This defines the minimum number of calibration measurements that will be made before considering that the performance model is calibrated. The default value is 10.
- STARPU\_BUS\_CALIBRATE If this variable is set to 1, the bus is recalibrated during intialization.
- **STARPU\_PREFETCH** This variable indicates whether data prefetching should be enabled (0 means that it is disabled). If prefetching is enabled, when a task is scheduled to be executed e.g. on a GPU, StarPU will request an asynchronous transfer in advance, so that data is already present on the GPU when the task starts. As a result, computation and data transfers are overlapped. Note that prefetching is enabled by default in StarPU.
- **STARPU\_SCHED\_ALPHA** To estimate the cost of a task StarPU takes into account the estimated computation time (obtained thanks to performance models). The alpha factor is the coefficient to be applied to it before adding it to the communication part.
- **STARPU\_SCHED\_BETA** To estimate the cost of a task StarPU takes into account the estimated data transfer time (obtained thanks to performance models). The beta factor is the coefficient to be applied to it before adding it to the computation part.
- STARPU SCHED GAMMA Define the execution time penalty of a joule (Power-based Scheduling).
- STARPU\_IDLE\_POWER Define the idle power of the machine (Power-based Scheduling).
- STARPU\_PROFILING Enable on-line performance monitoring (Enabling On-line Performance Monitoring).

#### 24.3 Extensions

- **SOCL\_OCL\_LIB\_OPENCL** THE SOCL test suite is only run when the environment variable SOCL\_OCL\_LIB\_O-PENCL is defined. It should contain the location of the file libOpenCL.so of the OCL ICD implementation.
- OCL\_ICD\_VENDORS When using SOCL with OpenCL ICD (https://forge.imag.fr/projects/ocl-icd/), this variable may be used to point to the directory where ICD files are installed. The default directory is /etc/OpenCL/vendors. StarPU installs ICD files in the directory \$prefix/share/starpu/opencl/vendors.
- **STARPU\_COMM\_STATS** Communication statistics for starpumpi (MPI Support) will be enabled when the environment variable STARPU\_COMM\_STATS is defined to an value other than 0.
- **STARPU\_MPI\_CACHE** Communication cache for starpumpi (MPI Support) will be disabled when the environment variable STARPU\_MPI\_CACHE is set to 0. It is enabled by default or for any other values of the variable ST-ARPU MPI CACHE.
- **STARPU\_MPI\_COMM** Communication trace for starpumpi (MPI Support) will be enabled when the environment variable STARPU\_MPI\_COMM is set to 1, and StarPU has been configured with the option --enable-verbose.
- **STARPU\_MPI\_CACHE\_STATS** When set to 1, statistics are enabled for the communication cache (MPI Support). For now, it prints messages on the standard output when data are added or removed from the received communication cache.
- **STARPU\_SIMGRID\_CUDA\_MALLOC\_COST** When set to 1 (which is the default), CUDA malloc costs are taken into account in simgrid mode.
- **STARPU\_SIMGRID\_CUDA\_QUEUE\_COST** When set to 1 (which is the default), CUDA task and transfer queueing costs are taken into account in simgrid mode.

#### 24.4 Miscellaneous And Debug

- **STARPU\_HOME** This specifies the main directory in which StarPU stores its configuration files. The default is \$HOME on Unix environments, and \$USERPROFILE on Windows environments.
- **STARPU\_PERF\_MODEL\_DIR** This specifies the main directory in which StarPU stores its performance model files. The default is \$STARPU\_HOME/.starpu/sampling.
- **STARPU\_HOSTNAME** When set, force the hostname to be used when dealing performance model files. Models are indexed by machine name. When running for example on a homogeneous cluster, it is possible to share the models between machines by setting export STARPU\_HOSTNAME=some\_global\_name.
- **STARPU\_OPENCL\_PROGRAM\_DIR** This specifies the directory where the OpenCL codelet source files are located. The function starpu\_opencl\_load\_program\_source() looks for the codelet in the current directory, in the directory specified by the environment variable STARPU\_OPENCL\_PROGRAM\_DIR, in the directory share/starpu/opencl of the installation directory of StarPU, and finally in the source directory of StarPU.
- **STARPU\_SILENT** This variable allows to disable verbose mode at runtime when StarPU has been configured with the option --enable-verbose. It also disables the display of StarPU information and warning messages.
- STARPU\_LOGFILENAME This variable specifies in which file the debugging output should be saved to.
- **STARPU\_FXT\_PREFIX** This variable specifies in which directory to save the trace generated if FxT is enabled. It needs to have a trailing '/' character.
- **STARPU\_LIMIT\_CUDA\_devid\_MEM** This variable specifies the maximum number of megabytes that should be available to the application on the CUDA device with the identifier devid. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory. When defined, the variable overwrites the value of the variable STARPU\_LIMIT\_CUDA\_MEM.

- **STARPU\_LIMIT\_CUDA\_MEM** This variable specifies the maximum number of megabytes that should be available to the application on each CUDA devices. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory.
- **STARPU\_LIMIT\_OPENCL\_devid\_MEM** This variable specifies the maximum number of megabytes that should be available to the application on the OpenCL device with the identifier devid. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory. When defined, the variable overwrites the value of the variable STARPU\_LIMIT\_OPENCL\_MEM.
- **STARPU\_LIMIT\_OPENCL\_MEM** This variable specifies the maximum number of megabytes that should be available to the application on each OpenCL devices. This variable is intended to be used for experimental purposes as it emulates devices that have a limited amount of memory.
- **STARPU\_LIMIT\_CPU\_MEM** This variable specifies the maximum number of megabytes that should be available to the application on each CPU device. Setting it enables allocation cache in main memory
- **STARPU\_MINIMUM\_AVAILABLE\_MEM** This specifies the minimum percentage of memory that should be available in GPUs (or in main memory, when using out of core), below which a reclaiming pass is performed. The default is 5%.
- **STARPU\_TARGET\_AVAILABLE\_MEM** This specifies the target percentage of memory that should be reached in GPUs (or in main memory, when using out of core), when performing a periodic reclaiming pass. The default is 10%.
- **STARPU\_MINIMUM\_CLEAN\_BUFFERS** This specifies the minimum percentage of number of buffers that should be clean in GPUs (or in main memory, when using out of core), below which asynchronous writebacks will be issued. The default is to disable asynchronous writebacks.
- **STARPU\_TARGET\_CLEAN\_BUFFERS** This specifies the target percentage of number of buffers that should be reached in GPUs (or in main memory, when using out of core), when performing an asynchronous writeback pass. The default is to disable asynchronous writebacks.
- STARPU\_DISK\_SWAP This specifies a path where StarPU can push data when the main memory is getting full.
- **STARPU\_DISK\_SWAP\_BACKEND** This specifies then backend to be used by StarPU to push data when the main memory is getting full. The default is unistd (i.e. using read/write functions), other values are stdio (i.e. using fread/fwrite), unistd\_o\_direct (i.e. using read/write with O\_DIRECT), and leveldb (i.e. using a leveldb database).
- **STARPU\_DISK\_SWAP\_SIZE** This specifies then size to be used by StarPU to push data when the main memory is getting full. The default is unlimited.
- STARPU\_LIMIT\_MAX\_NSUBMITTED\_TASKS This variable allows the user to control the task submission flow by specifying to StarPU a maximum number of submitted tasks allowed at a given time, i.e. when this limit is reached task submission becomes blocking until enough tasks have completed, specified by STARPU\_LIMIT\_MIN\_NSUBMITTED\_TASKS. Setting it enables allocation cache buffer reuse in main memory.
- **STARPU\_LIMIT\_MIN\_NSUBMITTED\_TASKS** This variable allows the user to control the task submission flow by specifying to StarPU a submitted task threshold to wait before unblocking task submission. This variable has to be used in conjunction with STARPU\_LIMIT\_MAX\_NSUBMITTED\_TASKS which puts the task submission thread to sleep. Setting it enables allocation cache buffer reuse in main memory.
- **STARPU\_TRACE\_BUFFER\_SIZE** This sets the buffer size for recording trace events in MiB. Setting it to a big size allows to avoid pauses in the trace while it is recorded on the disk. This however also consumes memory, of course. The default value is 64.
- **STARPU\_GENERATE\_TRACE** When set to 1, this variable indicates that StarPU should automatically generate a Paje trace when starpu shutdown() is called.
- **STARPU\_MEMORY\_STATS** When set to 0, disable the display of memory statistics on data which have not been unregistered at the end of the execution (Memory Feedback).
- **STARPU\_BUS\_STATS** When defined, statistics about data transfers will be displayed when calling starpu\_shutdown() (Profiling).

- **STARPU\_WORKER\_STATS** When defined, statistics about the workers will be displayed when calling starpu\_shutdown() (Profiling). When combined with the environment variable STARPU\_PROFILING, it displays the power consumption (Power-based Scheduling).
- **STARPU\_STATS** When set to 0, data statistics will not be displayed at the end of the execution of an application (Data Statistics).
- **STARPU\_WATCHDOG\_TIMEOUT** When set to a value other than 0, allows to make StarPU print an error message whenever StarPU does not terminate any task for the given time (in μs). Should be used in combination with STARPU\_WATCHDOG\_CRASH (see Detection Stuck Conditions).
- **STARPU\_WATCHDOG\_CRASH** When set to a value other than 0, it triggers a crash when the watch dog is reached, thus allowing to catch the situation in gdb, etc (see Detection Stuck Conditions)
- **STARPU\_DISABLE\_KERNELS** When set to a value other than 1, it disables actually calling the kernel functions, thus allowing to quickly check that the task scheme is working properly, without performing the actual application-provided computation.
- **STARPU\_HISTORY\_MAX\_ERROR** History-based performance models will drop measurements which are really far froom the measured average. This specifies the allowed variation. The default is 50 (%), i.e. the measurement is allowed to be x1.5 faster or /1.5 slower than the average.
- **STARPU\_RAND\_SEED** The random scheduler and some examples use random numbers for their own working. Depending on the examples, the seed is by default juste always 0 or the current time() (unless simgrid mode is enabled, in which case it is always 0). STARPU\_RAND\_SEED allows to set the seed to a specific value.

#### 24.5 Configuring The Hypervisor

- **SC\_HYPERVISOR\_POLICY** Choose between the different resizing policies proposed by StarPU for the hypervisor: idle, app\_driven, feft\_lp, teft\_lp; ispeed\_lp, throughput\_lp etc.
  - Use SC\_HYPERVISOR\_POLICY=help to get the list of available policies for the hypervisor
- SC\_HYPERVISOR\_TRIGGER\_RESIZE Choose how should the hypervisor be triggered: speed if the resizing algorithm should be called whenever the speed of the context does not correspond to an optimal precomputed value, idle it the resizing algorithm should be called whenever the workers are idle for a period longer than the value indicated when configuring the hypervisor.
- **SC\_HYPERVISOR\_START\_RESIZE** Indicate the moment when the resizing should be available. The value correspond to the percentage of the total time of execution of the application. The default value is the resizing frame.
- SC\_HYPERVISOR\_MAX\_SPEED\_GAP Indicate the ratio of speed difference between contexts that should trigger the hypervisor. This situation may occur only when a theoretical speed could not be computed and the hypervisor has no value to compare the speed to. Otherwise the resizing of a context is not influenced by the the speed of the other contexts, but only by the the value that a context should have.
- **SC\_HYPERVISOR\_STOP\_PRINT** By default the values of the speed of the workers is printed during the execution of the application. If the value 1 is given to this environment variable this printing is not done.
- SC\_HYPERVISOR\_LAZY\_RESIZE By default the hypervisor resizes the contexts in a lazy way, that is workers are firstly added to a new context before removing them from the previous one. Once this workers are clearly taken into account into the new context (a task was poped there) we remove them from the previous one. However if the application would like that the change in the distribution of workers should change right away this variable should be set to 0
- SC\_HYPERVISOR\_SAMPLE\_CRITERIA By default the hypervisor uses a sample of flops when computing the speed of the contexts and of the workers. If this variable is set to time the hypervisor uses a sample of time (10% of an aproximation of the total execution time of the application)

# **Chapter 25**

# **Compilation Configuration**

The behavior of the StarPU library and tools may be tuned thanks to the following configure options.

#### 25.1 Common Configuration

- **-enable-debug** Enable debugging messages.
- **-enable-spinlock-check** Enable checking that spinlocks are taken and released properly.
- **-enable-fast** Disable assertion checks, which saves computation time.
- -enable-verbose Increase the verbosity of the debugging messages. This can be disabled at runtime by setting the environment variable STARPU\_SILENT to any value. -enable-verbose=extra increase even more the verbosity.

```
$ STARPU_SILENT=1 ./vector_scal
```

- **-enable-coverage** Enable flags for the coverage tool gcov.
- -enable-quick-check Specify tests and examples should be run on a smaller data set, i.e allowing a faster execution time
- **-enable-long-check** Enable some exhaustive checks which take a really long time.
- **-enable-new-check** Enable new testcases which are known to fail.
- -with-hwloc Specify hwloc should be used by StarPU. hwloc should be found by the means of the tool pkg-config.
- -with-hwloc=prefix Specify hwloc should be used by StarPU. hwloc should be found in the directory specified by prefix
- -without-hwloc Specify hwloc should not be used by StarPU.
- -disable-build-doc Disable the creation of the documentation. This should be done on a machine which does not have the tools doxygen and latex (plus the packages latex-xcolor and texlive-latex-extra).

Additionally, the script configure recognize many variables, which can be listed by typing ./configure –help. For example, ./configure NVCCFLAGS="-arch sm\_13" adds a flag for the compilation of C-UDA kernels.

#### 25.2 Configuring Workers

- **-enable-maxcpus=count** Use at most count CPU cores. This information is then available as the macro ::STARPU MAXCPUS.
- **-disable-cpu** Disable the use of CPUs of the machine. Only GPUs etc. will be used.
- -enable-maxcudadev=count Use at most count CUDA devices. This information is then available as the macro STARPU\_MAXCUDADEVS.
- -disable-cuda Disable the use of CUDA, even if a valid CUDA installation was detected.
- -with-cuda-dir=prefix Search for CUDA under prefix, which should notably contain the file include/cuda.h.
- -with-cuda-include-dir=dir Search for CUDA headers under dir, which should notably contain the file cuda.h. This defaults to /include appended to the value given to --with-cuda-dir.
- -with-cuda-lib-dir=dir Search for CUDA libraries under dir, which should notably contain the CUDA shared libraries—e.g., libcuda.so. This defaults to /lib appended to the value given to --with-cuda-dir.
- -disable-cuda-memcpy-peer Explicitly disable peer transfers when using CUDA 4.0.
- -enable-maxopencidev=count Use at most count OpenCL devices. This information is then available as the macro STARPU MAXOPENCLDEVS.
- -disable-opencl Disable the use of OpenCL, even if the SDK is detected.
- -with-opencl-dir=prefix Search for an OpenCL implementation under prefix, which should notably contain include/CL/cl.h (or include/OpenCL/cl.h on Mac OS).
- -with-opencl-include-dir=dir Search for OpenCL headers under dir, which should notably contain CL/cl.h (or OpenCL/cl.h on Mac OS). This defaults to /include appended to the value given to --with-opencl-dir.
- -with-opencl-lib-dir=dir Search for an OpenCL library under dir, which should notably contain the OpenCL shared libraries—e.g. libOpenCL.so. This defaults to /lib appended to the value given to --with-opencl-dir.
- -enable-opencl-simulator Enable considering the provided OpenCL implementation as a simulator, i.e. use the kernel duration returned by OpenCL profiling information as wallclock time instead of the actual measured real time. This requires simgrid support.
- **-enable-maximplementations=count** Allow for at most count codelet implementations for the same target device. This information is then available as the macro ::STARPU\_MAXIMPLEMENTATIONS macro.
- -enable-max-sched-ctxs=count Allow for at most count scheduling contexts This information is then available as the macro ::STARPU NMAX SCHED CTXS.
- -disable-asynchronous-copy Disable asynchronous copies between CPU and GPU devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- **-disable-asynchronous-cuda-copy** Disable asynchronous copies between CPU and CUDA devices.
- -disable-asynchronous-opencl-copy Disable asynchronous copies between CPU and OpenCL devices. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers.
- -enable-maxmicthreads Specify the maximum number of MIC threads
- -disable-asynchronous-mic-copy Disable asynchronous copies between CPU and MIC devices.
- **-enable-maxnodes=count** Use at most count memory nodes. This information is then available as the macro ::STARPU\_MAXNODES. Reducing it allows to considerably reduce memory used by StarPU data structures.

#### 25.3 Extension Configuration

- -disable-fortran Disable the fortran extension. By default, it is enabled when a fortran compiler is found.
- **-disable-socl** Disable the SOCL extension (SOCL OpenCL Extensions). By default, it is enabled when an Open-CL implementation is found.
- -disable-starpu-top Disable the StarPU-Top interface (StarPU-Top Interface). By default, it is enabled when the required dependencies are found.
- **-disable-gcc-extensions** Disable the GCC plug-in (C Extensions). By default, it is enabled when the GCC compiler provides a plug-in support.
- **-with-mpicc=path** Use the compiler mpicc at path, for StarPU-MPI. (MPI Support).
- **-enable-mpi-progression-hook** Enable the activity polling method for StarPU-MPI.
- -with-coi-dir Specify the directory to the COI library for MIC support. The default value is /opt/intel/mic/coi
- -mic-host Specify the precise MIC architecture host identifier. The default value is x86\_64-k1om-linux
- -enable-openmp Enable OpenMP Support (The StarPU OpenMP Runtime Support (SORS))

#### 25.4 Advanced Configuration

- -enable-perf-debug Enable performance debugging through gprof.
- -enable-model-debug Enable performance model debugging.
- **-enable-paje-codelet-details** Enable details about codelets in the paje trace. This requires a recent enough version of ViTE (at least r1430).
- **-enable-fxt-lock** Enable additional trace events which describes locks behaviour.
- -enable-stats (see ../../src/datawizard/datastats.c) Enable gathering of various data statistics (Data Statistics).
- **-enable-maxbuffers** Define the maximum number of buffers that tasks will be able to take as parameters, then available as the macro STARPU\_NMAXBUFS.
- -enable-allocation-cache Enable the use of a data allocation cache to avoid the cost of it with CUDA. Still experimental.
- **-enable-opengl-render** Enable the use of OpenGL for the rendering of some examples.
- **-enable-blas-lib** Specify the blas library to be used by some of the examples. The library has to be 'atlas' or 'goto'.
- -disable-starpufft Disable the build of libstarpufft, even if fftw or cuffT is available.
- -enable-starpufft-examples Enable the compilation and the execution of the libstarpufft examples. By default, they are neither compiled nor checked.
- -with-fxt=prefix Search for FxT under prefix. FxT (http://savannah.nongnu.org/projects/fkt) is used to generate traces of scheduling events, which can then be rendered them using ViTE (Off-line Performance Feedback). prefix should notably contain include/fxt/fxt.h.
- **-with-perf-model-dir=dir** Store performance models under dir, instead of the current user's home.
- -with-goto-dir=prefix Search for GotoBLAS under prefix, which should notably contain libgoto.so or libgoto2.so.
- -with-atlas-dir=prefix Search for ATLAS under prefix, which should notably contain include/cblas.-

- -with-mkl-cflags=cflags Use cflags to compile code that uses the MKL library.
- -with-mkl-ldflags=ldflags Use ldflags when linking code that uses the MKL library. Note that the MKL website (http://software.intel.com/en-us/articles/intel-mkl-link-line-advisor/) provides a script to determine the linking flags.
- -disable-build-tests Disable the build of tests.
- **-disable-build-examples** Disable the build of examples.
- -disable-build-tests Disable the build of tests.
- -enable-sc-hypervisor Enable the Scheduling Context Hypervisor plugin(Scheduling Context Hypervisor). By default, it is disabled.
- **-enable-memory-stats** Enable memory statistics (Memory Feedback).
- **-enable-simgrid** Enable simulation of execution in simgrid, to allow easy experimentation with various numbers of cores and GPUs, or amount of memory, etc. Experimental.

The path to simgrid can be specified through the SIMGRID\_CFLAGS and SIMGRID\_LIBS environment variables, for instance:

```
export SIMGRID_CFLAGS="-I/usr/local/simgrid/include"
export SIMGRID_LIBS="-L/usr/local/simgrid/lib -lsimgrid"
```

- **-with-simgrid-dir** Similar to the option --enable-simgrid but also allows to specify the location to the SimGrid library.
- **-with-simgrid-include-dir** Similar to the option --enable-simgrid but also allows to specify the location to the Sim-Grid include directory.
- -with-simgrid-lib-dir Similar to the option --enable-simgrid but also allows to specify the location to the SimGrid lib directory.
- -with-smpirun=path Use the smpirun at path
- -enable-calibration-heuristic Allows to set the maximum authorized percentage of deviation for the history-based calibrator of StarPU. A correct value of this parameter must be in [0..100]. The default value of this parameter is 10. Experimental.

# **Chapter 26**

# **Module Index**

### 26.1 Modules

Here	is a	list of	all	modu	ıles

Bitmap
Codelet And Tasks
CUDA Extensions
Data Interfaces
Data Management
Out Of Core
Data Partition
Expert Mode
Explicit Dependencies
FFT Support
FxT Support
Implicit Data Dependencies
Initialization and Termination
Insert_Task
Theoretical Lower Bound on Execution Time
MIC Extensions
Miscellaneous Helpers
Modularized Scheduler Interface
MPI Support
Multiformat Data Interface
OpenCL Extensions
OpenMP Runtime Support
Parallel Tasks
Performance Model
Profiling
Running Drivers
SCC Extensions
Scheduling Contexts
Scheduling Policy
Standard Memory Library
Task Bundles
Task Lists
Threads
Toolbox
StarPU-Top Interface
Tree
Versioning
Workers' Properties

Scheduling Context Hypervisor - Building a new resizing policy	 	 					 	326
Scheduling Context Hypervisor - Regular usage	 						 	322

# **Chapter 27**

# Module Documentation a.k.a StarPU's API

#### 27.1 Versioning

#### **Macros**

- #define STARPU\_MAJOR\_VERSION
- #define STARPU\_MINOR\_VERSION
- #define STARPU RELEASE VERSION

#### **Functions**

void starpu\_get\_version (int \*major, int \*minor, int \*release)

#### 27.1.1 Detailed Description

#### 27.1.2 Macro Definition Documentation

#### 27.1.2.1 #define STARPU\_MAJOR\_VERSION

Define the major version of StarPU. This is the version used when compiling the application.

#### 27.1.2.2 #define STARPU\_MINOR\_VERSION

Define the minor version of StarPU. This is the version used when compiling the application.

#### 27.1.2.3 #define STARPU\_RELEASE\_VERSION

Define the release version of StarPU. This is the version used when compiling the application.

#### 27.1.3 Function Documentation

27.1.3.1 void starpu\_get\_version ( int \* major, int \* minor, int \* release )

Return as 3 integers the version of StarPU used when running the application.

#### 27.2 Initialization and Termination

#### **Data Structures**

- · struct starpu\_driver
- · union starpu\_driver.id
- · struct starpu\_conf

#### **Functions**

- int starpu\_init (struct starpu\_conf \*conf) STARPU\_WARN\_UNUSED\_RESULT
- int starpu\_initialize (struct starpu\_conf \*user\_conf, int \*argc, char \*\*\*argv)
- int starpu\_conf\_init (struct starpu\_conf \*conf)
- void starpu\_shutdown (void)
- void starpu\_pause (void)
- void starpu\_resume (void)
- int starpu\_asynchronous\_copy\_disabled (void)
- int starpu asynchronous cuda copy disabled (void)
- int starpu\_asynchronous\_opencl\_copy\_disabled (void)
- int starpu\_asynchronous\_mic\_copy\_disabled (void)
- void starpu\_topology\_print (FILE \*f)

#### 27.2.1 Detailed Description

#### 27.2.2 Data Structure Documentation

#### 27.2.2.1 struct starpu\_driver

structure for a driver

#### **Data Fields**

enum starpu worker_archtype		The type of the driver. Only STARPU_CPU_WORKER, STARPU_CUDA_WORKER and STARPU_OPENCL_WORKER are currently supported.
union	id	The identifier of the driver.
starpu_driver		

#### 27.2.2.2 union starpu\_driver.id

#### **Data Fields**

unsigned	cpu_id	
unsigned	cuda_id	
cl_device_id	opencl_id	

#### 27.2.2.3 struct starpu\_conf

This structure is passed to the <a href="starpu\_init">starpu\_init</a>() function in order to configure StarPU. It has to be initialized with <a href="starpu\_init">starpu\_conf\_init</a>(). When the default value is used, StarPU automatically selects the number of processing units and takes the default scheduling policy. The environment variables overwrite the equivalent parameters.

#### Data Fields

int	magic	Will be initialized by starpu_conf_init(). Should not be set by hand.
const char *	sched_policy	This is the name of the scheduling policy. This can also be specified with
	name	the environment variable STARPU_SCHED. (default = NULL).
struct starpu	sched_policy	This is the definition of the scheduling policy. This field is ignored if starpu-
sched_policy		_conf::sched_policy_name is set. (default = NULL)
*		
int	ncpus	This is the number of CPU cores that StarPU can use. This can also be
		specified with the environment variable STARPU_NCPU . (default = -1)
int	ncuda	This is the number of CUDA devices that StarPU can use. This can also
		be specified with the environment variable STARPU_NCUDA. (default =
		-1)
int	nopencl	This is the number of OpenCL devices that StarPU can use. This can also
		be specified with the environment variable STARPU_NOPENCL. (default
		= -1)
int	nmic	This is the number of MIC devices that StarPU can use. This can also be
		specified with the environment variable STARPU_NMIC. (default = -1)
int	nscc	This is the number of SCC devices that StarPU can use. This can also be
		specified with the environment variable STARPU_NSCC. (default = -1)
unsigned	use_explicit	If this flag is set, the starpu_conf::workers_bindid array indicates where
	workers_bindid	the different workers are bound, otherwise StarPU automatically selects
		where to bind the different workers. This can also be specified with the
		environment variable STARPU_WORKERS_CPUID. (default = 0)
unsigned	workers_bindid	If the starpu_conf::use_explicit_workers_bindid flag is set, this array indi-
		cates where to bind the different workers. The i-th entry of the starpu
		conf::workers_bindid indicates the logical identifier of the processor which
		should execute the i-th worker. Note that the logical ordering of the CPUs
		is either determined by the OS, or provided by the hwloc library in case it
		is available.
unsigned	use_explicit	If this flag is set, the CUDA workers will be attached to the CUDA devices
	workers_cuda	specified in the starpu_conf::workers_cuda_gpuid array. Otherwise, Star-
	gpuid	PU affects the CUDA devices in a round-robin fashion. This can also be
		specified with the environment variable STARPU_WORKERS_CUDAID.
		(default = 0)
unsigned	workers_cuda	If the starpu_conf::use_explicit_workers_cuda_gpuid flag is set, this array
	gpuid	contains the logical identifiers of the CUDA devices (as used by cudaGet-
		Device()).
unsigned	use_explicit	If this flag is set, the OpenCL workers will be attached to the OpenCL
	workers_opencl-	devices specified in the starpu_conf::workers_opencl_gpuid array. Other-
	_gpuid	wise, StarPU affects the OpenCL devices in a round-robin fashion. This
		can also be specified with the environment variable STARPU_WORKER-
المسامسين		S_OPENCLID. (default = 0)
unsigned	workers_opencl-	If the starpu_conf::use_explicit_workers_opencl_gpuid flag is set, this ar-
ا مسامس	_gpuid	ray contains the logical identifiers of the OpenCL devices to be used.
unsigned	use_explicit	If this flag is set, the MIC workers will be attached to the MIC devices
	workers_mic	specified in the array starpu_conf::workers_mic_deviceid. Otherwise,
	deviceid	StarPU affects the MIC devices in a round-robin fashion. This can also be specified with the environment variable STARPU_WORKERS_MICID.
uncianad	workers mie	(default = 0)   If the flag starpu_conf::use_explicit_workers_mic_deviceid is set, the ar-
unsigned	workers_mic deviceid	ray contains the logical identifiers of the MIC devices to be used.
unsigned		If this flag is set, the SCC workers will be attached to the SCC devices
unsigned	use_explicit workers_scc	specified in the array starpu_conf::workers_scc_deviceid. (default = 0)
	deviceid	specified in the array starpu_confworkers_scc_uevicetd. (detault = 0)
	ueviceiu	

uncianod	workers see	If the flag starpu_conf::use_explicit_workers_scc_deviceid is set, the ar-
unsigned	workers_scc deviceid	ray contains the logical identifiers of the SCC devices to be used. Otherwise, StarPU affects the SCC devices in a round-robin fashion. This can also be specified with the environment variable STARPU_WORKERS_SCOID.
int	bus_calibrate	If this flag is set, StarPU will recalibrate the bus. If this value is equal to $-1$ , the default value is used. This can also be specified with the environment variable STARPU_BUS_CALIBRATE. (default = 0)
int	calibrate	If this flag is set, StarPU will calibrate the performance models when executing tasks. If this value is equal to $-1$ , the default value is used. If the value is equal to $1$ , it will force continuing calibration. If the value is equal to $2$ , the existing performance models will be overwritten. This can also be specified with the environment variable STARPU_CALIBRATE. (default = 0)
int	single combined worker	By default, StarPU executes parallel tasks concurrently. Some parallel libraries (e.g. most OpenMP implementations) however do not support concurrent calls to parallel code. In such case, setting this flag makes StarPU only start one parallel task at a time (but other CPU and GPU tasks are not affected and can be run concurrently). The parallel task scheduler will however still try varying combined worker sizes to look for the most efficient ones. This can also be specified with the environment variable STARPU_SINGLE_COMBINED_WORKER. (default = 0)
char *	mic_sink program_path	Path to the kernel to execute on the MIC device, compiled for MIC architecture. When set to NULL, StarPU automatically looks next to the host program location. (default = NULL)
int	disable asynchronous copy	This flag should be set to 1 to disable asynchronous copies between C-PUs and all accelerators. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_COPY. The AM-D implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers. This can also be specified at compilation time by giving to the configure script the optiondisable-asynchronous-copy. (default = 0)
int	disable asynchronous cuda_copy	This flag should be set to 1 to disable asynchronous copies between C-PUs and CUDA accelerators. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_CUDA_COP-Y. This can also be specified at compilation time by giving to the configure script the optiondisable-asynchronous-cuda-copy. (default = 0)
int	disable asynchronous opencl_copy	This flag should be set to 1 to disable asynchronous copies between C-PUs and OpenCL accelerators. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_OPENCL_C-OPY. The AMD implementation of OpenCL is known to fail when copying data asynchronously. When using this implementation, it is therefore necessary to disable asynchronous data transfers. This can also be specified at compilation time by giving to the configure script the optiondisable-asynchronous-opencl-copy. (default = 0)
int	disable asynchronous mic_copy	This flag should be set to 1 to disable asynchronous copies between CP-Us and MIC accelerators. This can also be specified with the environment variable STARPU_DISABLE_ASYNCHRONOUS_MIC_COPY. This can also be specified at compilation time by giving to the configure script the optiondisable-asynchronous-mic-copy. (default = 0).
unsigned *	cuda_opengl interoperability	Enable CUDA/OpenGL interoperation on these CUDA devices. This can be set to an array of CUDA device identifiers for which cudaGLSetGL-Device() should be called instead of cudaSetDevice(). Its size is specified by the starpu_conf::n_cuda_opengl_interoperability field below (default = NULL)

unsigned	n_cuda_opengl-	todo
	_interoperability	
struct	not_launched	Array of drivers that should not be launched by StarPU. The application
starpu_driver *	drivers	will run in one of its own threads. (default = NULL)
unsigned	n_not_launched-	The number of StarPU drivers that should not be launched by StarPU.
	_drivers	(default = 0)
unsigned	trace_buffer	Specifies the buffer size used for FxT tracing. Starting from FxT version
	size	0.2.12, the buffer will automatically be flushed when it fills in, but it may
		still be interesting to specify a bigger value to avoid any flushing (which
		would disturb the trace).
int	global_sched	
	ctx_min_priority	
int	global_sched	
	ctx_max_priority	

#### 27.2.3 Function Documentation

#### 27.2.3.1 int starpu\_init ( struct starpu\_conf \* conf )

This is StarPU initialization method, which must be called prior to any other StarPU call. It is possible to specify StarPU's configuration (e.g. scheduling policy, number of cores, ...) by passing a non-null argument. Default configuration is used if the passed argument is NULL. Upon successful completion, this function returns 0. Otherwise, -ENODEV indicates that no worker was available (so that StarPU was not initialized).

#### 27.2.3.2 int starpu\_initialize ( struct starpu\_conf \* $user\_conf$ , int \* argc, char \*\*\* argv )

This is the same as starpu\_init(), but also takes the <code>argc</code> and <code>argv</code> as defined by the application. This is needed for SCC execution to initialize the communication library. Do not call <code>starpu\_init()</code> and <code>starpu\_init()</code> in the same program.

#### 27.2.3.3 int starpu\_conf\_init ( struct starpu\_conf \* conf )

This function initializes the conf structure passed as argument with the default values. In case some configuration parameters are already specified through environment variables, starpu\_conf\_init() initializes the fields of the structure according to the environment variables. For instance if STARPU\_CALIBRATE is set, its value is put in the field starpu\_conf::calibrate of the structure passed as argument. Upon successful completion, this function returns 0. Otherwise, -EINVAL indicates that the argument was NULL.

#### 27.2.3.4 void starpu\_shutdown ( void )

This is StarPU termination method. It must be called at the end of the application: statistics and other post-mortem debugging information are not guaranteed to be available until this method has been called.

#### 27.2.3.5 void starpu\_pause (void)

This call is used to suspend the processing of new tasks by workers. It can be used in a program where StarPU is used during only a part of the execution. Without this call, the workers continue to poll for new tasks in a tight loop, wasting CPU time. The symmetric call to starpu resume() should be used to unfreeze the workers.

#### 27.2.3.6 void starpu\_resume (void)

This is the symmetrical call to starpu\_pause(), used to resume the workers polling for new tasks.

```
27.2.3.7 int starpu_asynchronous_copy_disabled ( void )
```

Return 1 if asynchronous data transfers between CPU and accelerators are disabled.

```
27.2.3.8 int starpu_asynchronous_cuda_copy_disabled ( void )
```

Return 1 if asynchronous data transfers between CPU and CUDA accelerators are disabled.

```
27.2.3.9 int starpu_asynchronous_opencl_copy_disabled ( void )
```

Return 1 if asynchronous data transfers between CPU and OpenCL accelerators are disabled.

```
27.2.3.10 int starpu_asynchronous_mic_copy_disabled ( void )
```

Return 1 if asynchronous data transfers between CPU and MIC devices are disabled.

```
27.2.3.11 void starpu_topology_print ( FILE * f )
```

Prints a description of the topology on f.

#### 27.3 Standard Memory Library

#### Macros

- #define starpu\_data\_malloc\_pinned\_if\_possible
- #define starpu\_data\_free\_pinned\_if\_possible
- #define STARPU MALLOC PINNED
- #define STARPU\_MALLOC\_COUNT
- #define STARPU MALLOC NORECLAIM
- #define STARPU\_MEMORY\_WAIT
- #define STARPU\_MEMORY\_OVERFLOW

#### **Functions**

- int starpu\_malloc\_flags (void \*\*A, size\_t dim, int flags)
- · void starpu malloc set align (size t align)
- int starpu\_malloc (void \*\*A, size\_t dim)
- int starpu\_free (void \*A)
- int starpu\_free\_flags (void \*A, size\_t dim, int flags)
- int starpu\_memory\_pin (void \*addr, size\_t size)
- int starpu\_memory\_unpin (void \*addr, size\_t size)
- starpu ssize t starpu memory get total (unsigned node)
- starpu\_ssize\_t starpu\_memory\_get\_available (unsigned node)
- int starpu\_memory\_allocate (unsigned node, size\_t size, int flags)
- void starpu\_memory\_deallocate (unsigned node, size\_t size)
- void starpu\_memory\_wait\_available (unsigned node, size\_t size)

#### 27.3.1 Detailed Description

#### 27.3.2 Macro Definition Documentation

#### 27.3.2.1 #define starpu\_data\_malloc\_pinned\_if\_possible

Deprecated Equivalent to starpu\_malloc(). This macro is provided to avoid breaking old codes.

#### 27.3.2.2 #define starpu\_data\_free\_pinned\_if\_possible

**Deprecated** Equivalent to starpu\_free(). This macro is provided to avoid breaking old codes.

#### 27.3.2.3 #define STARPU\_MALLOC\_PINNED

Value passed to the function starpu\_malloc\_flags() to indicate the memory allocation should be pinned.

#### 27.3.2.4 #define STARPU\_MALLOC\_COUNT

Value passed to the function starpu\_malloc\_flags() to indicate the memory allocation should be in the limit defined by the environment variables STARPU\_LIMIT\_CUDA\_devid\_MEM, STARPU\_LIMIT\_CUDA\_MEM, STARPU\_LIMIT\_OPENCL\_devid\_MEM, STARPU\_LIMIT\_OPENCL\_MEM and STARPU\_LIMIT\_CPU\_MEM (see Section How to limit memory used by StarPU and cache buffer allocations). If no memory is available, it tries to reclaim memory from StarPU. Memory allocated this way needs to be freed by calling the function starpu\_free\_flags() with the same flag.

#### 27.3.2.5 #define STARPU\_MALLOC\_NORECLAIM

Value passed to the function <a href="mailtoc-flags">starpu\_malloc\_flags</a>() along STARPU\_MALLOC\_COUNT to indicate that while the memory allocation should be kept in the limits defined for STARPU\_MALLOC\_COUNT, no reclaiming should be performed by starpu\_malloc\_flags itself, thus potentially overflowing the memory node a bit. StarPU will reclaim memory after next task termination, according to the STARPU\_MINIMUM\_AVAILABLE\_MEM and STARPU\_TARGET\_AVAILABLE\_MEM environment variables. If STARPU\_MEMORY\_WAIT is set, no overflowing will happen, starpu\_malloc\_flags() will wait for other eviction mechanisms to release enough memory.

#### 27.3.2.6 #define STARPU\_MEMORY\_WAIT

Value passed to <a href="starpu\_memory\_allocate">starpu\_memory\_allocate</a>() to specify that the function should wait for the requested amount of memory to become available, and atomically allocate it.

#### 27.3.2.7 #define STARPU\_MEMORY\_OVERFLOW

Value passed to <a href="starpu\_memory\_allocate">starpu\_memory\_allocate</a>() to specify that the function should allocate the amount of memory, even if that means overflowing the total size of the memory node.

#### 27.3.3 Function Documentation

27.3.3.1 int starpu\_malloc\_flags ( void \*\* A, size\_t dim, int flags )

Performs a memory allocation based on the constraints defined by the given flag.

27.3.3.2 void starpu\_malloc\_set\_align ( size\_t align )

This function sets an alignment constraints for starpu\_malloc() allocations. align must be a power of two. This is for instance called automatically by the OpenCL driver to specify its own alignment constraints.

```
27.3.3.3 int starpu_malloc ( void ** A, size_t dim )
```

This function allocates data of the given size in main memory. It will also try to pin it in CUDA or OpenCL, so that data transfers from this buffer can be asynchronous, and thus permit data transfer and computation overlapping. The allocated buffer must be freed thanks to the starpu free() function.

```
27.3.3.4 int starpu_free ( void * A )
```

This function frees memory which has previously been allocated with starpu\_malloc().

```
27.3.3.5 int starpu_free_flags ( void * A, size_t dim, int flags )
```

This function frees memory by specifying its size. The given flags should be consistent with the ones given to starpu\_malloc\_flags() when allocating the memory.

```
27.3.3.6 int starpu_memory_pin ( void * addr, size_t size )
```

This function pins the given memory area, so that CPU-GPU transfers can be done asynchronously with DMAs. The memory must be unpinned with starpu memory unpin() before being freed. Returns 0 on success, -1 on error.

```
27.3.3.7 int starpu_memory_unpin ( void * addr, size_t size )
```

This function unpins the given memory area previously pinned with starpu\_memory\_pin(). Returns 0 on success, -1 on error.

```
27.3.3.8 ssize_t starpu_memory_get_total ( unsigned node )
```

If a memory limit is defined on the given node (see Section How to limit memory used by StarPU and cache buffer allocations), return the amount of total memory on the node. Otherwise return -1.

```
27.3.3.9 ssize_t starpu_memory_get_available ( unsigned node )
```

If a memory limit is defined on the given node (see Section How to limit memory used by StarPU and cache buffer allocations), return the amount of available memory on the node. Otherwise return -1.

27.3.3.10 int starpu\_memory\_allocate ( unsigned node, size\_t size, int flags )

Try to allocate memory on the given node

#### **Parameters**

size	amount of memory to allocate
node	node where the memory is to be allocated

27.4 Toolbox 165

#### Returns

1 if the given amount of memory was allocated on the given node

If a memory limit is defined on the given node (see Section How to limit memory used by StarPU and cache buffer allocations), try to allocate some of it. This does not actually allocate memory, but only accounts for it. This can be useful when the application allocates data another way, but want StarPU to be aware of the allocation size e.g. for memory reclaiming. By default, the function returns -ENOMEM if there is not enough room on the given node. flags can be either STARPU\_MEMORY\_WAIT or STARPU\_MEMORY\_OVERFLOW to change this.

27.3.3.11 void starpu\_memory\_deallocate ( unsigned node, size\_t size )

Indicates the given amount of memory is going to be deallocated from the given node

#### **Parameters**

size	amount of memory to be deallocated
node	node where the memory is going to be deallocated

If a memory limit is defined on the given node (see Section How to limit memory used by StarPU and cache buffer allocations), free some of it. This does not actually free memory, but only accounts for it, like starpu\_memory\_allocate(). The amount does not have to be exactly the same as what was passed to starpu\_memory\_allocate(), only the eventual amount needs to be the same, i.e. one call to starpu\_memory\_allocate() can be followed by several calls to starpu\_memory\_deallocate() to declare the deallocation piece by piece.

27.3.3.12 void starpu\_memory\_wait\_available ( unsigned node, size\_t size )

If a memory limit is defined on the given node (see Section How to limit memory used by StarPU and cache buffer allocations), this will wait for <code>size</code> bytes to become available on <code>node</code>. Of course, since another thread may be allocating memory concurrently, this does not necessarily mean that this amount will be actually available, just that it was reached. To atomically wait for some amount of memory and reserve it, <code>starpu\_memory\_allocate()</code> should be used with the <code>STARPU\_MEMORY\_WAIT</code> flag.

#### 27.4 Toolbox

The following macros allow to make GCC extensions portable, and to have a code which can be compiled with any C compiler.

#### **Macros**

- #define STARPU GNUC PREREQ(maj, min)
- #define STARPU UNLIKELY(expr)
- #define STARPU LIKELY(expr)
- #define STARPU\_ATTRIBUTE\_UNUSED
- #define STARPU ATTRIBUTE INTERNAL
- #define STARPU\_ATTRIBUTE\_MALLOC
- #define STARPU\_ATTRIBUTE\_WARN\_UNUSED\_RESULT
- #define STARPU\_ATTRIBUTE\_PURE
- #define STARPU\_ATTRIBUTE\_ALIGNED(size)
- #define STARPU\_WARN\_UNUSED\_RESULT
- #define STARPU\_POISON\_PTR
- #define STARPU MIN(a, b)
- #define STARPU MAX(a, b)
- #define STARPU\_ASSERT(x)

- #define STARPU\_ASSERT\_MSG(x, msg,...)
- #define STARPU\_ABORT()
- #define STARPU\_ABORT\_MSG(msg,...)
- #define STARPU\_CHECK\_RETURN\_VALUE(err, message,...)
- #define STARPU CHECK RETURN VALUE IS(err, value, message,...)
- #define STARPU RMB()
- #define STARPU WMB()

#### **Functions**

• static \_\_starpu\_inline int starpu\_get\_env\_number (const char \*str)

#### 27.4.1 Detailed Description

The following macros allow to make GCC extensions portable, and to have a code which can be compiled with any C compiler.

#### 27.4.2 Macro Definition Documentation

```
27.4.2.1 #define STARPU_GNUC_PREREQ( maj, min )
```

Return true (non-zero) if GCC version MAJ.MIN or later is being used (macro taken from glibc.)

```
27.4.2.2 #define STARPU_UNLIKELY( expr )
```

When building with a GNU C Compiler, this macro allows programmers to mark an expression as unlikely.

```
27.4.2.3 #define STARPU_LIKELY( expr )
```

When building with a GNU C Compiler, this macro allows programmers to mark an expression as likely.

#### 27.4.2.4 #define STARPU\_ATTRIBUTE\_UNUSED

When building with a GNU C Compiler, this macro is defined to \_\_attribute\_\_((unused))

#### 27.4.2.5 #define STARPU\_ATTRIBUTE\_INTERNAL

When building with a GNU C Compiler, this macro is defined to \_\_attribute\_\_((visibility ("internal")))

#### 27.4.2.6 #define STARPU\_ATTRIBUTE\_MALLOC

When building with a GNU C Compiler, this macro is defined to \_\_attribute\_\_((malloc))

#### 27.4.2.7 #define STARPU\_ATTRIBUTE\_WARN\_UNUSED\_RESULT

When building with a GNU C Compiler, this macro is defined to \_\_attribute\_\_((warn\_unused\_result))

#### 27.4.2.8 #define STARPU\_ATTRIBUTE\_PURE

When building with a GNU C Compiler, this macro is defined to \_\_attribute\_\_((pure))

27.4 Toolbox 167

```
27.4.2.9 #define STARPU_ATTRIBUTE_ALIGNED( size )
When building with a GNU C Compiler, this macro is defined to __attribute __((aligned(size)))
27.4.2.10 #define STARPU_WARN_UNUSED_RESULT
When building with a GNU C Compiler, this macro is defined to attribute (( warn unused result ))
27.4.2.11 #define STARPU_POISON_PTR
This macro defines a value which can be used to mark pointers as invalid values.
27.4.2.12 #define STARPU_MIN( a, b)
This macro returns the min of the two parameters.
27.4.2.13 #define STARPU_MAX( a, b)
This macro returns the max of the two parameters.
27.4.2.14 #define STARPU_ASSERT( x )
Unless StarPU has been configured with the option --enable-fast, this macro will abort if the expression is false.
27.4.2.15 #define STARPU_ASSERT_MSG( x, msg, ... )
Unless StarPU has been configured with the option --enable-fast, this macro will abort if the expression is false. The
given message will be displayed.
27.4.2.16 #define STARPU_ABORT( )
This macro aborts the program.
27.4.2.17 #define STARPU_ABORT_MSG( msg, ... )
This macro aborts the program, and displays the given message.
27.4.2.18 #define STARPU_CHECK_RETURN_VALUE( err, message, ... )
If err has a value which is not 0, the given message is displayed before aborting.
27.4.2.19 #define STARPU_CHECK_RETURN_VALUE_IS( err, value, message, ... )
If err has a value which is not value, the given message is displayed before aborting.
27.4.2.20 #define STARPU_RMB( )
```

This macro can be used to do a synchronization.

#### 27.4.2.21 #define STARPU\_WMB( )

This macro can be used to do a synchronization.

#### 27.4.3 Function Documentation

```
27.4.3.1 int starpu_get_env_number ( const char * str ) [static]
```

If str is the name of a existing environment variable which is defined to an integer, the function returns the value of the integer. It returns 0 otherwise.

#### 27.5 Threads

This section describes the thread facilities provided by StarPU. The thread function are either implemented on top of the pthread library or the Simgrid library when the simulated performance mode is enabled (SimGrid Support).

#### **Macros**

- #define STARPU\_PTHREAD\_CREATE\_ON(name, thread, attr, routine, arg, where)
- #define STARPU PTHREAD CREATE(thread, attr, routine, arg)
- #define STARPU PTHREAD MUTEX INIT(mutex, attr)
- #define STARPU\_PTHREAD\_MUTEX\_DESTROY(mutex)
- #define STARPU\_PTHREAD\_MUTEX\_LOCK(mutex)
- #define STARPU\_PTHREAD\_MUTEX\_UNLOCK(mutex)
- #define STARPU\_PTHREAD\_KEY\_CREATE(key, destr)
- #define STARPU\_PTHREAD\_KEY\_DELETE(key)
- #define STARPU\_PTHREAD\_SETSPECIFIC(key, ptr)
- #define STARPU\_PTHREAD\_GETSPECIFIC(key)
- #define STARPU\_PTHREAD\_RWLOCK\_INIT(rwlock, attr)
- #define STARPU\_PTHREAD\_RWLOCK\_RDLOCK(rwlock)
- #define STARPU\_PTHREAD\_RWLOCK\_WRLOCK(rwlock)
- #define STARPU\_PTHREAD\_RWLOCK\_UNLOCK(rwlock)
- #define STARPU\_PTHREAD\_RWLOCK\_DESTROY(rwlock)
- #define STARPU\_PTHREAD\_COND\_INIT(cond, attr)#define STARPU\_PTHREAD\_COND\_DESTROY(cond)
- #define STARPU PTHREAD COND SIGNAL(cond)
- "I CARROL DALIBEAR COMP. PROABCACT
- #define STARPU\_PTHREAD\_COND\_BROADCAST(cond)
- #define STARPU\_PTHREAD\_COND\_WAIT(cond, mutex)
- #define STARPU\_PTHREAD\_BARRIER\_INIT(barrier, attr, count)
- #define STARPU\_PTHREAD\_BARRIER\_DESTROY(barrier)
- #define STARPU\_PTHREAD\_BARRIER\_WAIT(barrier)
- #define STARPU\_PTHREAD\_MUTEX\_INITIALIZER
- #define STARPU\_PTHREAD\_COND\_INITIALIZER

#### **Functions**

- int starpu\_pthread\_create (starpu\_pthread\_t \*thread, const starpu\_pthread\_attr\_t \*attr, void \*(\*start\_-routine)(void \*), void \*arg)
- int starpu\_pthread\_join (starpu\_pthread\_t thread, void \*\*retval)
- int starpu\_pthread\_exit (void \*retval) STARPU\_ATTRIBUTE\_NORETURN
- int starpu pthread attr init (starpu pthread attr t \*attr)
- int starpu\_pthread\_attr\_destroy (starpu\_pthread\_attr\_t \*attr)

27.5 Threads 169

- int starpu\_pthread\_attr\_setdetachstate (starpu\_pthread\_attr\_t \*attr, int detachstate)
- int starpu\_pthread\_mutex\_init (starpu\_pthread\_mutex\_t \*mutex, const starpu\_pthread\_mutexattr\_t \*mutexattr)
- int starpu pthread mutex destroy (starpu pthread mutex t \*mutex)
- int starpu pthread mutex lock (starpu pthread mutex t \*mutex)
- int starpu\_pthread\_mutex\_unlock (starpu\_pthread\_mutex\_t \*mutex)
- int starpu pthread mutex trylock (starpu pthread mutex t \*mutex)
- int starpu\_pthread\_mutexattr\_gettype (const starpu\_pthread\_mutexattr\_t \*attr, int \*type)
- int starpu\_pthread\_mutexattr\_settype (starpu\_pthread\_mutexattr\_t \*attr, int type)
- int starpu pthread mutexattr destroy (starpu pthread mutexattr t \*attr)
- int starpu pthread mutexattr init (starpu pthread mutexattr t \*attr)
- int starpu\_pthread\_key\_create (starpu\_pthread\_key\_t \*key, void(\*destr\_function)(void \*))
- int starpu\_pthread\_key\_delete (starpu\_pthread\_key\_t key)
- int starpu\_pthread\_setspecific (starpu\_pthread\_key\_t key, const void \*pointer)
- void \* starpu pthread getspecific (starpu pthread key t key)
- int starpu pthread cond init (starpu pthread cond t \*cond, starpu pthread condattr t \*cond attr)
- int starpu pthread cond signal (starpu pthread cond t \*cond)
- int starpu pthread cond broadcast (starpu pthread cond t \*cond)
- int starpu\_pthread\_cond\_wait (starpu\_pthread\_cond\_t \*cond, starpu\_pthread\_mutex\_t \*mutex)
- int starpu\_pthread\_cond\_timedwait (starpu\_pthread\_cond\_t \*cond, starpu\_pthread\_mutex\_t \*mutex, const struct timespec \*abstime)
- int starpu\_pthread\_cond\_destroy (starpu\_pthread\_cond\_t \*cond)
- int starpu\_pthread\_rwlock\_init (starpu\_pthread\_rwlock\_t \*rwlock, const starpu\_pthread\_rwlockattr\_t \*attr)
- int starpu\_pthread\_rwlock\_destroy (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu pthread rwlock rdlock (starpu pthread rwlock t \*rwlock)
- int starpu pthread rwlock tryrdlock (starpu pthread rwlock t \*rwlock)
- int starpu pthread rwlock wrlock (starpu pthread rwlock t \*rwlock)
- int starpu\_pthread\_rwlock\_trywrlock (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu\_pthread\_rwlock\_unlock (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu\_pthread\_barrier\_init (starpu\_pthread\_barrier\_t \*barrier, const starpu\_pthread\_barrierattr\_t \*attr, unsigned count)
- int starpu\_pthread\_barrier\_destroy (starpu\_pthread\_barrier\_t \*barrier)
- int starpu\_pthread\_barrier\_wait (starpu\_pthread\_barrier\_t \*barrier)
- int starpu\_pthread\_spin\_init (starpu\_pthread\_spinlock\_t \*lock, int pshared)
- int starpu\_pthread\_spin\_destroy (starpu\_pthread\_spinlock\_t \*lock)
- int starpu\_pthread\_spin\_lock (starpu\_pthread\_spinlock\_t \*lock)
- int starpu\_pthread\_spin\_trylock (starpu\_pthread\_spinlock\_t \*lock)
- int starpu\_pthread\_spin\_unlock (starpu\_pthread\_spinlock\_t \*lock)

#### 27.5.1 Detailed Description

This section describes the thread facilities provided by StarPU. The thread function are either implemented on top of the pthread library or the Simgrid library when the simulated performance mode is enabled (SimGrid Support).

#### 27.5.2 Macro Definition Documentation

27.5.2.1 #define STARPU\_PTHREAD\_CREATE\_ON( name, thread, attr, routine, arg, where )

This macro calls the function starpu\_pthread\_create\_on() and aborts on error.

27.5.2.2 #define STARPU\_PTHREAD\_CREATE( thread, attr, routine, arg )

This macro calls the function starpu\_pthread\_create() and aborts on error.

```
27.5.2.3 #define STARPU_PTHREAD_MUTEX_INIT( mutex, attr )
```

This macro calls the function starpu\_pthread\_mutex\_init() and aborts on error.

```
27.5.2.4 #define STARPU_PTHREAD_MUTEX_DESTROY( mutex )
```

This macro calls the function <a href="mailto:starpu\_pthread\_mutex\_destroy">starpu\_pthread\_mutex\_destroy</a>() and aborts on error.

```
27.5.2.5 #define STARPU_PTHREAD_MUTEX_LOCK( mutex )
```

This macro calls the function starpu\_pthread\_mutex\_lock() and aborts on error.

```
27.5.2.6 #define STARPU_PTHREAD_MUTEX_UNLOCK( mutex )
```

This macro calls the function starpu\_pthread\_mutex\_unlock() and aborts on error.

```
27.5.2.7 #define STARPU_PTHREAD_KEY_CREATE( key, destr )
```

This macro calls the function starpu\_pthread\_key\_create() and aborts on error.

```
27.5.2.8 #define STARPU_PTHREAD_KEY_DELETE( key )
```

This macro calls the function starpu\_pthread\_key\_delete() and aborts on error.

```
27.5.2.9 #define STARPU_PTHREAD_SETSPECIFIC( key, ptr )
```

This macro calls the function starpu\_pthread\_setspecific() and aborts on error.

```
27.5.2.10 #define STARPU_PTHREAD_GETSPECIFIC( key )
```

This macro calls the function starpu\_pthread\_getspecific() and aborts on error.

```
27.5.2.11 #define STARPU_PTHREAD_RWLOCK_INIT( rwlock, attr )
```

This macro calls the function starpu pthread rwlock init() and aborts on error.

```
27.5.2.12 #define STARPU_PTHREAD_RWLOCK_RDLOCK( rwlock )
```

This macro calls the function starpu\_pthread\_rwlock\_rdlock() and aborts on error.

```
27.5.2.13 #define STARPU_PTHREAD_RWLOCK_WRLOCK( rwlock )
```

This macro calls the function <a href="mailto:starpu\_pthread\_rwlock\_wrlock">starpu\_pthread\_rwlock\_wrlock</a>() and aborts on error.

```
27.5.2.14 #define STARPU_PTHREAD_RWLOCK_UNLOCK( rwlock )
```

This macro calls the function starpu\_pthread\_rwlock\_unlock() and aborts on error.

27.5 Threads 171

27.5.2.15 #define STARPU\_PTHREAD\_RWLOCK\_DESTROY( rwlock )

This macro calls the function <a href="mailto:starpu\_pthread\_rwlock\_destroy">starpu\_pthread\_rwlock\_destroy</a>() and aborts on error.

27.5.2.16 #define STARPU\_PTHREAD\_COND\_INIT( cond, attr )

This macro calls the function starpu\_pthread\_cond\_init() and aborts on error.

27.5.2.17 #define STARPU\_PTHREAD\_COND\_DESTROY( cond )

This macro calls the function starpu pthread cond destroy() and aborts on error.

27.5.2.18 #define STARPU\_PTHREAD\_COND\_SIGNAL( cond )

This macro calls the function starpu\_pthread\_cond\_signal() and aborts on error.

27.5.2.19 #define STARPU\_PTHREAD\_COND\_BROADCAST( cond )

This macro calls the function starpu pthread cond broadcast() and aborts on error.

27.5.2.20 #define STARPU\_PTHREAD\_COND\_WAIT( cond, mutex )

This macro calls the function starpu\_pthread\_cond\_wait() and aborts on error.

27.5.2.21 #define STARPU\_PTHREAD\_BARRIER\_INIT( barrier, attr, count )

This macro calls the function starpu\_pthread\_barrier\_init() and aborts on error.

27.5.2.22 #define STARPU\_PTHREAD\_BARRIER\_DESTROY( barrier )

This macro calls the function starpu\_pthread\_barrier\_destroy() and aborts on error.

27.5.2.23 #define STARPU\_PTHREAD\_BARRIER\_WAIT( barrier )

This macro calls the function starpu\_pthread\_barrier\_wait() and aborts on error.

27.5.2.24 STARPU\_PTHREAD\_MUTEX\_INITIALIZER

This macro initializes the mutex given in parameter.

27.5.2.25 STARPU\_PTHREAD\_COND\_INITIALIZER

This macro initializes the condition variable given in parameter.

27.5.3 Function Documentation

27.5.3.1 int starpu\_pthread\_create ( starpu\_pthread\_t \* thread, const starpu\_pthread\_attr\_t \* attr, void \*(\*)(void \*) start\_routine, void \* arg )

This function starts a new thread in the calling process. The new thread starts execution by invoking start\_routine; arg is passed as the sole argument of start\_routine.

27.5.3.2 int starpu\_pthread\_join ( starpu\_pthread\_t thread, void \*\* retval )

This function waits for the thread specified by thread to terminate. If that thread has already terminated, then the function returns immediately. The thread specified by thread must be joinable.

27.5.3.3 int starpu\_pthread\_exit ( void \* retval )

This function terminates the calling thread and returns a value via retval that (if the thread is joinable) is available to another thread in the same process that calls <a href="mailto:starpu\_pthread\_join">starpu\_pthread\_join</a>().

27.5.3.4 int starpu\_pthread\_attr\_init ( starpu\_pthread\_attr\_t \* attr )

This function initializes the thread attributes object pointed to by attr with default attribute values.

It does not do anything when the simulated performance mode is enabled (SimGrid Support).

27.5.3.5 int starpu\_pthread\_attr\_destroy ( starpu\_pthread\_attr\_t \* attr )

This function destroys a thread attributes object which is no longer required. Destroying a thread attributes object has no effect on threads that were created using that object.

It does not do anything when the simulated performance mode is enabled (SimGrid Support).

27.5.3.6 int starpu\_pthread\_attr\_setdetachstate ( starpu\_pthread\_attr\_t \* attr, int detachstate )

This function sets the detach state attribute of the thread attributes object referred to by attr to the value specified in detachstate. The detach state attribute determines whether a thread created using the thread attributes object attr will be created in a joinable or a detached state.

It does not do anything when the simulated performance mode is enabled (SimGrid Support).

27.5.3.7 int starpu\_pthread\_mutex\_init ( starpu\_pthread\_mutex\_t \* mutex, const starpu\_pthread\_mutexattr\_t \* mutexattr )

This function initializes the mutex object pointed to by mutex according to the mutex attributes specified in mutexattr. If mutexattr is NULL, default attributes are used instead.

27.5.3.8 int starpu\_pthread\_mutex\_destroy ( starpu\_pthread\_mutex\_t \* mutex )

This function destroys a mutex object, freeing the resources it might hold. The mutex must be unlocked on entrance.

27.5.3.9 int starpu\_pthread\_mutex\_lock ( starpu\_pthread\_mutex\_t \* mutex )

This function locks the given mutex. If the mutex is currently unlocked, it becomes locked and owned by the calling thread, and the function returns immediately. If the mutex is already locked by another thread, the function suspends the calling thread until the mutex is unlocked.

This function also produces trace when the configure option --enable-fxt-lock is enabled.

27.5 Threads 173

27.5.3.10 int starpu\_pthread\_mutex\_unlock ( starpu\_pthread\_mutex\_t \* mutex )

This function unlocks the given mutex. The mutex is assumed to be locked and owned by the calling thread on entrance to starpu\_pthread\_mutex\_unlock().

This function also produces trace when the configure option --enable-fxt-lock is enabled.

27.5.3.11 int starpu\_pthread\_mutex\_trylock ( starpu\_pthread\_mutex\_t \* mutex )

This function behaves identically to starpu\_pthread\_mutex\_lock(), except that it does not block the calling thread if the mutex is already locked by another thread (or by the calling thread in the case of a "fast" mutex). Instead, the function returns immediately with the error code EBUSY.

This function also produces trace when the configure option --enable-fxt-lock is enabled.

27.5.3.12 int starpu\_pthread\_mutexattr\_gettype ( const starpu\_pthread\_mutexattr\_t \* attr, int \* type )

todo

27.5.3.13 int starpu\_pthread\_mutexattr\_settype ( starpu\_pthread\_mutexattr\_t \* attr, int type )

todo

27.5.3.14 int starpu\_pthread\_mutexattr\_destroy ( starpu\_pthread\_mutexattr\_t \* attr )

todo

27.5.3.15 int starpu\_pthread\_mutexattr\_init ( starpu\_pthread\_mutexattr\_t \* attr )

todo

27.5.3.16 int starpu\_pthread\_key\_create ( starpu\_pthread\_key\_t \* key, void(\*)(void \*) destr\_function )

This function allocates a new TSD key. The key is stored in the location pointed to by key.

27.5.3.17 int starpu\_pthread\_key\_delete ( starpu\_pthread\_key\_t key )

This function deallocates a TSD key. It does not check whether non-NULL values are associated with that key in the currently executing threads, nor call the destructor function associated with the key.

27.5.3.18 int starpu\_pthread\_setspecific ( starpu\_pthread\_key\_t key, const void \* pointer )

This function changes the value associated with key in the calling thread, storing the given pointer instead.

27.5.3.19 \* starpu\_pthread\_getspecific ( starpu\_pthread\_key\_t key )

This function returns the value associated with key on success, and NULL on error.

27.5.3.20 starpu\_pthread\_cond\_init ( starpu\_pthread\_cond\_t \* cond, starpu\_pthread\_condattr\_t \* cond\_attr )

This function initializes the condition variable cond, using the condition attributes specified in cond\_attr, or default attributes if cond\_attr is NULL.

```
27.5.3.21 starpu_pthread_cond_signal ( starpu_pthread_cond_t * cond )
```

This function restarts one of the threads that are waiting on the condition variable cond. If no threads are waiting on cond, nothing happens. If several threads are waiting on cond, exactly one is restarted, but it not specified which.

```
27.5.3.22 starpu_pthread_cond_broadcast ( starpu_pthread_cond_t * cond )
```

This function restarts all the threads that are waiting on the condition variable cond. Nothing happens if no threads are waiting on cond.

```
27.5.3.23 starpu_pthread_cond_wait ( starpu_pthread_cond_t * cond, starpu_pthread_mutex_t * mutex )
```

This function atomically unlocks the mutex (as per starpu\_pthread\_mutex\_unlock()) and waits for the condition variable <code>cond</code> to be signaled. The thread execution is suspended and does not consume any CPU time until the condition variable is signaled. The mutex must be locked by the calling thread on entrance to starpu\_pthread\_cond-wait(). Before returning to the calling thread, the function re-acquires mutex (as per starpu\_pthread\_mutex\_lock()).

This function also produces trace when the configure option --enable-fxt-lock is enabled.

```
27.5.3.24 starpu_pthread_cond_timedwait ( starpu_pthread_cond_t * cond, starpu_pthread_mutex_t * mutex, const struct timespec * abstime )
```

This function atomically unlocks mutex and waits on cond, as starpu\_pthread\_cond\_wait() does, but it also bounds the duration of the wait.

```
27.5.3.25 starpu_pthread_cond_destroy ( starpu_pthread_cond_t * cond )
```

This function destroys a condition variable, freeing the resources it might hold. No threads must be waiting on the condition variable on entrance to the function.

```
27.5.3.26 starpu_pthread_rwlock_init ( starpu_pthread_rwlock_t * rwlock, const starpu_pthread_rwlockattr_t * attr )
```

This function is the same as starpu\_pthread\_mutex\_init().

```
27.5.3.27 starpu_pthread_rwlock_destroy ( starpu_pthread_rwlock_t * rwlock )
```

This function is the same as starpu\_pthread\_mutex\_destroy().

```
27.5.3.28 starpu_pthread_rwlock_rdlock ( starpu_pthread_rwlock_t * rwlock )
```

This function is the same as starpu pthread mutex lock().

27.5.3.29 int starpu\_pthread\_rwlock\_tryrdlock ( starpu\_pthread\_rwlock\_t \* rwlock )

todo

27.5.3.30 starpu\_pthread\_rwlock\_wrlock ( starpu\_pthread\_rwlock\_t \* rwlock )

This function is the same as starpu\_pthread\_mutex\_lock().

27.6 Bitmap 175

```
int starpu_pthread_rwlock_trywrlock ( starpu_pthread_rwlock_t * rwlock )
todo
27.5.3.32 starpu_pthread_rwlock_unlock ( starpu_pthread_rwlock_t * rwlock )
This function is the same as starpu_pthread_mutex_unlock().
27.5.3.33 int starpu_pthread_barrier_init ( starpu_pthread_barrier_t * barrier, const starpu_pthread_barrierattr_t * attr,
          unsigned count )
todo
          int starpu_pthread_barrier_destroy ( starpu_pthread_barrier_t * barrier )
27.5.3.34
todo
27.5.3.35 int starpu_pthread_barrier_wait ( starpu_pthread_barrier_t * barrier )
todo
27.5.3.36 int starpu_pthread_spin_init ( starpu_pthread_spinlock_t * lock, int pshared )
todo
27.5.3.37 int starpu_pthread_spin_destroy ( starpu_pthread_spinlock_t * lock )
todo
27.5.3.38 int starpu_pthread_spin_lock ( starpu_pthread_spinlock_t * lock )
todo
27.5.3.39 int starpu_pthread_spin_trylock ( starpu_pthread_spinlock_t * lock )
todo
27.5.3.40 int starpu_pthread_spin_unlock ( starpu_pthread_spinlock_t * lock )
todo
```

#### 27.6 Bitmap

This section describes the bitmap facilities provided by StarPU.

#### **Functions**

- struct starpu bitmap \* starpu bitmap create (void)
- void starpu\_bitmap\_destroy (struct starpu\_bitmap \*b)
- void starpu\_bitmap\_set (struct starpu\_bitmap \*b, int e)
- void starpu\_bitmap\_unset (struct starpu\_bitmap \*b, int e)
- void starpu bitmap unset all (struct starpu bitmap \*b)
- int starpu\_bitmap\_get (struct starpu\_bitmap \*b, int e)
- void starpu\_bitmap unset\_and (struct starpu\_bitmap \*a, struct starpu\_bitmap \*b, struct starpu\_bitmap \*c)
- void starpu bitmap or (struct starpu bitmap \*a, struct starpu bitmap \*b)
- int starpu\_bitmap\_and\_get (struct starpu\_bitmap \*b1, struct starpu\_bitmap \*b2, int e)
- int starpu\_bitmap\_cardinal (struct starpu\_bitmap \*b)
- int starpu\_bitmap\_first (struct starpu\_bitmap \*b)
- int starpu\_bitmap\_last (struct starpu\_bitmap \*b)
- int starpu\_bitmap\_next (struct starpu\_bitmap \*b, int e)
- int starpu\_bitmap\_has\_next (struct starpu\_bitmap \*b, int e)

#### 27.6.1 Detailed Description

This section describes the bitmap facilities provided by StarPU.

#### 27.6.2 Function Documentation

```
27.6.2.1 struct starpu_bitmap * starpu_bitmap_create ( void )  [read]
create a empty starpu_bitmap
27.6.2.2 void starpu_bitmap_destroy ( struct starpu_bitmap * b )
free a starpu_bitmap
27.6.2.3 void starpu_bitmap_set ( struct starpu_bitmap * b, int e )
set bit e in b
27.6.2.4 void starpu_bitmap_unset ( struct starpu_bitmap * b, int e )
unset bit e in b
27.6.2.5 void starpu_bitmap_unset_all ( struct starpu_bitmap * b )
unset all bits in b
27.6.2.6 int starpu_bitmap_get ( struct starpu_bitmap * b, int e )
return true iff bit e is set in b
27.6.2.7 void starpu_bitmap_unset_and ( struct starpu_bitmap * a, struct starpu_bitmap * b, struct starpu_bitmap * c )
Basically compute starpu_bitmap_unset_all(a); a = b & c;
```

```
27.6.2.8 void starpu_bitmap_or ( struct starpu_bitmap * a, struct starpu_bitmap * b )

Basically compute a |= b

27.6.2.9 int starpu_bitmap_and_get ( struct starpu_bitmap * b1, struct starpu_bitmap * b2, int e )

return 1 iff e set in b1 AND e set in b2

27.6.2.10 int starpu_bitmap_cardinal ( struct starpu_bitmap * b )

return the number of set bits in b

27.6.2.11 int starpu_bitmap_first ( struct starpu_bitmap * b )

return the index of first set bit of b, -1 if none

27.6.2.12 int starpu_bitmap_last ( struct starpu_bitmap * b )

return the position of the last set bit of b, -1 if none

27.6.2.13 int starpu_bitmap_next ( struct starpu_bitmap * b, int e )

return the position of set bit right after e in b, -1 if none
```

# 27.7 Workers' Properties

#### **Data Structures**

- struct starpu\_worker\_collection
- struct starpu\_sched\_ctx\_iterator

### **Macros**

• #define STARPU NMAXWORKERS

## **Enumerations**

- enum starpu\_node\_kind {
   STARPU\_UNUSED, STARPU\_CPU\_RAM, STARPU\_CUDA\_RAM, STARPU\_OPENCL\_RAM,
   STARPU\_DISK\_RAM, STARPU\_MIC\_RAM, STARPU\_SCC\_RAM, STARPU\_SCC\_SHM }
- enum starpu\_worker\_archtype {
   STARPU\_CPU\_WORKER, STARPU\_CUDA\_WORKER, STARPU\_OPENCL\_WORKER, STARPU\_MIC\_-WORKER,
   STARPU\_SCC\_WORKER, STARPU\_ANY\_WORKER }
- enum starpu\_worker\_collection\_type { STARPU\_WORKER\_TREE, STARPU\_WORKER\_LIST }

### **Functions**

- unsigned starpu\_worker\_get\_count (void)
- int starpu\_worker\_get\_count\_by\_type (enum starpu\_worker\_archtype type)
- unsigned starpu\_cpu\_worker\_get\_count (void)
- · unsigned starpu cuda worker get count (void)
- unsigned starpu\_mic\_worker\_get\_count (void)
- unsigned starpu mic device get count (void)
- unsigned starpu\_scc\_worker\_get\_count (void)
- unsigned starpu\_opencl\_worker\_get\_count (void)
- int starpu\_worker\_get\_id (void)
- int starpu\_worker\_get\_ids\_by\_type (enum starpu\_worker\_archtype type, int \*workerids, int maxsize)
- int starpu worker get by type (enum starpu worker archtype type, int num)
- int starpu\_worker\_get\_by\_devid (enum starpu\_worker\_archtype type, int devid)
- int starpu worker get devid (int id)
- enum starpu\_worker\_archtype starpu\_worker\_get\_type (int id)
- void starpu\_worker\_get\_name (int id, char \*dst, size\_t maxlen)
- unsigned starpu\_worker\_get\_memory\_node (unsigned workerid)
- enum starpu\_node\_kind starpu\_node\_get\_kind (unsigned node)
- char \* starpu\_worker\_get\_type\_as\_string (enum starpu\_worker\_archtype type)

## 27.7.1 Detailed Description

### 27.7.2 Data Structure Documentation

#### 27.7.2.1 struct starpu\_worker\_collection

A scheduling context manages a collection of workers that can be memorized using different data structures. Thus, a generic structure is available in order to simplify the choice of its type. Only the list data structure is available but further data structures(like tree) implementations are foreseen.

#### **Data Fields**

- void \* workerids
- unsigned nworkers
- void \* masters
- unsigned nmasters
- int present [STARPU NMAXWORKERS]
- int is\_master [STARPU\_NMAXWORKERS]
- enum starpu\_worker\_collection\_type type
- unsigned(\* has\_next )(struct starpu\_worker\_collection \*workers, struct starpu\_sched\_ctx\_iterator \*it)
- int(\* get\_next )(struct starpu\_worker\_collection \*workers, struct starpu\_sched\_ctx\_iterator \*it)
- unsigned(\* has\_next\_master )(struct starpu\_worker\_collection \*workers, struct starpu\_sched\_ctx\_iterator
   \*it)
- int(\* get\_next\_master)(struct starpu\_worker\_collection \*workers, struct starpu\_sched\_ctx\_iterator \*it)
- int(\* add )(struct starpu\_worker\_collection \*workers, int worker)
- int(\* remove )(struct starpu\_worker\_collection \*workers, int worker)
- void(\* init )(struct starpu\_worker\_collection \*workers)
- void(\* deinit )(struct starpu\_worker\_collection \*workers)
- void(\* init iterator)(struct starpu worker collection \*workers, struct starpu sched ctx iterator \*it)

## 27.7.2.1.1 Field Documentation

# 27.7.2.1.1.1 void \* starpu\_worker\_collection::workerids

The workerids managed by the collection

27.7.2.1.1.2 unsigned starpu\_worker\_collection::nworkers

The number of workers in the collection

27.7.2.1.1.3 enum starpu\_worker\_collection\_type starpu\_worker\_collection::type

The type of structure (currently STARPU\_WORKER\_LIST is the only one available)

27.7.2.1.1.4 unsigned(\* starpu\_worker\_collection::has\_next)(struct starpu\_worker\_collection \*workers, struct starpu\_sched\_ctx\_iterator \*it)

Checks if there is another element in collection

27.7.2.1.1.5 int(\* starpu\_worker\_collection::get\_next)(struct starpu\_worker\_collection \*workers, struct starpu sched ctx iterator \*it)

return the next element in the collection

27.7.2.1.1.6 int(\* starpu\_worker\_collection::add)(struct starpu worker collection \*workers, int worker)

add a new element in the collection

27.7.2.1.1.7 int(\* starpu\_worker\_collection::remove)(struct starpu\_worker\_collection \*workers, int worker)

remove an element from the collection

27.7.2.1.1.8 void(\* starpu\_worker\_collection::init)(struct starpu\_worker\_collection \*workers)

Initialize the collection

27.7.2.1.1.9 void(\* starpu\_worker\_collection::deinit)(struct starpu\_worker\_collection \*workers)

Deinitialize the colection

27.7.2.1.1.10 void(\* starpu\_worker\_collection::init\_iterator)(struct starpu\_worker\_collection \*workers, struct starpu\_sched\_ctx\_iterator \*it)

Initialize the cursor if there is one

27.7.2.2 struct starpu\_sched\_ctx\_iterator

Structure needed to iterate on the collection

#### **Data Fields**

int	cursor	The index of the current worker in the collection, needed when iterating
		on the collection.
void *	value	
void *	possible_value	
int	visited	

# 27.7.3 Macro Definition Documentation

## 27.7.3.1 #define STARPU\_NMAXWORKERS

Define the maximum number of workers managed by StarPU.

# 27.7.4 Enumeration Type Documentation

#### 27.7.4.1 enum starpu\_node\_kind

**TODO** 

#### **Enumerator:**

STARPU\_UNUSED TODO STARPU\_CPU\_RAM TODO STARPU\_CUDA\_RAM TODO STARPU\_OPENCL\_RAM TODO STARPU\_MIC\_RAM TODO

**STARPU\_SCC\_RAM** This node kind is not used anymore, but implementations in interfaces will be useful for MPI.

STARPU\_SCC\_SHM TODO

#### 27.7.4.2 enum starpu\_worker\_archtype

Worker Architecture Type

#### **Enumerator:**

STARPU\_CPU\_WORKER CPU core

STARPU\_CUDA\_WORKER NVIDIA CUDA device

STARPU\_OPENCL\_WORKER OpenCL device

STARPU\_MIC\_WORKER Intel MIC device

STARPU\_SCC\_WORKER Intel SCC device

STARPU\_ANY\_WORKER any worker, used in the hypervisor

### 27.7.4.3 enum starpu worker collection type

Types of structures the worker collection can implement

# **Enumerator:**

STARPU\_WORKER\_LIST The collection is an array

#### 27.7.5 Function Documentation

## 27.7.5.1 unsigned starpu\_worker\_get\_count ( void )

This function returns the number of workers (i.e. processing units executing StarPU tasks). The returned value should be at most STARPU NMAXWORKERS.

## 27.7.5.2 int starpu\_worker\_get\_count\_by\_type ( enum starpu\_worker\_archtype type )

Returns the number of workers of the given type. A positive (or NULL) value is returned in case of success, -EINVAL indicates that the type is not valid otherwise.

### 27.7.5.3 unsigned starpu\_cpu\_worker\_get\_count ( void )

This function returns the number of CPUs controlled by StarPU. The returned value should be at most STARPU\_-MAXCPUS.

27.7.5.4 unsigned starpu\_cuda\_worker\_get\_count ( void )

This function returns the number of CUDA devices controlled by StarPU. The returned value should be at most STARPU MAXCUDADEVS.

27.7.5.5 unsigned starpu\_mic\_worker\_get\_count ( void )

This function returns the number of MIC workers controlled by StarPU.

27.7.5.6 unsigned starpu\_mic\_device\_get\_count ( void )

This function returns the number of MIC devices controlled by StarPU. The returned value should be at most STA-RPU\_MAXMICDEVS.

27.7.5.7 unsigned starpu\_scc\_worker\_get\_count ( void )

This function returns the number of SCC devices controlled by StarPU. The returned value should be at most STARPU MAXSCCDEVS.

27.7.5.8 unsigned starpu\_opencl\_worker\_get\_count ( void )

This function returns the number of OpenCL devices controlled by StarPU. The returned value should be at most STARPU\_MAXOPENCLDEVS.

27.7.5.9 int starpu\_worker\_get\_id ( void )

This function returns the identifier of the current worker, i.e the one associated to the calling thread. The returned value is either -1 if the current context is not a StarPU worker (i.e. when called from the application outside a task or a callback), or an integer between 0 and starpu\_worker\_get\_count() - 1.

27.7.5.10 int starpu\_worker\_get\_ids\_by\_type ( enum starpu\_worker\_archtype type, int \* workerids, int maxsize )

This function gets the list of identifiers of workers with the given type. It fills the array workerids with the identifiers of the workers that have the type indicated in the first argument. The argument maxsize indicates the size of the array workerids. The returned value gives the number of identifiers that were put in the array. -ERANGE is returned is maxsize is lower than the number of workers with the appropriate type: in that case, the array is filled with the maxsize first elements. To avoid such overflows, the value of maxsize can be chosen by the means of the function starpu\_worker\_get\_count\_by\_type(), or by passing a value greater or equal to STARPU\_NMAXWORKERS.

27.7.5.11 int starpu\_worker\_get\_by\_type ( enum starpu\_worker\_archtype type, int num )

This returns the identifier of the num-th worker that has the specified type type. If there are no such worker, -1 is returned.

27.7.5.12 int starpu\_worker\_get\_by\_devid ( enum starpu\_worker\_archtype type, int devid )

This returns the identifier of the worker that has the specified type type and device id devid (which may not be the n-th, if some devices are skipped for instance). If there are no such worker, -1 is returned.

27.7.5.13 int starpu\_worker\_get\_devid ( int id )

27.7.5.14 enum starpu worker archtype starpu\_worker\_get\_type ( int id )

This function returns the type of processing unit associated to a worker. The worker identifier is a value returned by the function starpu\_worker\_get\_id()). The returned value indicates the architecture of the worker: STARPU\_CPU\_-WORKER for a CPU core, STARPU\_CUDA\_WORKER for a CUDA device, and STARPU\_OPENCL\_WORKER for a OpenCL device. The value returned for an invalid identifier is unspecified.

27.7.5.15 void starpu\_worker\_get\_name ( int id, char \* dst, size\_t maxlen )

This function allows to get the name of a given worker. StarPU associates a unique human readable string to each processing unit. This function copies at most the maxlen first bytes of the unique string associated to a worker identified by its identifier id into the dst buffer. The caller is responsible for ensuring that dst is a valid pointer to a buffer of maxlen bytes at least. Calling this function on an invalid identifier results in an unspecified behaviour.

27.7.5.16 unsigned starpu\_worker\_get\_memory\_node ( unsigned workerid )

This function returns the identifier of the memory node associated to the worker identified by workerid.

27.7.5.17 enum starpu\_node\_kind starpu\_node\_get\_kind ( unsigned node )

Returns the type of the given node as defined by starpu\_node\_kind. For example, when defining a new data interface, this function should be used in the allocation function to determine on which device the memory needs to be allocated.

27.7.5.18 char \* starpu\_worker\_get\_type\_as\_string ( enum starpu\_worker\_archtype type )

Returns the given worker type as a string.

# 27.8 Data Management

This section describes the data management facilities provided by StarPU. We show how to use existing data interfaces in Data Interfaces, but developers can design their own data interfaces if required.

### **Typedefs**

- typedef struct \_starpu\_data\_state \* starpu\_data\_handle\_t
- typedef struct starpu arbiter \* starpu arbiter t

## **Enumerations**

enum starpu\_data\_access\_mode {
 STARPU\_NONE, STARPU\_R, STARPU\_W, STARPU\_RW,
 STARPU\_SCRATCH, STARPU\_REDUX, STARPU\_COMMUTE, STARPU\_SSEND,
 STARPU\_ACCESS\_MODE\_MAX }

27.8 Data Management 183

### **Basic Data Management API**

Data management is done at a high-level in StarPU: rather than accessing a mere list of contiguous buffers, the tasks may manipulate data that are described by a high-level construct which we call data interface.

An example of data interface is the "vector" interface which describes a contiguous data array on a spefic memory node. This interface is a simple structure containing the number of elements in the array, the size of the elements, and the address of the array in the appropriate address space (this address may be invalid if there is no valid copy of the array in the memory node). More informations on the data interfaces provided by StarPU are given in Data Interfaces.

When a piece of data managed by StarPU is used by a task, the task implementation is given a pointer to an interface describing a valid copy of the data that is accessible from the current processing unit.

Every worker is associated to a memory node which is a logical abstraction of the address space from which the processing unit gets its data. For instance, the memory node associated to the different CPU workers represents main memory (RAM), the memory node associated to a GPU is DRAM embedded on the device. Every memory node is identified by a logical index which is accessible from the function starpu\_worker\_get\_memory\_node(). When registering a piece of data to StarPU, the specified memory node indicates where the piece of data initially resides (we also call this memory node the home node of a piece of data).

- void starpu\_data\_register (starpu\_data\_handle\_t \*handleptr, unsigned home\_node, void \*data\_interface, struct starpu\_data\_interface ops \*ops)
- void starpu\_data\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node)
- void starpu\_data\_register\_same (starpu\_data\_handle\_t \*handledst, starpu\_data\_handle\_t handlesrc)
- void starpu\_data\_unregister (starpu\_data\_handle\_t handle)
- void starpu data unregister no coherency (starpu data handle t handle)
- void starpu\_data\_unregister\_submit (starpu\_data\_handle\_t handle)
- void starpu\_data\_invalidate (starpu\_data\_handle\_t handle)
- void starpu\_data\_invalidate\_submit (starpu\_data\_handle\_t handle)
- void starpu\_data\_set\_wt\_mask (starpu\_data\_handle\_t handle, uint32\_t wt\_mask)
- int starpu\_data\_fetch\_on\_node (starpu\_data\_handle\_t handle, unsigned node, unsigned async)
- int starpu\_data\_prefetch\_on\_node (starpu\_data\_handle\_t handle, unsigned node, unsigned async)
- · int starpu data idle prefetch on node (starpu data handle t handle, unsigned node, unsigned async)
- void starpu data wont use (starpu data handle t handle)
- starpu data handle t starpu data lookup (const void \*ptr)
- int starpu\_data\_request\_allocation (starpu\_data\_handle\_t handle, unsigned node)
- void starpu\_data\_query\_status (starpu\_data\_handle\_t handle, int memory\_node, int \*is\_allocated, int \*is\_requested)
- · void starpu data advise as important (starpu data handle t handle, unsigned is important)
- void starpu\_data\_set\_reduction\_methods (starpu\_data\_handle\_t handle, struct starpu\_codelet \*redux\_cl, struct starpu\_codelet \*init\_cl)
- struct starpu\_data\_interface\_ops \* starpu\_data\_get\_interface\_ops (starpu\_data\_handle\_t handle)

### Access registered data from the application

- #define STARPU DATA ACQUIRE CB(handle, mode, code)
- int starpu\_data\_acquire (starpu\_data\_handle\_t handle, enum starpu\_data\_access\_mode mode)
- int starpu\_data\_acquire\_cb (starpu\_data\_handle\_t handle, enum starpu\_data\_access\_mode mode, void(\*callback)(void \*), void \*arg)
- int starpu\_data\_acquire\_cb\_sequential\_consistency (starpu\_data\_handle\_t handle, enum starpu\_data\_access mode mode, void(\*callback)(void \*), void \*arg, int sequential consistency)
- int starpu\_data\_acquire\_on\_node (starpu\_data\_handle\_t handle, int node, enum starpu\_data\_access\_mode mode)
- int starpu\_data\_acquire\_on\_node\_cb (starpu\_data\_handle\_t handle, int node, enum starpu\_data\_access\_mode mode, void(\*callback)(void \*), void \*arg)

- int starpu\_data\_acquire\_on\_node\_cb\_sequential\_consistency (starpu\_data\_handle\_t handle, int node, enum starpu\_data\_access\_mode mode, void(\*callback)(void \*), void \*arg, int sequential\_consistency)
- void starpu\_data\_release (starpu\_data\_handle\_t handle)
- void starpu\_data\_release\_on\_node (starpu\_data\_handle\_t handle, int node)
- starpu arbiter t starpu arbiter create (void)
- void starpu data assign arbiter (starpu data handle t handle, starpu arbiter t arbiter)
- void starpu\_arbiter\_destroy (starpu\_arbiter\_t arbiter)

## 27.8.1 Detailed Description

This section describes the data management facilities provided by StarPU. We show how to use existing data interfaces in Data Interfaces, but developers can design their own data interfaces if required.

#### 27.8.2 Macro Definition Documentation

27.8.2.1 #define STARPU\_DATA\_ACQUIRE\_CB( handle, mode, code )

STARPU\_DATA\_ACQUIRE\_CB() is the same as starpu\_data\_acquire\_cb(), except that the code to be executed in a callback is directly provided as a macro parameter, and the data handle is automatically released after it. This permits to easily execute code which depends on the value of some registered data. This is non-blocking too and may be called from task callbacks.

### 27.8.3 Typedef Documentation

```
27.8.3.1 starpu data handle t
```

StarPU uses starpu\_data\_handle\_t as an opaque handle to manage a piece of data. Once a piece of data has been registered to StarPU, it is associated to a starpu\_data\_handle\_t which keeps track of the state of the piece of data over the entire machine, so that we can maintain data consistency and locate data replicates for instance.

```
27.8.3.2 starpu_arbiter_t
```

This is an arbiter, which implements an advanced but centralized management of concurrent data accesses, see Concurrent Data accesses for the details.

## 27.8.4 Enumeration Type Documentation

27.8.4.1 enum starpu data access mode

This datatype describes a data access mode.

## **Enumerator:**

STARPU\_NONE TODO

STARPU\_R read-only mode.

STARPU\_W write-only mode.

STARPU\_RW read-write mode. This is equivalent to STARPU\_R|STARPU\_W

STARPU\_SCRATCH A temporary buffer is allocated for the task, but StarPU does not enforce data consistency—i.e. each device has its own buffer, independently from each other (even for CPUs), and no data transfer is ever performed. This is useful for temporary variables to avoid allocating/freeing buffers inside each task. Currently, no behavior is defined concerning the relation with the STARPU\_R and STARPU\_W modes and the value provided at registration — i.e., the value of the scratch buffer is undefined

27.8 Data Management 185

at entry of the codelet function. It is being considered for future extensions at least to define the initial value. For now, data to be used in STARPU\_SCRATCH mode should be registered with node -1 and a NULL pointer, since the value of the provided buffer is simply ignored for now.

STARPU REDUX todo

**STARPU\_COMMUTE** In addition to that, STARPU\_COMMUTE can be passed along STARPU\_W or STAR-PU\_RW to express that StarPU can let tasks commute, which is useful e.g. when bringing a contribution into some data, which can be done in any order (but still require sequential consistency against reads or non-commutative writes).

**STARPU\_SSEND** used in starpu\_mpi\_insert\_task() to specify the data has to be sent using a synchronous and non-blocking mode (see starpu\_mpi\_issend())

#### 27.8.5 Function Documentation

27.8.5.1 void starpu\_data\_register ( starpu\_data\_handle\_t \* handleptr, unsigned home\_node, void \* data\_interface, struct starpu\_data\_interface ops \* ops )

Register a piece of data into the handle located at the handleptr address. The data\_interface buffer contains the initial description of the data in the home\_node. The ops argument is a pointer to a structure describing the different methods used to manipulate this type of interface. See starpu\_data\_interface\_ops for more details on this structure. If home\_node is -1, StarPU will automatically allocate the memory when it is used for the first time in write-only mode. Once such data handle has been automatically allocated, it is possible to access it using any access mode. Note that StarPU supplies a set of predefined types of interface (e.g. vector or matrix) which can be registered by the means of helper functions (e.g. starpu\_vector\_data\_register() or starpu\_matrix\_data\_register()).

27.8.5.2 void starpu\_data\_ptr\_register ( starpu\_data\_handle\_t handle, unsigned node )

Register that a buffer for handle on node will be set. This is typically used by starpu\_\*\_ptr\_register helpers before setting the interface pointers for this node, to tell the core that that is now allocated.

27.8.5.3 void starpu\_data\_register\_same ( starpu\_data\_handle\_t \* handledst, starpu\_data\_handle\_t handlesrc )

Register a new piece of data into the handle handledst with the same interface as the handle handlesrc.

27.8.5.4 void starpu\_data\_unregister ( starpu\_data\_handle\_t handle )

This function unregisters a data handle from StarPU. If the data was automatically allocated by StarPU because the home node was -1, all automatically allocated buffers are freed. Otherwise, a valid copy of the data is put back into the home node in the buffer that was initially registered. Using a data handle that has been unregistered from StarPU results in an undefined behaviour. In case we do not need to update the value of the data in the home node, we can use the function starpu\_data\_unregister\_no\_coherency() instead.

27.8.5.5 void starpu\_data\_unregister\_no\_coherency ( starpu\_data\_handle\_t handle )

This is the same as starpu\_data\_unregister(), except that StarPU does not put back a valid copy into the home node, in the buffer that was initially registered.

27.8.5.6 void starpu\_data\_unregister\_submit ( starpu\_data\_handle t handle )

Destroy the data handle once it is not needed anymore by any submitted task. No coherency is assumed.

27.8.5.7 void starpu\_data\_invalidate ( starpu\_data\_handle\_t handle )

Destroy all replicates of the data handle immediately. After data invalidation, the first access to the handle must be performed in write-only mode. Accessing an invalidated data in read-mode results in undefined behaviour.

27.8.5.8 void starpu\_data\_invalidate\_submit ( starpu\_data\_handle\_t handle )

Submits invalidation of the data handle after completion of previously submitted tasks.

27.8.5.9 void starpu\_data\_set\_wt\_mask ( starpu\_data\_handle\_t handle, uint32\_t wt\_mask )

This function sets the write-through mask of a given data (and its children), i.e. a bitmask of nodes where the data should be always replicated after modification. It also prevents the data from being evicted from these nodes when memory gets scarse. When the data is modified, it is automatically transferred into those memory node. For instance a 1 < < 0 write-through mask means that the CUDA workers will commit their changes in main memory (node 0).

27.8.5.10 int starpu\_data\_fetch\_on\_node ( starpu\_data\_handle\_t handle, unsigned node, unsigned async )

Issue a fetch request for a given data to a given node, i.e. requests that the data be replicated to the given node as soon as possible, so that it is available there for tasks. If the <code>async</code> parameter is 0, the call will block until the transfer is achieved, else the call will return immediately, after having just queued the request. In the latter case, the request will asynchronously wait for the completion of any task writing on the data.

27.8.5.11 int starpu\_data\_prefetch\_on\_node ( starpu\_data\_handle\_t handle, unsigned node, unsigned async )

Issue a prefetch request for a given data to a given node, i.e. requests that the data be replicated to the given node when there is room for it, so that it is available there for tasks. If the <code>async</code> parameter is 0, the call will block until the transfer is achieved, else the call will return immediately, after having just queued the request. In the latter case, the request will asynchronously wait for the completion of any task writing on the data.

27.8.5.12 int starpu\_data\_idle\_prefetch\_on\_node ( starpu\_data\_handle\_t handle, unsigned node, unsigned async )

Issue an idle prefetch request for a given data to a given node, i.e. requests that the data be replicated to the given node, so that it is available there for tasks, but only when the bus is really idle. If the <code>async</code> parameter is 0, the call will block until the transfer is achieved, else the call will return immediately, after having just queued the request. In the latter case, the request will asynchronously wait for the completion of any task writing on the data.

27.8.5.13 void starpu\_data\_wont\_use ( starpu data handle t handle )

Advise StarPU that this handle will not be used in the close future, and is thus a good candidate for eviction from GPUs. StarPU will thus write its value back to its home node when the bus is idle, and select this data in priority for eviction when memory gets low.

27.8.5.14 starpu\_data\_handle\_t starpu\_data\_lookup ( const void \* ptr )

Return the handle corresponding to the data pointed to by the ptr host pointer.

27.8.5.15 int starpu\_data\_request\_allocation ( starpu\_data\_handle\_t handle, unsigned node )

Explicitly ask StarPU to allocate room for a piece of data on the specified memory node.

27.8 Data Management 187

27.8.5.16 void starpu\_data\_query\_status ( starpu\_data\_handle\_t handle, int memory\_node, int \* is\_allocated, int \* is\_valid, int \* is\_requested )

Query the status of handle on the specified memory\_node.

27.8.5.17 void starpu\_data\_advise\_as\_important ( starpu\_data\_handle\_t handle, unsigned is\_important )

This function allows to specify that a piece of data can be discarded without impacting the application.

27.8.5.18 void starpu\_data\_set\_reduction\_methods ( starpu\_data\_handle\_t handle, struct starpu\_codelet \* redux\_cl, struct starpu codelet \* init\_cl )

This sets the codelets to be used for handle when it is accessed in the mode STARPU\_REDUX. Per-worker buffers will be initialized with the codelet  $init_cl$ , and reduction between per-worker buffers will be done with the codelet  $redux_cl$ .

```
27.8.5.19 struct starpu_data_interface_ops * starpu_data_get_interface_ops ( starpu_data_handle_t handle ) [read]
```

todo

27.8.5.20 int starpu\_data\_acquire ( starpu\_data\_handle\_t handle, enum starpu\_data\_access\_mode mode )

The application must call this function prior to accessing registered data from main memory outside tasks. StarPU ensures that the application will get an up-to-date copy of the data in main memory located where the data was originally registered, and that all concurrent accesses (e.g. from tasks) will be consistent with the access mode specified in the mode argument. starpu\_data\_release() must be called once the application does not need to access the piece of data anymore. Note that implicit data dependencies are also enforced by starpu\_data\_acquire(), i.e. starpu\_data\_acquire() will wait for all tasks scheduled to work on the data, unless they have been disabled explictly by calling starpu\_data\_set\_default\_sequential\_consistency\_flag() or starpu\_data\_set\_sequential\_consistency\_flag(). starpu\_data\_acquire() is a blocking call, so that it cannot be called from tasks or from their callbacks (in that case, starpu\_data\_acquire() returns -EDEADLK). Upon successful completion, this function returns 0.

```
27.8.5.21 int starpu_data_acquire_cb ( starpu_data_handle_t handle, enum starpu_data_access_mode mode, void(*)(void *) callback, void * arg )
```

Asynchronous equivalent of starpu\_data\_acquire(). When the data specified in handle is available in the appropriate access mode, the callback function is executed. The application may access the requested data during the execution of this callback. The callback function must call starpu\_data\_release() once the application does not need to access the piece of data anymore. Note that implicit data dependencies are also enforced by starpu\_data\_acquire\_cb() in case they are not disabled. Contrary to starpu\_data\_acquire(), this function is non-blocking and may be called from task callbacks. Upon successful completion, this function returns 0.

```
27.8.5.22 int starpu_data_acquire_cb_sequential_consistency ( starpu_data_handle_t handle, enum starpu_data_access_mode mode, void(*)(void *) callback, void * arg, int sequential_consistency )
```

Equivalent of starpu\_data\_acquire\_cb() with the possibility of enabling or disabling data dependencies. When the data specified in handle is available in the appropriate access mode, the callback function is executed. The application may access the requested data during the execution of this callback. The callback function must call starpu\_data\_release() once the application does not need to access the piece of data anymore. Note that implicit data dependencies are also enforced by starpu\_data\_acquire\_cb\_sequential\_consistency() in case they are not disabled specifically for the given handle or by the parameter sequential\_consistency. Similarly to starpu\_data\_acquire\_cb(), this function is non-blocking and may be called from task callbacks. Upon successful completion, this function returns 0.

```
27.8.5.23 int starpu_data_acquire_on_node ( starpu_data_handle_t handle, int node, enum starpu_data_access mode mode )
```

This is the same as starpu\_data\_acquire(), except that the data will be available on the given memory node instead of main memory.

```
27.8.5.24 int starpu_data_acquire_on_node_cb ( starpu_data_handle_t handle, int node, enum starpu_data_access_mode_mode, void(*)(void *) callback, void * arg )
```

This is the same as starpu\_data\_acquire\_cb(), except that the data will be available on the given memory node instead of main memory.

```
27.8.5.25 int starpu_data_acquire_on_node_cb_sequential_consistency ( starpu_data_handle_t handle, int node, enum starpu_data_access_mode mode, void(*)(void *) callback, void * arg, int sequential_consistency )
```

This is the same as starpu\_data\_acquire\_cb\_sequential\_consistency(), except that the data will be available on the given memory node instead of main memory.

```
27.8.5.26 void starpu_data_release ( starpu data handle t handle )
```

This function releases the piece of data acquired by the application either by starpu\_data\_acquire() or by starpu\_data\_acquire\_cb().

```
27.8.5.27 void starpu_data_release_on_node ( starpu_data_handle_t handle, int node )
```

This is the same as starpu\_data\_release(), except that the data will be available on the given memory node instead of main memory.

```
27.8.5.28 starpu_arbiter_t starpu_arbiter_create ( void )
```

This creates a data access arbiter, see Concurrent Data accesses for the details

```
27.8.5.29 void starpu_data_assign_arbiter ( starpu_data_handle_t handle, starpu_arbiter_t arbiter )
```

This makes accesses to handle managed by arbiter

```
27.8.5.30 void starpu_arbiter_destroy ( starpu_arbiter_t arbiter )
```

This destroys the arbiter. This must only be called after all data assigned to it have been unregistered.

### 27.9 Data Interfaces

## **Data Structures**

- · struct starpu data interface ops
- struct starpu\_data\_copy\_methods
- · struct starpu variable interface
- struct starpu\_vector\_interface
- · struct starpu matrix interface
- struct starpu\_block\_interface

- · struct starpu\_bcsr\_interface
- struct starpu csr interface
- · struct starpu\_coo\_interface

#### **Enumerations**

enum starpu\_data\_interface\_id {
 STARPU\_UNKNOWN\_INTERFACE\_ID, STARPU\_MATRIX\_INTERFACE\_ID, STARPU\_BLOCK\_INTERFACE\_ID, STARPU\_VECTOR\_INTERFACE\_ID,
 STARPU\_CSR\_INTERFACE\_ID, STARPU\_BCSR\_INTERFACE\_ID, STARPU\_VARIABLE\_INTERFACE\_ID,
 STARPU\_VOID\_INTERFACE\_ID,
 STARPU\_MULTIFORMAT\_INTERFACE\_ID, STARPU\_COO\_INTERFACE\_ID, STARPU\_MAX\_INTERFACE\_ID}

## **Registering Data**

There are several ways to register a memory region so that it can be managed by StarPU. The functions below allow the registration of vectors, 2D matrices, 3D matrices as well as BCSR and CSR sparse matrices.

- void starpu void data register (starpu data handle t \*handle)
- void starpu\_variable\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, size-\_t size)
- void starpu\_variable\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size t offset)
- void starpu\_vector\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, uint32-\_t nx, size\_t elemsize)
- void starpu\_vector\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size\_t offset)
- void starpu\_matrix\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, uint32-\_t ld, uint32\_t nx, uint32\_t ny, size\_t elemsize)
- void starpu\_matrix\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size t offset, uint32 t ld)
- void starpu\_block\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, uint32\_t ldy, uint32\_t ldz, uint32\_t nx, uint32\_t nx, uint32\_t nz, size\_t elemsize)
- void starpu\_block\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size\_t offset, uint32\_t ldy, uint32\_t ldz)
- void starpu\_bcsr\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uint32\_t nnz, uint32\_t nrow, uintptr\_t nzval, uint32\_t \*colind, uint32\_t \*rowptr, uint32\_t firstentry, uint32\_t r, uint32\_t c, size\_t elemsize)
- void starpu\_csr\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uint32\_t nnz, uint32\_t nrow, uintptr\_t nzval, uint32\_t \*colind, uint32\_t \*rowptr, uint32\_t firstentry, size\_t elemsize)
- void starpu\_coo\_data\_register (starpu\_data\_handle\_t \*handleptr, unsigned home\_node, uint32\_t nx, uint32\_t ny, uint32\_t n\_values, uint32\_t \*rows, uintptr\_t values, size\_t elemsize)
- void \* starpu data get interface on node (starpu data handle t handle, unsigned memory node)

# **Accessing Data Interfaces**

Each data interface is provided with a set of field access functions. The ones using a void \* parameter aimed to be used in codelet implementations (see for example the code in Vector Scaling Using StarPU's API).

- void \* starpu\_data\_handle\_to\_pointer (starpu\_data\_handle\_t handle, unsigned node)
- void \* starpu\_data\_get\_local\_ptr (starpu\_data\_handle\_t handle)
- enum starpu\_data\_interface\_id starpu\_data\_get\_interface\_id (starpu\_data\_handle\_t handle)
- size\_t starpu\_data\_get\_size (starpu\_data\_handle\_t handle)
- int starpu data pack (starpu data handle t handle, void \*\*ptr, starpu ssize t \*count)
- int starpu\_data\_unpack (starpu\_data\_handle\_t handle, void \*ptr, size\_t count)

## **Accessing Variable Data Interfaces**

- #define STARPU\_VARIABLE\_GET\_PTR(interface)
- #define STARPU\_VARIABLE\_GET\_ELEMSIZE(interface)
- #define STARPU\_VARIABLE\_GET\_DEV\_HANDLE(interface)
- #define STARPU VARIABLE GET OFFSET(interface)
- size t starpu variable get elemsize (starpu data handle t handle)
- uintptr t starpu variable get local ptr (starpu data handle t handle)

## **Accessing Vector Data Interfaces**

- #define STARPU\_VECTOR\_GET\_PTR(interface)
- #define STARPU\_VECTOR\_GET\_DEV\_HANDLE(interface)
- #define STARPU\_VECTOR\_GET\_OFFSET(interface)
- #define STARPU VECTOR GET NX(interface)
- #define STARPU VECTOR GET ELEMSIZE(interface)
- #define STARPU VECTOR GET SLICE BASE(interface)
- uint32\_t starpu\_vector\_get\_nx (starpu\_data\_handle\_t handle)
- size\_t starpu\_vector\_get\_elemsize (starpu\_data\_handle\_t handle)
- uintptr\_t starpu\_vector\_get\_local\_ptr (starpu\_data\_handle\_t handle)

### **Accessing Matrix Data Interfaces**

- #define STARPU MATRIX GET PTR(interface)
- #define STARPU MATRIX GET DEV HANDLE(interface)
- #define STARPU\_MATRIX\_GET\_OFFSET(interface)
- #define STARPU\_MATRIX\_GET\_NX(interface)
- #define STARPU\_MATRIX\_GET\_NY(interface)
- #define STARPU\_MATRIX\_GET\_LD(interface)
- #define STARPU MATRIX GET ELEMSIZE(interface)
- uint32 t starpu matrix get nx (starpu data handle t handle)
- uint32\_t starpu\_matrix\_get\_ny (starpu\_data\_handle\_t handle)
- uint32 t starpu matrix get local ld (starpu data handle t handle)
- uintptr\_t starpu\_matrix\_get\_local\_ptr (starpu\_data\_handle\_t handle)
- size\_t starpu\_matrix\_get\_elemsize (starpu\_data\_handle\_t handle)

### **Accessing Block Data Interfaces**

- #define STARPU BLOCK GET PTR(interface)
- #define STARPU BLOCK GET DEV HANDLE(interface)
- #define STARPU\_BLOCK\_GET\_OFFSET(interface)
- #define STARPU\_BLOCK\_GET\_NX(interface)
- #define STARPU\_BLOCK\_GET\_NY(interface)
- #define STARPU\_BLOCK\_GET\_NZ(interface)
- #define STARPU BLOCK GET LDY(interface)
- #define STARPU BLOCK GET LDZ(interface)
- #define STARPU\_BLOCK\_GET\_ELEMSIZE(interface)
- uint32\_t starpu\_block\_get\_nx (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_block\_get\_ny (starpu\_data\_handle\_t handle)
- uint32 t starpu block get nz (starpu data handle t handle)
- uint32\_t starpu\_block\_get\_local\_ldy (starpu\_data\_handle\_t handle)
- uint32 t starpu block get local ldz (starpu data handle t handle)
- uintptr\_t starpu\_block\_get\_local\_ptr (starpu\_data\_handle\_t handle)
- size\_t starpu\_block\_get\_elemsize (starpu\_data\_handle\_t handle)

### **Accessing BCSR Data Interfaces**

- #define STARPU BCSR GET NNZ(interface)
- #define STARPU\_BCSR\_GET\_NZVAL(interface)
- #define STARPU BCSR GET NZVAL DEV HANDLE(interface)
- #define STARPU BCSR GET COLIND(interface)
- #define STARPU BCSR GET COLIND DEV HANDLE(interface)
- #define STARPU BCSR GET ROWPTR(interface)
- #define STARPU BCSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU\_BCSR\_GET\_OFFSET
- uint32\_t starpu\_bcsr\_get\_nnz (starpu\_data\_handle\_t handle)
- uint32 t starpu bcsr get nrow (starpu data handle t handle)
- uint32\_t starpu\_bcsr\_get\_firstentry (starpu\_data\_handle\_t handle)
- uintptr t starpu bcsr get local nzval (starpu data handle t handle)
- uint32\_t \* starpu\_bcsr\_get\_local\_colind (starpu\_data\_handle\_t handle)
- uint32\_t \* starpu\_bcsr\_get\_local\_rowptr (starpu\_data\_handle\_t handle)
- uint32 t starpu bcsr get r (starpu data handle t handle)
- uint32 t starpu bcsr get c (starpu data handle t handle)
- size t starpu bcsr get elemsize (starpu data handle t handle)

## **Accessing CSR Data Interfaces**

- #define STARPU\_CSR\_GET\_NNZ(interface)
- #define STARPU CSR GET NROW(interface)
- #define STARPU\_CSR\_GET\_NZVAL(interface)
- #define STARPU\_CSR\_GET\_NZVAL\_DEV\_HANDLE(interface)
- #define STARPU\_CSR\_GET\_COLIND(interface)
- #define STARPU\_CSR\_GET\_COLIND\_DEV\_HANDLE(interface)
- #define STARPU CSR GET ROWPTR(interface)
- #define STARPU\_CSR\_GET\_ROWPTR\_DEV\_HANDLE(interface)
- #define STARPU\_CSR\_GET\_OFFSET
- #define STARPU CSR GET FIRSTENTRY(interface)
- #define STARPU CSR GET ELEMSIZE(interface)
- uint32\_t starpu\_csr\_get\_nnz (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_csr\_get\_nrow (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_csr\_get\_firstentry (starpu\_data\_handle\_t handle)
- uintptr\_t starpu\_csr\_get\_local\_nzval (starpu\_data\_handle\_t handle)
- uint32\_t \* starpu\_csr\_get\_local\_colind (starpu\_data\_handle\_t handle)
- uint32\_t \* starpu\_csr\_get\_local\_rowptr (starpu\_data\_handle\_t handle)
- size t starpu csr get elemsize (starpu data handle t handle)

## **Accessing COO Data Interfaces**

- #define STARPU\_COO\_GET\_COLUMNS(interface)
- #define STARPU\_COO\_GET\_COLUMNS\_DEV\_HANDLE(interface)
- #define STARPU COO GET ROWS(interface)
- #define STARPU COO GET ROWS DEV HANDLE(interface)
- #define STARPU\_COO\_GET\_VALUES(interface)
- #define STARPU COO GET VALUES DEV HANDLE(interface)
- #define STARPU COO GET OFFSET
- #define STARPU\_COO\_GET\_NX(interface)
- #define STARPU COO GET NY(interface)
- #define STARPU\_COO\_GET\_NVALUES(interface)
- #define STARPU\_COO\_GET\_ELEMSIZE(interface)

## **Defining Interface**

Applications can provide their own interface as shown in Defining A New Data Interface.

- uintptr t starpu malloc on node flags (unsigned dst node, size t size, int flags)
- void starpu\_free\_on\_node\_flags (unsigned dst\_node, uintptr\_t addr, size\_t size, int flags)
- uintptr\_t starpu\_malloc\_on\_node (unsigned dst\_node, size\_t size)
- void starpu\_free\_on\_node (unsigned dst\_node, uintptr\_t addr, size\_t size)
- void starpu\_malloc\_on\_node\_set\_default\_flags (unsigned node, int flags)
- int starpu\_interface\_copy (uintptr\_t src, size\_t src\_offset, unsigned src\_node, uintptr\_t dst, size\_t dst\_offset, unsigned dst\_node, size\_t size, void \*async\_data)
- uint32\_t starpu\_hash\_crc32c\_be\_n (const void \*input, size\_t n, uint32\_t inputcrc)
- uint32\_t starpu\_hash\_crc32c\_be (uint32\_t input, uint32\_t inputcrc)
- uint32\_t starpu\_hash\_crc32c\_string (const char \*str, uint32\_t inputcrc)
- int starpu\_data\_interface\_get\_next\_id (void)

## 27.9.1 Detailed Description

### 27.9.2 Data Structure Documentation

27.9.2.1 struct starpu\_data\_interface\_ops

Per-interface data transfer methods.

#### **Data Fields**

- void(\* register data handle )(starpu data handle t handle, unsigned home node, void \*data interface)
- starpu ssize t(\* allocate data on node)(void \*data interface, unsigned node)
- void(\* free\_data\_on\_node )(void \*data\_interface, unsigned node)
- struct starpu\_data\_copy\_methods \* copy\_methods
- void \*(\* handle\_to\_pointer)(starpu\_data\_handle\_t handle, unsigned node)
- size\_t(\* get\_size )(starpu\_data\_handle\_t handle)
- uint32\_t(\* footprint )(starpu\_data\_handle\_t handle)
- int(\* compare )(void \*data\_interface\_a, void \*data\_interface\_b)
- void(\* display )(starpu\_data\_handle\_t handle, FILE \*f)
- starpu\_ssize\_t(\* describe )(void \*data\_interface, char \*buf, size\_t size)
- · enum starpu data interface id interfaceid
- size\_t interface\_size
- · char is multiformat
- · char dontcache
- struct
  - starpu\_multiformat\_data\_interface\_ops \*(\* get\_mf\_ops )(void \*data\_interface)
- int(\* pack\_data )(starpu\_data\_handle\_t handle, unsigned node, void \*\*ptr, starpu\_ssize\_t \*count)
- int(\* unpack\_data )(starpu\_data\_handle\_t handle, unsigned node, void \*ptr, size\_t count)

## 27.9.2.1.1 Field Documentation

27.9.2.1.1.1 void(\* starpu\_data\_interface\_ops::register\_data\_handle)(starpu\_data\_handle\_t handle, unsigned home\_node, void \*data\_interface)

Register an existing interface into a data handle.

27.9.2.1.1.2 starpu\_ssize\_t(\* starpu\_data\_interface\_ops::allocate\_data\_on\_node)(void \*data\_interface, unsigned node)

Allocate data for the interface on a given node.

27.9.2.1.1.3 void(\* starpu\_data\_interface\_ops::free\_data\_on\_node)(void \*data\_interface, unsigned node)

Free data of the interface on a given node.

27.9.2.1.1.4 const struct starpu\_data\_copy\_methods \* starpu\_data\_interface\_ops::copy\_methods

ram/cuda/opencl synchronous and asynchronous transfer methods.

27.9.2.1.1.5 void \*(\* starpu\_data\_interface\_ops::handle\_to\_pointer)(starpu\_data\_handle\_t handle, unsigned node)

Return the current pointer (if any) for the handle on the given node.

27.9.2.1.1.6 size\_t(\* starpu\_data\_interface\_ops::get\_size)(starpu\_data\_handle\_t handle)

Return an estimation of the size of data, for performance models.

27.9.2.1.1.7 uint32\_t(\* starpu\_data\_interface\_ops::footprint)(starpu\_data\_handle\_t handle)

Return a 32bit footprint which characterizes the data size.

27.9.2.1.1.8 int(\* starpu\_data\_interface\_ops::compare)(void \*data\_interface\_a, void \*data\_interface\_b)

Compare the data size of two interfaces.

27.9.2.1.1.9 void(\* starpu\_data\_interface\_ops::display)(starpu\_data\_handle\_t handle, FILE \*f)

Dump the sizes of a handle to a file.

27.9.2.1.1.10 starpu\_ssize\_t(\* starpu\_data\_interface\_ops::describe)(void \*data\_interface, char \*buf, size\_t size)

Describe the data into a string.

27.9.2.1.1.11 enum starpu data interface id starpu\_data\_interface\_ops::interfaceid

An identifier that is unique to each interface.

27.9.2.1.1.12 size\_t starpu\_data\_interface\_ops::interface\_size

The size of the interface data descriptor.

27.9.2.1.1.13 char starpu\_data\_interface\_ops::is\_multiformat

todo

27.9.2.1.1.14 char starpu\_data\_interface\_ops::dontcache

If set to non-zero, StarPU will never try to reuse an allocated buffer for a different handle. This can be notably useful for application-defined interfaces which have a dynamic size, and for which it thus does not make sense to reuse the buffer since will probably not have the proper size.

```
27.9.2.1.1.15 struct starpu_multiformat_data_interface_ops *(* starpu_data_interface_ops::get_mf_ops)(void *data_interface) [read]
```

todo

27.9.2.1.1.16 int(\* starpu\_data\_interface\_ops::pack\_data)(starpu\_data\_handle\_t handle, unsigned node, void \*\*ptr, starpu\_ssize\_t \*count)

Pack the data handle into a contiguous buffer at the address allocated with starpu\_malloc\_flags(ptr, size, 0) (and thus returned in ptr) and set the size of the newly created buffer in count. If ptr is NULL, the function should not copy the data in the buffer but just set count to the size of the buffer which would have been allocated. The special value -1 indicates the size is yet unknown.

27.9.2.1.1.17 int(\* starpu\_data\_interface\_ops::unpack\_data)(starpu\_data\_handle\_t handle, unsigned node, void \*ptr, size\_t count)

Unpack the data handle from the contiguous buffer at the address ptr of size count

#### 27.9.2.2 struct starpu\_data\_copy\_methods

Defines the per-interface methods. If the any\_to\_any method is provided, it will be used by default if no more specific method is provided. It can still be useful to provide more specific method in case of e.g. available particular CUDA or OpenCL support.

#### **Data Fields**

- int(\* can\_copy )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, unsigned handling node)
- int(\* ram\_to\_ram )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* ram to cuda )(void \*src interface, unsigned src node, void \*dst interface, unsigned dst node)
- int(\* ram\_to\_opencl )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* ram to mic)(void \*src interface, unsigned src node, void \*dst interface, unsigned dst node)
- int(\* cuda\_to\_ram )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* cuda to cuda )(void \*src interface, unsigned src node, void \*dst interface, unsigned dst node)
- int(\* cuda to opencl )(void \*src interface, unsigned src node, void \*dst interface, unsigned dst node)
- int(\* opencl to ram )(void \*src interface, unsigned src node, void \*dst interface, unsigned dst node)
- int(\* opencl\_to\_cuda )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* opencl to opencl)(void \*src interface, unsigned src node, void \*dst interface, unsigned dst node)
- int(\* mic to ram)(void \*src interface, unsigned srd node, void \*dst interface, unsigned dst node)
- int(\* scc\_src\_to\_sink )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* scc\_sink\_to\_src )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* scc\_sink\_to\_sink )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* ram\_to\_cuda\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, starpu\_cudaStream\_t stream)
- int(\* cuda\_to\_ram\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, starpu cudaStream t stream)
- int(\* cuda\_to\_cuda\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, starpu\_cudaStream\_t stream)
- int(\* ram\_to\_opencl\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cl event \*event)
- int(\* opencl\_to\_ram\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cl\_event \*event)
- int(\* opencl\_to\_opencl\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cl\_event \*event)
- int(\* ram\_to\_mic\_async )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* mic\_to\_ram\_async )(void \*src\_interface, unsigned srd\_node, void \*dst\_interface, unsigned dst\_node)
- int(\* any\_to\_any )(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, void \*async\_data)

#### 27.9.2.2.1 Field Documentation

27.9.2.2.1.1 int(\* starpu\_data\_copy\_methods::can\_copy)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, unsigned handling\_node)

If defined, allows the interface to declare whether it supports transferring from  $src\_interface$  on node  $src\_node$  to  $dst\_interface$  on node  $dst\_node$ , run from node  $handling\_node$ . If not defined, it is assumed that the interface supports all transfers.

27.9.2.2.1.2 int(\* starpu\_data\_copy\_methods::ram\_to\_ram)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface on the dst\_node CPU node. Return 0 on success.

27.9.2.2.1.3 int(\* starpu\_data\_copy\_methods::ram\_to\_cuda)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface on the dst\_node CUDA node. Return 0 on success.

27.9.2.2.1.4 int(\* starpu\_data\_copy\_methods::ram\_to\_opencl)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface on the dst\_node OpenCL node. Return 0 on success.

27.9.2.2.1.5 int(\* starpu\_data\_copy\_methods::ram\_to\_mic)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface on the dst\_node MIC node. Return 0 on success.

27.9.2.2.1.6 int(\* starpu\_data\_copy\_methods::cuda\_to\_ram)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CUDA node to the dst\_-interface interface on the dst\_node CPU node. Return 0 on success.

27.9.2.2.1.7 int(\* starpu\_data\_copy\_methods::cuda\_to\_cuda)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CUDA node to the dst\_-interface interface on the dst\_node CUDA node. Return 0 on success.

27.9.2.2.1.8 int(\* starpu\_data\_copy\_methods::cuda\_to\_opencl)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CUDA node to the dst\_-interface interface on the dst\_node OpenCL node. Return 0 on success.

27.9.2.2.1.9 int(\* starpu\_data\_copy\_methods::opencl\_to\_ram)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node OpenCL node to the dst\_-interface interface on the dst\_node CPU node. Return 0 on success.

27.9.2.2.1.10 int(\* starpu\_data\_copy\_methods::opencl\_to\_cuda)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the  $src\_interface$  interface on the  $src\_node$  OpenCL node to the  $dst\_interface$  interface on the  $dst\_node$  CUDA node. Return 0 on success.

27.9.2.2.1.11 int(\* starpu\_data\_copy\_methods::opencl\_to\_opencl)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node OpenCL node to the dst\_-interface interface interface on the dst\_node OpenCL node. Return 0 on success.

27.9.2.2.1.12 int(\* starpu\_data\_copy\_methods::mic\_to\_ram)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node MIC node to the dst\_-interface interface on the dst\_node CPU node. Return 0 on success.

27.9.2.2.1.13 int(\* starpu\_data\_copy\_methods::scc\_src\_to\_sink)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node node to the dst\_interface interface on the dst\_node node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.14 int(\* starpu\_data\_copy\_methods::scc\_sink\_to\_src)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node node to the dst\_interface interface on the dst\_node node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.15 int(\* starpu\_data\_copy\_methods::scc\_sink\_to\_sink)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node node to the dst\_interface interface on the dst\_node node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.16 int(\* starpu\_data\_copy\_methods::ram\_to\_cuda\_async)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cudaStream\_t stream)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface interface on the dst\_node CUDA node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.17 int(\* starpu\_data\_copy\_methods::cuda\_to\_ram\_async)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cudaStream\_t stream)

Define how to copy data from the src\_interface interface on the src\_node CUDA node to the dst\_-interface interface on the dst\_node CPU node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.18 int(\* starpu\_data\_copy\_methods::cuda\_to\_cuda\_async)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cudaStream\_t stream)

Define how to copy data from the src\_interface interface on the src\_node CUDA node to the dst\_-interface interface on the dst\_node CUDA node, using the given stream. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.19 int(\* starpu\_data\_copy\_methods::ram\_to\_opencl\_async)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cl\_event \*event)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface interface on the dst\_node OpenCL node, by recording in event, a pointer to a cl\_event, the event of the last submitted transfer. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.20 int(\* starpu\_data\_copy\_methods::opencl\_to\_ram\_async)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cl\_event \*event)

Define how to copy data from the src\_interface interface on the src\_node OpenCL node to the dst\_-interface interface interface on the dst\_node CPU node, by recording in event, a pointer to a cl\_event, the event of the last submitted transfer. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.21 int(\* starpu\_data\_copy\_methods::opencl\_to\_opencl\_async)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, cl\_event \*event)

Define how to copy data from the src\_interface interface on the src\_node OpenCL node to the dst\_-interface interface interface on the dst\_node OpenCL node, by recording in event, a pointer to a cl\_event, the event of the last submitted transfer. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.22 int(\* starpu\_data\_copy\_methods::ram\_to\_mic\_async)(void \*src\_intreface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node CPU node to the dst\_-interface interface interface on the dst\_node MIC node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.23 int(\* starpu\_data\_copy\_methods::mic\_to\_ram\_async)(void \*src\_intreface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node)

Define how to copy data from the src\_interface interface on the src\_node MIC node to the dst\_-interface interface interface on the dst\_node CPU node. Must return 0 if the transfer was actually completed completely synchronously, or -EAGAIN if at least some transfers are still ongoing and should be awaited for by the core.

27.9.2.2.1.24 int(\* starpu\_data\_copy\_methods::any\_to\_any)(void \*src\_interface, unsigned src\_node, void \*dst\_interface, unsigned dst\_node, void \*async\_data)

Define how to copy data from the src\_interface interface on the src\_node node to the dst\_interface interface on the dst\_node node. This is meant to be implemented through the starpu\_interface\_copy() helper, to which async\_data should be passed as such, and will be used to manage asynchronicity. This must return -EAGAIN if any of the starpu\_interface\_copy() calls has returned -EAGAIN (i.e. at least some transfer is still ongoing), and return 0 otherwise.

### 27.9.2.3 struct starpu\_variable\_interface

Variable interface for a single data (not a vector, a matrix, a list, ...)

#### **Data Fields**

enum	id	Identifier of the interface
starpu_data		
interface_id		
uintptr_t	ptr	local pointer of the variable
uintptr_t	dev_handle	device handle of the variable.
size_t	offset	offset in the variable
size_t	elemsize	size of the variable

#### 27.9.2.4 struct starpu\_vector\_interface

Vector interface

# Data Fields

enum	id	Identifier of the interface
starpu_data		
interface_id		
uintptr_t	ptr	local pointer of the vector
uintptr_t	dev_handle	device handle of the vector.
size_t	offset	offset in the vector
uint32_t	nx	number of elements on the x-axis of the vector
size_t	elemsize	size of the elements of the vector
uint32_t	slice_base	vector slice base, used by the StarPU OpenMP runtime support

# 27.9.2.5 struct starpu\_matrix\_interface

Matrix interface for dense matrices

### **Data Fields**

enum	id	Identifier of the interface
starpu_data		
interface_id		
uintptr_t	ptr	local pointer of the matrix
uintptr_t	dev_handle	device handle of the matrix.
size_t	offset	offset in the matrix
uint32_t	nx	number of elements on the x-axis of the matrix
uint32_t	ny	number of elements on the y-axis of the matrix
uint32_t	ld	number of elements between each row of the matrix. Maybe be equal to
		starpu_matrix_interface::nx when there is no padding.
size_t	elemsize	size of the elements of the matrix

# 27.9.2.6 struct starpu\_block\_interface

Block interface for 3D dense blocks

### **Data Fields**

enum	id	identifier of the interface
starpu_data		
interface_id		
uintptr_t	ptr	local pointer of the block
uintptr_t	dev_handle	device handle of the block.
size_t	offset	offset in the block.
uint32_t	nx	number of elements on the x-axis of the block.
uint32_t	ny	number of elements on the y-axis of the block.
uint32_t	nz	number of elements on the z-axis of the block.
uint32_t	ldy	number of elements between two lines
uint32_t	ldz	number of elements between two planes
size_t	elemsize	size of the elements of the block.

# 27.9.2.7 struct starpu\_bcsr\_interface

BCSR interface for sparse matrices (blocked compressed sparse row representation)

# Data Fields

enum	id	Identifier of the interface
starpu_data		
interface_id		
uint32_t	nnz	number of non-zero BLOCKS
uint32_t	nrow	number of rows (in terms of BLOCKS)
uintptr_t	nzval	non-zero values
uint32_t *	colind	position of non-zero entried on the row
uint32_t *	rowptr	index (in nzval) of the first entry of the row
uint32_t	firstentry	k for k-based indexing (0 or 1 usually). Also useful when partitionning the
		matrix.
uint32_t	r	size of the blocks
uint32_t	С	size of the blocks
size_t	elemsize	size of the elements of the matrix

# 27.9.2.8 struct starpu\_csr\_interface

CSR interface for sparse matrices (compressed sparse row representation)

## **Data Fields**

enum	id	Identifier of the interface
starpu_data		
interface_id		
uint32_t	nnz	number of non-zero entries
uint32_t	nrow	number of rows
uintptr_t	nzval	non-zero values
uint32_t *	colind	position of non-zero entries on the row
uint32_t *	rowptr	index (in nzval) of the first entry of the row
uint32_t	firstentry	k for k-based indexing (0 or 1 usually). also useful when partitionning the
		matrix.
size_t	elemsize	size of the elements of the matrix

# 27.9.2.9 struct starpu\_coo\_interface

# **COO** Matrices

# Data Fields

enum	id	identifier of the interface
starpu_data		
interface_id		
uint32_t *	columns	column array of the matrix
uint32_t *	rows	row array of the matrix
uintptr_t	values	values of the matrix
uint32_t	nx	number of elements on the x-axis of the matrix
uint32_t	ny	number of elements on the y-axis of the matrix
uint32_t	n_values	number of values registered in the matrix
size_t	elemsize	size of the elements of the matrix

# 27.9.3 Macro Definition Documentation

27.9.3.1 #define STARPU\_VARIABLE\_GET\_PTR( interface )

Return a pointer to the variable designated by interface.

27.9.3.2 #define STARPU\_VARIABLE\_GET\_ELEMSIZE( interface )

Return the size of the variable designated by interface.

27.9.3.3 #define STARPU\_VARIABLE\_GET\_DEV\_HANDLE( interface )

Return a device handle for the variable designated by interface, to be used on OpenCL. The offset documented below has to be used in addition to this.

27.9.3.4 #define STARPU\_VARIABLE\_GET\_OFFSET( interface )

Return the offset in the variable designated by interface, to be used with the device handle.

27.9.3.5 #define STARPU\_VECTOR\_GET\_PTR( interface )

Return a pointer to the array designated by interface, valid on CPUs and CUDA only. For OpenCL, the device handle and offset need to be used instead.

27.9.3.6 #define STARPU\_VECTOR\_GET\_DEV\_HANDLE( interface )

Return a device handle for the array designated by interface, to be used on OpenCL. the offset documented below has to be used in addition to this.

27.9.3.7 #define STARPU\_VECTOR\_GET\_OFFSET( interface )

Return the offset in the array designated by interface, to be used with the device handle.

27.9.3.8 #define STARPU\_VECTOR\_GET\_NX( interface )

Return the number of elements registered into the array designated by interface.

27.9.3.9 #define STARPU\_VECTOR\_GET\_ELEMSIZE( interface )

Return the size of each element of the array designated by interface.

27.9.3.10 #define STARPU\_VECTOR\_GET\_SLICE\_BASE( interface )

Return the OpenMP slice base annotation of each element of the array designated by interface.

See Also

starpu\_omp\_vector\_annotate

27.9.3.11 #define STARPU\_MATRIX\_GET\_PTR( interface )

Return a pointer to the matrix designated by interface, valid on CPUs and CUDA devices only. For OpenCL devices, the device handle and offset need to be used instead.

27.9.3.12 #define STARPU\_MATRIX\_GET\_DEV\_HANDLE( interface )

Return a device handle for the matrix designated by interface, to be used on OpenCL. The offset documented below has to be used in addition to this.

27.9.3.13 #define STARPU\_MATRIX\_GET\_OFFSET( interface )

Return the offset in the matrix designated by interface, to be used with the device handle.

27.9.3.14 #define STARPU\_MATRIX\_GET\_NX( interface )

Return the number of elements on the x-axis of the matrix designated by interface.

27.9.3.15 #define STARPU\_MATRIX\_GET\_NY( interface )

Return the number of elements on the y-axis of the matrix designated by interface.

27.9.3.16 #define STARPU\_MATRIX\_GET\_LD( interface )

Return the number of elements between each row of the matrix designated by interface. May be equal to nx when there is no padding.

27.9.3.17 #define STARPU\_MATRIX\_GET\_ELEMSIZE( interface )

Return the size of the elements registered into the matrix designated by interface.

27.9.3.18 #define STARPU\_BLOCK\_GET\_PTR( interface )

Return a pointer to the block designated by interface.

27.9.3.19 #define STARPU\_BLOCK\_GET\_DEV\_HANDLE( interface )

Return a device handle for the block designated by interface, to be used on OpenCL. The offset document below has to be used in addition to this.

27.9.3.20 #define STARPU\_BLOCK\_GET\_OFFSET( interface )

Return the offset in the block designated by interface, to be used with the device handle.

27.9.3.21 #define STARPU\_BLOCK\_GET\_NX( interface )

Return the number of elements on the x-axis of the block designated by interface.

27.9.3.22 #define STARPU\_BLOCK\_GET\_NY( interface )

Return the number of elements on the y-axis of the block designated by interface.

27.9.3.23 #define STARPU\_BLOCK\_GET\_NZ( interface )

Return the number of elements on the z-axis of the block designated by interface.

27.9.3.24 #define STARPU\_BLOCK\_GET\_LDY( interface )

Return the number of elements between each row of the block designated by interface. May be equal to nx when there is no padding.

27.9.3.25 #define STARPU\_BLOCK\_GET\_LDZ( interface )

Return the number of elements between each z plane of the block designated by interface. May be equal to nx\*ny when there is no padding.

27.9.3.26 #define STARPU\_BLOCK\_GET\_ELEMSIZE( interface )

Return the size of the elements of the block designated by interface.

27.9.3.27 #define STARPU\_BCSR\_GET\_NNZ( interface )

Return the number of non-zero values in the matrix designated by interface.

27.9.3.28 #define STARPU\_BCSR\_GET\_NZVAL( interface )

Return a pointer to the non-zero values of the matrix designated by interface.

27.9.3.29 #define STARPU\_BCSR\_GET\_NZVAL\_DEV\_HANDLE( interface )

Return a device handle for the array of non-zero values in the matrix designated by interface. The offset documented below has to be used in addition to this.

27.9.3.30 #define STARPU\_BCSR\_GET\_COLIND( interface )

Return a pointer to the column index of the matrix designated by interface.

27.9.3.31 #define STARPU\_BCSR\_GET\_COLIND\_DEV\_HANDLE( interface )

Return a device handle for the column index of the matrix designated by interface. The offset documented below has to be used in addition to this.

27.9.3.32 #define STARPU\_BCSR\_GET\_ROWPTR( interface )

Return a pointer to the row pointer array of the matrix designated by interface.

27.9.3.33 #define STARPU\_BCSR\_GET\_ROWPTR\_DEV\_HANDLE( interface )

Return a device handle for the row pointer array of the matrix designated by interface. The offset documented below has to be used in addition to this.

27.9.3.34 #define STARPU\_BCSR\_GET\_OFFSET

Return the offset in the arrays (coling, rowptr, nzval) of the matrix designated by interface, to be used with the device handles.

27.9.3.35 #define STARPU\_CSR\_GET\_NNZ( interface )

Return the number of non-zero values in the matrix designated by interface.

27.9.3.36 #define STARPU\_CSR\_GET\_NROW( interface )

Return the size of the row pointer array of the matrix designated by interface.

27.9.3.37 #define STARPU\_CSR\_GET\_NZVAL( interface )

Return a pointer to the non-zero values of the matrix designated by interface.

27.9.3.38 #define STARPU\_CSR\_GET\_NZVAL\_DEV\_HANDLE( interface )

Return a device handle for the array of non-zero values in the matrix designated by interface. The offset documented below has to be used in addition to this.

27.9.3.39 #define STARPU\_CSR\_GET\_COLIND( interface )

Return a pointer to the column index of the matrix designated by interface.

27.9.3.40 #define STARPU\_CSR\_GET\_COLIND\_DEV\_HANDLE( interface )

Return a device handle for the column index of the matrix designated by interface. The offset documented below has to be used in addition to this.

27.9.3.41 #define STARPU\_CSR\_GET\_ROWPTR( interface )

Return a pointer to the row pointer array of the matrix designated by interface.

27.9.3.42 #define STARPU\_CSR\_GET\_ROWPTR\_DEV\_HANDLE( interface )

Return a device handle for the row pointer array of the matrix designated by interface. The offset documented below has to be used in addition to this.

27.9.3.43 #define STARPU\_CSR\_GET\_OFFSET

Return the offset in the arrays (colind, rowptr, nzval) of the matrix designated by interface, to be used with the device handles.

27.9.3.44 #define STARPU\_CSR\_GET\_FIRSTENTRY( interface )

Return the index at which all arrays (the column indexes, the row pointers...) of the interface start.

27.9.3.45 #define STARPU\_CSR\_GET\_ELEMSIZE( interface )

Return the size of the elements registered into the matrix designated by interface.

27.9.3.46 #define STARPU\_COO\_GET\_COLUMNS( interface )

Return a pointer to the column array of the matrix designated by interface.

27.9.3.47 #define STARPU\_COO\_GET\_COLUMNS\_DEV\_HANDLE( interface )

Return a device handle for the column array of the matrix designated by interface, to be used on OpenCL. The offset documented below has to be used in addition to this.

27.9.3.48 #define STARPU\_COO\_GET\_ROWS( interface )

Return a pointer to the rows array of the matrix designated by interface.

27.9.3.49 #define STARPU\_COO\_GET\_ROWS\_DEV\_HANDLE( interface )

Return a device handle for the row array of the matrix designated by interface, to be used on OpenCL. The offset documented below has to be used in addition to this.

27.9.3.50 #define STARPU\_COO\_GET\_VALUES( interface )

Return a pointer to the values array of the matrix designated by interface.

27.9.3.51 #define STARPU\_COO\_GET\_VALUES\_DEV\_HANDLE( interface )

Return a device handle for the value array of the matrix designated by interface, to be used on OpenCL. The offset documented below has to be used in addition to this.

27.9.3.52 #define STARPU\_COO\_GET\_OFFSET

Return the offset in the arrays of the COO matrix designated by interface.

27.9.3.53 #define STARPU\_COO\_GET\_NX( interface )

Return the number of elements on the x-axis of the matrix designated by interface.

27.9.3.54 #define STARPU\_COO\_GET\_NY( interface )

Return the number of elements on the y-axis of the matrix designated by interface.

27.9.3.55 #define STARPU\_COO\_GET\_NVALUES( interface )

Return the number of values registered in the matrix designated by interface.

27.9.3.56 #define STARPU\_COO\_GET\_ELEMSIZE( interface )

Return the size of the elements registered into the matrix designated by  ${\tt interface}.$ 

## 27.9.4 Enumeration Type Documentation

27.9.4.1 enum starpu\_data\_interface\_id

Identifier for all predefined StarPU data interfaces

#### **Enumerator:**

```
STARPU_MATRIX_INTERFACE_ID Identifier for the matrix data interface

STARPU_BLOCK_INTERFACE_ID Identifier for block data interface

STARPU_VECTOR_INTERFACE_ID Identifier for the vector data interface

STARPU_CSR_INTERFACE_ID Identifier for the csr data interface

STARPU_BCSR_INTERFACE_ID Identifier for the bcsr data interface

STARPU_VARIABLE_INTERFACE_ID Identifier for the variable data interface

STARPU_VOID_INTERFACE_ID Identifier for the void data interface

STARPU_MULTIFORMAT_INTERFACE_ID Identifier for the multiformat data interface

STARPU_COO_INTERFACE_ID Identifier for the coo data interface

STARPU_MAX_INTERFACE_ID Maximum number of data interfaces
```

#### 27.9.5 Function Documentation

27.9.5.1 void starpu\_void\_data\_register ( starpu\_data\_handle\_t \* handle )

Register a void interface. There is no data really associated to that interface, but it may be used as a synchronization mechanism. It also permits to express an abstract piece of data that is managed by the application internally: this makes it possible to forbid the concurrent execution of different tasks accessing the same void data in read-write concurrently.

27.9.5.2 void starpu\_variable\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, uintptr\_t ptr, size\_t size )

Register the size byte element pointed to by ptr, which is typically a scalar, and initialize handle to represent this data item.

Here an example of how to use the function.

27.9.5.3 void starpu\_variable\_ptr\_register ( starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size\_t offset )

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev\_handle and offset offset (for OpenCL, notably)

27.9.5.4 void starpu\_vector\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, uintptr\_t ptr, uint32\_t nx, size\_t elemsize )

Register the nx elemsize-byte elements pointed to by ptr and initialize handle to represent it.

Here an example of how to use the function.

27.9.5.5 void starpu\_vector\_ptr\_register ( starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size\_t offset )

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev\_handle and offset offset (for OpenCL, notably)

27.9.5.6 void starpu\_matrix\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, uintptr\_t ptr, uint32\_t ld, uint32\_t nx, uint32\_t ny, size\_t elemsize )

Register the nx x ny 2D matrix of elemsize-byte elements pointed by ptr and initialize handle to represent it. ld specifies the number of elements between rows. a value greater than nx adds padding, which can be useful for alignment purposes.

Here an example of how to use the function.

27.9.5.7 void starpu\_matrix\_ptr\_register ( starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size\_t offset, uint32\_t ld )

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev\_handle and offset offset (for OpenCL, notably), with ld elements between rows.

27.9.5.8 void starpu\_block\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, uintptr\_t ptr, uint32\_t ldy, uint32\_t ldz, uint32\_t nx, uint32\_t nz, size\_t elemsize )

Register the nx x ny x nz 3D matrix of elemsize byte elements pointed by ptr and initialize handle to represent it. Again, ldy and ldz specify the number of elements between rows and between z planes.

Here an example of how to use the function.

27.9.5.9 void starpu\_block\_ptr\_register ( starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size\_t offset, uint32\_t ldy, uint32\_t ldz )

Register into the handle that to store data on node node it should use the buffer located at ptr, or device handle dev\_handle and offset offset (for OpenCL, notably), with ldy elements between rows and ldz elements between z planes.

27.9.5.10 void starpu\_bcsr\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, uint32\_t nnz, uint32\_t nrow, uintptr\_t nzval, uint32\_t \* colind, uint32\_t \* rowptr, uint32\_t firstentry, uint32\_t r, uint32\_t c, size\_t elemsize )

This variant of starpu\_data\_register() uses the BCSR (Blocked Compressed Sparse Row Representation) sparse matrix interface. Register the sparse matrix made of nnz non-zero blocks of elements of size elemsize stored in nzval and initializes handle to represent it. Blocks have size r \* c. nrow is the number of rows (in terms of blocks), colind[i] is the block-column index for block in nzval, rowptr[i] is the block-index (in nzval) of the first block of row i. firstentry is the index of the first entry of the given arrays (usually 0 or 1).

27.9.5.11 void starpu\_csr\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, uint32\_t nnz, uint32\_t nrow, uintptr\_t nzval, uint32\_t \* colind, uint32\_t \* rowptr, uint32\_t firstentry, size\_t elemsize )

This variant of starpu\_data\_register() uses the CSR (Compressed Sparse Row Representation) sparse matrix interface. TODO

27.9.5.12 void starpu\_coo\_data\_register ( starpu\_data\_handle\_t \* handleptr, unsigned home\_node, uint32\_t nx, uint32\_t ny, uint32\_t \* columns, uint32\_t \* rows, uintptr\_t values, size\_t elemsize )

Register the nx x ny 2D matrix given in the COO format, using the columns, rows, values arrays, which must have  $n_values$  elements of size elemsize. Initialize handleptr.

27.9.5.13 void \* starpu\_data\_get\_interface\_on\_node ( starpu\_data\_handle\_t handle, unsigned memory\_node )

Return the interface associated with handle on memory\_node.

27.9.5.14 void \* starpu\_data\_handle\_to\_pointer ( starpu\_data\_handle\_t handle, unsigned node )

Return the pointer associated with handle on node node or NULL if handle's interface does not support this operation or data for this handle is not allocated on that node.

27.9.5.15 void \* starpu\_data\_get\_local\_ptr ( starpu\_data\_handle\_t handle )

Return the local pointer associated with handle or NULL if handle's interface does not have data allocated locally

27.9.5.16 enum starpu\_data\_interface\_id starpu\_data\_get\_interface\_id ( starpu\_data\_handle\_t handle )

Return the unique identifier of the interface associated with the given handle.

27.9.5.17 size\_t starpu\_data\_get\_size ( starpu\_data\_handle\_t handle )

Return the size of the data associated with handle.

27.9.5.18 int starpu\_data\_pack ( starpu\_data\_handle\_t handle, void \*\* ptr, starpu\_ssize\_t \* count )

Execute the packing operation of the interface of the data registered at handle (see starpu\_data\_interface\_ops). This packing operation must allocate a buffer large enough at ptr and copy into the newly allocated buffer the data associated to handle. count will be set to the size of the allocated buffer. If ptr is NULL, the function should not copy the data in the buffer but just set count to the size of the buffer which would have been allocated. The special value -1 indicates the size is yet unknown.

```
27.9.5.19 int starpu_data_unpack ( starpu_data_handle_t handle, void * ptr, size_t count )
```

Unpack in handle the data located at ptr of size count as described by the interface of the data. The interface registered at handle must define a unpacking operation (see starpu\_data\_interface\_ops). The memory at the address ptr is freed after calling the data unpacking operation.

```
27.9.5.20 size_t starpu_variable_get_elemsize ( starpu_data_handle_t handle )
```

Return the size of the variable designated by handle.

```
27.9.5.21 uintptr_t starpu_variable_get_local_ptr ( starpu_data_handle_t handle )
```

Return a pointer to the variable designated by handle.

```
27.9.5.22 uint32_t starpu_vector_get_nx ( starpu_data_handle_t handle )
```

Return the number of elements registered into the array designated by handle.

```
27.9.5.23 size_t starpu_vector_get_elemsize ( starpu_data_handle_t handle )
```

Return the size of each element of the array designated by handle.

```
27.9.5.24 uintptr_t starpu_vector_get_local_ptr ( starpu_data_handle_t handle )
```

Return the local pointer associated with handle.

```
27.9.5.25 uint32_t starpu_matrix_get_nx ( starpu_data_handle_t handle )
```

Return the number of elements on the x-axis of the matrix designated by handle.

```
27.9.5.26 uint32_t starpu_matrix_get_ny ( starpu_data_handle_t handle )
```

Return the number of elements on the y-axis of the matrix designated by handle.

```
27.9.5.27 uint32_t starpu_matrix_get_local_ld ( starpu_data_handle_t handle )
```

Return the number of elements between each row of the matrix designated by handle. Maybe be equal to nx when there is no padding.

```
27.9.5.28 uintptr_t starpu_matrix_get_local_ptr ( starpu_data_handle_t handle )
```

Return the local pointer associated with handle.

```
27.9.5.29 size_t starpu_matrix_get_elemsize ( starpu_data_handle_t handle )
```

Return the size of the elements registered into the matrix designated by handle.

```
27.9.5.30 uint32_t starpu_block_get_nx ( starpu_data_handle_t handle )
```

Return the number of elements on the x-axis of the block designated by  ${\tt handle}.$ 

```
27.9.5.31 uint32_t starpu_block_get_ny ( starpu_data_handle_t handle )
```

Return the number of elements on the y-axis of the block designated by handle.

```
27.9.5.32 uint32_t starpu_block_get_nz ( starpu_data_handle_t handle )
```

Return the number of elements on the z-axis of the block designated by handle.

```
27.9.5.33 uint32_t starpu_block_get_local_ldy ( starpu_data_handle_t handle_)
```

Return the number of elements between each row of the block designated by handle, in the format of the current memory node.

```
27.9.5.34 uint32_t starpu_block_get_local_ldz ( starpu_data_handle_t handle )
```

Return the number of elements between each z plane of the block designated by handle, in the format of the current memory node.

```
27.9.5.35 uintptr_t starpu_block_get_local_ptr ( starpu_data_handle_t handle )
```

Return the local pointer associated with handle.

```
27.9.5.36 size_t starpu_block_get_elemsize ( starpu_data_handle_t handle )
```

Return the size of the elements of the block designated by handle.

```
27.9.5.37 uint32_t starpu_bcsr_get_nnz ( starpu_data_handle_t handle )
```

Return the number of non-zero elements in the matrix designated by handle.

```
27.9.5.38 uint32_t starpu_bcsr_get_nrow ( starpu data handle t handle )
```

Return the number of rows (in terms of blocks of size r\*c) in the matrix designated by handle.

```
27.9.5.39 uint32_t starpu_bcsr_get_firstentry ( starpu_data_handle_t handle )
```

Return the index at which all arrays (the column indexes, the row pointers...) of the matrix desginated by handle.

```
27.9.5.40 uintptr_t starpu_bcsr_get_local_nzval ( starpu_data_handle_t handle )
```

Return a pointer to the non-zero values of the matrix designated by handle.

```
27.9.5.41 uint32_t * starpu_bcsr_get_local_colind ( starpu_data_handle_t handle_)
```

Return a pointer to the column index, which holds the positions of the non-zero entries in the matrix designated by handle.

```
27.9.5.42 uint32_t * starpu_bcsr_get_local_rowptr ( starpu_data_handle_t handle_)
```

Return the row pointer array of the matrix designated by handle.

27.9.5.43 uint32\_t starpu\_bcsr\_get\_r ( starpu\_data\_handle\_t handle )

Return the number of rows in a block.

27.9.5.44 uint32\_t starpu\_bcsr\_get\_c ( starpu\_data\_handle\_t handle )

Return the number of columns in a block.

27.9.5.45 size\_t starpu\_bcsr\_get\_elemsize ( starpu\_data\_handle\_t handle\_)

Return the size of the elements in the matrix designated by handle.

27.9.5.46 uint32\_t starpu\_csr\_get\_nnz ( starpu data handle t handle )

Return the number of non-zero values in the matrix designated by handle.

27.9.5.47 uint32\_t starpu\_csr\_get\_nrow ( starpu\_data\_handle\_t handle )

Return the size of the row pointer array of the matrix designated by handle.

27.9.5.48 uint32\_t starpu\_csr\_get\_firstentry ( starpu\_data\_handle\_t handle )

Return the index at which all arrays (the column indexes, the row pointers...) of the matrix designated by handle.

27.9.5.49 uintptr\_t starpu\_csr\_get\_local\_nzval ( starpu\_data\_handle\_t handle )

Return a local pointer to the non-zero values of the matrix designated by handle.

27.9.5.50 uint32\_t \* starpu\_csr\_get\_local\_colind ( starpu\_data\_handle\_t handle )

Return a local pointer to the column index of the matrix designated by handle.

27.9.5.51 uint32\_t \* starpu\_csr\_get\_local\_rowptr ( starpu\_data\_handle\_t handle )

Return a local pointer to the row pointer array of the matrix designated by handle.

27.9.5.52 size\_t starpu\_csr\_get\_elemsize ( starpu\_data\_handle\_t handle )

Return the size of the elements registered into the matrix designated by handle.

27.9.5.53 uintptr\_t starpu\_malloc\_on\_node\_flags ( unsigned dst\_node, size\_t size, int flags )

Allocate size bytes on node dst\_node with the given allocation flags. This returns 0 if allocation failed, the allocation method should then return -ENOMEM as allocated size. Deallocation must be done with starpu\_free\_on\_node.

27.9.5.54 void starpu\_free\_on\_node\_flags ( unsigned dst\_node, uintptr\_t addr, size\_t size, int flags )

Free addr of size bytes on node dst\_node which was previously allocated with starpu\_malloc\_on\_node with the given allocation flags.

27.10 Data Partition 211

27.9.5.55 uintptr\_t starpu\_malloc\_on\_node ( unsigned dst\_node, size\_t size )

Allocate size bytes on node dst\_node with the default allocation flags. This returns 0 if allocation failed, the allocation method should then return -ENOMEM as allocated size. Deallocation must be done with starpu\_free\_onnode.

27.9.5.56 void starpu\_free\_on\_node ( unsigned dst\_node, uintptr\_t addr, size\_t size )

Free addr of size bytes on node dst\_node which was previously allocated with starpu\_malloc\_on\_node.

27.9.5.57 void starpu\_malloc\_on\_node\_set\_default\_flags ( unsigned node, int flags )

Define the defaultflags for allocations performed by starpu\_malloc\_on\_node() and starpu\_free\_on\_node(). The default is STARPU\_MALLOC\_PINNED | STARPU\_MALLOC\_COUNT.

27.9.5.58 int starpu\_interface\_copy ( uintptr\_t src, size\_t src\_offset, unsigned src\_node, uintptr\_t dst, size\_t dst\_offset, unsigned dst\_node, size\_t size, void \* async\_data )

Copy size bytes from byte offset  $src\_offset$  of  $src\_on$   $src\_node$  to byte offset  $dst\_offset$  of dst on  $dst\_node$ . This is to be used in the any\_to\_any() copy method, which is provided with the async\_data to be passed to  $starpu\_interface\_copy()$ . this returns -EAGAIN if the transfer is still ongoing, or 0 if the transfer is already completed.

27.9.5.59 uint32\_t starpu\_hash\_crc32c\_be\_n ( const void \* input, size\_t n, uint32\_t inputcrc )

Compute the CRC of a byte buffer seeded by the inputere *current state*. The return value should be considered as the new *current state* for future CRC computation. This is used for computing data size footprint.

27.9.5.60 uint32\_t starpu\_hash\_crc32c\_be ( uint32\_t input, uint32\_t inputcrc )

Compute the CRC of a 32bit number seeded by the inputoro current state. The return value should be considered as the new current state for future CRC computation. This is used for computing data size footprint.

27.9.5.61 uint32\_t starpu\_hash\_crc32c\_string ( const char \* str, uint32\_t inputcrc )

Compute the CRC of a string seeded by the inputore *current state*. The return value should be considered as the new *current state* for future CRC computation. This is used for computing data size footprint.

27.9.5.62 int starpu\_data\_interface\_get\_next\_id ( void )

Return the next available id for a newly created data interface (Defining A New Data Interface).

## 27.10 Data Partition

# **Data Structures**

struct starpu\_data\_filter

### **Basic API**

- void starpu\_data\_partition (starpu\_data\_handle\_t initial\_handle, struct starpu\_data\_filter \*f)
- void starpu data unpartition (starpu data handle t root data, unsigned gathering node)
- int starpu\_data\_get\_nb\_children (starpu\_data\_handle\_t handle)
- starpu\_data\_handle\_t starpu\_data\_get\_child (starpu\_data\_handle\_t handle, unsigned i)
- starpu\_data\_handle\_t starpu\_data\_get\_sub\_data (starpu\_data\_handle\_t root\_data, unsigned depth,...)
- starpu\_data\_handle\_t starpu\_data\_vget\_sub\_data (starpu\_data\_handle\_t root\_data, unsigned depth, va\_list pa)
- void starpu data map filters (starpu data handle t root data, unsigned nfilters,...)
- · void starpu data vmap filters (starpu data handle t root data, unsigned nfilters, va list pa)

## **Asynchronous API**

- void starpu\_data\_partition\_plan (starpu\_data\_handle\_t initial\_handle, struct starpu\_data\_filter \*f, starpu\_data handle t \*children)
- void starpu\_data\_partition\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle t \*children)
- void starpu\_data\_partition\_readonly\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle t \*children)
- void starpu\_data\_partition\_readwrite\_upgrade\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children)
- void starpu\_data\_unpartition\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle t \*children, int gathering node)
- void starpu\_data\_unpartition\_readonly\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children, int gathering node)
- void starpu\_data\_partition\_clean (starpu\_data\_handle\_t root\_data, unsigned nparts, starpu\_data\_handle\_t \*children)

## **Predefined Vector Filter Functions**

This section gives a partial list of the predefined partitioning functions for vector data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h.

- void starpu\_vector\_filter\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_vector\_filter\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_vector\_filter\_list (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_vector\_filter\_divide\_in\_2 (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)

### **Predefined Matrix Filter Functions**

This section gives a partial list of the predefined partitioning functions for matrix data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h.

- void starpu\_matrix\_filter\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_matrix\_filter\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_matrix\_filter\_vertical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_matrix\_filter\_vertical\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data filter \*f, unsigned id, unsigned nparts)

27.10 Data Partition 213

## **Predefined Block Filter Functions**

This section gives a partial list of the predefined partitioning functions for block data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h. A usage example is available in examples/filters/shadow3d.c

- void starpu\_block\_filter\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_vertical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_vertical\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data filter \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_depth\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_depth\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)

### **Predefined BCSR Filter Functions**

This section gives a partial list of the predefined partitioning functions for BCSR data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h.

- void starpu\_bcsr\_filter\_canonical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)
- void starpu\_csr\_filter\_vertical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)

# 27.10.1 Detailed Description

# 27.10.2 Data Structure Documentation

# 27.10.2.1 struct starpu\_data\_filter

The filter structure describes a data partitioning operation, to be given to the starpu\_data\_partition() function.

## **Data Fields**

- void(\* filter\_func )(void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*, unsigned id, unsigned nparts)
- · unsigned nchildren
- unsigned(\* get nchildren )(struct starpu data filter \*, starpu data handle t initial handle)
- struct
   starpu\_data\_interface\_ops \*(\* get\_child\_ops )(struct starpu\_data\_filter \*, unsigned id)
- unsigned filter\_arg
- void \* filter\_arg\_ptr

## 27.10.2.1.1 Field Documentation

27.10.2.1.1.1 void(\* starpu\_data\_filter::filter\_func)(void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*, unsigned id, unsigned nparts)

This function fills the child\_interface structure with interface information for the id-th child of the parent father\_interface (among nparts).

27.10.2.1.1.2 unsigned starpu\_data\_filter::nchildren

This is the number of parts to partition the data into.

27.10.2.1.1.3 unsigned(\* starpu\_data\_filter::get\_nchildren)(struct starpu\_data\_filter \*, starpu\_data\_handle\_t initial\_handle)

This returns the number of children. This can be used instead of nchildren when the number of children depends on the actual data (e.g. the number of blocks in a sparse matrix).

```
27.10.2.1.1.4 struct starpu_data_interface_ops *(* starpu_data_filter::get_child_ops)(struct starpu_data_filter *, unsigned id) [read]
```

In case the resulting children use a different data interface, this function returns which interface is used by child number id.

27.10.2.1.1.5 unsigned starpu\_data\_filter::filter\_arg

Allow to define an additional parameter for the filter function.

```
27.10.2.1.1.6 void * starpu_data_filter::filter_arg_ptr
```

Allow to define an additional pointer parameter for the filter function, such as the sizes of the different parts.

### 27.10.3 Function Documentation

```
27.10.3.1 void starpu_data_partition ( starpu_data_handle_t initial_handle, struct starpu_data_filter * f )
```

This requests partitioning one StarPU data initial\_handle into several subdata according to the filter  ${\tt f.}$ 

Here an example of how to use the function.

27.10.3.2 void starpu\_data\_unpartition ( starpu\_data\_handle\_t root\_data, unsigned gathering\_node )

This unapplies one filter, thus unpartitioning the data. The pieces of data are collected back into one big piece in the <code>gathering\_node</code> (usually STARPU\_MAIN\_RAM). Tasks working on the partitioned data must be already finished when calling <code>starpu\_data\_unpartition()</code>.

Here an example of how to use the function.

```
starpu_data_unpartition(A_handle, STARPU_MAIN_RAM
);
```

27.10.3.3 int starpu\_data\_get\_nb\_children ( starpu\_data\_handle\_t handle )

This function returns the number of children.

27.10.3.4 starpu\_data\_handle\_t starpu\_data\_get\_child ( starpu\_data\_handle\_t handle, unsigned i )

Return the ith child of the given handle, which must have been partitionned beforehand.

27.10 Data Partition 215

```
27.10.3.5 starpu_data_handle_t starpu_data_get_sub_data ( starpu_data_handle_t root_data, unsigned depth, ... )
```

After partitioning a StarPU data by applying a filter, starpu\_data\_get\_sub\_data() can be used to get handles for each of the data portions. root\_data is the parent data that was partitioned. depth is the number of filters to traverse (in case several filters have been applied, to e.g. partition in row blocks, and then in column blocks), and the subsequent parameters are the indexes. The function returns a handle to the subdata.

Here an example of how to use the function.

```
h = starpu_data_get_sub_data(A_handle, 1, taskx);
```

27.10.3.6 starpu\_data\_handle\_t starpu\_data\_vget\_sub\_data ( starpu\_data\_handle\_t root\_data, unsigned depth, va\_list pa )

This function is similar to starpu\_data\_get\_sub\_data() but uses a va\_list for the parameter list.

```
27.10.3.7 void starpu_data_map_filters ( starpu_data_handle_t root_data, unsigned nfilters, ... )
```

Applies nfilters to the handle designated by root\_handle recursively. nfilters pointers to variables of the type starpu\_data\_filter should be given.

```
27.10.3.8 void starpu_data_vmap_filters ( starpu_data_handle_t root_data, unsigned nfilters, va_list pa)
```

Applies nfilters filters to the handle designated by root\_handle recursively. It uses a va\_list of pointers to variables of the type starpu data filter.

```
27.10.3.9 void starpu_data_partition_plan ( starpu_data_handle_t initial_handle, struct starpu_data_filter * f, starpu_data_handle_t * children )
```

This plans for partitioning one StarPU data handle initial\_handle into several subdata according to the filter f. The handles are returned into the children array, which has to be the same size as the number of parts described in f. These handles are not immediately usable, starpu\_data\_partition\_submit has to be called to submit the actual partitioning.

Here is an example of how to use the function:

27.10.3.10 void starpu\_data\_partition\_submit ( starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \* children )

This submits the actual partitioning of initial\_handle into the nparts children handles. This call is asynchronous, it only submits that the partitioning should be done, so that the children handles can now be used to submit tasks, and initial\_handle can not be used to submit tasks any more (to guarantee coherency).

For instance,

27.10.3.11 void starpu\_data\_partition\_readonly\_submit ( starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \* children )

This is the same as starpu\_data\_partition\_submit, but does not invalidate initial\_handle. This allows to continue using it, but the application has to be careful not to write to initial\_handle or children handles, only read from them, since the coherency is otherwise not guaranteed. This thus allows to submit various tasks which concurrently read from various partitions of the data.

When the application wants to write to initial\_handle again, it should call starpu\_data\_unpartition\_submit, which will properly add dependencies between the reads on the children and the writes to be submitted.

If instead the application wants to write to children handles, it should call starpu\_data\_partition\_readwrite\_upgrade\_submit, which will properly add dependencies between the reads on the initial\_handle and the writes to be submitted.

27.10.3.12 void starpu\_data\_partition\_readwrite\_upgrade\_submit ( starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle t \* children )

This assumes that a partitioning of initial\_handle has already been submited in readonly mode through starpu\_data\_partition\_readonly\_submit, and will upgrade that partitioning into read-write mode for the children, by invalidating initial\_handle, and adding the necessary dependencies.

27.10.3.13 void starpu\_data\_unpartition\_submit ( starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \* children, int gathering\_node )

This assumes that initial\_handle is partitioned into children, and submits an unpartitionning of it, i.e. submitting a gathering of the pieces on the requested gathering\_node memory node, and submitting an invalidation of the children.

gathering\_node can be set to -1 to let the runtime decide which memory node should be used to gather the pieces.

27.10.3.14 void starpu\_data\_unpartition\_readonly\_submit ( starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \* children, int gathering\_node )

This assumes that <code>initial\_handle</code> is partitioned into <code>children</code>, and submits just a readonly unpartitionning of it, i.e. submitting a gathering of the pieces on the requested <code>gathering\_node</code> memory node. It does not invalidate the children. This brings <code>initial\_handle</code> and <code>children</code> handles to the same state as obtained with starpu data partition readonly submit.

gathering\_node can be set to -1 to let the runtime decide which memory node should be used to gather the pieces.

27.10.3.15 void starpu\_data\_partition\_clean ( starpu\_data\_handle\_t root\_data, unsigned nparts, starpu\_data\_handle\_t \* children )

This should be used to clear the partition planning established between root\_data and children with starpudata\_partition\_plan. This will notably submit an unregister all the children, which can thus not be used any more afterwards.

27.10.3.16 void starpu\_vector\_filter\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

Return in child\_interface the id th element of the vector represented by father\_interface once partitioned in nparts chunks of equal size.

27.10 Data Partition 217

27.10.3.17 void starpu\_vector\_filter\_block\_shadow ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

Return in child\_interface the id th element of the vector represented by father\_interface once partitioned in nparts chunks of equal size with a shadow border filter\_arg\_ptr, thus getting a vector of size (n-2\*shadow)/nparts+2\*shadow. The filter\_arg\_ptr field of f must be the shadow size casted into void\*. IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts. An usage example is available in examples/filters/shadow.c

27.10.3.18 void starpu\_vector\_filter\_list ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

Return in child\_interface the id th element of the vector represented by father\_interface once partitioned into nparts chunks according to the filter\_arg\_ptr field of f. The filter\_arg\_ptr field must point to an array of nparts uint32\_t elements, each of which specifies the number of elements in each chunk of the partition.

27.10.3.19 void starpu\_vector\_filter\_divide\_in\_2 ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

Return in child\_interface the id th element of the vector represented by father\_interface once partitioned in 2 chunks of equal size, ignoring nparts. Thus, id must be 0 or 1.

27.10.3.20 void starpu\_matrix\_filter\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a dense Matrix along the x dimension, thus getting (x/nparts ,y) matrices. If nparts does not divide x, the last submatrix contains the remainder.

27.10.3.21 void starpu\_matrix\_filter\_block\_shadow ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a dense Matrix along the x dimension, with a shadow border filter\_arg\_ptr, thus getting ((x-2\*shadow)/nparts +2\*shadow,y) matrices. If nparts does not divide x-2\*shadow, the last submatrix contains the remainder. IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts. A usage example is available in examples/filters/shadow2d.c

27.10.3.22 void starpu\_matrix\_filter\_vertical\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a dense Matrix along the y dimension, thus getting (x,y/nparts) matrices. If nparts does not divide y, the last submatrix contains the remainder.

27.10.3.23 void starpu\_matrix\_filter\_vertical\_block\_shadow ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a dense Matrix along the y dimension, with a shadow border filter\_arg\_ptr, thus getting (x,(y-2\*shadow)/nparts +2\*shadow) matrices. If nparts does not divide y-2\*shadow, the last submatrix contains the remainder. IMPORTANT: This can only be used for read-only access, as no coherency is enforced for the shadowed parts. A usage example is available in examples/filters/shadow2d.c

27.10.3.24 void starpu\_block\_filter\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block along the X dimension, thus getting (x/nparts, y,z) 3D matrices. If nparts does not divide x, the last submatrix contains the remainder.

27.10.3.25 void starpu\_block\_filter\_block\_shadow ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block along the X dimension, with a shadow border filter\_arg\_ptr, thus getting ((x-2\*shadow)/nparts +2\*shadow,y,z) blocks. If nparts does not divide x, the last submatrix contains the remainder. **IMPORTANT**: This can only be used for read-only access, as no coherency is enforced for the shadowed parts.

27.10.3.26 void starpu\_block\_filter\_vertical\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block along the Y dimension, thus getting (x,y/nparts,z) blocks. If nparts does not divide y, the last submatrix contains the remainder.

27.10.3.27 void starpu\_block\_filter\_vertical\_block\_shadow ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block along the Y dimension, with a shadow border filter\_arg\_ptr, thus getting (x,(y-2\*shadow)/nparts +2\*shadow,z) 3D matrices. If nparts does not divide y, the last submatrix contains the remainder. **IMPORTANT**: This can only be used for read-only access, as no coherency is enforced for the shadowed parts.

27.10.3.28 void starpu\_block\_filter\_depth\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block along the Z dimension, thus getting (x,y,z/nparts) blocks. If nparts does not divide z, the last submatrix contains the remainder.

27.10.3.29 void starpu\_block\_filter\_depth\_block\_shadow ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block along the Z dimension, with a shadow border  $filter\_arg\_ptr$ , thus getting (x,y,(z-2\*shadow)/nparts +2\*shadow) blocks. If nparts does not divide z, the last submatrix contains the remainder. **IMPORTANT**: This can only be used for read-only access, as no coherency is enforced for the shadowed parts.

27.10.3.30 void starpu\_bcsr\_filter\_canonical\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block-sparse matrix into dense matrices.

27.10.3.31 void starpu\_csr\_filter\_vertical\_block ( void \* father\_interface, void \* child\_interface, struct starpu\_data\_filter \* f, unsigned id, unsigned nparts )

This partitions a block-sparse matrix into vertical block-sparse matrices.

27.11 Out Of Core 219

## 27.11 Out Of Core

# **Data Structures**

struct starpu\_disk\_ops

## **Functions**

- int starpu disk register (struct starpu disk ops \*func, void \*parameter, starpu ssize t size)
- void \* starpu\_disk\_open (unsigned node, void \*pos, size\_t size)
- void starpu\_disk\_close (unsigned node, void \*obj, size\_t size)

## **Variables**

- struct starpu\_disk\_ops starpu\_disk\_stdio\_ops
- struct starpu\_disk\_ops starpu\_disk\_unistd\_ops
- · struct starpu disk ops starpu disk unistd o direct ops
- struct starpu\_disk\_ops starpu\_disk\_leveldb\_ops

# 27.11.1 Detailed Description

### 27.11.2 Data Structure Documentation

## 27.11.2.1 struct starpu\_disk\_ops

This is a set of functions to manipulate datas on disk.

## **Data Fields**

- void \*(\* plug )(void \*parameter, starpu ssize t size)
- void(\* unplug )(void \*base)
- int(\* bandwidth )(unsigned node)
- void \*(\* alloc )(void \*base, size t size)
- void(\* free )(void \*base, void \*obj, size t size)
- void \*(\* open )(void \*base, void \*pos, size\_t size)
- void(\* close )(void \*base, void \*obj, size t size)
- int(\* read )(void \*base, void \*obj, void \*buf, off t offset, size t size)
- int(\* write )(void \*base, void \*obj, const void \*buf, off\_t offset, size\_t size)
- int(\* full\_read )(void \*base, void \*obj, void \*\*ptr, size\_t \*size)
- int(\* full write )(void \*base, void \*obj, void \*ptr, size t size)
- void \*(\* async\_write )(void \*base, void \*obj, void \*buf, off\_t offset, size\_t size)
- void \*(\* async\_read )(void \*base, void \*obj, void \*buf, off\_t offset, size\_t size)
- void \*(\* async full read )(void \*base, void \*obj, void \*\*ptr, size t \*size)
- void \*(\* async\_full\_write )(void \*base, void \*obj, void \*ptr, size\_t size)
- void \*(\* copy )(void \*base\_src, void \*obj\_src, off\_t offset\_src, void \*base\_dst, void \*obj\_dst, off\_t offset\_dst, size\_t size)
- void(\* wait\_request )(void \*async\_channel)
- int(\* test\_request )(void \*async\_channel)
- void(\* free\_request )(void \*async\_channel)

27.11.2.1.1 Field Documentation

27.11.2.1.1.1 void \*(\* starpu\_disk\_ops::plug)(void \*parameters, size\_t size)

Connect a disk memory at location parameter with size size, and return a base as void\*, which will be passed by StarPU to all other methods.

27.11.2.1.1.2 void(\* starpu\_disk\_ops::unplug)(void \*base)

Disconnect a disk memory base.

27.11.2.1.1.3 int(\* starpu\_disk\_ops::bandwidth)(unsigned node)

Measure the bandwidth and the latency for the disk node and save it. Returns 1 if it could measure it.

27.11.2.1.1.4 void \*(\* starpu\_disk\_ops::alloc)(void \*base, size\_t size)

Create a new location for datas of size size. This returns an opaque object pointer.

27.11.2.1.1.5 void(\* starpu\_disk\_ops::free)(void \*base, void \*obj, size\_t size)

Free a data obj previously allocated with alloc.

27.11.2.1.1.6 void \*(\* starpu\_disk\_ops::open)(void \*base, void \*pos, size\_t size)

Open an existing location of datas, at a specific position pos dependent on the backend.

27.11.2.1.1.7 void(\* starpu\_disk\_ops::close)(void \*base, void \*obj, size\_t size)

Close, without deleting it, a location of datas obj.

27.11.2.1.1.8 int(\* starpu\_disk\_ops::read)(void \*base, void \*obj, void \*buf, off\_t offset, size\_t size)

Read size bytes of data from obj in base, at offset offset, and put into buf. Returns the actual number of read bytes.

27.11.2.1.1.9 int(\* starpu\_disk\_ops::write)(void \*base, void \*obj, const void \*buf, off\_t offset, size\_t size)

Write size bytes of data to obj in base, at offset offset, from buf. Returns 0 on success.

27.11.2.1.1.10 int(\* starpu\_disk\_ops::full\_read)(void \*base, void \*obj, void \*\*ptr, size\_t \*size)

Read all data from obj of base, from offset 0. Returns it in an allocated buffer ptr, of size size

27.11.2.1.1.11 int(\* starpu\_disk\_ops::full\_write)(void \*base, void \*obj, void \*ptr, size\_t size)

Write data in ptr to obj of base, from offset 0, and truncate obj to size, so that a full\_read will get it.

27.11.2.1.1.12 void \*(\* starpu\_disk\_ops::async\_write)(void \*base, void \*obj, const void \*buf, off\_t offset, size\_t size)

Asynchronously write size bytes of data to obj in base, at offset offset, from buf. Returns a void\* pointer that StarPU will pass to  $*_request$  methods for testing for the completion.

27.11.2.1.1.13 void \*(\* starpu\_disk\_ops::async\_read)(void \*base, void \*obj, void \*buf, off\_t offset, size\_t size)

Asynchronously read size bytes of data from obj in base, at offset offset, and put into buf. Returns a void\* pointer that StarPU will pass to  $*\_request$  methods for testing for the completion.

27.11.2.1.1.14 void \*(\* starpu\_disk\_ops::async\_full\_read)(void \*base, void \*obj, void \*\*ptr, size\_t \*size)

Read all data from obj of base, from offset 0. Returns it in an allocated buffer ptr, of size size

27.11 Out Of Core 221

27.11.2.1.1.15 void \*(\* starpu\_disk\_ops::async\_full\_write)(void \*base, void \*obj, void \*ptr, size\_t size)

Write data in ptr to obj of base, from offset 0, and truncate obj to size, so that a full\_read will get it.

27.11.2.1.1.16 void \*(\* starpu\_disk\_ops::copy)(void \*base\_src, void \*obj\_src, off\_t offset\_src, void \*base\_dst, void \*obj\_dst, off\_t offset\_dst, size\_t size)

Copy from offset offset\_src of disk object obj\_src in base\_src to offset offset\_dst of disk object obj\_dst in base\_dst. Returns a void\* pointer that StarPU will pass to \*\_request methods for testing for the completion.

27.11.2.1.1.17 void(\* starpu\_disk\_ops::wait\_request)(void \*async\_channel)

Wait for completion of request async\_channel returned by a previous asynchronous read, write or copy.

27.11.2.1.1.18 void(\* starpu\_disk\_ops::test\_request)(void \*async\_channel)

Test for completion of request async\_channel returned by a previous asynchronous read, write or copy. Returns 1 on completion, 0 otherwise.

27.11.2.1.1.19 void(\* starpu\_disk\_ops::free\_request)(void \*async\_channel)

Free the request allocated by a previous asynchronous read, write or copy.

### 27.11.3 Function Documentation

27.11.3.1 int starpu\_disk\_register ( struct starpu\_disk\_ops \* func, void \* parameter, starpu\_ssize\_t size )

Register a disk memory node with a set of functions to manipulate datas. The plug member of func will be passed parameter, and return a base which will be passed to all func methods.

SUCCESS: return the disk node.

FAIL: return an error code.

The size must be at least 1 MB! size being negative means infinite size.

27.11.3.2 void \* starpu\_disk\_open ( unsigned node, void \* pos, size\_t size )

Open an existing file memory in a disk node. size: this is a size of your file. pos is specific position dependent on the backend, given to the open method of the disk operations. This returns an opaque object pointer.

27.11.3.3 void starpu\_disk\_close ( unsigned node, void \* obj, size\_t size )

Close an existing data opened with starpu\_disk\_open.

### 27.11.4 Variable Documentation

27.11.4.1 starpu\_disk\_stdio\_ops

This set uses the stdio library (fwrite, fread...) to read/write on disk.

Warning: It creates one file per allocation!

It doesn't support asynchronous transfers.

27.11.4.2 starpu\_disk\_unistd\_ops

This set uses the unistd library (write, read...) to read/write on disk.

Warning: It creates one file per allocation!

27.11.4.3 starpu\_disk\_unistd\_o\_direct\_ops

This set uses the unistd library (write, read...) to read/write on disk with the O\_DIRECT flag.

Warning: It creates one file per allocation!

Only available on Linux systems.

27.11.4.4 starpu\_disk\_leveldb\_ops

This set uses the leveldb created by Google

Show here: https://code.google.com/p/leveldb/

It doesn't support asynchronous transfers.

# 27.12 Multiformat Data Interface

## **Data Structures**

- struct starpu\_multiformat\_data\_interface\_ops
- struct starpu\_multiformat\_interface

# **Macros**

- #define STARPU\_MULTIFORMAT\_GET\_CPU\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_CUDA\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_OPENCL\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_MIC\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_NX(interface)

# **Functions**

• void starpu\_multiformat\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, void \*ptr, uint32\_t nobjects, struct starpu\_multiformat\_data\_interface\_ops \*format\_ops)

# 27.12.1 Detailed Description

## 27.12.2 Data Structure Documentation

27.12.2.1 struct starpu\_multiformat\_data\_interface\_ops

The different fields are:

# **Data Fields**

size_t	cpu_elemsize	the size of each element on CPUs
size_t	opencl_elemsize	the size of each element on OpenCL devices
struct	cpu_to_opencl	pointer to a codelet which converts from CPU to OpenCL
starpu_codelet *	cl	
struct	opencl_to_cpu	pointer to a codelet which converts from OpenCL to CPU
starpu_codelet *	cl	
size_t	cuda_elemsize	the size of each element on CUDA devices
struct	cpu_to_cuda_cl	pointer to a codelet which converts from CPU to CUDA
starpu_codelet *		
struct	cuda_to_cpu_cl	pointer to a codelet which converts from CUDA to CPU
starpu_codelet *		
size_t	mic_elemsize	the size of each element on MIC devices
struct	cpu_to_mic_cl	pointer to a codelet which converts from CPU to MIC
starpu_codelet *		
struct	mic_to_cpu_cl	pointer to a codelet which converts from MIC to CPU
starpu_codelet *		

# 27.12.2.2 struct starpu\_multiformat\_interface

### todo

## **Data Fields**

enum	id	
starpu_data		
interface_id		
void *	cpu_ptr	
void *	cuda_ptr	
void *	opencl_ptr	
void *	mic_ptr	
uint32_t	nx	
struct	ops	
starpu		
multiformat		
data_interface		
ops		
*		

# 27.12.3 Macro Definition Documentation

27.12.3.1 #define STARPU\_MULTIFORMAT\_GET\_CPU\_PTR( interface )

returns the local pointer to the data with CPU format.

27.12.3.2 #define STARPU\_MULTIFORMAT\_GET\_CUDA\_PTR( interface )

returns the local pointer to the data with CUDA format.

27.12.3.3 #define STARPU\_MULTIFORMAT\_GET\_OPENCL\_PTR( interface )

returns the local pointer to the data with OpenCL format.

27.12.3.4 #define STARPU\_MULTIFORMAT\_GET\_MIC\_PTR( interface )

returns the local pointer to the data with MIC format.

27.12.3.5 #define STARPU\_MULTIFORMAT\_GET\_NX( interface )

returns the number of elements in the data.

### 27.12.4 Function Documentation

27.12.4.1 void starpu\_multiformat\_data\_register ( starpu\_data\_handle\_t \* handle, unsigned home\_node, void \* ptr, uint32\_t nobjects, struct starpu\_multiformat\_data\_interface\_ops \* format\_ops )

Register a piece of data that can be represented in different ways, depending upon the processing unit that manipulates it. It allows the programmer, for instance, to use an array of structures when working on a CPU, and a structure of arrays when working on a GPU. nobjects is the number of elements in the data. format\_ops describes the format.

## 27.13 Codelet And Tasks

This section describes the interface to manipulate codelets and tasks.

## **Data Structures**

- struct starpu\_codelet
- struct starpu\_data\_descr
- struct starpu\_task

### **Macros**

- #define STARPU NOWHERE
- #define STARPU\_CPU
- #define STARPU CUDA
- #define STARPU OPENCL
- #define STARPU MIC
- #define STARPU SCC
- #define STARPU MAIN RAM
- #define STARPU\_MULTIPLE\_CPU\_IMPLEMENTATIONS
- #define STARPU MULTIPLE CUDA IMPLEMENTATIONS
- #define STARPU MULTIPLE OPENCL IMPLEMENTATIONS
- #define STARPU NMAXBUFS
- #define STARPU\_VARIABLE\_NBUFFERS
- #define STARPU\_TASK\_INITIALIZER
- #define STARPU TASK GET NBUFFERS(task)
- #define STARPU\_TASK\_GET\_HANDLE(task, i)
- #define STARPU TASK SET HANDLE(task, handle, i)
- #define STARPU\_CODELET\_GET\_MODE(codelet, i)
- #define STARPU\_CODELET\_SET\_MODE(codelet, mode, i)
- #define STARPU TASK GET MODE(task, i)
- #define STARPU TASK SET MODE(task, mode, i)
- #define STARPU\_TASK\_INVALID

## **Typedefs**

- typedef void(\* starpu\_cpu\_func\_t )(void \*\*, void \*)
- typedef void(\* starpu cuda func t)(void \*\*, void \*)
- typedef void(\* starpu\_opencl\_func\_t )(void \*\*, void \*)
- typedef starpu\_mic\_kernel\_t(\* starpu\_mic\_func\_t)(void)
- typedef starpu scc kernel t(\* starpu scc func t)(void)
- typedef void(\* starpu\_mic\_kernel\_t )(void \*\*, void \*)
- typedef void(\* starpu\_scc\_kernel\_t)(void \*\*, void \*)

### **Enumerations**

- enum starpu\_codelet\_type { STARPU\_SEQ, STARPU\_SPMD, STARPU\_FORKJOIN }
- enum starpu\_task\_status {
   STARPU\_TASK\_INVALID, STARPU\_TASK\_INVALID, STARPU\_TASK\_BLOCKED, STARPU\_TASK\_RE-

ADY, STARPU\_TASK\_RUNNING, STARPU\_TASK\_FINISHED, STARPU\_TASK\_BLOCKED\_ON\_TAG, STARP-U\_TASK\_BLOCKED\_ON\_TASK,

STARPU\_TASK\_BLOCKED\_ON\_DATA, STARPU\_TASK\_STOPPED }

## **Functions**

- void starpu codelet init (struct starpu codelet \*cl)
- void starpu\_task\_init (struct starpu\_task \*task)
- struct starpu\_task \* starpu\_task\_create (void)
- struct starpu\_task \* starpu\_task\_dup (struct starpu\_task \*task)
- void starpu\_task\_clean (struct starpu\_task \*task)
- void starpu\_task\_destroy (struct starpu\_task \*task)
- int starpu\_task\_wait (struct starpu\_task \*task) STARPU\_WARN\_UNUSED\_RESULT
- int starpu\_task\_submit (struct starpu\_task \*task) STARPU\_WARN\_UNUSED\_RESULT
- int starpu\_task\_submit\_to\_ctx (struct starpu\_task \*task, unsigned sched\_ctx\_id)
- int starpu\_task\_wait\_for\_all (void)
- int starpu task wait for all in ctx (unsigned sched ctx id)
- int starpu\_task\_wait\_for\_n\_submitted (unsigned n)
- int starpu\_task\_wait\_for\_n\_submitted\_in\_ctx (unsigned sched\_ctx\_id, unsigned n)
- int starpu\_task\_nready (void)
- int starpu\_task\_nsubmitted (void)
- struct starpu\_task \* starpu\_task\_get\_current (void)
- void starpu\_codelet\_display\_stats (struct starpu\_codelet \*cl)
- int starpu\_task\_wait\_for\_no\_ready (void)
- void starpu\_task\_set\_implementation (struct starpu\_task \*task, unsigned impl)
- unsigned starpu\_task\_get\_implementation (struct starpu\_task \*task)
- void starpu\_create\_sync\_task (starpu\_tag\_t sync\_tag, unsigned ndeps, starpu\_tag\_t \*deps, void(\*callback)(void \*), void \*callback\_arg)

# 27.13.1 Detailed Description

This section describes the interface to manipulate codelets and tasks.

### 27.13.2 Data Structure Documentation

### 27.13.2.1 struct starpu\_codelet

The codelet structure describes a kernel that is possibly implemented on various targets. For compatibility, make sure to initialize the whole structure to zero, either by using explicit memset, or the function starpu\_codelet\_init(), or by letting the compiler implicitly do it in e.g. static storage case.

#### Data Fields

- · uint32 t where
- int(\* can execute )(unsigned workerid, struct starpu task \*task, unsigned nimpl)
- enum starpu\_codelet\_type type
- int max parallelism
- · starpu\_cpu\_func\_t cpu\_func
- · starpu cuda func t cuda func
- · starpu opencl func topencl func
- starpu\_cpu\_func\_t cpu\_funcs [STARPU\_MAXIMPLEMENTATIONS]
- starpu cuda func t cuda funcs [STARPU MAXIMPLEMENTATIONS]
- char cuda\_flags [STARPU\_MAXIMPLEMENTATIONS]
- starpu\_opencl\_func\_t opencl\_funcs [STARPU\_MAXIMPLEMENTATIONS]
- char opencl flags [STARPU MAXIMPLEMENTATIONS]
- starpu mic func t mic funcs [STARPU MAXIMPLEMENTATIONS]
- starpu\_scc\_func\_t scc\_funcs [STARPU\_MAXIMPLEMENTATIONS]
- char \* cpu\_funcs\_name [STARPU\_MAXIMPLEMENTATIONS]
- int nbuffers
- enum starpu data access mode modes [STARPU NMAXBUFS]
- enum starpu data access mode \* dyn modes
- · unsigned specific nodes
- int nodes [STARPU\_NMAXBUFS]
- int \* dyn nodes
- struct starpu\_perfmodel \* model
- struct starpu\_perfmodel \* power\_model
- unsigned long per\_worker\_stats [STARPU\_NMAXWORKERS]
- const char \* name

# 27.13.2.1.1 Field Documentation

# 27.13.2.1.1.1 uint32\_t starpu\_codelet::where

Optional field to indicate which types of processing units are able to execute the codelet. The different values STAR-PU\_CPU, STARPU\_CUDA, STARPU\_OPENCL can be combined to specify on which types of processing units the codelet can be executed. STARPU\_CPU|STARPU\_CUDA for instance indicates that the codelet is implemented for both CPU cores and CUDA devices while STARPU\_OPENCL indicates that it is only available on OpenCL devices. If the field is unset, its value will be automatically set based on the availability of the XXX\_funcs fields defined below. It can also be set to STARPU\_NOWHERE to specify that no computation has to be actually done.

27.13.2.1.1.2 int(\* starpu\_codelet::can\_execute)(unsigned workerid, struct starpu\_task \*task, unsigned nimpl)

Define a function which should return 1 if the worker designated by workerid can execute the nimplth implementation of the given task, 0 otherwise.

# 27.13.2.1.1.3 enum starpu\_codelet\_type starpu\_codelet::type

Optional field to specify the type of the codelet. The default is STARPU\_SEQ, i.e. usual sequential implementation. Other values (STARPU\_SPMD or STARPU\_FORKJOIN declare that a parallel implementation is also available. See Parallel Tasks for details.

27.13.2.1.1.4 int starpu\_codelet::max\_parallelism

Optional field. If a parallel implementation is available, this denotes the maximum combined worker size that StarPU will use to execute parallel tasks for this codelet.

27.13.2.1.1.5 starpu cpu func t starpu\_codelet::cpu\_func

**Deprecated** Optional field which has been made deprecated. One should use instead the field starpu\_codelet:::cpu\_funcs.

27.13.2.1.1.6 starpu\_cuda\_func\_t starpu\_codelet::cuda\_func

**Deprecated** Optional field which has been made deprecated. One should use instead the starpu\_codelet::cuda\_funcs field.

27.13.2.1.1.7 starpu opencl func t starpu\_codelet::opencl\_func

**Deprecated** Optional field which has been made deprecated. One should use instead the starpu\_codelet::opencl-funcs field.

27.13.2.1.1.8 starpu\_cpu\_func\_t starpu\_codelet::cpu\_funcs[STARPU\_MAXIMPLEMENTATIONS]

Optional array of function pointers to the CPU implementations of the codelet. The functions prototype must be:

```
void cpu_func(void *buffers[], void *cl_arg)
```

The first argument being the array of data managed by the data management library, and the second argument is a pointer to the argument passed from the field <a href="starpu\_task::cl\_arg">starpu\_task::cl\_arg</a>. If the field <a href="starpu\_codelet::where">starpu\_codelet::where</a> is ignored if <a href="starpu\_codelet::where">STARPU\_CPU</a> does not appear in the field <a href="starpu\_codelet::where">starpu\_codelet::where</a>, it must be non-null otherwise.

27.13.2.1.1.9 starpu\_cuda\_func\_t starpu\_codelet::cuda\_funcs[STARPU\_MAXIMPLEMENTATIONS]

Optional array of function pointers to the CUDA implementations of the codelet. The functions must be host-functions written in the CUDA runtime API. Their prototype must be:

```
void cuda_func(void *buffers[], void *cl_arg)
```

If the field starpu\_codelet::where is set, then the field starpu\_codelet::cuda\_funcs is ignored if STARPU\_CUDA does not appear in the field starpu\_codelet::where, it must be non-null otherwise.

27.13.2.1.1.10 char starpu\_codelet::cuda\_flags[STARPU\_MAXIMPLEMENTATIONS]

Optional array of flags for CUDA execution. They specify some semantic details about CUDA kernel execution, such as asynchronous execution.

27.13.2.1.1.11 starpu opencl func t starpu\_codelet::opencl\_funcs[STARPU\_MAXIMPLEMENTATIONS]

Optional array of function pointers to the OpenCL implementations of the codelet. The functions prototype must be:

```
void opencl_func(void *buffers[], void *cl_arg)
```

If the field starpu\_codelet::where field is set, then the field starpu\_codelet::opencl\_funcs is ignored if STARPU\_O-PENCL does not appear in the field starpu\_codelet::where, it must be non-null otherwise.

27.13.2.1.1.12 char starpu\_codelet::opencl\_flags[STARPU\_MAXIMPLEMENTATIONS]

Optional array of flags for OpenCL execution. They specify some semantic details about OpenCL kernel execution, such as asynchronous execution.

27.13.2.1.1.13 starpu\_mic\_func\_t starpu\_codelet::mic\_funcs[STARPU\_MAXIMPLEMENTATIONS]

Optional array of function pointers to a function which returns the MIC implementation of the codelet. The functions prototype must be:

```
starpu_mic_kernel_t mic_func(struct starpu_codelet
     *cl, unsigned nimpl)
```

If the field starpu\_codelet::where is set, then the field starpu\_codelet::mic\_funcs is ignored if STARPU\_MIC does not appear in the field starpu\_codelet::where. It can be null if starpu\_codelet::cpu\_funcs\_name is non-NULL, in which case StarPU will simply make a symbol lookup to get the implementation.

27.13.2.1.1.14 starpu\_scc func t starpu\_codelet::scc\_funcs[STARPU\_MAXIMPLEMENTATIONS]

Optional array of function pointers to a function which returns the SCC implementation of the codelet. The functions prototype must be:

```
starpu_scc_kernel_t scc_func(struct starpu_codelet
    *cl, unsigned nimpl)
```

If the field starpu\_codelet::where is set, then the field starpu\_codelet::scc\_funcs is ignored if STARPU\_SCC does not appear in the field starpu\_codelet::where. It can be null if starpu\_codelet::cpu\_funcs\_name is non-NULL, in which case StarPU will simply make a symbol lookup to get the implementation.

27.13.2.1.1.15 char \* starpu\_codelet::cpu\_funcs\_name[STARPU\_MAXIMPLEMENTATIONS]

Optional array of strings which provide the name of the CPU functions referenced in the array starpu\_codelet::cpu\_funcs. This can be used when running on MIC devices or the SCC platform, for StarPU to simply look up the MIC function implementation through its name.

27.13.2.1.1.16 int starpu\_codelet::nbuffers

Specify the number of arguments taken by the codelet. These arguments are managed by the DSM and are accessed from the <code>void \*buffers[]</code> array. The constant argument passed with the field <code>starpu\_task::cl\_arg</code> is not counted in this number. This value should not be above <code>STARPU\_NMAXBUFS</code>. It may be set to <code>STARPU\_VARIABLE\_NBUFFERS</code> to specify that the number of buffers and their access modes will be set in <code>starpu\_task::nbuffers</code> and <code>starpu\_task::modes</code> or <code>starpu\_task::dyn\_modes</code>, which thus permits to define codelets with a varying number of data.

27.13.2.1.1.17 enum starpu\_data\_access\_mode starpu\_codelet::modes[STARPU\_NMAXBUFS]

Is an array of starpu\_data\_access\_mode. It describes the required access modes to the data needed by the codelet (e.g. STARPU\_RW). The number of entries in this array must be specified in the field starpu\_codelet::nbuffers, and should not exceed STARPU\_NMAXBUFS. If unsufficient, this value can be set with the configure option --enable-maxbuffers.

27.13.2.1.1.18 enum starpu data access mode \* starpu\_codelet::dyn\_modes

Is an array of starpu\_data\_access\_mode. It describes the required access modes to the data needed by the codelet (e.g. STARPU\_RW). The number of entries in this array must be specified in the field starpu\_codelet::nbuffers. This field should be used for codelets having a number of datas greater than STARPU\_NMAXBUFS (see Setting The Data Handles For A Task). When defining a codelet, one should either define this field or the field starpu\_codelet::modes defined above.

27.13.2.1.1.19 unsigned starpu\_codelet::specific\_nodes

Default value is 0. If this flag is set, StarPU will not systematically send all data to the memory node where the task will be executing, it will read the starpu\_codelet::nodes or starpu\_codelet::dyn\_nodes array to determine, for each data, whether to send it on the memory node where the task will be executing (-1), or on a specific node (!= -1).

# 27.13.2.1.1.20 int starpu\_codelet::nodes[STARPU\_NMAXBUFS]

Optional field. When starpu\_codelet::specific\_nodes is 1, this specifies the memory nodes where each data should be sent to for task execution. The number of entries in this array is starpu\_codelet::nbuffers, and should not exceed STARPU\_NMAXBUFS.

27.13.2.1.1.21 int \* starpu\_codelet::dyn\_nodes

Optional field. When starpu\_codelet::specific\_nodes is 1, this specifies the memory nodes where each data should be sent to for task execution. The number of entries in this array is starpu\_codelet::nbuffers. This field should be used for codelets having a number of datas greater than STARPU\_NMAXBUFS (see Setting The Data Handles For A Task). When defining a codelet, one should either define this field or the field starpu\_codelet::nodes defined above.

27.13.2.1.1.22 struct starpu\_perfmodel \* starpu\_codelet::model

Optional pointer to the task duration performance model associated to this codelet. This optional field is ignored when set to NULL or when its field starpu\_perfmodel::symbol is not set.

27.13.2.1.1.23 struct starpu\_perfmodel \* starpu\_codelet::power\_model

Optional pointer to the task power consumption performance model associated to this codelet. This optional field is ignored when set to <code>NULL</code> or when its field starpu\_perfmodel::field is not set. In the case of parallel codelets, this has to account for all processing units involved in the parallel execution.

27.13.2.1.1.24 unsigned long starpu\_codelet::per\_worker\_stats[STARPU\_NMAXWORKERS]

Optional array for statistics collected at runtime: this is filled by StarPU and should not be accessed directly, but for example by calling the function starpu\_codelet\_display\_stats() (See starpu\_codelet\_display\_stats() for details).

27.13.2.1.1.25 const char \* starpu\_codelet::name

Optional name of the codelet. This can be useful for debugging purposes.

27.13.2.2 struct starpu\_data\_descr

This type is used to describe a data handle along with an access mode.

# Data Fields

	starpu_data handle t	handle	describes a data
f	enum	mode	describes its access mode
	starpu_data		
	access_mode		

# 27.13.2.3 struct starpu\_task

The structure describes a task that can be offloaded on the various processing units managed by StarPU. It instantiates a codelet. It can either be allocated dynamically with the function <a href="mailto:starpu\_task\_create">starpu\_task\_create</a>(), or declared statically. In the latter case, the programmer has to zero the structure <a href="mailto:starpu\_task">starpu\_task</a> and to fill the different fields properly. The indicated default values correspond to the configuration of a task allocated with <a href="mailto:starpu\_task\_create">starpu\_task</a> create().

## **Data Fields**

- · const char \* name
- struct starpu\_codelet \* cl

- · int nbuffers
- starpu\_data\_handle\_t handles [STARPU\_NMAXBUFS]
- void \* interfaces [STARPU NMAXBUFS]
- enum starpu data access mode modes [STARPU NMAXBUFS]
- starpu data handle t \* dyn handles
- void \*\* dyn\_interfaces
- enum starpu\_data\_access\_mode \* dyn\_modes
- void \* cl arg
- · size t cl arg size
- void(\* callback\_func )(void \*)
- void \* callback\_arg
- void(\* prologue callback func )(void \*)
- void \* prologue callback arg
- void(\* prologue\_callback\_pop\_func )(void \*)
- void \* prologue\_callback\_pop\_arg
- · starpu\_tag\_t tag\_id
- unsigned cl\_arg\_free:1
- · unsigned callback arg free:1
- · unsigned prologue\_callback\_arg\_free:1
- unsigned prologue\_callback\_pop\_arg\_free:1
- unsigned use\_tag:1
- · unsigned sequential\_consistency:1
- unsigned synchronous:1
- unsigned execute\_on\_a\_specific\_worker:1
- · unsigned detach:1
- · unsigned destroy:1
- unsigned regenerate:1
- unsigned workerid
- · unsigned workerorder
- unsigned scheduled:1
- unsigned int mf\_skip:1
- · int priority
- · enum starpu\_task\_status status
- · int magic
- unsigned sched ctx
- int hypervisor\_tag
- unsigned possibly\_parallel
- starpu\_task\_bundle\_t bundle
- struct starpu\_profiling\_task\_info \* profiling\_info
- · double flops
- · double predicted
- double predicted\_transfer
- struct starpu task \* prev
- struct starpu\_task \* next
- void \* starpu private
- · unsigned prefetched
- struct starpu\_omp\_task \* omp\_task

## 27.13.2.3.1 Field Documentation

# 27.13.2.3.1.1 const char \* starpu\_task::name

Optional name of the task. This can be useful for debugging purposes.

27.13.2.3.1.2 struct starpu\_codelet \* starpu\_task::cl

Is a pointer to the corresponding structure starpu\_codelet. This describes where the kernel should be executed, and supplies the appropriate implementations. When set to NULL, no code is executed during the tasks, such empty tasks can be useful for synchronization purposes. This field has been made deprecated. One should use instead the field starpu\_task::handles to specify the data handles accessed by the task. The access modes are now defined in the field starpu\_codelet::modes.

27.13.2.3.1.3 int starpu\_task::nbuffers

Specifies the number of buffers. This is only used when <a href="mailto:starpu\_codelet::nbuffers">starpu\_codelet::nbuffers</a> is STARPU\_VARIABLE\_NBUFF-ERS.

27.13.2.3.1.4 starpu\_data\_handle\_t starpu\_task::handles[STARPU\_NMAXBUFS]

Is an array of starpu\_data\_handle\_t. It specifies the handles to the different pieces of data accessed by the task. The number of entries in this array must be specified in the field starpu\_codelet::nbuffers, and should not exceed STARPU\_NMAXBUFS. If unsufficient, this value can be set with the configure option --enable-maxbuffers.

27.13.2.3.1.5 void \* starpu\_task::interfaces[STARPU NMAXBUFS]

The actual data pointers to the memory node where execution will happen, managed by the DSM.

27.13.2.3.1.6 enum starpu\_data\_access\_mode starpu\_task::modes[STARPU\_NMAXBUFS]

Is used only when starpu\_codelet::nbuffers is STARPU\_VARIABLE\_NBUFFERS. It is an array of starpu\_data\_-access\_mode. It describes the required access modes to the data needed by the codelet (e.g. STARPU\_RW). The number of entries in this array must be specified in the field starpu\_task::nbuffers, and should not exceed STARPU\_NMAXBUFS. If unsufficient, this value can be set with the configure option --enable-maxbuffers.

27.13.2.3.1.7 starpu\_data\_handle\_t \* starpu\_task::dyn\_handles

Is an array of <a href="starpu\_data\_handle\_t">starpu\_data\_handle\_t</a>. It specifies the handles to the different pieces of data accessed by the task. The number of entries in this array must be specified in the field <a href="starpu\_codelet::nbuffers">starpu\_codelet::nbuffers</a>. This field should be used for tasks having a number of datas greater than <a href="starpu\_NMAXBUFS">STARPU\_NMAXBUFS</a> (see Setting The Data Handles For A Task). When defining a task, one should either define this field or the field <a href="starpu\_task::handles">starpu\_task::handles</a> defined above.

27.13.2.3.1.8 void \*\* starpu\_task::dyn\_interfaces

The actual data pointers to the memory node where execution will happen, managed by the DSM. Is used when the field <a href="starpu\_task::dyn\_handles">starpu\_task::dyn\_handles</a> is defined.

27.13.2.3.1.9 enum starpu\_data\_access\_mode \* starpu\_task::dyn\_modes

Is used only when <a href="starpu\_codelet::nbuffers">starpu\_codelet::nbuffers</a> is STARPU\_VARIABLE\_NBUFFERS. It is an array of <a href="starpu\_data\_access\_mode">starpu\_codelet::nbuffers</a>. It is an array of <a href="starpu\_data\_access\_mode">starpu\_data\_access\_mode</a>. It describes the required access modes to the data needed by the codelet (e.g. <a href="starpu\_RW">STARPU\_RW</a>). The number of entries in this array must be specified in the field <a href="starpu\_codelet::nbuffers">starpu\_codelet::nbuffers</a>. This field should be used for codelets having a number of datas greater than <a href="starpu\_NMAXBUFS">STARPU\_NMAXBUFS</a> (see Setting The Data Handles For A Task). When defining a codelet, one should either define this field or the field <a href="starpu\_task::modes">starpu\_task::modes</a> defined above.

27.13.2.3.1.10 void \* starpu\_task::cl\_arg

Optional pointer which is passed to the codelet through the second argument of the codelet implementation (e.g.  $starpu\_codelet::cpu\_func$  or  $starpu\_codelet::cuda\_func$ ). The default value is NULL.

27.13.2.3.1.11 size\_t starpu\_task::cl\_arg\_size

Optional field. For some specific drivers, the pointer starpu\_task::cl\_arg cannot not be directly given to the driver function. A buffer of size starpu\_task::cl\_arg\_size needs to be allocated on the driver. This buffer is then filled with the starpu\_task::cl\_arg\_size bytes starting at address starpu\_task::cl\_arg. In this case, the argument given to the codelet is therefore not the starpu\_task::cl\_arg pointer, but the address of the buffer in local store (LS) instead. This

field is ignored for CPU, CUDA and OpenCL codelets, where the starpu\_task::cl\_arg pointer is given as such.

27.13.2.3.1.12 void(\* starpu\_task::callback\_func)(void \*)

Optional field, the default value is NULL. This is a function pointer of prototype void (\*f) (void \*) which specifies a possible callback. If this pointer is non-null, the callback function is executed on the host after the execution of the task. Tasks which depend on it might already be executing. The callback is passed the value contained in the starpu\_task::callback\_arg field. No callback is executed if the field is set to NULL.

27.13.2.3.1.13 void \* starpu\_task::callback\_arg

Optional field, the default value is NULL. This is the pointer passed to the callback function. This field is ignored if the field starpu task::callback func is set to NULL.

27.13.2.3.1.14 void(\* starpu\_task::prologue\_callback\_func)(void \*)

Optional field, the default value is NULL. This is a function pointer of prototype void (\*f) (void \*) which specifies a possible callback. If this pointer is non-null, the callback function is executed on the host when the task becomes ready for execution, before getting scheduled. The callback is passed the value contained in the starpu\_task::prologue\_callback\_arg field. No callback is executed if the field is set to NULL.

27.13.2.3.1.15 void \* starpu\_task::prologue\_callback\_arg

Optional field, the default value is NULL. This is the pointer passed to the prologue callback function. This field is ignored if the field starpu\_task::prologue\_callback\_func is set to NULL.

27.13.2.3.1.16 starpu\_tag\_t starpu\_task::tag\_id

This optional field contains the tag associated to the task if the field <a href="starpu\_task::use\_tag">starpu\_task::use\_tag</a> is set, it is ignored otherwise.

27.13.2.3.1.17 unsigned starpu\_task::cl\_arg\_free

Optional field. In case starpu\_task::cl\_arg was allocated by the application through malloc(), setting starpu\_task::cl\_arg\_free to 1 makes StarPU automatically call free(cl\_arg) when destroying the task. This saves the user from defining a callback just for that. This is mostly useful when targetting MIC or SCC, where the codelet does not execute in the same memory space as the main thread.

27.13.2.3.1.18 unsigned starpu\_task::callback\_arg\_free

Optional field. In case starpu\_task::callback\_arg was allocated by the application through malloc(), setting starpu\_task::callback\_arg\_free to 1 makes StarPU automatically call free (callback\_arg) when destroying the task.

27.13.2.3.1.19 unsigned starpu\_task::prologue\_callback\_arg\_free

Optional field. In case starpu\_task::prologue\_callback\_arg was allocated by the application through malloc(), setting starpu\_task::prologue\_callback\_arg\_free to 1 makes StarPU automatically call free (prologue\_callback\_arg) when destroying the task.

27.13.2.3.1.20 unsigned starpu\_task::use\_tag

Optional field, the default value is 0. If set, this flag indicates that the task should be associated with the tag contained in the <a href="mailto:starpu\_task::tag\_id">starpu\_task::tag\_id</a> field. Tag allow the application to synchronize with the task and to express task dependencies easily.

27.13.2.3.1.21 unsigned starpu\_task::sequential\_consistency

If this flag is set (which is the default), sequential consistency is enforced for the data parameters of this task for which sequential consistency is enabled. Clearing this flag permits to disable sequential consistency for this task, even if data have it enabled.

27.13.2.3.1.22 unsigned starpu\_task::synchronous

If this flag is set, the function <a href="starpu\_task\_submit(">starpu\_task\_submit()</a> is blocking and returns only when the task has been executed (or if no worker is able to process the task). Otherwise, <a href="starpu\_task\_submit(">starpu\_task\_submit()</a> returns immediately.

27.13.2.3.1.23 unsigned starpu\_task::execute\_on\_a\_specific\_worker

Default value is 0. If this flag is set, StarPU will bypass the scheduler and directly affect this task to the worker specified by the field starpu\_task::workerid.

27.13.2.3.1.24 unsigned starpu\_task::detach

Optional field, default value is 1. If this flag is set, it is not possible to synchronize with the task by the means of <a href="mailto:starpu\_task\_wait">starpu\_task\_wait()</a> later on. Internal data structures are only guaranteed to be freed once <a href="mailto:starpu\_task\_wait()">starpu\_task\_wait()</a> is called if the flag is not set.

27.13.2.3.1.25 unsigned starpu\_task::destroy

Optional value. Default value is 0 for <a href="starpu\_task\_init">starpu\_task\_create()</a>. If this flag is set, the task structure will automatically be freed, either after the execution of the callback if the task is detached, or during <a href="starpu\_task\_wait">starpu\_task\_wait()</a>) otherwise. If this flag is not set, dynamically allocated data structures will not be freed until <a href="starpu\_task\_destroy">starpu\_task\_destroy()</a>) is called explicitly. Setting this flag for a statically allocated task structure will result in undefined behaviour. The flag is set to 1 when the task is created by calling <a href="starpu\_task\_create()">starpu\_task\_create()</a>. Note that <a href="starpu\_task\_wait\_for\_all()">starpu\_task\_create()</a>. Note that <a href="starpu\_task\_wait\_for\_all()">starpu\_task\_create()</a>. Note that <a href="starpu\_task\_wait\_for\_all()">starpu\_task\_wait\_for\_all()</a> will not free any task.

27.13.2.3.1.26 unsigned starpu\_task::regenerate

Optional field. If this flag is set, the task will be re-submitted to StarPU once it has been executed. This flag must not be set if the flag starpu\_task::destroy is set. This flag must be set before making another task depend on this one.

27.13.2.3.1.27 unsigned starpu\_task::workerid

Optional field. If the field starpu\_task::execute\_on\_a\_specific\_worker is set, this field indicates the identifier of the worker that should process this task (as returned by starpu\_worker\_get\_id()). This field is ignored if the field starpu\_task::execute\_on\_a\_specific\_worker is set to 0.

27.13.2.3.1.28 unsigned starpu\_task::workerorder

Optional field. If the field starpu\_task::execute\_on\_a\_specific\_worker is set, this field indicates the per-worker consecutive order in which tasks should be executed on the worker. Tasks will be executed in consecutive starpu\_task::workerorder values, thus ignoring the availability order or task priority. See Static Scheduling for more details. This field is ignored if the field starpu\_task::execute\_on\_a\_specific\_worker is set to 0.

27.13.2.3.1.29 unsigned starpu\_task::scheduled

Whether the scheduler has pushed the task on some queue

27.13.2.3.1.30 unsigned int starpu\_task::mf\_skip

This is only used for tasks that use multiformat handle. This should only be used by StarPU.

27.13.2.3.1.31 int starpu\_task::priority

Optional field, the default value is STARPU\_DEFAULT\_PRIO. This field indicates a level of priority for the task. This is an integer value that must be set between the return values of the function starpu\_sched\_get\_min\_priority() for the least important tasks, and that of the function starpu\_sched\_get\_max\_priority() for the most important tasks (included). The STARPU\_MIN\_PRIO and STARPU\_MAX\_PRIO macros are provided for convenience and respectively returns the value of starpu\_sched\_get\_min\_priority() and starpu\_sched\_get\_max\_priority(). Default priority is STARPU\_DEFAULT\_PRIO, which is always defined as 0 in order to allow static task initialization. Scheduling strategies that take priorities into account can use this parameter to take better scheduling decisions, but the

scheduling policy may also ignore it.

27.13.2.3.1.32 enum starpu\_task\_status starpu\_task::status

Optional field. Current state of the task.

27.13.2.3.1.33 int starpu\_task::magic

This field is set when initializing a task. The function <a href="mailto:starpu\_task\_submit">starpu\_task\_submit</a>() will fail if the field does not have the right value. This will hence avoid submitting tasks which have not been properly initialised.

27.13.2.3.1.34 unsigned starpu\_task::sched\_ctx

Scheduling context.

27.13.2.3.1.35 int starpu\_task::hypervisor\_tag

Helps the hypervisor monitor the execution of this task.

27.13.2.3.1.36 starpu task bundle t starpu\_task::bundle

Optional field. The bundle that includes this task. If no bundle is used, this should be NULL.

27.13.2.3.1.37 struct starpu\_profiling\_task\_info \* starpu\_task::profiling\_info

Optional field. Profiling information for the task.

27.13.2.3.1.38 double starpu\_task::flops

This can be set to the number of floating points operations that the task will have to achieve. This is useful for easily getting GFlops curves from the tool starpu\_perfmodel\_plot, and for the hypervisor load balancing.

27.13.2.3.1.39 double starpu\_task::predicted

Output field. Predicted duration of the task. This field is only set if the scheduling strategy uses performance models.

27.13.2.3.1.40 double starpu\_task::predicted\_transfer

Optional field. Predicted data transfer duration for the task in microseconds. This field is only valid if the scheduling strategy uses performance models.

27.13.2.3.1.41 struct starpu\_task \* starpu\_task::prev

A pointer to the previous task. This should only be used by StarPU.

27.13.2.3.1.42 struct starpu\_task \* starpu\_task::next

A pointer to the next task. This should only be used by StarPU.

27.13.2.3.1.43 void \* starpu\_task::starpu\_private

This is private to StarPU, do not modify. If the task is allocated by hand (without starpu\_task\_create()), this field should be set to NULL.

## 27.13.3 Macro Definition Documentation

### 27.13.3.1 #define STARPU\_NOWHERE

This macro is used when setting the field starpu\_codelet::where to specify that the codelet has no computation part, and thus does not need to be scheduled, and data does not need to be actually loaded. This is thus essentially used for synchronization tasks.

### 27.13.3.2 #define STARPU\_CPU

This macro is used when setting the field starpu\_codelet::where to specify the codelet may be executed on a CPU processing unit.

### 27.13.3.3 #define STARPU\_CUDA

This macro is used when setting the field starpu\_codelet::where to specify the codelet may be executed on a CUDA processing unit.

#### 27.13.3.4 #define STARPU\_OPENCL

This macro is used when setting the field starpu\_codelet::where to specify the codelet may be executed on a Open-CL processing unit.

### 27.13.3.5 #define STARPU\_MIC

This macro is used when setting the field starpu\_codelet::where to specify the codelet may be executed on a MIC processing unit.

# 27.13.3.6 #define STARPU\_SCC

This macro is used when setting the field starpu\_codelet::where to specify the codelet may be executed on an SCC processing unit.

### 27.13.3.7 #define STARPU\_MAIN\_RAM

This macro is used when the RAM memory node is specified.

# 27.13.3.8 #define STARPU\_MULTIPLE\_CPU\_IMPLEMENTATIONS

**Deprecated** Setting the field starpu\_codelet::cpu\_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu\_codelet::cpu\_funcs.

# 27.13.3.9 #define STARPU\_MULTIPLE\_CUDA\_IMPLEMENTATIONS

**Deprecated** Setting the field starpu\_codelet::cuda\_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu\_codelet::cuda\_funcs.

### 27.13.3.10 #define STARPU\_MULTIPLE\_OPENCL\_IMPLEMENTATIONS

**Deprecated** Setting the field starpu\_codelet::opencl\_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu\_codelet::opencl\_funcs.

### 27.13.3.11 #define STARPU\_NMAXBUFS

Defines the maximum number of buffers that tasks will be able to take as parameters. The default value is 8, it can be changed by using the configure option --enable-maxbuffers.

## 27.13.3.12 #define STARPU\_VARIABLE\_NBUFFERS

Value to set in starpu\_codelet::nbuffers to specify that the codelet can accept a variable number of buffers, specified in starpu\_task::nbuffers.

### 27.13.3.13 #define STARPU\_TASK\_INITIALIZER

It is possible to initialize statically allocated tasks with this value. This is equivalent to initializing a structure starputask with the function starputask init() function.

```
27.13.3.14 #define STARPU_TASK_GET_NBUFFERS( task )
```

Return the number of buffers for this task, i.e. starpu\_codelet::nbuffers, or starpu\_task::nbuffers if the former is STARPU\_VARIABLE\_BUFFERS.

```
27.13.3.15 #define STARPU_TASK_GET_HANDLE( task, i)
```

Return the i th data handle of the given task. If the task is defined with a static or dynamic number of handles, will either return the i th element of the field starpu\_task::handles or the i th element of the field starpu\_task::dyn\_handles (see Setting The Data Handles For A Task)

```
27.13.3.16 #define STARPU_TASK_SET_HANDLE( task, handle, i)
```

Set the i th data handle of the given task with the given dat handle. If the task is defined with a static or dynamic number of handles, will either set the i th element of the field starpu\_task::handles or the i th element of the field starpu task::dyn handles (see Setting The Data Handles For A Task)

```
27.13.3.17 #define STARPU_CODELET_GET_MODE( codelet, i)
```

Return the access mode of the i th data handle of the given codelet. If the codelet is defined with a static or dynamic number of handles, will either return the i th element of the field starpu\_codelet::modes or the i th element of the field starpu\_codelet::dyn\_modes (see Setting The Data Handles For A Task)

```
27.13.3.18 #define STARPU_CODELET_SET_MODE( codelet, mode, i)
```

Set the access mode of the i th data handle of the given codelet. If the codelet is defined with a static or dynamic number of handles, will either set the i th element of the field starpu\_codelet::modes or the i th element of the field starpu\_codelet::dyn\_modes (see Setting The Data Handles For A Task)

```
27.13.3.19 #define STARPU_TASK_GET_MODE( task, i)
```

Return the access mode of the i th data handle of the given task. If the task is defined with a static or dynamic number of handles, will either return the i th element of the field starpu\_task::modes or the i th element of the field starpu\_task::dyn\_modes (see Setting The Data Handles For A Task)

```
27.13.3.20 #define STARPU_TASK_SET_MODE( task, mode, i)
```

Set the access mode of the i th data handle of the given task. If the task is defined with a static or dynamic number of handles, will either set the i th element of the field starpu\_task::modes or the i th element of the field starpu\_task::dyn\_modes (see Setting The Data Handles For A Task)

27.13.3.21 starpu\_task\_status::STARPU\_TASK\_INVALID

The task has just been initialized.

27.13.4 Typedef Documentation

27.13.4.1 starpu\_cpu\_func\_t

CPU implementation of a codelet.

27.13.4.2 starpu\_cuda\_func\_t

CUDA implementation of a codelet.

27.13.4.3 starpu\_opencl\_func\_t

OpenCL implementation of a codelet.

27.13.4.4 starpu\_mic\_func\_t

MIC implementation of a codelet.

27.13.4.5 starpu\_scc\_func\_t

SCC implementation of a codelet.

27.13.4.6 starpu\_mic\_kernel\_t

MIC kernel for a codelet

27.13.4.7 \* starpu\_scc\_kernel\_t

SCC kernel for a codelet

# 27.13.5 Enumeration Type Documentation

27.13.5.1 enum starpu\_codelet\_type

Describes the type of parallel task. See Parallel Tasks for details.

**Enumerator:** 

**STARPU\_SEQ** (default) for classical sequential tasks.

**STARPU\_SPMD** for a parallel task whose threads are handled by StarPU, the code has to use starpu\_combined worker get size() and starpu combined worker get rank() to distribute the work.

**STARPU\_FORKJOIN** for a parallel task whose threads are started by the codelet function, which has to use starpu\_combined\_worker\_get\_size() to determine how many threads should be started.

27.13.5.2 enum starpu task status

Task status

**Enumerator:** 

**STARPU\_TASK\_BLOCKED** The task has just been submitted, and its dependencies has not been checked yet.

**STARPU\_TASK\_READY** The task is ready for execution.

STARPU\_TASK\_RUNNING The task is running on some worker.

STARPU\_TASK\_FINISHED The task is finished executing.

STARPU\_TASK\_BLOCKED\_ON\_TAG The task is waiting for a tag.

STARPU\_TASK\_BLOCKED\_ON\_TASK The task is waiting for a task.

STARPU\_TASK\_BLOCKED\_ON\_DATA The task is waiting for some data.

# 27.13.6 Function Documentation

27.13.6.1 void starpu\_codelet\_init ( struct starpu\_codelet \* cl )

Initialize cl with default values. Codelets should preferably be initialized statically as shown in Defining A Codelet. However such a initialisation is not always possible, e.g. when using C++.

```
27.13.6.2 void starpu_task_init ( struct starpu_task * task )
```

Initialize task with default values. This function is implicitly called by starpu\_task\_create(). By default, tasks initialized with starpu\_task\_init() must be deinitialized explicitly with starpu\_task\_clean(). Tasks can also be initialized statically, using STARPU\_TASK\_INITIALIZER.

```
27.13.6.3 struct starpu_task * starpu_task_create ( void ) [read]
```

Allocate a task structure and initialize it with default values. Tasks allocated dynamically with starpu\_task\_create() are automatically freed when the task is terminated. This means that the task pointer can not be used any more once the task is submitted, since it can be executed at any time (unless dependencies make it wait) and thus freed at any time. If the field starpu\_task::destroy is explicitly unset, the resources used by the task have to be freed by calling starpu\_task\_destroy().

```
27.13.6.4 struct starpu task * starpu_task_dup( struct starpu task * task ) [read]
```

Allocate a task structure which is the exact duplicate of the given task.

27.13.6.5 void starpu\_task\_clean ( struct starpu\_task \* task )

Release all the structures automatically allocated to execute task, but not the task structure itself and values set by the user remain unchanged. It is thus useful for statically allocated tasks for instance. It is also useful when users want to execute the same operation several times with as least overhead as possible. It is called automatically by starpu\_task\_destroy(). It has to be called only after explicitly waiting for the task or after starpu\_shutdown() (waiting for the callback is not enough, since StarPU still manipulates the task after calling the callback).

```
27.13.6.6 void starpu_task_destroy ( struct starpu_task * task )
```

Free the resource allocated during <a href="mailto:starpu\_task\_create">starpu\_task\_create</a>() and associated with task. This function is already called automatically after the execution of a task when the field <a href="mailto:starpu\_task::destroy">starpu\_task</a>::destroy is set, which is the default for tasks created by <a href="mailto:starpu\_task\_create">starpu\_task\_create</a>(). Calling this function on a statically allocated task results in an undefined behaviour.

```
27.13.6.7 int starpu_task_wait ( struct starpu_task * task )
```

This function blocks until task has been executed. It is not possible to synchronize with a task more than once. It is not possible to wait for synchronous or detached tasks. Upon successful completion, this function returns 0. Otherwise, -EINVAL indicates that the specified task was either synchronous or detached.

```
27.13.6.8 int starpu_task_submit ( struct starpu_task * task )
```

This function submits task to StarPU. Calling this function does not mean that the task will be executed immediately as there can be data or task (tag) dependencies that are not fulfilled yet: StarPU will take care of scheduling this task with respect to such dependencies. This function returns immediately if the field starpu\_task::synchronous is set to 0, and block until the termination of the task otherwise. It is also possible to synchronize the application with asynchronous tasks by the means of tags, using the function starpu\_tag\_wait() function for instance. In case of success, this function returns 0, a return value of -ENODEV means that there is no worker able to process this task (e.g. there is no GPU available and this task is only implemented for CUDA devices). starpu\_task\_submit() can be called from anywhere, including codelet functions and callbacks, provided that the field starpu\_task::synchronous is set to 0.

```
27.13.6.9 int starpu_task_submit_to_ctx ( struct starpu_task * task, unsigned sched_ctx_id )
```

This function submits a task to StarPU to the context <code>sched\_ctx\_id</code> . By default starpu\_task\_submit submits the task to a global context that is created automatically by StarPU.

```
27.13.6.10 int starpu_task_wait_for_all ( void )
```

This function blocks until all the tasks that were submitted (to the current context or the global one if there aren't any) are terminated. It does not destroy these tasks.

```
27.13.6.11 int starpu_task_wait_for_all_in_ctx ( unsigned sched_ctx_id )
```

This function waits until all the tasks that were already submitted to the context sched\_ctx\_id have been executed

```
27.13.6.12 int starpu_task_wait_for_n_submitted ( unsigned n )
```

This function blocks until there are n submitted tasks left (to the current context or the global one if there aren't any) to be executed. It does not destroy these tasks.

27.13.6.13 int starpu\_task\_wait\_for\_n\_submitted\_in\_ctx ( unsigned sched\_ctx\_id, unsigned n )

This function waits until there are n tasks submitted left to be executed that were already submitted to the context  $sched\_ctx\_id$ .

27.13.6.14 int starpu\_task\_nready ( void )

### **TODO**

Return the number of submitted tasks which are ready for execution are already executing. It thus does not include tasks waiting for dependencies.

27.13.6.15 int starpu\_task\_nsubmitted ( void )

Return the number of submitted tasks which have not completed yet.

```
27.13.6.16 struct starpu_task * starpu_task_get_current( void ) [read]
```

This function returns the task currently executed by the worker, or NULL if it is called either from a thread that is not a task or simply because there is no task being executed at the moment.

27.13.6.17 void starpu\_codelet\_display\_stats ( struct starpu\_codelet \* cl )

Output on stderr some statistics on the codelet cl.

27.13.6.18 int starpu\_task\_wait\_for\_no\_ready ( void )

This function waits until there is no more ready task.

27.13.6.19 void starpu\_task\_set\_implementation ( struct starpu\_task \* task, unsigned impl )

This function should be called by schedulers to specify the codelet implementation to be executed when executing the task.

27.13.6.20 unsigned starpu\_task\_get\_implementation ( struct starpu\_task \* task )

This function return the codelet implementation to be executed when executing the task.

27.13.6.21 void starpu\_create\_sync\_task ( starpu\_tag\_t sync\_tag, unsigned ndeps, starpu\_tag\_t \* deps, void(\*)(void \*) callback, void \* callback\_arg )

This creates (and submits) an empty task that unlocks a tag once all its dependencies are fulfilled.

# 27.14 Insert\_Task

# **Macros**

- #define STARPU VALUE
- #define STARPU CALLBACK
- #define STARPU\_CALLBACK\_WITH\_ARG

27.14 Insert\_Task 241

- #define STARPU\_CALLBACK\_ARG
- #define STARPU\_PRIORITY
- #define STARPU\_DATA\_ARRAY
- #define STARPU DATA MODE ARRAY
- #define STARPU EXECUTE ON WORKER
- #define STARPU WORKER ORDER
- #define STARPU\_TAG
- #define STARPU\_TAG\_ONLY
- #define STARPU NAME
- #define STARPU FLOPS
- #define STARPU\_SCHED\_CTX

### **Functions**

- int starpu\_insert\_task (struct starpu\_codelet \*cl,...)
- int starpu task insert (struct starpu codelet \*cl,...)
- void starpu\_codelet\_pack\_args (void \*\*arg\_buffer, size\_t \*arg\_buffer\_size,...)
- void starpu codelet unpack args (void \*cl arg,...)
- struct starpu\_task \* starpu\_task\_build (struct starpu\_codelet \*cl,...)

## 27.14.1 Detailed Description

### 27.14.2 Macro Definition Documentation

### 27.14.2.1 #define STARPU\_VALUE

this macro is used when calling starpu\_task\_insert(), and must be followed by a pointer to a constant value and the size of the constant

# 27.14.2.2 #define STARPU\_CALLBACK

this macro is used when calling starpu\_task\_insert(), and must be followed by a pointer to a callback function

### 27.14.2.3 #define STARPU\_CALLBACK\_WITH\_ARG

this macro is used when calling starpu\_task\_insert(), and must be followed by two pointers: one to a callback function, and the other to be given as an argument to the callback function; this is equivalent to using both STARP-U\_CALLBACK and STARPU\_CALLBACK\_WITH\_ARG.

### 27.14.2.4 #define STARPU\_CALLBACK\_ARG

this macro is used when calling starpu\_task\_insert(), and must be followed by a pointer to be given as an argument to the callback function

### 27.14.2.5 #define STARPU\_PRIORITY

this macro is used when calling starpu\_task\_insert(), and must be followed by a integer defining a priority level

# 27.14.2.6 #define STARPU\_DATA\_ARRAY

# **TODO**

### 27.14.2.7 #define STARPU\_DATA\_MODE\_ARRAY

TODO

## 27.14.2.8 #define STARPU\_EXECUTE\_ON\_WORKER

this macro is used when calling starpu\_task\_insert(), and must be followed by an integer value specifying the worker on which to execute the task (as specified by starpu\_task::execute\_on\_a\_specific\_worker)

#### 27.14.2.9 #define STARPU\_WORKER\_ORDER

this macro is used when calling <a href="mailto:starpu\_task\_insert">starpu\_task\_insert</a>(), and must be followed by an integer value specifying the worker order in which to execute the tasks (as specified by <a href="mailto:starpu\_task::workerorder">starpu\_task::workerorder</a>)

### 27.14.2.10 #define STARPU\_TAG

this macro is used when calling starpu\_task\_insert(), and must be followed by a tag.

### 27.14.2.11 #define STARPU\_TAG\_ONLY

this macro is used when calling starpu\_task\_insert(), and must be followed by a tag. It sets starpu\_task::tag\_id, but leaves starpu\_task::use\_tag as 0.

#### 27.14.2.12 #define STARPU\_NAME

this macro is used when calling starpu\_task\_insert(), and must be followed by a char \*. It sets starpu\_task::name to it.

## 27.14.2.13 #define STARPU\_FLOPS

this macro is used when calling <a href="mailto:starpu\_task\_insert">starpu\_task\_insert</a>(), and must be followed by an amount of floating point operations, as a double. Users <a href="mailto:must be followed">must be followed by an amount of floating point operations</a>, as a double. Users <a href="mailto:must be followed">must be followed by an amount of floating point operations</a>, as a double. Users <a href="mailto:must be followed">must be followed by an amount of floating point operations</a>, as a double. Users <a href="mailto:must be followed">must be followed</a> by an amount of floating point operations, as a double. Users <a href="mailto:must be followed">must be followed</a> by an amount of floating point operations, as a double. Users <a href="mailto:must be followed">must be followed</a> by an amount of floating point operations.

# 27.14.2.14 #define STARPU\_SCHED\_CTX

this macro is used when calling starpu\_task\_insert(), and must be followed by the id of the scheduling context to which we want to submit the task.

# 27.14.3 Function Documentation

```
27.14.3.1 starpu_insert_task ( struct starpu_codelet * cl, ... )
```

This function does the same as the function starpu task insert(). It has been kept to avoid breaking old codes.

```
27.14.3.2 int starpu_task_insert ( struct starpu_codelet * cl, ... )
```

Create and submit a task corresponding to cl with the following arguments. The argument list must be zero-terminated.

The arguments following the codelet can be of the following types:

- STARPU\_R, STARPU\_W, STARPU\_RW, STARPU\_SCRATCH, STARPU\_REDUX an access mode followed by a data handle;
- STARPU\_DATA\_ARRAY followed by an array of data handles and its number of elements;
- STARPU\_DATA\_MODE\_ARRAY followed by an array of struct starpu\_data\_descr, i.e data handles with their associated access modes, and its number of elements;
- STARPU\_EXECUTE\_ON\_WORKER, STARPU\_WORKER\_ORDER followed by an integer value specifying the worker on which to execute the task (as specified by starpu\_task::execute\_on\_a\_specific\_worker)
- the specific values STARPU\_VALUE, STARPU\_CALLBACK, STARPU\_CALLBACK\_ARG, STARPU\_CALLBACK\_WITH\_ARG, STARPU\_PRIORITY, STARPU\_TAG, STARPU\_TAG\_ONLY, STARPU\_FLOPS, STARPU\_SCHED\_CTX followed by the appropriated objects as defined elsewhere.

When using STARPU\_DATA\_ARRAY, the access mode of the data handles is not defined, it will be taken from the codelet starpu\_codelet::modes or starpu\_codelet::dyn\_modes field. One should use STARPU\_DATA\_MODE\_ARRAY to define the data handles along with the access modes.

Parameters to be passed to the codelet implementation are defined through the type STARPU\_VALUE. The function starpu\_codelet\_unpack\_args() must be called within the codelet implementation to retrieve them.

```
27.14.3.3 void starpu_codelet_pack_args ( void ** arg_buffer, size_t * arg_buffer_size, ... )
```

Pack arguments of type STARPU\_VALUE into a buffer which can be given to a codelet and later unpacked with the function starpu\_codelet\_unpack\_args().

```
27.14.3.4 void starpu_codelet_unpack_args ( void * cl_arg, ... )
```

Retrieve the arguments of type STARPU\_VALUE associated to a task automatically created using the function starpu task insert().

```
27.14.3.5 struct starpu_task * starpu_task_build ( struct starpu_codelet * cl, ... ) [read]
```

Create a task corresponding to cl with the following arguments. The argument list must be zero-terminated. The arguments following the codelet are the same as the ones for the function <a href="mailto:starpu\_task\_insert">starpu\_task\_insert</a>(). If some arguments of type <a href="mailto:STARPU\_VALUE">STARPU\_VALUE</a> are given, the parameter <a href="mailto:starpu\_task::cl\_arg\_free">starpu\_task::cl\_arg\_free</a> will be set to 1.

# 27.15 Explicit Dependencies

## **Typedefs**

· typedef uint64\_t starpu\_tag\_t

### **Functions**

- void starpu\_task\_declare\_deps\_array (struct starpu\_task \*task, unsigned ndeps, struct starpu\_task \*task\_array[])
- int starpu\_task\_get\_task\_succs (struct starpu\_task \*task, unsigned ndeps, struct starpu\_task \*task\_array[])
- void starpu\_tag\_declare\_deps (starpu\_tag\_t id, unsigned ndeps,...)
- void starpu\_tag\_declare\_deps\_array (starpu\_tag\_t id, unsigned ndeps, starpu\_tag\_t \*array)
- int starpu\_tag\_wait (starpu\_tag\_t id)
- int starpu tag wait array (unsigned ntags, starpu tag t \*id)
- void starpu\_tag\_restart (starpu\_tag\_t id)
- · void starpu tag remove (starpu tag t id)
- void starpu\_tag\_notify\_from\_apps (starpu\_tag\_t id)

# 27.15.1 Detailed Description

# 27.15.2 Typedef Documentation

```
27.15.2.1 starpu tag t
```

This type defines a task logical identifer. It is possible to associate a task with a unique *tag* chosen by the application, and to express dependencies between tasks by the means of those tags. To do so, fill the field starpu\_task::tag\_id with a tag number (can be arbitrary) and set the field starpu\_task::use\_tag to 1. If starpu\_tag\_declare\_deps() is called with this tag number, the task will not be started until the tasks which holds the declared dependency tags are completed.

### 27.15.3 Function Documentation

27.15.3.1 void starpu\_task\_declare\_deps\_array ( struct starpu\_task \* task, unsigned ndeps, struct starpu\_task \* task\_array[] )

Declare task dependencies between a task and an array of tasks of length ndeps. This function must be called prior to the submission of the task, but it may called after the submission or the execution of the tasks in the array, provided the tasks are still valid (i.e. they were not automatically destroyed). Calling this function on a task that was already submitted or with an entry of task\_array that is no longer a valid task results in an undefined behaviour. If ndeps is 0, no dependency is added. It is possible to call starpu\_task\_declare\_deps\_array() several times on the same task, in this case, the dependencies are added. It is possible to have redundancy in the task dependencies.

```
27.15.3.2 int starpu_task_get_task_succs ( struct starpu_task * task, unsigned ndeps, struct starpu_task * task_array[])
```

Fills task\_array with the list of tasks which are direct children of task. ndeps is the size of task\_array. This function returns the number of direct children. task\_array can be set to NULL if ndeps is 0, which allows to compute the number of children before allocating an array to store them. This function can only be called if task has not completed yet, otherwise the results are undefined. The result may also be outdated if some additional dependency has been added in the meanwhile.

```
27.15.3.3 void starpu_tag_declare_deps ( starpu_tag_t id, unsigned ndeps, ... )
```

Specify the dependencies of the task identified by tag id. The first argument specifies the tag which is configured, the second argument gives the number of tag(s) on which id depends. The following arguments are the tags which have to be terminated to unlock the task. This function must be called before the associated task is submitted to StarPU with starpu task submit().

**WARNING!** Use with caution. Because of the variable arity of starpu\_tag\_declare\_deps(), note that the last arguments must be of type starpu\_tag\_t : constant values typically need to be explicitly casted. Otherwise, due to integer sizes and argument passing on the stack, the C compiler might consider the tag  $0 \times 200000003$  instead of  $0 \times 2$  and  $0 \times 3$  when calling starpu\_tag\_declare\_deps( $0 \times 1$ , 2,  $0 \times 2$ ,  $0 \times 3$ ). Using the starpu\_tag\_declare\_deps\_array() function avoids this hazard.

27.15.3.4 void starpu\_tag\_declare\_deps\_array ( starpu\_tag\_t id, unsigned ndeps, starpu\_tag\_t \* array )

This function is similar to starpu\_tag\_declare\_deps(), except that its does not take a variable number of arguments but an array of tags of size ndeps.

```
/* Tag 0x1 depends on tags 0x32 and 0x52 */
```

```
starpu_tag_t tag_array[2] = {0x32, 0x52};
starpu_tag_declare_deps_array((starpu_tag_t
        )0x1, 2, tag_array);
```

```
27.15.3.5 int starpu_tag_wait ( starpu_tag_t id )
```

This function blocks until the task associated to tag id has been executed. This is a blocking call which must therefore not be called within tasks or callbacks, but only from the application directly. It is possible to synchronize with the same tag multiple times, as long as the <a href="starpu\_tag\_remove">starpu\_tag\_remove</a>() function is not called. Note that it is still possible to synchronize with a tag associated to a task for which the strucuture <a href="starpu\_task">starpu\_task</a> was freed (e.g. if the field <a href="starpu\_task">starpu\_task</a>::destroy was enabled).

```
27.15.3.6 int starpu_tag_wait_array ( unsigned ntags, starpu_tag_t * id )
```

This function is similar to starpu\_tag\_wait() except that it blocks until all the ntags tags contained in the array id are terminated.

```
27.15.3.7 void starpu_tag_restart ( starpu_tag_t id )
```

This function can be used to clear the *already notified* status of a tag which is not associated with a task. Before that, calling starpu\_tag\_notify\_from\_apps() again will not notify the successors. After that, the next call to starpu\_tag\_notify\_from\_apps() will notify the successors.

```
27.15.3.8 void starpu_tag_remove ( starpu_tag_t id )
```

This function releases the resources associated to tag id. It can be called once the corresponding task has been executed and when there is no other tag that depend on this tag anymore.

```
27.15.3.9 void starpu_tag_notify_from_apps ( starpu_tag_t id )
```

This function explicitly unlocks tag id. It may be useful in the case of applications which execute part of their computation outside StarPU tasks (e.g. third-party libraries). It is also provided as a convenient tool for the programmer, for instance to entirely construct the task DAG before actually giving StarPU the opportunity to execute the tasks. When called several times on the same tag, notification will be done only on first call, thus implementing "OR" dependencies, until the tag is restarted using starpu tag restart().

# 27.16 Implicit Data Dependencies

In this section, we describe how StarPU makes it possible to insert implicit task dependencies in order to enforce sequential data consistency. When this data consistency is enabled on a specific data handle, any data access will appear as sequentially consistent from the application. For instance, if the application submits two tasks that access the same piece of data in read-only mode, and then a third task that access it in write mode, dependencies will be added between the two first tasks and the third one. Implicit data dependencies are also inserted in the case of data accesses from the application.

### **Functions**

- void starpu\_data\_set\_default\_sequential\_consistency\_flag (unsigned flag)
- unsigned starpu\_data\_get\_default\_sequential\_consistency\_flag (void)
- void starpu\_data\_set\_sequential\_consistency\_flag (starpu\_data\_handle\_t handle, unsigned flag)
- unsigned starpu\_data\_get\_sequential\_consistency\_flag (starpu\_data\_handle\_t handle)

# 27.16.1 Detailed Description

In this section, we describe how StarPU makes it possible to insert implicit task dependencies in order to enforce sequential data consistency. When this data consistency is enabled on a specific data handle, any data access will appear as sequentially consistent from the application. For instance, if the application submits two tasks that access the same piece of data in read-only mode, and then a third task that access it in write mode, dependencies will be added between the two first tasks and the third one. Implicit data dependencies are also inserted in the case of data accesses from the application.

## 27.16.2 Function Documentation

27.16.2.1 starpu\_data\_set\_default\_sequential\_consistency\_flag ( unsigned flag )

Set the default sequential consistency flag. If a non-zero value is passed, a sequential data consistency will be enforced for all handles registered after this function call, otherwise it is disabled. By default, StarPU enables sequential data consistency. It is also possible to select the data consistency mode of a specific data handle with the function starpu data set sequential consistency flag().

27.16.2.2 unsigned starpu\_data\_get\_default\_sequential\_consistency\_flag ( void )

Return the default sequential consistency flag

27.16.2.3 void starpu\_data\_set\_sequential\_consistency\_flag ( starpu\_data\_handle\_t handle, unsigned flag )

Set the data consistency mode associated to a data handle. The consistency mode set using this function has the priority over the default mode which can be set with <a href="mailto:starpu\_data\_set\_default\_sequential\_consistency\_flag">starpu\_data\_set\_default\_sequential\_consistency\_flag</a>().

27.16.2.4 unsigned starpu\_data\_get\_sequential\_consistency\_flag ( starpu\_data\_handle\_t handle\_)

Get the data consistency mode associated to the data handle handle

# 27.17 Performance Model

# **Data Structures**

- · struct starpu\_perfmodel
- struct starpu\_perfmodel\_regression\_model
- · struct starpu perfmodel per arch
- struct starpu\_perfmodel\_history\_list
- struct starpu\_perfmodel\_history\_entry

# **Enumerations**

enum starpu\_perfmodel\_type {
 STARPU\_PERFMODEL\_INVALID, STARPU\_PER\_ARCH, STARPU\_COMMON, STARPU\_HISTORY\_BASED,
 STARPU\_REGRESSION\_BASED, STARPU\_NL\_REGRESSION\_BASED }

27.17 Performance Model 247

### **Functions**

- void starpu\_perfmodel\_init (struct starpu\_perfmodel \*model)
- void starpu\_perfmodel\_free\_sampling\_directories (void)
- int starpu perfmodel load file (const char \*filename, struct starpu perfmodel \*model)
- int starpu\_perfmodel\_load\_symbol (const char \*symbol, struct starpu\_perfmodel \*model)
- int starpu\_perfmodel\_unload\_model (struct starpu\_perfmodel \*model)
- void starpu\_perfmodel\_debugfilepath (struct starpu\_perfmodel \*model, struct starpu\_perfmodel\_arch \*arch, char \*path, size t maxlen, unsigned nimpl)
- char \* starpu perfmodel get archtype name (enum starpu worker archtype archtype)
- void starpu\_perfmodel\_get\_arch\_name (struct starpu\_perfmodel\_arch \*arch, char \*archname, size\_t maxlen, unsigned nimpl)
- struct starpu\_perfmodel\_arch \* starpu\_worker\_get\_perf\_archtype (int workerid, unsigned sched ctx id)
- int starpu\_perfmodel\_list (FILE \*output)
- void starpu\_perfmodel\_directory (FILE \*output)
- void starpu\_perfmodel\_print (struct starpu\_perfmodel \*model, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl, char \*parameter, uint32 t \*footprint, FILE \*output)
- int starpu\_perfmodel\_print\_all (struct starpu\_perfmodel \*model, char \*arch, char \*parameter, uint32\_t \*footprint, FILE \*output)
- void starpu\_bus\_print\_bandwidth (FILE \*f)
- void starpu bus print affinity (FILE \*f)
- void starpu\_perfmodel\_update\_history (struct starpu\_perfmodel \*model, struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned cpuid, unsigned nimpl, double measured)
- double starpu\_transfer\_bandwidth (unsigned src\_node, unsigned dst\_node)
- double starpu\_transfer\_latency (unsigned src\_node, unsigned dst\_node)
- double starpu\_transfer\_predict (unsigned src\_node, unsigned dst\_node, size\_t size)
- double starpu\_perfmodel\_history\_based\_expected\_perf (struct starpu\_perfmodel \*model, struct starpu\_perfmodel\_arch \*arch, uint32\_t footprint)

# 27.17.1 Detailed Description

# 27.17.2 Data Structure Documentation

# 27.17.2.1 struct starpu\_perfmodel

Contains all information about a performance model. At least the type and symbol fields have to be filled when defining a performance model for a codelet. For compatibility, make sure to initialize the whole structure to zero, either by using explicit memset, or by letting the compiler implicitly do it in e.g. static storage case. If not provided, other fields have to be zero.

## **Data Fields**

- enum starpu\_perfmodel\_type type
- double(\* cost\_function )(struct starpu\_task \*, unsigned nimpl)
- size\_t(\* size\_base )(struct starpu\_task \*, unsigned nimpl)
- uint32 t(\* footprint )(struct starpu task \*)
- const char \* symbol
- · unsigned is loaded
- unsigned benchmarking
- unsigned is\_init
- · starpu\_perfmodel\_state\_t state

### 27.17.2.1.1 Field Documentation

27.17.2.1.1.1 enum starpu\_perfmodel\_type starpu\_perfmodel::type

is the type of performance model

- STARPU\_HISTORY\_BASED, STARPU\_REGRESSION\_BASED, STARPU\_NL\_REGRESSION\_BASED: No other fields needs to be provided, this is purely history-based.
- STARPU\_PER\_ARCH: field starpu\_perfmodel::per\_arch has to be filled with functions which return the cost in micro-seconds.
- STARPU\_COMMON: field starpu\_perfmodel::cost\_function has to be filled with a function that returns the cost in micro-seconds on a CPU, timing on other archs will be determined by multiplying by an arch-specific factor

27.17.2.1.1.2 double(\* starpu\_perfmodel::cost\_function)(struct starpu\_task \*, unsigned nimpl)

Used by STARPU\_COMMON: takes a task and implementation number, and must return a task duration estimation in micro-seconds.

27.17.2.1.1.3 size\_t(\* starpu\_perfmodel::size\_base)(struct starpu\_task \*, unsigned nimpl)

Used by STARPU\_HISTORY\_BASED, STARPU\_REGRESSION\_BASED and STARPU\_NL\_REGRESSION\_BASED. If not NULL, takes a task and implementation number, and returns the size to be used as index to distinguish histories and as a base for regressions.

27.17.2.1.1.4 uint32\_t(\* starpu\_perfmodel::footprint)(struct starpu\_task \*)

Used by STARPU\_HISTORY\_BASED. If not NULL, takes a task and returns the footprint to be used as index to distinguish histories. The default is to use the starpu\_task\_data\_footprint function.

27.17.2.1.1.5 const char \* starpu\_perfmodel::symbol

is the symbol name for the performance model, which will be used as file name to store the model. It must be set otherwise the model will be ignored.

27.17.2.1.1.6 unsigned starpu\_perfmodel::is\_loaded

Whether the performance model is already loaded from the disk.

27.17.2.1.1.7 unsigned starpu\_perfmodel::is\_init

todo

27.17.2.2 struct starpu\_perfmodel\_regression\_model

...

### **Data Fields**

double	sumlny	sum of In(measured)
double	sumlnx	sum of In(size)
double	sumlnx2	sum of ln(size) <sup>^</sup> 2
unsigned long	minx	minimum size
unsigned long	maxx	maximum size
double	sumlnxlny	sum of In(size)*In(measured)
double	alpha	estimated = alpha $*$ size $^{\wedge}$ beta
double	beta	estimated = alpha $*$ size $^{\wedge}$ beta
unsigned	valid	whether the linear regression model is valid (i.e. enough measures)

27.17 Performance Model 249

al a cola lia	_	
double	a	estimated = a size ^b + c
double	b	estimated = a size ^b + c
double	С	estimated = a size ^b + c
unsigned	nl_valid	whether the non-linear regression model is valid (i.e. enough measures)
unsigned	nsample	number of sample values for non-linear regression

# 27.17.2.3 struct starpu\_perfmodel\_per\_arch

contains information about the performance model of a given arch.

# **Data Fields**

starpu	cost_function	Used by STARPU_PER_ARCH, must point to functions which take a task,
perfmodel_per		the target arch and implementation number (as mere conveniency, since
arch_cost		the array is already indexed by these), and must return a task duration
function		estimation in micro-seconds.
starpu	size_base	Same as in structure starpu_perfmodel, but per-arch, in case it depends
perfmodel_per		on the architecture-specific implementation.
arch_size_base		
struct	history	The history of performance measurements.
starpu		
perfmodel		
history_table		
*		
struct	list	Used by STARPU_HISTORY_BASED and STARPU_NL_REGRESSIO-
starpu		N_BASED, records all execution history measures.
perfmodel		
history_list		
*		
struct	regression	Used by STARPU_REGRESSION_BASED and STARPU_NL_REGRE-
starpu		SSION_BASED, contains the estimated factors of the regression.
perfmodel		
regression		
model		
char	debug_path	

# 27.17.2.4 struct starpu\_perfmodel\_history\_list

todo

# **Data Fields**

struct	next	todo
starpu		
perfmodel		
history_list		
*		
struct	entry	todo
starpu		
perfmodel		
history_entry		
*		

### 27.17.2.5 struct starpu\_perfmodel\_history\_entry

todo

#### **Data Fields**

double	mean	mean_n = 1/n sum
double	deviation	$n \text{ dev}_n = \text{sum} 2 - 1/n (\text{sum})^2$
double	sum	sum of samples (in μs)
double	sum2	sum of samples <sup>^</sup> 2
unsigned	nsample	number of samples
unsigned	nerror	
uint32_t	footprint	data footprint
size_t	size	in bytes
double	flops	Provided by the application

# 27.17.3 Enumeration Type Documentation

### 27.17.3.1 enum starpu\_perfmodel\_type

**TODO** 

#### **Enumerator:**

**STARPU\_PER\_ARCH** Application-provided per-arch cost model function

STARPU\_COMMON Application-provided common cost model function, with per-arch factor

STARPU\_HISTORY\_BASED Automatic history-based cost model

STARPU\_REGRESSION\_BASED Automatic linear regression-based cost model (alpha \* size ^ beta)

STARPU\_NL\_REGRESSION\_BASED Automatic non-linear regression-based cost model (a \* size ^ b + c)

### 27.17.4 Function Documentation

27.17.4.1 void starpu\_perfmodel\_init ( struct starpu\_perfmodel \* model )

todo

27.17.4.2 void starpu\_perfmodel\_free\_sampling\_directories (void)

this function frees internal memory used for sampling directory management. It should only be called by an application which is not calling starpu\_shutdown as this function already calls it. See for example tools/starpu\_perfmodel\_display.c.

27.17.4.3 int starpu\_perfmodel\_load\_file ( const char \* filename, struct starpu\_perfmodel \* model )

loads the performance model found in the given file. The model structure has to be completely zero, and will be filled with the information stored in the given file.

 $27.17.4.4 \quad int\ starpu\_perfmodel\_load\_symbol\ (\ const\ char* \textit{symbol},\ struct\ starpu\_perfmodel* \textit{model}\ )$ 

loads a given performance model. The model structure has to be completely zero, and will be filled with the information saved in  $STARPU\_HOME/.starpu$ . The function is intended to be used by external tools that should read the performance model files.

27.17 Performance Model 251

```
27.17.4.5 int starpu_perfmodel_unload_model ( struct starpu_perfmodel * model )
unloads the given model which has been previously loaded through the function starpu_perfmodel_load_symbol()
27.17.4.6 void starpu_perfmodel_debugfilepath ( struct starpu_perfmodel * model, struct starpu_perfmodel_arch *
          arch, char * path, size_t maxlen, unsigned nimpl )
returns the path to the debugging information for the performance model.
27.17.4.7 char * starpu_perfmodel_get_archtype_name ( enum starpu_worker_archtype archtype )
todo
27.17.4.8 void starpu_perfmodel_get_arch_name ( struct starpu_perfmodel_arch * arch, char * archname, size_t maxlen,
          unsigned nimpl)
returns the architecture name for arch
27.17.4.9 struct starpu_perfmodel_arch * starpu_worker_get_perf_archtype ( int workerid, unsigned sched_ctx_id )
          [read]
returns the architecture type of a given worker.
27.17.4.10 int starpu_perfmodel_list ( FILE * output )
prints a list of all performance models on {\tt output}
27.17.4.11 void starpu_perfmodel_directory ( FILE * output )
prints the directory name storing performance models on output
27.17.4.12 void starpu_perfmodel_print ( struct starpu_perfmodel * model, struct starpu_perfmodel_arch * arch,
           unsigned nimpl, char * parameter, uint32_t * footprint, FILE * output )
todo
27.17.4.13 int starpu_perfmodel_print_all ( struct starpu_perfmodel * model, char * arch, char * parameter, uint32_t *
           footprint, FILE * output )
todo
27.17.4.14 void starpu_bus_print_bandwidth ( FILE * f )
prints a matrix of bus bandwidths on f.
27.17.4.15 void starpu_bus_print_affinity ( FILE * f )
prints the affinity devices on f.
```

27.17.4.16 void starpu\_perfmodel\_update\_history ( struct starpu\_perfmodel \* model, struct starpu\_task \* task, struct starpu\_perfmodel arch \* arch, unsigned cpuid, unsigned nimpl, double measured )

This feeds the performance model model with an explicit measurement measured (in  $\mu$ s), in addition to measurements done by StarPU itself. This can be useful when the application already has an existing set of measurements done in good conditions, that StarPU could benefit from instead of doing on-line measurements. And example of use can be seen in Performance Model Example.

27.17.4.17 double starpu\_transfer\_bandwidth ( unsigned src\_node, unsigned dst\_node )

Return the bandwidth of data transfer between two memory nodes

27.17.4.18 double starpu\_transfer\_latency ( unsigned src\_node, unsigned dst\_node )

Return the latency of data transfer between two memory nodes

27.17.4.19 double starpu\_transfer\_predict ( unsigned src\_node, unsigned dst\_node, size\_t size )

Return the estimated time to transfer a given size between two memory nodes.

27.17.4.20 double starpu\_perfmodel\_history\_based\_expected\_perf ( struct starpu\_perfmodel \* model, struct starpu perfmodel arch \* arch, uint32\_t footprint )

Return the estimated time of a task whose model is named and whose footprint is footprint

# 27.18 Profiling

### **Data Structures**

- · struct starpu profiling task info
- · struct starpu profiling worker info
- · struct starpu profiling bus info

### Macros

- #define STARPU\_PROFILING\_DISABLE
- #define STARPU\_PROFILING\_ENABLE

### **Functions**

- int starpu\_profiling\_status\_set (int status)
- int starpu\_profiling\_status\_get (void)
- void starpu profiling init (void)
- void starpu\_profiling\_set\_id (int new\_id)
- int starpu profiling worker get info (int workerid, struct starpu profiling worker info) \*worker info)
- int starpu\_bus\_get\_profiling\_info (int busid, struct starpu\_profiling\_bus\_info \*bus\_info)
- int starpu\_bus\_get\_count (void)
- int starpu\_bus\_get\_id (int src, int dst)
- int starpu\_bus\_get\_src (int busid)
- int starpu bus get dst (int busid)
- double starpu\_timing\_timespec\_delay\_us (struct timespec \*start, struct timespec \*end)

27.18 Profiling 253

- double starpu\_timing\_timespec\_to\_us (struct timespec \*ts)
- void starpu\_profiling\_bus\_helper\_display\_summary (void)
- void starpu\_profiling\_worker\_helper\_display\_summary (void)
- void starpu\_data\_display\_memory\_stats ()

# 27.18.1 Detailed Description

### 27.18.2 Data Structure Documentation

# 27.18.2.1 struct starpu\_profiling\_task\_info

This structure contains information about the execution of a task. It is accessible from the field <a href="mailto:starpu\_task::profiling-info">starpu\_task::profiling-info</a> if profiling was enabled.

### **Data Fields**

struct timespec	submit_time	Date of task submission (relative to the initialization of StarPU).
struct timespec	push_start_time	Time when the task was submitted to the scheduler.
struct timespec	push_end_time	Time when the scheduler finished with the task submission.
struct timespec	pop_start_time	Time when the scheduler started to be requested for a task, and eventu-
		ally gave that task.
struct timespec	pop_end_time	Time when the scheduler finished providing the task for execution.
struct timespec	acquire_data	Time when the worker started fetching input data.
	start_time	
struct timespec	acquire_data	Time when the worker finished fetching input data.
	end_time	
struct timespec	start_time	Date of task execution beginning (relative to the initialization of StarPU).
struct timespec	end_time	Date of task execution termination (relative to the initialization of StarPU).
struct timespec	release_data	Time when the worker started releasing data.
	start_time	
struct timespec	release_data	Time when the worker finished releasing data.
	end_time	
struct timespec	callback_start	Time when the worker started the application callback for the task.
	time	
struct timespec	callback_end	Time when the worker finished the application callback for the task.
	time	
int	workerid	Identifier of the worker which has executed the task.
uint64_t	used_cycles	Number of cycles used by the task, only available in the MoviSim
uint64_t	stall_cycles	Number of cycles stalled within the task, only available in the MoviSim
double	power	Power consumed by the task, only available in the MoviSim
	consumed	

## 27.18.2.2 struct starpu\_profiling\_worker\_info

This structure contains the profiling information associated to a worker. The timing is provided since the previous call to starpu\_profiling\_worker\_get\_info()

# Data Fields

struct timespec	start_time	Starting date for the reported profiling measurements.
struct timespec	total_time	Duration of the profiling measurement interval.
struct timespec	executing_time	Time spent by the worker to execute tasks during the profiling measure-
		ment interval.
struct timespec	sleeping_time	Time spent idling by the worker during the profiling measurement interval.
int	executed_tasks	Number of tasks executed by the worker during the profiling measurement
		interval.

uint64_t	used_cycles	Number of cycles used by the worker, only available in the MoviSim
uint64_t	stall_cycles	Number of cycles stalled within the worker, only available in the MoviSim
double	power	Power consumed by the worker, only available in the MoviSim
	consumed	

## 27.18.2.3 struct starpu\_profiling\_bus\_info

todo

#### **Data Fields**

struct timespec	start_time	Time of bus profiling startup.
struct timespec	total_time	Total time of bus profiling.
int long long	transferred	Number of bytes transferred during profiling.
	bytes	
int	transfer_count	Number of transfers during profiling.

## 27.18.3 Macro Definition Documentation

### 27.18.3.1 STARPU\_PROFILING\_DISABLE

This value is used when calling the function starpu\_profiling\_status\_set() to disable profiling.

### 27.18.3.2 STARPU\_PROFILING\_ENABLE

This value is used when calling the function starpu\_profiling\_status\_set() to enable profiling.

### 27.18.4 Function Documentation

### 27.18.4.1 int starpu\_profiling\_status\_set ( int status )

This function sets the profiling status. Profiling is activated by passing STARPU\_PROFILING\_ENABLE in status. Passing STARPU\_PROFILING\_DISABLE disables profiling. Calling this function resets all profiling measurements. When profiling is enabled, the field starpu\_task::profiling\_info points to a valid structure starpu\_profiling\_task\_info containing information about the execution of the task. Negative return values indicate an error, otherwise the previous status is returned.

# 27.18.4.2 int starpu\_profiling\_status\_get ( void )

Return the current profiling status or a negative value in case there was an error.

# 27.18.4.3 void starpu\_profiling\_init ( void )

This function resets performance counters and enable profiling if the environment variable STARPU\_PROFILING is set to a positive value.

# 27.18.4.4 void starpu\_profiling\_set\_id ( int new\_id )

This function sets the ID used for profiling trace filename. It needs to be called before <a href="mailto:starpu\_init()">starpu\_init()</a>.

27.18 Profiling 255

27.18.4.5 int starpu\_profiling\_worker\_info ( int workerid, struct starpu\_profiling\_worker\_info \* worker\_info )

Get the profiling info associated to the worker identified by workerid, and reset the profiling measurements. If the argument worker\_info is NULL, only reset the counters associated to worker workerid. Upon successful completion, this function returns 0. Otherwise, a negative value is returned.

27.18.4.6 int starpu\_bus\_get\_profiling\_info ( int busid, struct starpu\_profiling\_bus\_info \* bus\_info )

todo

27.18.4.7 int starpu\_bus\_get\_count ( void )

Return the number of buses in the machine

27.18.4.8 int starpu\_bus\_get\_id ( int src, int dst )

Return the identifier of the bus between src and dst

27.18.4.9 int starpu\_bus\_get\_src ( int busid )

Return the source point of bus busid

27.18.4.10 int starpu\_bus\_get\_dst ( int busid )

Return the destination point of bus busid

27.18.4.11 double starpu\_timing\_timespec\_delay\_us ( struct timespec \* start, struct timespec \* end )

Returns the time elapsed between start and end in microseconds.

27.18.4.12 double starpu\_timing\_timespec\_to\_us ( struct timespec \* ts )

Converts the given timespec ts into microseconds

27.18.4.13 void starpu\_profiling\_bus\_helper\_display\_summary (void)

Displays statistics about the bus on stderr. if the environment variable STARPU\_BUS\_STATS is defined. The function is called automatically by starpu\_shutdown().

27.18.4.14 void starpu\_profiling\_worker\_helper\_display\_summary (void )

Displays statistics about the workers on stderr if the environment variable STARPU\_WORKER\_STATS is defined. The function is called automatically by starpu\_shutdown().

27.18.4.15 void starpu\_data\_display\_memory\_stats ( )

Display statistics about the current data handles registered within StarPU. StarPU must have been configured with the configure option --enable-memory-stats (see Memory Feedback).

### 27.19 Theoretical Lower Bound on Execution Time

Compute theoretical upper computation efficiency bound corresponding to some actual execution.

#### **Functions**

- void starpu\_bound\_start (int deps, int prio)
- void starpu\_bound\_stop (void)
- void starpu\_bound\_print\_dot (FILE \*output)
- void starpu\_bound\_compute (double \*res, double \*integer\_res, int integer)
- void starpu bound print lp (FILE \*output)
- void starpu\_bound\_print\_mps (FILE \*output)
- void starpu\_bound\_print (FILE \*output, int integer)

# 27.19.1 Detailed Description

Compute theoretical upper computation efficiency bound corresponding to some actual execution.

#### 27.19.2 Function Documentation

```
27.19.2.1 void starpu_bound_start ( int deps, int prio )
```

Start recording tasks (resets stats). deps tells whether dependencies should be recorded too (this is quite expensive)

```
27.19.2.2 void starpu_bound_stop (void)
```

Stop recording tasks

```
27.19.2.3 void starpu_bound_print_dot ( FILE * output )
```

Print the DAG that was recorded

```
27.19.2.4 void starpu_bound_compute ( double * res, double * integer_res, int integer )
```

Get theoretical upper bound (in ms) (needs glpk support detected by configure script). It returns 0 if some performance models are not calibrated.

```
27.19.2.5 void starpu_bound_print_lp ( FILE * output )
```

Emit the Linear Programming system on output for the recorded tasks, in the lp format

```
27.19.2.6 void starpu_bound_print_mps ( FILE * output )
```

Emit the Linear Programming system on output for the recorded tasks, in the mps format

```
27.19.2.7 void starpu_bound_print ( FILE * output, int integer )
```

Emit statistics of actual execution vs theoretical upper bound. integer permits to choose between integer solving (which takes a long time but is correct), and relaxed solving (which provides an approximate solution).

27.20 CUDA Extensions 257

### 27.20 CUDA Extensions

#### Macros

- #define STARPU USE CUDA
- #define STARPU MAXCUDADEVS
- #define STARPU\_CUDA\_REPORT\_ERROR(status)
- #define STARPU\_CUBLAS\_REPORT\_ERROR(status)

### **Functions**

- cudaStream\_t starpu\_cuda\_get\_local\_stream (void)
- struct cudaDeviceProp \* starpu\_cuda\_get\_device\_properties (unsigned workerid)
- void starpu\_cuda\_report\_error (const char \*func, const char \*file, int line, cudaError\_t status)
- int starpu\_cuda\_copy\_async\_sync (void \*src\_ptr, unsigned src\_node, void \*dst\_ptr, unsigned dst\_node, size\_t ssize, cudaStream\_t stream, enum cudaMemcpyKind kind)
- void starpu\_cuda\_set\_device (unsigned devid)
- void starpu\_cublas\_init (void)
- void starpu\_cublas\_shutdown (void)
- void starpu cublas report error (const char \*func, const char \*file, int line, int status)

### 27.20.1 Detailed Description

#### 27.20.2 Macro Definition Documentation

### 27.20.2.1 #define STARPU\_USE\_CUDA

This macro is defined when StarPU has been installed with CUDA support. It should be used in your code to detect the availability of CUDA as shown in Full source code for the 'Scaling a Vector' example.

### 27.20.2.2 #define STARPU\_MAXCUDADEVS

This macro defines the maximum number of CUDA devices that are supported by StarPU.

```
27.20.2.3 #define STARPU_CUDA_REPORT_ERROR( status )
```

Calls starpu\_cuda\_report\_error(), passing the current function, file and line position.

27.20.2.4 #define STARPU\_CUBLAS\_REPORT\_ERROR( status )

Calls starpu\_cublas\_report\_error(), passing the current function, file and line position.

# 27.20.3 Function Documentation

27.20.3.1 cudaStream\_t starpu\_cuda\_get\_local\_stream ( void )

This function gets the current worker's CUDA stream. StarPU provides a stream for every CUDA device controlled by StarPU. This function is only provided for convenience so that programmers can easily use asynchronous operations within codelets without having to create a stream by hand. Note that the application is not forced to use the stream provided by <a href="mailto:starpu\_cuda\_get\_local\_stream">stream</a>() and may also create its own streams. Synchronizing with cudaThread-Synchronize() is allowed, but will reduce the likelihood of having all transfers overlapped.

27.20.3.2 const struct cudaDeviceProp \* starpu\_cuda\_get\_device\_properties ( unsigned workerid ) [read]

This function returns a pointer to device properties for worker workerid (assumed to be a CUDA worker).

27.20.3.3 void starpu\_cuda\_report\_error ( const char \* func, const char \* file, int line, cudaError\_t status )

Report a CUDA error.

27.20.3.4 int starpu\_cuda\_copy\_async\_sync ( void \* src\_ptr, unsigned src\_node, void \* dst\_ptr, unsigned dst\_node, size\_t ssize, cudaStream\_t stream, enum cudaMemcpyKind kind )

Copy ssize bytes from the pointer src\_ptr on src\_node to the pointer dst\_ptr on dst\_node. The function first tries to copy the data asynchronous (unless stream is NULL). If the asynchronous copy fails or if stream is NULL, it copies the data synchronously. The function returns -EAGAIN if the asynchronous launch was successfull. It returns 0 if the synchronous copy was successful, or fails otherwise.

27.20.3.5 void starpu\_cuda\_set\_device ( unsigned devid )

Calls cudaSetDevice(devid) or cudaGLSetGLDevice(devid), according to whether devid is among the field starpuconf::cuda\_opengl\_interoperability.

27.20.3.6 void starpu\_cublas\_init ( void )

This function initializes CUBLAS on every CUDA device. The CUBLAS library must be initialized prior to any CUBLAS call. Calling <a href="mailto:starpu\_cublas\_init">starpu\_cublas\_init()</a> will initialize CUBLAS on every CUDA device controlled by StarPU. This call blocks until CUBLAS has been properly initialized on every device.

27.20.3.7 void starpu\_cublas\_shutdown ( void )

This function synchronously deinitializes the CUBLAS library on every CUDA device.

27.20.3.8 void starpu\_cublas\_report\_error ( const char \* func, const char \* file, int line, int status )

Report a cublas error.

# 27.21 OpenCL Extensions

### **Data Structures**

struct starpu\_opencl\_program

### **Macros**

- #define STARPU\_USE\_OPENCL
- #define STARPU MAXOPENCLDEVS
- #define STARPU OPENCL DATADIR

# Writing OpenCL kernels

- void starpu\_opencl\_get\_context (int devid, cl\_context \*context)
- void starpu\_opencl\_get\_device (int devid, cl\_device\_id \*device)
- void starpu\_opencl\_get\_queue (int devid, cl\_command\_queue \*queue)
- void starpu opencl get current context (cl context \*context)
- void starpu opencl get current queue (cl command queue \*queue)
- int starpu\_opencl\_set\_kernel\_args (cl\_int \*err, cl\_kernel \*kernel,...)

### Compiling OpenCL kernels

Source codes for OpenCL kernels can be stored in a file or in a string. StarPU provides functions to build the program executable for each available OpenCL device as a cl\_program object. This program executable can then be loaded within a specific queue as explained in the next section. These are only helpers, Applications can also fill a starpu\_opencl\_program array by hand for more advanced use (e.g. different programs on the different OpenCL devices, for relocation purpose for instance).

- int starpu\_opencl\_load\_opencl\_from\_file (const char \*source\_file\_name, struct starpu\_opencl\_program \*opencl programs, const char \*build options)
- int starpu\_opencl\_load\_opencl\_from\_string (const char \*opencl\_program\_source, struct starpu\_opencl\_program \*opencl\_programs, const char \*build\_options)
- int starpu opencl unload opencl (struct starpu opencl program \*opencl programs)
- void starpu\_opencl\_load\_program\_source (const char \*source\_file\_name, char \*located\_file\_name, char \*located\_file\_name,
- int starpu opencl compile opencl from file (const char \*source file name, const char \*build options)
- int starpu\_opencl\_compile\_opencl\_from\_string (const char \*opencl\_program\_source, const char \*file\_name, const char \*build\_options)
- int starpu\_opencl\_load\_binary\_opencl (const char \*kernel\_id, struct starpu\_opencl\_program \*opencl\_programs)

## **Loading OpenCL kernels**

- int starpu\_opencl\_load\_kernel (cl\_kernel \*kernel, cl\_command\_queue \*queue, struct starpu\_opencl\_program \*opencl\_programs, const char \*kernel\_name, int devid)
- int starpu\_opencl\_release\_kernel (cl\_kernel kernel)

### OpenCL statistics

int starpu opencl collect stats (cl event event)

# **OpenCL utilities**

- #define STARPU\_OPENCL\_DISPLAY\_ERROR(status)
- #define STARPU OPENCL REPORT ERROR(status)
- #define STARPU OPENCL REPORT ERROR WITH MSG(msg, status)
- const char \* starpu opencl error string (cl int status)
- void starpu\_opencl\_display\_error (const char \*func, const char \*file, int line, const char \*msg, cl\_int status)
- static \_\_starpu\_inline void starpu\_opencl\_report\_error (const char \*func, const char \*file, int line, const char \*msg, cl int status)
- cl int starpu opencl allocate memory (int devid, cl mem \*addr, size t size, cl mem flags flags)
- cl\_int starpu\_opencl\_copy\_ram\_to\_opencl (void \*ptr, unsigned src\_node, cl\_mem buffer, unsigned dst\_node, size t size, size t offset, cl event \*event, int \*ret)
- cl\_int starpu\_opencl\_copy\_opencl\_to\_ram (cl\_mem buffer, unsigned src\_node, void \*ptr, unsigned dst\_node, size\_t size, size\_t offset, cl\_event \*event, int \*ret)

- cl\_int starpu\_opencl\_copy\_opencl\_to\_opencl (cl\_mem src, unsigned src\_node, size\_t src\_offset, cl\_mem dst, unsigned dst\_node, size\_t dst\_offset, size\_t size, cl\_event \*event, int \*ret)
- cl\_int starpu\_opencl\_copy\_async\_sync (uintptr\_t src, size\_t src\_offset, unsigned src\_node, uintptr\_t dst, size\_t dst\_offset, unsigned dst\_node, size\_t size, cl\_event \*event)

### 27.21.1 Detailed Description

#### 27.21.2 Data Structure Documentation

### 27.21.2.1 struct starpu\_opencl\_program

Stores the OpenCL programs as compiled for the different OpenCL devices.

#### **Data Fields**

cl_program	programs	Stores each program for each OpenCL device.

### 27.21.3 Macro Definition Documentation

#### 27.21.3.1 #define STARPU\_USE\_OPENCL

This macro is defined when StarPU has been installed with OpenCL support. It should be used in your code to detect the availability of OpenCL as shown in Full source code for the 'Scaling a Vector' example.

#### 27.21.3.2 #define STARPU\_MAXOPENCLDEVS

This macro defines the maximum number of OpenCL devices that are supported by StarPU.

# 27.21.3.3 #define STARPU\_OPENCL\_DATADIR

This macro defines the directory in which the OpenCL codelets of the applications provided with StarPU have been installed.

### 27.21.3.4 #define STARPU\_OPENCL\_DISPLAY\_ERROR( status )

Call the function starpu\_opencl\_display\_error() with the given error status, the current function name, current file and line number, and a empty message.

#### 27.21.3.5 #define STARPU\_OPENCL\_REPORT\_ERROR( status )

Call the function starpu\_opencl\_report\_error() with the given error status, with the current function name, current file and line number, and a empty message.

### 27.21.3.6 #define STARPU\_OPENCL\_REPORT\_ERROR\_WITH\_MSG( msg, status )

Call the function  $starpu\_opencl\_report\_error()$  with the given msg and the given error status, with the current function name, current file and line number.

# 27.21.4 Function Documentation

```
27.21.4.1 void starpu_opencl_get_context ( int devid, cl_context * context )
```

Places the OpenCL context of the device designated by devid into context.

```
27.21.4.2 void starpu_opencl_get_device ( int devid, cl_device_id * device )
```

Places the cl device id corresponding to devid in device.

```
27.21.4.3 void starpu_opencl_get_queue ( int devid, cl_command_queue * queue )
```

Places the command queue of the device designated by devid into queue.

```
27.21.4.4 void starpu_opencl_get_current_context ( cl_context * context )
```

Return the context of the current worker.

```
27.21.4.5 void starpu_opencl_get_current_queue ( cl_command_queue * queue )
```

Return the computation kernel command queue of the current worker.

```
27.21.4.6 int starpu_opencl_set_kernel_args ( cl_int * err, cl_kernel * kernel, ... )
```

Sets the arguments of a given kernel. The list of arguments must be given as (size\_t size\_of\_the\_argument, cl\_mem \* pointer\_to\_the\_argument). The last argument must be 0. Returns the number of arguments that were successfully set. In case of failure, returns the id of the argument that could not be set and err is set to the error returned by OpenCL. Otherwise, returns the number of arguments that were set.

Here an example:

27.21.4.7 int starpu\_opencl\_load\_opencl\_from\_file ( const char \* source\_file\_name, struct starpu\_opencl\_program \* opencl\_programs, const char \* build\_options )

This function compiles an OpenCL source code stored in a file.

```
27.21.4.8 int starpu_opencl_load_opencl_from_string ( const char * opencl_program_source, struct starpu_opencl_program * opencl_programs, const char * build_options )
```

This function compiles an OpenCL source code stored in a string.

27.21.4.9 int starpu\_opencl\_unload\_opencl ( struct starpu\_opencl\_program \* opencl\_programs )

This function unloads an OpenCL compiled code.

27.21.4.10 void starpu\_opencl\_load\_program\_source ( const char \* source\_file\_name, char \* located\_file\_name, char \* located\_dir\_name, char \* opencl\_program\_source )

Store the contents of the file <code>source\_file\_name</code> in the buffer <code>opencl\_program\_source</code>. The file <code>source\_file\_name</code> can be located in the current directory, or in the directory specified by the environment variable <code>STARPU\_OPENCL\_PROGRAM\_DIR</code>, or in the directory <code>share/starpu/opencl</code> of the installation directory of <code>StarPU</code>, or in the source directory of <code>StarPU</code>. When the file is found, <code>located\_file\_name</code> is the full name of the file as it has been located on the <code>system</code>, <code>located\_dir\_name</code> the directory where it has been located. Otherwise, they are both set to the empty string.

27.21.4.11 int starpu\_opencl\_compile\_opencl\_from\_file ( const char \* source\_file\_name, const char \* build\_options )

Compile the OpenCL kernel stored in the file <code>source\_file\_name</code> with the given options <code>build\_options</code> and stores the result in the directory <code>\$STARPU\_HOME/.starpu/opencl</code> with the same filename as <code>source\_file\_name</code>. The compilation is done for every OpenCL device, and the filename is suffixed with the vendor id and the device id of the OpenCL device.

27.21.4.12 int starpu\_opencl\_compile\_opencl\_from\_string ( const char \* opencl\_program\_source, const char \* file\_name, const char \* build\_options )

Compile the OpenCL kernel in the string <code>opencl\_program\_source</code> with the given options <code>build\_options</code> and stores the result in the directory <code>\$STARPU\_HOME/.starpu/opencl</code> with the filename <code>file\_name</code>. The compilation is done for every <code>OpenCL</code> device, and the filename is suffixed with the vendor id and the device id of the <code>OpenCL</code> device.

27.21.4.13 int starpu\_opencl\_load\_binary\_opencl ( const char \* kernel\_id, struct starpu\_opencl\_program \* opencl\_programs )

Compile the binary OpenCL kernel identified with kernel\_id. For every OpenCL device, the binary OpenCL kernel will be loaded from the file \$STARPU\_HOME/.starpu/opencl/<kernel\_id>.<device\_type>.vendor id <vendor id> device id <device id>.

27.21.4.14 int starpu\_opencl\_load\_kernel ( cl\_kernel \* kernel, cl\_command\_queue \* queue, struct starpu\_opencl\_program \* opencl\_programs, const char \* kernel\_name, int devid )

Create a kernel kernel for device devid, on its computation command queue returned in queue, using program opencl\_programs and name kernel\_name.

27.21.4.15 int starpu\_opencl\_release\_kernel ( cl\_kernel kernel )

Release the given kernel, to be called after kernel execution.

27.21.4.16 int starpu\_opencl\_collect\_stats ( cl\_event event )

This function allows to collect statistics on a kernel execution. After termination of the kernels, the OpenCL codelet should call this function to pass it the even returned by clEnqueueNDRangeKernel, to let StarPU collect statistics about the kernel execution (used cycles, consumed power).

27.21.4.17 const char \* starpu\_opencl\_error\_string ( cl\_int status )

Return the error message in English corresponding to status, an OpenCL error code.

27.21.4.18 void starpu\_opencl\_display\_error ( const char \* func, const char \* file, int line, const char \* msg, cl\_int status )

Given a valid error status, prints the corresponding error message on stdout, along with the given function name func, the given filename file, the given line number line and the given message msq.

27.21.4.19 void starpu\_opencl\_report\_error ( const char \* func, const char \* file, int line, const char \* msg, cl\_int status ) [static]

Call the function starpu\_opencl\_display\_error() and abort.

27.21.4.20 cl\_int starpu\_opencl\_allocate\_memory ( int devid, cl\_mem \* addr, size\_t size, cl\_mem\_flags flags )

Allocate size bytes of memory, stored in addr. flags must be a valid combination of cl\_mem\_flags values.

27.21.4.21 cl\_int starpu\_opencl\_copy\_ram\_to\_opencl ( void \* ptr, unsigned src\_node, cl\_mem buffer, unsigned dst\_node, size\_t size, size\_t offset, cl\_event \* event, int \* ret )

Copy size bytes from the given ptr on RAM src\_node to the given buffer on OpenCL dst\_node. offset is the offset, in bytes, in buffer. if event is NULL, the copy is synchronous, i.e the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. This function returns CL\_SUCCESS if the copy was successful, or a valid OpenCL error code otherwise. The integer pointed to by ret is set to -EAGAIN if the asynchronous launch was successful, or to 0 if event was NULL.

27.21.4.22 cl\_int starpu\_opencl\_copy\_opencl\_to\_ram ( cl\_mem buffer, unsigned src\_node, void \* ptr, unsigned dst\_node, size\_t size, size\_t offset, cl\_event \* event, int \* ret )

Copy size bytes asynchronously from the given <code>buffer</code> on <code>OpenCL src\_node</code> to the given <code>ptr</code> on <code>RAM dst\_node</code>. offset is the offset, in bytes, in <code>buffer</code>. if <code>event</code> is <code>NULL</code>, the copy is synchronous, i.e the queue is synchronised before returning. If not <code>NULL</code>, <code>event</code> can be used after the call to wait for this particular copy to complete. This function returns <code>CL\_SUCCESS</code> if the copy was successful, or a valid <code>OpenCL</code> error code otherwise. The integer pointed to by <code>ret</code> is set to <code>-EAGAIN</code> if the asynchronous launch was successful, or to 0 if <code>event was NULL</code>.

27.21.4.23 cl\_int starpu\_opencl\_copy\_opencl\_to\_opencl ( cl\_mem *src*, unsigned *src\_node*, size\_t *src\_offset*, cl\_mem *dst*, unsigned *dst\_node*, size\_t *dst\_offset*, size\_t *size*, cl\_event \* *event*, int \* *ret* )

Copy size bytes asynchronously from byte offset src\_offset of src on OpenCL src\_node to byte offset dst\_offset of dst on OpenCL dst\_node. if event is NULL, the copy is synchronous, i.e. the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. This function returns CL\_SUCCESS if the copy was successful, or a valid OpenCL error code otherwise. The integer pointed to by ret is set to -EAGAIN if the asynchronous launch was successful, or to 0 if event was NULL.

27.21.4.24 cl\_int starpu\_opencl\_copy\_async\_sync ( uintptr\_t src, size\_t src\_offset, unsigned src\_node, uintptr\_t dst, size\_t dst\_offset, unsigned dst\_node, size\_t size, cl\_event \* event )

Copy size bytes from byte offset src\_offset of src on src\_node to byte offset dst\_offset of dst on dst\_node. if event is NULL, the copy is synchronous, i.e. the queue is synchronised before returning. If not NULL, event can be used after the call to wait for this particular copy to complete. The function returns -EAGAIN if the asynchronous launch was successfull. It returns 0 if the synchronous copy was successful, or fails otherwise.

# 27.22 OpenMP Runtime Support

This section describes the interface provided for implementing OpenMP runtimes on top of StarPU.

#### **Data Structures**

- · struct starpu\_omp\_lock\_t
- · struct starpu\_omp\_nest\_lock\_t
- · struct starpu omp parallel region attr
- · struct starpu\_omp\_task\_region\_attr

#### **Enumerations**

```
    enum starpu_omp_sched_value {
        starpu_omp_sched_undefined, starpu_omp_sched_static, starpu_omp_sched_dynamic, starpu_omp_sched_guided,
        starpu_omp_sched_auto, starpu_omp_sched_runtime }
    enum starpu_omp_proc_bind_value {
        starpu_omp_proc_bind_undefined, starpu_omp_proc_bind_false, starpu_omp_proc_bind_true, starpu_omp_proc_bind_master,
        starpu_omp_proc_bind_close, starpu_omp_proc_bind_spread }
```

### Initialisation

- #define STARPU\_OPENMP
- int starpu\_omp\_init (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_shutdown (void) \_\_STARPU\_OMP\_NOTHROW

### **Parallel**

- void starpu\_omp\_parallel\_region (const struct starpu\_omp\_parallel\_region\_attr \*attr) \_\_STARPU\_OMP\_N-OTHROW
- void starpu\_omp\_master (void(\*f)(void \*arg), void \*arg) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_master\_inline (void) \_\_STARPU\_OMP\_NOTHROW

# **Synchronization**

- void starpu omp barrier (void) STARPU OMP NOTHROW
- void starpu\_omp\_critical (void(\*f)(void \*arg), void \*arg, const char \*name) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_critical\_inline\_begin (const char \*name) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_critical\_inline\_end (const char \*name) \_\_STARPU\_OMP\_NOTHROW

# Worksharing

- void starpu\_omp\_single (void(\*f)(void \*arg), void \*arg, int nowait) \_\_STARPU\_OMP\_NOTHROW
- int starpu omp single inline (void) STARPU OMP NOTHROW
- void starpu\_omp\_single\_copyprivate (void(\*f)(void \*arg, void \*data, unsigned long long data\_size), void \*arg, void \*data, unsigned long long data\_size) \_\_STARPU\_OMP\_NOTHROW
- void \* starpu omp single copyprivate inline begin (void \*data)
   STARPU OMP NOTHROW
- void starpu\_omp\_single\_copyprivate\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW

- void starpu\_omp\_for (void(\*f)(unsigned long long \_first\_i, unsigned long long \_nb\_i, void \*arg), void \*arg, unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, int nowait) \_\_STARP-U OMP NOTHROW
- int starpu\_omp\_for\_inline\_first (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_first\_i, unsigned long long \*\_nb\_i) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_for\_inline\_next (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_first\_i, unsigned long long \*\_nb\_i) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_for\_alt (void(\*f)(unsigned long long \_begin\_i, unsigned long long \_end\_i, void \*arg), void \*arg, unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, int nowait) \_\_S-TARPU OMP NOTHROW
- int starpu\_omp\_for\_inline\_first\_alt (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_begin\_i, unsigned long long \*\_end\_i) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_for\_inline\_next\_alt (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_begin\_i, unsigned long long \*\_end\_i) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_ordered (void(\*f)(void \*arg), void \*arg) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_ordered\_inline\_begin (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_ordered\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_sections (unsigned long long nb\_sections, void(\*\*section\_f)(void \*arg), void \*\*section\_arg, int nowait) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_sections\_combined (unsigned long long nb\_sections, void(\*section\_f)(unsigned long long section\_num, void \*arg), void \*section\_arg, int nowait) \_\_STARPU\_OMP\_NOTHROW

#### Task

- void starpu\_omp\_task\_region (const struct starpu\_omp\_task\_region\_attr \*attr) \_\_STARPU\_OMP\_NOTHR-OW
- void starpu\_omp\_taskwait (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp taskgroup (void(\*f)(void \*arg), void \*arg)
   STARPU OMP NOTHROW
- void starpu\_omp\_taskgroup\_inline\_begin (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_taskgroup\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW

### API

- void starpu omp set num threads (int threads)
   STARPU OMP NOTHROW
- int starpu\_omp\_get\_num\_threads () \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_thread\_num () \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_max\_threads () \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_num\_procs (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_in\_parallel (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_dynamic (int dynamic\_threads) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_dynamic (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_nested (int nested) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_nested (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_cancellation (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_schedule (enum starpu\_omp\_sched\_value kind, int modifier) \_\_STARPU\_OMP\_NOT-HROW
- void starpu\_omp\_get\_schedule (enum starpu\_omp\_sched\_value \*kind, int \*modifier) \_\_STARPU\_OMP\_N-OTHROW
- int starpu\_omp\_get\_thread\_limit (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_max\_active\_levels (int max\_levels) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_max\_active\_levels (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_level (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu omp get ancestor thread num (int level) STARPU OMP NOTHROW
- int starpu\_omp\_get\_team\_size (int level) \_\_STARPU\_OMP\_NOTHROW

- int starpu\_omp\_get\_active\_level (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_in\_final (void) \_\_STARPU\_OMP\_NOTHROW
- enum starpu omp proc bind value starpu omp get proc bind (void)
   STARPU OMP NOTHROW
- · void starpu omp set default device (int device num) STARPU OMP NOTHROW
- int starpu\_omp\_get\_default\_device (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_num\_devices (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_num\_teams (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_team\_num (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu omp is initial device (void) STARPU OMP NOTHROW
- void starpu omp init lock (starpu omp lock t \*lock) STARPU OMP NOTHROW
- void starpu omp destroy lock (starpu omp lock t \*lock)
   STARPU OMP NOTHROW
- void starpu\_omp\_set\_lock (starpu\_omp\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_unset\_lock (starpu\_omp\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_test\_lock (starpu\_omp\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp init nest lock (starpu omp nest lock t \*lock)
   STARPU OMP NOTHROW
- void starpu omp destroy nest lock (starpu omp nest lock t \*lock)
   STARPU OMP NOTHROW
- void starpu\_omp\_set\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_unset\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_test\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_atomic\_fallback\_inline\_begin (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_atomic\_fallback\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW
- double starpu\_omp\_get\_wtime (void) \_\_STARPU\_OMP\_NOTHROW
- double starpu\_omp\_get\_wtick (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_vector\_annotate (starpu\_data\_handle\_t handle, uint32\_t slice\_base) \_\_STARPU\_OMP\_-NOTHROW

### 27.22.1 Detailed Description

This section describes the interface provided for implementing OpenMP runtimes on top of StarPU.

### 27.22.2 Data Structure Documentation

27.22.2.1 struct starpu\_omp\_lock\_t

Opaque Simple Lock object (Simple Locks) for inter-task synchronization operations.

### See Also

```
starpu_omp_init_lock()
starpu_omp_destroy_lock()
starpu_omp_set_lock()
starpu_omp_unset_lock()
starpu_omp_test_lock()
```

# **Data Fields**

void *	internal	Is an opaque pointer for internal use.

#### 27.22.2.2 struct starpu\_omp\_nest\_lock\_t

Opaque Nestable Lock object (Nestable Locks) for inter-task synchronization operations.

## See Also

```
starpu_omp_init_nest_lock()
starpu_omp_destroy_nest_lock()
starpu_omp_set_nest_lock()
starpu_omp_unset_nest_lock()
starpu_omp_test_nest_lock()
```

## **Data Fields**

void *	internal	Is an opaque pointer for internal use.

# 27.22.2.3 struct starpu\_omp\_parallel\_region\_attr

Set of attributes used for creating a new parallel region.

### See Also

```
starpu_omp_parallel_region()
```

### **Data Fields**

struct starpu_codelet	cl	Is a starpu_codelet (Codelet And Tasks) to use for the parallel region implicit tasks. The codelet must provide a CPU implementation function.
		·
starpu_data	handles	Is an array of zero or more starpu_data_handle_t data handle to be
handle_t		passed to the parallel region implicit tasks.
*		
void *	cl_arg	Is an optional pointer to an inline argument to be passed to the region
		implicit tasks.
size_t	cl_arg_size	Is the size of the optional inline argument to be passed to the region
		implicit tasks, or 0 if unused.
unsigned	cl_arg_free	Is a boolean indicating whether the optional inline argument should be
		automatically freed (true), or not (false).
int	if_clause	Is a boolean indicating whether the if clause of the corresponding
		pragma omp parallel is true or false.
int	num_threads	Is an integer indicating the requested number of threads in the team of the
		newly created parallel region, or 0 to let the runtime choose the number
		of threads alone. This attribute may be ignored by the runtime system
		if the requested number of threads is higher than the number of threads
		that the runtime can create.

## 27.22.2.4 struct starpu\_omp\_task\_region\_attr

Set of attributes used for creating a new task region.

## See Also

```
starpu_omp_task_region()
```

### **Data Fields**

struct starpu_codelet	Is a starpu_codelet (Codelet And Tasks) to use for the task region explicit task. The codelet must provide a CPU implementation function or an accelerator implementation for offloaded target regions.
starpu_data handle_t *	Is an array of zero or more starpu_data_handle_t data handle to be passed to the task region explicit tasks.

Generated on Thu Dec 17 2015 14:27:36 for StarPU Handbook by Doxygen

void *	cl_arg	Is an optional pointer to an inline argument to be passed to the region implicit tasks.
size t	cl arg size	Is the size of the optional inline argument to be passed to the region
		implicit tasks, or 0 if unused.
unsigned	cl_arg_free	Is a boolean indicating whether the optional inline argument should be
		automatically freed (true), or not (false).
int	priority	
int	if_clause	Is a boolean indicating whether the if clause of the corresponding
		pragma omp task is true or false.
int	final_clause	Is a boolean indicating whether the final clause of the corresponding
		pragma omp task is true or false.
int	untied_clause	Is a boolean indicating whether the untied clause of the corresponding
		pragma omp task is true or false.
int	mergeable	Is a boolean indicating whether the <b>mergeable</b> clause of the correspond-
	clause	ing pragma omp task is true or false.

#### 27.22.3 Macro Definition Documentation

#### 27.22.3.1 #define STARPU\_OPENMP

This macro is defined when StarPU has been installed with OpenMP Runtime support. It should be used in your code to detect the availability of the runtime support for OpenMP.

## 27.22.4 Enumeration Type Documentation

### 27.22.4.1 enum starpu\_omp\_sched\_value

Set of constants for selecting the for loop iteration scheduling algorithm (Parallel For) as defined by the OpenMP specification.

### **Enumerator:**

```
starpu_omp_sched_undefined Undefined iteration scheduling algorithm.
starpu_omp_sched_static Static iteration scheduling algorithm.
starpu_omp_sched_dynamic Dynamic iteration scheduling algorithm.
starpu_omp_sched_guided Guided iteration scheduling algorithm.
starpu_omp_sched_auto Automatically choosen iteration scheduling algorithm.
starpu_omp_sched_runtime Choice of iteration scheduling algorithm deferred at runtime.
See Also
```

```
starpu_omp_for()
starpu_omp_for_inline_first()
starpu_omp_for_inline_next()
starpu_omp_for_alt()
starpu_omp_for_inline_first_alt()
starpu_omp_for_inline_next_alt()
```

# 27.22.4.2 enum starpu\_omp\_proc\_bind\_value

Set of constants for selecting the processor binding method, as defined in the OpenMP specification.

### **Enumerator:**

**starpu\_omp\_proc\_bind\_undefined** Undefined processor binding method.

starpu\_omp\_proc\_bind\_false Team threads may be moved between places at any time.

starpu\_omp\_proc\_bind\_true Team threads may not be moved between places.

starpu\_omp\_proc\_bind\_master Assign every thread in the team to the same place as the master thread.

starpu\_omp\_proc\_bind\_close Assign every thread in the team to a place close to the parent thread.

starpu\_omp\_proc\_bind\_spread Assign team threads as a sparse distribution over the selected places.

See Also

starpu\_omp\_get\_proc\_bind()

27.22.5 Function Documentation

27.22.5.1 int starpu\_omp\_init ( void )

Initializes StarPU and its OpenMP Runtime support.

27.22.5.2 void starpu\_omp\_shutdown ( void )

Shutdown StarPU and its OpenMP Runtime support.

27.22.5.3 void starpu\_omp\_parallel\_region ( const struct starpu\_omp\_parallel\_region\_attr \* attr )

Generates and launch an OpenMP parallel region and return after its completion. attr specifies the attributes for the generated parallel region. If this function is called from inside another, generating, parallel region, the generated parallel region is nested within the generating parallel region.

This function can be used to implement #pragma omp parallel.

27.22.5.4 void starpu\_omp\_master ( void(\*)(void \*arg) f, void \* arg )

Executes a function only on the master thread of the OpenMP parallel region it is called from. When called from a thread that is not the master of the parallel region it is called from, this function does nothing. f is the function to be called. f is an argument passed to function f.

This function can be used to implement #pragma omp master.

27.22.5.5 int starpu\_omp\_master\_inline ( void )

Determines whether the calling thread is the master of the OpenMP parallel region it is called from or not.

This function can be used to implement #pragma omp master without code outlining.

Returns

! 0 if called by the region's master thread.

 $\ensuremath{\text{0}}$  if not called by the region's master thread.

27.22.5.6 void starpu\_omp\_barrier (void)

Waits until each participating thread of the innermost OpenMP parallel region has reached the barrier and each explicit OpenMP task bound to this region has completed its execution.

This function can be used to implement #pragma omp barrier.

```
27.22.5.7 void starpu_omp_critical (void(*)(void *arg) f, void * arg, const char * name)
```

Waits until no other thread is executing within the context of the selected critical section, then proceeds to the exclusive execution of a function within the critical section. f is the function to be executed in the critical section. f arg is an argument passed to function f. f name is the name of the selected critical section. If f name f name f name is the unique anonymous critical section.

This function can be used to implement #pragma omp critical.

```
27.22.5.8 void starpu_omp_critical_inline_begin ( const char * name )
```

Waits until execution can proceed exclusively within the context of the selected critical section. name is the name of the selected critical section. If name == NULL, the selected critical section is the unique anonymous critical section.

This function together with starpu\_omp\_critical\_inline\_end can be used to implement #pragma omp critical without code outlining.

```
27.22.5.9 void starpu_omp_critical_inline_end ( const char * name )
```

Ends the exclusive execution within the context of the selected critical section. name is the name of the selected critical section. If name==NULL, the selected critical section is the unique anonymous critical section.

This function together with starpu\_omp\_critical\_inline\_begin can be used to implement #pragma omp critical without code outlining.

```
27.22.5.10 void starpu_omp_single (void(*)(void *arg) f, void * arg, int nowait)
```

Ensures that a single participating thread of the innermost OpenMP parallel region executes a function. f is the function to be executed by a single thread. arg is an argument passed to function f. nowait is a flag indicating whether an implicit barrier is requested after the single section (nowait==0) or not (nowait==10).

This function can be used to implement #pragma omp single.

```
27.22.5.11 int starpu_omp_single_inline ( void )
```

Decides whether the current thread is elected to run the following single section among the participating threads of the innermost OpenMP parallel region.

This function can be used to implement #pragma omp single without code outlining.

### Returns

- ! 0 if the calling thread has won the election.
- 0 if the calling thread has lost the election.

27.22.5.12 void starpu\_omp\_single\_copyprivate ( void(\*)(void \*arg, void \*data, unsigned long long data\_size) f, void \* arg, void \* data, unsigned long long data\_size )

This function executes f on a single task of the current parallel region task, and then broadcast the contents of the memory block pointed by the copyprivate pointer data and of size data\_size to the corresponding data pointed memory blocks of all the other participating region tasks. This function can be used to implement #pragma omp single with a copyprivate clause.

#### See Also

```
starpu_omp_single_copyprivate_inline
starpu_omp_single_copyprivate_inline_begin
starpu_omp_single_copyprivate_inline_end
```

27.22.5.13 void \* starpu\_omp\_single\_copyprivate\_inline\_begin ( void \* data )

This function elects one task among the tasks of the current parallel region task to execute the following single section, and then broadcast the copyprivate pointer data to all the other participating region tasks. This function can be used to implement #pragma omp single with a copyprivate clause without code outlining.

#### See Also

```
starpu_omp_single_copyprivate_inline
starpu_omp_single_copyprivate_inline_end
```

27.22.5.14 void starpu\_omp\_single\_copyprivate\_inline\_end (void)

This function completes the execution of a single section and returns the broadcasted copyprivate pointer for tasks that lost the election and NULL for the task that won the election. This function can be used to implement #pragma omp single with a copyprivate clause without code outlining.

#### Returns

the copyprivate pointer for tasks that lost the election and therefore did not execute the code of the single section.

NULL for the task that won the election and executed the code of the single section.

#### See Also

```
starpu_omp_single_copyprivate_inline
starpu_omp_single_copyprivate_inline_begin
```

27.22.5.15 void starpu\_omp\_for ( void(\*)(unsigned long long \_first\_i, unsigned long long \_nb\_i, void \*arg) f, void \* arg, unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, int nowait )

Executes a parallel loop together with the other threads participating to the innermost parallel region. f is the function to be executed iteratively. f is an argument passed to function f. f inb\_iterations is the number of iterations to be performed by the parallel loop. f chunk is the number of consecutive iterations that should be affected to the same thread when scheduling the loop workshares, it follows the semantics of the modifier argument in OpenMP #pragma omp for specification. f schedule is the scheduling mode according to the OpenMP specification. f ordered is a flag indicating whether the loop region may contain an ordered section (f ordered==0) or not (f or not

The function f will be called with arguments  $\_first\_i$ , the first iteration to perform,  $\_nb\_i$ , the number of consecutive iterations to perform before returning, arg, the free arg argument.

This function can be used to implement #pragma omp for.

27.22.5.16 int starpu\_omp\_for\_inline\_first ( unsigned long long *nb\_iterations*, unsigned long long *chunk*, int *schedule*, int *ordered*, unsigned long long \* \_*first\_i*, unsigned long long \* \_*nb\_i* )

Decides whether the current thread should start to execute a parallel loop section. See <a href="mailto:starpu\_omp\_for">starpu\_omp\_for</a> for the argument description.

This function together with starpu\_omp\_for\_inline\_next can be used to implement #pragma omp for without code outlining.

#### Returns

 $!\ 0$  if the calling thread participates to the loop region and should execute a first chunk of iterations. In that case,  $*\_first\_i$  will be set to the first iteration of the chunk to perform and  $*\_nb\_i$  will be set to the number of iterations of the chunk to perform.

0 if the calling thread does not participate to the loop region because all the available iterations have been affected to the other threads of the parallel region.

### See Also

```
starpu omp for
```

27.22.5.17 int starpu\_omp\_for\_inline\_next ( unsigned long long *nb\_iterations*, unsigned long long *chunk*, int *schedule*, int *ordered*, unsigned long long \* \_*first\_i*, unsigned long long \* \_*nb\_i* )

Decides whether the current thread should continue to execute a parallel loop section. See <a href="mailto:starpu\_omp\_for">starpu\_omp\_for</a> for the argument description.

This function together with starpu\_omp\_for\_inline\_first can be used to implement #pragma omp for without code outlining.

#### Returns

! 0 if the calling thread should execute a next chunk of iterations. In that case, \*\_first\_i will be set to the first iteration of the chunk to perform and \*\_nb\_i will be set to the number of iterations of the chunk to perform. 0 if the calling thread does not participate anymore to the loop region because all the available iterations have been affected to the other threads of the parallel region.

#### See Also

```
starpu_omp_for
```

27.22.5.18 void starpu\_omp\_for\_alt ( void(\*)(unsigned long long \_begin\_i, unsigned long long \_end\_i, void \* arg, unsigned long long \_nb\_iterations, unsigned long long \_chunk, int schedule, int ordered, int nowait )

Alternative implementation of a parallel loop. This function differs from  $starpu\_omp\_for$  in the expected arguments of the loop function f.

The function f will be called with arguments \_begin\_i, the first iteration to perform, \_end\_i, the first iteration not to perform before returning, arg, the free arg argument.

This function can be used to implement #pragma omp for.

## See Also

```
starpu_omp_for
```

27.22.5.19 int starpu\_omp\_for\_inline\_first\_alt ( unsigned long long *nb\_iterations*, unsigned long long *chunk*, int *schedule*, int *ordered*, unsigned long long \* \_*begin\_i*, unsigned long long \* \_*end\_i* )

Inline version of the alternative implementation of a parallel loop.

This function together with starpu\_omp\_for\_inline\_next\_alt can be used to implement #pragma omp for without code outlining.

#### See Also

```
starpu_omp_for
starpu_omp_for_alt
starpu_omp_for_inline_first
```

27.22.5.20 int starpu\_omp\_for\_inline\_next\_alt ( unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \* \_begin\_i, unsigned long long \* \_end\_i )

Inline version of the alternative implementation of a parallel loop.

This function together with starpu\_omp\_for\_inline\_first\_alt can be used to implement #pragma omp for without code outlining.

#### See Also

```
starpu_omp_for
starpu_omp_for_alt
starpu_omp_for_inline_next
```

```
27.22.5.21 void starpu_omp_ordered ( void(*)(void *arg) f, void * arg )
```

Ensures that a function is sequentially executed once for each iteration in order within a parallel loop, by the thread that own the iteration. f is the function to be executed by the thread that own the current iteration. f is an argument passed to function f.

This function can be used to implement #pragma omp ordered.

```
27.22.5.22 void starpu_omp_ordered_inline_begin ( void )
```

Waits until all the iterations of a parallel loop below the iteration owned by the current thread have been executed.

This function together with starpu\_omp\_ordered\_inline\_end can be used to implement #pragma omp ordered without code code outlining.

```
27.22.5.23 void starpu_omp_ordered_inline_end (void)
```

Notifies that the ordered section for the current iteration has been completed.

This function together with starpu\_omp\_ordered\_inline\_begin can be used to implement #pragma omp ordered without code code outlining.

27.22.5.24 void starpu\_omp\_sections ( unsigned long long nb\_sections, void(\*\*)(void \*arg) section\_f, void \*\* section\_arg, int nowait )

Ensures that each function of a given array of functions is executed by one and only one thread.  $nb\_sections$  is the number of functions in the array  $section\_f$ .  $section\_f$  is the array of functions to be executed as sections.  $section\_arg$  is an array of arguments to be passed to the corresponding function. nowait is a flag indicating whether an implicit barrier is requested after the execution of all the sections (nowait==0) or not (nowait==10).

This function can be used to implement #pragma omp sections and #pragma omp section.

27.22.5.25 void starpu\_omp\_sections\_combined ( unsigned long long nb\_sections, void(\*)(unsigned long long section\_num, void \*arg) section\_f, void \* section\_arg, int nowait )

Alternative implementation of sections. This function differs from starpu\_omp\_sections in that all the sections are combined within a single function in this version. section\_f is the function implementing the combined sections.

The function section\_f will be called with arguments section\_num, the section number to be executed, arg, the entry of section\_arg corresponding to this section.

This function can be used to implement #pragma omp sections and #pragma omp section.

#### See Also

```
starpu_omp_sections
```

```
27.22.5.26 void starpu_omp_task_region ( const struct starpu_omp_task_region_attr * attr )
```

Generates an explicit child task. The execution of the generated task is asynchronous with respect to the calling code unless specified otherwise. attr specifies the attributes for the generated task region.

This function can be used to implement #pragma omp task.

```
27.22.5.27 void starpu_omp_taskwait ( void )
```

Waits for the completion of the tasks generated by the current task. This function does not wait for the descendants of the tasks generated by the current task.

This function can be used to implement #pragma omp taskwait.

```
27.22.5.28 void starpu_omp_taskgroup ( void(*)(void *arg) f, void * arg )
```

Launches a function and wait for the completion of every descendant task generated during the execution of the function

This function can be used to implement #pragma omp taskgroup.

## See Also

```
starpu_omp_taskgroup_inline_begin
starpu_omp_taskgroup_inline_end
```

```
27.22.5.29 void starpu_omp_taskgroup_inline_begin ( void )
```

Launches a function and gets ready to wait for the completion of every descendant task generated during the dynamic scope of the taskgroup.

This function can be used to implement #pragma omp taskgroup without code outlining.

### See Also

```
starpu_omp_taskgroup
starpu_omp_taskgroup_inline_end
```

```
27.22.5.30 void starpu_omp_taskgroup_inline_end ( void )
```

Waits for the completion of every descendant task generated during the dynamic scope of the taskgroup.

This function can be used to implement #pragma omp taskgroup without code outlining.

#### See Also

```
starpu_omp_taskgroup
starpu_omp_taskgroup_inline_begin
```

27.22.5.31 void starpu\_omp\_set\_num\_threads ( int threads )

This function sets ICVS nthreads\_var for the parallel regions to be created with the current region.

Note: The StarPU OpenMP runtime support currently ignores this setting for nested parallel regions.

### See Also

```
starpu_omp_get_num_threads
starpu_omp_get_thread_num
starpu_omp_get_max_threads
starpu_omp_get_num_procs
```

27.22.5.32 int starpu\_omp\_get\_num\_threads ( )

This function returns the number of threads of the current region.

#### Returns

the number of threads of the current region.

### See Also

```
starpu_omp_set_num_threads
starpu_omp_get_thread_num
starpu_omp_get_max_threads
starpu_omp_get_num_procs
```

27.22.5.33 int starpu\_omp\_get\_thread\_num ( )

This function returns the rank of the current thread among the threads of the current region.

#### Returns

the rank of the current thread in the current region.

### See Also

```
starpu_omp_set_num_threads
starpu_omp_get_num_threads
starpu_omp_get_max_threads
starpu_omp_get_num_procs
```

 $27.22.5.34 \quad int \ starpu\_omp\_get\_max\_threads (\quad)$ 

This function returns the maximum number of threads that can be used to create a region from the current region.

#### Returns

the maximum number of threads that can be used to create a region from the current region.

#### See Also

```
starpu_omp_set_num_threads
starpu_omp_get_num_threads
starpu_omp_get_thread_num
starpu_omp_get_num_procs
```

27.22.5.35 int starpu\_omp\_get\_num\_procs ( void )

This function returns the number of StarPU CPU workers.

#### Returns

the number of StarPU CPU workers.

#### See Also

```
starpu_omp_set_num_threads
starpu_omp_get_num_threads
starpu_omp_get_thread_num
starpu_omp_get_max_threads
```

```
27.22.5.36 int starpu_omp_in_parallel ( void )
```

This function returns whether it is called from the scope of a parallel region or not.

### Returns

```
! 0 if called from a parallel region scope.
```

0 otherwise.

```
27.22.5.37 void starpu_omp_set_dynamic ( int dynamic_threads )
```

This function enables (1) or disables (0) dynamically adjusting the number of parallel threads.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function.

### See Also

```
starpu_omp_get_dynamic
```

```
27.22.5.38 int starpu_omp_get_dynamic ( void )
```

This function returns the state of dynamic thread number adjustment.

# Returns

```
! 0 if dynamic thread number adjustment is enabled.
```

0 otherwise.

```
starpu_omp_set_dynamic
```

```
27.22.5.39 void starpu_omp_set_nested ( int nested )
```

This function enables (1) or disables (0) nested parallel regions.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function.

#### See Also

```
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

## 27.22.5.40 int starpu\_omp\_get\_nested ( void )

This function returns whether nested parallel sections are enabled or not.

#### Returns

```
! 0 if nested parallel sections are enabled.
```

0 otherwise.

#### See Also

```
starpu_omp_set_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

```
27.22.5.41 int starpu_omp_get_cancellation ( void )
```

This function returns the state of the cancel ICVS var.

```
27.22.5.42 void starpu_omp_set_schedule ( enum starpu_omp_sched_value kind, int modifier )
```

This function sets the default scheduling kind for upcoming loops within the current parallel section. kind is the scheduler kind, modifier complements the scheduler kind with informations such as the chunk size, in accordance with the OpenMP specification.

#### See Also

```
starpu_omp_get_schedule
```

27.22.5.43 void starpu\_omp\_get\_schedule ( enum starpu\_omp\_sched\_value \* kind, int \* modifier )

This function returns the current selected default loop scheduler.

### Returns

the kind and the modifier of the current default loop scheduler.

```
starpu_omp_set_schedule
```

```
27.22.5.44 int starpu_omp_get_thread_limit ( void )
```

This function returns the number of StarPU CPU workers.

### Returns

the number of StarPU CPU workers.

```
27.22.5.45 void starpu_omp_set_max_active_levels ( int max_levels )
```

This function sets the maximum number of allowed active parallel section levels.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function and assume max\_-levels equals 1 instead.

#### See Also

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

```
27.22.5.46 int starpu_omp_get_max_active_levels ( void )
```

This function returns the current maximum number of allowed active parallel section levels

### Returns

the current maximum number of allowed active parallel section levels.

### See Also

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_set_max_active_levels
starpu_omp_get_level
starpu_omp_get_active_level
```

```
27.22.5.47 int starpu_omp_get_level ( void )
```

This function returns the nesting level of the current parallel section.

# Returns

the nesting level of the current parallel section.

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_active_level
```

```
27.22.5.48 int starpu_omp_get_ancestor_thread_num ( int level )
```

This function returns the number of the ancestor of the current parallel section.

#### Returns

the number of the ancestor of the current parallel section.

```
27.22.5.49 int starpu_omp_get_team_size ( int level )
```

This function returns the size of the team of the current parallel section.

#### Returns

the size of the team of the current parallel section.

```
27.22.5.50 int starpu_omp_get_active_level ( void )
```

This function returns the nestinglevel of the current innermost active parallel section.

#### Returns

the nestinglevel of the current innermost active parallel section.

# See Also

```
starpu_omp_set_nested
starpu_omp_get_nested
starpu_omp_get_max_active_levels
starpu_omp_set_max_active_levels
starpu_omp_get_level
```

```
27.22.5.51 int starpu_omp_in_final ( void )
```

This function checks whether the current task is final or not.

### Returns

```
! 0 if called from a final task.
```

0 otherwise.

```
27.22.5.52 enum starpu_omp_proc_bind_value starpu_omp_get_proc_bind (void)
```

This function returns the proc bind setting of the current parallel region.

### Returns

the proc\_bind setting of the current parallel region.

```
27.22.5.53 void starpu_omp_set_default_device ( int device_num )
```

This function sets the number of the device to use as default.

Note: The StarPU OpenMP runtime support currently ignores the argument of this function.

#### See Also

```
starpu_omp_get_default_device
starpu_omp_is_initial_device
```

```
27.22.5.54 int starpu_omp_get_default_device ( void )
```

This function returns the number of the device used as default.

#### Returns

the number of the device used as default.

#### See Also

```
starpu_omp_set_default_device
starpu_omp_is_initial_device
```

```
27.22.5.55 int starpu_omp_get_num_devices ( void )
```

This function returns the number of the devices.

### Returns

the number of the devices.

```
27.22.5.56 int starpu_omp_get_num_teams ( void )
```

This function returns the number of teams in the current teams region.

### **Returns**

the number of teams in the current teams region.

### See Also

```
starpu_omp_get_num_teams
```

```
27.22.5.57 int starpu_omp_get_team_num ( void )
```

This function returns the team number of the calling thread.

# Returns

the team number of the calling thread.

```
starpu_omp_get_num_teams
```

```
27.22.5.58 int starpu_omp_is_initial_device ( void )
```

This function checks whether the current device is the initial device or not.

#### Returns

```
! 0 if called from the host device. 0 otherwise.
```

### See Also

```
starpu_omp_set_default_device
starpu_omp_get_default_device
```

```
27.22.5.59 void starpu_omp_init_lock ( starpu_omp_lock_t * lock )
```

This function initializes an opaque lock object.

#### See Also

```
starpu_omp_destroy_lock
starpu_omp_set_lock
starpu_omp_unset_lock
starpu_omp_test_lock
```

```
27.22.5.60 void starpu_omp_destroy_lock ( starpu_omp_lock_t * lock )
```

This function destroys an opaque lock object.

# See Also

```
starpu_omp_init_lock
starpu_omp_set_lock
starpu_omp_unset_lock
starpu_omp_test_lock
```

```
27.22.5.61 void starpu_omp_set_lock ( starpu_omp_lock_t * lock )
```

This function locks an opaque lock object. If the lock is already locked, the function will block until it succeeds in exclusively acquiring the lock.

## See Also

```
starpu_omp_init_lock
starpu_omp_destroy_lock
starpu_omp_unset_lock
starpu_omp_test_lock
```

```
27.22.5.62 void starpu_omp_unset_lock ( starpu_omp_lock_t * lock )
```

This function unlocks a previously locked lock object. The behaviour of this function is unspecified if it is called on an unlocked lock object.

#### See Also

```
starpu_omp_init_lock
starpu_omp_destroy_lock
starpu_omp_set_lock
starpu_omp_test_lock
27.22.5.63 int starpu_omp_test_lock ( starpu_omp_lock_t * lock )
```

This function unblockingly attempts to lock a lock object and returns whether it succeeded or not.

#### Returns

```
! 0 if the function succeeded in acquiring the lock. 0 if the lock was already locked.
```

### See Also

```
starpu_omp_init_lock
starpu_omp_destroy_lock
starpu_omp_set_lock
starpu_omp_unset_lock
```

```
27.22.5.64 void starpu_omp_init_nest_lock ( starpu_omp_nest_lock_t * lock )
```

This function initializes an opaque lock object supporting nested locking operations.

#### See Also

```
starpu_omp_destroy_nest_lock
starpu_omp_set_nest_lock
starpu_omp_unset_nest_lock
starpu_omp_test_nest_lock
```

```
27.22.5.65 void starpu_omp_destroy_nest_lock ( starpu_omp_nest_lock_t * lock )
```

This function destroys an opaque lock object supporting nested locking operations.

# See Also

```
starpu_omp_init_nest_lock
starpu_omp_set_nest_lock
starpu_omp_unset_nest_lock
starpu_omp_test_nest_lock
```

```
27.22.5.66 void starpu_omp_set_nest_lock ( starpu_omp_nest_lock_t * lock )
```

This function locks an opaque lock object supporting nested locking operations. If the lock is already locked by another task, the function will block until it succeeds in exclusively acquiring the lock. If the lock is already taken by the current task, the function will increase the nested locking level of the lock object.

```
starpu_omp_init_nest_lock
starpu_omp_destroy_nest_lock
starpu_omp_unset_nest_lock
starpu_omp_test_nest_lock
```

```
27.22.5.67 void starpu_omp_unset_nest_lock ( starpu_omp_nest_lock_t * lock )
```

This function unlocks a previously locked lock object supporting nested locking operations. If the lock has been locked multiple times in nested fashion, the nested locking level is decreased and the lock remains locked. Otherwise, if the lock has only been locked once, it becomes unlocked. The behaviour of this function is unspecified if it is called on an unlocked lock object. The behaviour of this function is unspecified if it is called from a different task than the one that locked the lock object.

#### See Also

```
starpu_omp_init_nest_lock
starpu_omp_destroy_nest_lock
starpu_omp_set_nest_lock
starpu_omp_test_nest_lock
```

```
27.22.5.68 int starpu_omp_test_nest_lock ( starpu omp_nest_lock t * lock )
```

This function unblocking attempts to lock an opaque lock object supporting nested locking operations and returns whether it succeeded or not. If the lock is already locked by another task, the function will return without having acquired the lock. If the lock is already taken by the current task, the function will increase the nested locking level of the lock object.

#### Returns

- ! 0 if the function succeeded in acquiring the lock.
- 0 if the lock was already locked.

### See Also

```
starpu_omp_init_nest_lock
starpu_omp_destroy_nest_lock
starpu_omp_set_nest_lock
starpu_omp_unset_nest_lock
```

27.22.5.69 void starpu\_omp\_atomic\_fallback\_inline\_begin (void)

This function implements the entry point of a fallback global atomic region. It blocks until it succeeds in acquiring exclusive access to the global atomic region.

#### See Also

```
starpu omp atomic fallback inline end
```

27.22.5.70 void starpu\_omp\_atomic\_fallback\_inline\_end ( void )

This function implements the exit point of a fallback global atomic region. It release the exclusive access to the global atomic region.

```
starpu_omp_atomic_fallback_inline_begin
```

```
27.22.5.71 double starpu_omp_get_wtime ( void )
```

This function returns the elapsed wallclock time in seconds.

#### Returns

the elapsed wallclock time in seconds.

#### See Also

```
starpu_omp_get_wtick
```

27.22.5.72 double starpu\_omp\_get\_wtick ( void )

This function returns the precision of the time used by starpu\_omp\_get\_wtime.

### **Returns**

the precision of the time used by starpu\_omp\_get\_wtime.

### See Also

```
starpu_omp_get_wtime
```

27.22.5.73 void starpu\_omp\_vector\_annotate ( starpu\_data\_handle\_t handle, uint32\_t slice\_base )

This function enables setting additional vector metadata needed by the OpenMP Runtime Support.

handle is vector data handle. slice\_base is the base of an array slice, expressed in number of vector elements from the array base.

#### See Also

```
STARPU_VECTOR_GET_SLICE_BASE
```

## 27.23 MIC Extensions

# Macros

- #define STARPU\_USE\_MIC
- #define STARPU MAXMICDEVS

# **Typedefs**

typedef void \* starpu\_mic\_func\_symbol\_t

### **Functions**

- int starpu\_mic\_register\_kernel (starpu\_mic\_func\_symbol\_t \*symbol, const char \*func\_name)
- starpu\_mic\_kernel\_t starpu\_mic\_get\_kernel (starpu\_mic\_func\_symbol\_t symbol)

27.24 SCC Extensions 285

## 27.23.1 Detailed Description

## 27.23.2 Macro Definition Documentation

# 27.23.2.1 #define STARPU\_USE\_MIC

This macro is defined when StarPU has been installed with MIC support. It should be used in your code to detect the availability of MIC.

#### 27.23.2.2 #define STARPU\_MAXMICDEVS

This macro defines the maximum number of MIC devices that are supported by StarPU.

## 27.23.3 Typedef Documentation

```
27.23.3.1 starpu_mic_func_symbol_t
```

Type for MIC function symbols

#### 27.23.4 Function Documentation

```
 27.23.4.1 \quad \text{int starpu\_mic\_register\_kernel (} \quad \text{starpu\_mic\_func\_symbol\_t} * \textit{symbol}, \text{ const char} * \textit{func\_name} \text{ )}
```

Initiate a lookup on each MIC device to find the adress of the function named func\_name, store them in the global array kernels and return the index in the array through symbol.

```
27.23.4.2 starpu_mic_kernel_t starpu_mic_get_kernel ( starpu_mic_func_symbol_t symbol )
```

If success, return the pointer to the function defined by symbol on the device linked to the called device. This can for instance be used in a starpu\_mic\_func\_t implementation.

# 27.24 SCC Extensions

### **Macros**

- #define STARPU\_USE\_SCC
- #define STARPU MAXSCCDEVS

## **Typedefs**

• typedef void \* starpu\_scc\_func\_symbol\_t

#### **Functions**

- int starpu\_scc\_register\_kernel (starpu\_scc\_func\_symbol\_t \*symbol, const char \*func\_name)
- starpu\_scc\_kernel\_t starpu\_scc\_get\_kernel (starpu\_scc\_func\_symbol\_t symbol)

#### 27.24.1 Detailed Description

### 27.24.2 Macro Definition Documentation

#### 27.24.2.1 #define STARPU\_USE\_SCC

This macro is defined when StarPU has been installed with SCC support. It should be used in your code to detect the availability of SCC.

#### 27.24.2.2 #define STARPU\_MAXSCCDEVS

This macro defines the maximum number of SCC devices that are supported by StarPU.

### 27.24.3 Typedef Documentation

```
27.24.3.1 starpu_scc_func_symbol_t
```

Type for SCC function symbols

#### 27.24.4 Function Documentation

```
27.24.4.1 int starpu_scc_register_kernel ( starpu_scc_func_symbol_t * symbol, const char * func_name )
```

Initiate a lookup on each SCC device to find the adress of the function named func\_name, store them in the global array kernels and return the index in the array through symbol.

```
27.24.4.2 starpu_scc_kernel_t starpu_scc_get_kernel ( starpu_scc_func_symbol_t symbol )
```

If success, return the pointer to the function defined by symbol on the device linked to the called device. This can for instance be used in a  $starpu\_scc\_func\_t$  implementation.

# 27.25 Miscellaneous Helpers

# **Functions**

- int starpu\_data\_cpy (starpu\_data\_handle\_t dst\_handle, starpu\_data\_handle\_t src\_handle, int asynchronous, void(\*callback\_func)(void \*), void \*callback\_arg)
- void starpu execute on each worker (void(\*func)(void \*), void \*arg, uint32 t where)
- void starpu\_execute\_on\_each\_worker\_ex (void(\*func)(void \*), void \*arg, uint32\_t where, const char \*name)
- void starpu\_execute\_on\_specific\_workers (void(\*func)(void \*), void \*arg, unsigned num\_workers, unsigned \*workers, const char \*name)
- double starpu\_timing\_now (void)

### 27.25.1 Detailed Description

### 27.25.2 Function Documentation

27.25.2.1 int starpu\_data\_cpy ( starpu\_data\_handle\_t dst\_handle, starpu\_data\_handle\_t src\_handle, int asynchronous, void(\*)(void \*) callback\_func, void \* callback\_arg )

Copy the content of src\_handle into dst\_handle. The parameter asynchronous indicates whether the function should block or not. In the case of an asynchronous call, it is possible to synchronize with the termination

27.26 FxT Support 287

of this operation either by the means of implicit dependencies (if enabled) or by calling starpu\_task\_wait\_for\_all(). If callback\_func is not NULL, this callback function is executed after the handle has been copied, and it is given the pointer callback\_arg as argument.

```
27.25.2.2 void starpu_execute_on_each_worker ( void(*)(void *) func, void * arg, uint32_t where )
```

This function executes the given function on a subset of workers. When calling this method, the offloaded function func is executed by every StarPU worker that may execute the function. The argument arg is passed to the offloaded function. The argument where specifies on which types of processing units the function should be executed. Similarly to the field starpu\_codelet::where, it is possible to specify that the function should be executed on every CUDA device and every CPU by passing STARPU\_CPU|STARPU\_CUDA. This function blocks until the function has been executed on every appropriate processing units, so that it may not be called from a callback function for instance.

```
27.25.2.3 void starpu_execute_on_each_worker_ex ( void(*)(void *) func, void * arg, uint32_t where, const char * name )
```

Same as starpu\_execute\_on\_each\_worker(), except that the task name is specified in the argument name.

```
27.25.2.4 void starpu_execute_on_specific_workers ( void(*)(void *) func, void * arg, unsigned num_workers, unsigned * workers, const char * name )
```

Call func(arg) on every worker in the workers array. num\_workers indicates the number of workers in this array. This function is synchronous, but the different workers may execute the function in parallel.

```
27.25.2.5 double starpu_timing_now ( void )
```

Return the current date in micro-seconds.

# 27.26 FxT Support

#### **Data Structures**

- · struct starpu fxt codelet event
- struct starpu\_fxt\_options

# **Functions**

- void starpu\_fxt\_options\_init (struct starpu\_fxt\_options \*options)
- void starpu\_fxt\_generate\_trace (struct starpu\_fxt\_options \*options)
- void starpu\_fxt\_start\_profiling (void)
- void starpu\_fxt\_stop\_profiling (void)
- void starpu\_fxt\_write\_data\_trace (char \*filename\_in)
- void starpu\_fxt\_trace\_user\_event (unsigned long code)

#### 27.26.1 Detailed Description

#### 27.26.2 Data Structure Documentation

#### 27.26.2.1 struct starpu\_fxt\_codelet\_event

todo

# **Data Fields**

char	symbol	name of the codelet
int	workerid	
char	perfmodel archname	
	archname	
uint32_t	hash	
size_t	size	
float	time	

# 27.26.2.2 struct starpu\_fxt\_options

todo

# **Data Fields**

unsigned	per_task_colour	
unsigned	no_counter	
unsigned	no_bus	
unsigned	ninputfiles	
char *	filenames	
char *	out_paje_path	
char *	distrib_time	
	path	
char *	activity_path	
char *	dag_path	
char *	tasks_path	
char *	anim_path	
char *	file_prefix	In case we are going to gather multiple traces (e.g in the case of MPI
		processes), we may need to prefix the name of the containers.
uint64_t	file_offset	In case we are going to gather multiple traces (e.g in the case of MPI
		processes), we may need to prefix the name of the containers.
int	file_rank	In case we are going to gather multiple traces (e.g in the case of MPI
		processes), we may need to prefix the name of the containers.
char	worker_names	Output parameters
struct starpu	worker	Output parameters
perfmodel_arch	archtypes	
int	nworkers	Output parameters
struct starpu_fxt-	dumped	In case we want to dump the list of codelets to an external tool
_codelet_event	codelets	
**		
long	dumped	In case we want to dump the list of codelets to an external tool
	codelets_count	

# 27.26.3 Function Documentation

27.26.3.1 void starpu\_fxt\_options\_init ( struct starpu\_fxt\_options \* options )

todo

 ${\tt 27.26.3.2 \quad void \ starpu\_fxt\_generate\_trace \left( \ struct \ starpu\_fxt\_options * \textit{options} \ \right)}$ 

todo

27.27 FFT Support 289

```
27.26.3.3 void starpu_fxt_start_profiling ( void )
```

Start recording the trace. The trace is by default started from starpu\_init() call, but can be paused by using starpu\_fxt\_stop\_profiling(), in which case starpu\_fxt\_start\_profiling() should be called to resume recording events.

```
27.26.3.4 void starpu_fxt_stop_profiling ( void )
```

Stop recording the trace. The trace is by default stopped when calling starpu\_shutdown(). starpu\_fxt\_stop\_profiling() can however be used to stop it earlier. starpu\_fxt\_start\_profiling() can then be called to start recording it again, etc.

```
27.26.3.5 void starpu_fxt_write_data_trace ( char * filename_in )
```

todo

27.26.3.6 void starpu\_fxt\_trace\_user\_event ( unsigned long code )

Add an event in the execution trace if FxT is enabled.

# 27.27 FFT Support

# **Functions**

- void \* starpufft malloc (size t n)
- void starpufft free (void \*p)
- starpufft\_plan starpufft\_plan\_dft\_1d (int n, int sign, unsigned flags)
- starpufft\_plan starpufft\_plan\_dft\_2d (int n, int m, int sign, unsigned flags)
- struct starpu\_task \* starpufft\_start (starpufft\_plan p, void \*in, void \*out)
- struct starpu\_task \* starpufft\_start\_handle (starpufft\_plan p, starpu\_data\_handle\_t in, starpu\_data\_handle\_t out)
- int starpufft\_execute (starpufft\_plan p, void \*in, void \*out)
- int starpufft\_execute\_handle (starpufft\_plan p, starpu\_data\_handle\_t in, starpu\_data\_handle\_t out)
- void starpufft\_cleanup (starpufft\_plan p)
- void starpufft\_destroy\_plan (starpufft\_plan p)

## 27.27.1 Detailed Description

## 27.27.2 Function Documentation

```
27.27.2.1 void * starpufft_malloc ( size_t n )
```

Allocates memory for n bytes. This is preferred over malloc(), since it allocates pinned memory, which allows overlapped transfers.

```
27.27.2.2 void * starpufft_free ( void * p )
```

Release memory previously allocated.

```
27.27.2.3 struct starpufft_plan * starpufft_plan_dft_1d ( int n, int sign, unsigned flags )
```

Initializes a plan for 1D FFT of size n. sign can be STARPUFFT\_FORWARD or STARPUFFT\_INVERSE. flags must be 0.

27.27.2.4 struct starpufft\_plan \* starpufft\_plan\_dft\_2d ( int n, int m, int sign, unsigned flags )

Initializes a plan for 2D FFT of size (n, m). sign can be STARPUFFT\_FORWARD or STARPUFFT\_INVERSE. flags must be 0.

```
27.27.2.5 struct starpu task * starpufft_start ( starpufft_plan p, void * in, void * out ) [read]
```

Start an FFT previously planned as p, using in and out as input and output. This only submits the task and does not wait for it. The application should call starpufft cleanup() to unregister the

```
27.27.2.6 struct starpu_task * starpufft_start_handle ( starpufft_plan p, starpu_data_handle_t in, starpu_data_handle_t out ) [read]
```

Start an FFT previously planned as p, using data handles in and out as input and output (assumed to be vectors of elements of the expected types). This only submits the task and does not wait for it.

```
27.27.2.7 void starpufft_execute ( starpufft_plan p, void * in, void * out )
```

Execute an FFT previously planned as p, using in and out as input and output. This submits and waits for the task.

```
27.27.2.8 void starpufft_execute_handle ( starpufft_plan p, starpu_data_handle_t in, starpu_data_handle_t out )
```

Execute an FFT previously planned as p, using data handles in and out as input and output (assumed to be vectors of elements of the expected types). This submits and waits for the task.

```
27.27.2.9 void starpufft_cleanup ( starpufft_plan p )
```

Releases data for plan p, in the starpufft start() case.

```
27.27.2.10 void starpufft_destroy_plan ( starpufft_plan p )
```

Destroys plan p, i.e. release all CPU (fftw) and GPU (cufft) resources.

# 27.28 MPI Support

### Initialisation

- #define STARPU USE MPI
- int starpu\_mpi\_init\_comm (int \*argc, char \*\*\*argv, int initialize\_mpi, MPI\_Comm comm)
- int starpu mpi init (int \*argc, char \*\*\*argv, int initialize mpi)
- int starpu\_mpi\_initialize (void)
- int starpu\_mpi\_initialize\_extended (int \*rank, int \*world\_size)
- int starpu\_mpi\_shutdown (void)
- void starpu\_mpi\_comm\_amounts\_retrieve (size\_t \*comm\_amounts)

#### Communication

• int starpu\_mpi\_send (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm)

27.28 MPI Support 291

• int starpu\_mpi\_recv (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, MPI\_-Status \*status)

- int starpu\_mpi\_isend (starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \*req, int dest, int mpi\_tag, MPI\_-Comm comm)
- int starpu\_mpi\_irecv (starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \*req, int source, int mpi\_tag, MPI\_Comm comm)
- int starpu\_mpi\_isend\_detached (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg)
- int starpu\_mpi\_irecv\_detached (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg)
- int starpu\_mpi\_irecv\_detached\_sequential\_consistency (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg, int sequential\_consistency)
- int starpu\_mpi\_issend (starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \*req, int dest, int mpi\_tag, MPI\_Comm comm)
- int starpu\_mpi\_issend\_detached (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg)
- int starpu\_mpi\_wait (starpu\_mpi\_req \*req, MPI\_Status \*status)
- int starpu mpi test (starpu mpi reg \*reg, int \*flag, MPI Status \*status)
- int starpu mpi barrier (MPI Comm comm)
- int starpu\_mpi\_isend\_detached\_unlock\_tag (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_-Comm comm, starpu\_tag\_t tag)
- int starpu\_mpi\_irecv\_detached\_unlock\_tag (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MP-I\_Comm comm, starpu\_tag\_t tag)
- int starpu\_mpi\_isend\_array\_detached\_unlock\_tag (unsigned array\_size, starpu\_data\_handle\_t \*data\_handle, int \*dest, int \*mpi\_tag, MPI\_Comm \*comm, starpu\_tag\_t tag)
- int starpu\_mpi\_irecv\_array\_detached\_unlock\_tag (unsigned array\_size, starpu\_data\_handle\_t \*data\_handle, int \*source, int \*mpi\_tag, MPI\_Comm \*comm, starpu\_tag\_t tag)
- int starpu\_mpi\_get\_communication\_tag (void)
- void starpu\_mpi\_set\_communication\_tag (int tag)
- int starpu\_mpi\_datatype\_register (starpu\_data\_handle\_t handle, starpu\_mpi\_datatype\_allocate\_func\_t allocate\_datatype\_func, starpu\_mpi\_datatype\_free\_func\_t free\_datatype\_func)
- int starpu mpi datatype unregister (starpu data handle t handle)

## **Communication Cache**

- · int starpu mpi cache is enabled ()
- int starpu\_mpi\_cache\_set (int enabled)
- void starpu\_mpi\_cache\_flush (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle)
- void starpu\_mpi\_cache\_flush\_all\_data (MPI\_Comm comm)

#### **MPI Insert Task**

- #define starpu mpi data register(data handle, tag, rank)
- #define starpu\_data\_set\_tag
- #define starpu\_mpi\_data\_set\_rank(handle, rank)
- #define starpu data set rank
- #define starpu\_data\_get\_rank
- · #define starpu data get tag
- #define STARPU\_EXECUTE\_ON\_NODE
- #define STARPU EXECUTE ON DATA
- void starpu\_mpi\_data\_register\_comm (starpu\_data\_handle\_t data\_handle, int tag, int rank, MPI\_Comm comm)
- void starpu mpi data set tag (starpu data handle t handle, int tag)
- void starpu\_mpi\_data\_set\_rank\_comm (starpu\_data\_handle\_t handle, int rank, MPI\_Comm comm)

- int starpu\_mpi\_data\_get\_rank (starpu\_data\_handle\_t handle)
- int starpu mpi data get tag (starpu data handle t handle)
- int starpu mpi insert task (MPI Comm comm, struct starpu codelet \*codelet,...)
- int starpu\_mpi\_task\_insert (MPI\_Comm comm, struct starpu\_codelet \*codelet,...)
- struct starpu\_task \* starpu\_mpi\_task\_build (MPI\_Comm comm, struct starpu\_codelet \*codelet,...)
- int starpu mpi task post build (MPI Comm comm, struct starpu codelet \*codelet,...)
- void starpu\_mpi\_get\_data\_on\_node (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle, int node)
- void starpu\_mpi\_get\_data\_on\_node\_detached (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle, int node, void(\*callback)(void \*), void \*arg)

### **Node Selection Policy**

- int starpu\_mpi\_node\_selection\_get\_current\_policy ()
- int starpu\_mpi\_node\_selection\_set\_current\_policy (int policy)
- int starpu\_mpi\_node\_selection\_register\_policy (starpu\_mpi\_select\_node\_policy\_func\_t policy\_func)
- int starpu\_mpi\_node\_selection\_unregister\_policy (int policy)

# **Collective Operations**

- void starpu\_mpi\_redux\_data (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle)
- int starpu\_mpi\_scatter\_detached (starpu\_data\_handle\_t \*data\_handles, int count, int root, MPI\_Comm comm, void(\*scallback)(void \*), void \*sarg, void(\*rcallback)(void \*), void \*rarg)
- int starpu\_mpi\_gather\_detached (starpu\_data\_handle\_t \*data\_handles, int count, int root, MPI\_Comm comm, void(\*scallback)(void \*), void \*sarg, void(\*rcallback)(void \*), void \*rarg)

#### 27.28.1 Detailed Description

# 27.28.2 Macro Definition Documentation

#### 27.28.2.1 #define STARPU\_USE\_MPI

This macro is defined when StarPU has been installed with MPI support. It should be used in your code to detect the availability of MPI.

```
27.28.2.2 #define starpu_mpi_data_register( data_handle, tag, rank )
```

Register to MPI a StarPU data handle with the given tag, rank and the MPI communicator MPI\_COMM\_WORLD. It also automatically clears the MPI communication cache when unregistering the data.

27.28.2.3 #define starpu\_data\_set\_tag

Symbol kept for backward compatibility. Calling function starpu mpi data set tag

27.28.2.4 #define starpu\_mpi\_data\_set\_rank( handle, rank )

Register to MPI a StarPU data handle with the given rank and the MPI communicator MPI\_COMM\_WORLD. No tag will be defined. It also automatically clears the MPI communication cache when unregistering the data. Symbol kept for backward compatibility. Calling function starpu\_mpi\_data\_set\_rank

27.28 MPI Support 293

### 27.28.2.5 #define starpu\_data\_set\_rank

Register to MPI a StarPU data handle with the given rank and the MPI communicator MPI\_COMM\_WORLD. No tag will be defined. It also automatically clears the MPI communication cache when unregistering the data. Symbol kept for backward compatibility. Calling function starpu\_mpi\_data\_set\_rank

27.28.2.6 #define starpu\_data\_get\_rank

Return the rank of the given data. Symbol kept for backward compatibility. Calling function starpu\_mpi\_data\_get\_rank

27.28.2.7 #define starpu\_data\_get\_tag

Return the tag of the given data. Symbol kept for backward compatibility. Calling function starpu\_mpi\_data\_get\_tag

27.28.2.8 #define STARPU\_EXECUTE\_ON\_NODE

this macro is used when calling starpu\_mpi\_task\_insert(), and must be followed by a integer value which specified the node on which to execute the codelet.

27.28.2.9 #define STARPU\_EXECUTE\_ON\_DATA

this macro is used when calling starpu\_mpi\_task\_insert(), and must be followed by a data handle to specify that the node owning the given data will execute the codelet.

27.28.3 Function Documentation

27.28.3.1 int starpu\_mpi\_init\_comm ( int \* argc, char \*\*\* argv, int initialize\_mpi, MPI\_Comm comm )

Initializes the starpumpi library with the given communicator. initialize\_mpi indicates if MPI should be initialized or not by StarPU. If the value is not 0, MPI will be initialized by calling MPI\_Init\_Thread(argc, argv, MPI\_THREAD\_SERIALIZED, ...).

27.28.3.2 int starpu\_mpi\_init ( int \* argc, char \*\*\* argv, int initialize\_mpi )

Call starpu\_mpi\_init\_comm() with the MPI communicator MPI\_COMM\_WORLD.

27.28.3.3 int starpu\_mpi\_initialize ( void )

**Deprecated** This function has been made deprecated. One should use instead the function starpu\_mpi\_init(). This function does not call MPI\_Init(), it should be called beforehand.

27.28.3.4 int starpu\_mpi\_initialize\_extended ( int \* rank, int \* world\_size )

Deprecated This function has been made deprecated. One should use instead the function starpu\_mpi\_init(). MPI will be initialized by starpumpi by calling MPI\_Init\_Thread(argc, argv, MPI\_THREAD\_- SERIALIZED, ...).

27.28.3.5 int starpu\_mpi\_shutdown ( void )

Cleans the starpumpi library. This must be called between calling starpu\_mpi functions and starpu\_shutdown(). MPI\_Finalize() will be called if StarPU-MPI has been initialized by starpu\_mpi\_init().

27.28.3.6 void starpu\_mpi\_comm\_amounts\_retrieve ( size\_t \* comm\_amounts )

Retrieve the current amount of communications from the current node in the array <code>comm\_amounts</code> which must have a size greater or equal to the world size. Communications statistics must be enabled (see STARPU\_COMM\_STATS).

27.28.3.7 int starpu\_mpi\_send ( starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm )

Performs a standard-mode, blocking send of data\_handle to the node dest using the message tag mpi\_tag within the communicator comm.

27.28.3.8 int starpu\_mpi\_recv ( starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, MPI\_Status \* status )

Performs a standard-mode, blocking receive in data\_handle from the node source using the message tag mpi\_tag within the communicator comm.

27.28.3.9 int starpu\_mpi\_isend ( starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \* req, int dest, int mpi\_tag, MPI\_Comm comm )

Posts a standard-mode, non blocking send of  $data\_handle$  to the node dest using the message tag  $mpi\_tag$  within the communicator comm. After the call, the pointer to the request req can be used to test or to wait for the completion of the communication.

27.28.3.10 int starpu\_mpi\_irecv ( starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \* req, int source, int mpi\_tag, MPI\_Comm comm )

Posts a nonblocking receive in  $data_handle$  from the node source using the message tag  $mpi_tag$  within the communicator comm. After the call, the pointer to the request req can be used to test or to wait for the completion of the communication.

27.28.3.11 int starpu\_mpi\_isend\_detached ( starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, void(\*)(void \*) callback, void \* arg )

Posts a standard-mode, non blocking send of data\_handle to the node dest using the message tag mpi\_tag within the communicator comm. On completion, the callback function is called with the argument arg. Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

27.28.3.12 int starpu\_mpi\_irecv\_detached ( starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, void(\*)(void \*) callback, void \* arg )

Posts a nonblocking receive in data\_handle from the node source using the message tag mpi\_tag within the communicator comm. On completion, the callback function is called with the argument arg. Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

27.28 MPI Support 295

27.28.3.13 int starpu\_mpi\_irecv\_detached\_sequential\_consistency ( starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, void(\*)(void \*) callback, void \* arg, int sequential\_consistency )

Posts a nonblocking receive in data\_handle from the node source using the message tag mpi\_tag within the communicator comm. On completion, the callback function is called with the argument arg. The parameter sequential\_consistency allows to enable or disable the sequential consistency for data handle (sequential consistency will be enabled or disabled based on the value of the parameter sequential\_consistency and the value of the sequential consistency defined for data\_handle). Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

27.28.3.14 int starpu\_mpi\_issend ( starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \* req, int dest, int mpi\_tag, MPI\_Comm comm )

Performs a synchronous-mode, non-blocking send of data\_handle to the node dest using the message tag mpi\_tag within the communicator comm.

27.28.3.15 int starpu\_mpi\_issend\_detached ( starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, void(\*)(void \*) callback, void \* arg )

Performs a synchronous-mode, non-blocking send of  $\mathtt{data\_handle}$  to the node  $\mathtt{dest}$  using the message tag  $\mathtt{mpi\_tag}$  within the communicator  $\mathtt{comm}$ . On completion, the  $\mathtt{callback}$  function is called with the argument  $\mathtt{arg}$ . Similarly to the pthread detached functionality, when a detached communication completes, its resources are automatically released back to the system, there is no need to test or to wait for the completion of the request.

27.28.3.16 int starpu\_mpi\_wait ( starpu\_mpi\_req \* req, MPI\_Status \* status )

Returns when the operation identified by request reg is complete.

27.28.3.17 int starpu\_mpi\_test ( starpu\_mpi\_req \* req, int \* flag, MPI\_Status \* status )

If the operation identified by req is complete, set flag to 1. The status object is set to contain information on the completed operation.

27.28.3.18 int starpu\_mpi\_barrier ( MPI\_Comm comm )

Blocks the caller until all group members of the communicator comm have called it.

27.28.3.19 int starpu\_mpi\_isend\_detached\_unlock\_tag ( starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, starpu\_tag\_t tag )

Posts a standard-mode, non blocking send of data\_handle to the node dest using the message tag mpi\_tag within the communicator comm. On completion, tag is unlocked.

27.28.3.20 int starpu\_mpi\_irecv\_detached\_unlock\_tag ( starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, starpu tag t tag )

Posts a nonblocking receive in  $data\_handle$  from the node source using the message tag  $mpi\_tag$  within the communicator comm. On completion, tag is unlocked.

27.28.3.21 int starpu\_mpi\_isend\_array\_detached\_unlock\_tag ( unsigned array\_size, starpu\_data\_handle\_t \* data\_handle, int \* dest, int \* mpi\_tag, MPI\_Comm \* comm, starpu\_tag t tag )

Posts array\_size standard-mode, non blocking send. Each post sends the n-th data of the array data\_handle to the n-th node of the array dest using the n-th message tag of the array mpi\_tag within the n-th communicator of the array comm. On completion of the all the requests, tag is unlocked.

27.28.3.22 int starpu\_mpi\_irecv\_array\_detached\_unlock\_tag ( unsigned array\_size, starpu\_data\_handle\_t \* data\_handle, int \* source, int \* mpi\_tag, MPI\_Comm \* comm, starpu tag t tag )

Posts array\_size nonblocking receive. Each post receives in the n-th data of the array data\_handle from the n-th node of the array source using the n-th message tag of the array mpi\_tag within the n-th communicator of the array comm. On completion of the all the requests, tag is unlocked.

27.28.3.23 int starpu\_mpi\_get\_communication\_tag ( void )

todo

27.28.3.24 void starpu\_mpi\_set\_communication\_tag ( int tag )

todo

27.28.3.25 int starpu\_mpi\_datatype\_register ( starpu\_data\_handle\_t handle, starpu\_mpi\_datatype\_allocate\_func\_t allocate\_datatype\_func, starpu\_mpi\_datatype\_free\_func\_t free\_datatype\_func )

Register functions to create and free a MPI datatype for the given handle. It is important that the function is called before any communication can take place for a data with the given handle. See Exchanging User Defined Data Interface for an example.

27.28.3.26 int starpu\_mpi\_datatype\_unregister ( starpu\_data\_handle\_t handle\_)

Unregister the MPI datatype functions stored for the interface of the given handle.

27.28.3.27 int starpu\_mpi\_cache\_is\_enabled ( )

Return 1 if the communication cache is enabled, 0 otherwise

27.28.3.28 int starpu\_mpi\_cache\_set ( int enabled )

If enabled is 1, enable the communication cache. Otherwise, clean the cache if it was enabled and disable it.

27.28.3.29 void starpu\_mpi\_cache\_flush ( MPI\_Comm comm, starpu\_data\_handle\_t data\_handle )

Clear the send and receive communication cache for the data <code>data\_handle</code> and invalidate the value. The function has to be called synchronously by all the MPI nodes. The function does nothing if the cache mechanism is disabled (see <code>STARPU\_MPI\_CACHE</code>).

27.28.3.30 void starpu\_mpi\_cache\_flush\_all\_data ( MPI\_Comm comm )

Clear the send and receive communication cache for all data and invalidate their values. The function has to be called synchronously by all the MPI nodes. The function does nothing if the cache mechanism is disabled (see STARPU\_MPI\_CACHE).

27.28 MPI Support 297

27.28.3.31 void starpu\_mpi\_data\_register\_comm ( starpu\_data\_handle\_t data\_handle, int tag, int rank, MPI\_Comm comm )

Register to MPI a StarPU data handle with the given tag, rank and MPI communicator. It also automatically clears the MPI communication cache when unregistering the data.

```
27.28.3.32 void starpu_mpi_data_set_tag ( starpu_data_handle_t handle, int tag )
```

Register to MPI a StarPU data handle with the given tag. No rank will be defined. It also automatically clears the MPI communication cache when unregistering the data.

```
27.28.3.33 void starpu_mpi_data_set_rank_comm ( starpu data handle t handle, int rank, MPI_Comm comm )
```

Register to MPI a StarPU data handle with the given rank and given communicator. No tag will be defined. It also automatically clears the MPI communication cache when unregistering the data.

```
27.28.3.34 int starpu_mpi_data_get_rank ( starpu_data_handle_t handle )
```

Return the rank of the given data.

```
27.28.3.35 int starpu_mpi_data_get_tag ( starpu_data_handle_t handle )
```

Return the tag of the given data.

```
27.28.3.36 int starpu_mpi_insert_task ( MPI_Comm comm, struct starpu_codelet * codelet, ... )
```

This function does the same as the function starpu\_mpi\_task\_insert(). It has been kept to avoid breaking old codes.

```
27.28.3.37 int starpu_mpi_task_insert ( MPI_Comm comm, struct starpu_codelet * codelet, ... )
```

Create and submit a task corresponding to codelet with the following arguments. The argument list must be zero-terminated.

The arguments following the codelet are the same types as for the function <a href="mailto:starpu\_task\_insert">starpu\_task\_insert</a>(). Access modes for data can also be set with <a href="mailto:STARPU\_SSEND">STARPU\_SSEND</a> to specify the data has to be sent using a synchronous and non-blocking mode (see <a href="mailto:starpu\_mpi\_issend">starpu\_mpi\_issend</a>()). The extra argument <a href="mailto:STARPU\_EXECUTE\_ON\_NODE">STARPU\_EXECUTE\_ON\_NODE</a> followed by an integer allows to specify the MPI node to execute the codelet. It is also possible to specify that the node owning a specific data will execute the codelet, by using <a href="mailto:STARPU\_EXECUTE\_ON\_DATA">STARPU\_EXECUTE\_ON\_DATA</a> followed by a data handle.

The internal algorithm is as follows:

- 1. Find out which MPI node is going to execute the codelet.
  - If there is only one node owning data in STARPU\_W mode, it will be selected;
  - If there is several nodes owning data in STARPU\_W node, a node will be selected according to a given node selection policy (see ::STARPU\_NODE\_SELECTION\_POLICY or starpu\_mpi\_node\_selection\_set current policy())
  - The argument STARPU EXECUTE ON NODE followed by an integer can be used to specify the node;
  - The argument STARPU\_EXECUTE\_ON\_DATA followed by a data handle can be used to specify that the node owing the given data will execute the codelet.
- 2. Send and receive data as requested. Nodes owning data which need to be read by the task are sending them to the MPI node which will execute it. The latter receives them.
- 3. Execute the codelet. This is done by the MPI node selected in the 1st step of the algorithm.

4. If several MPI nodes own data to be written to, send written data back to their owners.

The algorithm also includes a communication cache mechanism that allows not to send data twice to the same MPI node, unless the data has been modified. The cache can be disabled (see STARPU MPI CACHE).

```
27.28.3.38 struct starpu_task * starpu_mpi_task_build ( MPI_Comm comm, struct starpu_codelet * codelet, ... ) [read]
```

Create a task corresponding to codelet with the following arguments. The argument list must be zero-terminated. The function performs the first two steps of the function starpu\_mpi\_task\_insert(). Only the MPI node selected in the first step of the algorithm will return a valid task structure which can then be submitted, others will return NULL. The function starpu\_mpi\_task\_post\_build() MUST be called after that on all nodes, and after the submission of the task on the node which creates it, with the SAME list of arguments.

```
27.28.3.39 int starpu_mpi_task_post_build ( MPI_Comm comm, struct starpu_codelet * codelet, ... )
```

This function MUST be called after a call to <a href="mailto:starpu\_mpi\_task\_build">starpu\_mpi\_task\_build</a>(), with the SAME list of arguments. It performs the fourth – last – step of the algorithm described in <a href="mailto:starpu\_mpi\_task\_insert">starpu\_mpi\_task\_insert</a>().

```
27.28.3.40 void starpu_mpi_get_data_on_node ( MPI_Comm comm, starpu_data_handle_t data_handle, int node )
```

Transfer data data\_handle to MPI node node, sending it from its owner if needed. At least the target node and the owner have to call the function.

```
27.28.3.41 void starpu_mpi_get_data_on_node_detached ( MPI_Comm comm, starpu_data_handle_t data_handle, int node, void(*)(void *) callback, void * arg )
```

Transfer data data\_handle to MPI node node, sending it from its owner if needed. At least the target node and the owner have to call the function. On reception, the callback function is called with the argument arg.

```
27.28.3.42 int starpu_mpi_node_selection_get_current_policy ( )
```

Return the current policy used to select the node which will execute the codelet

```
27.28.3.43 int starpu_mpi_node_selection_set_current_policy ( int policy )
```

Set the current policy used to select the node which will execute the codelet. The policy STARPU\_MPI\_NODE\_SE-LECTION\_MOST\_R\_DATA selects the node having the most data in R mode so as to minimize the amount of data to be transfered.

```
27.28.3.44 int starpu_mpi_node_selection_register_policy ( starpu_mpi_select_node_policy_func_t policy_func )
```

Register a new policy which can then be used when there is several nodes owning data in W mode. Here an example of function defining a node selection policy. The codelet will be executed on the node owing the first data with a size bigger than 1M, or on the node 0 if no data fits the given size.

```
int my_node_selection_policy(int me, int nb_nodes, struct starpu_data_descr
    *descr, int nb_data)
{
    // me is the current MPI rank
    // nb_nodes is the number of MPI nodes
    // descr is the description of the data specified when calling
    starpu_mpi_task_insert
    // nb_data is the number of data in descr
    int i;
    for(i= 0 ; i<nb_data ; i++)</pre>
```

27.29 Task Bundles 299

```
{
    starpu_data_handle_t data = descr[i].handle
;
    enum starpu_data_access_mode mode =
descr[i].mode;
    if (mode & STARPU_R)
    {
        int rank = starpu_data_get_rank(
        data);
        size_t size = starpu_data_get_size(
        if (size > 1024*1024) return rank;
    }
}
return 0;
}
```

27.28.3.45 int starpu\_mpi\_node\_selection\_unregister\_policy (int policy)

Unregister a previously registered policy.

27.28.3.46 void starpu\_mpi\_redux\_data ( MPI\_Comm comm, starpu\_data\_handle\_t data\_handle\_)

Perform a reduction on the given data. All nodes send the data to its owner node which will perform a reduction.

```
27.28.3.47 int starpu_mpi_scatter_detached ( starpu_data_handle_t * data_handles, int count, int root, MPI_Comm comm, void(*)(void *) scallback, void * sarg, void(*)(void *) rcallback, void * rarg )
```

Scatter data among processes of the communicator based on the ownership of the data. For each data of the array  $data_handles$ , the process root sends the data to the process owning this data. Processes receiving data must have valid data handles to receive them. On completion of the collective communication, the scallback function is called with the argument sarg on the process root, the reallback function is called with the argument rarg on any other process.

```
27.28.3.48 int starpu_mpi_gather_detached ( starpu_data_handle_t * data_handles, int count, int root, MPI_Comm comm, void(*)(void *) scallback, void * sarg, void(*)(void *) rcallback, void * rarg )
```

Gather data from the different processes of the communicator onto the process root. Each process owning data handle in the array  $data\_handles$  will send them to the process root. The process root must have valid data handles to receive the data. On completion of the collective communication, the reallback function is called with the argument rarg on the process root, the scallback function is called with the argument sarg on any other process.

# 27.29 Task Bundles

# **Typedefs**

typedef struct \_starpu\_task\_bundle \* starpu\_task\_bundle\_t

#### **Functions**

- void starpu\_task\_bundle\_create (starpu\_task\_bundle\_t \*bundle)
- int starpu task bundle insert (starpu task bundle t bundle, struct starpu task \*task)
- int starpu task bundle remove (starpu task bundle t bundle, struct starpu task \*task)
- void starpu\_task\_bundle\_close (starpu\_task\_bundle\_t bundle)

- double starpu\_task\_bundle\_expected\_length (starpu\_task\_bundle\_t bundle, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_task\_bundle\_expected\_power (starpu\_task\_bundle\_t bundle, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_task\_bundle\_expected\_data\_transfer\_time (starpu\_task\_bundle\_t bundle, unsigned memory-node)

#### 27.29.1 Detailed Description

### 27.29.2 Typedef Documentation

#### 27.29.2.1 starpu task bundle t

Opaque structure describing a list of tasks that should be scheduled on the same worker whenever it's possible. It must be considered as a hint given to the scheduler as there is no guarantee that they will be executed on the same worker.

#### 27.29.3 Function Documentation

27.29.3.1 void starpu\_task\_bundle\_create ( starpu\_task\_bundle\_t \* bundle )

Factory function creating and initializing bundle, when the call returns, memory needed is allocated and bundle is ready to use.

27.29.3.2 int starpu\_task\_bundle\_insert ( starpu\_task\_bundle\_t bundle, struct starpu\_task \* task )

Insert task in bundle. Until task is removed from bundle its expected length and data transfer time will be considered along those of the other tasks of bundle. This function must not be called if bundle is already closed and/or task is already submitted. On success, it returns 0. There are two cases of error: if bundle is already closed it returns -EPERM, if task was already submitted it returns -EINVAL.

27.29.3.3 int starpu\_task\_bundle\_remove ( starpu\_task\_bundle\_t bundle, struct starpu\_task \* task )

Remove task from bundle. Of course task must have been previously inserted in bundle. This function must not be called if bundle is already closed and/or task is already submitted. Doing so would result in undefined behaviour. On success, it returns 0. If bundle is already closed it returns -ENOENT.

27.29.3.4 void starpu\_task\_bundle\_close ( starpu\_task\_bundle\_t bundle )

Inform the runtime that the user will not modify <code>bundle</code> anymore, it means no more inserting or removing task. Thus the runtime can destroy it when possible.

27.29.3.5 double starpu\_task\_bundle\_expected\_length ( starpu\_task\_bundle\_t bundle, struct starpu\_perfmodel\_arch \* arch, unsigned nimpl )

Return the expected duration of bundle in micro-seconds.

27.29.3.6 double starpu\_task\_bundle\_expected\_power ( starpu\_task\_bundle\_t bundle, struct starpu\_perfmodel\_arch \* arch, unsigned nimpl )

Return the expected power consumption of  $\verb"bundle"$  in J.

27.30 Task Lists 301

27.29.3.7 double starpu\_task\_bundle\_expected\_data\_transfer\_time ( starpu\_task\_bundle\_t bundle, unsigned memory\_node )

Return the time (in micro-seconds) expected to transfer all data used within bundle.

## 27.30 Task Lists

#### **Data Structures**

· struct starpu task list

#### **Functions**

- static STARPU\_INLINE void starpu\_task\_list\_init (struct starpu\_task\_list \*list)
- static STARPU\_INLINE void starpu\_task\_list\_push\_front (struct starpu\_task\_list \*list, struct starpu\_task \*task)
- static STARPU\_INLINE void starpu\_task\_list\_push\_back (struct starpu\_task\_list \*list, struct starpu\_task \*task)
- static STARPU\_INLINE struct

```
starpu_task * starpu_task_list_front (struct starpu_task_list *list)
```

• static STARPU INLINE struct

starpu\_task \* starpu\_task\_list\_back (struct starpu\_task\_list \*list)

- static STARPU\_INLINE int starpu\_task\_list\_empty (struct starpu\_task\_list \*list)
- static STARPU\_INLINE void starpu\_task\_list\_erase (struct starpu\_task\_list \*list, struct starpu\_task \*task)
- static STARPU INLINE struct

```
starpu_task * starpu_task_list_pop_front (struct starpu_task_list *list)
```

static STARPU\_INLINE struct

```
starpu_task * starpu_task_list_pop_back (struct starpu_task_list *list)
```

static STARPU\_INLINE struct

```
starpu_task * starpu_task_list_begin (struct starpu_task_list *list)
```

static STARPU\_INLINE struct
 starpu\_task \* starpu\_task\_list\_next (struct starpu\_task \*task)

# 27.30.1 Detailed Description

## 27.30.2 Data Structure Documentation

27.30.2.1 struct starpu\_task\_list

Stores a double-chained list of tasks

# Data Fields

struct	head	head of the list
starpu_task *		
struct	tail	tail of the list
starpu_task *		

## 27.30.3 Function Documentation

**27.30.3.1 void starpu\_task\_list\_init ( struct starpu\_task\_list \* list )** [static]

Initialize a list structure

```
27.30.3.2 void starpu_task_list_push_front ( struct starpu_task_list * list, struct starpu_task * task ) [static]
Push task at the front of list
27.30.3.3 void starpu_task_list_push_back ( struct starpu_task_list, struct starpu_task * task ) [static]
Push task at the back of list
27.30.3.4 struct starpu task * starpu_task_list_front( struct starpu task list * list ) [static], [read]
Get the front of list (without removing it)
27.30.3.5 struct starpu_task * starpu_task_list_back( struct starpu_task_list * list ) [static], [read]
Get the back of list (without removing it)
27.30.3.6 int starpu_task_list_empty ( struct starpu_task_list * list ) [static]
Test if list is empty
27.30.3.7 void starpu_task_list_erase ( struct starpu_task_list, struct starpu_task * task ) [static]
Remove task from list
27.30.3.8 struct starpu task * starpu_task_list_pop_front( struct starpu task list * list ) [static], [read]
Remove the element at the front of list
27.30.3.9 struct starpu_task * starpu_task_list_pop_back( struct starpu_task_list * list ) [static], [read]
Remove the element at the back of list
27.30.3.10 struct starpu_task * starpu_task_list_begin ( struct starpu_task_list * list ) [static], [read]
Get the first task of list.
27.30.3.11 struct starpu task * starpu_task_list_next( struct starpu task * task) [static], [read]
Get the next task of list. This is not erase-safe.
```

# 27.31 Parallel Tasks

#### **Functions**

- int starpu\_combined\_worker\_get\_size (void)
- · int starpu combined worker get rank (void)
- unsigned starpu\_combined\_worker\_get\_count (void)
- int starpu combined worker get id (void)
- int starpu\_combined\_worker\_assign\_workerid (int nworkers, int workerid\_array[])

27.31 Parallel Tasks 303

- int starpu\_combined\_worker\_get\_description (int workerid, int \*worker\_size, int \*\*combined\_workerid)
- int starpu\_combined\_worker\_can\_execute\_task (unsigned workerid, struct starpu\_task \*task, unsigned nimpl)
- void starpu\_parallel\_task\_barrier\_init (struct starpu\_task \*task, int workerid)
- void starpu\_parallel\_task\_barrier\_init\_n (struct starpu\_task \*task, int worker\_size)

## 27.31.1 Detailed Description

#### 27.31.2 Function Documentation

27.31.2.1 int starpu\_combined\_worker\_get\_size ( void )

Return the size of the current combined worker, i.e. the total number of cpus running the same task in the case of STARPU\_SPMD parallel tasks, or the total number of threads that the task is allowed to start in the case of STARPU\_FORKJOIN parallel tasks.

27.31.2.2 int starpu\_combined\_worker\_get\_rank ( void )

Return the rank of the current thread within the combined worker. Can only be used in STARPU\_FORKJOIN parallel tasks, to know which part of the task to work on.

27.31.2.3 unsigned starpu\_combined\_worker\_get\_count ( void )

Return the number of different combined workers.

27.31.2.4 int starpu\_combined\_worker\_get\_id ( void )

Return the identifier of the current combined worker.

27.31.2.5 int starpu\_combined\_worker\_assign\_workerid ( int nworkers, int workerid\_array[] )

Register a new combined worker and get its identifier

27.31.2.6 int starpu\_combined\_worker\_qet\_description ( int workerid, int \* worker\_size, int \*\* combined\_workerid )

Get the description of a combined worker

27.31.2.7 int starpu\_combined\_worker\_can\_execute\_task ( unsigned workerid, struct starpu\_task \* task, unsigned nimpl )

Variant of starpu\_worker\_can\_execute\_task() compatible with combined workers

27.31.2.8 void starpu\_parallel\_task\_barrier\_init ( struct starpu\_task \* task, int workerid )

Initialise the barrier for the parallel task, and dispatch the task between the different workers of the given combined worker.

27.31.2.9 void starpu\_parallel\_task\_barrier\_init\_n ( struct starpu\_task \* task, int worker\_size )

Initialise the barrier for the parallel task, to be pushed to *worker\_size* workers (without having to explicit a given combined worker).

# 27.32 Running Drivers

#### **Functions**

- int starpu\_driver\_run (struct starpu\_driver \*d)
- int starpu\_driver\_init (struct starpu\_driver \*d)
- int starpu driver run once (struct starpu driver \*d)
- int starpu\_driver\_deinit (struct starpu\_driver \*d)
- void starpu\_drivers\_request\_termination (void)

## 27.32.1 Detailed Description

#### 27.32.2 Function Documentation

27.32.2.1 int starpu\_driver\_run ( struct starpu\_driver \* d )

Initialize the given driver, run it until it receives a request to terminate, deinitialize it and return 0 on success. It returns <code>-EINVAL</code> if <code>d->type</code> is not a valid StarPU device type (STARPU\_CPU\_WORKER, STARPU\_CUDA\_WORKER or STARPU\_OPENCL\_WORKER). This is the same as using the following functions: calling starpu\_driver\_init(), then calling starpu driver run once() in a loop, and eventually starpu driver deinit().

27.32.2.2 int starpu\_driver\_init ( struct starpu\_driver \* d )

Initialize the given driver. Returns 0 on success, -EINVAL if d->type is not a valid starpu worker archtype.

27.32.2.3 int starpu\_driver\_run\_once ( struct starpu\_driver \* d )

Run the driver once, then returns 0 on success, -EINVAL if d->type is not a valid starpu worker archtype.

27.32.2.4 int starpu\_driver\_deinit ( struct starpu\_driver \* d )

Deinitialize the given driver. Returns 0 on success, -EINVAL if d->type is not a valid starpu\_worker\_archtype.

27.32.2.5 void starpu\_drivers\_request\_termination ( void )

Notify all running drivers they should terminate.

# 27.33 Expert Mode

#### **Functions**

- void starpu\_wake\_all\_blocked\_workers (void)
- int starpu\_progression\_hook\_register (unsigned(\*func)(void \*arg), void \*arg)
- void starpu\_progression\_hook\_deregister (int hook\_id)

## 27.33.1 Detailed Description

### 27.33.2 Function Documentation

```
27.33.2.1 void starpu_wake_all_blocked_workers ( void )
```

Wake all the workers, so they can inspect data requests and task submissions again.

```
27.33.2.2 int starpu_progression_hook_register ( unsigned(*)(void *arg) func, void * arg )
```

Register a progression hook, to be called when workers are idle.

```
27.33.2.3 void starpu_progression_hook_deregister ( int hook_id )
```

Unregister a given progression hook.

# 27.34 StarPU-Top Interface

## **Data Structures**

- · struct starpu\_top\_data
- · struct starpu top param

#### **Enumerations**

- enum starpu\_top\_data\_type { STARPU\_TOP\_DATA\_BOOLEAN, STARPU\_TOP\_DATA\_INTEGER, STAR-PU\_TOP\_DATA\_FLOAT }
- enum starpu\_top\_param\_type { STARPU\_TOP\_PARAM\_BOOLEAN, STARPU\_TOP\_PARAM\_INTEGER, STARPU\_TOP\_PARAM\_FLOAT, STARPU\_TOP\_PARAM\_ENUM }
- enum starpu\_top\_message\_type {
   TOP\_TYPE\_GO, TOP\_TYPE\_SET, TOP\_TYPE\_CONTINUE, TOP\_TYPE\_ENABLE,
   TOP\_TYPE\_DISABLE, TOP\_TYPE\_DEBUG, TOP\_TYPE\_UNKNOW }

#### Functions to call before the initialisation

- struct starpu\_top\_data \* starpu\_top\_add\_data\_boolean (const char \*data\_name, int active)
- struct starpu\_top\_data \* starpu\_top\_add\_data\_integer (const char \*data\_name, int minimum\_value, int maximum\_value, int active)
- struct starpu\_top\_data \* starpu\_top\_add\_data\_float (const char \*data\_name, double minimum\_value, double maximum\_value, int active)
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_boolean (const char \*param\_name, int \*parameter\_field, void(\*callback)(struct starpu\_top\_param \*))
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_float (const char \*param\_name, double \*parameter\_field, double minimum\_value, double maximum\_value, void(\*callback)(struct starpu\_top\_param \*))
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_integer (const char \*param\_name, int \*parameter\_field, int minimum\_value, int maximum\_value, void(\*callback)(struct starpu\_top\_param \*))
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_enum (const char \*param\_name, int \*parameter\_field, char \*\*values, int nb\_values, void(\*callback)(struct starpu\_top\_param \*))

#### Initialisation

void starpu\_top\_init\_and\_wait (const char \*server\_name)

## To call after initialisation

- void starpu\_top\_update\_parameter (const struct starpu\_top\_param \*param)
- void starpu\_top\_update\_data\_boolean (const struct starpu\_top\_data \*data, int value)
- void starpu\_top\_update\_data\_integer (const struct starpu\_top\_data \*data, int value)
- void starpu top update data float (const struct starpu top data \*data, double value)
- void starpu\_top\_task\_prevision (struct starpu\_task \*task, int devid, unsigned long long start, unsigned long long end)
- void starpu\_top\_debug\_log (const char \*message)
- void starpu\_top\_debug\_lock (const char \*message)

# 27.34.1 Detailed Description

#### 27.34.2 Data Structure Documentation

#### 27.34.2.1 struct starpu\_top\_data

todo

#### **Data Fields**

unsigned int	id	todo
const char *	name	todo
int	int_min_value	todo
int	int_max_value	todo
double	double_min	todo
	value	
double	double_max	todo
	value	
int	active	todo
enum starpu	type	todo
top_data_type		
struct	next	todo
starpu_top_data		
*		

# 27.34.2.2 struct starpu\_top\_param

todo

# **Data Fields**

- · unsigned int id
- const char \* name
- enum starpu\_top\_param\_type type
- void \* value
- char \*\* enum\_values
- int nb\_values
- void(\* callback )(struct starpu\_top\_param \*)
- int int\_min\_value
- int int\_max\_value
- double double\_min\_value
- double double\_max\_value
- struct starpu\_top\_param \* next

```
27.34.2.2.1 Field Documentation
27.34.2.2.1.1 unsigned int starpu_top_param::id
todo
\textbf{27.34.2.2.1.2} \quad \textbf{const char} * \textbf{starpu\_top\_param::name}
todo
27.34.2.2.1.3 enum starpu_top_param_type starpu_top_param::type
todo
27.34.2.2.1.4 void * starpu_top_param::value
todo
27.34.2.2.1.5 char ** starpu_top_param::enum_values
only for enum type can be NULL
27.34.2.2.1.6 int starpu_top_param::nb_values
todo
27.34.2.2.1.7 void(* starpu_top_param::callback)(struct starpu_top_param *)
todo
27.34.2.2.1.8 int starpu_top_param::int_min_value
only for integer type
27.34.2.2.1.9 int starpu_top_param::int_max_value
todo
27.34.2.2.1.10 double starpu_top_param::double_min_value
only for double type
27.34.2.2.1.11 double starpu_top_param::double_max_value
todo
27.34.2.2.1.12 struct starpu_top_param * starpu_top_param::next
todo
27.34.3 Enumeration Type Documentation
27.34.3.1 enum starpu_top_data_type
StarPU-Top Data type
Enumerator:
    STARPU_TOP_DATA_BOOLEAN todo
    STARPU_TOP_DATA_INTEGER todo
```

STARPU\_TOP\_DATA\_FLOAT todo

```
27.34.3.2 enum starpu_top_param_type
```

StarPU-Top Parameter type

#### **Enumerator:**

STARPU\_TOP\_PARAM\_BOOLEAN todo STARPU\_TOP\_PARAM\_INTEGER todo STARPU\_TOP\_PARAM\_FLOAT todo STARPU\_TOP\_PARAM\_ENUM todo

27.34.3.3 enum starpu\_top\_message\_type

StarPU-Top Message type

#### **Enumerator:**

TOP\_TYPE\_GO todo

TOP\_TYPE\_SET todo

TOP\_TYPE\_CONTINUE todo

TOP\_TYPE\_ENABLE todo

TOP\_TYPE\_DISABLE todo

TOP\_TYPE\_DEBUG todo

TOP\_TYPE\_UNKNOW todo

## 27.34.4 Function Documentation

27.34.4.1 struct starpu\_top\_data \* starpu\_top\_add\_data\_boolean ( const char \* data\_name, int active ) [read]

This fonction register a data named data\_name of type boolean. If active=0, the value will NOT be displayed to user by default. Any other value will make the value displayed by default.

27.34.4.2 struct starpu\_top\_data \* starpu\_top\_add\_data\_integer ( const char \* data\_name, int minimum\_value, int maximum\_value, int active ) [read]

This fonction register a data named data\_name of type integer. The minimum and maximum value will be usefull to define the scale in UI. If active=0, the value will NOT be displayed to user by default. Any other value will make the value displayed by default.

27.34.4.3 struct starpu\_top\_data \* starpu\_top\_add\_data\_float ( const char \* data\_name, double minimum\_value, double maximum\_value, int active ) [read]

This fonction register a data named data\_name of type float. The minimum and maximum value will be usefull to define the scale in UI. If active=0, the value will NOT be displayed to user by default. Any other value will make the value displayed by default.

27.34.4.4 struct starpu\_top\_param \* starpu\_top\_register\_parameter\_boolean ( const char \* param\_name, int \* parameter\_field, void(\*)(struct starpu\_top\_param \*) callback ) [read]

This fonction register a parameter named parameter\_name, of type boolean. The callback fonction will be called when the parameter is modified by UI, and can be null.

27.34.4.5 struct starpu\_top\_param \* starpu\_top\_register\_parameter\_float ( const char \* param\_name, double \* parameter\_field, double minimum\_value, double maximum\_value, void(\*)(struct starpu\_top\_param \*) callback )

[read]

his fonction register a parameter named param\_name, of type integer. Minimum and maximum value will be used to prevent user seting incorrect value. The callback fonction will be called when the parameter is modified by UI, and can be null.

27.34.4.6 struct starpu\_top\_param \* starpu\_top\_register\_parameter\_integer ( const char \* param\_name, int \* parameter\_field, int minimum\_value, int maximum\_value, void(\*)(struct starpu\_top\_param \*) callback ) [read]

This fonction register a parameter named param\_name, of type float. Minimum and maximum value will be used to prevent user seting incorrect value. The callback fonction will be called when the parameter is modified by UI, and can be null.

27.34.4.7 struct starpu\_top\_param \* starpu\_top\_register\_parameter\_enum ( const char \* param\_name, int \* parameter\_field, char \*\* values, int nb\_values, void(\*)(struct starpu\_top\_param \*) callback ) [read]

This fonction register a parameter named param\_name, of type enum. Minimum and maximum value will be used to prevent user seting incorrect value. The callback fonction will be called when the parameter is modified by UI, and can be null.

27.34.4.8 void starpu\_top\_init\_and\_wait ( const char \* server\_name )

This function must be called when all parameters and data have been registered AND initialised (for parameters). This function will wait for a TOP to connect, send initialisation sentences, and wait for the GO message.

27.34.4.9 void starpu\_top\_update\_parameter ( const struct starpu\_top\_param \* param )

This function should be called after every modification of a parameter from something other than starpu\_top. This fonction notice UI that the configuration changed.

27.34.4.10 void starpu\_top\_update\_data\_boolean ( const struct starpu top data \* data, int value )

This function updates the value of the starpu top data on UI.

27.34.4.11 void starpu\_top\_update\_data\_integer ( const struct starpu\_top\_data \* data, int value )

This function updates the value of the starpu top data on UI.

27.34.4.12 void starpu\_top\_update\_data\_float ( const struct starpu\_top\_data \* data, double value )

This function updates the value of the starpu\_top\_data on UI.

27.34.4.13 void starpu\_task\_prevision ( struct starpu\_task \* task, int devid, unsigned long long start, unsigned long long end )

This function notifies UI than the task have been planed to run from start to end, on computation-core.

27.34.4.14 void starpu\_top\_debug\_log ( const char \* message )

This function is useful in debug mode. The starpu developper doesn't need to check if the debug mode is active. This is checked by starpu top itsefl. It just send a message to display by UI.

27.34.4.15 void starpu\_top\_debug\_lock ( const char \* message )

This function is useful in debug mode. The starpu developper doesn't need to check if the debug mode is active. This is checked by starpu\_top itsefl. It send a message and wait for a continue message from UI to return. The lock (wich create a stop-point) should be called only by the main thread. Calling it from more than one thread is not supported.

# 27.35 Scheduling Contexts

StarPU permits on one hand grouping workers in combined workers in order to execute a parallel task and on the other hand grouping tasks in bundles that will be executed by a single specified worker. In contrast when we group workers in scheduling contexts we submit starpu tasks to them and we schedule them with the policy assigned to the context. Scheduling contexts can be created, deleted and modified dynamically.

#### **Data Structures**

· struct starpu sched ctx performance counters

# **Scheduling Contexts Basic API**

- #define STARPU SCHED CTX POLICY NAME
- #define STARPU\_SCHED\_CTX\_POLICY\_STRUCT
- #define STARPU\_SCHED\_CTX\_POLICY\_MIN\_PRIO
- #define STARPU\_SCHED\_CTX\_POLICY\_MAX\_PRIO
- unsigned starpu sched ctx create (int \*workerids ctx, int nworkers ctx, const char \*sched ctx name,...)
- unsigned starpu\_sched\_ctx\_create\_inside\_interval (const char \*policy\_name, const char \*sched\_ctx\_name, int min\_ncpus, int max\_ncpus, int max\_ncpus, unsigned allow\_overlap)
- void starpu\_sched\_ctx\_register\_close\_callback (unsigned sched\_ctx\_id, void(\*close\_callback)(unsigned sched\_ctx\_id, void \*args), void \*args)
- void starpu\_sched\_ctx\_add\_workers (int \*workerids\_ctx, int nworkers\_ctx, unsigned sched\_ctx\_id)
- void starpu\_sched\_ctx\_remove\_workers (int \*workerids\_ctx, int nworkers\_ctx, unsigned sched\_ctx\_id)
- void starpu\_sched\_ctx\_display\_workers (unsigned sched\_ctx\_id, FILE \*f)
- void starpu\_sched\_ctx\_delete (unsigned sched\_ctx\_id)
- void starpu\_sched\_ctx\_set\_inheritor (unsigned sched\_ctx\_id, unsigned inheritor)
- void starpu\_sched\_ctx\_set\_context (unsigned \*sched\_ctx\_id)
- unsigned starpu sched ctx get context (void)
- void starpu\_sched\_ctx\_stop\_task\_submission (void)
- void starpu\_sched\_ctx\_finished\_submit (unsigned sched\_ctx\_id)
- unsigned starpu sched ctx get workers list (unsigned sched ctx id, int \*\*workerids)
- unsigned starpu\_sched\_ctx\_get\_nworkers (unsigned sched\_ctx\_id)
- unsigned starpu\_sched\_ctx\_get\_nshared\_workers (unsigned sched\_ctx\_id, unsigned sched\_ctx\_id2)
- unsigned starpu\_sched\_ctx\_contains\_worker (int workerid, unsigned sched\_ctx\_id)
- unsigned starpu sched ctx worker get id (unsigned sched ctx id)
- unsigned starpu\_sched\_ctx\_overlapping\_ctxs\_on\_worker (int workerid)

# **Scheduling Context Priorities**

- #define STARPU\_MIN\_PRIO
- #define STARPU MAX PRIO
- #define STARPU DEFAULT PRIO
- int starpu\_sched\_ctx\_set\_min\_priority (unsigned sched\_ctx\_id, int min\_prio)
- int starpu\_sched\_ctx\_set\_max\_priority (unsigned sched\_ctx\_id, int max\_prio)
- int starpu sched ctx get min priority (unsigned sched ctx id)
- int starpu\_sched\_ctx\_get\_max\_priority (unsigned sched\_ctx\_id)
- int starpu\_sched\_ctx\_min\_priority\_is\_set (unsigned sched\_ctx\_id)
- int starpu\_sched\_ctx\_max\_priority\_is\_set (unsigned sched\_ctx\_id)

# **Scheduling Context Worker Collection**

- struct starpu\_worker\_collection \* starpu\_sched\_ctx\_create\_worker\_collection (unsigned sched\_ctx\_id, enum starpu\_worker\_collection\_type type)
- void starpu\_sched\_ctx\_delete\_worker\_collection (unsigned sched ctx id)
- struct starpu\_worker\_collection \* starpu\_sched\_ctx\_get\_worker\_collection (unsigned sched\_ctx\_id)

## Scheduling Context Link with Hypervisor

- void starpu\_sched\_ctx\_set\_perf\_counters (unsigned sched\_ctx\_id, void \*perf\_counters)
- void starpu\_sched\_ctx\_call\_pushed\_task\_cb (int workerid, unsigned sched\_ctx\_id)
- void starpu sched ctx notify hypervisor exists (void)
- unsigned starpu sched ctx check if hypervisor exists (void)
- void starpu\_sched\_ctx\_set\_policy\_data (unsigned sched\_ctx\_id, void \*policy\_data)
- void \* starpu sched ctx get policy data (unsigned sched ctx id)
- void \* starpu sched ctx exec parallel code (void \*(\*func)(void \*), void \*param, unsigned sched ctx id)
- int starpu\_sched\_ctx\_get\_nready\_tasks (unsigned sched\_ctx\_id)
- double starpu\_sched\_ctx\_get\_nready\_flops (unsigned sched\_ctx\_id)

# 27.35.1 Detailed Description

StarPU permits on one hand grouping workers in combined workers in order to execute a parallel task and on the other hand grouping tasks in bundles that will be executed by a single specified worker. In contrast when we group workers in scheduling contexts we submit starpu tasks to them and we schedule them with the policy assigned to the context. Scheduling contexts can be created, deleted and modified dynamically.

#### 27.35.2 Data Structure Documentation

#### 27.35.2.1 struct starpu\_sched\_ctx\_performance\_counters

Performance counters used by the starpu to indicate the hypervisor how the application and the resources are executing.

### **Data Fields**

- void(\* notify\_idle\_cycle )(unsigned sched\_ctx\_id, int worker, double idle\_time)
- void(\* notify\_poped\_task )(unsigned sched\_ctx\_id, int worker)
- void(\* notify pushed task)(unsigned sched ctx id, int worker)
- void(\* notify\_post\_exec\_task )(struct starpu\_task \*task, size\_t data\_size, uint32\_t footprint, int hypervisor\_tag, double flops)
- void(\* notify\_submitted\_job )(struct starpu\_task \*task, uint32\_t footprint, size\_t data\_size)
- void(\* notify\_empty\_ctx )(unsigned sched\_ctx\_id, struct starpu\_task \*task)
- void(\* notify\_delete\_context )(unsigned sched\_ctx)

27.35.2.1.1 Field Documentation

27.35.2.1.1.1 void(\* starpu\_sched\_ctx\_performance\_counters::notify\_idle\_cycle)(unsigned sched\_ctx\_id, int worker, double idle\_time)

Informs the hypervisor for how long a worker has been idle in the specified context

27.35.2.1.1.2 void(\* starpu\_sched\_ctx\_performance\_counters::notify\_poped\_task)(unsigned sched\_ctx\_id, int worker)

Informs the hypervisor that a task executing a specified number of instructions has been poped from the worker

27.35.2.1.1.3 void(\* starpu\_sched\_ctx\_performance\_counters::notify\_pushed\_task)(unsigned sched\_ctx\_id, int worker)

Notifies the hypervisor that a task has been scheduled on the queue of the worker corresponding to the specified context

27.35.2.1.1.4 void(\* starpu\_sched\_ctx\_performance\_counters::notify\_post\_exec\_task)(struct starpu\_task \*task, size\_t data\_size, uint32\_t footprint, int hypervisor\_tag, double flops)

Notifies the hypervisor that a task has just been executed

27.35.2.1.1.5 void(\* starpu\_sched\_ctx\_performance\_counters::notify\_submitted\_job)(struct starpu\_task \*task, uint32\_t footprint, size\_t data\_size)

Notifies the hypervisor that a task has just been submitted

27.35.2.1.1.6 void(\* starpu\_sched\_ctx\_performance\_counters::notify\_delete\_context)(unsigned sched\_ctx)

Notifies the hypervisor that the context was deleted

27.35.3 Macro Definition Documentation

27.35.3.1 #define STARPU\_SCHED\_CTX\_POLICY\_NAME

This macro is used when calling starpu\_sched\_ctx\_create() to specify a name for a scheduling policy

27.35.3.2 #define STARPU\_SCHED\_CTX\_POLICY\_STRUCT

This macro is used when calling starpu\_sched\_ctx\_create() to specify a pointer to a scheduling policy

27.35.3.3 #define STARPU\_SCHED\_CTX\_POLICY\_MIN\_PRIO

This macro is used when calling starpu\_sched\_ctx\_create() to specify a minimum scheduler priority value.

27.35.3.4 #define STARPU\_SCHED\_CTX\_POLICY\_MAX\_PRIO

This macro is used when calling starpu\_sched\_ctx\_create() to specify a maximum scheduler priority value.

27.35.3.5 #define STARPU\_MIN\_PRIO

Provided for legacy reasons.

27.35.3.6 #define STARPU\_MAX\_PRIO

Provided for legacy reasons.

#### 27.35.3.7 #define STARPU\_DEFAULT\_PRIO

By convention, the default priority level should be 0 so that we can statically allocate tasks with a default priority.

## 27.35.4 Function Documentation

27.35.4.1 unsigned starpu\_sched\_ctx\_create ( int \* workerids\_ctx, int nworkers\_ctx, const char \* sched\_ctx\_name, ... )

This function creates a scheduling context with the given parameters (see below) and assigns the workers in workerids\_ctx to execute the tasks submitted to it. The return value represents the identifier of the context that has just been created. It will be further used to indicate the context the tasks will be submitted to. The return value should be at most STARPU\_NMAX\_SCHED\_CTXS.

The arguments following the name of the scheduling context can be of the following types:

- · STARPU SCHED CTX POLICY NAME, followed by the name of a predefined scheduling policy
- STARPU\_SCHED\_CTX\_POLICY\_STRUCT, followed by a pointer to a custom scheduling policy (struct starpu\_sched\_policy \*)
- STARPU\_SCHED\_CTX\_POLICY\_MIN\_PRIO, followed by a integer representing the minimum priority value to be defined for the scheduling policy.
- STARPU\_SCHED\_CTX\_POLICY\_MAX\_PRIO, followed by a integer representing the maximum priority value to be defined for the scheduling policy.

27.35.4.2 unsigned starpu\_sched\_ctx\_create\_inside\_interval ( const char \* policy\_name, const char \* sched\_ctx\_name, int min\_ncpus, int max\_ncpus, int max\_ncpus, int max\_ncpus, unsigned allow\_overlap )

Create a context indicating an approximate interval of resources

27.35.4.3 void starpu\_sched\_ctx\_register\_close\_callback ( unsigned sched\_ctx\_id, void(\*)(unsigned sched\_ctx\_id, void \*args) close\_callback, void \* args )

Execute the callback whenever the last task of the context finished executing, it is called with the pramaters: sched\_ctx and any other paramter needed by the application (packed in a void\*)

27.35.4.4 void starpu\_sched\_ctx\_add\_workers ( int \* workerids\_ctx, int nworkers\_ctx, unsigned sched\_ctx\_id )

This function adds dynamically the workers in  $workerids\_ctx$  to the context  $sched\_ctx\_id$ . The last argument cannot be greater than STARPU\_NMAX\_SCHED\_CTXS.

27.35.4.5 void starpu\_sched\_ctx\_remove\_workers ( int \* workerids\_ctx, int nworkers\_ctx, unsigned sched\_ctx\_id )

This function removes the workers in workerids\_ctx from the context sched\_ctx\_id. The last argument cannot be greater than STARPU NMAX SCHED CTXS.

27.35.4.6 void starpu\_sched\_ctx\_display\_workers ( unsigned  $sched_ctx\_id$ , FILE \*f )

This function prints on the file f the worker names belonging to the context sched\_ctx\_id

27.35.4.7 void starpu\_sched\_ctx\_delete ( unsigned sched\_ctx\_id )

Delete scheduling context sched\_ctx\_id and transfer remaining workers to the inheritor scheduling context.

27.35.4.8 void starpu\_sched\_ctx\_set\_inheritor ( unsigned sched\_ctx\_id, unsigned inheritor )

Indicate which context whill inherit the resources of this context when he will be deleted.

27.35.4.9 void starpu\_sched\_ctx\_set\_context ( unsigned \* sched\_ctx\_id )

Set the scheduling context the subsequent tasks will be submitted to

27.35.4.10 unsigned starpu\_sched\_ctx\_get\_context ( void )

Return the scheduling context the tasks are currently submitted to, or ::STARPU\_NMAX\_SCHED\_CTXS if no default context has been defined by calling the function starpu\_sched\_ctx\_set\_context().

27.35.4.11 void starpu\_sched\_ctx\_stop\_task\_submission ( void )

Stop submitting tasks from the empty context list until the next time the context has time to check the empty context list

27.35.4.12 void starpu\_sched\_ctx\_finished\_submit ( unsigned sched\_ctx\_id )

Indicate starpu that the application finished submitting to this context in order to move the workers to the inheritor as soon as possible.

27.35.4.13 unsigned starpu\_sched\_ctx\_get\_workers\_list ( unsigned sched\_ctx\_id, int \*\* workerids )

Returns the list of workers in the array workerids, the returned value is the number of workers. The user should free the workerids table after finishing using it (it is allocated inside the function with the proper size)

27.35.4.14 unsigned starpu\_sched\_ctx\_get\_nworkers ( unsigned sched\_ctx\_id )

Return the number of workers managed by the specified contexts (Usually needed to verify if it manages any workers or if it should be blocked)

27.35.4.15 unsigned starpu\_sched\_ctx\_get\_nshared\_workers ( unsigned sched\_ctx\_id, unsigned sched\_ctx\_id2 )

Return the number of workers shared by two contexts.

27.35.4.16 unsigned starpu\_sched\_ctx\_contains\_worker ( int workerid, unsigned sched\_ctx\_id )

Return 1 if the worker belongs to the context and 0 otherwise

27.35.4.17 unsigned starpu\_sched\_ctx\_worker\_get\_id ( unsigned sched\_ctx\_id )

Return the workerid if the worker belongs to the context and -1 otherwise. If the thread calling this function is not a worker the function returns -1 as it calls the function starpu\_worker\_get\_id()

27.35.4.18 unsigned starpu\_sched\_ctx\_overlapping\_ctxs\_on\_worker ( int workerid )

Check if a worker is shared between several contexts

27.35.4.19 int starpu\_sched\_ctx\_set\_min\_priority ( unsigned sched\_ctx\_id, int min\_prio )

Defines the minimum task priority level supported by the scheduling policy of the given scheduler context. The default minimum priority level is the same as the default priority level which is 0 by convention. The application may access that value by calling the function <a href="mailto:starpu\_sched\_ctx\_get\_min\_priority">starpu\_sched\_ctx\_get\_min\_priority</a>(). This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

27.35.4.20 int starpu\_sched\_ctx\_set\_max\_priority ( unsigned sched\_ctx\_id, int max\_prio )

Defines the maximum priority level supported by the scheduling policy of the given scheduler context. The default maximum priority level is 1. The application may access that value by calling the starpu\_sched\_ctx\_get\_max\_priority function. This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

27.35.4.21 int starpu\_sched\_ctx\_get\_min\_priority ( unsigned sched\_ctx\_id )

Returns the current minimum priority level supported by the scheduling policy of the given scheduler context.

27.35.4.22 int starpu\_sched\_ctx\_get\_max\_priority ( unsigned sched\_ctx\_id )

Returns the current maximum priority level supported by the scheduling policy of the given scheduler context.

27.35.4.23 int starpu\_sched\_ctx\_min\_priority\_is\_set ( unsigned sched\_ctx\_id )

todo

27.35.4.24 int starpu\_sched\_ctx\_max\_priority\_is\_set ( unsigned sched\_ctx\_id )

todo

27.35.4.25 struct starpu\_worker\_collection \* starpu\_sched\_ctx\_create\_worker\_collection ( unsigned sched\_ctx\_id, enum starpu\_worker\_collection type type ) [read]

Create a worker collection of the type indicated by the last parameter for the context specified through the first parameter.

27.35.4.26 void starpu\_sched\_ctx\_delete\_worker\_collection ( unsigned sched\_ctx\_id )

Delete the worker collection of the specified scheduling context

27.35.4.27 struct starpu\_worker\_collection \* starpu\_sched\_ctx\_get\_worker\_collection ( unsigned sched\_ctx\_id ) [read]

Return the worker collection managed by the indicated context

27.35.4.28 void starpu\_sched\_ctx\_set\_perf\_counters ( unsigned sched\_ctx\_id, void \* perf\_counters )

Indicates to starpu the pointer to the performance counter

```
27.35.4.29 void starpu_sched_ctx_call_pushed_task_cb ( int workerid, unsigned sched_ctx_id )
```

Callback that lets the scheduling policy tell the hypervisor that a task was pushed on a worker

```
27.35.4.30 void starpu_sched_ctx_notify_hypervisor_exists ( void )
```

Allow the hypervisor to let starpu know he's initialised

```
27.35.4.31 unsigned starpu_sched_ctx_check_if_hypervisor_exists ( void )
```

Ask starpu if he is informed if the hypervisor is initialised

```
27.35.4.32 void starpu_sched_ctx_set_policy_data ( unsigned sched_ctx_id, void * policy_data )
```

Allocate the scheduling policy data (private information of the scheduler like queues, variables, additional condition variables) the context

```
27.35.4.33 void * starpu_sched_ctx_get_policy_data ( unsigned sched_ctx_id )
```

Return the scheduling policy data (private information of the scheduler) of the contexts previously assigned to.

```
27.35.4.34 void * starpu_sched_ctx_exec_parallel_code ( void *(*)(void *) func, void * param, unsigned sched_ctx_id )
```

execute any parallel code on the workers of the sched ctx (workers are blocked)

```
27.35.4.35 int starpu_sched_ctx_get_nready_tasks ( unsigned sched_ctx_id )
```

todo

27.35.4.36 double starpu\_sched\_ctx\_get\_nready\_flops ( unsigned sched\_ctx\_id )

todo

# 27.36 Scheduling Policy

TODO. While StarPU comes with a variety of scheduling policies (see Task Scheduling Policy), it may sometimes be desirable to implement custom policies to address specific problems. The API described below allows users to write their own scheduling policy.

#### **Data Structures**

· struct starpu\_sched\_policy

## **Functions**

- struct starpu\_sched\_policy \*\* starpu\_sched\_get\_predefined\_policies ()
- void starpu\_worker\_get\_sched\_condition (int workerid, starpu\_pthread\_mutex\_t \*\*sched\_mutex, starpu\_pthread\_cond\_t \*\*sched\_cond)
- int starpu\_sched\_set\_min\_priority (int min\_prio)

- int starpu\_sched\_set\_max\_priority (int max\_prio)
- int starpu sched get min priority (void)
- int starpu\_sched\_get\_max\_priority (void)
- int starpu\_push\_local\_task (int workerid, struct starpu\_task \*task, int back)
- int starpu\_push\_task\_end (struct starpu\_task \*task)
- int starpu worker can execute task (unsigned workerid, struct starpu task \*task, unsigned nimpl)
- int starpu\_worker\_can\_execute\_task\_impl (unsigned workerid, struct starpu\_task \*task, unsigned \*impl\_mask)
- int starpu\_worker\_can\_execute\_task\_first\_impl (unsigned workerid, struct starpu\_task \*task, unsigned \*nimpl)
- uint32\_t starpu\_task\_footprint (struct starpu\_perfmodel \*model, struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- uint32\_t starpu\_task\_data\_footprint (struct starpu\_task \*task)
- double starpu\_task\_expected\_length (struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_worker\_get\_relative\_speedup (struct starpu\_perfmodel\_arch \*perf\_arch)
- double starpu task expected data transfer time (unsigned memory node, struct starpu task \*task)
- double starpu\_data\_expected\_transfer\_time (starpu\_data\_handle\_t handle, unsigned memory\_node, enum starpu\_data\_access\_mode mode)
- double starpu\_task\_expected\_power (struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_task\_expected\_conversion\_time (struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- int starpu\_get\_prefetch\_flag (void)
- int starpu\_prefetch\_task\_input\_on\_node (struct starpu\_task \*task, unsigned node)
- int starpu\_idle\_prefetch\_task\_input\_on\_node (struct starpu\_task \*task, unsigned node)
- · void starpu sched ctx worker shares tasks lists (int workerid, int sched ctx id)

## 27.36.1 Detailed Description

TODO. While StarPU comes with a variety of scheduling policies (see Task Scheduling Policy), it may sometimes be desirable to implement custom policies to address specific problems. The API described below allows users to write their own scheduling policy.

# 27.36.2 Data Structure Documentation

### 27.36.2.1 struct starpu\_sched\_policy

This structure contains all the methods that implement a scheduling policy. An application may specify which scheduling strategy in the field <a href="mailto:starpu\_conf::sched\_policy">starpu\_conf::sched\_policy</a> passed to the function <a href="mailto:starpu\_init()">starpu\_init()</a>.

#### **Data Fields**

- void(\* init sched )(unsigned sched ctx id)
- void(\* deinit\_sched )(unsigned sched\_ctx\_id)
- int(\* push task )(struct starpu task \*)
- double(\* simulate\_push\_task )(struct starpu\_task \*)
- void(\* push\_task\_notify)(struct starpu\_task \*, int workerid, int perf\_workerid, unsigned sched\_ctx\_id)
- struct starpu task \*(\* pop task )(unsigned sched ctx id)
- struct starpu\_task \*(\* pop\_every\_task )(unsigned sched\_ctx\_id)
- void(\* pre\_exec\_hook )(struct starpu\_task \*)
- void(\* post\_exec\_hook )(struct starpu\_task \*)
- void(\* add workers )(unsigned sched ctx id, int \*workerids, unsigned nworkers)
- void(\* remove\_workers )(unsigned sched\_ctx\_id, int \*workerids, unsigned nworkers)
- const char \* policy name
- const char \* policy\_description

27.36.2.1.1 Field Documentation

27.36.2.1.1.1 void(\* starpu\_sched\_policy::init\_sched)(unsigned sched\_ctx\_id)

Initialize the scheduling policy.

27.36.2.1.1.2 void(\* starpu\_sched\_policy::deinit\_sched)(unsigned sched\_ctx\_id)

Cleanup the scheduling policy.

27.36.2.1.1.3 int(\* starpu\_sched\_policy::push\_task)(struct starpu\_task \*)

Insert a task into the scheduler.

27.36.2.1.1.4 void(\* starpu\_sched\_policy::push\_task\_notify)(struct starpu\_task \*, int workerid, int perf\_workerid, unsigned sched\_ctx\_id)

Notify the scheduler that a task was pushed on a given worker. This method is called when a task that was explicitly assigned to a worker becomes ready and is about to be executed by the worker. This method therefore permits to keep the state of the scheduler coherent even when StarPU bypasses the scheduling strategy.

27.36.2.1.1.5 struct starpu task \*(\* starpu\_sched\_policy::pop\_task)(unsigned sched\_ctx\_id) [read]

Get a task from the scheduler. The mutex associated to the worker is already taken when this method is called. If this method is defined as NULL, the worker will only execute tasks from its local queue. In this case, the push\_task method should use the starpu push local task method to assign tasks to the different workers.

27.36.2.1.1.6 struct starpu\_task \*(\* starpu\_sched\_policy::pop\_every\_task)(unsigned sched\_ctx\_id) [read]

Remove all available tasks from the scheduler (tasks are chained by the means of the field <a href="starpu\_task::prev">starpu\_task::prev</a> and <a href="starpu\_task::next">starpu\_task::next</a>). The mutex associated to the worker is already taken when this method is called. This is currently not used.

27.36.2.1.1.7 void(\* starpu\_sched\_policy::pre\_exec\_hook)(struct starpu\_task \*)

Optional field. This method is called every time a task is starting.

27.36.2.1.1.8 void(\* starpu\_sched\_policy::post\_exec\_hook)(struct starpu\_task \*)

Optional field. This method is called every time a task has been executed.

27.36.2.1.1.9 void(\* starpu\_sched\_policy::add\_workers)(unsigned sched\_ctx\_id, int \*workerids, unsigned nworkers)

Initialize scheduling structures corresponding to each worker used by the policy.

27.36.2.1.1.10 void(\* starpu\_sched\_policy::remove\_workers)(unsigned sched\_ctx\_id, int \*workerids, unsigned nworkers)

Deinitialize scheduling structures corresponding to each worker used by the policy.

 ${\bf 27.36.2.1.1.11} \quad {\bf const\; char * starpu\_sched\_policy::policy\_name}$ 

Optional field. Name of the policy.

27.36.2.1.1.12 const char \* starpu\_sched\_policy::policy\_description

Optional field. Human readable description of the policy.

### 27.36.3 Function Documentation

```
27.36.3.1 struct starpu_sched_policy ** starpu_sched_get_predefined_policies( ) [read]
```

Return an NULL-terminated array of all the predefined scheduling policies.

```
27.36.3.2 void starpu_worker_get_sched_condition ( int workerid, starpu_pthread_mutex_t ** sched_mutex, starpu_pthread_cond_t ** sched_cond )
```

When there is no available task for a worker, StarPU blocks this worker on a condition variable. This function specifies which condition variable (and the associated mutex) should be used to block (and to wake up) a worker. Note that multiple workers may use the same condition variable. For instance, in the case of a scheduling strategy with a single task queue, the same condition variable would be used to block and wake up all workers.

```
27.36.3.3 int starpu_sched_set_min_priority ( int min_prio )
```

TODO: check if this is correct Defines the minimum task priority level supported by the scheduling policy. The default minimum priority level is the same as the default priority level which is 0 by convention. The application may access that value by calling the function <a href="mailto:starpu\_sched\_get\_min\_priority">starpu\_sched\_get\_min\_priority</a>(). This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

```
27.36.3.4 int starpu_sched_set_max_priority ( int max_prio )
```

TODO: check if this is correct Defines the maximum priority level supported by the scheduling policy. The default maximum priority level is 1. The application may access that value by calling the function <a href="max\_sched\_get\_max\_priority">starpu\_sched\_get\_max\_priority</a>(). This function should only be called from the initialization method of the scheduling policy, and should not be used directly from the application.

```
27.36.3.5 int starpu_sched_get_min_priority ( void )
```

TODO: check if this is correct Returns the current minimum priority level supported by the scheduling policy

```
27.36.3.6 int starpu_sched_get_max_priority ( void )
```

TODO: check if this is correct Returns the current maximum priority level supported by the scheduling policy

```
27.36.3.7 int starpu_push_local_task ( int workerid, struct starpu_task * task, int back )
```

The scheduling policy may put tasks directly into a worker's local queue so that it is not always necessary to create its own queue when the local queue is sufficient. If back is not 0, task is put at the back of the queue where the worker will pop tasks first. Setting back to 0 therefore ensures a FIFO ordering.

```
27.36.3.8 int starpu_push_task_end ( struct starpu_task * task )
```

This function must be called by a scheduler to notify that the given task has just been pushed.

```
27.36.3.9 int starpu_worker_can_execute_task ( unsigned workerid, struct starpu_task * task, unsigned nimpl )
```

Check if the worker specified by workerid can execute the codelet. Schedulers need to call it before assigning a task to a worker, otherwise the task may fail to execute.

27.36.3.10 int starpu\_worker\_can\_execute\_task\_impl ( unsigned workerid, struct starpu\_task \* task, unsigned \* impl\_mask )

Check if the worker specified by workerid can execute the codelet and returns which implementation numbers can be used. Schedulers need to call it before assigning a task to a worker, otherwise the task may fail to execute. This should be preferred rather than calling starpu\_worker\_can\_execute\_task for each and every implementation. It can also be used with impl mask == NULL to check for at least one implementation without determining which.

27.36.3.11 int starpu\_worker\_can\_execute\_task\_first\_impl ( unsigned workerid, struct starpu\_task \* task, unsigned \* nimpl )

Check if the worker specified by workerid can execute the codelet and returns the first implementation which can be used. Schedulers need to call it before assigning a task to a worker, otherwise the task may fail to execute. This should be preferred rather than calling starpu\_worker\_can\_execute\_task for each and every implementation. It can also be used with impl\_mask == NULL to check for at least one implementation without determining which.

27.36.3.12 uint32\_t starpu\_task\_footprint ( struct starpu\_perfmodel \* model, struct starpu\_task \* task, struct starpu\_perfmodel\_arch \* arch, unsigned nimpl )

Returns the footprint for a given task, taking into account user-provided perfmodel footprint or size\_base functions.

27.36.3.13 uint32\_t starpu\_task\_data\_footprint ( struct starpu\_task \* task )

Returns the raw footprint for the data of a given task (without taking into account user-provided functions).

27.36.3.14 double starpu\_task\_expected\_length ( struct starpu\_task \* task, struct starpu\_perfmodel\_arch \* arch, unsigned nimpl )

Returns expected task duration in micro-seconds.

27.36.3.15 double starpu\_worker\_get\_relative\_speedup ( struct starpu\_perfmodel\_arch \* perf\_arch )

Returns an estimated speedup factor relative to CPU speed

27.36.3.16 double starpu\_task\_expected\_data\_transfer\_time ( unsigned memory\_node, struct starpu\_task \* task )

Returns expected data transfer time in micro-seconds.

27.36.3.17 double starpu\_data\_expected\_transfer\_time ( starpu\_data\_handle\_t handle, unsigned memory\_node, enum starpu\_data\_access\_mode mode )

Predict the transfer time (in micro-seconds) to move handle to a memory node

27.36.3.18 double starpu\_task\_expected\_power ( struct starpu\_task \* task, struct starpu\_perfmodel\_arch \* arch, unsigned nimpl )

Returns expected power consumption in J

27.36.3.19 double starpu\_task\_expected\_conversion\_time ( struct starpu\_task \* task, struct starpu\_perfmodel\_arch \* arch, unsigned nimpl )

Returns expected conversion time in ms (multiformat interface only)

27.37 Tree 321

27.36.3.20 int starpu\_get\_prefetch\_flag ( void )

Whether STARPU\_PREFETCH was set

27.36.3.21 int starpu\_prefetch\_task\_input\_on\_node ( struct starpu\_task \* task, unsigned node )

Prefetch data for a given task on a given node

27.36.3.22 int starpu\_idle\_prefetch\_task\_input\_on\_node ( struct starpu\_task \* task, unsigned node )

Prefetch data for a given task on a given node when the bus is idle

27.36.3.23 void starpu\_sched\_ctx\_worker\_shares\_tasks\_lists ( int workerid, int sched\_ctx\_id )

The scheduling policies indicates if the worker may pop tasks from the list of other workers or if there is a central list with task for all the workers

# 27.37 Tree

This section describes the tree facilities provided by StarPU.

### **Data Structures**

· struct starpu\_tree

# **Functions**

- void starpu tree reset visited (struct starpu tree \*tree, int \*visited)
- void starpu\_tree\_insert (struct starpu\_tree \*tree, int id, int level, int is\_pu, int arity, struct starpu\_tree \*father)
- struct starpu\_tree \* starpu\_tree\_get (struct starpu\_tree \*tree, int id)
- struct starpu\_tree \* starpu\_tree\_get\_neighbour (struct starpu\_tree \*tree, struct starpu\_tree \*node, int \*visited, int \*present)
- void starpu\_tree\_free (struct starpu\_tree \*tree)

# 27.37.1 Detailed Description

This section describes the tree facilities provided by StarPU.

### 27.37.2 Data Structure Documentation

# 27.37.2.1 struct starpu\_tree

#### **Data Fields**

struct	nodes	todo
starpu_tree **		
struct	father	todo
starpu_tree *		
int	arity	todo
int	id	todo
int	level	todo
int	is_pu	todo

# 27.38 Scheduling Context Hypervisor - Regular usage

### **Macros**

- #define SC\_HYPERVISOR\_MAX\_IDLE
- #define SC HYPERVISOR PRIORITY
- #define SC\_HYPERVISOR\_MIN\_WORKERS
- #define SC\_HYPERVISOR\_MAX\_WORKERS
- #define SC\_HYPERVISOR\_GRANULARITY
- #define SC\_HYPERVISOR\_FIXED\_WORKERS
- #define SC HYPERVISOR MIN TASKS
- #define SC HYPERVISOR NEW WORKERS MAX IDLE
- #define SC HYPERVISOR TIME TO APPLY
- #define SC HYPERVISOR ISPEED W SAMPLE
- #define SC\_HYPERVISOR\_ISPEED\_CTX\_SAMPLE
- #define SC HYPERVISOR NULL

#### **Functions**

- void \* sc\_hypervisor\_init (struct sc\_hypervisor\_policy \*policy)
- void sc\_hypervisor\_shutdown (void)
- void sc\_hypervisor\_register\_ctx (unsigned sched\_ctx, double total\_flops)
- void sc\_hypervisor\_unregister\_ctx (unsigned sched\_ctx)
- void sc hypervisor resize ctxs (unsigned \*sched ctxs, int nsched ctxs, int \*workers, int nworkers)
- void sc\_hypervisor\_stop\_resize (unsigned sched\_ctx)
- void sc\_hypervisor\_start\_resize (unsigned sched\_ctx)
- const char \* sc\_hypervisor\_get\_policy ()

- void sc\_hypervisor\_add\_workers\_to\_sched\_ctx (int \*workers\_to\_add, unsigned nworkers\_to\_add, unsigned sched\_ctx)
- void sc\_hypervisor\_remove\_workers\_from\_sched\_ctx (int \*workers\_to\_remove, unsigned nworkers\_to\_remove, unsigned sched\_ctx, unsigned now)
- void sc\_hypervisor\_move\_workers (unsigned sender\_sched\_ctx, unsigned receiver\_sched\_ctx, int \*workers\_to\_move, unsigned now)
- void sc\_hypervisor\_size\_ctxs (unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- void sc\_hypervisor\_set\_type\_of\_task (struct starpu\_codelet \*cl, unsigned sched\_ctx, uint32\_t footprint, size-t data size)
- void sc\_hypervisor\_update\_diff\_total\_flops (unsigned sched\_ctx, double diff\_total\_flops)
- void sc\_hypervisor\_update\_diff\_elapsed\_flops (unsigned sched\_ctx, double diff\_task\_flops)
- void sc\_hypervisor\_ctl (unsigned sched\_ctx,...)

### 27.38.1 Detailed Description

#### 27.38.2 Macro Definition Documentation

#### 27.38.2.1 #define SC\_HYPERVISOR\_MAX\_IDLE

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 3 arguments: an array of int for the workerids to apply the condition, an int to indicate the size of the array, and a double value indicating the maximum idle time allowed for a worker before the resizing process should be triggered

#### 27.38.2.2 #define SC\_HYPERVISOR\_PRIORITY

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 3 arguments: an array of int for the workerids to apply the condition, an int to indicate the size of the array, and an int value indicating the priority of the workers previously mentioned. The workers with the smallest priority are moved the first.

# 27.38.2.3 #define SC\_HYPERVISOR\_MIN\_WORKERS

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument(int) indicating the minimum number of workers a context should have, underneath this limit the context cannot execute.

# 27.38.2.4 #define SC\_HYPERVISOR\_MAX\_WORKERS

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument(int) indicating the maximum number of workers a context should have, above this limit the context would not be able to scale

#### 27.38.2.5 #define SC\_HYPERVISOR\_GRANULARITY

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument(int) indicating the granularity of the resizing process (the number of workers should be moved from the context once it is resized) This parameter is ignore for the Gflops rate based strategy (see Resizing Strategies), the number of workers that have to be moved is calculated by the strategy.

#### 27.38.2.6 #define SC\_HYPERVISOR\_FIXED\_WORKERS

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 2 arguments: an array of int for the workerids to apply the condition and an int to indicate the size of the array. These workers are not allowed to be moved from the context.

#### 27.38.2.7 #define SC\_HYPERVISOR\_MIN\_TASKS

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument (int) that indicated the minimum number of tasks that have to be executed before the context could be resized. This parameter is ignored for the Application Driven strategy (see Resizing Strategies) where the user indicates exactly when the resize should be done.

#### 27.38.2.8 #define SC\_HYPERVISOR\_NEW\_WORKERS\_MAX\_IDLE

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument, a double value indicating the maximum idle time allowed for workers that have just been moved from other contexts in the current context.

### 27.38.2.9 #define SC\_HYPERVISOR\_TIME\_TO\_APPLY

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument (int) indicating the tag an executed task should have such that this configuration should be taken into account.

#### 27.38.2.10 #define SC\_HYPERVISOR\_ISPEED\_W\_SAMPLE

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument, a double, that indicates the number of flops needed to be executed before computing the speed of a worker

#### 27.38.2.11 #define SC\_HYPERVISOR\_ISPEED\_CTX\_SAMPLE

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 argument, a double, that indicates the number of flops needed to be executed before computing the speed of a context

# 27.38.2.12 #define SC\_HYPERVISOR\_NULL

This macro is used when calling sc\_hypervisor\_ctl() and must be followed by 1 arguments

# 27.38.3 Function Documentation

27.38.3.1 void \* sc\_hypervisor\_init ( struct sc\_hypervisor\_policy \* policy )

There is a single hypervisor that is in charge of resizing contexts and the resizing strategy is chosen at the initialization of the hypervisor. A single resize can be done at a time.

The Scheduling Context Hypervisor Plugin provides a series of performance counters to StarPU. By incrementing them, StarPU can help the hypervisor in the resizing decision making process.

This function initializes the hypervisor to use the strategy provided as parameter and creates the performance counters (see <a href="starpu\_sched\_ctx\_performance\_counters">starpu\_sched\_ctx\_performance\_counters</a>). These performance counters represent actually some callbacks that will be used by the contexts to notify the information needed by the hypervisor.

Note: The Hypervisor is actually a worker that takes this role once certain conditions trigger the resizing process (there is no additional thread assigned to the hypervisor).

# 27.38.3.2 void sc\_hypervisor\_shutdown ( void )

The hypervisor and all information concerning it is cleaned. There is no synchronization between this function and starpu\_shutdown(). Thus, this should be called after starpu\_shutdown(), because the performance counters will still need allocated callback functions.

27.38.3.3 void sc\_hypervisor\_register\_ctx ( unsigned sched\_ctx, double total\_flops )

Scheduling Contexts that have to be resized by the hypervisor must be first registered to the hypervisor. This function registers the context to the hypervisor, and indicate the number of flops the context will execute (used for Gflops rate based strategy or any other custom strategy needing it, for the others we can pass 0.0)

27.38.3.4 void sc\_hypervisor\_unregister\_ctx ( unsigned sched\_ctx )

Whenever we want to exclude contexts from the resizing process we have to unregister them from the hypervisor.

27.38.3.5 void sc\_hypervisor\_resize\_ctxs ( unsigned \* sched\_ctxs, int nsched\_ctxs, int \* workers, int nworkers )

Requires reconsidering the distribution of ressources over the indicated scheduling contexts

27.38.3.6 void sc\_hypervisor\_stop\_resize ( unsigned sched\_ctx )

The user can totally forbid the resizing of a certain context or can then change his mind and allow it (in this case the resizing is managed by the hypervisor, that can forbid it or allow it)

27.38.3.7 void sc\_hypervisor\_start\_resize ( unsigned sched\_ctx )

Allow resizing of a context. The user can then provide information to the hypervisor concerning the conditions of resizing.

27.38.3.8 char \* sc\_hypervisor\_get\_policy ( )

Returns the name of the resizing policy the hypervisor uses

27.38.3.9 void sc\_hypervisor\_add\_workers\_to\_sched\_ctx ( int \* workers\_to\_add, unsigned nworkers\_to\_add, unsigned sched\_ctx )

Ask the hypervisor to add workers to a sched\_ctx

27.38.3.10 void sc\_hypervisor\_remove\_workers\_from\_sched\_ctx ( int \* workers\_to\_remove, unsigned nworkers\_to\_remove, unsigned sched\_ctx, unsigned now )

Ask the hypervisor to remove workers from a sched\_ctx

27.38.3.11 void sc\_hypervisor\_move\_workers ( unsigned sender\_sched\_ctx, unsigned receiver\_sched\_ctx, int \* workers\_to\_move, unsigned nworkers\_to\_move, unsigned now )

Moves workers from one context to another

27.38.3.12 void sc\_hypervisor\_size\_ctxs ( unsigned \* sched\_ctxs, int nsched\_ctxs, int \* workers, int nworkers )

Ask the hypervisor to chose a distribution of workers in the required contexts

27.38.3.13 void sc\_hypervisor\_set\_type\_of\_task ( struct starpu\_codelet \* cl, unsigned sched\_ctx, uint32\_t footprint, size\_t data\_size )

Indicate the types of tasks a context will execute in order to better decide the sizing of ctxs

27.38.3.14 void sc\_hypervisor\_update\_diff\_total\_flops ( unsigned sched\_ctx, double diff\_total\_flops )

Change dynamically the total number of flops of a context, move the deadline of the finishing time of the context

27.38.3.15 void sc\_hypervisor\_update\_diff\_elapsed\_flops ( unsigned sched\_ctx, double diff\_task\_flops )

Change dynamically the number of the elapsed flops in a context, modify the past in order to better compute the speed

27.38.3.16 void sc\_hypervisor\_ctl ( unsigned sched\_ctx, ... )

Inputs conditions to the context sched\_ctx with the following arguments. The argument list must be zero-terminated.

# 27.39 Scheduling Context Hypervisor - Building a new resizing policy

### **Data Structures**

- · struct sc\_hypervisor\_policy
- · struct sc\_hypervisor\_policy\_config
- struct sc\_hypervisor\_wrapper
- struct sc\_hypervisor\_resize\_ack
- struct sc\_hypervisor\_policy\_task\_pool

### **Functions**

- void sc\_hypervisor\_post\_resize\_request (unsigned sched\_ctx, int task\_tag)
- unsigned sc\_hypervisor\_get\_size\_req (unsigned \*\*sched\_ctxs, int \*nsched\_ctxs, int \*\*workers, int \*nworkers)
- void sc\_hypervisor\_save\_size\_req (unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- void sc\_hypervisor\_free\_size\_req (void)
- unsigned sc\_hypervisor\_can\_resize (unsigned sched\_ctx)
- struct

sc\_hypervisor\_policy\_config \* sc\_hypervisor\_get\_config (unsigned sched\_ctx)

- void sc\_hypervisor\_set\_config (unsigned sched\_ctx, void \*config)
- unsigned \* sc\_hypervisor\_get\_sched\_ctxs ()
- int sc\_hypervisor\_get\_nsched\_ctxs ()
- struct sc\_hypervisor\_wrapper \* sc\_hypervisor\_get\_wrapper (unsigned sched\_ctx)
- double sc\_hypervisor\_get\_elapsed\_flops\_per\_sched\_ctx (struct sc\_hypervisor\_wrapper \*sc\_w)

# 27.39.1 Detailed Description

# 27.39.2 Data Structure Documentation

27.39.2.1 struct sc\_hypervisor\_policy

This structure contains all the methods that implement a hypervisor resizing policy.

#### **Data Fields**

- const char \* name
- unsigned custom
- void(\* size\_ctxs )(unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- void(\* resize\_ctxs )(unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- void(\* handle\_idle\_cycle )(unsigned sched\_ctx, int worker)
- void(\* handle pushed task)(unsigned sched ctx, int worker)
- void(\* handle\_poped\_task )(unsigned sched\_ctx, int worker, struct starpu\_task \*task, uint32\_t footprint)
- void(\* handle\_idle\_end )(unsigned sched\_ctx, int worker)
- void(\* handle\_post\_exec\_hook )(unsigned sched\_ctx, int task\_tag)
- void(\* handle\_submitted\_job )(struct starpu\_codelet \*cl, unsigned sched\_ctx, uint32\_t footprint, size\_t data\_size)
- void(\* end ctx )(unsigned sched ctx)

#### 27.39.2.1.1 Field Documentation

27.39.2.1.1.1 sc\_hypervisor\_policy::name

Indicates the name of the policy, if there is not a custom policy, the policy corresponding to this name will be used by the hypervisor

27.39.2.1.1.2 sc\_hypervisor\_policy::custom

Indicates whether the policy is custom or not

27.39.2.1.1.3 sc\_hypervisor\_policy::size\_ctxs

Distribute workers to contexts even at the beginning of the program

27.39.2.1.1.4 sc\_hypervisor\_policy::resize\_ctxs

Require explicit resizing

27.39.2.1.1.5 sc\_hypervisor\_policy::handle\_idle\_cycle

It is called whenever the indicated worker executes another idle cycle in sched ctx

27.39.2.1.1.6 sc\_hypervisor\_policy::handle\_pushed\_task

It is called whenever a task is pushed on the worker's queue corresponding to the context sched\_ctx

27.39.2.1.1.7 sc\_hypervisor\_policy::handle\_poped\_task

It is called whenever a task is poped from the worker's queue corresponding to the context sched\_ctx

The hypervisor takes a decision when another task was poped from this worker in this ctx

27.39.2.1.1.8 sc\_hypervisor\_policy::handle\_idle\_end

It is called whenever a task is executed on the indicated worker and context after a long period of idle time

27.39.2.1.1.9 sc\_hypervisor\_policy::handle\_post\_exec\_hook

It is called whenever a tag task has just been executed. The table of resize requests is provided as well as the tag

27.39.2.1.1.10 sc\_hypervisor\_policy::handle\_submitted\_job

The hypervisor takes a decision when a job was submitted in this ctx

# 27.39.2.1.1.11 sc\_hypervisor\_policy::end\_ctx

The hypervisor takes a decision when a certain ctx was deleted

# 27.39.2.2 struct sc\_hypervisor\_policy\_config

This structure contains all configuration information of a context. It contains configuration information for each context, which can be used to construct new resize strategies.

### **Data Fields**

int	min_nworkers	Indicates the minimum number of workers needed by the context
int	max_nworkers	Indicates the maximum number of workers needed by the context
int	granularity	Indicates the workers granularity of the context
int	priority	Indicates the priority of each worker in the context
double	max_idle	Indicates the maximum idle time accepted before a resize is triggered
double	min_working	Indicates that underneath this limit the priority of the worker is reduced
int	fixed_workers	Indicates which workers can be moved and which ones are fixed
double	new_workers	Indicates the maximum idle time accepted before a resize is triggered for
	max_idle	the workers that just arrived in the new context
double	ispeed_w	Indicates the sample used to compute the instant speed per worker
	sample	
double	ispeed_ctx	Indicates the sample used to compute the instant speed per ctxs
	sample	
double	time_sample	todo

# 27.39.2.3 struct sc\_hypervisor\_wrapper

This structure is a wrapper of the contexts available in StarPU and contains all information about a context obtained by incrementing the performance counters.

# Data Fields

unsigned	sched_ctx	The context wrapped
struct	config	The corresponding resize configuration
sc_hypervisor		
policy_config		
*		
double	start_time_w	
double	current_idle	The idle time counter of each worker of the context
	time	
double	idle_time	The time the workers were idle from the last resize
double	idle_start_time	The moment when the workers started being idle
double	exec_time	
double	exec_start_time	
int	worker_to_be	The list of workers that will leave this contexts (lazy resizing process)
	removed	
int	pushed_tasks	The number of pushed tasks of each worker of the context
int	poped_tasks	The number of poped tasks of each worker of the context
double	total_flops	The total number of flops to execute by the context
double	total_elapsed	The number of flops executed by each workers of the context
	flops	
double	elapsed_flops	The number of flops executed by each worker of the context from last
		resize
size_t	elapsed_data	The quantity of data (in bytes) used to execute tasks on each worker in
		this ctx

int	elapsed_tasks	The nr of tasks executed on each worker in this ctx
double	ref_speed	The average speed of the workers (type of workers) when they belonged
		to this context 0 - cuda 1 - cpu
double	submitted_flops	The number of flops submitted to this ctx
double	remaining_flops	The number of flops that still have to be executed by the workers in the
		context
double	start_time	The time when he started executed
double	real_start_time	The first time a task was pushed to this context
double	hyp_react_start-	
	_time	
struct	resize_ack	The structure confirming the last resize finished and a new one can be
sc_hypervisor		done
resize_ack		
starpu_pthread-	mutex	The mutex needed to synchronize the acknowledgment of the workers
_mutex_t		into the receiver context
unsigned	total_flops	A boolean indicating if the hypervisor can use the flops corresponding to
	available	the entire execution of the context
unsigned	to_be_sized	
unsigned	compute_idle	
unsigned	compute_partial-	
	_idle	
unsigned	consider max	

# 27.39.2.4 struct sc\_hypervisor\_resize\_ack

This structures checks if the workers moved to another context are actually taken into account in that context.

### **Data Fields**

int	receiver_sched-	The context receiving the new workers
	_ctx	
int *	moved_workers	The workers moved to the receiver context
int	nmoved_workers	The number of workers moved
int *	acked_workers	If the value corresponding to a worker is 1, this one is taken into account
		in the new context if 0 not yet

# 27.39.2.5 struct sc\_hypervisor\_policy\_task\_pool

task wrapper linked list

### **Data Fields**

struct	cl	Which codelet has been executed
starpu_codelet *		
uint32_t	footprint	Task footprint key
unsigned	sched_ctx_id	Context the task belongs to
unsigned long	n	Number of tasks of this kind
size_t	data_size	The quantity of data(in bytes) needed by the task to execute
struct	next	Other task kinds
sc_hypervisor		
policy_task_pool		
*		

```
27.39.3 Function Documentation
27.39.3.1 void sc_hypervisor_post_resize_request ( unsigned sched_ctx, int task_tag )
Requires resizing the context sched_ctx whenever a task tagged with the id task_tag finished executing
27.39.3.2 unsigned sc_hypervisor_get_size_req ( unsigned ** sched_ctxs, int * nsched_ctxs, int ** workers, int * nworkers )
Check if there are pending demands of resizing
27.39.3.3 void sc_hypervisor_save_size_req ( unsigned * sched_ctxs, int nsched_ctxs, int * workers, int nworkers )
Save a demand of resizing
27.39.3.4 void sc_hypervisor_free_size_req ( void )
Clear the list of pending demands of resizing
27.39.3.5 unsigned sc_hypervisor_can_resize ( unsigned sched_ctx )
Check out if a context can be resized
27.39.3.6 struct sc_hypervisor_policy_config * sc_hypervisor_get_config ( unsigned sched_ctx ) [read]
Returns the configuration structure of a context
27.39.3.7 void sc_hypervisor_set_config ( unsigned sched_ctx, void * config )
Set a certain configuration to a contexts
27.39.3.8 unsigned * sc_hypervisor_get_sched_ctxs ( )
Gets the contexts managed by the hypervisor
27.39.3.9 int sc_hypervisor_get_nsched_ctxs ( )
Gets the number of contexts managed by the hypervisor
27.39.3.10 struct sc_hypervisor_wrapper * sc_hypervisor_get_wrapper ( unsigned sched_ctx ) [read]
Returns the wrapper corresponding the context sched_ctx
27.39.3.11 double sc_hypervisor_get_elapsed_flops_per_sched_ctx ( struct sc_hypervisor_wrapper * sc_w )
```

Returns the flops of a context elapsed from the last resize

### 27.40 Modularized Scheduler Interface

### **Data Structures**

- struct starpu\_sched\_component
- · struct starpu sched tree
- struct starpu\_sched\_component\_fifo\_data
- struct starpu\_sched\_component\_prio\_data
- · struct starpu sched component mct data
- struct starpu\_sched\_component\_perfmodel\_select\_data
- · struct starpu\_sched\_component\_composed\_recipe
- struct starpu\_sched\_component\_specs

#### **Macros**

- #define STARPU SCHED COMPONENT IS HOMOGENEOUS(component)
- #define STARPU\_SCHED\_COMPONENT\_IS\_SINGLE\_MEMORY\_NODE(component)

#### **Enumerations**

 enum starpu\_sched\_component\_properties { STARPU\_SCHED\_COMPONENT\_HOMOGENEOUS, STAR-PU\_SCHED\_COMPONENT\_SINGLE\_MEMORY\_NODE }

# **Scheduling Tree API**

- struct starpu sched tree \* starpu sched tree create (unsigned sched ctx id)
- void starpu sched tree destroy (struct starpu sched tree \*tree)
- void starpu\_sched\_tree\_update\_workers (struct starpu\_sched\_tree \*t)
- void starpu\_sched\_tree\_update\_workers\_in\_ctx (struct starpu\_sched\_tree \*t)
- int starpu\_sched\_tree\_push\_task (struct starpu\_task \*task)
- void starpu\_sched\_tree\_add\_workers (unsigned sched\_ctx\_id, int \*workerids, unsigned nworkers)
- void starpu\_sched\_tree\_remove\_workers (unsigned sched\_ctx\_id, int \*workerids, unsigned nworkers)
- void starpu\_sched\_component\_connect (struct starpu\_sched\_component \*parent, struct starpu\_sched\_component \*child)

# **Generic Scheduling Component API**

- void starpu\_sched\_component\_destroy (struct starpu\_sched\_component \*component)
- void starpu\_sched\_component\_destroy\_rec (struct starpu\_sched\_component \*component)
- int starpu\_sched\_component\_can\_execute\_task (struct starpu\_sched\_component \*component, struct starpu\_task \*task)
- int STARPU\_WARN\_UNUSED\_RESULT starpu\_sched\_component\_execute\_preds (struct starpu\_sched\_component \*component, struct starpu\_task \*task, double \*length)
- double starpu\_sched\_component\_transfer\_length (struct starpu\_sched\_component \*component, struct starpu task \*task)

# **Worker Component API**

- struct starpu\_sched\_component \* starpu\_sched\_component\_worker\_get (unsigned sched\_ctx, int workerid)
- int starpu\_sched\_component\_worker\_get\_workerid (struct starpu\_sched\_component \*worker\_component)
- int starpu sched component is worker (struct starpu sched component \*component)
- int starpu\_sched\_component\_is\_simple\_worker (struct starpu\_sched\_component \*component)
- int starpu sched component is combined worker (struct starpu sched component \*component)
- void starpu\_sched\_component\_worker\_pre\_exec\_hook (struct starpu\_task \*task)
- void starpu\_sched\_component\_worker\_post\_exec\_hook (struct starpu\_task \*task)

# Flow-control Fifo Component API

- struct starpu\_sched\_component \* starpu\_sched\_component\_fifo\_create (struct starpu\_sched\_tree \*tree, struct starpu\_sched\_component\_fifo\_data \*fifo\_data)
- int starpu\_sched\_component\_is\_fifo (struct starpu\_sched\_component \*component)

# Flow-control Prio Component API

- struct starpu\_sched\_component \* starpu\_sched\_component\_prio\_create (struct starpu\_sched\_tree \*tree, struct starpu\_sched\_component\_prio\_data \*prio\_data)
- int starpu\_sched\_component\_is\_prio (struct starpu\_sched\_component \*component)

# **Resource-mapping Work-Stealing Component API**

- int starpu\_sched\_tree\_work\_stealing\_push\_task (struct starpu\_task \*task)
- int starpu\_sched\_component\_is\_work\_stealing (struct starpu\_sched\_component \*component)

# **Resource-mapping Random Component API**

int starpu sched component is random (struct starpu sched component \*)

# **Resource-mapping Eager Component API**

int starpu\_sched\_component\_is\_eager (struct starpu\_sched\_component \*)

# **Resource-mapping Eager-Calibration Component API**

• int starpu\_sched\_component\_is\_eager\_calibration (struct starpu\_sched\_component \*)

# Resource-mapping MCT Component API

- struct starpu\_sched\_component \* starpu\_sched\_component\_mct\_create (struct starpu\_sched\_tree \*tree, struct starpu\_sched\_component\_mct\_data \*mct\_data)
- int starpu\_sched\_component\_is\_mct (struct starpu\_sched\_component \*component)

## **Resource-mapping Heft Component API**

- struct starpu\_sched\_component \* starpu\_sched\_component\_heft\_create (struct starpu\_sched\_tree \*tree, struct starpu\_sched\_component\_mct\_data \*mct\_data)
- int starpu\_sched\_component\_is\_heft (struct starpu\_sched\_component \*component)

# Special-purpose Perfmodel\_Select Component API

- struct starpu\_sched\_component \* starpu\_sched\_component\_perfmodel\_select\_create (struct starpu\_sched\_tree \*tree, struct starpu\_sched\_component\_perfmodel\_select\_data \*perfmodel\_select\_data)
- int starpu\_sched\_component\_is\_perfmodel\_select (struct starpu\_sched\_component \*component)

# **Recipe Component API**

- struct starpu\_sched\_component\_composed\_recipe \* starpu\_sched\_component\_composed\_recipe\_create (void)
- struct
   starpu\_sched\_component\_composed\_recipe \* starpu\_sched\_component\_composed\_recipe\_create\_singleton (struct starpu\_sched\_component \*(\*create\_component)(struct starpu\_sched\_tree \*tree, void \*arg), void \*arg)
- void starpu\_sched\_component\_composed\_recipe\_add (struct starpu\_sched\_component\_composed\_recipe \*recipe, struct starpu\_sched\_component \*(\*create\_component)(struct starpu\_sched\_tree \*tree, void \*arg), void \*arg)
- void starpu\_sched\_component\_composed\_recipe\_destroy (struct starpu\_sched\_component\_composed\_recipe \*)
- struct starpu\_sched\_component \* starpu\_sched\_component\_composed\_component\_create (struct starpu\_sched\_tree \*tree, struct starpu\_sched\_component\_composed\_recipe \*recipe)
- struct starpu\_sched\_tree \* starpu\_sched\_component\_make\_scheduler (unsigned sched\_ctx\_id, struct starpu\_sched\_component\_specs s)

### 27.40.1 Detailed Description

#### 27.40.2 Data Structure Documentation

# 27.40.2.1 struct starpu\_sched\_component

This structure represent a scheduler module. A scheduler is a tree-like structure of them, some parts of scheduler can be shared by several contexes to perform some local optimisations, so, for all components, a list of parent is defined indexed by sched\_ctx\_id. They embed there specialised method in a pseudo object-style, so calls are like component->push\_task(component,task)

#### **Data Fields**

- struct starpu sched tree \* tree
- struct starpu\_bitmap \* workers
- struct starpu bitmap \* workers in ctx
- void \* data
- char \* name
- · int nchildren
- struct starpu\_sched\_component \*\* children
- · int nparents
- struct starpu sched component \*\* parents
- void(\* add\_child )(struct starpu\_sched\_component \*component, struct starpu\_sched\_component \*child)
- void(\* remove\_child )(struct starpu\_sched\_component \*component, struct starpu\_sched\_component \*child)
- void(\* add\_parent )(struct starpu\_sched\_component \*component, struct starpu\_sched\_component \*parent)
- void(\* remove\_parent )(struct starpu\_sched\_component \*component \*struct starpu\_sched\_component \*parent)
- int(\* push\_task )(struct starpu\_sched\_component \*, struct starpu\_task \*)
- struct starpu task \*(\* pull task )(struct starpu sched component \*)
- int(\* can\_push )(struct starpu\_sched\_component \*component)

- void(\* can\_pull )(struct starpu\_sched\_component \*component)
- double(\* estimated\_load )(struct starpu\_sched\_component \*component)
- double(\* estimated end)(struct starpu sched component \*component)
- void(\* deinit\_data )(struct starpu\_sched\_component \*component)
- void(\* notify\_change\_workers )(struct starpu\_sched\_component \*component)
- · int properties
- hwloc\_obj\_t obj

27.40.2.1.1 Field Documentation

27.40.2.1.1.1 struct starpu\_sched\_tree \* starpu\_sched\_component::tree

The tree containing the component

27.40.2.1.1.2 struct starpu\_bitmap \* starpu\_sched\_component::workers

this member contain the set of underlying workers

27.40.2.1.1.3 starpu\_sched\_component::workers\_in\_ctx

this member contain the subset of <a href="starpu\_sched\_component::workers">starpu\_sched\_component::workers</a> that is currently available in the context The push method should take this member into account. this member is set with : component->workers UNION tree->workers UNION component->child[i]->workers\_in\_ctx iff exist x such as component->children[i]->parents[x] == component

27.40.2.1.1.4 void \* starpu\_sched\_component::data

private data

27.40.2.1.1.5 int starpu\_sched\_component::nchildren

the number of compoments's children

27.40.2.1.1.6 struct starpu\_sched\_component \*\* starpu\_sched\_component::children

the vector of component's children

27.40.2.1.1.7 int starpu\_sched\_component::nparents

the numbers of component's parents

27.40.2.1.1.8 struct starpu\_sched\_component \*\* starpu\_sched\_component::parents

the vector of component's parents

27.40.2.1.1.9 void(\* starpu\_sched\_component::add\_child)(struct starpu\_sched\_component \*component \*struct starpu\_sched\_component \*child)

add a child to component

27.40.2.1.1.10 void(\* starpu\_sched\_component::remove\_child)(struct starpu\_sched\_component \*component struct starpu\_sched\_component \*child)

remove a child from component

27.40.2.1.1.11 void(\* starpu\_sched\_component::add\_parent)(struct starpu\_sched\_component \*component struct starpu\_sched\_component \*parent)

todo

27.40.2.1.1.12 void(\* starpu\_sched\_component::remove\_parent)(struct starpu\_sched\_component \*component, struct starpu\_sched\_component \*parent)

todo

27.40.2.1.1.13 int(\* starpu\_sched\_component::push\_task)(struct starpu\_sched\_component \*, struct starpu\_task \*)

push a task in the scheduler module. this function is called to push a task on component subtree, this can either perform a recursive call on a child or store the task in the component, then it will be returned by a further pull\_task call. the caller must ensure that component is able to execute task.

27.40.2.1.1.14 struct starpu\_task \*(\* starpu\_sched\_component::pull\_task)(struct starpu\_sched\_component \*)

[read]

pop a task from the scheduler module. this function is called by workers to get a task from their parents. this function should first return a locally stored task or perform a recursive call on the parents. the task returned by this function is executable by the caller

27.40.2.1.1.15 int(\* starpu\_sched\_component::can\_push)(struct starpu\_sched\_component \*component)

This function is called by a component which implements a queue, allowing it to signify to its parents that an empty slot is available in its queue. The basic implementation of this function is a recursive call to its parents, the user have to specify a personally-made function to catch those calls.

27.40.2.1.1.16 void(\* starpu\_sched\_component::can\_pull)(struct starpu\_sched\_component \*component)

This function allow a component to wake up a worker. It is currently called by component which implements a queue, to signify to its children that a task have been pushed in its local queue, and is available to been popped by a worker, for example. The basic implementation of this function is a recursive call to its children, until at least one worker have been woken up.

27.40.2.1.1.17 double(\* starpu\_sched\_component::estimated\_load)(struct starpu\_sched\_component \*component)

is an heuristic to compute load of scheduler module. Basically the number of tasks divided by the sum of relatives speedup of workers available in context. estimated\_load(component) = sum(estimated\_load(component\_children)) + nb\_local\_tasks / average(relative\_speedup(underlying\_worker))

27.40.2.1.1.18 starpu\_sched\_component::estimated\_end

return the time when a worker will enter in starvation. This function is relevant only if the task->predicted member has been set.

27.40.2.1.1.19 void(\* starpu\_sched\_component::deinit\_data)(struct starpu\_sched\_component \*component)

called by starpu sched component destroy. Should free data allocated during creation

27.40.2.1.1.20 void(\* starpu\_sched\_component::notify\_change\_workers)(struct starpu\_sched\_component \*component)

this function is called for each component when workers are added or removed from a context

27.40.2.1.1.21 int starpu\_sched\_component::properties

todo

27.40.2.1.1.22 hwloc\_obj\_t starpu\_sched\_component::obj

the hwloc object associated to scheduler module. points to the part of topology that is binded to this component, eg: a numa node for a ws component that would balance load between underlying sockets

# 27.40.2.2 struct starpu\_sched\_tree

# The actual scheduler

# Data Fields

struct starpu_sched component *	root	this is the entry module of the scheduler
struct starpu_bitmap *	workers	this is the set of workers available in this context, this value is used to mask workers in modules
unsigned	sched_ctx_id	the context id of the scheduler
struct starpu_sched component *	worker components	worker components
starpu_pthread- _mutex_t	lock	this lock is used to protect the scheduler, it is taken in read mode pushing a task and in write mode for adding or removing workers

# 27.40.2.3 struct starpu\_sched\_component\_fifo\_data

### **Data Fields**

unsigned	ntasks_threshold	todo
double	exp_len	todo
	threshold	

# 27.40.2.4 struct starpu\_sched\_component\_prio\_data

# **Data Fields**

unsigned	ntasks_threshold	todo
double	exp_len	todo
	threshold	

# 27.40.2.5 struct starpu\_sched\_component\_mct\_data

# **Data Fields**

double	alpha	todo
double	beta	todo
double	_gamma	todo
double	idle_power	todo

# 27.40.2.6 struct starpu\_sched\_component\_perfmodel\_select\_data

#### **Data Fields**

struct	calibrator	todo
starpu_sched	component	
component		
*		
struct	no_perfmodel	todo
starpu_sched	component	
component		
*		
struct	perfmodel	todo
starpu_sched	component	
component		
*		

#### 27.40.2.7 struct starpu\_sched\_component\_composed\_recipe

parameters for starpu\_sched\_component\_composed\_component\_create

#### 27.40.2.8 struct starpu\_sched\_component\_specs

Define how build a scheduler according to topology. Each level (except for hwloc\_machine\_composed\_sched\_component) can be NULL, then the level is just skipped. Bugs everywhere, do not rely on.

### **Data Fields**

- · struct
- starpu\_sched\_component\_composed\_recipe \* hwloc\_machine\_composed\_sched\_component
- struct

starpu\_sched\_component\_composed\_recipe \* hwloc\_component\_composed\_sched\_component

- struct
- starpu\_sched\_component\_composed\_recipe \* hwloc\_socket\_composed\_sched\_component
- struct
  - starpu\_sched\_component\_composed\_recipe \* hwloc\_cache\_composed\_sched\_component
- struct
  - starpu\_sched\_component\_composed\_recipe \*(\* worker\_composed\_sched\_component )(enum starpu\_worker\_archtype archtype)
- int mix\_heterogeneous\_workers

# 27.40.3 Macro Definition Documentation

27.40.3.1 #define STARPU\_SCHED\_COMPONENT\_IS\_HOMOGENEOUS( component )

indicate if component is homogeneous

27.40.3.2 #define STARPU\_SCHED\_COMPONENT\_IS\_SINGLE\_MEMORY\_NODE( component )

indicate if all workers have the same memory component

# 27.40.4 Enumeration Type Documentation

27.40.4.1 enum starpu sched component properties

flags for starpu\_sched\_component::properties

**Enumerator:** 

```
STARPU_SCHED_COMPONENT_HOMOGENEOUS indicate that all workers have the same starpu_worker-archtype
```

**STARPU\_SCHED\_COMPONENT\_SINGLE\_MEMORY\_NODE** indicate that all workers have the same memory component

```
27.40.5 Function Documentation
27.40.5.1 struct starpu_sched_tree * starpu_sched_tree_create ( unsigned sched_ctx_id ) [read]
create a empty initialized starpu_sched_tree
27.40.5.2 void starpu_sched_tree_destroy ( struct starpu_sched_tree * tree )
destroy tree and free all non shared component in it.
27.40.5.3 void starpu_sched_tree_update_workers ( struct starpu_sched_tree * t )
recursively set all starpu sched component::workers, do not take into account shared parts (except workers).
27.40.5.4 void starpu_sched_tree_update_workers_in_ctx ( struct starpu_sched_tree * t )
recursively set all starpu_sched_component::workers_in_ctx, do not take into account shared parts (except workers)
27.40.5.5 int starpu_sched_tree_push_task ( struct starpu_task * task )
compatibility with starpu_sched_policy interface
27.40.5.6 void starpu_sched_tree_add_workers ( unsigned sched_ctx_id, int * workerids, unsigned nworkers )
compatibility with starpu_sched_policy interface
27.40.5.7 void starpu_sched_tree_remove_workers ( unsigned sched_ctx_id, int * workerids, unsigned nworkers )
compatibility with starpu_sched_policy interface
27.40.5.8 void starpu_sched_component_connect ( struct starpu_sched_component * parent, struct
          starpu sched component * child )
Attaches component child to parent parent. Some component may accept only one child, others accept several
(e.g. MCT)
27.40.5.9 void starpu_sched_component_destroy ( struct starpu_sched_component * component )
free data allocated by starpu_sched_component_create and call component->deinit_data(component) set to null
the member starpu_sched_component::fathers[sched_ctx_id] of all child if its equal to component
```

27.40.5.10 void starpu\_sched\_component\_destroy\_rec ( struct starpu\_sched\_component \* component ) recursively destroy non shared parts of a component 's tree 27.40.5.11 int starpu\_sched\_component\_can\_execute\_task ( struct starpu\_sched\_component \* component, struct starpu task \* task ) return true iff component can execute task, this function take into account the workers available in the scheduling context 27.40.5.12 int starpu\_sched\_component\_execute\_preds ( struct starpu\_sched\_component \* component, struct starpu\_task \* task, double \* length ) return a non null value if component can execute task. write the execution prediction length for the best implementation of the best worker available and write this at length address. this result is more relevant if starpu sched component::is homogeneous is non null. if a worker need to be calibrated for an implementation, nan is set to length. 27.40.5.13 double starpu\_sched\_component\_transfer\_length ( struct starpu\_sched\_component \* component, struct starpu\_task \* task ) return the average time to transfer task data to underlying component workers. 27.40.5.14 struct starpu sched component \* starpu\_sched\_component\_worker\_get ( unsigned sched\_ctx, int workerid ) [read] return the struct starpu sched component corresponding to workerid. Undefined if workerid is not a valid workerid 27.40.5.15 int starpu\_sched\_component\_worker\_get\_workerid ( struct starpu\_sched\_component \* worker\_component ) return the workerid of worker\_component, undefined if starpu\_sched\_component\_is\_worker(worker\_component) == 0 27.40.5.16 int starpu\_sched\_component\_is\_worker ( struct starpu\_sched\_component \* component ) return true iff component is a worker component 27.40.5.17 int starpu\_sched\_component\_is\_simple\_worker ( struct starpu\_sched\_component \* component ) return true iff component is a simple worker component 27.40.5.18 int starpu\_sched\_component\_is\_combined\_worker ( struct starpu\_sched\_component \* component ) return true iff component is a combined worker component 27.40.5.19 void starpu\_sched\_component\_worker\_pre\_exec\_hook ( struct starpu\_task \* task )

compatibility with <a href="mailto:starpu\_sched\_policy">starpu\_sched\_policy</a> interface update predictions for workers

```
27.40.5.20 void starpu_sched_component_worker_post_exec_hook ( struct starpu_task * task )
compatibility with starpu_sched_policy interface
          struct starpu sched component * starpu_sched_component_fifo_create ( struct starpu sched tree * tree,
27.40.5.21
           struct starpu_sched_component_fifo_data * fifo_data ) [read]
Return a struct starpu sched component with a fifo. A stable sort is performed according to tasks priorities. A push-
task call on this component does not perform recursive calls, underlying components will have to call pop task to
get it. starpu sched component::estimated end function compute the estimated length by dividing the sequential
length by the number of underlying workers. Do not take into account tasks that are currently executed.
27.40.5.22 int starpu_sched_component_is_fifo ( struct starpu_sched_component * component )
return true iff component is a fifo component
27.40.5.23 struct starpu sched component * starpu_sched_component_prio_create ( struct starpu sched tree * tree,
           struct starpu sched component prio data * prio_data ) [read]
todo
27.40.5.24 int starpu_sched_component_is_prio ( struct starpu_sched_component * component )
todo
27.40.5.25 int starpu_sched_tree_work_stealing_push_task ( struct starpu_task * task )
undefined if there is no work stealing component in the scheduler. If any, task is pushed in a default way if the
caller is the application, and in the caller's fifo if its a worker.
27.40.5.26 int starpu_sched_component_is_work_stealing ( struct starpu_sched_component * component )
return true iff component is a work stealing component
27.40.5.27 int starpu_sched_component_is_random ( struct starpu_sched_component * )
return true iff component is a random component
27.40.5.28 int starpu_sched_component_is_eager ( struct starpu_sched_component * )
todo
27.40.5.29 int starpu_sched_component_is_eager_calibration ( struct starpu_sched_component * )
todo
27.40.5.30 struct starpu sched component * starpu_sched_component_mct_create ( struct starpu sched tree * tree,
           struct starpu_sched component mct data * mct_data ) [read]
create a component with mct_data paremeters. the mct component doesnt do anything but pushing tasks on no_-
```

perf\_model\_component and calibrating\_component

```
27.40.5.31 int starpu_sched_component_is_mct ( struct starpu_sched_component * component )
todo
27.40.5.32 struct starpu sched component * starpu_sched_component_heft_create ( struct starpu sched tree * tree,
          struct starpu sched component mct data * mct_data ) [read]
this component perform a heft scheduling
27.40.5.33 int starpu_sched_component_is_heft ( struct starpu_sched_component * component )
return true iff component is a heft component
27.40.5.34 struct starpu sched component * starpu_sched_component_perfmodel_select_create ( struct
          starpu sched tree * tree, struct starpu sched component perfmodel select data *
          perfmodel_select_data ) [read]
todo
27.40.5.35 int starpu_sched_component_is_perfmodel_select ( struct starpu_sched_component * component )
todo
27.40.5.36 struct starpu_sched_component_composed_recipe * starpu_sched_component_composed_recipe_create (
          void ) [read]
return an empty recipe for a composed component, it should not be used without modification
27.40.5.37 struct starpu_sched_component_composed_recipe * starpu_sched_component_composed_recipe-
          _create_singleton ( struct starpu sched component *(*)(struct starpu sched tree *tree, void *arg)
          create_component, void * arg ) [read]
return a recipe to build a composed component with a create_component
27.40.5.38 void starpu_sched_component_composed_recipe_add( struct starpu_sched_component_composed_recipe
          * recipe, struct starpu sched component *(*)(struct starpu sched tree *tree, void *arg)
          create_component, void * arg )
add create_component under all previous components in recipe
27.40.5.39 void starpu_sched_component_composed_recipe_destroy ( struct starpu_sched_component_composed_-
          recipe * )
destroy composed_sched_component, this should be done after starpu_sched_component_composed_-
component create was called
27.40.5.40 struct starpu sched component * starpu_sched_component_composed_component_create ( struct
          starpu sched tree * tree, struct starpu sched component composed recipe * recipe ) [read]
create a component that behave as all component of recipe where linked. Except that you cant use starpu sched -
component_is_foo function if recipe contain a single create_foo arg_foo pair, create_foo(arg_foo) is returned instead
```

of a composed component

27.40.5.41 struct starpu\_sched\_tree \* starpu\_sched\_component\_make\_scheduler ( unsigned sched\_ctx\_id, struct starpu\_sched\_component\_specs s ) [read]

this function build a scheduler for  $sched\_ctx\_id$  according to s and the hwloc topology of the machine.

# **Chapter 28**

# File Index

# 28.1 File List

Here is a list of all documented files with brief descriptions:

sc_hypervisor.h
sc_hypervisor_config.h
sc_hypervisor_lp.h
sc_hypervisor_monitoring.h
sc_hypervisor_policy.h
starpu.h
starpu_bitmap.h
starpu_bound.h
starpu_config.h
starpu_cublas.h
starpu_cuda.h
starpu_data.h
starpu_data_filters.h
starpu_data_interfaces.h
starpu_deprecated_api.h
starpu_disk.h
starpu_driver.h
starpu_expert.h
starpu_fxt.h
starpu_hash.h
starpu_mic.h
starpu_mpi.h
starpu_opencl.h
starpu_openmp.h
starpu_perfmodel.h
starpu_profiling.h
starpu_rand.h
starpu_scc.h
starpu_sched_component.h
starpu_sched_ctx.h
starpu_sched_ctx_hypervisor.h
starpu_scheduler.h
starpu_sink.h
starpu_stdlib.h
starpu_task.h
starpu_task_bundle.h
starpu_task_list.h
starnu task util h

344 File Index

arpu_thread.h	
arpu_thread_util.h	377
arpu_top.h	378
arpu_tree.h	379
arpu_util.h	379
arpu_worker.h	381
arpufft.h	384

# **Chapter 29**

# **File Documentation**

# 29.1 starpu.h File Reference

```
#include <stdlib.h>
#include <stdint.h>
#include <starpu_config.h>
#include <starpu_opencl.h>
#include <starpu_thread.h>
#include <starpu_thread_util.h>
#include <starpu_util.h>
#include <starpu data.h>
#include <starpu_disk.h>
#include <starpu_data_interfaces.h>
#include <starpu_data_filters.h>
#include <starpu_stdlib.h>
#include <starpu_perfmodel.h>
#include <starpu_worker.h>
#include <starpu_task.h>
#include <starpu_task_list.h>
#include <starpu_task_util.h>
#include <starpu_sched_ctx.h>
#include <starpu_expert.h>
#include <starpu_rand.h>
#include <starpu_cuda.h>
#include <starpu_cublas.h>
#include <starpu_bound.h>
#include <starpu_hash.h>
#include <starpu_profiling.h>
#include <starpu_top.h>
#include <starpu_fxt.h>
#include <starpu_driver.h>
#include <starpu_tree.h>
#include <starpu_openmp.h>
#include <starpu_simgrid_wrap.h>
#include <starpu_bitmap.h>
#include "starpu_deprecated_api.h"
```

# **Data Structures**

· struct starpu\_conf

346 File Documentation

#### **Functions**

- int starpu\_conf\_init (struct starpu\_conf \*conf)
- int starpu init (struct starpu conf \*conf) STARPU WARN UNUSED RESULT
- int starpu\_initialize (struct starpu\_conf \*user\_conf, int \*argc, char \*\*\*argv)
- void starpu pause (void)
- void starpu\_resume (void)
- · void starpu shutdown (void)
- void starpu\_topology\_print (FILE \*f)
- int starpu\_asynchronous\_copy\_disabled (void)
- · int starpu asynchronous cuda copy disabled (void)
- int starpu\_asynchronous\_opencl\_copy\_disabled (void)
- int starpu\_asynchronous\_mic\_copy\_disabled (void)
- void starpu display stats ()
- void starpu get version (int \*major, int \*minor, int \*release)

### 29.1.1 Detailed Description

# 29.2 starpu\_bitmap.h File Reference

### **Functions**

- struct starpu bitmap \* starpu bitmap create (void)
- void starpu\_bitmap\_destroy (struct starpu\_bitmap \*b)
- void starpu bitmap set (struct starpu bitmap \*b, int e)
- void starpu\_bitmap\_unset (struct starpu\_bitmap \*b, int e)
- void starpu\_bitmap\_unset\_all (struct starpu\_bitmap \*b)
- int starpu\_bitmap\_get (struct starpu\_bitmap \*b, int e)
- void starpu\_bitmap\_unset\_and (struct starpu\_bitmap \*a, struct starpu\_bitmap \*b, struct starpu\_bitmap \*c)
- void starpu bitmap or (struct starpu bitmap \*a, struct starpu bitmap \*b)
- int starpu\_bitmap\_and\_get (struct starpu\_bitmap \*b1, struct starpu\_bitmap \*b2, int e)
- int starpu\_bitmap\_cardinal (struct starpu\_bitmap \*b)
- int starpu\_bitmap\_first (struct starpu\_bitmap \*b)
- int starpu\_bitmap\_last (struct starpu\_bitmap \*b)
- int starpu bitmap next (struct starpu bitmap \*b, int e)
- int starpu\_bitmap\_has\_next (struct starpu\_bitmap \*b, int e)

# 29.2.1 Detailed Description

# 29.3 starpu\_bound.h File Reference

#include <stdio.h>

#### **Functions**

- void starpu\_bound\_start (int deps, int prio)
- void starpu\_bound\_stop (void)
- void starpu\_bound\_print\_dot (FILE \*output)
- void starpu bound compute (double \*res, double \*integer res, int integer)
- void starpu bound print lp (FILE \*output)
- void starpu\_bound\_print\_mps (FILE \*output)
- void starpu\_bound\_print (FILE \*output, int integer)

### 29.3.1 Detailed Description

# 29.4 starpu\_config.h File Reference

#include <sys/types.h>

#### Macros

- #define STARPU MAJOR VERSION
- #define STARPU\_MINOR\_VERSION
- #define STARPU RELEASE VERSION
- #define STARPU\_USE\_CPU
- #define STARPU USE CUDA
- #define STARPU USE OPENCL
- #define STARPU USE MIC
- #define STARPU\_USE\_SCC
- #define STARPU\_SIMGRID
- #define STARPU\_SIMGRID\_HAVE\_XBT\_BARRIER\_INIT
- #define STARPU HAVE SIMGRID MSG H
- #define STARPU\_HAVE\_ICC
- #define STARPU\_ATLAS
- #define STARPU GOTO
- #define STARPU MKL
- #define STARPU SYSTEM BLAS
- #define STARPU\_BUILD\_DIR
- #define STARPU\_OPENCL\_DATADIR
- #define STARPU\_HAVE\_MAGMA
- #define STARPU OPENGL RENDER
- #define STARPU USE GTK
- #define STARPU\_HAVE\_X11
- #define STARPU\_HAVE\_POSIX\_MEMALIGN
- #define STARPU\_HAVE\_MEMALIGN
- #define STARPU\_HAVE\_MALLOC\_H
- #define STARPU HAVE SYNC BOOL COMPARE AND SWAP
- #define STARPU HAVE SYNC VAL COMPARE AND SWAP
- #define STARPU\_HAVE\_SYNC\_FETCH\_AND\_ADD
- #define STARPU HAVE SYNC FETCH AND OR
- #define STARPU\_HAVE\_SYNC\_LOCK\_TEST\_AND\_SET
- #define STARPU HAVE SYNC SYNCHRONIZE
- #define STARPU\_MODEL\_DEBUG
- #define STARPU\_NO\_ASSERT
- #define STARPU\_HAVE\_FFTW
- #define STARPU\_HAVE\_FFTWF
- #define STARPU\_HAVE\_FFTWL
- #define STARPU\_HAVE\_CURAND#define STARPU MAXNODES
- #define STARPU NMAXBUFS
- #define STARPU MAXCPUS
- #define STARPU MAXCUDADEVS
- #define STARPU MAXOPENCLDEVS
- #define STARPU MAXMICDEVS
- #define STARPU MAXSCCDEVS

348 File Documentation

- #define STARPU NMAXWORKERS
- #define STARPU\_NMAX\_SCHED\_CTXS
- #define STARPU\_MAXIMPLEMENTATIONS
- #define STARPU\_MAXMPKERNELS
- #define STARPU USE SC HYPERVISOR
- #define STARPU\_SC\_HYPERVISOR\_DEBUG
- #define STARPU HAVE GLPK H
- #define STARPU\_HAVE\_LIBNUMA
- #define STARPU\_HAVE\_WINDOWS
- #define STARPU\_LINUX\_SYS
- #define STARPU\_HAVE\_UNSETENV
- #define STARPU\_HAVE\_UNISTD\_H
- #define starpu func
- #define starpu inline
- #define STARPU QUICK CHECK
- #define STARPU\_USE\_DRAND48
- #define STARPU\_USE\_ERAND48\_R
- #define STARPU\_HAVE\_NEARBYINTF
- #define STARPU\_HAVE\_RINTF
- #define STARPU\_USE\_TOP
- #define STARPU\_HAVE\_HWLOC
- #define STARPU\_HAVE\_PTHREAD\_SPIN\_LOCK
- #define STARPU HAVE PTHREAD BARRIER
- #define STARPU\_HAVE\_STRUCT\_TIMESPEC
- #define STARPU\_HAVE\_HELGRIND\_H

#### Initialisation

• #define STARPU\_OPENMP

# Initialisation

• #define STARPU USE MPI

# **Typedefs**

typedef ssize\_t starpu\_ssize\_t

# 29.4.1 Detailed Description

# 29.5 starpu\_cublas.h File Reference

### **Functions**

- void starpu\_cublas\_init (void)
- void starpu\_cublas\_shutdown (void)

# 29.5.1 Detailed Description

# 29.6 starpu\_cuda.h File Reference

```
#include <starpu_config.h>
#include <cuda.h>
#include <cuda_runtime.h>
#include <cuda_runtime_api.h>
```

# **Macros**

- #define STARPU\_CUBLAS\_REPORT\_ERROR(status)
- #define STARPU\_CUDA\_REPORT\_ERROR(status)

### **Functions**

- void starpu\_cublas\_report\_error (const char \*func, const char \*file, int line, int status)
- void starpu\_cuda\_report\_error (const char \*func, const char \*file, int line, cudaError\_t status)
- cudaStream\_t starpu\_cuda\_get\_local\_stream (void)
- struct cudaDeviceProp \* starpu\_cuda\_get\_device\_properties (unsigned workerid)
- int starpu\_cuda\_copy\_async\_sync (void \*src\_ptr, unsigned src\_node, void \*dst\_ptr, unsigned dst\_node, size\_t ssize, cudaStream\_t stream, enum cudaMemcpyKind kind)
- void starpu\_cuda\_set\_device (unsigned devid)

### 29.6.1 Detailed Description

# 29.7 starpu\_data.h File Reference

```
#include <starpu.h>
```

#### **Data Structures**

struct starpu\_data\_descr

# Macros

- #define starpu\_data\_malloc\_pinned\_if\_possible
- #define starpu\_data\_free\_pinned\_if\_possible
- #define STARPU\_MAIN\_RAM

# **Typedefs**

- typedef struct starpu data state \* starpu data handle t
- typedef struct starpu\_arbiter \* starpu\_arbiter\_t

350 File Documentation

### **Enumerations**

enum starpu\_data\_access\_mode {
 STARPU\_NONE, STARPU\_R, STARPU\_W, STARPU\_RW,
 STARPU\_SCRATCH, STARPU\_REDUX, STARPU\_COMMUTE, STARPU\_SSEND,
 STARPU\_ACCESS\_MODE\_MAX }

enum starpu\_node\_kind {
 STARPU\_UNUSED, STARPU\_CPU\_RAM, STARPU\_CUDA\_RAM, STARPU\_OPENCL\_RAM,
 STARPU\_DISK\_RAM, STARPU\_MIC\_RAM, STARPU\_SCC\_RAM, STARPU\_SCC\_SHM }

# **Functions**

- void starpu\_data\_display\_memory\_stats ()
- unsigned starpu\_worker\_get\_memory\_node (unsigned workerid)
- unsigned starpu memory nodes get count (void)
- enum starpu\_node\_kind starpu\_node\_get\_kind (unsigned node)
- · void starpu data set sequential consistency flag (starpu data handle t handle, unsigned flag)
- · unsigned starpu data get sequential consistency flag (starpu data handle t handle)
- · unsigned starpu data get default sequential consistency flag (void)
- void starpu\_data\_set\_default\_sequential\_consistency\_flag (unsigned flag)
- unsigned starpu\_data\_test\_if\_allocated\_on\_node (starpu\_data\_handle\_t handle, unsigned memory\_node)
- void starpu\_memchunk\_tidy (unsigned memory\_node)

# **Basic Data Management API**

Data management is done at a high-level in StarPU: rather than accessing a mere list of contiguous buffers, the tasks may manipulate data that are described by a high-level construct which we call data interface.

An example of data interface is the "vector" interface which describes a contiguous data array on a spefic memory node. This interface is a simple structure containing the number of elements in the array, the size of the elements, and the address of the array in the appropriate address space (this address may be invalid if there is no valid copy of the array in the memory node). More informations on the data interfaces provided by StarPU are given in Data Interfaces.

When a piece of data managed by StarPU is used by a task, the task implementation is given a pointer to an interface describing a valid copy of the data that is accessible from the current processing unit.

Every worker is associated to a memory node which is a logical abstraction of the address space from which the processing unit gets its data. For instance, the memory node associated to the different CPU workers represents main memory (RAM), the memory node associated to a GPU is DRAM embedded on the device. Every memory node is identified by a logical index which is accessible from the function starpu\_worker\_get\_memory\_node(). When registering a piece of data to StarPU, the specified memory node indicates where the piece of data initially resides (we also call this memory node the home node of a piece of data).

- void starpu\_data\_unregister (starpu\_data\_handle\_t handle)
- void starpu\_data\_unregister\_no\_coherency (starpu\_data\_handle\_t handle)
- · void starpu data unregister submit (starpu data handle t handle)
- · void starpu data invalidate (starpu data handle t handle)
- void starpu\_data\_invalidate\_submit (starpu\_data\_handle\_t handle)
- void starpu\_data\_advise\_as\_important (starpu\_data\_handle\_t handle, unsigned is\_important)
- int starpu\_data\_request\_allocation (starpu\_data\_handle\_t handle, unsigned node)
- int starpu data fetch on node (starpu data handle t handle, unsigned node, unsigned async)
- int starpu\_data\_prefetch\_on\_node (starpu\_data\_handle\_t handle, unsigned node, unsigned async)
- int starpu\_data\_idle\_prefetch\_on\_node (starpu\_data\_handle\_t handle, unsigned node, unsigned async)
- void starpu\_data\_wont\_use (starpu\_data\_handle\_t handle)
- void starpu\_data\_set\_wt\_mask (starpu\_data\_handle\_t handle, uint32\_t wt\_mask)
- void starpu\_data\_query\_status (starpu\_data\_handle\_t handle, int memory\_node, int \*is\_allocated, int \*is-valid, int \*is requested)
- void starpu\_data\_set\_reduction\_methods (starpu\_data\_handle\_t handle, struct starpu\_codelet \*redux\_cl, struct starpu\_codelet \*init\_cl)
- struct starpu\_data\_interface\_ops \* starpu\_data\_get\_interface\_ops (starpu\_data\_handle\_t handle)

# Access registered data from the application

- #define STARPU\_DATA\_ACQUIRE\_CB(handle, mode, code)
- int starpu\_data\_acquire (starpu\_data\_handle\_t handle, enum starpu\_data\_access\_mode mode)
- int starpu\_data\_acquire\_on\_node (starpu\_data\_handle\_t handle, int node, enum starpu\_data\_access\_mode mode)
- int starpu\_data\_acquire\_cb (starpu\_data\_handle\_t handle, enum starpu\_data\_access\_mode mode, void(\*callback)(void \*), void \*arg)
- int starpu\_data\_acquire\_on\_node\_cb (starpu\_data\_handle\_t handle, int node, enum starpu\_data\_access\_mode mode, void(\*callback)(void \*), void \*arg)
- int starpu\_data\_acquire\_cb\_sequential\_consistency (starpu\_data\_handle\_t handle, enum starpu\_data\_access\_mode mode, void(\*callback)(void \*), void \*arg, int sequential\_consistency)
- int starpu\_data\_acquire\_on\_node\_cb\_sequential\_consistency (starpu\_data\_handle\_t handle, int node, enum starpu\_data\_access mode mode, void(\*callback)(void \*), void \*arg, int sequential\_consistency)
- void starpu data release (starpu data handle t handle)
- void starpu data release on node (starpu data handle t handle, int node)
- starpu arbiter t starpu arbiter create (void)
- void starpu\_data\_assign\_arbiter (starpu\_data\_handle\_t handle, starpu\_arbiter\_t arbiter)
- · void starpu arbiter destroy (starpu arbiter t arbiter)

# 29.7.1 Detailed Description

# 29.8 starpu\_data\_filters.h File Reference

```
#include <starpu.h>
#include <stdarg.h>
```

### **Data Structures**

· struct starpu\_data\_filter

# **Functions**

# Basic API

- void starpu data partition (starpu data handle t initial handle, struct starpu data filter \*f)
- void starpu data unpartition (starpu data handle t root data, unsigned gathering node)
- int starpu\_data\_get\_nb\_children (starpu\_data\_handle\_t handle)
- starpu data handle t starpu data get child (starpu data handle t handle, unsigned i)
- starpu\_data\_handle\_t starpu\_data\_get\_sub\_data (starpu\_data\_handle\_t root\_data, unsigned depth,...)
- starpu\_data\_handle\_t starpu\_data\_vget\_sub\_data (starpu\_data\_handle\_t root\_data, unsigned depth, valist pa)
- void starpu data map filters (starpu data handle t root data, unsigned nfilters,...)
- void starpu\_data\_vmap\_filters (starpu\_data\_handle\_t root\_data, unsigned nfilters, va\_list pa)

# Asynchronous API

- void starpu\_data\_partition\_plan (starpu\_data\_handle\_t initial\_handle, struct starpu\_data\_filter \*f, starpu-data handle t \*children)
- void starpu\_data\_partition\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children)
- void starpu\_data\_partition\_readonly\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children)
- void starpu\_data\_partition\_readwrite\_upgrade\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children)

352 File Documentation

void starpu\_data\_unpartition\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children, int gathering\_node)

- void starpu\_data\_unpartition\_readonly\_submit (starpu\_data\_handle\_t initial\_handle, unsigned nparts, starpu\_data\_handle\_t \*children, int gathering\_node)
- void starpu\_data\_partition\_clean (starpu\_data\_handle\_t root\_data, unsigned nparts, starpu\_data\_handle-t \*children)

#### **Predefined BCSR Filter Functions**

This section gives a partial list of the predefined partitioning functions for BCSR data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h.

- void starpu\_bcsr\_filter\_canonical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_csr\_filter\_vertical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)

#### **Predefined Matrix Filter Functions**

This section gives a partial list of the predefined partitioning functions for matrix data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h.

- void starpu\_matrix\_filter\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_matrix\_filter\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_matrix\_filter\_vertical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_matrix\_filter\_vertical\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu data filter \*f, unsigned id, unsigned nparts)

### **Predefined Vector Filter Functions**

This section gives a partial list of the predefined partitioning functions for vector data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h.

- void starpu\_vector\_filter\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_vector\_filter\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_vector\_filter\_list (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_vector\_filter\_divide\_in\_2 (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)

#### **Predefined Block Filter Functions**

This section gives a partial list of the predefined partitioning functions for block data. Examples on how to use them are shown in Partitioning Data. The complete list can be found in the file starpu\_data\_filters.h. A usage example is available in examples/filters/shadow3d.c

- void starpu\_block\_filter\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpu\_data\_-filter \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_vertical\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_-filter \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_vertical\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpudata filter \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_depth\_block (void \*father\_interface, void \*child\_interface, struct starpu\_data\_filter
   \*f, unsigned id, unsigned nparts)
- void starpu\_block\_filter\_depth\_block\_shadow (void \*father\_interface, void \*child\_interface, struct starpudata filter \*f, unsigned id, unsigned nparts)

### 29.8.1 Detailed Description

#### 29.9 starpu\_data\_interfaces.h File Reference

```
#include <starpu.h>
#include <cuda_runtime.h>
```

#### **Data Structures**

- · struct starpu\_data\_copy\_methods
- struct starpu\_data\_interface\_ops
- struct starpu\_matrix\_interface
- struct starpu coo interface
- struct starpu\_block\_interface
- struct starpu\_vector\_interface
- · struct starpu\_variable\_interface
- · struct starpu\_csr\_interface
- · struct starpu\_bcsr\_interface
- struct starpu\_multiformat\_data\_interface\_ops
- · struct starpu multiformat interface

#### **Macros**

- #define STARPU MULTIFORMAT GET CPU PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_CUDA\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_OPENCL\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_MIC\_PTR(interface)
- #define STARPU\_MULTIFORMAT\_GET\_NX(interface)

# **Accessing COO Data Interfaces**

- #define STARPU COO GET COLUMNS(interface)
- #define STARPU\_COO\_GET\_COLUMNS\_DEV\_HANDLE(interface)
- #define STARPU\_COO\_GET\_ROWS(interface)
- #define STARPU\_COO\_GET\_ROWS\_DEV\_HANDLE(interface)
- #define STARPU\_COO\_GET\_VALUES(interface)
  #define STARPU\_COO\_GET\_VALUES\_DEV\_HANDLE(interface)
  #define STARPU\_COO\_GET\_OFFSET
- #define STARPU\_COO\_GET\_NX(interface)
- #define STARPU\_COO\_GET\_NY(interface)
- #define STARPU\_COO\_GET\_NVALUES(interface)#define STARPU\_COO\_GET\_ELEMSIZE(interface)

# **Typedefs**

typedef cudaStream\_t starpu\_cudaStream\_t

#### **Enumerations**

enum starpu\_data\_interface\_id { STARPU UNKNOWN INTERFACE ID, STARPU MATRIX INTERFACE ID, STARPU BLOCK INTERF-ACE ID, STARPU VECTOR INTERFACE ID, STARPU CSR INTERFACE ID, STARPU BCSR INTERFACE ID, STARPU VARIABLE INTERFACE I-D, STARPU\_VOID\_INTERFACE\_ID, STARPU\_MULTIFORMAT\_INTERFACE\_ID, STARPU\_COO\_INTERFACE\_ID, STARPU\_MAX\_INTERFA-CE ID }

354 File Documentation

### **Functions**

void starpu\_multiformat\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, void \*ptr, uint32 t nobjects, struct starpu multiformat data interface ops \*format ops)

# **Defining Interface**

Applications can provide their own interface as shown in Defining A New Data Interface.

- int starpu\_interface\_copy (uintptr\_t src, size\_t src\_offset, unsigned src\_node, uintptr\_t dst, size\_t dst\_offset, unsigned dst node, size t size, void \*async data)
- uintptr\_t starpu\_malloc\_on\_node\_flags (unsigned dst\_node, size\_t size, int flags)
- uintptr\_t starpu\_malloc\_on\_node (unsigned dst\_node, size\_t size)
- void starpu\_free\_on\_node\_flags (unsigned dst\_node, uintptr\_t addr, size\_t size, int flags)
- void starpu\_free\_on\_node (unsigned dst\_node, uintptr\_t addr, size\_t size)
- void starpu\_malloc\_on\_node\_set\_default\_flags (unsigned node, int flags)
- int starpu\_data\_interface\_get\_next\_id (void)

#### **Basic Data Management API**

Data management is done at a high-level in StarPU: rather than accessing a mere list of contiguous buffers, the tasks may manipulate data that are described by a high-level construct which we call data interface.

An example of data interface is the "vector" interface which describes a contiguous data array on a spefic memory node. This interface is a simple structure containing the number of elements in the array, the size of the elements, and the address of the array in the appropriate address space (this address may be invalid if there is no valid copy of the array in the memory node). More informations on the data interfaces provided by StarPU are given in Data Interfaces.

When a piece of data managed by StarPU is used by a task, the task implementation is given a pointer to an interface describing a valid copy of the data that is accessible from the current processing unit.

Every worker is associated to a memory node which is a logical abstraction of the address space from which the processing unit gets its data. For instance, the memory node associated to the different CPU workers represents main memory (RAM), the memory node associated to a GPU is DRAM embedded on the device. Every memory node is identified by a logical index which is accessible from the function <a href="mailto:starpu\_worker\_get\_memory\_node">starpu\_worker\_get\_memory\_node</a>(). When registering a piece of data to StarPU, the specified memory node indicates where the piece of data initially resides (we also call this memory node the home node of a piece of data).

- void starpu\_data\_register (starpu\_data\_handle\_t \*handleptr, unsigned home\_node, void \*data\_interface, struct starpu\_data\_interface\_ops \*ops)
- void starpu\_data\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node)
- void starpu\_data\_register\_same (starpu\_data\_handle\_t \*handledst, starpu\_data\_handle\_t handlesrc)
- starpu\_data\_handle\_t starpu\_data\_lookup (const void \*ptr)

# **Accessing Data Interfaces**

Each data interface is provided with a set of field access functions. The ones using a void \* parameter aimed to be used in codelet implementations (see for example the code in Vector Scaling Using StarPU's API).

- void \* starpu\_data\_handle\_to\_pointer (starpu\_data\_handle\_t handle, unsigned node)
- void \* starpu\_data\_get\_local\_ptr (starpu\_data\_handle\_t handle)
- enum starpu\_data\_interface\_id starpu\_data\_get\_interface\_id (starpu\_data\_handle\_t handle)
- int starpu data pack (starpu data handle t handle, void \*\*ptr, starpu ssize t \*count)
- int starpu\_data\_unpack (starpu\_data\_handle\_t handle, void \*ptr, size\_t count)
- size\_t starpu\_data\_get\_size (starpu\_data\_handle\_t handle)

#### **Registering Data**

There are several ways to register a memory region so that it can be managed by StarPU. The functions below allow the registration of vectors, 2D matrices, 3D matrices as well as BCSR and CSR sparse matrices.

- void \* starpu\_data\_get\_interface\_on\_node (starpu\_data\_handle\_t handle, unsigned memory\_node)
- void starpu\_matrix\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, uint32\_t ld, uint32\_t nx, uint32\_t ny, size\_t elemsize)

- void starpu\_matrix\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev-handle, size t offset, uint32 t ld)
- void starpu\_coo\_data\_register (starpu\_data\_handle\_t \*handleptr, unsigned home\_node, uint32\_t nx, uint32\_t ny, uint32\_t n\_values, uint32\_t \*columns, uint32\_t \*rows, uintptr\_t values, size\_t elemsize)
- void starpu\_block\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, uint32\_t ldy, uint32\_t ldz, uint32\_t nx, uint32\_t nz, size\_t elemsize)
- void starpu\_block\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev\_handle, size t offset, uint32 t ldy, uint32 t ldz)
- void starpu\_vector\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, uint32 t nx, size t elemsize)
- void starpu\_vector\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev-handle, size t offset)
- void starpu\_variable\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uintptr\_t ptr, size t size)
- void starpu\_variable\_ptr\_register (starpu\_data\_handle\_t handle, unsigned node, uintptr\_t ptr, uintptr\_t dev handle, size t offset)
- void starpu void data register (starpu data handle t \*handle)
- void starpu\_csr\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uint32\_t nnz, uint32\_t nrow, uintptr\_t nzval, uint32\_t \*colind, uint32\_t \*rowptr, uint32\_t firstentry, size\_t elemsize)
- void starpu\_bcsr\_data\_register (starpu\_data\_handle\_t \*handle, unsigned home\_node, uint32\_t nnz, uint32\_t nrow, uintptr\_t nzval, uint32\_t \*colind, uint32\_t \*rowptr, uint32\_t firstentry, uint32\_t r, uint32\_t c, size\_t elemsize)

### **Variables**

- · struct starpu data interface ops starpu interface matrix ops
- struct starpu\_data\_interface\_ops starpu\_interface\_coo\_ops
- · struct starpu data interface ops starpu interface block ops
- struct starpu\_data\_interface\_ops starpu\_interface\_vector\_ops
- struct starpu\_data\_interface\_ops starpu\_interface\_variable\_ops
- struct starpu\_data\_interface\_ops starpu\_interface\_void\_ops
- struct starpu\_data\_interface\_ops starpu\_interface\_csr\_ops
- struct starpu\_data\_interface\_ops starpu\_interface\_bcsr\_ops

# **Accessing Variable Data Interfaces**

- #define STARPU VARIABLE GET PTR(interface)
- #define STARPU VARIABLE GET OFFSET(interface)
- #define STARPU\_VARIABLE\_GET\_ELEMSIZE(interface)
- #define STARPU VARIABLE GET DEV HANDLE(interface)
- size t starpu variable get elemsize (starpu data handle t handle)
- uintptr\_t starpu\_variable\_get\_local\_ptr (starpu\_data\_handle\_t handle)

# **Accessing Vector Data Interfaces**

- #define STARPU VECTOR GET PTR(interface)
- #define STARPU\_VECTOR\_GET\_DEV\_HANDLE(interface)
- #define STARPU\_VECTOR\_GET\_OFFSET(interface)
- #define STARPU VECTOR GET NX(interface)
- #define STARPU VECTOR GET ELEMSIZE(interface)
- #define STARPU VECTOR GET SLICE BASE(interface)
- uint32\_t starpu\_vector\_get\_nx (starpu\_data\_handle\_t handle)
- size\_t starpu\_vector\_get\_elemsize (starpu\_data\_handle\_t handle)
- uintptr\_t starpu\_vector\_get\_local\_ptr (starpu\_data\_handle\_t handle)

356 File Documentation

### **Accessing Matrix Data Interfaces**

- #define STARPU MATRIX GET PTR(interface)
- #define STARPU\_MATRIX\_GET\_DEV\_HANDLE(interface)
- #define STARPU MATRIX GET OFFSET(interface)
- #define STARPU MATRIX GET NX(interface)
- #define STARPU MATRIX GET NY(interface)
- #define STARPU MATRIX GET LD(interface)
- #define STARPU\_MATRIX\_GET\_ELEMSIZE(interface)
- uint32\_t starpu\_matrix\_get\_nx (starpu\_data\_handle\_t handle)
- uint32 t starpu matrix get ny (starpu data handle t handle)
- uint32\_t starpu\_matrix\_get\_local\_ld (starpu\_data\_handle\_t handle)
- uintptr\_t starpu\_matrix\_get\_local\_ptr (starpu\_data\_handle\_t handle)
- size\_t starpu\_matrix\_get\_elemsize (starpu\_data\_handle\_t handle)

# **Accessing Block Data Interfaces**

- #define STARPU BLOCK GET PTR(interface)
- #define STARPU BLOCK GET DEV HANDLE(interface)
- #define STARPU BLOCK GET OFFSET(interface)
- #define STARPU BLOCK GET NX(interface)
- #define STARPU\_BLOCK\_GET\_NY(interface)
- #define STARPU BLOCK GET NZ(interface)
- #define STARPU BLOCK GET LDY(interface)
- #define STARPU\_BLOCK\_GET\_LDZ(interface)
- #define STARPU BLOCK GET ELEMSIZE(interface)
- uint32\_t starpu\_block\_get\_nx (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_block\_get\_ny (starpu\_data\_handle\_t handle)
- uint32 t starpu block get nz (starpu data handle t handle)
- uint32\_t starpu\_block\_get\_local\_ldy (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_block\_get\_local\_ldz (starpu\_data\_handle\_t handle)
- uintptr\_t starpu\_block\_get\_local\_ptr (starpu\_data\_handle\_t handle)
- size t starpu block get elemsize (starpu data handle t handle)

### **Accessing BCSR Data Interfaces**

- #define STARPU BCSR GET NNZ(interface)
- #define STARPU BCSR GET NZVAL(interface)
- #define STARPU\_BCSR\_GET\_NZVAL\_DEV\_HANDLE(interface)
- #define STARPU\_BCSR\_GET\_COLIND(interface)
- #define STARPU BCSR GET COLIND DEV HANDLE(interface)
- #define STARPU BCSR GET ROWPTR(interface)
- #define STARPU BCSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU BCSR GET OFFSET
- uint32\_t starpu\_bcsr\_get\_nnz (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_bcsr\_get\_nrow (starpu\_data\_handle\_t handle)
- uint32 t starpu bcsr get firstentry (starpu data handle t handle)
- uintptr\_t starpu\_bcsr\_get\_local\_nzval (starpu\_data\_handle\_t handle)
- uint32\_t \* starpu\_bcsr\_get\_local\_colind (starpu\_data\_handle\_t handle)
- uint32 t \* starpu bcsr get local rowptr (starpu data handle t handle)
- uint32\_t starpu\_bcsr\_get\_r (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_bcsr\_get\_c (starpu\_data\_handle\_t handle)
- size\_t starpu\_bcsr\_get\_elemsize (starpu\_data\_handle\_t handle)

# **Accessing CSR Data Interfaces**

- #define STARPU\_CSR\_GET\_NNZ(interface)
- #define STARPU CSR GET NROW(interface)
- #define STARPU\_CSR\_GET\_NZVAL(interface)
- #define STARPU\_CSR\_GET\_NZVAL\_DEV\_HANDLE(interface)
- #define STARPU CSR GET COLIND(interface)
- #define STARPU\_CSR\_GET\_COLIND\_DEV\_HANDLE(interface)
- #define STARPU\_CSR\_GET\_ROWPTR(interface)
- #define STARPU CSR GET ROWPTR DEV HANDLE(interface)
- #define STARPU\_CSR\_GET\_OFFSET
- #define STARPU\_CSR\_GET\_FIRSTENTRY(interface)
- #define STARPU\_CSR\_GET\_ELEMSIZE(interface)
- uint32\_t starpu\_csr\_get\_nnz (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_csr\_get\_nrow (starpu\_data\_handle\_t handle)
- uint32\_t starpu\_csr\_get\_firstentry (starpu\_data\_handle\_t handle)
- uintptr\_t starpu\_csr\_get\_local\_nzval (starpu\_data\_handle\_t handle)
- uint32\_t \* starpu\_csr\_get\_local\_colind (starpu\_data\_handle\_t handle)
- uint32\_t \* starpu\_csr\_get\_local\_rowptr (starpu\_data\_handle\_t handle)
- size\_t starpu\_csr\_get\_elemsize (starpu\_data\_handle\_t handle)

### 29.9.1 Detailed Description

# 29.10 starpu\_deprecated\_api.h File Reference

### Macros

· #define starpu permodel history based expected perf

### 29.10.1 Detailed Description

### 29.11 starpu\_disk.h File Reference

```
#include <sys/types.h>
#include <starpu_config.h>
```

#### **Data Structures**

struct starpu\_disk\_ops

- void starpu\_disk\_close (unsigned node, void \*obj, size\_t size)
- void \* starpu\_disk\_open (unsigned node, void \*pos, size\_t size)
- int starpu\_disk\_register (struct starpu\_disk\_ops \*func, void \*parameter, starpu\_ssize\_t size)

### **Variables**

- struct starpu\_disk\_ops starpu\_disk\_stdio\_ops
- struct starpu\_disk\_ops starpu\_disk\_unistd\_ops
- struct starpu\_disk\_ops starpu\_disk\_unistd\_o\_direct\_ops
- struct starpu\_disk\_ops starpu\_disk\_leveldb\_ops

# 29.11.1 Detailed Description

# 29.12 starpu\_driver.h File Reference

```
#include <starpu_config.h>
#include <starpu_opencl.h>
```

### **Data Structures**

- · struct starpu\_driver
- · union starpu\_driver.id

### **Functions**

- int starpu\_driver\_run (struct starpu\_driver \*d)
- void starpu\_drivers\_request\_termination (void)
- int starpu\_driver\_init (struct starpu\_driver \*d)
- int starpu\_driver\_run\_once (struct starpu\_driver \*d)
- int starpu\_driver\_deinit (struct starpu\_driver \*d)

### 29.12.1 Detailed Description

# 29.13 starpu\_expert.h File Reference

```
#include <starpu.h>
```

### **Functions**

- void starpu\_wake\_all\_blocked\_workers (void)
- int starpu\_progression\_hook\_register (unsigned(\*func)(void \*arg), void \*arg)
- void starpu\_progression\_hook\_deregister (int hook\_id)

# 29.13.1 Detailed Description

# 29.14 starpu\_fxt.h File Reference

```
#include <starpu_perfmodel.h>
```

### **Data Structures**

- struct starpu fxt codelet event
- struct starpu\_fxt\_options

### **Macros**

• #define STARPU\_FXT\_MAX\_FILES

### **Functions**

- void starpu\_fxt\_options\_init (struct starpu\_fxt\_options \*options)
- void starpu\_fxt\_generate\_trace (struct starpu\_fxt\_options \*options)
- void starpu\_fxt\_start\_profiling (void)
- void starpu\_fxt\_stop\_profiling (void)
- void starpu\_fxt\_write\_data\_trace (char \*filename\_in)
- void starpu\_fxt\_trace\_user\_event (unsigned long code)

# 29.14.1 Detailed Description

# 29.15 starpu\_hash.h File Reference

```
#include <stdint.h>
#include <stddef.h>
```

### **Functions**

# **Defining Interface**

Applications can provide their own interface as shown in Defining A New Data Interface.

- uint32\_t starpu\_hash\_crc32c\_be\_n (const void \*input, size\_t n, uint32\_t inputcrc)
- uint32\_t starpu\_hash\_crc32c\_be (uint32\_t input, uint32\_t inputcrc)
- uint32\_t starpu\_hash\_crc32c\_string (const char \*str, uint32\_t inputcrc)

# 29.15.1 Detailed Description

# 29.16 starpu\_mic.h File Reference

```
#include <starpu_config.h>
```

### **Typedefs**

typedef void \* starpu\_mic\_func\_symbol\_t

- int starpu\_mic\_register\_kernel (starpu\_mic\_func\_symbol\_t \*symbol, const char \*func\_name)
- starpu\_mic\_kernel\_t starpu\_mic\_get\_kernel (starpu\_mic\_func\_symbol\_t symbol)

### 29.16.1 Detailed Description

# 29.17 starpu\_opencl.h File Reference

```
#include <starpu_config.h>
#include <CL/cl.h>
#include <assert.h>
```

#### **Data Structures**

· struct starpu opencl program

#### **Functions**

# Writing OpenCL kernels

- void starpu opencl get context (int devid, cl context \*context)
- void starpu opencl get device (int devid, cl device id \*device)
- void starpu\_opencl\_get\_queue (int devid, cl\_command\_queue \*queue)
- void starpu\_opencl\_get\_current\_context (cl\_context \*context)
- void starpu\_opencl\_get\_current\_queue (cl\_command\_queue \*queue)
- int starpu\_opencl\_set\_kernel\_args (cl\_int \*err, cl\_kernel \*kernel,...)

### Compiling OpenCL kernels

Source codes for OpenCL kernels can be stored in a file or in a string. StarPU provides functions to build the program executable for each available OpenCL device as a cl\_program object. This program executable can then be loaded within a specific queue as explained in the next section. These are only helpers, Applications can also fill a starpu\_opencl\_program array by hand for more advanced use (e.g. different programs on the different OpenCL devices, for relocation purpose for instance).

- void starpu\_opencl\_load\_program\_source (const char \*source\_file\_name, char \*located\_file\_name, char \*located\_dir name, char \*opencl\_program\_source)
- int starpu\_opencl\_compile\_opencl\_from\_file (const char \*source\_file\_name, const char \*build\_options)
- int starpu\_opencl\_compile\_opencl\_from\_string (const char \*opencl\_program\_source, const char \*file\_-name, const char \*build\_options)
- int starpu\_opencl\_load\_binary\_opencl (const char \*kernel\_id, struct starpu\_opencl\_program \*opencl\_programs)
- int starpu\_opencl\_load\_opencl\_from\_file (const char \*source\_file\_name, struct starpu\_opencl\_program \*opencl\_programs, const char \*build\_options)
- int starpu\_opencl\_load\_opencl\_from\_string (const char \*opencl\_program\_source, struct starpu\_opencl\_program \*opencl\_programs, const char \*build\_options)
- int starpu\_opencl\_unload\_opencl (struct starpu\_opencl\_program \*opencl\_programs)

### Loading OpenCL kernels

- int starpu\_opencl\_load\_kernel (cl\_kernel \*kernel, cl\_command\_queue \*queue, struct starpu\_opencl\_-program \*opencl\_programs, const char \*kernel\_name, int devid)
- int starpu\_opencl\_release\_kernel (cl\_kernel kernel)

#### OpenCL statistics

int starpu\_opencl\_collect\_stats (cl\_event event)

# OpenCL utilities

- #define STARPU\_OPENCL\_DISPLAY\_ERROR(status)
- #define STARPU\_OPENCL\_REPORT\_ERROR(status)
- #define STARPU\_OPENCL\_REPORT\_ERROR\_WITH\_MSG(msg, status)
- const char \* starpu\_opencl\_error\_string (cl\_int status)
- void starpu\_opencl\_display\_error (const char \*func, const char \*file, int line, const char \*msg, cl\_int status)
- static \_\_starpu\_inline void starpu\_opencl\_report\_error (const char \*func, const char \*file, int line, const char \*msg, cl int status)
- cl\_int starpu\_opencl\_allocate\_memory (int devid, cl\_mem \*addr, size\_t size, cl\_mem\_flags flags)
- cl\_int starpu\_opencl\_copy\_ram\_to\_opencl (void \*ptr, unsigned src\_node, cl\_mem buffer, unsigned dst\_node, size t size, size t offset, cl\_event \*event, int \*ret)
- cl\_int starpu\_opencl\_copy\_opencl\_to\_ram (cl\_mem buffer, unsigned src\_node, void \*ptr, unsigned dst\_node, size\_t size, size\_t offset, cl\_event \*event, int \*ret)
- cl\_int starpu\_opencl\_copy\_opencl\_to\_opencl (cl\_mem src, unsigned src\_node, size\_t src\_offset, cl\_mem dst, unsigned dst\_node, size\_t dst\_offset, size\_t size, cl\_event \*event, int \*ret)
- cl\_int starpu\_opencl\_copy\_async\_sync (uintptr\_t src, size\_t src\_offset, unsigned src\_node, uintptr\_t dst, size\_t dst\_offset, unsigned dst\_node, size\_t size, cl\_event \*event)

### 29.17.1 Detailed Description

# 29.18 starpu\_openmp.h File Reference

```
#include <starpu_config.h>
```

#### **Data Structures**

- struct starpu\_omp\_lock\_t
- struct starpu\_omp\_nest\_lock\_t
- struct starpu\_omp\_parallel\_region\_attr
- struct starpu\_omp\_task\_region\_attr

### Macros

#define STARPU OMP NOTHROW

#### **Enumerations**

```
    enum starpu_omp_sched_value {
        starpu_omp_sched_undefined, starpu_omp_sched_static, starpu_omp_sched_dynamic, starpu_omp_sched_guided,
        starpu_omp_sched_auto, starpu_omp_sched_runtime }
    enum starpu_omp_proc_bind_value {
```

```
    enum starpu_omp_proc_bind_value {
        starpu_omp_proc_bind_undefined, starpu_omp_proc_bind_false, starpu_omp_proc_bind_true, starpu_omp_proc_bind_master,
        starpu_omp_proc_bind_close, starpu_omp_proc_bind_spread }
```

### **Functions**

• struct starpu arbiter \* starpu omp get default arbiter (void) STARPU OMP NOTHROW

#### Initialisation

- int starpu omp init (void) STARPU OMP NOTHROW
- void starpu omp shutdown (void) STARPU OMP NOTHROW

#### **Parallel**

- void starpu\_omp\_parallel\_region (const struct starpu\_omp\_parallel\_region\_attr \*attr) \_\_STARPU\_OMP\_-NOTHROW
- void starpu omp master (void(\*f)(void \*arg), void \*arg)
   STARPU OMP NOTHROW
- int starpu\_omp\_master\_inline (void) \_\_STARPU\_OMP\_NOTHROW

#### **Synchronization**

- void starpu\_omp\_barrier (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp critical (void(\*f)(void \*arg), void \*arg, const char \*name)
   STARPU OMP NOTHROW
- void starpu\_omp\_critical\_inline\_begin (const char \*name) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_critical\_inline\_end (const char \*name) \_\_STARPU\_OMP\_NOTHROW

# Worksharing

- void starpu\_omp\_single (void(\*f)(void \*arg), void \*arg, int nowait) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_single\_inline (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_single\_copyprivate (void(\*f)(void \*arg, void \*data, unsigned long long data\_size), void \*arg, void \*data, unsigned long long data\_size) \_\_STARPU\_OMP\_NOTHROW
- void \* starpu\_omp\_single\_copyprivate\_inline\_begin (void \*data) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_single\_copyprivate\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_for (void(\*f)(unsigned long long \_first\_i, unsigned long long \_nb\_i, void \*arg), void \*arg, unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, int nowait) \_\_STA-RPU\_OMP\_NOTHROW
- int starpu\_omp\_for\_inline\_first (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_first\_i, unsigned long long \*\_nb\_i) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_for\_inline\_next (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_first\_i, unsigned long long \*\_nb\_i) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_for\_alt (void(\*f)(unsigned long long \_begin\_i, unsigned long long \_end\_i, void \*arg), void \*arg, unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, int nowait) \_-\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_for\_inline\_first\_alt (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_begin\_i, unsigned long long \*\_end\_i) \_\_STARPU\_OMP\_NOTHR-OW
- int starpu\_omp\_for\_inline\_next\_alt (unsigned long long nb\_iterations, unsigned long long chunk, int schedule, int ordered, unsigned long long \*\_begin\_i, unsigned long long \*\_end\_i) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_ordered\_inline\_begin (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_ordered\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_ordered (void(\*f)(void \*arg), void \*arg) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_sections (unsigned long long nb\_sections, void(\*\*section\_f)(void \*arg), void \*\*section\_arg, int nowait) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_sections\_combined (unsigned long long nb\_sections, void(\*section\_f)(unsigned long long section\_num, void \*arg), void \*section\_arg, int nowait) \_\_STARPU\_OMP\_NOTHROW

### Task

- void starpu\_omp\_task\_region (const struct starpu\_omp\_task\_region\_attr \*attr) \_\_STARPU\_OMP\_NOT-HROW
- void starpu omp taskwait (void)
   STARPU OMP NOTHROW

- void starpu\_omp\_taskgroup (void(\*f)(void \*arg), void \*arg) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_taskgroup\_inline\_begin (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_taskgroup\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW

#### API

- void starpu\_omp\_set\_num\_threads (int threads) \_\_STARPU\_OMP\_NOTHROW
   int starpu\_omp\_get\_num\_threads () \_\_STARPU\_OMP\_NOTHROW

- int starpu\_omp\_get\_thread\_num () \_\_STARPU\_OMP\_NOTHROW
   int starpu\_omp\_get\_max\_threads () \_\_STARPU\_OMP\_NOTHROW
- int starpu omp get num procs (void)
   STARPU OMP NOTHROW
- int starpu\_omp\_in\_parallel (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_dynamic (int dynamic\_threads) \_\_STARPU\_OMP\_NOTHROW
   int starpu\_omp\_get\_dynamic (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_nested (int nested) \_\_STARPU\_OMP\_NOTHROW
   int starpu\_omp\_get\_nested (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_cancellation (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_schedule (enum starpu\_omp\_sched\_value kind, int modifier) \_\_STARPU\_OMP\_N-**OTHROW**
- void starpu\_omp\_get\_schedule (enum starpu\_omp\_sched\_value \*kind, int \*modifier) \_\_STARPU\_OMP-**NOTHROW**
- int starpu\_omp\_get\_thread\_limit (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp set max active levels (int max levels)
   STARPU OMP NOTHROW
- int starpu omp get max active levels (void)
   STARPU OMP NOTHROW
- int starpu\_omp\_get\_level (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_ancestor\_thread\_num (int level) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_team\_size (int level) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_active\_level (void) \_\_STARPU\_OMP\_NOTHROW
   int starpu\_omp\_in\_final (void) \_\_STARPU\_OMP\_NOTHROW
- enum starpu omp proc bind value starpu omp get proc bind (void)
   STARPU OMP NOTHROW
- void starpu\_omp\_set\_default\_device (int device\_num) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_default\_device (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_num\_devices (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_num\_teams (void) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_get\_team\_num (void) \_\_STARPU\_OMP\_NOTHROW
   int starpu\_omp\_is\_initial\_device (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_init\_lock (starpu\_omp\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp destroy lock (starpu omp lock t \*lock)
   STARPU OMP NOTHROW
- void starpu\_omp\_set\_lock (starpu\_omp\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp unset lock (starpu omp lock t \*lock)
   STARPU OMP NOTHROW
- int starpu\_omp\_test\_lock (starpu\_omp\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp init nest lock (starpu omp nest lock t \*lock)
   STARPU OMP NOTHROW
- void starpu\_omp\_destroy\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_set\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_unset\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- int starpu\_omp\_test\_nest\_lock (starpu\_omp\_nest\_lock\_t \*lock) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_atomic\_fallback\_inline\_begin (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu\_omp\_atomic\_fallback\_inline\_end (void) \_\_STARPU\_OMP\_NOTHROW
- double starpu\_omp\_get\_wtime (void) \_\_STARPU\_OMP\_NOTHROW
- double starpu\_omp\_get\_wtick (void) \_\_STARPU\_OMP\_NOTHROW
- void starpu omp vector annotate (starpu data handle t handle, uint32 t slice base)
   STARPU OMP-NOTHROW

### 29.18.1 Detailed Description

#### 29.19 starpu\_perfmodel.h File Reference

```
#include <starpu.h>
#include <stdio.h>
#include <starpu util.h>
#include <starpu_worker.h>
```

### **Data Structures**

- · struct starpu perfmodel device
- struct starpu\_perfmodel\_arch
- · struct starpu\_perfmodel\_history\_entry
- · struct starpu perfmodel history list
- struct starpu\_perfmodel\_regression\_model
- struct starpu\_perfmodel\_per\_arch
- · struct starpu perfmodel

### **Macros**

- #define STARPU NARCH
- #define starpu\_per\_arch\_perfmodel

## **Typedefs**

- typedef double(\* starpu\_perfmodel\_per\_arch\_cost\_function )(struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- typedef size\_t(\* starpu\_perfmodel\_per\_arch\_size\_base )(struct starpu\_task \*task, struct starpu\_perfmodel arch \*arch, unsigned nimpl)
- typedef struct
   \_starpu\_perfmodel\_state \* starpu\_perfmodel\_state\_t

#### **Enumerations**

enum starpu\_perfmodel\_type {
 STARPU\_PERFMODEL\_INVALID, STARPU\_PER\_ARCH, STARPU\_COMMON, STARPU\_HISTORY\_BASED,
 STARPU REGRESSION BASED, STARPU NL REGRESSION BASED }

- void starpu\_perfmodel\_init (struct starpu\_perfmodel \*model)
- int starpu\_perfmodel\_load\_file (const char \*filename, struct starpu\_perfmodel \*model)
- int starpu\_perfmodel\_load\_symbol (const char \*symbol, struct starpu\_perfmodel \*model)
- int starpu perfmodel unload model (struct starpu perfmodel \*model)
- void starpu perfmodel get model path (const char \*symbol, char \*path, size t maxlen)
- void starpu\_perfmodel\_free\_sampling\_directories (void)
- struct starpu\_perfmodel\_arch \* starpu\_worker\_get\_perf\_archtype (int workerid, unsigned sched\_ctx\_id)
- int starpu\_perfmodel\_get\_narch\_combs ()
- int starpu perfmodel arch comb add (int ndevices, struct starpu perfmodel device \*devices)
- int starpu\_perfmodel\_arch\_comb\_get (int ndevices, struct starpu\_perfmodel\_device \*devices)
- struct starpu\_perfmodel\_per\_arch \* starpu\_perfmodel\_get\_model\_per\_arch (struct starpu\_perfmodel \*model, struct starpu perfmodel arch \*arch, unsigned impl)
- struct starpu\_perfmodel\_per\_arch \* starpu\_perfmodel\_get\_model\_per\_devices (struct starpu\_perfmodel \*model, int impl,...)
- int starpu\_perfmodel\_set\_per\_devices\_cost\_function (struct starpu\_perfmodel \*model, int impl, starpu\_perfmodel per arch cost function func,...)
- int starpu\_perfmodel\_set\_per\_devices\_size\_base (struct starpu\_perfmodel \*model, int impl, starpu\_perfmodel\_per\_arch\_size\_base func,...)
- void starpu\_perfmodel\_debugfilepath (struct starpu\_perfmodel \*model, struct starpu\_perfmodel\_arch \*arch, char \*path, size\_t maxlen, unsigned nimpl)

- char \* starpu\_perfmodel\_get\_archtype\_name (enum starpu\_worker\_archtype archtype)
- void starpu\_perfmodel\_get\_arch\_name (struct starpu\_perfmodel\_arch \*arch, char \*archname, size\_t maxlen, unsigned nimpl)
- double starpu\_perfmodel\_history\_based\_expected\_perf (struct starpu\_perfmodel \*model, struct starpu\_perfmodel\_arch \*arch, uint32\_t footprint)
- int starpu\_perfmodel\_list (FILE \*output)
- void starpu\_perfmodel\_print (struct starpu\_perfmodel \*model, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl, char \*parameter, uint32\_t \*footprint, FILE \*output)
- int starpu\_perfmodel\_print\_all (struct starpu\_perfmodel \*model, char \*arch, char \*parameter, uint32\_t \*footprint, FILE \*output)
- int starpu\_perfmodel\_list\_combs (FILE \*output, struct starpu\_perfmodel \*model)
- void starpu\_perfmodel\_update\_history (struct starpu\_perfmodel \*model, struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned cpuid, unsigned nimpl, double measured)
- void starpu\_perfmodel\_directory (FILE \*output)
- void starpu\_bus\_print\_bandwidth (FILE \*f)
- void starpu\_bus\_print\_affinity (FILE \*f)
- double starpu transfer bandwidth (unsigned src node, unsigned dst node)
- double starpu\_transfer\_latency (unsigned src\_node, unsigned dst\_node)
- double starpu\_transfer\_predict (unsigned src\_node, unsigned dst\_node, size\_t size)

### 29.19.1 Detailed Description

### 29.19.2 Data Structure Documentation

### 29.19.2.1 struct starpu\_perfmodel\_device

#### **Data Fields**

enum starpu	type	
worker_archtype		
int	devid	
int	ncores	

# 29.19.2.2 struct starpu\_perfmodel\_arch

#### **Data Fields**

int	ndevices	
struct starpu	devices	
perfmodel		
device		
*		

# 29.20 starpu\_profiling.h File Reference

```
#include <starpu.h>
#include <errno.h>
#include <time.h>
#include <starpu_util.h>
```

### **Data Structures**

- · struct starpu\_profiling\_task\_info
- · struct starpu\_profiling\_worker\_info
- · struct starpu\_profiling\_bus\_info

#### **Macros**

- #define STARPU\_PROFILING\_DISABLE
- #define STARPU PROFILING ENABLE
- #define starpu\_timespec\_cmp(a, b, CMP)

### **Functions**

- void starpu\_profiling\_init (void)
- void starpu\_profiling\_set\_id (int new\_id)
- int starpu\_profiling\_status\_set (int status)
- int starpu profiling status get (void)
- int starpu\_profiling\_worker\_get\_info (int workerid, struct starpu\_profiling\_worker\_info \*worker\_info)
- int starpu\_bus\_get\_count (void)
- int starpu\_bus\_get\_id (int src, int dst)
- int starpu\_bus\_get\_src (int busid)
- int starpu bus get dst (int busid)
- int starpu bus get profiling info (int busid, struct starpu profiling bus info \*bus info)
- static starpu inline void starpu\_timespec\_clear (struct timespec \*tsp)
- static \_\_starpu\_inline void starpu\_timespec\_add (struct timespec \*a, struct timespec \*b, struct timespec \*result)
- static \_\_starpu\_inline void starpu\_timespec\_accumulate (struct timespec \*result, struct timespec \*a)
- static \_\_starpu\_inline void **starpu\_timespec\_sub** (const struct timespec \*a, const struct timespec \*b, struct timespec \*result)
- double starpu\_timing\_timespec\_delay\_us (struct timespec \*start, struct timespec \*end)
- double starpu\_timing\_timespec\_to\_us (struct timespec \*ts)
- void starpu\_profiling\_bus\_helper\_display\_summary (void)
- void starpu\_profiling\_worker\_helper\_display\_summary (void)

### 29.20.1 Detailed Description

# 29.21 starpu\_rand.h File Reference

```
#include <stdlib.h>
#include <starpu_config.h>
```

#### **Macros**

- #define starpu\_seed(seed)
- #define starpu\_srand48(seed)
- #define starpu\_drand48()
- #define starpu\_erand48(xsubi)
- #define starpu\_srand48\_r(seed, buffer)
- #define starpu\_erand48\_r(xsubi, buffer, result)

### **Typedefs**

· typedef int starpu\_drand48\_data

### 29.21.1 Detailed Description

# 29.22 starpu\_scc.h File Reference

```
#include <starpu_config.h>
```

### **Typedefs**

typedef void \* starpu\_scc\_func\_symbol\_t

### **Functions**

- int starpu\_scc\_register\_kernel (starpu\_scc\_func\_symbol\_t \*symbol, const char \*func\_name)
- starpu\_scc\_kernel\_t starpu\_scc\_get\_kernel (starpu\_scc\_func\_symbol\_t symbol)

### 29.22.1 Detailed Description

# 29.23 starpu\_sched\_ctx.h File Reference

```
#include <starpu.h>
```

#### **Macros**

- #define STARPU SCHED CTX HIERARCHY LEVEL
- #define STARPU SCHED CTX NESTED
- #define STARPU\_SCHED\_CTX\_AWAKE\_WORKERS

- unsigned starpu sched ctx get inheritor (unsigned sched ctx id)
- unsigned starpu\_sched\_ctx\_get\_hierarchy\_level (unsigned sched\_ctx\_id)
- unsigned starpu\_sched\_ctx\_contains\_type\_of\_worker (enum starpu\_worker\_archtype arch, unsigned sched\_ctx\_id)
- int starpu\_sched\_get\_min\_priority (void)
- int starpu\_sched\_get\_max\_priority (void)
- int starpu\_sched\_set\_min\_priority (int min\_prio)
- int starpu\_sched\_set\_max\_priority (int max\_prio)
- void starpu\_sched\_ctx\_set\_priority (int \*workers, int nworkers, unsigned sched\_ctx\_id, unsigned priority)
- void starpu\_sched\_ctx\_set\_priority\_on\_level (int \*workers\_to\_add, unsigned nworkers\_to\_add, unsigned sched\_ctx, unsigned priority)
- unsigned starpu\_sched\_ctx\_get\_priority (int worker, unsigned sched\_ctx\_id)
- void **starpu\_sched\_ctx\_get\_available\_cpuids** (unsigned sched\_ctx\_id, int \*\*cpuids, int \*ncpuids)
- void starpu\_sched\_ctx\_bind\_current\_thread\_to\_cpuid (unsigned cpuid)
- int starpu\_sched\_ctx\_book\_workers\_for\_task (unsigned sched\_ctx\_id, int \*workerids, int nworkers)

- void starpu\_sched\_ctx\_unbook\_workers\_for\_task (unsigned sched\_ctx\_id, int master)
- unsigned starpu\_sched\_ctx\_worker\_is\_master\_for\_child\_ctx (int workerid, unsigned sched\_ctx\_id)
- void starpu\_sched\_ctx\_revert\_task\_counters (unsigned sched\_ctx\_id, double flops)
- void starpu\_sched\_ctx\_move\_task\_to\_ctx (struct starpu\_task \*task, unsigned sched\_ctx)
- int starpu\_sched\_ctx\_get\_worker\_rank (unsigned sched\_ctx\_id)

### **Scheduling Context Worker Collection**

- struct starpu\_worker\_collection \* starpu\_sched\_ctx\_create\_worker\_collection (unsigned sched\_ctx\_id, enum starpu\_worker\_collection\_type type)
- void starpu\_sched\_ctx\_delete\_worker\_collection (unsigned sched\_ctx\_id)
- struct starpu\_worker\_collection \* starpu\_sched\_ctx\_get\_worker\_collection (unsigned sched\_ctx\_id)

### Scheduling Context Link with Hypervisor

- void starpu\_sched\_ctx\_set\_policy\_data (unsigned sched\_ctx\_id, void \*policy\_data)
- void \* starpu\_sched\_ctx\_get\_policy\_data (unsigned sched\_ctx\_id)
- void \* starpu sched ctx exec parallel code (void \*(\*func)(void \*), void \*param, unsigned sched ctx id)
- int starpu\_sched\_ctx\_get\_nready\_tasks (unsigned sched\_ctx\_id)
- double starpu\_sched\_ctx\_get\_nready\_flops (unsigned sched\_ctx\_id)
- void starpu\_sched\_ctx\_call\_pushed\_task\_cb (int workerid, unsigned sched\_ctx\_id)

# **Scheduling Contexts Basic API**

- #define STARPU\_SCHED\_CTX\_POLICY\_NAME
- #define STARPU\_SCHED\_CTX\_POLICY\_STRUCT
- #define STARPU\_SCHED\_CTX\_POLICY\_MIN\_PRIO
- #define STARPU\_SCHED\_CTX\_POLICY\_MAX\_PRIO
- unsigned starpu\_sched\_ctx\_create (int \*workerids\_ctx, int nworkers\_ctx, const char \*sched\_ctx\_name,...)
- unsigned starpu\_sched\_ctx\_create\_inside\_interval (const char \*policy\_name, const char \*sched\_ctx\_name, int min\_ncpus, int max\_ncpus, int max\_ncpus, int max\_ncpus, unsigned allow\_overlap)
- void starpu\_sched\_ctx\_register\_close\_callback (unsigned sched\_ctx\_id, void(\*close\_callback)(unsigned sched\_ctx\_id, void \*args), void \*args)
- void starpu\_sched\_ctx\_add\_workers (int \*workerids\_ctx, int nworkers\_ctx, unsigned sched\_ctx\_id)
- void starpu sched ctx remove workers (int \*workerids ctx, int nworkers ctx, unsigned sched ctx id)
- void starpu\_sched\_ctx\_display\_workers (unsigned sched\_ctx\_id, FILE \*f)
- void starpu\_sched\_ctx\_delete (unsigned sched\_ctx\_id)
- void starpu\_sched\_ctx\_set\_inheritor (unsigned sched\_ctx\_id, unsigned inheritor)
- void starpu\_sched\_ctx\_set\_context (unsigned \*sched\_ctx\_id)
- unsigned starpu\_sched\_ctx\_get\_context (void)
- void starpu\_sched\_ctx\_stop\_task\_submission (void)
- void starpu sched ctx finished submit (unsigned sched ctx id)
- unsigned starpu\_sched\_ctx\_get\_workers\_list (unsigned sched\_ctx\_id, int \*\*workerids)
- unsigned starpu\_sched\_ctx\_get\_nworkers (unsigned sched\_ctx\_id)
- unsigned starpu\_sched\_ctx\_get\_nshared\_workers (unsigned sched\_ctx\_id, unsigned sched\_ctx\_id2)
- unsigned starpu\_sched\_ctx\_contains\_worker (int workerid, unsigned sched\_ctx\_id)
- unsigned starpu sched ctx worker get id (unsigned sched ctx id)
- unsigned starpu\_sched\_ctx\_overlapping\_ctxs\_on\_worker (int workerid)

# **Scheduling Context Priorities**

- #define STARPU MIN PRIO
- #define STARPU\_MAX\_PRIO
- #define STARPU DEFAULT PRIO
- int starpu\_sched\_ctx\_get\_min\_priority (unsigned sched\_ctx\_id)
- int starpu\_sched\_ctx\_get\_max\_priority (unsigned sched\_ctx\_id)
- int starpu\_sched\_ctx\_set\_min\_priority (unsigned sched\_ctx\_id, int min\_prio)
- int starpu\_sched\_ctx\_set\_max\_priority (unsigned sched\_ctx\_id, int max\_prio)
- int starpu\_sched\_ctx\_min\_priority\_is\_set (unsigned sched\_ctx\_id)
- int starpu\_sched\_ctx\_max\_priority\_is\_set (unsigned sched\_ctx\_id)

# 29.23.1 Detailed Description

# 29.24 starpu\_sched\_ctx\_hypervisor.h File Reference

### **Data Structures**

· struct starpu sched ctx performance counters

#### **Functions**

void starpu\_sched\_ctx\_update\_start\_resizing\_sample (unsigned sched\_ctx\_id, double start\_sample)

### **Scheduling Context Link with Hypervisor**

- void starpu\_sched\_ctx\_set\_perf\_counters (unsigned sched\_ctx\_id, void \*perf\_counters)
- void starpu\_sched\_ctx\_notify\_hypervisor\_exists (void)
- unsigned starpu\_sched\_ctx\_check\_if\_hypervisor\_exists (void)

# 29.24.1 Detailed Description

# 29.25 starpu\_scheduler.h File Reference

```
#include <starpu.h>
```

### **Data Structures**

struct starpu\_sched\_policy

- struct starpu sched policy \*\* starpu sched get predefined policies ()
- void starpu\_worker\_get\_sched\_condition (int workerid, starpu\_pthread\_mutex\_t \*\*sched\_mutex, starpu\_pthread\_cond\_t \*\*sched\_cond)
- int starpu\_wake\_worker (int workerid)
- int starpu\_wakeup\_worker (int workerid, starpu\_pthread\_cond\_t \*cond, starpu\_pthread\_mutex\_t \*mutex)
- int starpu\_wake\_worker\_locked (int workerid)
- int starpu\_wakeup\_worker\_locked (int workerid, starpu\_pthread\_cond\_t \*cond, starpu\_pthread\_mutex\_t \*mutex)

- int starpu\_worker\_can\_execute\_task (unsigned workerid, struct starpu\_task \*task, unsigned nimpl)
- int starpu\_worker\_can\_execute\_task\_impl (unsigned workerid, struct starpu\_task \*task, unsigned \*impl\_mask)
- int starpu\_worker\_can\_execute\_task\_first\_impl (unsigned workerid, struct starpu\_task \*task, unsigned \*nimpl)
- int starpu\_push\_local\_task (int workerid, struct starpu\_task \*task, int back)
- int starpu\_push\_task\_end (struct starpu\_task \*task)
- int starpu\_combined\_worker\_assign\_workerid (int nworkers, int workerid\_array[])
- int starpu\_combined\_worker\_get\_description (int workerid, int \*worker\_size, int \*\*combined\_workerid)
- int starpu\_combined\_worker\_can\_execute\_task (unsigned workerid, struct starpu\_task \*task, unsigned nimpl)
- int starpu\_get\_prefetch\_flag (void)
- int starpu\_prefetch\_task\_input\_on\_node (struct starpu\_task \*task, unsigned node)
- int starpu\_idle\_prefetch\_task\_input\_on\_node (struct starpu\_task \*task, unsigned node)
- uint32\_t starpu\_task\_footprint (struct starpu\_perfmodel \*model, struct starpu\_task \*task, struct starpu\_perfmodel arch \*arch, unsigned nimpl)
- uint32\_t starpu\_task\_data\_footprint (struct starpu\_task \*task)
- double starpu\_task\_expected\_length (struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_worker\_get\_relative\_speedup (struct starpu\_perfmodel\_arch \*perf\_arch)
- double starpu\_task\_expected\_data\_transfer\_time (unsigned memory\_node, struct starpu\_task \*task)
- double starpu\_data\_expected\_transfer\_time (starpu\_data\_handle\_t handle, unsigned memory\_node, enum starpu\_data\_access\_mode mode)
- double starpu\_task\_expected\_power (struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_task\_expected\_conversion\_time (struct starpu\_task \*task, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_task\_bundle\_expected\_length (starpu\_task\_bundle\_t bundle, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- double starpu\_task\_bundle\_expected\_data\_transfer\_time (starpu\_task\_bundle\_t bundle, unsigned memory\_node)
- double starpu\_task\_bundle\_expected\_power (starpu\_task\_bundle\_t bundle, struct starpu\_perfmodel\_arch \*arch, unsigned nimpl)
- void starpu\_sched\_ctx\_worker\_shares\_tasks\_lists (int workerid, int sched\_ctx\_id)

# 29.25.1 Detailed Description

# 29.26 starpu\_sink.h File Reference

# **Functions**

void starpu\_sink\_common\_worker (int argc, char \*\*argv)

### 29.26.1 Detailed Description

# 29.27 starpu\_stdlib.h File Reference

#include <starpu.h>

#### **Macros**

- #define STARPU MALLOC PINNED
- #define STARPU\_MALLOC\_COUNT
- #define STARPU MALLOC NORECLAIM
- #define STARPU MEMORY WAIT
- #define STARPU\_MEMORY\_OVERFLOW

#### **Functions**

- void starpu\_malloc\_set\_align (size\_t align)
- int starpu malloc (void \*\*A, size t dim)
- int starpu\_free (void \*A)
- int starpu\_malloc\_flags (void \*\*A, size\_t dim, int flags)
- int starpu\_free\_flags (void \*A, size\_t dim, int flags)
- int starpu\_memory\_pin (void \*addr, size\_t size)
- int starpu\_memory\_unpin (void \*addr, size\_t size)
- starpu\_ssize\_t starpu\_memory\_get\_total (unsigned node)
- starpu\_ssize\_t starpu\_memory\_get\_available (unsigned node)
- void starpu\_memory\_wait\_available (unsigned node, size\_t size)
- int starpu\_memory\_allocate (unsigned node, size\_t size, int flags)
- void starpu\_memory\_deallocate (unsigned node, size\_t size)

# 29.27.1 Detailed Description

# 29.28 starpu\_task.h File Reference

```
#include <starpu.h>
#include <starpu_data.h>
#include <starpu_util.h>
#include <starpu_task_bundle.h>
#include <errno.h>
#include <cuda.h>
```

# **Data Structures**

- · struct starpu codelet
- · struct starpu\_task

#### Macros

- #define STARPU NOWHERE
- #define STARPU\_CPU
- #define STARPU CUDA
- #define STARPU\_OPENCL
- #define STARPU MIC
- #define STARPU SCC
- #define STARPU\_CUDA\_ASYNC
- #define STARPU OPENCL ASYNC
- #define STARPU TASK INVALID
- #define STARPU\_MULTIPLE\_CPU\_IMPLEMENTATIONS

- #define STARPU MULTIPLE CUDA IMPLEMENTATIONS
- #define STARPU\_MULTIPLE\_OPENCL\_IMPLEMENTATIONS
- #define STARPU VARIABLE NBUFFERS
- #define STARPU TASK INITIALIZER
- #define STARPU TASK GET NBUFFERS(task)
- #define STARPU TASK GET HANDLE(task, i)
- #define STARPU TASK GET\_HANDLES(task)
- #define STARPU\_TASK\_SET\_HANDLE(task, handle, i)
- #define STARPU CODELET GET MODE(codelet, i)
- #define STARPU CODELET SET MODE(codelet, mode, i)
- #define STARPU TASK GET MODE(task, i)
- #define STARPU\_TASK\_SET\_MODE(task, mode, i)
- #define STARPU\_CODELET\_GET\_NODE(codelet, i)
- #define STARPU\_CODELET\_SET\_NODE(codelet, \_\_node, i)

# **Typedefs**

- typedef uint64 t starpu tag t
- typedef void(\* starpu\_cpu\_func\_t )(void \*\*, void \*)
- typedef void(\* starpu\_cuda\_func\_t )(void \*\*, void \*)
- typedef void(\* starpu\_opencl\_func\_t )(void \*\*, void \*)
- typedef void(\* starpu\_mic\_kernel\_t )(void \*\*, void \*)
- typedef void(\* starpu\_scc\_kernel\_t)(void \*\*, void \*)
- typedef starpu mic kernel t(\* starpu mic func t)(void)
- typedef starpu\_scc\_kernel\_t(\* starpu\_scc\_func\_t)(void)

### **Enumerations**

- enum starpu codelet type { STARPU SEQ, STARPU SPMD, STARPU FORKJOIN }
- enum starpu task status {

STARPU\_TASK\_INVALID, STARPU\_TASK\_INVALID, STARPU\_TASK\_BLOCKED, STARPU\_TASK\_READY.

 $\begin{array}{l} \mathtt{STARPU\_TASK\_RUNNING}, \ \mathtt{STARPU\_TASK\_FINISHED}, \ \mathtt{STARPU\_TASK\_BLOCKED\_ON\_TAG}, \ \mathtt{STARPU\_TASK\_BLOCKED\_ON\_TAGK}, \\ \mathtt{U\_TASK\_BLOCKED\_ON\_TASK}, \end{array}$ 

STARPU\_TASK\_BLOCKED\_ON\_DATA, STARPU\_TASK\_STOPPED }

- void starpu tag declare deps (starpu tag t id, unsigned ndeps,...)
- void starpu tag declare deps array (starpu tag t id, unsigned ndeps, starpu tag t \*array)
- void starpu\_task\_declare\_deps\_array (struct starpu\_task \*task, unsigned ndeps, struct starpu\_task \*task\_array[])
- int starpu\_task\_get\_task\_succs (struct starpu\_task \*task, unsigned ndeps, struct starpu\_task \*task\_array[])
- int starpu\_tag\_wait (starpu\_tag\_t id)
- int starpu\_tag\_wait\_array (unsigned ntags, starpu\_tag\_t \*id)
- void starpu\_tag\_notify\_from\_apps (starpu\_tag\_t id)
- void starpu\_tag\_restart (starpu\_tag\_t id)
- void starpu\_tag\_remove (starpu\_tag\_t id)
- void starpu\_task\_init (struct starpu\_task \*task)
- void starpu\_task\_clean (struct starpu\_task \*task)
- struct starpu\_task \* starpu\_task\_create (void)
- void starpu\_task\_destroy (struct starpu\_task \*task)
- int starpu\_task\_submit (struct starpu\_task \*task) STARPU\_WARN\_UNUSED\_RESULT

- int starpu\_task\_submit\_to\_ctx (struct starpu\_task \*task, unsigned sched\_ctx\_id)
- int starpu\_task\_finished (struct starpu\_task \*task) STARPU\_WARN\_UNUSED\_RESULT
- int starpu\_task\_wait (struct starpu\_task \*task) STARPU\_WARN\_UNUSED\_RESULT
- int starpu\_task\_wait\_for\_all (void)
- int starpu task wait for n submitted (unsigned n)
- int starpu\_task\_wait\_for\_all\_in\_ctx (unsigned sched\_ctx\_id)
- int starpu task wait for n submitted in ctx (unsigned sched ctx id, unsigned n)
- int starpu\_task\_wait\_for\_no\_ready (void)
- int starpu\_task\_nready (void)
- int starpu\_task\_nsubmitted (void)
- void starpu\_codelet\_init (struct starpu\_codelet \*cl)
- void starpu\_codelet\_display\_stats (struct starpu\_codelet \*cl)
- struct starpu\_task \* starpu\_task\_get\_current (void)
- void starpu parallel task barrier init (struct starpu task \*task, int workerid)
- void starpu\_parallel\_task\_barrier\_init\_n (struct starpu\_task \*task, int worker\_size)
- struct starpu\_task \* starpu\_task\_dup (struct starpu\_task \*task)
- void starpu\_task\_set\_implementation (struct starpu\_task \*task, unsigned impl)
- unsigned starpu\_task\_get\_implementation (struct starpu\_task \*task)

### 29.28.1 Detailed Description

### 29.28.2 Macro Definition Documentation

#### 29.28.2.1 #define STARPU\_CUDA\_ASYNC

Value to be set in <a href="starpu\_codelet::cuda\_flags">starpu\_codelet::cuda\_flags</a> to allow asynchronous CUDA kernel execution.

#### 29.28.2.2 #define STARPU\_OPENCL\_ASYNC

Value to be set in starpu\_codelet::opencl\_flags to allow asynchronous OpenCL kernel execution.

# 29.29 starpu\_task\_bundle.h File Reference

# **Typedefs**

```
typedef struct
_starpu_task_bundle * starpu_task_bundle_t
```

# **Functions**

- void starpu\_task\_bundle\_create (starpu\_task\_bundle\_t \*bundle)
- int starpu\_task\_bundle\_insert (starpu\_task\_bundle\_t bundle, struct starpu\_task \*task)
- int starpu\_task\_bundle\_remove (starpu\_task\_bundle\_t bundle, struct starpu\_task \*task)
- void starpu\_task\_bundle\_close (starpu\_task\_bundle\_t bundle)

### 29.29.1 Detailed Description

# 29.30 starpu\_task\_list.h File Reference

```
#include <starpu_task.h>
#include <starpu_util.h>
```

### **Data Structures**

· struct starpu\_task\_list

#### **Functions**

- static STARPU INLINE void starpu task list init (struct starpu task list \*list)
- static STARPU\_INLINE void starpu\_task\_list\_push\_front (struct starpu\_task\_list \*list, struct starpu\_task \*task)
- static STARPU\_INLINE void starpu\_task\_list\_push\_back (struct starpu\_task\_list \*list, struct starpu\_task \*task)
- static STARPU\_INLINE struct

```
starpu_task * starpu_task_list_front (struct starpu_task_list *list)
```

- static STARPU INLINE struct
- starpu\_task \* starpu\_task\_list\_back (struct starpu\_task\_list \*list)
- static STARPU\_INLINE int starpu\_task\_list\_empty (struct starpu\_task\_list \*list)
- static STARPU\_INLINE void starpu\_task\_list\_erase (struct starpu\_task\_list \*list, struct starpu\_task \*task)
- static STARPU\_INLINE struct

```
starpu_task * starpu_task_list_pop_front (struct starpu_task_list *list)
```

- static STARPU INLINE struct
  - starpu task \* starpu task list pop back (struct starpu task list \*list)
- static STARPU INLINE struct

```
starpu_task * starpu_task_list_begin (struct starpu_task_list *list)
```

· static STARPU INLINE struct

```
starpu_task * starpu_task_list_end (struct starpu_task_list *list STARPU_ATTRIBUTE_UNUSED)
```

static STARPU\_INLINE struct

```
starpu task * starpu task list next (struct starpu task *task)
```

# 29.30.1 Detailed Description

# 29.31 starpu\_task\_util.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <assert.h>
#include <starpu.h>
```

#### **Macros**

- #define STARPU\_MODE\_SHIFT
- #define STARPU VALUE
- #define STARPU\_CALLBACK
- #define STARPU CALLBACK WITH ARG
- #define STARPU CALLBACK ARG
- #define STARPU PRIORITY
- #define STARPU\_DATA\_ARRAY
- #define STARPU\_DATA\_MODE\_ARRAY
- #define STARPU TAG
- #define STARPU\_HYPERVISOR\_TAG
- #define STARPU FLOPS
- #define STARPU\_SCHED\_CTX

- #define STARPU PROLOGUE CALLBACK
- #define STARPU\_PROLOGUE\_CALLBACK\_ARG
- #define STARPU PROLOGUE CALLBACK POP
- #define STARPU PROLOGUE CALLBACK POP ARG
- #define STARPU\_EXECUTE\_ON\_WORKER
- #define STARPU TAG ONLY
- #define STARPU\_POSSIBLY\_PARALLEL
- #define STARPU\_WORKER\_ORDER
- #define STARPU NODE SELECTION POLICY
- #define STARPU NAME
- #define STARPU\_SHIFTED\_MODE\_MAX

#### **MPI Insert Task**

- #define STARPU EXECUTE ON NODE
- #define STARPU\_EXECUTE\_ON\_DATA

#### **Functions**

- void starpu\_create\_sync\_task (starpu\_tag\_t sync\_tag, unsigned ndeps, starpu\_tag\_t \*deps, void(\*callback)(void \*), void \*callback\_arg)
- struct starpu\_task \* starpu\_task\_build (struct starpu\_codelet \*cl,...)
- int starpu\_task\_insert (struct starpu\_codelet \*cl,...)
- int starpu\_insert\_task (struct starpu\_codelet \*cl,...)
- void starpu\_codelet\_unpack\_args (void \*cl\_arg,...)
- void starpu\_codelet\_pack\_args (void \*\*arg\_buffer, size\_t \*arg\_buffer\_size,...)

# 29.31.1 Detailed Description

# 29.32 starpu\_thread.h File Reference

```
#include <starpu_config.h>
#include <starpu_util.h>
#include <xbt/synchro_core.h>
#include <msg/msg.h>
#include <stdint.h>
```

# **Data Structures**

- struct starpu\_pthread\_barrier\_t
- · struct starpu\_pthread\_spinlock\_t

### **Macros**

- #define STARPU PTHREAD MUTEX INITIALIZER
- #define STARPU PTHREAD COND INITIALIZER
- #define STARPU\_PTHREAD\_BARRIER\_SERIAL\_THREAD

### **Typedefs**

- typedef msg\_process\_t starpu\_pthread\_t
- typedef int starpu\_pthread\_attr\_t
- typedef xbt\_mutex\_t starpu\_pthread\_mutex\_t
- typedef int starpu pthread mutexattr t
- typedef int starpu pthread key t
- typedef xbt cond t starpu pthread cond t
- · typedef int starpu pthread condattr t
- typedef xbt\_mutex\_t starpu\_pthread\_rwlock\_t
- typedef int starpu\_pthread\_rwlockattr\_t
- typedef int starpu pthread barrierattr t

- int **starpu\_pthread\_create\_on** (char \*name, starpu\_pthread\_t \*thread, const starpu\_pthread\_attr\_t \*attr, void \*(\*start\_routine)(void \*), void \*arg, msg\_host\_t host)
- int starpu\_pthread\_create (starpu\_pthread\_t \*thread, const starpu\_pthread\_attr\_t \*attr, void \*(\*start\_routine)(void \*), void \*arg)
- int starpu pthread join (starpu pthread t thread, void \*\*retval)
- int starpu\_pthread\_exit (void \*retval) STARPU\_ATTRIBUTE\_NORETURN
- int starpu pthread attr init (starpu pthread attr t \*attr)
- int starpu\_pthread\_attr\_destroy (starpu\_pthread\_attr\_t \*attr)
- int starpu\_pthread\_attr\_setdetachstate (starpu\_pthread\_attr\_t \*attr, int detachstate)
- int starpu\_pthread\_mutex\_init (starpu\_pthread\_mutex\_t \*mutex, const starpu\_pthread\_mutexattr\_t \*mutexattr)
- int starpu\_pthread\_mutex\_destroy (starpu\_pthread\_mutex\_t \*mutex)
- int starpu pthread mutex lock (starpu pthread mutex t \*mutex)
- int starpu\_pthread\_mutex\_unlock (starpu\_pthread\_mutex\_t \*mutex)
- int starpu\_pthread\_mutex\_trylock (starpu\_pthread\_mutex\_t \*mutex)
- int starpu\_pthread\_mutexattr\_gettype (const starpu\_pthread\_mutexattr\_t \*attr, int \*type)
- int starpu\_pthread\_mutexattr\_settype (starpu\_pthread\_mutexattr\_t \*attr, int type)
- int starpu\_pthread\_mutexattr\_destroy (starpu\_pthread\_mutexattr\_t \*attr)
- int starpu pthread mutexattr init (starpu pthread mutexattr t \*attr)
- int starpu pthread key create (starpu pthread key t \*key, void(\*destr function)(void \*))
- int starpu\_pthread\_key\_delete (starpu\_pthread\_key\_t key)
- int starpu pthread setspecific (starpu pthread key t key, const void \*pointer)
- void \* starpu\_pthread\_getspecific (starpu\_pthread\_key\_t key)
- int starpu\_pthread\_cond\_init (starpu\_pthread\_cond\_t \*cond, starpu\_pthread\_condattr\_t \*cond\_attr)
- int starpu pthread cond signal (starpu pthread cond t \*cond)
- int starpu\_pthread\_cond\_broadcast (starpu\_pthread\_cond\_t \*cond)
- int starpu pthread cond wait (starpu pthread cond t \*cond, starpu pthread mutex t \*mutex)
- int starpu\_pthread\_cond\_timedwait (starpu\_pthread\_cond\_t \*cond, starpu\_pthread\_mutex\_t \*mutex, const struct timespec \*abstime)
- int starpu\_pthread\_cond\_destroy (starpu\_pthread\_cond\_t \*cond)
- int starpu\_pthread\_rwlock\_init (starpu\_pthread\_rwlock\_t \*rwlock, const starpu\_pthread\_rwlockattr\_t \*attr)
- int starpu\_pthread\_rwlock\_destroy (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu\_pthread\_rwlock\_rdlock (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu\_pthread\_rwlock\_tryrdlock (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu\_pthread\_rwlock\_wrlock (starpu\_pthread\_rwlock\_t \*rwlock)
- int starpu pthread rwlock trywrlock (starpu pthread rwlock t \*rwlock)
- int starpu pthread rwlock unlock (starpu pthread rwlock t \*rwlock)
- int starpu\_pthread\_barrier\_init (starpu\_pthread\_barrier\_t \*barrier, const starpu\_pthread\_barrierattr\_t \*attr, unsigned count)
- int starpu\_pthread\_barrier\_destroy (starpu\_pthread\_barrier\_t \*barrier)

- int starpu\_pthread\_barrier\_wait (starpu\_pthread\_barrier\_t \*barrier)
- int starpu\_pthread\_spin\_init (starpu\_pthread\_spinlock\_t \*lock, int pshared)
- int starpu\_pthread\_spin\_destroy (starpu\_pthread\_spinlock\_t \*lock)
- int starpu\_pthread\_spin\_lock (starpu\_pthread\_spinlock\_t \*lock)
- int starpu\_pthread\_spin\_trylock (starpu\_pthread\_spinlock\_t \*lock)
- int starpu\_pthread\_spin\_unlock (starpu\_pthread\_spinlock\_t \*lock)

### 29.32.1 Detailed Description

### 29.32.2 Data Structure Documentation

### 29.32.2.1 struct starpu\_pthread\_barrier\_t

#### **Data Fields**

starpu_pthread-	mutex	
_mutex_t		
starpu_pthread-	cond	
_cond_t		
starpu_pthread-	cond_destroy	
_cond_t		
unsigned	count	
unsigned	done	
unsigned	busy	

### 29.32.2.2 struct starpu\_pthread\_spinlock\_t

#### **Data Fields**

int	taken	

# 29.33 starpu\_thread\_util.h File Reference

```
#include <starpu_util.h>
#include <errno.h>
```

### **Macros**

- #define STARPU PTHREAD CREATE ON(name, thread, attr, routine, arg, where)
- #define STARPU\_PTHREAD\_CREATE(thread, attr, routine, arg)
- #define STARPU\_PTHREAD\_MUTEX\_INIT(mutex, attr)
- #define STARPU\_PTHREAD\_MUTEX\_DESTROY(mutex)
- #define STARPU\_PTHREAD\_MUTEX\_LOCK(mutex)
- #define STARPU\_PTHREAD\_MUTEX\_TRYLOCK(mutex)
- #define STARPU\_PTHREAD\_MUTEX\_UNLOCK(mutex)
- #define STARPU PTHREAD KEY CREATE(key, destr)
- #define STARPU\_PTHREAD\_KEY\_DELETE(key)
- #define STARPU\_PTHREAD\_SETSPECIFIC(key, ptr)
- #define STARPU PTHREAD GETSPECIFIC(key)
- #define STARPU\_PTHREAD\_RWLOCK\_INIT(rwlock, attr)
- #define STARPU\_PTHREAD\_RWLOCK\_RDLOCK(rwlock)
- #define STARPU\_PTHREAD\_RWLOCK\_TRYRDLOCK(rwlock)

- #define STARPU\_PTHREAD\_RWLOCK\_WRLOCK(rwlock)
- #define STARPU\_PTHREAD\_RWLOCK\_TRYWRLOCK(rwlock)
- #define STARPU\_PTHREAD\_RWLOCK\_UNLOCK(rwlock)
- #define STARPU PTHREAD RWLOCK DESTROY(rwlock)
- #define STARPU\_PTHREAD\_COND\_INIT(cond, attr)
- #define STARPU PTHREAD COND DESTROY(cond)
- #define STARPU PTHREAD COND SIGNAL(cond)
- #define STARPU\_PTHREAD\_COND\_BROADCAST(cond)
- #define STARPU PTHREAD COND WAIT(cond, mutex)
- #define STARPU\_PTHREAD\_BARRIER\_INIT(barrier, attr, count)
- #define STARPU PTHREAD BARRIER DESTROY(barrier)
- #define STARPU PTHREAD BARRIER WAIT(barrier)

### **Functions**

- static STARPU\_INLINE int \_starpu\_pthread\_mutex\_trylock (starpu\_pthread\_mutex\_t \*mutex, char \*file, int line)
- static STARPU\_INLINE int \_starpu\_pthread\_rwlock\_tryrdlock (starpu\_pthread\_rwlock\_t \*rwlock, char \*file, int line)
- static STARPU\_INLINE int \_starpu\_pthread\_rwlock\_trywrlock (starpu\_pthread\_rwlock\_t \*rwlock, char \*file, int line)

### 29.33.1 Detailed Description

# 29.34 starpu\_top.h File Reference

```
#include <starpu.h>
#include <stdlib.h>
#include <time.h>
```

### **Data Structures**

- · struct starpu\_top\_data
- struct starpu\_top\_param

#### **Enumerations**

- enum starpu\_top\_data\_type { STARPU\_TOP\_DATA\_BOOLEAN, STARPU\_TOP\_DATA\_INTEGER, STAR-PU\_TOP\_DATA\_FLOAT }
- enum starpu\_top\_param\_type { STARPU\_TOP\_PARAM\_BOOLEAN, STARPU\_TOP\_PARAM\_INTEGER, STARPU\_TOP\_PARAM\_FLOAT, STARPU\_TOP\_PARAM\_ENUM }
- enum starpu\_top\_message\_type {
   TOP\_TYPE\_GO, TOP\_TYPE\_SET, TOP\_TYPE\_CONTINUE, TOP\_TYPE\_ENABLE,
   TOP\_TYPE\_DISABLE, TOP\_TYPE\_DEBUG, TOP\_TYPE\_UNKNOW }

# **Functions**

#### Functions to call before the initialisation

- struct starpu\_top\_data \* starpu\_top\_add\_data\_boolean (const char \*data\_name, int active)
- struct starpu\_top\_data \* starpu\_top\_add\_data\_integer (const char \*data\_name, int minimum\_value, int maximum\_value, int active)

- struct starpu\_top\_data \* starpu\_top\_add\_data\_float (const char \*data\_name, double minimum\_value, double maximum value, int active)
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_boolean (const char \*param\_name, int \*parameter field, void(\*callback)(struct starpu top param \*))
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_integer (const char \*param\_name, int \*parameter field, int minimum value, int maximum value, void(\*callback)(struct starpu top param \*))
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_float (const char \*param\_name, double \*parameter\_field, double minimum\_value, double maximum\_value, void(\*callback)(struct starpu\_top-param \*))
- struct starpu\_top\_param \* starpu\_top\_register\_parameter\_enum (const char \*param\_name, int \*parameter field, char \*\*values, int nb values, void(\*callback)(struct starpu\_top\_param \*))

#### Initialisation

void starpu top init and wait (const char \*server name)

#### To call after initialisation

- void starpu top update parameter (const struct starpu top param \*param)
- void starpu top update data boolean (const struct starpu top data \*data, int value)
- void starpu\_top\_update\_data\_integer (const struct starpu\_top\_data \*data, int value)
- void starpu\_top\_update\_data\_float (const struct starpu\_top\_data \*data, double value)
- void starpu\_top\_task\_prevision (struct starpu\_task \*task, int devid, unsigned long long start, unsigned long long end)
- void starpu\_top\_debug\_log (const char \*message)
- void starpu\_top\_debug\_lock (const char \*message)

### 29.34.1 Detailed Description

# 29.35 starpu\_tree.h File Reference

# **Data Structures**

struct starpu\_tree

# **Functions**

- void starpu\_tree\_reset\_visited (struct starpu\_tree \*tree, int \*visited)
- void starpu\_tree\_insert (struct starpu\_tree \*tree, int id, int level, int is\_pu, int arity, struct starpu\_tree \*father)
- struct starpu\_tree \* starpu\_tree\_get (struct starpu\_tree \*tree, int id)
- struct starpu\_tree \* starpu\_tree\_get\_neighbour (struct starpu\_tree \*tree, struct starpu\_tree \*node, int \*visited, int \*present)
- void starpu\_tree\_free (struct starpu\_tree \*tree)

### 29.35.1 Detailed Description

# 29.36 starpu\_util.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <assert.h>
#include <starpu_config.h>
#include <starpu_task.h>
#include <sys/time.h>
```

#### **Macros**

- #define STARPU GNUC PREREQ(maj, min)
- #define STARPU UNLIKELY(expr)
- #define STARPU LIKELY(expr)
- #define STARPU\_ATTRIBUTE\_UNUSED
- #define STARPU\_ATTRIBUTE\_NORETURN
- #define STARPU\_ATTRIBUTE\_INTERNAL
- #define STARPU ATTRIBUTE MALLOC
- #define STARPU ATTRIBUTE WARN UNUSED RESULT
- #define STARPU\_ATTRIBUTE\_PURE
- #define STARPU\_ATTRIBUTE\_ALIGNED(size)
- #define STARPU\_INLINE
- · #define endif
- #define STARPU\_WARN\_UNUSED\_RESULT
- #define STARPU\_POISON\_PTR
- #define STARPU\_MIN(a, b)
- #define STARPU\_MAX(a, b)
- #define STARPU BACKTRACE LENGTH
- #define STARPU DUMP BACKTRACE()
- #define STARPU\_ASSERT(x)
- #define STARPU ASSERT MSG(x, msg,...)
- #define \_starpu\_abort()
- #define STARPU ABORT()
- #define STARPU\_ABORT\_MSG(msg,...)
- #define STARPU\_CHECK\_RETURN\_VALUE(err, message,...)
- #define STARPU\_CHECK\_RETURN\_VALUE\_IS(err, value, message,...)
- #define STARPU ATOMIC SOMETHING(name, expr)
- #define STARPU\_RMB()
- #define STARPU\_WMB()

# **Functions**

- char \* starpu\_getenv (const char \*str)
- static starpu inline int starpu get env number (const char \*str)
- static \_\_starpu\_inline int starpu\_get\_env\_number\_default (const char \*str, int defval)
- static \_\_starpu\_inline float starpu\_get\_env\_float\_default (const char \*str, float defval)
- void starpu execute on each worker (void(\*func)(void \*), void \*arg, uint32 t where)
- void starpu\_execute\_on\_each\_worker\_ex (void(\*func)(void \*), void \*arg, uint32\_t where, const char \*name)
- void starpu\_execute\_on\_specific\_workers (void(\*func)(void \*), void \*arg, unsigned num\_workers, unsigned \*workers, const char \*name)
- int starpu\_data\_cpy (starpu\_data\_handle\_t dst\_handle, starpu\_data\_handle\_t src\_handle, int asynchronous, void(\*callback func)(void \*), void \*callback arg)
- double starpu\_timing\_now (void)

### **Variables**

· int \_starpu\_silent

### 29.36.1 Detailed Description

# 29.37 starpu\_worker.h File Reference

```
#include <stdlib.h>
#include <starpu_config.h>
#include <starpu_thread.h>
```

#### **Data Structures**

- · struct starpu\_sched\_ctx\_iterator
- · struct starpu worker collection

#### **Enumerations**

- enum starpu\_worker\_archtype {
   STARPU\_CPU\_WORKER, STARPU\_CUDA\_WORKER, STARPU\_OPENCL\_WORKER, STARPU\_MIC\_-WORKER,
   STARPU\_SCC\_WORKER, STARPU\_ANY\_WORKER }
- enum starpu\_worker\_collection\_type { STARPU\_WORKER\_TREE, STARPU\_WORKER\_LIST }

- unsigned starpu\_worker\_get\_count (void)
- unsigned starpu combined worker get count (void)
- unsigned starpu\_worker\_is\_combined\_worker (int id)
- unsigned starpu\_cpu\_worker\_get\_count (void)
- unsigned starpu\_cuda\_worker\_get\_count (void)
- unsigned starpu\_opencl\_worker\_get\_count (void)
- unsigned starpu\_mic\_worker\_get\_count (void)
- unsigned starpu\_scc\_worker\_get\_count (void)
- unsigned starpu\_mic\_device\_get\_count (void)
- int starpu\_worker\_get\_id (void)
- int starpu\_worker\_get\_bindid (int workerid)
- int starpu combined worker get id (void)
- · int starpu combined worker get size (void)
- int starpu\_combined\_worker\_get\_rank (void)
- enum starpu\_worker\_archtype starpu\_worker\_get\_type (int id)
- int starpu\_worker\_get\_count\_by\_type (enum starpu\_worker\_archtype type)
- int starpu\_worker\_get\_ids\_by\_type (enum starpu\_worker\_archtype type, int \*workerids, int maxsize)
- int starpu\_worker\_get\_by\_type (enum starpu\_worker\_archtype type, int num)
- int starpu\_worker\_get\_by\_devid (enum starpu\_worker\_archtype type, int devid)
- void starpu\_worker\_get\_name (int id, char \*dst, size\_t maxlen)
- · int starpu\_worker\_get\_devid (int id)
- int starpu\_worker\_get\_mp\_nodeid (int id)
- struct starpu\_tree \* starpu\_workers\_get\_tree (void)
- unsigned starpu\_worker\_get\_sched\_ctx\_list (int worker, unsigned \*\*sched\_ctx)
- unsigned starpu worker is slave (int workerid)
- char \* starpu\_worker\_get\_type\_as\_string (enum starpu\_worker\_archtype type)

#### **Variables**

- · struct starpu worker collection worker list
- struct starpu\_worker\_collection worker\_tree

# 29.37.1 Detailed Description

# 29.38 starpu\_mpi.h File Reference

```
#include <starpu.h>
#include <mpi.h>
```

### **Macros**

- #define STARPU MPI NODE SELECTION CURRENT POLICY
- · #define STARPU MPI NODE SELECTION MOST R DATA

# **Typedefs**

- typedef void \* starpu\_mpi\_req
- typedef int(\* starpu\_mpi\_select\_node\_policy\_func\_t )(int me, int nb\_nodes, struct starpu\_data\_descr \*descr, int nb\_data)
- typedef void(\* starpu mpi datatype allocate func t)(starpu data handle t, MPI Datatype \*)
- typedef void(\* starpu\_mpi\_datatype\_free\_func\_t )(MPI\_Datatype \*)

# **Functions**

- int starpu\_mpi\_comm\_size (MPI\_Comm comm, int \*size)
- int starpu\_mpi\_comm\_rank (MPI\_Comm comm, int \*rank)
- int starpu mpi world rank (void)

### Communication

- int starpu\_mpi\_isend (starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \*req, int dest, int mpi\_tag, M-PI Comm comm)
- int starpu\_mpi\_irecv (starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \*req, int source, int mpi\_tag, MPI\_Comm comm)
- int starpu\_mpi\_send (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm)
- int starpu\_mpi\_recv (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, MPI\_Status \*status)
- int starpu\_mpi\_isend\_detached (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg)
- int starpu\_mpi\_irecv\_detached (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg)
- int starpu\_mpi\_issend (starpu\_data\_handle\_t data\_handle, starpu\_mpi\_req \*req, int dest, int mpi\_tag, MPI\_Comm comm)
- int starpu\_mpi\_issend\_detached (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg)
- int starpu\_mpi\_wait (starpu\_mpi\_req \*req, MPI\_Status \*status)
- int starpu\_mpi\_test (starpu\_mpi\_req \*req, int \*flag, MPI\_Status \*status)
- int starpu\_mpi\_barrier (MPI\_Comm comm)
- int starpu\_mpi\_irecv\_detached\_sequential\_consistency (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, void(\*callback)(void \*), void \*arg, int sequential\_consistency)

- int starpu\_mpi\_isend\_detached\_unlock\_tag (starpu\_data\_handle\_t data\_handle, int dest, int mpi\_tag, M-PI\_Comm comm, starpu\_tag\_t tag)
- int starpu\_mpi\_irecv\_detached\_unlock\_tag (starpu\_data\_handle\_t data\_handle, int source, int mpi\_tag, MPI\_Comm comm, starpu\_tag\_t tag)
- int starpu\_mpi\_isend\_array\_detached\_unlock\_tag (unsigned array\_size, starpu\_data\_handle\_t \*data\_handle, int \*dest, int \*mpi tag, MPI Comm \*comm, starpu tag t tag)
- int starpu\_mpi\_irecv\_array\_detached\_unlock\_tag (unsigned array\_size, starpu\_data\_handle\_t \*data\_handle, int \*source, int \*mpi\_tag, MPI\_Comm \*comm, starpu\_tag\_t tag)
- int starpu\_mpi\_get\_communication\_tag (void)
- void starpu\_mpi\_set\_communication\_tag (int tag)
- int starpu\_mpi\_datatype\_register (starpu\_data\_handle\_t handle, starpu\_mpi\_datatype\_allocate\_func\_t allocate\_datatype\_func, starpu\_mpi\_datatype\_free\_func\_t free\_datatype\_func)
- int starpu mpi datatype unregister (starpu data handle t handle)

#### Initialisation

- int starpu mpi init comm (int \*argc, char \*\*\*argv, int initialize mpi, MPI Comm comm)
- int starpu mpi init (int \*argc, char \*\*\*argv, int initialize mpi)
- int starpu\_mpi\_initialize (void)
- int starpu\_mpi\_initialize\_extended (int \*rank, int \*world\_size)
- int starpu mpi shutdown (void)
- void starpu\_mpi\_comm\_amounts\_retrieve (size\_t \*comm\_amounts)

### **Collective Operations**

- void starpu\_mpi\_redux\_data (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle)
- int starpu\_mpi\_scatter\_detached (starpu\_data\_handle\_t \*data\_handles, int count, int root, MPI\_Comm comm, void(\*scallback)(void \*), void \*sarg, void(\*rcallback)(void \*), void \*rarg)
- int starpu\_mpi\_gather\_detached (starpu\_data\_handle\_t \*data\_handles, int count, int root, MPI\_Comm comm, void(\*scallback)(void \*), void \*sarg, void(\*rcallback)(void \*), void \*rarg)

#### **Communication Cache**

- void starpu\_mpi\_cache\_flush (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle)
- void starpu mpi cache flush all data (MPI Comm comm)
- int starpu\_mpi\_cache\_is\_enabled ()
- · int starpu mpi cache set (int enabled)

#### **Node Selection Policy**

- int starpu mpi node selection register policy (starpu mpi select node policy func t policy func)
- int starpu\_mpi\_node\_selection\_unregister\_policy (int policy)
- int starpu\_mpi\_node\_selection\_get\_current\_policy ()
- int starpu\_mpi\_node\_selection\_set\_current\_policy (int policy)

#### **MPI Insert Task**

- #define starpu\_mpi\_data\_register(data\_handle, tag, rank)
- #define starpu\_mpi\_data\_set\_rank(handle, rank)
- #define starpu\_data\_set\_rank
- #define starpu\_data\_set\_tag
- #define starpu\_data\_get\_rank
- #define starpu\_data\_get\_tag
- struct starpu\_task \* starpu\_mpi\_task\_build (MPI\_Comm comm, struct starpu\_codelet \*codelet,...)
- int starpu\_mpi\_task\_post\_build (MPI\_Comm comm, struct starpu\_codelet \*codelet,...)
- int starpu mpi task insert (MPI Comm comm, struct starpu codelet \*codelet,...)
- int starpu mpi insert task (MPI Comm comm, struct starpu codelet \*codelet,...)
- void starpu\_mpi\_get\_data\_on\_node (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle, int node)

 void starpu\_mpi\_get\_data\_on\_node\_detached (MPI\_Comm comm, starpu\_data\_handle\_t data\_handle, int node, void(\*callback)(void \*), void \*arg)

- void starpu\_mpi\_data\_register\_comm (starpu\_data\_handle\_t data\_handle, int tag, int rank, MPI\_Comm comm)
- void starpu\_mpi\_data\_set\_rank\_comm (starpu\_data\_handle\_t handle, int rank, MPI\_Comm comm)
- void starpu\_mpi\_data\_set\_tag (starpu\_data\_handle\_t handle, int tag)
- int starpu mpi data get rank (starpu data handle t handle)
- int starpu\_mpi\_data\_get\_tag (starpu\_data\_handle\_t handle)

### 29.38.1 Detailed Description

# 29.39 starpufft.h File Reference

### **Typedefs**

- typedef double \_Complex starpufft\_complex
- typedef struct starpufft\_plan \* starpufft\_plan
- typedef float \_Complex starpufftf\_complex
- typedef struct starpufftf plan \* starpufftf plan
- typedef long double \_Complex starpufftl\_complex
- typedef struct starpufftl\_plan \* starpufftl\_plan

- starpufft\_plan starpufft\_plan\_dft\_1d (int n, int sign, unsigned flags)
- starpufft\_plan\_starpufft\_plan\_dft\_2d (int n, int m, int sign, unsigned flags)
- starpufft\_plan\_dft\_r2c\_1d (int n, unsigned flags)
- starpufft\_plan starpufft\_plan\_dft\_c2r\_1d (int n, unsigned flags)
- void \* starpufft\_malloc (size\_t n)
- void starpufft\_free (void \*p)
- int starpufft execute (starpufft plan p, void \*in, void \*out)
- struct starpu task \* starpufft start (starpufft plan p, void \*in, void \*out)
- int starpufft execute handle (starpufft plan p, starpu data handle t in, starpu data handle t out)
- struct starpu\_task \* starpufft\_start\_handle (starpufft\_plan p, starpu\_data\_handle\_t in, starpu\_data\_handle\_t out)
- void starpufft\_cleanup (starpufft\_plan p)
- void starpufft\_destroy\_plan (starpufft\_plan p)
- void starpufft\_startstats (void)
- void starpufft\_stopstats (void)
- void starpufft showstats (FILE \*out)
- starpufftf plan starpufftf plan dft 1d (int n, int sign, unsigned flags)
- starpufftf\_plan\_dft\_2d (int n, int m, int sign, unsigned flags)
- starpufftf\_plan starpufftf\_plan\_dft\_r2c\_1d (int n, unsigned flags)
- starpufftf plan starpufftf plan dft c2r\_1d (int n, unsigned flags)
- void \* starpufftf\_malloc (size t n)
- void starpufftf free (void \*p)
- int starpufftf\_execute (starpufftf\_plan p, void \*in, void \*out)
- struct starpu task \* starpufftf start (starpufftf plan p, void \*in, void \*out)
- int starpufftf execute handle (starpufftf plan p, starpu data handle t in, starpu data handle t out)
- struct starpu\_task \* **starpufftf\_start\_handle** (starpufftf\_plan p, starpu\_data\_handle\_t in, starpu\_data\_handle\_t out)
- void **starpufftf cleanup** (starpufftf plan p)
- void starpufftf\_destroy\_plan (starpufftf\_plan p)

- · void starpufftf\_startstats (void)
- void starpufftf\_stopstats (void)
- void starpufftf\_showstats (FILE \*out)
- starpufftl plan starpufftl plan dft 1d (int n, int sign, unsigned flags)
- starpufftl\_plan starpufftl\_plan\_dft\_2d (int n, int m, int sign, unsigned flags)
- starpufftl plan starpufftl plan dft r2c 1d (int n, unsigned flags)
- starpufftl\_plan\_dft\_c2r\_1d (int n, unsigned flags)
- void \* starpufftl\_malloc (size t n)
- void starpufftl\_free (void \*p)
- int starpufftl\_execute (starpufftl\_plan p, void \*in, void \*out)
- struct starpu task \* starpufftl start (starpufftl plan p, void \*in, void \*out)
- int starpufftl\_execute\_handle (starpufftl\_plan p, starpu\_data\_handle\_t in, starpu\_data\_handle\_t out)
- struct starpu\_task \* starpufftl\_start\_handle (starpufftl\_plan p, starpu\_data\_handle\_t in, starpu\_data\_handle\_t out)
- void starpufftl\_cleanup (starpufftl\_plan p)
- void starpufftl\_destroy\_plan (starpufftl\_plan p)
- void starpufftl\_startstats (void)
- void starpufftl\_stopstats (void)
- void starpufftl\_showstats (FILE \*out)

### **Variables**

· int starpufft\_last\_plan\_number

### 29.39.1 Detailed Description

# 29.40 sc\_hypervisor.h File Reference

```
#include <starpu.h>
#include <starpu_sched_ctx_hypervisor.h>
#include <sc_hypervisor_config.h>
#include <sc_hypervisor_monitoring.h>
#include <math.h>
```

#### **Data Structures**

struct sc\_hypervisor\_policy

- void \* sc\_hypervisor\_init (struct sc\_hypervisor\_policy \*policy)
- void sc hypervisor shutdown (void)
- void sc hypervisor register ctx (unsigned sched ctx, double total flops)
- void sc\_hypervisor\_unregister\_ctx (unsigned sched\_ctx)
- void sc\_hypervisor\_post\_resize\_request (unsigned sched\_ctx, int task\_tag)
- void sc\_hypervisor\_resize\_ctxs (unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- void sc hypervisor stop resize (unsigned sched ctx)
- void sc hypervisor start resize (unsigned sched ctx)
- const char \* sc\_hypervisor\_get\_policy ()
- void sc\_hypervisor\_add\_workers\_to\_sched\_ctx (int \*workers\_to\_add, unsigned nworkers\_to\_add, unsigned sched\_ctx)

void sc\_hypervisor\_remove\_workers\_from\_sched\_ctx (int \*workers\_to\_remove, unsigned nworkers\_to\_remove, unsigned sched ctx, unsigned now)

- void sc\_hypervisor\_move\_workers (unsigned sender\_sched\_ctx, unsigned receiver\_sched\_ctx, int \*workers\_to\_move, unsigned now)
- void sc\_hypervisor\_size\_ctxs (unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- unsigned sc\_hypervisor\_get\_size\_req (unsigned \*\*sched\_ctxs, int \*nsched\_ctxs, int \*\*workers, int \*nworkers)
- void sc\_hypervisor\_save\_size\_req (unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- void sc hypervisor free size reg (void)
- unsigned sc\_hypervisor\_can\_resize (unsigned sched\_ctx)
- void sc\_hypervisor\_set\_type\_of\_task (struct starpu\_codelet \*cl, unsigned sched\_ctx, uint32\_t footprint, size-\_t data\_size)
- void sc\_hypervisor\_update\_diff\_total\_flops (unsigned sched\_ctx, double diff\_total\_flops)
- void sc\_hypervisor\_update\_diff\_elapsed\_flops (unsigned sched\_ctx, double diff\_task\_flops)
- void sc hypervisor update resize interval (unsigned \*sched ctxs, int nsched ctxs, int max nworkers)
- void sc\_hypervisor\_get\_ctxs\_on\_level (unsigned \*\*sched\_ctxs, int \*nsched\_ctxs, unsigned hierarchy\_-level, unsigned father sched\_ctx id)
- unsigned sc hypervisor get nhierarchy levels (void)
- void sc hypervisor get leaves (unsigned \*sched ctxs, int nsched ctxs, unsigned \*leaves, int \*nleaves)
- double sc\_hypervisor\_get\_nready\_flops\_of\_all\_sons\_of\_sched\_ctx (unsigned sched\_ctx)
- void sc\_hypervisor\_print\_overhead ()

### **Variables**

starpu pthread mutex t act hypervisor mutex

### 29.40.1 Detailed Description

# 29.41 sc\_hypervisor\_config.h File Reference

#include <sc\_hypervisor.h>

### **Data Structures**

· struct sc hypervisor policy config

### Macros

- #define SC\_HYPERVISOR\_MAX IDLE
- #define SC HYPERVISOR MIN WORKING
- #define SC\_HYPERVISOR\_PRIORITY
- #define SC\_HYPERVISOR\_MIN\_WORKERS
- #define SC\_HYPERVISOR\_MAX\_WORKERS
- #define SC\_HYPERVISOR\_GRANULARITY
- #define SC\_HYPERVISOR\_FIXED\_WORKERS
- #define SC\_HYPERVISOR\_MIN\_TASKS
- #define SC\_HYPERVISOR\_NEW\_WORKERS\_MAX\_IDLE
- #define SC HYPERVISOR TIME TO APPLY
- #define SC HYPERVISOR NULL
- #define SC HYPERVISOR ISPEED W SAMPLE
- #define SC HYPERVISOR ISPEED CTX SAMPLE

- #define SC\_HYPERVISOR\_TIME\_SAMPLE
- #define MAX\_IDLE\_TIME
- #define MIN\_WORKING\_TIME

### **Functions**

- void sc hypervisor set config (unsigned sched ctx, void \*config)
- struct
   sc\_hypervisor\_policy\_config \* sc\_hypervisor\_get\_config (unsigned sched\_ctx)
- void sc hypervisor ctl (unsigned sched ctx,...)

# 29.41.1 Detailed Description

# 29.42 sc\_hypervisor\_lp.h File Reference

```
#include <sc_hypervisor.h>
#include <starpu_config.h>
```

#### **Functions**

- double **sc\_hypervisor\_lp\_get\_nworkers\_per\_ctx** (int nsched\_ctxs, int ntypes\_of\_workers, double res[nsched\_ctxs][ntypes\_of\_workers], int total\_nw[ntypes\_of\_workers], struct types\_of\_workers \*tw, unsigned \*in\_sched\_ctxs)
- double sc\_hypervisor\_lp\_get\_tmax (int nw, int \*workers)
- void sc\_hypervisor\_lp\_round\_double\_to\_int (int ns, int nw, double res[ns][nw], int res\_rounded[ns][nw])
- void **sc\_hypervisor\_lp\_redistribute\_resources\_in\_ctxs** (int ns, int nw, int res\_rounded[ns][nw], double res[ns][nw], unsigned \*sched\_ctxs, struct types\_of\_workers \*tw)
- void sc\_hypervisor\_lp\_distribute\_resources\_in\_ctxs (unsigned \*sched\_ctxs, int ns, int nw, int res\_rounded[ns][nw], double res[ns][nw], int \*workers, int nworkers, struct types\_of\_workers \*tw)
- void sc\_hypervisor\_lp\_distribute\_floating\_no\_resources\_in\_ctxs (unsigned \*sched\_ctxs, int ns, int nw, double res[ns][nw], int \*workers, int nworkers, struct types\_of\_workers \*tw)
- void **sc\_hypervisor\_lp\_place\_resources\_in\_ctx** (int ns, int nw, double w\_in\_s[ns][nw], unsigned \*sched\_ctxs, int \*workers, unsigned do\_size, struct types\_of\_workers \*tw)
- void sc\_hypervisor\_lp\_share\_remaining\_resources (int ns, unsigned \*sched\_ctxs, int nworkers, int \*workers)
- double sc\_hypervisor\_lp\_find\_tmax (double t1, double t2)
- unsigned sc\_hypervisor\_lp\_execute\_dichotomy (int ns, int nw, double w\_in\_s[ns][nw], unsigned solve\_lp\_integer, void \*specific\_data, double tmin, double tmax, double smallest\_tmax, double(\*lp\_estimated\_distrib\_func)(int ns, int nw, double draft\_w\_in\_s[ns][nw], unsigned is\_integer, double tmax, void \*specifc\_data))

### 29.42.1 Detailed Description

# 29.43 sc\_hypervisor\_monitoring.h File Reference

```
#include <sc hypervisor.h>
```

### **Data Structures**

- struct sc\_hypervisor\_resize\_ack
- struct sc\_hypervisor\_wrapper

#### **Functions**

- struct sc\_hypervisor\_wrapper \* sc\_hypervisor\_get\_wrapper (unsigned sched\_ctx)
- unsigned \* sc\_hypervisor\_get\_sched\_ctxs ()
- int sc\_hypervisor\_get\_nsched\_ctxs ()
- int sc\_hypervisor\_get\_nworkers\_ctx (unsigned sched\_ctx, enum starpu\_worker\_archtype arch)
- double sc hypervisor get elapsed flops per sched ctx (struct sc hypervisor wrapper \*sc w)
- double sc\_hypervisor\_get\_total\_elapsed\_flops\_per\_sched\_ctx (struct sc\_hypervisor\_wrapper \*sc\_w)
- double sc\_hypervisorsc\_hypervisor\_get\_speed\_per\_worker\_type (struct sc\_hypervisor\_wrapper \*sc\_w, enum starpu worker archtype arch)
- double sc\_hypervisor\_get\_speed (struct sc\_hypervisor\_wrapper \*sc\_w, enum starpu\_worker\_archtype arch)

# 29.43.1 Detailed Description

# 29.44 sc\_hypervisor\_policy.h File Reference

#include <sc\_hypervisor.h>

#### **Data Structures**

- struct types\_of\_workers
- struct sc\_hypervisor\_policy\_task\_pool

### **Macros**

- #define HYPERVISOR REDIM SAMPLE
- #define HYPERVISOR START REDIM SAMPLE
- #define SC NOTHING
- #define SC IDLE
- #define SC SPEED

- void sc\_hypervisor\_policy\_add\_task\_to\_pool (struct starpu\_codelet \*cl, unsigned sched\_ctx, uint32\_t footprint, struct sc\_hypervisor\_policy\_task\_pool \*\*task\_pools, size\_t data\_size)
- void sc\_hypervisor\_policy\_remove\_task\_from\_pool (struct starpu\_task \*task, uint32\_t footprint, struct sc\_hypervisor\_policy\_task\_pool \*\*task\_pools)
- struct sc\_hypervisor\_policy\_task\_pool \* sc\_hypervisor\_policy\_clone\_task\_pool (struct sc\_hypervisor\_policy\_task\_pool \*tp)
- void **sc\_hypervisor\_get\_tasks\_times** (int nw, int nt, double times[nw][nt], int \*workers, unsigned size\_ctxs, struct sc\_hypervisor\_policy\_task\_pool \*task\_pools)
- unsigned **sc\_hypervisor\_find\_lowest\_prio\_sched\_ctx** (unsigned req\_sched\_ctx, int nworkers\_to\_move)
- int \* sc\_hypervisor\_get\_idlest\_workers (unsigned sched\_ctx, int \*nworkers, enum starpu\_worker\_archtype arch)
- int \* sc\_hypervisor\_get\_idlest\_workers\_in\_list (int \*start, int \*workers, int nall\_workers, int \*nworkers, enum starpu worker archtype arch)
- int sc\_hypervisor\_get\_movable\_nworkers (struct sc\_hypervisor\_policy\_config \*config, unsigned sched\_-ctx, enum starpu\_worker\_archtype arch)
- int sc\_hypervisor\_compute\_nworkers\_to\_move (unsigned req\_sched\_ctx)

- unsigned sc\_hypervisor\_policy\_resize (unsigned sender\_sched\_ctx, unsigned receiver\_sched\_ctx, unsigned force resize, unsigned now)
- unsigned sc\_hypervisor\_policy\_resize\_to\_unknown\_receiver (unsigned sender\_sched\_ctx, unsigned now)
- double sc\_hypervisor\_get\_ctx\_speed (struct sc\_hypervisor\_wrapper \*sc\_w)
- double sc\_hypervisor\_get\_slowest\_ctx\_exec\_time (void)
- double sc\_hypervisor\_get\_fastest\_ctx\_exec\_time (void)
- double sc\_hypervisor\_get\_speed\_per\_worker (struct sc\_hypervisor\_wrapper \*sc\_w, unsigned worker)
- double sc\_hypervisor\_get\_speed\_per\_worker\_type (struct sc\_hypervisor\_wrapper \*sc\_w, enum starpu\_-worker\_archtype arch)
- double sc\_hypervisor\_get\_ref\_speed\_per\_worker\_type (struct sc\_hypervisor\_wrapper \*sc\_w, enum starpu worker archtype arch)
- double sc\_hypervisor\_get\_avg\_speed (enum starpu\_worker\_archtype arch)
- void sc\_hypervisor\_check\_if\_consider\_max (struct types\_of\_workers \*tw)
- void sc hypervisor group workers by type (struct types of workers \*tw, int \*total nw)
- enum starpu\_worker\_archtype sc\_hypervisor\_get\_arch\_for\_index (unsigned w, struct types\_of\_workers \*tw)
- unsigned sc\_hypervisor\_get\_index\_for\_arch (enum starpu\_worker\_archtype arch, struct types\_of\_workers \*tw)
- unsigned sc\_hypervisor\_criteria\_fulfilled (unsigned sched\_ctx, int worker)
- unsigned sc hypervisor check idle (unsigned sched ctx, int worker)
- unsigned sc\_hypervisor\_check\_speed\_gap\_btw\_ctxs (unsigned \*sched\_ctxs, int nsched\_ctxs, int \*workers, int nworkers)
- unsigned **sc\_hypervisor\_check\_speed\_gap\_btw\_ctxs\_on\_level** (int level, int \*workers\_in, int nworkers\_in, unsigned father\_sched\_ctx\_id, unsigned \*\*sched\_ctxs, int \*nsched\_ctxs)
- unsigned sc\_hypervisor\_get\_resize\_criteria ()
- struct types of workers \* sc hypervisor get types of workers (int \*workers, unsigned nworkers)

### 29.44.1 Detailed Description

### 29.44.2 Data Structure Documentation

### 29.44.2.1 struct types\_of\_workers

#### **Data Fields**

unsigned	ncpus	
unsigned	ncuda	
unsigned	nw	

# **Chapter 30**

# **Deprecated List**

### Global starpu codelet::cpu func

Optional field which has been made deprecated. One should use instead the field starpu\_codelet::cpu\_funcs.

#### Global starpu codelet::cuda func

Optional field which has been made deprecated. One should use instead the starpu\_codelet::cuda\_funcs field.

### Global starpu\_codelet::opencl\_func

Optional field which has been made deprecated. One should use instead the starpu\_codelet::opencl\_funcs field.

### Global starpu data free pinned if possible

Equivalent to starpu\_free(). This macro is provided to avoid breaking old codes.

### Global starpu\_data\_malloc\_pinned\_if\_possible

Equivalent to starpu\_malloc(). This macro is provided to avoid breaking old codes.

# Global starpu\_mpi\_initialize (void)

This function has been made deprecated. One should use instead the function starpu\_mpi\_init(). This function does not call MPI\_Init(), it should be called beforehand.

# Global starpu\_mpi\_initialize\_extended (int \*rank, int \*world\_size)

This function has been made deprecated. One should use instead the function starpu\_mpi\_init(). MPI will be initialized by starpumpi by calling MPI\_Init\_Thread(argc, argv, MPI\_THREAD\_SERIALIZED, ...).

### Global STARPU\_MULTIPLE\_CPU\_IMPLEMENTATIONS

Setting the field starpu\_codelet::cpu\_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu\_codelet::cpu\_funcs.

#### Global STARPU MULTIPLE CUDA IMPLEMENTATIONS

Setting the field <a href="starpu\_codelet::cuda\_func">starpu\_codelet::cuda\_func</a> with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field <a href="starpu\_codelet::cuda\_funcs">starpu\_codelet::cuda\_funcs</a>.

### **Global STARPU MULTIPLE OPENCL IMPLEMENTATIONS**

Setting the field starpu\_codelet::opencl\_func with this macro indicates the codelet will have several implementations. The use of this macro is deprecated. One should always only define the field starpu\_codelet::opencl\_funcs.

392 **Deprecated List**  Part VI

**Appendix** 

## **Chapter 31**

# Full Source Code for the 'Scaling a Vector' Example

## 31.1 Main Application

```
* This example demonstrates how to use StarPU to scale an array by a factor.
 * It shows how to manipulate data with StarPU's data management library.
 \star 1- how to declare a piece of data to StarPU (starpu_vector_data_register)
 \star 2- how to describe which data are accessed by a task (task->handles[0])
 * 3- how a kernel can manipulate the data (buffers[0].vector.ptr)
#include <starpu.h>
#define NX
extern void scal_cpu_func(void *buffers[], void *_args);
extern void scal_sse_func(void *buffers[], void *_args);
extern void scal_cuda_func(void *buffers[], void *_args);
extern void scal_opencl_func(void *buffers[], void *_args);
static struct starpu_codelet cl = {
    .where = STARPU_CPU | STARPU_CUDA | STARPU_OPENCL
    /* CPU implementation of the codelet \star/
    cpu_funcs = { scal_cpu_func, scal_sse_func },
.cpu_funcs_name = { "scal_cpu_func", "scal_sse_func" },
#ifdef STARPU_USE_CUDA
    /\star CUDA implementation of the codelet \star/
    .cuda_funcs = { scal_cuda_func },
#endif
#ifdef STARPU_USE_OPENCL
    /* OpenCL implementation of the codelet */
     .opencl_funcs = { scal_opencl_func },
#endif
    .nbuffers = 1,
    .modes = { STARPU_RW }
#ifdef STARPU_USE_OPENCL
struct starpu_opencl_program programs;
#endif
int main (int argc, char **argv)
    /\star We consider a vector of float that is initialized just as any of {\rm C}
       * data */
    float vector[NX];
    unsigned i;
for (i = 0; i < NX; i++)</pre>
         vector[i] = 1.0f;
    fprintf(stderr, "BEFORE: First element was f^n, vector[0]);
    /* Initialize StarPU with default configuration */
    starpu init(NULL);
#ifdef STARPU_USE_OPENCL
         starpu_opencl_load_opencl_from_file(
                 "examples/basic_examples/vector_scal_opencl_kernel.cl", &
programs, NULL);
#endif
    /\star Tell StaPU to associate the "vector" vector with the "vector_handle"
```

```
* identifier. When a task needs to access a piece of data, it should
     * refer to the handle that is associated to it.
* In the case of the "vector" data interface:
     \star\, - the first argument of the registration method is a pointer to the
          handle that should describe the data
       - the second argument is the memory node where the data (ie. "vector")
          resides initially: STARPU_MAIN_RAM stands for an address in main
       memory, as

* opposed to an adress on a GPU for instance.
* - the third argument is the adress of the vector in RAM
* - the fourth argument is the number of elements in the vector

       - the fifth argument is the size of each element.
    starpu_data_handle_t vector_handle;
    starpu_vector_data_register(&vector_handle,
      STARPU_MAIN_RAM, (uintptr_t) vector,
                                   NX, sizeof(vector[0]));
    float factor = 3.14;
    /* create a synchronous task: any call to starpu_task_submit will block
      * until it is terminated */
    struct starpu_task *task = starpu_task_create(
    task->synchronous = 1;
    task->cl = &cl;
    /\star the codelet manipulates one buffer in RW mode \star/
    task->handles[0] = vector_handle;
    /* an argument is passed to the codelet, beware that this is a
     \star READ-ONLY buffer and that the codelet may be given a pointer to a
     \star COPY of the argument \star/
    task->cl_arg = &factor;
    task->cl_arg_size = sizeof(factor);
    /* execute the task on any eligible computational ressource */
    starpu_task_submit(task);
    /\star StarPU does not need to manipulate the array anymore so we can stop
      * monitoring it */
    starpu_data_unregister(vector handle):
#ifdef STARPU_USE_OPENCL
    starpu_opencl_unload_opencl(&programs);
#endif
    /\star terminate StarPU, no task can be submitted after \star/
    starpu shutdown();
    fprintf(stderr, "AFTER First element is f^n, vector[0]);
    return 0;
```

### 31.2 CPU Kernel

```
#include <starpu.h>
#include <xmmintrin.h>

/* This kernel takes a buffer and scales it by a constant factor */
void scal_cpu_func(void *buffers[], void *cl_arg)
{
    unsigned i;
    float *factor = cl_arg;

    /*
        * The "buffers" array matches the task->handles array: for instance
        * task->handles[0] is a handle that corresponds to a data with
        * vector "interface", so that the first entry of the array in the
        * codelet is a pointer to a structure describing such a vector (ie.
        * struct starpu_vector_interface *). Here, we therefore manipulate
        * the buffers[0] element as a vector: nx gives the number of elements
        * in the array, ptr gives the location of the array (that was possibly
        * migrated/replicated), and elemsize gives the size of each elements.
        */
        struct starpu_vector_interface *vector = buffers[0];

        /* length of the vector */
        unsigned n = STARPU_VECTOR_GET_NX(vector);
```

31.3 CUDA Kernel 397

```
/* get a pointer to the local copy of the vector: note that we have to
      \star cast it in (float \star) since a vector could contain any type of
     * elements so that the .ptr field is actually a uintptr_t float *val = (float *)STARPU_VECTOR_GET_PTR(vector);
     /* scale the vector */
for (i = 0; i < n; i++)</pre>
          val[i] *= *factor;
void scal_sse_func(void *buffers[], void *cl_arg)
     float *vector = (float *) STARPU_VECTOR_GET_PTR(
       buffers[0]);
     unsigned int n = STARPU_VECTOR_GET_NX(buffers[0]);
     unsigned int n_iterations = n/4;
     __m128 *VECTOR = (__m128*) vector;
__m128 FACTOR STARPU_ATTRIBUTE_ALIGNED(16);
     float factor = *(float *) cl_arg;
     FACTOR = _mm_set1_ps(factor);
     unsigned int i;
for (i = 0; i < n_iterations; i++)
    VECTOR[i] = _mm_mul_ps(FACTOR, VECTOR[i]);</pre>
     unsigned int remainder = n%4;
     if (remainder != 0)
          unsigned int start = 4 * n_iterations;
for (i = start; i < start+remainder; ++i)</pre>
                vector[i] = factor * vector[i];
     }
```

## 31.3 CUDA Kernel

```
#include <starpu.h>
static __global__ void vector_mult_cuda(unsigned n, float *val,
{
        unsigned i = blockIdx.x*blockDim.x + threadIdx.x;
        if (i < n)
               val[i] *= factor;
extern "C" void scal_cuda_func(void *buffers[], void *_args)
        float *factor = (float *)_args;
        /* length of the vector */
        unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
        /* local copy of the vector pointer */
        float *val = (float *)STARPU_VECTOR_GET_PTR(
      buffers[0]);
        unsigned threads_per_block = 64;
        unsigned nblocks = (n + threads_per_block-1) / threads_per_block;
        vector_mult_cuda<<<nblocks,threads_per_block, 0,</pre>
       starpu_cuda_get_local_stream()>>>
                        (n, val, *factor);
       cudaStreamSynchronize(starpu_cuda_get_local_stream
      ());
```

## 31.4 OpenCL Kernel

## 31.4.1 Invoking the Kernel

```
#include <starpu.h>
extern struct starpu_opencl_program programs;
void scal_opencl_func(void *buffers[], void *_args)
```

```
{
    float *factor = _args;
    int id, devid, err;
                                              /* OpenCL specific code */
    cl_kernel kernel;
                                              /\star OpenCL specific code \star/
    cl_command_queue queue;
                                              /* OpenCL specific code */
                                              /* OpenCL specific code */
    cl event event;
    /* length of the vector */
    unsigned n = STARPU_VECTOR_GET_NX(buffers[0]);
    /* OpenCL copy of the vector pointer */
cl_mem val = (cl_mem) STARPU_VECTOR_GET_DEV_HANDLE
      (buffers[0]);
    { /* OpenCL specific code */
         id = starpu_worker_get_id();
         devid = starpu_worker_get_devid(id);
         err = starpu_opencl_load_kernel(&kernel, &
      queue,
                                              &programs,
                                              "vector_mult_opencl", /* Name of the
       codelet */
                                             devid);
         if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR
      (err);
         err = clSetKernelArg(kernel, 0, sizeof(n), &n);
         err |= clSetKernelArg(kernel, 1, sizeof(val), &val);
err |= clSetKernelArg(kernel, 2, sizeof(*factor), factor);
if (err) STARPU_OPENCL_REPORT_ERROR(err);
       /* OpenCL specific code */
        size_t global=n;
        size_t local;
        size_t s;
        cl_device_id device;
        starpu_opencl_get_device(devid, &device);
         err = clGetKernelWorkGroupInfo (kernel, device,
      CL_KERNEL_WORK_GROUP_SIZE,
                                            sizeof(local), &local, &s);
        if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR
      (err);
        if (local > global) local=global;
        err = clEnqueueNDRangeKernel(queue, kernel, 1, NULL, &global, &local, 0
                                        NULL, &event);
         if (err != CL_SUCCESS) STARPU_OPENCL_REPORT_ERROR
      (err);
    { /* OpenCL specific code */
         clFinish(queue);
         starpu_opencl_collect_stats(event);
         clReleaseEvent(event);
         starpu_opencl_release_kernel(kernel);
    }
}
```

#### 31.4.2 Source of the Kernel

```
__kernel void vector_mult_opencl(int nx, __global float* val, float factor)
{
      const int i = get_global_id(0);
      if (i < nx) {
           val[i] *= factor;
      }
}</pre>
```

## **Chapter 32**

## **GNU Free Documentation License**

Version 1.3, 3 November 2008

Copyright

2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc. http://fsf.org/ Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 1. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document *free* in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 2. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does

not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

The "publisher" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

#### 3. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 4. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 5. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- (a) Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- (b) List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- (c) State on the Title page the name of the publisher of the Modified Version, as the publisher.
- (d) Preserve all the copyright notices of the Document.
- (e) Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- (f) Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- (g) Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- (h) Include an unaltered copy of this License.
- (i) Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- (j) Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- (k) For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- (I) Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- (m) Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- (n) Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- (o) Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these

sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

#### 6. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements."

### 7. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

#### 8. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

### 9. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

#### 10. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

#### 11. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

#### 12. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

## 32.1 ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (C) year your name. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published

by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

with the Invariant Sections being *list their titles*, with the Front-Cover Texts being *list*, and with the Back-Cover Texts being *list*.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

Part VII

Index

# Index

_Configure Options	mic-host, 153
disable-asynchronous-copy, 152	with-atlas-dir, 153
disable-asynchronous-cuda-copy, 152	with-coi-dir, 153
disable-asynchronous-mic-copy, 152	with-cuda-dir, 152
disable-asynchronous-opencl-copy, 152	with-cuda-include-dir, 152
disable-build-doc, 151	with-cuda-lib-dir, 152
disable-build-examples, 154	with-fxt, 153
disable-build-tests, 154	with-goto-dir, 153
disable-cpu, 152	with-hwloc, 151
disable-cuda, 152	with-mkl-cflags, 154
disable-cuda-memcpy-peer, 152	with-mkl-ldflags, 154
disable-fortran, 153	with-mpicc, 153
disable-gcc-extensions, 153	with-opencl-dir, 152
disable-opencl, 152	with-opencl-include-dir, 152
disable-socl, 153	with-opencl-lib-dir, 152
disable-starpu-top, 153	with-perf-model-dir, 153
disable-starpufft, 153	with-simgrid-dir, 154
enable-allocation-cache, 153	with-simgrid-include-dir, 154
enable-blas-lib, 153	with-simgrid-lib-dir, 154
enable-calibration-heuristic, 154	with-smpirun, 154
enable-coverage, 151	without-hwloc, 151
enable-debug, 151	Environment Variables
enable-fast, 151	OCL_ICD_VENDORS, 148
enable-fxt-lock, 153	SC_HYPERVISOR_LAZY_RESIZE, 150
enable-long-check, 151	SC_HYPERVISOR_MAX_SPEED_GAP, 150
enable-max-sched-ctxs, 152	SC_HYPERVISOR_POLICY, 150
enable-maxbuffers, 153	SC_HYPERVISOR_SAMPLE_CRITERIA, 150
enable-maxcpus, 152	SC_HYPERVISOR_START_RESIZE, 150
enable-maxcudadev, 152	SC_HYPERVISOR_STOP_PRINT, 150
enable-maximplementations, 152	SC_HYPERVISOR_TRIGGER_RESIZE, 150
enable-maxmicthreads, 152	SOCL_OCL_LIB_OPENCL, 148
enable-maxnodes, 152	STARPU_BUS_CALIBRATE, 147
enable-maxopencldev, 152	STARPU_BUS_STATS, 149
enable-memory-stats, 154	STARPU_CALIBRATE, 147
enable-model-debug, 153	STARPU_CALIBRATE_MINIMUM, 147
enable-mpi-progression-hook, 153	STARPU_COMM_STATS, 148
enable-new-check, 151	STARPU_CUDA_PIPELINE, 145
enable-opencl-simulator, 152	STARPU_DISABLE_ASYNCHRONOUS_COPY,
enable-opengl-render, 153	147
enable-openmp, 153	STARPU_DISABLE_ASYNCHRONOUS_CUDA
enable-paje-codelet-details, 153	COPY, 147
enable-perf-debug, 153	STARPU_DISABLE_ASYNCHRONOUS_MIC
enable-quick-check, 151	COPY, 147
enable-sc-hypervisor, 154	STARPU_DISABLE_ASYNCHRONOUS_OPENCL
enable-simgrid, 154	_COPY, 147
enable-spinlock-check, 151	STARPU_DISABLE_KERNELS, 150
enable-starpufft-examples, 153	STARPU_DISABLE_PINNING, 147
enable-stats, 153	STARPU_DISK_SWAP, 149
enable-verbose, 151	STARPU_DISK_SWAP_BACKEND, 149

STARPU_DISK_SWAP_SIZE, 149	STARPU_WORKER_STATS, 150
STARPU_ENABLE_CUDA_GPU_GPU_DIRECT,	STARPU WORKERS CPUID, 146
147	STARPU WORKERS CUDAID, 146
STARPU_FXT_PREFIX, 148	STARPU WORKERS MICID, 146
STARPU GENERATE TRACE, 149	STARPU_WORKERS_NOBIND, 146
STARPU HISTORY MAX ERROR, 150	STARPU_WORKERS_OPENCLID, 146
STARPU HOME, 148	STARPU_WORKERS_SCCID, 146
STARPU HOSTNAME, 148	
STARPU IDLE POWER, 147	add
STARPU_LIMIT_CPU_MEM, 149	starpu_worker_collection, 179
STARPU_LIMIT_CUDA_devid_MEM, 148	add_child
STARPU LIMIT CUDA MEM, 149	starpu_sched_component, 334
STARPU LIMIT MAX NSUBMITTED TASKS,	add_parent
149	starpu_sched_component, 334
STARPU_LIMIT_MIN_NSUBMITTED_TASKS, 149	add_workers
STARPU LIMIT OPENCL devid MEM, 149	starpu_sched_policy, 318
STARPU LIMIT OPENCL MEM, 149	alloc
STARPU LOGFILENAME, 148	starpu_disk_ops, 220
STARPU MAX WORKERSIZE, 146	allocate_data_on_node
STARPU MEMORY STATS, 149	starpu_data_interface_ops, 192
STARPU MIN WORKERSIZE, 146	any_to_any
STARPU MINIMUM AVAILABLE MEM, 149	starpu_data_copy_methods, 197
STARPU MINIMUM CLEAN BUFFERS, 149	async_full_read
STARPU MPI CACHE, 148	starpu_disk_ops, 220
STARPU MPI CACHE STATS, 148	async_full_write
STARPU MPI COMM, 148	starpu_disk_ops, 220
STARPU_NCPU, 145	async_read
STARPU NCPUS, 145	starpu_disk_ops, 220
STARPU NCUDA, 145	async_write
STARPU_NMIC, 145	starpu_disk_ops, 220
STARPU NMICCORES, 145	
STARPU NOPENCL, 145	bandwidth
——————————————————————————————————————	starpu_disk_ops, 220
STARPU_NSCC, 146	Bitmap, 175
STARPU_NWORKER_PER_CUDA, 145 STARPU_OPENCL_ON_CPUS, 145	starpu_bitmap_and_get, 177
:	starpu_bitmap_cardinal, 177
STARPU_OPENCL_ONLY_ON_CPUS, 145	starpu_bitmap_create, 176
STARPU_OPENCL_PIPELINE, 145	starpu_bitmap_destroy, 176
STARPU_OPENCL_PROGRAM_DIR, 148	starpu_bitmap_first, 177
STARPU_PERF_MODEL_DIR, 148	starpu_bitmap_get, 176
STARPU_PREFETCH, 147	starpu_bitmap_has_next, 177
STARPU_PROFILING, 147	starpu_bitmap_last, 177
STARPU_RAND_SEED, 150	starpu_bitmap_next, 177
STARPU_SCHED, 147	starpu_bitmap_or, 176
STARPU_SCHED_ALPHA, 147	starpu_bitmap_set, 176
STARPU_SCHED_BETA, 147	starpu_bitmap_unset, 176
STARPU_SCHED_GAMMA, 147	starpu_bitmap_unset_all, 176
STARPU_SILENT, 148	starpu_bitmap_unset_and, 176
STARPU_SIMGRID_CUDA_MALLOC_COST, 148	bundle
STARPU_SIMGRID_CUDA_QUEUE_COST, 148	starpu_task, 234
STARPU_SINGLE_COMBINED_WORKER, 146	
STARPU_STATS, 150	CUDA Extensions, 257
STARPU_SYNTHESIZE_ARITY_COMBINED	STARPU_MAXCUDADEVS, 257
WORKER, 146	STARPU_USE_CUDA, 257
STARPU_TARGET_AVAILABLE_MEM, 149	starpu_cublas_init, 258
STARPU_TARGET_CLEAN_BUFFERS, 149	starpu_cublas_report_error, 258
STARPU_TRACE_BUFFER_SIZE, 149	starpu_cublas_shutdown, 258
STARPU_WATCHDOG_CRASH, 150	starpu_cuda_copy_async_sync, 258
STARPU WATCHDOG TIMEOUT, 150	starpu cuda get device properties, 257

starpu_cuda_get_local_stream, 257	starpu_mic_kernel_t, 237
starpu_cuda_report_error, 258	starpu_opencl_func_t, 237
starpu_cuda_set_device, 258	starpu_scc_func_t, 237
callback	starpu_scc_kernel_t, 237
starpu_top_param, 307	starpu_task_clean, 238
callback_arg	starpu_task_create, 238
starpu_task, 232	starpu_task_destroy, 239
callback_arg_free	starpu_task_dup, 238
starpu_task, 232	starpu_task_get_current, 240
callback func	starpu_task_get_implementation, 240
starpu_task, 232	starpu_task_init, 238
can_copy	starpu_task_nready, 240
starpu_data_copy_methods, 194	starpu_task_nsubmitted, 240
can execute	starpu_task_set_implementation, 240
starpu_codelet, 226	starpu_task_status, 238
can_pull	starpu_task_submit, 239
	starpu task submit to ctx, 239
starpu_sched_component, 335	starpu_task_wait, 239
can_push	starpu_task_wait_for_all, 239
starpu_sched_component, 335	starpu task wait for all in ctx, 239
children	starpu task wait for n submitted, 239
starpu_sched_component, 334	
cl	starpu_task_wait_for_n_submitted_in_ctx, 239
starpu_task, 230	starpu_task_wait_for_no_ready, 240
cl_arg	compare
starpu_task, 231	starpu_data_interface_ops, 193
cl_arg_free	сору
starpu_task, 232	starpu_disk_ops, 221
cl_arg_size	copy_methods
starpu_task, 231	starpu_data_interface_ops, 193
	cost_function
close	cost_function starpu_perfmodel, 248
close starpu_disk_ops, 220	
close starpu_disk_ops, 220 Codelet And Tasks, 224	starpu_perfmodel, 248
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238	starpu_perfmodel, 248 cpu_func
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227 cpu_funcs
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227 cpu_funcs starpu_codelet, 227 cpu_funcs_name
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227 cpu_funcs starpu_codelet, 227 cpu_funcs_name starpu_codelet, 228
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227 cpu_funcs starpu_codelet, 227 cpu_funcs_name starpu_codelet, 228 cuda_flags
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227 cpu_funcs starpu_codelet, 227 cpu_funcs_name starpu_codelet, 228 cuda_flags starpu_codelet, 227
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238	starpu_perfmodel, 248 cpu_func starpu_codelet, 227 cpu_funcs starpu_codelet, 227 cpu_funcs_name starpu_codelet, 228 cuda_flags starpu_codelet, 227 cuda_func
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_func     starpu_codelet, 227
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAGK, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAGK, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CUDA, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237 starpu_codelet_display_stats, 240	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async     starpu_data_copy_methods, 195
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 238 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237 starpu_codelet_display_stats, 240 starpu_codelet_init, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async     starpu_data_copy_methods, 196  custom
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237 starpu_codelet_display_stats, 240 starpu_codelet_type, 238	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async     starpu_data_copy_methods, 195
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237 starpu_codelet_display_stats, 240 starpu_codelet_type, 238 starpu_codelet_type, 238 starpu_cpu_func_t, 237	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async     starpu_data_copy_methods, 196  custom     sc_hypervisor_policy, 327
close starpu_disk_ops, 220  Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_CPU, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_MIC, 235 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237 starpu_codelet_display_stats, 240 starpu_codelet_type, 238 starpu_cpu_func_t, 237 starpu_create_sync_task, 240	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_funcs     starpu_data_copy_methods, 195  cuda_to_cuda     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async     starpu_data_copy_methods, 196  custom     sc_hypervisor_policy, 327
close starpu_disk_ops, 220 Codelet And Tasks, 224 STARPU_FORKJOIN, 238 STARPU_SEQ, 238 STARPU_SPMD, 238 STARPU_TASK_BLOCKED, 238 STARPU_TASK_BLOCKED_ON_DATA, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TAG, 238 STARPU_TASK_BLOCKED_ON_TASK, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_FINISHED, 238 STARPU_TASK_READY, 238 STARPU_TASK_RUNNING, 238 STARPU_TASK_RUNNING, 235 STARPU_CUDA, 235 STARPU_MAIN_RAM, 235 STARPU_MIC, 235 STARPU_NMAXBUFS, 236 STARPU_NOWHERE, 234 STARPU_OPENCL, 235 STARPU_SCC, 235 STARPU_TASK_INVALID, 237 starpu_codelet_display_stats, 240 starpu_codelet_type, 238 starpu_codelet_type, 238 starpu_cpu_func_t, 237	starpu_perfmodel, 248  cpu_func     starpu_codelet, 227  cpu_funcs     starpu_codelet, 227  cpu_funcs_name     starpu_codelet, 228  cuda_flags     starpu_codelet, 227  cuda_func     starpu_codelet, 227  cuda_funcs     starpu_codelet, 227  cuda_to_cuda     starpu_data_copy_methods, 195  cuda_to_cuda_async     starpu_data_copy_methods, 196  cuda_to_opencl     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram     starpu_data_copy_methods, 195  cuda_to_ram_async     starpu_data_copy_methods, 196  custom     sc_hypervisor_policy, 327

STARPU BCSR INTERFACE ID, 205	starpu_free_on_node_flags, 210
STARPU BLOCK INTERFACE ID, 205	starpu hash crc32c be, 211
STARPU COO INTERFACE ID, 205	starpu_hash_crc32c_be_n, 211
STARPU CSR INTERFACE ID, 205	starpu_hash_crc32c_string, 211
STARPU MATRIX INTERFACE ID, 205	starpu_interface_copy, 211
STARPU MAX INTERFACE ID, 205	starpu_malloc_on_node, 210
STARPU_MULTIFORMAT_INTERFACE_ID, 205	starpu_malloc_on_node_flags, 210
STARPU UNKNOWN INTERFACE ID, 205	starpu_malloc_on_node_set_default_flags, 211
STARPU VARIABLE INTERFACE ID, 205	starpu matrix data register, 206
STARPU_VECTOR_INTERFACE_ID, 205	starpu matrix get elemsize, 208
STARPU VOID INTERFACE ID, 205	starpu_matrix_get_local_ld, 208
STARPU BCSR GET NNZ, 202	starpu_matrix_get_local_ptr, 208
STARPU_BLOCK_GET_NX, 201	starpu_matrix_get_nocal_ptr, 208 starpu_matrix_get_nx, 208
STARPU BLOCK GET NY, 201	starpu_matrix_get_nx, 200 starpu_matrix_get_ny, 208
STARPU_BLOCK_GET_NZ, 201	starpu_matrix_ptr_register, 206
STARPU_COO_GET_NX, 204	starpu_mamx_pti_register, 200 starpu_variable_data_register, 205
STARPU_COO_GET_NY, 204	starpu_variable_data_register, 200 starpu_variable_get_elemsize, 208
	•
STARPU_COO_GET_ROWS, 204	starpu_variable_get_local_ptr, 208
STARPU_CSR_GET_NNZ, 202	starpu_variable_ptr_register, 205
STARPU_CSR_GET_NROW, 203	starpu_vector_data_register, 205
starpu_bcsr_data_register, 206	starpu_vector_get_elemsize, 208
starpu_bcsr_get_c, 210	starpu_vector_get_local_ptr, 208
starpu_bcsr_get_elemsize, 210	starpu_vector_get_nx, 208
starpu_bcsr_get_firstentry, 209	starpu_vector_ptr_register, 206
starpu_bcsr_get_local_colind, 209	starpu_void_data_register, 205
starpu_bcsr_get_local_nzval, 209	Data Management, 182
starpu_bcsr_get_local_rowptr, 209	STARPU_COMMUTE, 185
starpu_bcsr_get_nnz, 209	STARPU_NONE, 184
starpu_bcsr_get_nrow, 209	STARPU_R, 184
starpu_bcsr_get_r, 209	STARPU_REDUX, 185
starpu_block_data_register, 206	STARPU_RW, 184
starpu_block_get_elemsize, 209	STARPU_SCRATCH, 184
starpu_block_get_local_ldy, 209	STARPU_SSEND, 185
starpu_block_get_local_ldz, 209	STARPU_W, 184
starpu_block_get_local_ptr, 209	starpu_arbiter_create, 188
starpu_block_get_nx, 208	starpu_arbiter_destroy, 188
starpu_block_get_ny, 208	starpu_arbiter_t, 184
starpu_block_get_nz, 209	starpu_data_access_mode, 184
starpu_block_ptr_register, 206	starpu_data_acquire, 187
starpu_coo_data_register, 207	starpu_data_acquire_cb, 187
starpu_csr_data_register, 207	starpu_data_acquire_cb_sequential_consistency,
starpu_csr_get_elemsize, 210	187
starpu_csr_get_firstentry, 210	starpu_data_acquire_on_node, 187
starpu_csr_get_local_colind, 210	starpu_data_acquire_on_node_cb, 188
starpu_csr_get_local_nzval, 210	starpu_data_acquire_on_node_cb_sequential
starpu_csr_get_local_rowptr, 210	consistency, 188
starpu_csr_get_nnz, 210	starpu_data_advise_as_important, 187
starpu_csr_get_nrow, 210	starpu_data_assign_arbiter, 188
starpu_data_get_interface_id, 207	starpu_data_fetch_on_node, 186
starpu_data_get_interface_on_node, 207	starpu_data_get_interface_ops, 187
starpu_data_get_local_ptr, 207	starpu_data_handle_t, 184
starpu_data_get_size, 207	starpu_data_idle_prefetch_on_node, 186
starpu_data_handle_to_pointer, 207	starpu_data_invalidate, 185
starpu_data_interface_get_next_id, 211	starpu_data_invalidate_submit, 186
starpu_data_interface_id, 205	starpu_data_lookup, 186
starpu_data_pack, 207	starpu_data_prefetch_on_node, 186
starpu_data_unpack, 207	starpu_data_ptr_register, 185
starpu_free_on_node, 211	starpu_data_query_status, 186

starpu_data_register, 185	dontcache
starpu_data_register_same, 185	starpu_data_interface_ops, 193
starpu_data_release, 188	double_max_value
starpu_data_release_on_node, 188	starpu_top_param, 307
starpu_data_request_allocation, 186	double_min_value
starpu_data_set_reduction_methods, 187	starpu_top_param, 307
starpu_data_set_wt_mask, 186	dyn_handles
starpu_data_unregister, 185	starpu_task, 231
starpu_data_unregister_no_coherency, 185	dyn_interfaces
	starpu_task, 231
starpu_data_unregister_submit, 185	
starpu_data_wont_use, 186	dyn_modes
Data Partition, 211	starpu_codelet, 228
starpu_bcsr_filter_canonical_block, 218	starpu_task, 231
starpu_block_filter_block, 217	dyn_nodes
starpu_block_filter_block_shadow, 218	starpu_codelet, 229
starpu_block_filter_depth_block, 218	
starpu_block_filter_depth_block_shadow, 218	end_ctx
starpu_block_filter_vertical_block, 218	sc_hypervisor_policy, 327
starpu_block_filter_vertical_block_shadow, 218	enum_values
starpu csr filter vertical block, 218	starpu_top_param, 307
starpu_data_get_child, 214	estimated_end
starpu_data_get_nb_children, 214	starpu_sched_component, 335
starpu_data_get_sub_data, 214	estimated_load
	starpu_sched_component, 335
starpu_data_map_filters, 215	execute_on_a_specific_worker
starpu_data_partition, 214	starpu_task, 233
starpu_data_partition_clean, 216	Expert Mode, 304
starpu_data_partition_plan, 215	starpu_progression_hook_deregister, 305
starpu_data_partition_readonly_submit, 215	starpu_progression_hook_register, 305
starpu_data_partition_readwrite_upgrade_submit,	starpu_wake_all_blocked_workers, 304
216	Explicit Dependencies, 243
starpu_data_partition_submit, 215	starpu_tag_declare_deps, 244
starpu_data_unpartition, 214	
starpu_data_unpartition_readonly_submit, 216	starpu_tag_declare_deps_array, 244
starpu_data_unpartition_submit, 216	starpu_tag_notify_from_apps, 245
starpu_data_vget_sub_data, 215	starpu_tag_remove, 245
starpu_data_vmap_filters, 215	starpu_tag_restart, 245
starpu matrix filter block, 217	starpu_tag_t, 244
starpu matrix filter block shadow, 217	starpu_tag_wait, 245
•	starpu_tag_wait_array, 245
starpu_matrix_filter_vertical_block, 217	starpu_task_declare_deps_array, 244
starpu_matrix_filter_vertical_block_shadow, 217	starpu_task_get_task_succs, 244
starpu_vector_filter_block, 216	
starpu_vector_filter_block_shadow, 216	FFT Support, 289
starpu_vector_filter_divide_in_2, 217	starpufft_cleanup, 290
starpu_vector_filter_list, 217	starpufft_destroy_plan, 290
deinit	starpufft_execute, 290
starpu_worker_collection, 179	starpufft_execute_handle, 290
deinit_data	starpufft_free, 289
starpu_sched_component, 335	starpufft_malloc, 289
deinit sched	starpufft_plan_dft_1d, 289
starpu_sched_policy, 318	starpufft_plan_dft_2d, 289
describe	starpufft_start, 290
starpu_data_interface_ops, 193	starpufft_start_handle, 290
destroy	• — —
-	filter_arg
starpu_task, 233	starpu_data_filter, 214
detach	filter_arg_ptr
starpu_task, 233	starpu_data_filter, 214
display	filter_func
starpu_data_interface_ops, 193	starpu_data_filter, 213

flops	starpu_data_get_default_sequential_consistency-
starpu_task, 234	_flag, 246
footprint	starpu_data_get_sequential_consistency_flag, 246
starpu_data_interface_ops, 193	starpu_data_set_default_sequential_consistency
starpu_perfmodel, 248	flag, 246
free	starpu_data_set_sequential_consistency_flag, 246
starpu_disk_ops, 220	init
free_data_on_node	starpu_worker_collection, 179
starpu_data_interface_ops, 192	init_iterator
free_request	starpu_worker_collection, 179
starpu_disk_ops, 221	init_sched
full_read	starpu_sched_policy, 318
starpu_disk_ops, 220	Initialization and Termination, 158
full_write	starpu_asynchronous_copy_disabled, 161
starpu_disk_ops, 220	starpu_asynchronous_cuda_copy_disabled, 162
FxT Support, 287	starpu_asynchronous_mic_copy_disabled, 162
starpu_fxt_generate_trace, 288	starpu_asynchronous_opencl_copy_disabled, 162
starpu_fxt_options_init, 288	starpu_conf_init, 161
starpu_fxt_start_profiling, 288	starpu_init, 161
starpu_fxt_stop_profiling, 289	starpu_initialize, 161
starpu_fxt_trace_user_event, 289	starpu pause, 161
starpu_fxt_write_data_trace, 289	starpu_resume, 161
Starpu_ixt_write_data_trace, 209	starpu_shutdown, 161
get shild and	starpu_topology_print, 162
get_child_ops	Insert_Task, 240
starpu_data_filter, 214	STARPU_CALLBACK, 241
get_mf_ops	STARPU_DATA_ARRAY, 241
starpu_data_interface_ops, 193	STARPU FLOPS, 242
get_nchildren	STARPU NAME, 242
starpu_data_filter, 214	STARPU PRIORITY, 241
get_next	STARPU_SCHED_CTX, 242
starpu_worker_collection, 179	STARPU_TAG, 242
get_size	STARPU_TAG_ONLY, 242
starpu_data_interface_ops, 193	STARPU_VALUE, 241
	starpu_codelet_pack_args, 243
handle_idle_cycle	starpu_codelet_unpack_args, 243
sc_hypervisor_policy, 327	starpu_insert_task, 242
handle_idle_end	starpu_task_build, 243
sc_hypervisor_policy, 327	starpu_task_insert, 242
handle_poped_task	int_max_value
sc_hypervisor_policy, 327	starpu_top_param, 307
handle_post_exec_hook	int_min_value
sc_hypervisor_policy, 327	starpu_top_param, 307
handle_pushed_task	interface size
sc_hypervisor_policy, 327	starpu data interface ops, 193
handle_submitted_job	interfaceid
sc_hypervisor_policy, 327	starpu_data_interface_ops, 193
handle_to_pointer	interfaces
starpu_data_interface_ops, 193	starpu_task, 231
handles	is_init
starpu_task, 231	starpu_perfmodel, 248
has_next	is_loaded
starpu_worker_collection, 179	starpu_perfmodel, 248
hypervisor_tag	is_multiformat
starpu_task, 234	starpu_data_interface_ops, 193
id	MIC Extensions, 284
starpu_top_param, 307	STARPU_MAXMICDEVS, 285
Implicit Data Dependencies, 245	STARPU_USE_MIC, 285

	starpu_mic_func_symbol_t, 285	starpu_mpi_set_communication_tag, 296
	starpu_mic_get_kernel, 285	starpu_mpi_shutdown, 293
	starpu_mic_register_kernel, 285	starpu_mpi_task_build, 298
MPI	Support, 290	starpu_mpi_task_insert, 297
	STARPU_USE_MPI, 292	starpu_mpi_task_post_build, 298
	starpu_data_get_rank, 293	starpu_mpi_test, 295
	starpu_data_get_tag, 293	starpu_mpi_wait, 295
	starpu_data_set_rank, 292	magic
	starpu_data_set_tag, 292	starpu_task, 234
	starpu_mpi_barrier, 295	max_parallelism
	starpu_mpi_cache_flush, 296	starpu_codelet, 226
	starpu_mpi_cache_flush_all_data, 296	mf_skip
	starpu_mpi_cache_is_enabled, 296	starpu_task, 233
	starpu_mpi_cache_set, 296	mic_funcs
	starpu_mpi_comm_amounts_retrieve, 294	starpu_codelet, 227
	starpu_mpi_data_get_rank, 297	mic_to_ram
	starpu_mpi_data_get_tag, 297	starpu_data_copy_methods, 195
	starpu_mpi_data_register, 292	mic_to_ram_async
	starpu mpi data register comm, 296	starpu data copy methods, 197
	starpu_mpi_data_set_rank, 292	Miscellaneous Helpers, 286
	starpu mpi data set rank comm, 297	starpu_data_cpy, 286
	starpu mpi data set tag, 297	starpu_execute_on_each_worker, 287
	starpu_mpi_datatype_register, 296	starpu execute on each worker ex, 287
	starpu_mpi_datatype_unregister, 296	starpu_execute_on_specific_workers, 287
	starpu_mpi_gather_detached, 299	starpu_timing_now, 287
	starpu_mpi_get_communication_tag, 296	model
	starpu_mpi_get_data_on_node, 298	starpu_codelet, 229
	starpu_mpi_get_data_on_node_detached, 298	modes
	starpu_mpi_init, 293	starpu_codelet, 228
	starpu_mpi_init_comm, 293	starpu_task, 231
	starpu_mpi_initialize, 293	Modularized Scheduler Interface, 331
	starpu_mpi_initialize_extended, 293	STARPU SCHED COMPONENT HOMOGENE-
	starpu_mpi_insert_task, 297	OUS, 338
	starpu_mpi_irecv, 294	STARPU_SCHED_COMPONENT_SINGLE_ME-
	starpu_mpi_irecv_array_detached_unlock_tag,	MORY NODE, 338
	296	starpu_sched_component_can_execute_task, 339
	starpu_mpi_irecv_detached, 294	starpu_sched_component_composed_component-
	starpu mpi irecv detached sequential consistency,	
	294	starpu_sched_component_composed_recipe_add,
	starpu_mpi_irecv_detached_unlock_tag, 295	341
	starpu_mpi_isend, 294	starpu_sched_component_composed_recipe
	starpu_mpi_isend_array_detached_unlock_tag,	create, 341
	295	starpu sched component composed recipe -
	starpu_mpi_isend_detached, 294	create singleton, 341
	starpu_mpi_isend_detached_unlock_tag, 295	starpu_sched_component_composed_recipe
	starpu_mpi_issend, 295	destroy, 341
	starpu_mpi_issend_detached, 295	starpu_sched_component_connect, 338
	starpu_mpi_node_selection_get_current_policy,	starpu_sched_component_destroy, 338
	298	starpu_sched_component_destroy_rec, 338
	starpu_mpi_node_selection_register_policy, 298	starpu_sched_component_execute_preds, 339
	starpu_mpi_node_selection_set_current_policy,	starpu_sched_component_fifo_create, 340
	298	starpu_sched_component_heft_create, 341
	starpu_mpi_node_selection_unregister_policy,	starpu_sched_component_is_combined_worker,
	299	339
	starpu_mpi_recv, 294	starpu_sched_component_is_eager, 340
	starpu_mpi_redux_data, 299	starpu_sched_component_is_eager_calibration,
	starpu_mpi_scatter_detached, 299	starpu_scried_component_is_eager_calibration,
	starpu_mpi_scatter_detached, 299 starpu_mpi_send, 294	starpu_sched_component_is_fifo, 340
	starpu_mpi_senu, 234	starpu_scrieu_component_is_iiio, 340

starpu_sched_component_is_heft, 341	starpu_sched_ctx_performance_counters, 312
starpu_sched_component_is_mct, 340	notify_post_exec_task
starpu_sched_component_is_perfmodel_select,	starpu_sched_ctx_performance_counters, 312
341	notify_pushed_task
starpu_sched_component_is_prio, 340	starpu_sched_ctx_performance_counters, 312
starpu_sched_component_is_random, 340	notify submitted job
starpu_sched_component_is_simple_worker, 339	starpu_sched_ctx_performance_counters, 312
starpu_sched_component_is_work_stealing, 340	nparents
starpu_sched_component_is_worker, 339	starpu_sched_component, 334
· = - · - = =	
starpu_sched_component_make_scheduler, 341	nworkers
starpu_sched_component_mct_create, 340	starpu_worker_collection, 178
starpu_sched_component_perfmodel_select	ahi
create, 341	obj
starpu_sched_component_prio_create, 340	starpu_sched_component, 335
starpu_sched_component_properties, 337	open
starpu_sched_component_transfer_length, 339	starpu_disk_ops, 220
starpu_sched_component_worker_get, 339	OpenMP Runtime Support
starpu_sched_component_worker_get_workerid,	starpu_omp_proc_bind_close, 269
339	starpu_omp_proc_bind_false, 268
starpu_sched_component_worker_post_exec	starpu_omp_proc_bind_master, 269
hook, 339	starpu_omp_proc_bind_spread, 269
starpu_sched_component_worker_pre_exec	starpu_omp_proc_bind_true, 269
	starpu_omp_proc_bind_undefined, 268
hook, 339	starpu_omp_sched_auto, 268
starpu_sched_tree_add_workers, 338	starpu_omp_sched_dynamic, 268
starpu_sched_tree_create, 338	
starpu_sched_tree_destroy, 338	starpu_omp_sched_guided, 268
starpu_sched_tree_push_task, 338	starpu_omp_sched_runtime, 268
starpu_sched_tree_remove_workers, 338	starpu_omp_sched_static, 268
starpu_sched_tree_update_workers, 338	starpu_omp_sched_undefined, 268
starpu_sched_tree_update_workers_in_ctx, 338	OpenCL Extensions, 258
starpu_sched_tree_work_stealing_push_task, 340	STARPU_USE_OPENCL, 260
Multiformat Data Interface, 222	starpu_opencl_allocate_memory, 263
starpu_multiformat_data_register, 224	starpu_opencl_collect_stats, 262
ota.paaaaa.a og.oto., == :	starpu_opencl_compile_opencl_from_file, 262
name	starpu_opencl_compile_opencl_from_string, 262
sc_hypervisor_policy, 327	starpu_opencl_copy_async_sync, 263
starpu codelet, 229	starpu_opencl_copy_opencl_to_opencl, 263
starpu_task, 230	starpu_opencl_copy_opencl_to_ram, 263
starpu_top_param, 307	starpu_opencl_copy_ram_to_opencl, 263
nb_values	starpu openci display error, 262
starpu_top_param, 307	starpu_opencl_error_string, 262
nbuffers	starpu_opencl_get_context, 260
starpu_codelet, 228	starpu_opencl_get_current_context, 261
starpu_task, 231	starpu_opencl_get_current_queue, 261
nchildren	starpu_opencl_get_device, 261
starpu_data_filter, 213	starpu_opencl_get_queue, 261
starpu_sched_component, 334	starpu_opencl_load_binary_opencl, 262
next	starpu_opencl_load_kernel, 262
next starpu task, 234	starpu_opencl_load_kernel, 262
starpu_task, 234	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261
starpu_task, 234 starpu_top_param, 307	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261
starpu_task, 234 starpu_top_param, 307 nodes	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261
starpu_task, 234 starpu_top_param, 307 nodes starpu_codelet, 228	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262
starpu_task, 234 starpu_top_param, 307 nodes starpu_codelet, 228 notify_change_workers	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262 starpu_opencl_report_error, 263
starpu_task, 234 starpu_top_param, 307 nodes starpu_codelet, 228 notify_change_workers starpu_sched_component, 335	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262 starpu_opencl_report_error, 263 starpu_opencl_set_kernel_args, 261
starpu_task, 234 starpu_top_param, 307 nodes starpu_codelet, 228 notify_change_workers starpu_sched_component, 335 notify_delete_context	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262 starpu_opencl_report_error, 263 starpu_opencl_set_kernel_args, 261 starpu_opencl_unload_opencl, 261
starpu_task, 234 starpu_top_param, 307 nodes starpu_codelet, 228 notify_change_workers starpu_sched_component, 335 notify_delete_context starpu_sched_ctx_performance_counters, 312	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262 starpu_opencl_report_error, 263 starpu_opencl_set_kernel_args, 261 starpu_opencl_unload_opencl, 261 OpenMP Runtime Support, 264
starpu_task, 234 starpu_top_param, 307  nodes starpu_codelet, 228  notify_change_workers starpu_sched_component, 335  notify_delete_context starpu_sched_ctx_performance_counters, 312  notify_idle_cycle	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262 starpu_opencl_report_error, 263 starpu_opencl_set_kernel_args, 261 starpu_opencl_unload_opencl, 261 OpenMP Runtime Support, 264 STARPU_OPENMP, 268
starpu_task, 234 starpu_top_param, 307 nodes starpu_codelet, 228 notify_change_workers starpu_sched_component, 335 notify_delete_context starpu_sched_ctx_performance_counters, 312	starpu_opencl_load_kernel, 262 starpu_opencl_load_opencl_from_file, 261 starpu_opencl_load_opencl_from_string, 261 starpu_opencl_load_program_source, 261 starpu_opencl_release_kernel, 262 starpu_opencl_report_error, 263 starpu_opencl_set_kernel_args, 261 starpu_opencl_unload_opencl, 261 OpenMP Runtime Support, 264

starpu_omp_barrier, 269	starpu_omp_single, 270
starpu_omp_critical, 269	starpu_omp_single_copyprivate, 270
starpu_omp_critical_inline_begin, 270	starpu_omp_single_copyprivate_inline_begin, 271
starpu_omp_critical_inline_end, 270	starpu_omp_single_copyprivate_inline_end, 271
starpu_omp_destroy_lock, 281	starpu_omp_single_inline, 270
starpu_omp_destroy_nest_lock, 282	starpu_omp_task_region, 274
starpu_omp_for, 271	starpu_omp_taskgroup, 274
starpu_omp_for_alt, 272	starpu_omp_taskgroup_inline_begin, 274
starpu_omp_for_inline_first, 271	starpu_omp_taskgroup_inline_end, 274
starpu_omp_for_inline_first_alt, 272	starpu omp taskwait, 274
starpu omp for inline next, 272	starpu omp test lock, 282
starpu_omp_for_inline_next_alt, 273	starpu_omp_test_nest_lock, 283
	starpu_omp_unset_lock, 281
starpu_omp_get_active_level, 279	starpu_omp_unset_nest_lock, 282
starpu_omp_get_ancestor_thread_num, 278	starpu_omp_vector_annotate, 284
starpu_omp_get_cancellation, 277	opencl_flags
starpu_omp_get_default_device, 280	starpu codelet, 227
starpu_omp_get_dynamic, 276	• —
starpu_omp_get_level, 278	opencl_func
starpu_omp_get_max_active_levels, 278	starpu_codelet, 227
starpu_omp_get_max_threads, 275	opencl_funcs
starpu_omp_get_nested, 277	starpu_codelet, 227
starpu_omp_get_num_devices, 280	opencl_to_cuda
starpu_omp_get_num_procs, 276	starpu_data_copy_methods, 195
starpu_omp_get_num_teams, 280	opencl_to_opencl
starpu_omp_get_num_threads, 275	starpu_data_copy_methods, 195
starpu_omp_get_proc_bind, 279	opencl_to_opencl_async
starpu_omp_get_schedule, 277	starpu_data_copy_methods, 197
starpu_omp_get_team_num, 280	opencl_to_ram
starpu_omp_get_team_size, 279	starpu_data_copy_methods, 195
starpu_omp_get_team_size, 273 starpu_omp_get_thread_limit, 277	opencl_to_ram_async
	starpu_data_copy_methods, 196
starpu_omp_get_thread_num, 275	Out Of Core, 219
starpu_omp_get_wtick, 284	starpu_disk_close, 221
starpu_omp_get_wtime, 283	starpu_disk_leveldb_ops, 222
starpu_omp_in_final, 279	starpu_disk_open, 221
starpu_omp_in_parallel, 276	starpu_disk_register, 221
starpu_omp_init, 269	starpu_disk_stdio_ops, 221
starpu_omp_init_lock, 281	starpu_disk_unistd_o_direct_ops, 222
starpu_omp_init_nest_lock, 282	starpu_disk_unistd_ops, 221
starpu_omp_is_initial_device, 280	starpu_disk_driistd_ops, 221
starpu_omp_master, 269	pack_data
starpu_omp_master_inline, 269	starpu_data_interface_ops, 193
starpu_omp_ordered, 273	Parallel Tasks, 302
starpu_omp_ordered_inline_begin, 273	starpu_combined_worker_assign_workerid, 303
starpu_omp_ordered_inline_end, 273	starpu combined worker can execute task, 303
starpu_omp_parallel_region, 269	starpu combined worker get count, 303
starpu_omp_proc_bind_value, 268	starpu_combined_worker_get_description, 303
starpu_omp_sched_value, 268	starpu_combined_worker_get_id, 303
starpu_omp_sections, 273	·
starpu_omp_sections_combined, 273	starpu_combined_worker_get_rank, 303
	starpu_combined_worker_get_size, 303
starpu_omp_set_default_device, 279	starpu_parallel_task_barrier_init, 303
starpu_omp_set_dynamic, 276	starpu_parallel_task_barrier_init_n, 303
starpu_omp_set_lock, 281	parents
starpu_omp_set_max_active_levels, 278	starpu_sched_component, 334
starpu_omp_set_nest_lock, 282	per_worker_stats
starpu_omp_set_nested, 276	starpu_codelet, 229
starpu_omp_set_num_threads, 275	Performance Model, 246
starpu_omp_set_schedule, 277	STARPU_COMMON, 250
starpu_omp_shutdown, 269	STARPU_HISTORY_BASED, 250

STARPU_NL_REGRESSION_BASED, 250 STARPU_PER_ARCH, 250 STARPU_REGRESSION_BASED, 250	starpu_profiling_init, 254 starpu_profiling_set_id, 254 starpu_profiling_status_get, 254
	starpu_profiling_status_set, 254
starpu_bus_print_affinity, 251	starpu_profiling_status_set, 254 starpu_profiling_worker_get_info, 254
starpu_bus_print_bandwidth, 251	starpu_profiling_worker_helper_display_summary,
starpu_perfmodel_debugfilepath, 251	255
starpu_perfmodel_directory, 251	
starpu_perfmodel_free_sampling_directories, 250	starpu_timing_timespec_delay_us, 255 starpu_timing_timespec_to_us, 255
starpu_perfmodel_get_arch_name, 251	profiling_info
starpu_perfmodel_get_archtype_name, 251	starpu task, 234
starpu_perfmodel_history_based_expected_perf,	prologue_callback_arg
252	starpu_task, 232
starpu_perfmodel_init, 250	prologue_callback_arg_free
starpu_perfmodel_list, 251	starpu_task, 232
starpu_perfmodel_load_file, 250	prologue_callback_func
starpu_perfmodel_load_symbol, 250	starpu_task, 232
starpu_perfmodel_print, 251	properties
starpu_perfmodel_print_all, 251	• •
starpu_perfmodel_type, 250	starpu_sched_component, 335
starpu_perfmodel_unload_model, 250	pull_task
starpu_perfmodel_update_history, 251	starpu_sched_component, 335
starpu_transfer_bandwidth, 252	push_task starpu_sched_component, 335
starpu_transfer_latency, 252	starpu_sched_policy, 318
starpu_transfer_predict, 252	push_task_notify
starpu_worker_get_perf_archtype, 251	
olug	starpu_sched_policy, 318
starpu_disk_ops, 220	ram_to_cuda
policy_description	starpu_data_copy_methods, 195
starpu_sched_policy, 318	ram_to_cuda_async
policy_name	starpu_data_copy_methods, 196
starpu_sched_policy, 318	ram_to_mic
pop_every_task	starpu_data_copy_methods, 195
starpu_sched_policy, 318	ram to mic async
pop_task	starpu_data_copy_methods, 197
starpu_sched_policy, 318	ram_to_opencl
post_exec_hook	starpu_data_copy_methods, 195
starpu_sched_policy, 318	ram_to_opencl_async
power_model	starpu_data_copy_methods, 196
starpu_codelet, 229	ram to ram
ore_exec_hook	starpu data copy methods, 194
starpu_sched_policy, 318	read
predicted	starpu_disk_ops, 220
starpu_task, 234	regenerate
oredicted_transfer	starpu_task, 233
starpu_task, 234	register_data_handle
orev	starpu_data_interface_ops, 192
starpu_task, 234	remove
oriority	starpu_worker_collection, 179
starpu_task, 233	remove_child
Profiling, 252	starpu_sched_component, 334
starpu_bus_get_count, 255	remove parent
starpu_bus_get_dst, 255	starpu_sched_component, 334
starpu_bus_get_id, 255	remove_workers
starpu_bus_get_profiling_info, 255	starpu_sched_policy, 318
starpu_bus_get_src, 255	resize_ctxs
starpu_data_display_memory_stats, 255	sc_hypervisor_policy, 327
starpu_profiling_bus_helper_display_summary,	Running Drivers, 304
255	starpu_driver_deinit, 304

starpu_driver_init, 304	STARPU_SCC_RAM
starpu_driver_run, 304	Workers' Properties, 180
starpu_driver_run_once, 304	STARPU SCC SHM
starpu_drivers_request_termination, 304	Workers' Properties, 180
starpa_drivers_request_termination, 504	·
STARPU ANY WORKER	STARPU_SCC_WORKER
Workers' Properties, 180	Workers' Properties, 180
STARPU_BCSR_INTERFACE_ID	STARPU_SCHED_COMPONENT_HOMOGENEOUS
Data Interfaces, 205	Modularized Scheduler Interface, 338
STARPU_BLOCK_INTERFACE_ID	STARPU_SCHED_COMPONENT_SINGLE_MEMOR-
Data Interfaces, 205	Y_NODE
	Modularized Scheduler Interface, 338
STARPU_COMMON	STARPU_SCRATCH
Performance Model, 250	Data Management, 184
STARPU_COMMUTE	STARPU_SEQ
Data Management, 185	Codelet And Tasks, 238
STARPU_COO_INTERFACE_ID	STARPU_SPMD
Data Interfaces, 205	Codelet And Tasks, 238
STARPU_CPU_RAM	STARPU_SSEND
Workers' Properties, 180	Data Management, 185
STARPU_CPU_WORKER	STARPU_TASK_BLOCKED
Workers' Properties, 180	
STARPU_CSR_INTERFACE_ID	Codelet And Tasks, 238
Data Interfaces, 205	STARPU_TASK_BLOCKED_ON_DATA
STARPU_CUDA_RAM	Codelet And Tasks, 238
Workers' Properties, 180	STARPU_TASK_BLOCKED_ON_TAG
STARPU_CUDA_WORKER	Codelet And Tasks, 238
Workers' Properties, 180	STARPU_TASK_BLOCKED_ON_TASK
STARPU_FORKJOIN	Codelet And Tasks, 238
Codelet And Tasks, 238	STARPU_TASK_FINISHED
STARPU_HISTORY_BASED	Codelet And Tasks, 238
Performance Model, 250	STARPU_TASK_READY
STARPU_MATRIX_INTERFACE_ID	Codelet And Tasks, 238
	STARPU_TASK_RUNNING
Data Interfaces, 205	Codelet And Tasks, 238
STARPU_MAX_INTERFACE_ID	STARPU_TOP_DATA_BOOLEAN
Data Interfaces, 205	StarPU-Top Interface, 307
STARPU_MIC_RAM	STARPU_TOP_DATA_FLOAT
Workers' Properties, 180	StarPU-Top Interface, 307
STARPU_MIC_WORKER	•
Workers' Properties, 180	STARPU_TOP_DATA_INTEGER
STARPU_MULTIFORMAT_INTERFACE_ID	StarPU-Top Interface, 307
Data Interfaces, 205	STARPU_TOP_PARAM_BOOLEAN
STARPU_NL_REGRESSION_BASED	StarPU-Top Interface, 308
Performance Model, 250	STARPU_TOP_PARAM_ENUM
STARPU_NONE	StarPU-Top Interface, 308
Data Management, 184	STARPU_TOP_PARAM_FLOAT
STARPU_OPENCL_RAM	StarPU-Top Interface, 308
Workers' Properties, 180	STARPU_TOP_PARAM_INTEGER
STARPU_OPENCL_WORKER	StarPU-Top Interface, 308
Workers' Properties, 180	STARPU_UNKNOWN_INTERFACE_ID
STARPU PER ARCH	Data Interfaces, 205
Performance Model, 250	STARPU_UNUSED
STARPU R	Workers' Properties, 180
Data Management, 184	STARPU_VARIABLE_INTERFACE_ID
STARPU REDUX	Data Interfaces, 205
Data Management, 185	STARPU_VECTOR_INTERFACE_ID
STARPU_REGRESSION_BASED	Data Interfaces, 205
Performance Model, 250	STARPU_VOID_INTERFACE_ID
STARPU RW	Data Interfaces, 205
<del>-</del>	STARPU W
Data Management, 184	OTALL U_VV

Data Management, 184	STARPU_MAJOR_VERSION
STARPU_WORKER_LIST	Versioning, 157
Workers' Properties, 180	STARPU_MALLOC_COUNT
SC_HYPERVISOR_NULL	Standard Memory Library, 163
Scheduling Context Hypervisor - Regular usage,	STARPU_MAX
324	Toolbox, 167
SCC Extensions, 285	STARPU_MAX_PRIO
STARPU_MAXSCCDEVS, 286	Scheduling Contexts, 312
STARPU_USE_SCC, 286	STARPU_MAXCUDADEVS
starpu_scc_func_symbol_t, 286	CUDA Extensions, 257
starpu_scc_get_kernel, 286	STARPU MAXMICDEVS
starpu_scc_register_kernel, 286	MIC Extensions, 285
STARPU_ABORT	STARPU_MAXOPENCLDEVS
Toolbox, 167	OpenCL Extensions, 260
STARPU ABORT MSG	STARPU MAXSCCDEVS
Toolbox, 167	SCC Extensions, 286
STARPU_ASSERT	STARPU_MEMORY_WAIT
Toolbox, 167	Standard Memory Library, 163
STARPU_ASSERT_MSG	STARPU MIC
Toolbox, 167	Codelet And Tasks, 235
STARPU_BCSR_GET_NNZ	STARPU MIN
Data Interfaces, 202	Toolbox, 167
STARPU_BLOCK_GET_NX	STARPU_MIN_PRIO
Data Interfaces, 201	Scheduling Contexts, 312
STARPU_BLOCK_GET_NY	STARPU_MINOR_VERSION
Data Interfaces, 201	Versioning, 157
STARPU_BLOCK_GET_NZ	STARPU NAME
Data Interfaces, 201	Insert_Task, 242
STARPU_CALLBACK	STARPU NMAXBUFS
Insert_Task, 241	Codelet And Tasks, 236
STARPU_COO_GET_NX	STARPU NMAXWORKERS
Data Interfaces, 204	Workers' Properties, 179
STARPU_COO_GET_NY	STARPU_NOWHERE
Data Interfaces, 204	Codelet And Tasks, 234
STARPU_COO_GET_ROWS	STARPU OPENCL
Data Interfaces, 204	Codelet And Tasks, 235
STARPU_CPU	STARPU OPENMP
Codelet And Tasks, 235	OpenMP Runtime Support, 268
STARPU_CSR_GET_NNZ	STARPU POISON PTR
Data Interfaces, 202	Toolbox, 167
STARPU_CSR_GET_NROW	STARPU_PRIORITY
Data Interfaces, 203	Insert_Task, 241
STARPU_CUDA	STARPU_RMB
Codelet And Tasks, 235	Toolbox, 167
STARPU_CUDA_ASYNC	STARPU_SCC
starpu_task.h, 373	Codelet And Tasks, 235
STARPU_DATA_ARRAY	STARPU_SCHED_CTX
Insert_Task, 241	Insert_Task, 242
STARPU_DEFAULT_PRIO	STARPU_TAG
Scheduling Contexts, 312	Insert_Task, 242
STARPU_FLOPS	STARPU_TAG_ONLY
Insert_Task, 242	Insert_Task, 242
STARPU_GNUC_PREREQ	STARPU_TASK_INVALID
Toolbox, 166	Codelet And Tasks, 237
STARPU_LIKELY	STARPU_UNLIKELY
Toolbox, 166	Toolbox, 166
STARPU_MAIN_RAM	STARPU_USE_CUDA
Codelet And Tasks, 235	CUDA Extensions, 257

STARPU_USE_MIC	Scheduling Context Hypervisor - Regular usage,
MIC Extensions, 285	325
STARPU_USE_MPI	sc_hypervisor_policy
MPI Support, 292	custom, 327
STARPU_USE_OPENCL	end_ctx, 327
OpenCL Extensions, 260	handle_idle_cycle, 327
STARPU_USE_SCC	handle_idle_end, 327
SCC Extensions, 286	handle_poped_task, 327
STARPU_VALUE	handle_post_exec_hook, 327
Insert_Task, 241	handle_pushed_task, 327
STARPU_WMB	handle_submitted_job, 327
Toolbox, 167	name, 327
sc_hypervisor_policy, 326	resize_ctxs, 327
sc_hypervisor_policy_config, 328	size_ctxs, 327
sc_hypervisor_policy_task_pool, 329	sc_hypervisor_policy.h, 388
sc_hypervisor_resize_ack, 329	sc_hypervisor_post_resize_request
sc_hypervisor_wrapper, 328	Scheduling Context Hypervisor - Building a new re-
sc_hypervisor.h, 385	sizing policy, 330
sc_hypervisor_add_workers_to_sched_ctx	sc_hypervisor_register_ctx
Scheduling Context Hypervisor - Regular usage,	Scheduling Context Hypervisor - Regular usage,
325	324
sc_hypervisor_can_resize	sc_hypervisor_remove_workers_from_sched_ctx
	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Building a new re-	
sizing policy, 330	325
sc_hypervisor_config.h, 386	sc_hypervisor_resize_ctxs
sc_hypervisor_ctl	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Regular usage,	325
326	sc_hypervisor_save_size_req
sc_hypervisor_free_size_req	Scheduling Context Hypervisor - Building a new re-
Scheduling Context Hypervisor - Building a new re-	sizing policy, 330
sizing policy, 330	sc_hypervisor_set_config
sc_hypervisor_get_config	Scheduling Context Hypervisor - Building a new re-
Scheduling Context Hypervisor - Building a new re-	sizing policy, 330
sizing policy, 330	sc_hypervisor_set_type_of_task
sc_hypervisor_get_elapsed_flops_per_sched_ctx	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Building a new re-	325
sizing policy, 330	sc_hypervisor_shutdown
sc_hypervisor_get_nsched_ctxs	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Building a new re-	324
sizing policy, 330	sc_hypervisor_size_ctxs
sc_hypervisor_get_policy	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Regular usage,	325
325	sc_hypervisor_start_resize
sc_hypervisor_get_sched_ctxs	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Building a new re-	325
sizing policy, 330	sc_hypervisor_stop_resize
sc_hypervisor_get_size_req	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Building a new re-	325
sizing policy, 330	sc_hypervisor_unregister_ctx
sc_hypervisor_get_wrapper	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Building a new re-	325
sizing policy, 330	sc_hypervisor_update_diff_elapsed_flops
sc_hypervisor_init	Scheduling Context Hypervisor - Regular usage,
Scheduling Context Hypervisor - Regular usage,	326
324	sc_hypervisor_update_diff_total_flops
sc_hypervisor_lp.h, 387	Scheduling Context Hypervisor - Regular usage,
sc_hypervisor_monitoring.h, 387	325
sc_hypervisor_move_workers	scc_funcs

starpu_codelet, 228	starpu_sched_ctx_exec_parallel_code, 316
scc_sink_to_sink	starpu_sched_ctx_finished_submit, 314
starpu_data_copy_methods, 196	starpu_sched_ctx_get_context, 314
scc_sink_to_src	starpu_sched_ctx_get_max_priority, 315
starpu_data_copy_methods, 196	starpu_sched_ctx_get_min_priority, 315
scc_src_to_sink	starpu_sched_ctx_get_nready_flops, 316
starpu_data_copy_methods, 196	starpu_sched_ctx_get_nready_tasks, 316
sched_ctx	starpu_sched_ctx_get_nshared_workers, 314
starpu_task, 234	starpu_sched_ctx_get_nworkers, 314
scheduled	starpu_sched_ctx_get_policy_data, 316
starpu_task, 233	starpu_sched_ctx_get_worker_collection, 315
Scheduling Context Hypervisor - Building a new resizing	starpu_sched_ctx_get_workers_list, 314
policy, 326	starpu_sched_ctx_max_priority_is_set, 315
sc_hypervisor_can_resize, 330	starpu_sched_ctx_min_priority_is_set, 315
sc_hypervisor_free_size_req, 330	starpu_sched_ctx_notify_hypervisor_exists, 316
sc_hypervisor_get_config, 330	starpu_sched_ctx_overlapping_ctxs_on_worker,
sc_hypervisor_get_elapsed_flops_per_sched_ctx,	314
330	starpu_sched_ctx_register_close_callback, 313
sc_hypervisor_get_nsched_ctxs, 330	starpu_sched_ctx_remove_workers, 313
sc_hypervisor_get_sched_ctxs, 330	starpu_sched_ctx_set_context, 314
sc_hypervisor_get_size_req, 330	starpu_sched_ctx_set_inheritor, 313
sc_hypervisor_get_wrapper, 330	starpu_sched_ctx_set_max_priority, 315
sc_hypervisor_post_resize_request, 330	starpu_sched_ctx_set_min_priority, 314
sc_hypervisor_save_size_req, 330	starpu_sched_ctx_set_perf_counters, 315
sc_hypervisor_set_config, 330	starpu_sched_ctx_set_policy_data, 316
Scheduling Context Hypervisor - Regular usage, 322	starpu_sched_ctx_stop_task_submission, 314
SC_HYPERVISOR_NULL, 324	starpu_sched_ctx_worker_get_id, 314
sc_hypervisor_add_workers_to_sched_ctx, 325	Scheduling Policy, 316
sc_hypervisor_ctl, 326	starpu_data_expected_transfer_time, 320
sc_hypervisor_get_policy, 325	starpu_get_prefetch_flag, 320
sc_hypervisor_init, 324	starpu_idle_prefetch_task_input_on_node, 321
sc_hypervisor_move_workers, 325	starpu_prefetch_task_input_on_node, 321
sc_hypervisor_register_ctx, 324	starpu_push_local_task, 319
sc_hypervisor_remove_workers_from_sched_ctx,	starpu_push_task_end, 319
325	starpu_sched_ctx_worker_shares_tasks_lists, 321
sc_hypervisor_resize_ctxs, 325	starpu_sched_get_max_priority, 319
sc_hypervisor_set_type_of_task, 325	starpu_sched_get_min_priority, 319
sc_hypervisor_shutdown, 324	starpu_sched_get_predefined_policies, 318
sc_hypervisor_size_ctxs, 325	starpu_sched_set_max_priority, 319
sc_hypervisor_start_resize, 325	starpu_sched_set_min_priority, 319
sc_hypervisor_stop_resize, 325	starpu_task_data_footprint, 320
sc_hypervisor_unregister_ctx, 325	starpu_task_expected_conversion_time, 320
sc_hypervisor_update_diff_elapsed_flops, 326	starpu_task_expected_data_transfer_time, 320
sc_hypervisor_update_diff_total_flops, 325	starpu_task_expected_length, 320
Scheduling Contexts, 310	starpu task expected power, 320
STARPU_DEFAULT_PRIO, 312	starpu_task_footprint, 320
STARPU_MAX_PRIO, 312	starpu_worker_can_execute_task, 319
STARPU_MIN_PRIO, 312	starpu worker can execute task first impl, 320
starpu_sched_ctx_add_workers, 313	starpu_worker_can_execute_task_impl, 319
starpu_sched_ctx_call_pushed_task_cb, 315	starpu_worker_get_relative_speedup, 320
starpu_sched_ctx_check_if_hypervisor_exists, 316	starpu_worker_get_sched_condition, 319
starpu_sched_ctx_contains_worker, 314	sequential_consistency
starpu_sched_ctx_create, 313	starpu_task, 232
starpu_sched_ctx_create_inside_interval, 313	size_base
starpu_sched_ctx_create_worker_collection, 315	starpu_perfmodel, 248
starpu_sched_ctx_delete, 313	size_ctxs
starpu_sched_ctx_delete_worker_collection, 315	sc_hypervisor_policy, 327
starpu_sched_ctx_display_workers, 313	specific_nodes

starpu_codelet, 228	starpu_csr_interface, 199
Standard Memory Library, 162	starpu_data_copy_methods, 194
STARPU_MALLOC_COUNT, 163	starpu_data_descr, 229
STARPU_MEMORY_WAIT, 163	starpu_data_filter, 213
starpu_data_free_pinned_if_possible, 163	starpu_data_interface_ops, 192
starpu_data_malloc_pinned_if_possible, 163	starpu_disk_ops, 219
starpu_free, 164	starpu_driver, 158
starpu_free_flags, 164	starpu_driver.id, 158
starpu_malloc, 164	starpu_fxt_codelet_event, 287
starpu_malloc_flags, 163	starpu_fxt_options, 288
starpu_malloc_set_align, 163	starpu_matrix_interface, 198
starpu_memory_allocate, 164	starpu_multiformat_data_interface_ops, 222
starpu_memory_deallocate, 165	starpu_multiformat_interface, 223
starpu_memory_get_available, 164	starpu_omp_lock_t, 266
starpu_memory_get_total, 164	starpu_omp_nest_lock_t, 266
starpu_memory_pin, 164	starpu_omp_parallel_region_attr, 267
starpu_memory_unpin, 164	starpu_omp_proc_bind_close
starpu_memory_wait_available, 165	OpenMP Runtime Support, 269
StarPU-Top Interface	starpu_omp_proc_bind_false
STARPU_TOP_DATA_BOOLEAN, 307	OpenMP Runtime Support, 268
STARPU_TOP_DATA_FLOAT, 307	starpu_omp_proc_bind_master
STARPU_TOP_DATA_INTEGER, 307	OpenMP Runtime Support, 269
STARPU_TOP_PARAM_BOOLEAN, 308	starpu_omp_proc_bind_spread
STARPU_TOP_PARAM_ENUM, 308	OpenMP Runtime Support, 269
STARPU_TOP_PARAM_FLOAT, 308	starpu_omp_proc_bind_true
STARPU_TOP_PARAM_INTEGER, 308	OpenMP Runtime Support, 269
TOP_TYPE_CONTINUE, 308	starpu_omp_proc_bind_undefined
TOP_TYPE_DEBUG, 308	OpenMP Runtime Support, 268
TOP_TYPE_DISABLE, 308	starpu_omp_sched_auto
TOP_TYPE_ENABLE, 308	OpenMP Runtime Support, 268
TOP_TYPE_GO, 308	starpu_omp_sched_dynamic
TOP_TYPE_SET, 308	OpenMP Runtime Support, 268
TOP_TYPE_UNKNOW, 308	starpu_omp_sched_guided
StarPU-Top Interface, 305	OpenMP Runtime Support, 268
starpu_top_add_data_boolean, 308	starpu_omp_sched_runtime
starpu_top_add_data_float, 308	OpenMP Runtime Support, 268
starpu_top_add_data_integer, 308	starpu_omp_sched_static
starpu_top_data_type, 307	OpenMP Runtime Support, 268
starpu_top_debug_lock, 310	starpu_omp_sched_undefined
starpu_top_debug_log, 309	OpenMP Runtime Support, 268
starpu_top_init_and_wait, 309	starpu_omp_task_region_attr, 267
starpu_top_message_type, 308	starpu_opencl_program, 260
starpu_top_param_type, 307	starpu_perfmodel, 247
starpu_top_register_parameter_boolean, 308	starpu_perfmodel_arch, 365
starpu_top_register_parameter_enum, 309	starpu_perfmodel_device, 365
starpu_top_register_parameter_float, 308	starpu_perfmodel_history_entry, 249
starpu_top_register_parameter_integer, 309	starpu_perfmodel_history_list, 249
starpu_top_task_prevision, 309	starpu_perfmodel_per_arch, 249
starpu_top_update_data_boolean, 309	starpu_perfmodel_regression_model, 248
starpu_top_update_data_float, 309	starpu_profiling_bus_info, 254
starpu_top_update_data_integer, 309	starpu_profiling_task_info, 253
starpu_top_update_parameter, 309	starpu_profiling_worker_info, 253
starpu.h, 345	starpu_pthread_barrier_t, 377
starpu_bcsr_interface, 198	starpu_pthread_spinlock_t, 377
starpu_block_interface, 198	starpu_sched_component, 333
starpu_codelet, 226	starpu_sched_component_composed_recipe, 337
starpu_conf, 158	starpu_sched_component_fifo_data, 336
starpu_coo_interface, 199	starpu_sched_component_mct_data, 336

starpu_sched_component_perfmodel_select_data, 336	starpu_bitmap_destroy
starpu_sched_component_prio_data, 336	Bitmap, 176
starpu_sched_component_specs, 337	starpu_bitmap_first
starpu_sched_ctx_iterator, 179	Bitmap, 177
starpu_sched_ctx_performance_counters, 311	starpu_bitmap_get
starpu_sched_policy, 317	Bitmap, 176
starpu_sched_tree, 335	starpu_bitmap_has_next
starpu_task, 229	Bitmap, 177
starpu_task_list, 301	starpu_bitmap_last
starpu_top_data, 306	Bitmap, 177
starpu_top_param, 306	starpu_bitmap_next
starpu_tree, 321	Bitmap, 177
starpu_variable_interface, 197	starpu_bitmap_or
starpu_vector_interface, 197	Bitmap, 176
starpu_worker_collection, 178	starpu_bitmap_set
starpu_arbiter_create	Bitmap, 176
Data Management, 188	starpu_bitmap_unset
starpu_arbiter_destroy	Bitmap, 176
Data Management, 188	starpu_bitmap_unset_all
starpu_arbiter_t	Bitmap, 176
Data Management, 184	starpu_bitmap_unset_and
starpu_asynchronous_copy_disabled	Bitmap, 176
Initialization and Termination, 161	starpu_block_data_register
starpu_asynchronous_cuda_copy_disabled	Data Interfaces, 206
Initialization and Termination, 162	starpu_block_filter_block
starpu_asynchronous_mic_copy_disabled	Data Partition, 217
Initialization and Termination, 162	starpu_block_filter_block_shadow
starpu_asynchronous_opencl_copy_disabled	Data Partition, 218
Initialization and Termination, 162	starpu_block_filter_depth_block
starpu_bcsr_data_register	Data Partition, 218
Data Interfaces, 206	starpu_block_filter_depth_block_shadow
starpu_bcsr_filter_canonical_block	Data Partition, 218
Data Partition, 218	starpu_block_filter_vertical_block
starpu_bcsr_get_c	Data Partition, 218
Data Interfaces, 210	starpu_block_filter_vertical_block_shadow
starpu_bcsr_get_elemsize	Data Partition, 218
Data Interfaces, 210	starpu_block_get_elemsize
starpu_bcsr_get_firstentry	Data Interfaces, 209
Data Interfaces, 209	starpu_block_get_local_ldy
starpu_bcsr_get_local_colind	Data Interfaces, 209
Data Interfaces, 209	starpu_block_get_local_ldz
starpu_bcsr_get_local_nzval	Data Interfaces, 209
Data Interfaces, 209	starpu_block_get_local_ptr
starpu_bcsr_get_local_rowptr	Data Interfaces, 209
Data Interfaces, 209	starpu_block_get_nx
starpu_bcsr_get_nnz	Data Interfaces, 208
Data Interfaces, 209	starpu_block_get_ny
starpu_bcsr_get_nrow	Data Interfaces, 208
Data Interfaces, 209	starpu_block_get_nz
starpu_bcsr_get_r	Data Interfaces, 209
Data Interfaces, 209	starpu_block_ptr_register
starpu_bitmap.h, 346	Data Interfaces, 206
starpu_bitmap_and_get	starpu_bound.h, 346
Bitmap, 177	starpu_bound_compute
starpu_bitmap_cardinal	Theoretical Lower Bound on Execution Time, 256
Bitmap, 177	starpu_bound_print
starpu_bitmap_create	Theoretical Lower Bound on Execution Time, 256
Bitmap, 176	starpu_bound_print_dot

Theoretical Lower Bound on Execution Time, 256	Insert_Task, 243
starpu_bound_print_lp	starpu_combined_worker_assign_workerid
Theoretical Lower Bound on Execution Time, 256	Parallel Tasks, 303
starpu_bound_print_mps	starpu_combined_worker_can_execute_task
Theoretical Lower Bound on Execution Time, 256	Parallel Tasks, 303
starpu_bound_start	starpu_combined_worker_get_count
Theoretical Lower Bound on Execution Time, 256	Parallel Tasks, 303
starpu_bound_stop	starpu_combined_worker_get_description
	· – – – ·
Theoretical Lower Bound on Execution Time, 256	Parallel Tasks, 303
starpu_bus_get_count	starpu_combined_worker_get_id
Profiling, 255	Parallel Tasks, 303
starpu_bus_get_dst	starpu_combined_worker_get_rank
Profiling, 255	Parallel Tasks, 303
starpu_bus_get_id	starpu_combined_worker_get_size
Profiling, 255	Parallel Tasks, 303
starpu_bus_get_profiling_info	starpu_conf_init
Profiling, 255	Initialization and Termination, 161
starpu_bus_get_src	starpu_config.h, 347
Profiling, 255	starpu_coo_data_register
starpu_bus_print_affinity	Data Interfaces, 207
Performance Model, 251	starpu_cpu_func_t
starpu_bus_print_bandwidth	Codelet And Tasks, 237
Performance Model, 251	starpu_cpu_worker_get_count
starpu_codelet	Workers' Properties, 180
can_execute, 226	starpu_create_sync_task
cpu_func, 227	Codelet And Tasks, 240
cpu_funcs, 227	starpu_csr_data_register
cpu_funcs_name, 228	Data Interfaces, 207
cuda_flags, 227	starpu_csr_filter_vertical_block
cuda_func, 227	Data Partition, 218
cuda_funcs, 227	starpu_csr_get_elemsize
dyn_modes, 228	Data Interfaces, 210
dyn_nodes, 229	starpu_csr_get_firstentry
max parallelism, 226	Data Interfaces, 210
<del>_</del>	•
mic_funcs, 227	starpu_csr_get_local_colind
model, 229	Data Interfaces, 210
modes, 228	starpu_csr_get_local_nzval
name, 229	Data Interfaces, 210
nbuffers, 228	starpu_csr_get_local_rowptr
nodes, 228	Data Interfaces, 210
opencl_flags, 227	starpu_csr_get_nnz
opencl_func, 227	Data Interfaces, 210
opencl_funcs, 227	starpu_csr_get_nrow
per_worker_stats, 229	Data Interfaces, 210
power_model, 229	starpu_cublas.h, 348
scc_funcs, 228	starpu_cublas_init
specific_nodes, 228	CUDA Extensions, 258
• —	
type, 226	starpu_cublas_report_error
where, 226	CUDA Extensions, 258
starpu_codelet_display_stats	starpu_cublas_shutdown
Codelet And Tasks, 240	CUDA Extensions, 258
starpu_codelet_init	starpu_cuda.h, 349
Codelet And Tasks, 238	starpu_cuda_copy_async_sync
starpu_codelet_pack_args	CUDA Extensions, 258
Insert_Task, 243	starpu_cuda_func_t
starpu_codelet_type	Codelet And Tasks, 237
Codelet And Tasks, 238	starpu_cuda_get_device_properties
starpu_codelet_unpack_args	CUDA Extensions, 257

starpu_cuda_get_local_stream	starpu_data_fetch_on_node
CUDA Extensions, 257	Data Management, 186
starpu_cuda_report_error	starpu_data_filter
CUDA Extensions, 258	filter_arg, 214
starpu_cuda_set_device	filter_arg_ptr, 214
CUDA Extensions, 258	filter_func, 213
starpu_cuda_worker_get_count	get_child_ops, 214
Workers' Properties, 180	get_nchildren, 214
starpu_data.h, 349	nchildren, 213
starpu_data_access_mode	starpu_data_filters.h, 351
Data Management, 184	starpu_data_free_pinned_if_possible
starpu_data_acquire	Standard Memory Library, 163
Data Management, 187	starpu_data_get_child
starpu_data_acquire_cb	Data Partition, 214
Data Management, 187	starpu_data_get_default_sequential_consistency_flag
starpu_data_acquire_cb_sequential_consistency	Implicit Data Dependencies, 246
Data Management, 187	starpu_data_get_interface_id
starpu_data_acquire_on_node	Data Interfaces, 207
Data Management, 187	starpu_data_get_interface_on_node
starpu_data_acquire_on_node_cb	Data Interfaces, 207
Data Management, 188	starpu_data_get_interface_ops
starpu_data_acquire_on_node_cb_sequential_consistence	by Data Management, 187
Data Management, 188	starpu_data_get_local_ptr
starpu data advise as important	Data Interfaces, 207
Data Management, 187	starpu_data_get_nb_children
starpu_data_assign_arbiter	Data Partition, 214
Data Management, 188	starpu_data_get_rank
starpu_data_copy_methods	MPI Support, 293
any_to_any, 197	starpu_data_get_sequential_consistency_flag
can_copy, 194	Implicit Data Dependencies, 246
cuda_to_cuda, 195	starpu_data_get_size
cuda_to_cuda_async, 196	Data Interfaces, 207
cuda_to_opencl, 195	starpu_data_get_sub_data
cuda_to_ram, 195	Data Partition, 214
cuda_to_ram_async, 196	starpu_data_get_tag
mic_to_ram, 195	MPI Support, 293
mic_to_ram_async, 197	starpu_data_handle_t
opencl_to_cuda, 195	Data Management, 184
opencl to opencl, 195	starpu_data_handle_to_pointer
. – – .	Data Interfaces, 207
opencl_to_opencl_async, 197	
opencl_to_ram, 195	starpu_data_idle_prefetch_on_node
opencl_to_ram_async, 196	Data Management, 186
ram_to_cuda, 195	starpu_data_interface_get_next_id
ram_to_cuda_async, 196	Data Interfaces, 211
ram_to_mic, 195	starpu_data_interface_id
ram_to_mic_async, 197	Data Interfaces, 205
ram_to_opencl, 195	starpu_data_interface_ops
ram_to_opencl_async, 196	allocate_data_on_node, 192
ram_to_ram, 194	compare, 193
scc_sink_to_sink, 196	copy_methods, 193
scc_sink_to_src, 196	describe, 193
scc_src_to_sink, 196	display, 193
starpu_data_cpy	dontcache, 193
Miscellaneous Helpers, 286	footprint, 193
starpu_data_display_memory_stats	free_data_on_node, 192
Profiling, 255	get_mf_ops, 193
starpu_data_expected_transfer_time	get_size, 193
Scheduling Policy, 320	handle_to_pointer, 193

interface_size, 193	Data Management, 186
interfaceid, 193	starpu_data_unpack
is_multiformat, 193	Data Interfaces, 207
pack_data, 193	starpu_data_unpartition
register_data_handle, 192	Data Partition, 214
unpack_data, 193	starpu_data_unpartition_readonly_submit
starpu_data_interfaces.h, 353	Data Partition, 216
starpu_data_invalidate	starpu_data_unpartition_submit
Data Management, 185	Data Partition, 216
starpu_data_invalidate_submit	starpu_data_unregister
Data Management, 186	Data Management, 185
starpu_data_lookup	starpu_data_unregister_no_coherency
Data Management, 186	Data Management, 185
starpu_data_malloc_pinned_if_possible	starpu_data_unregister_submit
Standard Memory Library, 163	Data Management, 185
starpu_data_map_filters	starpu_data_vget_sub_data
Data Partition, 215	Data Partition, 215
starpu data pack	starpu_data_vmap_filters
Data Interfaces, 207	Data Partition, 215
starpu_data_partition	starpu_data_wont_use
Data Partition, 214	Data Management, 186
starpu_data_partition_clean	starpu_deprecated_api.h, 357
Data Partition, 216	starpu_disk.h, 357
starpu_data_partition_plan	starpu_disk_close
Data Partition, 215	Out Of Core, 221
starpu_data_partition_readonly_submit	starpu_disk_leveldb_ops
Data Partition, 215	Out Of Core, 222
starpu_data_partition_readwrite_upgrade_submit	starpu_disk_open
Data Partition, 216	Out Of Core, 221
starpu_data_partition_submit	starpu_disk_ops
Data Partition, 215	alloc, 220
starpu_data_prefetch_on_node	async_full_read, 220
Data Management, 186	async_full_write, 220
starpu_data_ptr_register	async_read, 220
Data Management, 185	async_write, 220
	bandwidth, 220
starpu_data_query_status	
Data Management, 186	close, 220
starpu_data_register	copy, 221 free, 220
Data Management, 185	
starpu_data_register_same	free_request, 221
Data Management, 185	full_read, 220
starpu_data_release	full_write, 220
Data Management, 188	open, 220
starpu_data_release_on_node	plug, 220
Data Management, 188	read, 220
starpu_data_request_allocation	test_request, 221
Data Management, 186	unplug, 220
starpu_data_set_default_sequential_consistency_flag	wait_request, 221
Implicit Data Dependencies, 246	write, 220
starpu_data_set_rank	starpu_disk_register
MPI Support, 292	Out Of Core, 221
starpu_data_set_reduction_methods	starpu_disk_stdio_ops
Data Management, 187	Out Of Core, 221
starpu_data_set_sequential_consistency_flag	starpu_disk_unistd_o_direct_ops
Implicit Data Dependencies, 246	Out Of Core, 222
starpu_data_set_tag	starpu_disk_unistd_ops
MPI Support, 292	Out Of Core, 221
starpu_data_set_wt_mask	starpu_driver.h, 358

starpu_driver_deinit	Insert_Task, 242
Running Drivers, 304	starpu_interface_copy
starpu_driver_init	Data Interfaces, 211
Running Drivers, 304	starpu_malloc
starpu_driver_run	Standard Memory Library, 164
Running Drivers, 304	starpu_malloc_flags
starpu_driver_run_once	Standard Memory Library, 163
Running Drivers, 304	starpu_malloc_on_node
starpu_drivers_request_termination	Data Interfaces, 210
Running Drivers, 304	starpu_malloc_on_node_flags
starpu_execute_on_each_worker	Data Interfaces, 210
Miscellaneous Helpers, 287	starpu_malloc_on_node_set_default_flags
starpu_execute_on_each_worker_ex	Data Interfaces, 211
Miscellaneous Helpers, 287	starpu_malloc_set_align
•	Standard Memory Library, 163
starpu_execute_on_specific_workers	•
Miscellaneous Helpers, 287	starpu_matrix_data_register
starpu_expert.h, 358	Data Interfaces, 206
starpu_free	starpu_matrix_filter_block
Standard Memory Library, 164	Data Partition, 217
starpu_free_flags	starpu_matrix_filter_block_shadow
Standard Memory Library, 164	Data Partition, 217
starpu_free_on_node	starpu_matrix_filter_vertical_block
Data Interfaces, 211	Data Partition, 217
starpu_free_on_node_flags	starpu_matrix_filter_vertical_block_shadow
Data Interfaces, 210	Data Partition, 217
starpu_fxt.h, 358	starpu_matrix_get_elemsize
starpu_fxt_generate_trace	Data Interfaces, 208
FxT Support, 288	starpu_matrix_get_local_ld
starpu_fxt_options_init	Data Interfaces, 208
FxT Support, 288	starpu_matrix_get_local_ptr
starpu_fxt_start_profiling	Data Interfaces, 208
FxT Support, 288	starpu_matrix_get_nx
starpu_fxt_stop_profiling	Data Interfaces, 208
FxT Support, 289	starpu_matrix_get_ny
starpu_fxt_trace_user_event	Data Interfaces, 208
FxT Support, 289	starpu_matrix_ptr_register
starpu_fxt_write_data_trace	Data Interfaces, 206
FxT Support, 289	starpu_memory_allocate
starpu_get_env_number	Standard Memory Library, 164
Toolbox, 168	starpu_memory_deallocate
starpu_get_prefetch_flag	Standard Memory Library, 165
Scheduling Policy, 320	starpu_memory_get_available
starpu_get_version	Standard Memory Library, 164
Versioning, 157	starpu_memory_get_total
starpu_hash.h, 359	Standard Memory Library, 164
starpu_hash_crc32c_be	starpu_memory_pin
Data Interfaces, 211	Standard Memory Library, 164
starpu_hash_crc32c_be_n	starpu_memory_unpin
Data Interfaces, 211	Standard Memory Library, 164
starpu_hash_crc32c_string	starpu_memory_wait_available
Data Interfaces, 211	Standard Memory Library, 165
starpu_idle_prefetch_task_input_on_node	starpu_mic.h, 359
Scheduling Policy, 321	starpu_mic_device_get_count
starpu_init	Workers' Properties, 181
Initialization and Termination, 161	starpu_mic_func_symbol_t
starpu_initialize	MIC Extensions, 285
Initialization and Termination, 161	starpu_mic_func_t
starpu_insert_task	Codelet And Tasks, 237

MIC Extensions, 285 starpu_mic_register_kernel_t Codelet And Tasks, 237 starpu_mic_register_kernel_t MIC Extensions, 285 starpu_mic_register_kernel MIC Extensions, 285 starpu_mpi_nic actenel MIC Extensions, 285 starpu_mpi_seach MIC Extensions, 285 starpu_mpi_revdetached MIC Support, 285 starpu_mpi_cache_detached_unlock_tag MIC Support, 294 starpu_mpi_send_detached_unlock_tag MIC Support, 296 starpu_mpi_send_detached MIC Support, 296 starpu_mpi_send_detached MIC Support, 296 starpu_mpi_data_set_tag MIC Support, 297 starpu_mpi_data_set_tag MIC Support, 298 starpu_mpi_data_set_tank MIC Support, 298 starpu_mpi_data_set_tag MIC Support, 298 starpu_mpi_setal MIC	starpu_mic_get_kernel	MPI Support, 294
starpu_mic_kernel_1 Codelet And Tasks, 237 starpu mic register kernel MIC Extensions, 285 starpu mic register kernel MIC Extensions, 285 starpu mic register kernel Workers' Properties, 181 Starpu mpi, 382 starpu mpi barrier MPI Support, 295 starpu mpi barrier MPI Support, 295 starpu mpi cache flush MPI Support, 296 starpu mpi, cache flush MPI Support, 296 starpu, mpi, cache je, senabled MPI Support, 296 starpu, mpi, data, get, trank MPI Support, 297 starpu mpi data, segister MPI Support, 297 starpu mpi data, segister comm MPI Support, 298 starpu mpi data, segister comm MPI Support, 299 starpu mpi data, segister comm MPI Support, 299 starpu, mpi, get, get, get, get, get, get, get, get	•	11 /
Codelet And Tasks, 237 starpu_mic_register_kernel MIC Extensions, 285 starpu_mic_worker_get_count Workers*Properties, 181 starpu_mic_worker_get_count Workers*Properties, 181 starpu_mpi_mot_consistency MPI Support, 295 starpu_mpi_barrier MPI Support, 295 starpu_mpi_cache_flush MPI Support, 295 starpu_mpi_cache_flush all_data MPI Support, 296 starpu_mpi_cache_is_enabled MPI Support, 296 starpu_mpi_cache set MPI Support, 296 starpu_mpi_cache set MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_rank MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_rank MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_rank MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_rank MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_intel MPI Support, 298 starpu_mpi_intel MPI Support, 298 starpu_mpi_intel MPI Support, 299 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_data_get_rank MPI Support, 298 s	starpu mic kernel t	. – . – . – . – . – . – .
starpu mic register, kernel  MIC Extensions, 285 starpu_mic, worker_get_count  Workers' Properties, 181 starpu_mpi, 382 starpu_mpi_barrier  MPI Support, 295 starpu_mpi_cache flush MPI Support, 296 starpu_mpi_cache flush MPI Support, 296 starpu_mpi_cache js_enabled MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_rank MPI Support, 298 starpu_mpi_data_get_rank MPI Support, 299 starpu_mpi_get_communication_lag MPI Support, 299 starpu_mpi_get_data_on_node_detached MPI Support,	•	• •
MIC Extensions, 285 starpu mpi, inerv_detached_sequential_consistency Workers' Properties, 181 Workers' Properties, 182 Starpu_mpi_barier MPI Support, 295 Starpu_mpi_cache_flush MPI Support, 296 Starpu_mpi_cache_set MPI Support, 297 Starpu_mpi_data_get_trank MPI Support, 297 Starpu_mpi_data_get_trank MPI Support, 297 MPI Support, 298 Starpu_mpi_data_set_rank MPI Support, 299 Starpu_mpi_scatter_detached MPI Support, 296 Starpu_mpi_init_comm MPI Support, 296 Starpu_mpi_init_comm MPI Support, 298 Starpu_mpi_init_comm MPI Support, 298 Starpu_mpi_init_comm MPI Support, 293 Starpu_mpi		. – . – –
starpu_mic_worker_get_count Workers' Properties, 181 starpu_mpi_h, 382 starpu_mpi_barrier MPI Support, 295 starpu_mpi_cache_flush MPI Support, 296 starpu_mpi_cache flush all_data MPI Support, 296 starpu_mpi_cache flush all_data MPI Support, 296 starpu_mpi_cache starpu_mpi_sel_communication_tag MPI Support, 296 starpu_mpi_cache starpu_mpi_sel_cached MPI Support, 296 starpu_mpi_sel_data sot_tag MPI Support, 298 starpu_mpi_sel_data sot_tag MPI Support, 299 starpu_mpi_sel_data sot_tag MPI Support, 299	. – – • –	• •
Workers' Properties, 181  starpu_mpi,h, 382  starpu_mpi, barrier MPI Support, 295  starpu_mpi_cache, flush MPI Support, 296  starpu_mpi_cache, flush all data MPI Support, 296  starpu_mpi_cache, flush all data MPI Support, 296  starpu_mpi_cache, se enabled MPI Support, 296  starpu_mpi_cache set MPI Support, 296  starpu_mpi_data_get_rank MPI Support, 297  starpu_mpi_data_get_rank MPI Support, 292  starpu_mpi_data_set_rank MPI Support, 292  starpu_mpi_data_set_rank MPI Support, 296  starpu_mpi_tata_set_rank MPI Support, 296  starpu_mpi_tata_pate_rank MPI Support, 296  starpu_mpi_tata_pate_rank MPI Support,		
starpu_mpi_barrier MPl Support, 295 starpu_mpi_cache_flush MPl Support, 296 starpu_mpi_cache_flush MPl Support, 296 starpu_mpi_cache_flush MPl Support, 296 starpu_mpi_cache_flush_all_data MPl Support, 296 starpu_mpi_cache_se_neabled MPl Support, 296 starpu_mpi_cache_se_se_neabled MPl Support, 296 starpu_mpi_cache_se_set MPl Support, 296 starpu_mpi_data_get_rank MPl Support, 297 starpu_mpi_data_get_tag MPl Support, 297 starpu_mpi_data_get_tag MPl Support, 298 starpu_mpi_data_set_rank MPl Support, 292 starpu_mpi_data_set_rank MPl Support, 292 starpu_mpi_data_set_rank MPl Support, 293 starpu_mpi_data_set_rank MPl Support, 297 starpu_mpi_data_set_tag MPl Support, 297 starpu_mpi_data_set_tag MPl Support, 296 MPl Support, 297 starpu_mpi_data_set_tag MPl Support, 296 MPl Support, 296 MPl Support, 296 MPl Support, 297 starpu_mpi_data_set_tag MPl Support, 298 starpu_mpi_gather_detached MPl Support, 296 MPl Support, 297 MPl Support, 296 MPl Support, 298 MPl Support, 299 MPl Support, 298 MPl Support, 298 MPl Support, 298 MPl Support, 299 MPl Support, 299 MPl Support, 298 MPl Support, 299 MPl Support, 299 MPl Support, 296 MPl Supp		• •
starpu_mpi_barrier MPI Support, 296 starpu_mpi_cache_flush MPI Support, 296 starpu_mpi_cache_flush_all_data MPI Support, 296 starpu_mpi_cache_sis_enabled MPI Support, 295 starpu_mpi_cache_sis_enabled MPI Support, 295 starpu_mpi_cache_sis_enabled MPI Support, 295 starpu_mpi_data_get_tank MPI Support, 297 starpu_mpi_data_get_tank MPI Support, 297 starpu_mpi_data_register MPI Support, 296 starpu_mpi_data_sis_enable MPI Support, 296 starpu_mpi_data_sis_enable MPI Support, 297 starpu_mpi_data_sis_enable MPI Support, 296 starpu_mpi_data_sis_enable MPI Support, 298 starpu_mpi_data_sis_enable MPI Support, 298 starpu_mpi_data_sis_enable MPI Support, 298 starpu_mpi_data	•	
MPI Support, 295 starpu_mpi_cache_flush MPI Support, 296 starpu_mpi_cache_flush all_data MPI Support, 296 starpu_mpi_cache_flush_all_data MPI Support, 296 starpu_mpi_cache_flush_all_data MPI Support, 296 starpu_mpi_cache_se_neabled MPI Support, 296 starpu_mpi_cache_se_set MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_comm_amounts_retrieve MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_tag MPI Support, 298 starpu_mpi_data_register MPI Support, 297 starpu_mpi_data_register comm MPI Support, 292 MPI Support, 298 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_rank MPI Support, 298 starpu_mpi_data_set_rank MPI Support, 296 starpu_mpi_data_set_rank MPI Support, 298 starpu_mpi_task_post_build MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_set_rank MPI Support, 293 starpu_mpi_initialize_set_rank MPI Support, 293 starpu_mpi_initialize_set_rand MPI Support, 293 starpu_mpi_initialize_mpi_initialize_set_rand MPI Support, 293 starpu_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initialize_mpi_initia	· <del>-</del> · ·	·
starpu_mpl_cache_flush MPl Support, 296 starpu_mpl_cache_flush_all_data MPl Support, 296 starpu_mpl_cache_flush_all_data MPl Support, 296 starpu_mpl_cache_is_enabled MPl Support, 296 MPl Support, 296 starpu_mpl_cache_is_enabled MPl Support, 296 MPl Support, 296 MPl Support, 296 starpu_mpl_cache_is_enabled MPl Support, 295 starpu_mpl_cache_is_enabled MPl Support, 296 MPl Support, 295 starpu_mpl_domm_amounts_retrieve MPl Support, 297 starpu_mpl_data_get_tag MPl Support, 297 MPl Support, 297 starpu_mpl_data_get_tag MPl Support, 297 starpu_mpl_data_register MPl Support, 299 starpu_mpl_data_register_comm MPl Support, 290 starpu_mpl_data_set_rank MPl Support, 292 starpu_mpl_data_set_rank MPl Support, 297 starpu_mpl_data_set_rank MPl Support, 297 starpu_mpl_data_set_tag MPl Support, 297 starpu_mpl_data_set_tag MPl Support, 297 starpu_mpl_data_set_tag MPl Support, 296 starpu_mpl_datatype_register MPl Support, 296 starpu_mpl_datatype_register MPl Support, 296 starpu_mpl_get_data_on_node MPl Support, 298 starpu_mpl_get_data_on_node MPl Support, 298 starpu_mpl_get_data_on_node MPl Support, 298 starpu_mpl_initic_omm MPl Support, 293 starpu_mpl_initic_omm MPl Support, 293 starpu_mpl_initic_omm MPl Support, 293 starpu_mpl_initic_omm MPl Support, 293 starpu_mpl_initidize MPl Suppo	. — . —	
MPI Support, 296 starpu_mpi_cache_flush_all_data MPI Support, 296 starpu_mpi_cache_is_enabled MPI Support, 296 starpu_mpi_cache_is_enabled MPI Support, 296 starpu_mpi_cache_is_enabled MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_tag MPI Support, 297 starpu_mpi_data_get_tag MPI Support, 297 starpu_mpi_data_register MPI Support, 298 starpu_mpi_data_set_rank MPI Support, 298 starpu_mpi_data_set_rank MPI Support, 299 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_rank MPI Support, 298 starpu_mpi_data_set_rank MPI Support, 299 starpu_mpi_set_data_on_node MPI Support, 296  MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node detached MPI Support, 298 starpu_mpi_init comm MPI Support, 298 starpu_mpi_init comm MPI Support, 293 starpu_mpi_initialize MPI Support, 295 starpu_mpi_initialize MPI Support, 295 starpu_mpi_initialize MPI Support, 295 starpu_mpi_initialize MPI Support, 296 MPI Support, 297 starpu_mpi_test MPI Support, 298 starpu_mpi_initialize MPI Support, 299 starpu_mpi_initialize MPI Support, 299 starpu_mpi_initialize MPI Support, 295 starpu_mpi_initial	• •	
starpu_mpi_cache_flush_all_data MPI Support, 296  MPI Support, 296  MPI Support, 296  starpu_mpi_cache_jse_nabled MPI Support, 295  starpu_mpi_cache_jse_nabled MPI Support, 296  starpu_mpi_cache_set MPI Support, 295  starpu_mpi_comm_amounts_retrieve MPI Support, 294  starpu_mpi_data_get_rank MPI Support, 297  starpu_mpi_data_get_tag MPI Support, 297  starpu_mpi_data_get_tag MPI Support, 297  starpu_mpi_data_get_tag MPI Support, 298  starpu_mpi_data_register MPI Support, 296  starpu_mpi_data_set_rank MPI Support, 296  starpu_mpi_data_set_rank MPI Support, 296  starpu_mpi_data_set_rank MPI Support, 297  starpu_mpi_data_set_rank Comm MPI Support, 297  starpu_mpi_data_set_rank MPI Support, 297  starpu_mpi_data_set_tag MPI Support, 297  starpu_mpi_data_set_tag MPI Support, 297  starpu_mpi_data_set_tag MPI Support, 298  starpu_mpi_data_set_tag MPI Support, 299  starpu_mpi_datalybe_register MPI Support, 296  starpu_mpi_datalybe_unregister MPI Support, 296  starpu_mpi_datalybe_unregister MPI Support, 296  starpu_mpi_data_set_tag MPI Support, 296  starpu_mpi_gather_detached MPI Support, 296  starpu_mpi_gather_detached MPI Support, 296  starpu_mpi_gather_detached MPI Support, 296  starpu_mpi_gather_detached MPI Support, 296  starpu_mpi_initialize MPI Support, 298  starpu_mpi_initialize MPI Support, 293  starpu_mpi_initialize MPI Support, 296  starpu_mpi_initialize MPI Support, 298  starpu_mpi_initialize MPI Support, 298		
MPI Support, 296 starpu_mpi_cache_is_enabled MPI Support, 296 Starpu_mpi_cache_set MPI Support, 296 MPI Support, 296 Starpu_mpi_comm_amounts_retrieve MPI Support, 294 MPI Support, 297 Starpu_mpi_data_get_rank MPI Support, 297 MPI Support, 297 Starpu_mpi_data_get_tag MPI Support, 297 MPI Support, 299 Starpu_mpi_data_register MPI Support, 299 Starpu_mpi_data_set_rank MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 296 Starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 298 Starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 297 Starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 297 MPI Support, 298 Starpu_mpi_data_set_tag MPI Support, 297 MPI Support, 298 MPI Support, 299 Starpu_mpi_datatype_register MPI Support, 296 MPI Support, 297 MPI Support, 298 MPI Support, 299 MPI Support, 298 MPI Support, 299 MPI Support, 296 MPI Support, 296 MPI Support, 297 MPI Support, 296 MPI Support, 296 MPI Support, 297 MPI Support, 296 MPI Support, 296 MPI Support, 297 MPI Support, 296 MPI	• •	• •
starpu_mpi_cache_is_enabled MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 295 starpu_mpi_cache_set MPI Support, 296 MPI Support, 295 starpu_mpi_cache_is_manner MPI Support, 294 MPI Support, 295 starpu_mpi_data_get_rank MPI Support, 297 MPI Support, 297 MPI Support, 297 MPI Support, 298 starpu_mpi_data_geister MPI Support, 299 MPI Support, 299 Starpu_mpi_data_register_comm MPI Support, 299 MPI Support, 299 Starpu_mpi_data_set_rank MPI Support, 299 MPI Support, 299 Starpu_mpi_data_set_rank MPI Support, 299 MPI Support, 299 MPI Support, 299 Starpu_mpi_data_set_tank MPI Support, 297 MPI Support, 299 Starpu_mpi_data_set_tank MPI Support, 296 MPI Support, 298 Starpu_mpi_gather_detached MPI Support, 299 Starpu_mpi_gather_detached MPI Support, 298 Starpu_mpi_get_data_on_node MPI Support, 298 Starpu_mpi_get_data_on_node MPI Support, 298 Starpu_mpi_get_data_on_node MPI Support, 298 Starpu_mpi_init MPI Support, 293 Starpu_mpi_init_comm MPI Support, 293 Starpu_mpi_init_comm MPI Support, 293 Starpu_mpi_initicomm MPI Support, 293 Starpu_mpi_initidize MPI Suppo		
MPI Support, 296 starpu_mpi_cache_set MPI Support, 296 starpu_mpi_comm_amounts_retrieve MPI Support, 294 starpu_mpi_data_get_rank MPI Support, 297 starpu_mpi_data_get_tag MPI Support, 298 starpu_mpi_data_get_tag MPI Support, 297 starpu_mpi_data_get_tag MPI Support, 298 starpu_mpi_data_register MPI Support, 299 starpu_mpi_data_register MPI Support, 299 starpu_mpi_data_register MPI Support, 299 starpu_mpi_data_set_rank MPI Support, 298 starpu_mpi_data_register MPI Support, 299 starpu_mpi_data_register_comm MPI Support, 296 MPI Support, 298 starpu_mpi_data_set_rank MPI Support, 296 MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 297 MPI Support, 297 MPI Support, 297 MPI Support, 297 MPI Support, 298 starpu_mpi_data_set_tag MPI Support, 297 MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 MPI Support, 296 starpu_mpi_get_communication_tag MPI Support, 296 MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_omm MPI Support, 293 starpu_mpi_init_omm MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize_extended M	• •	• •
starpu_mpi_cache_set MPI Support, 296 MPI Support, 295 starpu_mpi_comm_amounts_retrieve MPI Support, 294 MPI Support, 295 starpu_mpi_data_get_rank MPI Support, 297 MPI Support, 297 Starpu_mpi_data_get_tag MPI Support, 298 MPI Support, 297 MPI Support, 297 MPI Support, 298 Starpu_mpi_data_register MPI Support, 292 MPI Support, 292 MPI Support, 298 Starpu_mpi_data_register_comm MPI Support, 296 MPI Support, 298 Starpu_mpi_data_set_rank MPI Support, 299 MPI Support, 299 MPI Support, 299 Starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 299 MPI Support, 299 MPI Support, 299 Starpu_mpi_data_set_tag MPI Support, 297 MPI Support, 299 MPI Support, 299 Starpu_mpi_data_set_tag MPI Support, 296 MPI Support, 299 MPI Support, 299 Starpu_mpi_datatype_register MPI Support, 296 MPI Support, 296 MPI Support, 298 MPI Support, 299 MPI Support, 299 MPI Support, 299 MPI Support, 299 Starpu_mpi_gatlatype_unregister MPI Support, 296 MPI Support, 298 MPI Support, 298 MPI Support, 299 MPI Support, 298 MPI Support, 293 MPI Support, 295 MPI Support, 296 MPI Support, 297 MPI Support, 295 MPI Support, 295 MPI Support, 296 MPI Support, 297 MPI Support, 295 MPI Support,		
MPI Support, 296 starpu_mpi_comm amounts_retrieve MPI Support, 294 MPI Support, 294 MPI Support, 295 starpu_mpi_data_get_rank MPI Support, 297 MPI Support, 298 starpu_mpi_data_get_tag MPI Support, 298 starpu_mpi_data_get_tag MPI Support, 299 MPI Support, 298 starpu_mpi_data_register MPI Support, 292 MPI Support, 292 MPI Support, 292 MPI Support, 298 starpu_mpi_data_register_comm MPI Support, 296 MPI Support, 296 MPI Support, 299 MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 299 MPI Support, 298 MPI Support, 293 MPI Support, 295 MPI Support, 295 MPI Support, 296 MPI Support, 297 MPI Support, 298 MPI Support, 29	• •	• •
starpu_mpi_comm_amounts_retrieve MPI Support, 294 MPI Support, 295 starpu_mpi_data_get_tank MPI Support, 297 MPI Support, 298 starpu_mpi_data_get_tag MPI Support, 297 MPI Support, 297 MPI Support, 297 MPI Support, 298 starpu_mpi_data_get_tag MPI Support, 299 MPI Support, 292 starpu_mpi_data_register MPI Support, 292 MPI Support, 298 starpu_mpi_data_register MPI Support, 296 MPI Support, 296 MPI Support, 296 Starpu_mpi_data_set_rank MPI Support, 292 MPI Support, 299 MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 298 MPI Support,		
MPI Support, 294 starpu_mpi_data_get_rank MPI Support, 297  starpu_mpi_data_get_tag MPI Support, 298  starpu_mpi_data_get_tag MPI Support, 298  starpu_mpi_data_get_tag MPI Support, 298  starpu_mpi_data_getser MPI Support, 298  starpu_mpi_data_register MPI Support, 298  starpu_mpi_data_register_comm MPI Support, 298  starpu_mpi_data_set_rank MPI Support, 299  starpu_mpi_data_set_rank MPI Support, 292  starpu_mpi_data_set_rank MPI Support, 292  starpu_mpi_data_set_rank MPI Support, 299  starpu_mpi_data_set_rank MPI Support, 297  starpu_mpi_data_set_tag MPI Support, 297  starpu_mpi_data_set_tag MPI Support, 297  starpu_mpi_data_set_tag MPI Support, 297  starpu_mpi_dataype_register MPI Support, 296  starpu_mpi_dataype_unregister MPI Support, 296  starpu_mpi_dataype_unregister MPI Support, 299  starpu_mpi_gather_detached MPI Support, 299  starpu_mpi_gather_communication_tag MPI Support, 299  starpu_mpi_get_data_on_node MPI Support, 298  starpu_mpi_get_data_on_node MPI Support, 298  starpu_mpi_get_data_on_node MPI Support, 298  starpu_mpi_get_data_on_node MPI Support, 298  starpu_mpi_init MPI Support, 293  starpu_mpi_initicomm M	• •	• •
starpu_mpi_data_get_rank MPl Support, 297 Starpu_mpi_data_get_tag MPl Support, 297 Starpu_mpi_data_register MPl Support, 298 Starpu_mpi_data_register MPl Support, 298 Starpu_mpi_data_register MPl Support, 298 Starpu_mpi_data_register MPl Support, 298 Starpu_mpi_data_register MPl Support, 299 Starpu_mpi_data_set_comm MPl Support, 296 MPl Support, 299 Starpu_mpi_data_set_rank MPl Support, 292 Starpu_mpi_data_set_rank MPl Support, 297 Starpu_mpi_data_set_tag MPl Support, 297 Starpu_mpi_data_set_tag MPl Support, 297 Starpu_mpi_data_set_tag MPl Support, 297 Starpu_mpi_datatype_register MPl Support, 296 MPl Support, 296 Starpu_mpi_datatype_unregister MPl Support, 296 MPl Support, 296 Starpu_mpi_gather_detached MPl Support, 296 Starpu_mpi_get_data_on_node MPl Support, 296 MPl Support, 298 Starpu_mpi_get_data_on_node MPl Support, 298 Starpu_mpi_get_data_on_node MPl Support, 298 Starpu_mpi_get_data_on_node_detached MPl Support, 298 Starpu_mpi_init MPl Support, 298 Starpu_mpi_init MPl Support, 293 Starpu_mpi_init MPl Support, 293 Starpu_mpi_init MPl Support, 293 Starpu_mpi_init MPl Support, 293 Starpu_mpi_initalize MPl Support, 294 Starpu_mpi_insert_task MPl Support, 295 Starpu_mpi_insert_task MPl Support, 296 Starpu_mpi_data_fate MPl Sup		
MPI Support, 297  starpu mpi_data_get_tag  MPI Support, 297  starpu_mpi_data_get_tag  MPI Support, 297  starpu_mpi_data_register  MPI Support, 292  starpu_mpi_data_register  MPI Support, 292  starpu_mpi_data_register_comm  MPI Support, 296  MPI Support, 296  starpu_mpi_data_set_rank  MPI Support, 292  starpu_mpi_data_set_rank  MPI Support, 297  starpu_mpi_data_set_rank_comm  MPI Support, 297  starpu_mpi_data_set_tag  MPI Support, 297  starpu_mpi_data_set_tag  MPI Support, 297  starpu_mpi_data_set_tag  MPI Support, 299  starpu_mpi_datatype_register  MPI Support, 296  starpu_mpi_datatype_unregister  MPI Support, 296  starpu_mpi_gather_detached  MPI Support, 296  starpu_mpi_get_communication_tag  MPI Support, 296  starpu_mpi_get_communication_tag  MPI Support, 298  starpu_mpi_get_data_on_node  MPI Support, 298  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_init comm  MPI Support, 293  starpu_mpi_init comm  MPI Support, 293  starpu_mpi_initiclize  MPI Support, 293  starpu_mpi_initiclize_extended  MPI Support, 293  starpu_mpi_initiclize  MPI Support, 293  starpu_mpi_initiclize_extended  MPI Support, 293  starpu_mpi_initiclize_extended  MPI Support, 293  starpu_mpi_initiclize_extended  MPI Support, 293  starpu_mpi_initiclize_extended  MPI Support, 297  starpu_node_selection_node_selection_redictor_selectio	• •	• •
starpu_mpi_data_get_tag MPI Support, 297 MPI Support, 298 starpu_mpi_data_register MPI Support, 299 starpu_mpi_data_register MPI Support, 299 starpu_mpi_data_register_comm MPI Support, 296 MPI Support, 299 starpu_mpi_data_register_comm MPI Support, 299 starpu_mpi_data_set_tank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 292 MPI Support, 294 starpu_mpi_data_set_tank MPI Support, 297 MPI Support, 299 starpu_mpi_data_set_tank MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 296 starpu_mpi_datatype_urregister MPI Support, 296 MPI Support, 296 Starpu_mpi_gather_detached MPI Support, 296 MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 296 MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_dom MPI Support, 293 starpu_mpi_init_dom MPI Support, 293 starpu_mpi_initalize MPI Support, 293 starpu_mpi_initalize_extended MPI Support, 293 starpu_mpi_initalize MPI Support, 293		
MPI Support, 297 starpu_mpi_data_register MPI Support, 292 starpu_mpi_data_register_comm MPI Support, 296 starpu_mpi_data_register_comm MPI Support, 296 MPI Support, 296 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 294 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 299 starpu_mpi_data_set_day MPI Support, 299 starpu_mpi_data_set_day MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 MPI Support, 299 starpu_mpi_datatype_unregister MPI Support, 296 MPI Support, 296 MPI Support, 296 MPI Support, 296 Starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 MPI Support, 296 starpu_mpi_get_communication_tag MPI Support, 299 MPI Support, 298 starpu_mpi_get_communication_tag MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_eat MP	MPI Support, 297	MPI Support, 298
starpu_mpi_data_register MPI Support, 298 starpu_mpi_data_register_comm MPI Support, 296 starpu_mpi_data_register_comm MPI Support, 296 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank_comm MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_communication_tag MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_loomm MPI Support, 293 starpu_mpi_init_loomm MPI Support, 293 starpu_mpi_initialize starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize MPI Support, 293 starpu_mpi_datatype_register MPI Support, 293 starpu_mpi_datatype_register MPI Support, 293 starpu_mpi_datatype_register MPI Support, 295 sta	starpu_mpi_data_get_tag	starpu_mpi_node_selection_register_policy
MPI Support, 292 starpu_mpi_data_register_comm MPI Support, 296 MPI Support, 299 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 297 MPI Support, 299 starpu_mpi_data_set_rank_comm MPI Support, 297 MPI Support, 299 starpu_mpi_data_set_tank_comm MPI Support, 297 MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 297 MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 MPI Support, 296 Starpu_mpi_datatype_unregister MPI Support, 296 Starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_lomm MPI Support, 293 starpu_mpi_init_lomm MPI Support, 293 starpu_mpi_init_lomm MPI Support, 293 starpu_mpi_init_lommi MPI Support, 293 starpu_mpi_init_lomidalize MPI Support, 293 starpu_mpi_initialize MP	MPI Support, 297	MPI Support, 298
starpu_mpi_data_register_comm MPI Support, 299 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank_comm MPI Support, 297 starpu_mpi_data_set_rank_comm MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 297 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_init MPI Support, 293 starpu_mpi_init MPI Support, 293 starpu_mpi_initescomm MPI Support, 293 starpu_mpi_initialize MPI S	starpu_mpi_data_register	starpu_mpi_node_selection_set_current_policy
MPI Support, 296 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_init MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_insert_task MPI Support, 297	MPI Support, 292	MPI Support, 298
MPI Support, 296 starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_rank MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_init MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_insert_task MPI Support, 297	• •	·
starpu_mpi_data_set_rank MPI Support, 292 starpu_mpi_data_set_rank_comm MPI Support, 299 starpu_mpi_data_set_rank_comm MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_gather_detached MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_init MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_initiclize MPI Support, 293 starpu_mpi_initiclize MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_inisert_task MPI Support, 297 Workers' Properties, 179		. – . – – – –
MPI Support, 292  starpu_mpi_data_set_rank_comm	• •	• •
starpu_mpi_data_set_rank_comm MPI Support, 297 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_data_set_tag MPI Support, 299 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_initalize MPI Support, 293 starpu_mpi_initalize MPI Support, 293 starpu_mpi_initalize MPI Support, 293 starpu_mpi_initalize MPI Support, 293 starpu_mpi_initalize_extended MPI Support, 293 starpu_mpi_initer_task MPI Support, 297 Workers' Properties, 179		
MPI Support, 297  starpu_mpi_data_set_tag     MPI Support, 299  starpu_mpi_data_set_tag     MPI Support, 299  starpu_mpi_datatype_register     MPI Support, 299  starpu_mpi_datatype_register     MPI Support, 294  starpu_mpi_datatype_unregister     MPI Support, 296  starpu_mpi_datatype_unregister     MPI Support, 296  starpu_mpi_gather_detached     MPI Support, 299  starpu_mpi_get_communication_tag     MPI Support, 299  starpu_mpi_get_communication_tag     MPI Support, 298  starpu_mpi_get_data_on_node     MPI Support, 298  starpu_mpi_get_data_on_node     MPI Support, 298  starpu_mpi_get_data_on_node_detached     MPI Support, 298  starpu_mpi_get_data_on_node_detached     MPI Support, 298  starpu_mpi_init     starpu_mpi_init     starpu_mpi_init     starpu_mpi_init     MPI Support, 293  starpu_mpi_init_comm     MPI Support, 293  starpu_mpi_initialize     MPI Support, 293  starpu_mpi_initialize_extended     MPI Support, 293  starpu_mpi_insert_task     MPI Support, 297	• •	·
starpu_mpi_data_set_tag MPI Support, 297 starpu_mpi_datatype_register MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_datatype_unregister MPI Support, 296 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_gather_detached MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 299 starpu_mpi_get_communication_tag MPI Support, 296 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node MPI Support, 298 starpu_mpi_get_data_on_node_detached MPI Support, 298 starpu_mpi_init MPI Support, 298 starpu_mpi_init MPI Support, 298 starpu_mpi_init MPI Support, 293 starpu_mpi_init MPI Support, 293 starpu_mpi_init_comm MPI Support, 293 starpu_mpi_initalize Starpu_mpi_initalize Starpu_mpi_initalize Starpu_mpi_initalize MPI Support, 293 starpu_mpi_initalize Starpu_mpi_initalize Starpu_mpi_initalize_extended MPI Support, 293 starpu_mpi_initalize_extended MPI Support, 293 starpu_mpi_initalize_extended MPI Support, 293 starpu_mpi_insert_task MPI Support, 297 Workers' Properties, 179		
starpu_mpi_datatype_register MPI Support, 299  starpu_mpi_datatype_register MPI Support, 296  starpu_mpi_datatype_unregister MPI Support, 296  starpu_mpi_datatype_unregister MPI Support, 296  starpu_mpi_gather_detached MPI Support, 299  starpu_mpi_get_communication_tag MPI Support, 293  starpu_mpi_get_data_on_node MPI Support, 298  starpu_mpi_get_data_on_node_detached MPI Support, 298  starpu_mpi_get_data_on_node_detached MPI Support, 298  starpu_mpi_init MPI Support, 298  starpu_mpi_init MPI Support, 298  starpu_mpi_init MPI Support, 298  starpu_mpi_init MPI Support, 293  starpu_mpi_init_comm MPI Support, 293  starpu_mpi_initalize MPI Support, 293  starpu_mpi_initalize MPI Support, 293  starpu_mpi_initalize MPI Support, 293  starpu_mpi_initalize MPI Support, 293  starpu_mpi_initialize MPI Support, 293  starpu_mpi_initialize MPI Support, 293  starpu_mpi_initialize_extended MPI Support, 293  starpu_mpi_init	• •	• •
starpu_mpi_datatype_register MPI Support, 296 Starpu_mpi_datatype_unregister MPI Support, 296 Starpu_mpi_datatype_unregister MPI Support, 296 Starpu_mpi_gather_detached MPI Support, 299 Starpu_mpi_get_communication_tag MPI Support, 299 MPI Support, 293 Starpu_mpi_get_communication_tag MPI Support, 296 Starpu_mpi_get_data_on_node MPI Support, 298 Starpu_mpi_get_data_on_node MPI Support, 298 MPI Support, 297 Starpu_mpi_iget_data_on_node_detached MPI Support, 298 MPI Support, 298 Starpu_mpi_init MPI Support, 298 Starpu_mpi_init MPI Support, 293 Starpu_mpi_init_comm MPI Support, 293 Starpu_mpi_init_comm MPI Support, 293 Starpu_mpi_initlalize MPI Support, 293 Starpu_mpi_initlalize MPI Support, 293 Starpu_mpi_initlalize MPI Support, 293 Starpu_mpi_initlalize MPI Support, 293 Starpu_mpi_initialize_extended MPI Support, 293 Starpu_mpi_insert_task MPI Support, 297 Workers' Properties, 179		
MPI Support, 294  starpu_mpi_datatype_unregister	• •	• •
starpu_mpi_datatype_unregisterstarpu_mpi_set_communication_tagMPI Support, 296MPI Support, 296starpu_mpi_gather_detachedstarpu_mpi_shutdownMPI Support, 299MPI Support, 293starpu_mpi_get_communication_tagstarpu_mpi_task_buildMPI Support, 296MPI Support, 298starpu_mpi_get_data_on_nodestarpu_mpi_task_insertMPI Support, 298MPI Support, 297starpu_mpi_get_data_on_node_detachedstarpu_mpi_task_post_buildMPI Support, 298MPI Support, 298starpu_mpi_initstarpu_mpi_testMPI Support, 293MPI Support, 295starpu_mpi_init_commstarpu_mpi_waitMPI Support, 293MPI Support, 295starpu_mpi_initializestarpu_multiformat_data_registerMPI Support, 293Multiformat Data Interface, 224starpu_mpi_initialize_extendedstarpu_node_get_kindMPI Support, 293Workers' Properties, 182starpu_mpi_insert_taskstarpu_node_kindMPI Support, 297Workers' Properties, 179		
MPI Support, 296 starpu_mpi_gather_detached		
starpu_mpi_gather_detached starpu_mpi_shutdown MPI Support, 299 starpu_mpi_get_communication_tag starpu_mpi_task_build MPI Support, 296 starpu_mpi_get_data_on_node starpu_mpi_task_insert MPI Support, 298 starpu_mpi_get_data_on_node_detached starpu_mpi_task_post_build MPI Support, 298 starpu_mpi_get_data_on_node_detached starpu_mpi_task_post_build MPI Support, 298 starpu_mpi_init starpu_mpi_test MPI Support, 293 starpu_mpi_init_comm starpu_mpi_wait MPI Support, 293 starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_initialize_extended MPI Support, 293 starpu_mpi_insert_task MPI Support, 297 Workers' Properties, 182 starpu_node_kind MPI Support, 297 Workers' Properties, 179		
MPI Support, 299  starpu_mpi_get_communication_tag  MPI Support, 296  starpu_mpi_get_data_on_node  MPI Support, 298  starpu_mpi_get_data_on_node  MPI Support, 297  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_init  MPI Support, 298  starpu_mpi_init  MPI Support, 298  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  Workers' Properties, 179	• •	• •
starpu_mpi_get_communication_tag  MPI Support, 296  Starpu_mpi_get_data_on_node  MPI Support, 298  starpu_mpi_get_data_on_node  MPI Support, 298  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_init  MPI Support, 298  starpu_mpi_init  MPI Support, 293  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_initalize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mode_get_kind  MPI Support, 293  starpu_mode_kind  MPI Support, 297  Workers' Properties, 179		
MPI Support, 296  starpu_mpi_get_data_on_node	• •	·
starpu_mpi_get_data_on_node  MPI Support, 298  starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_init		
MPI Support, 298  starpu_mpi_get_data_on_node_detached     MPI Support, 298  starpu_mpi_init     MPI Support, 298  starpu_mpi_init     MPI Support, 293  starpu_mpi_init_comm     MPI Support, 293  starpu_mpi_init_comm     MPI Support, 295  starpu_mpi_initialize     MPI Support, 293  starpu_mpi_initialize_extended     MPI Support, 293  starpu_mpi_initialize_extended     MPI Support, 293  starpu_mpi_initialize_extended     MPI Support, 293  starpu_mpi_initialize_extended     MPI Support, 293  starpu_mpi_insert_task     MPI Support, 297  Workers' Properties, 179	• •	·
starpu_mpi_get_data_on_node_detached  MPI Support, 298  starpu_mpi_init  MPI Support, 293  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  Workers' Properties, 182  starpu_node_kind  MPI Support, 297  Workers' Properties, 179		
MPI Support, 298  starpu_mpi_init	• •	·
starpu_mpi_init  MPI Support, 293  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_init_alize  MPI Support, 295  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  Workers' Properties, 182  starpu_node_kind  MPI Support, 297  Workers' Properties, 179		
MPI Support, 293  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  MPI Support, 295  starpu_mpi_wait  starpu_multiformat_data_register  Multiformat Data Interface, 224  starpu_node_get_kind  Workers' Properties, 182  starpu_node_kind  MPI Support, 297  Workers' Properties, 179	··	·
starpu_mpi_init_comm  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  Starpu_mpi_insert_task  MPI Support, 297  Starpu_mode_kind  Workers' Properties, 179	starpu_mpi_init	starpu_mpi_test
MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize  MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  MPI Support, 293  Starpu_node_get_kind  Workers' Properties, 182  starpu_node_kind  Workers' Properties, 179	MPI Support, 293	MPI Support, 295
starpu_mpi_initialize starpu_multiformat_data_register  MPI Support, 293 Multiformat Data Interface, 224  starpu_mpi_initialize_extended starpu_node_get_kind  MPI Support, 293 Workers' Properties, 182  starpu_mpi_insert_task starpu_node_kind  MPI Support, 297 Workers' Properties, 179	starpu_mpi_init_comm	starpu_mpi_wait
MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  Multiformat Data Interface, 224  starpu_node_get_kind  Workers' Properties, 182  starpu_node_kind  Workers' Properties, 179	MPI Support, 293	MPI Support, 295
MPI Support, 293  starpu_mpi_initialize_extended  MPI Support, 293  starpu_mpi_insert_task  MPI Support, 297  Multiformat Data Interface, 224  starpu_node_get_kind  Workers' Properties, 182  starpu_node_kind  Workers' Properties, 179	starpu_mpi_initialize	starpu_multiformat_data_register
starpu_mpi_initialize_extended starpu_node_get_kind  MPI Support, 293 Workers' Properties, 182  starpu_mpi_insert_task starpu_node_kind  MPI Support, 297 Workers' Properties, 179		
MPI Support, 293 Workers' Properties, 182 starpu_mpi_insert_task starpu_node_kind MPI Support, 297 Workers' Properties, 179	• •	
starpu_mpi_insert_task starpu_node_kind MPI Support, 297 Workers' Properties, 179	. – . – –	·
MPI Support, 297 Workers' Properties, 179	• •	•
···		
	starpu_mpi_irecv	starpu_omp_atomic_fallback_inline_begin

OpenMP Runtime Support, 283	OpenMP Runtime Support, 280
starpu_omp_atomic_fallback_inline_end	starpu_omp_get_team_size
OpenMP Runtime Support, 283	OpenMP Runtime Support, 279
starpu_omp_barrier	starpu_omp_get_thread_limit
OpenMP Runtime Support, 269	OpenMP Runtime Support, 277
starpu_omp_critical	starpu_omp_get_thread_num
OpenMP Runtime Support, 269	OpenMP Runtime Support, 275
starpu_omp_critical_inline_begin	starpu_omp_get_wtick
OpenMP Runtime Support, 270	OpenMP Runtime Support, 284
starpu_omp_critical_inline_end	starpu_omp_get_wtime
OpenMP Runtime Support, 270	OpenMP Runtime Support, 283
starpu omp destroy lock	starpu_omp_in_final
OpenMP Runtime Support, 281	OpenMP Runtime Support, 279
starpu_omp_destroy_nest_lock	starpu_omp_in_parallel
OpenMP Runtime Support, 282	OpenMP Runtime Support, 276
starpu_omp_for	starpu_omp_init
OpenMP Runtime Support, 271	OpenMP Runtime Support, 269
starpu_omp_for_alt	starpu_omp_init_lock
OpenMP Runtime Support, 272	OpenMP Runtime Support, 281
starpu_omp_for_inline_first	starpu_omp_init_nest_lock
OpenMP Runtime Support, 271	OpenMP Runtime Support, 282
starpu_omp_for_inline_first_alt	starpu_omp_is_initial_device
OpenMP Runtime Support, 272	OpenMP Runtime Support, 280
starpu_omp_for_inline_next	starpu_omp_master
OpenMP Runtime Support, 272	OpenMP Runtime Support, 269
starpu_omp_for_inline_next_alt	starpu_omp_master_inline
OpenMP Runtime Support, 273	OpenMP Runtime Support, 269
starpu_omp_get_active_level	starpu_omp_ordered
OpenMP Runtime Support, 279	OpenMP Runtime Support, 273
starpu_omp_get_ancestor_thread_num	starpu_omp_ordered_inline_begin
OpenMP Runtime Support, 278	OpenMP Runtime Support, 273
starpu_omp_get_cancellation	starpu_omp_ordered_inline_end
OpenMP Runtime Support, 277	OpenMP Runtime Support, 273
·	
starpu omp get default device	starpu omp parallel region
starpu_omp_get_default_device OpenMP Runtime Support, 280	starpu_omp_parallel_region OpenMP Runtime Support. 269
OpenMP Runtime Support, 280	OpenMP Runtime Support, 269
OpenMP Runtime Support, 280 starpu_omp_get_dynamic	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value
OpenMP Runtime Support, 280 starpu_omp_get_dynamic OpenMP Runtime Support, 276	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value OpenMP Runtime Support, 268
OpenMP Runtime Support, 280 starpu_omp_get_dynamic OpenMP Runtime Support, 276 starpu_omp_get_level	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value OpenMP Runtime Support, 268 starpu_omp_sched_value
OpenMP Runtime Support, 280 starpu_omp_get_dynamic OpenMP Runtime Support, 276 starpu_omp_get_level OpenMP Runtime Support, 278	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value OpenMP Runtime Support, 268 starpu_omp_sched_value OpenMP Runtime Support, 268
OpenMP Runtime Support, 280 starpu_omp_get_dynamic OpenMP Runtime Support, 276 starpu_omp_get_level OpenMP Runtime Support, 278 starpu_omp_get_max_active_levels	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value OpenMP Runtime Support, 268 starpu_omp_sched_value OpenMP Runtime Support, 268 starpu_omp_sections
OpenMP Runtime Support, 280 starpu_omp_get_dynamic     OpenMP Runtime Support, 276 starpu_omp_get_level     OpenMP Runtime Support, 278 starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value OpenMP Runtime Support, 268 starpu_omp_sched_value OpenMP Runtime Support, 268 starpu_omp_sections OpenMP Runtime Support, 273
OpenMP Runtime Support, 280 starpu_omp_get_dynamic     OpenMP Runtime Support, 276 starpu_omp_get_level     OpenMP Runtime Support, 278 starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_get_max_threads	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined
OpenMP Runtime Support, 280 starpu_omp_get_dynamic     OpenMP Runtime Support, 276 starpu_omp_get_level     OpenMP Runtime Support, 278 starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_get_max_threads     OpenMP Runtime Support, 275	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value    OpenMP Runtime Support, 268 starpu_omp_sched_value    OpenMP Runtime Support, 268 starpu_omp_sections    OpenMP Runtime Support, 273 starpu_omp_sections_combined    OpenMP Runtime Support, 273
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value    OpenMP Runtime Support, 268 starpu_omp_sched_value    OpenMP Runtime Support, 268 starpu_omp_sections    OpenMP Runtime Support, 273 starpu_omp_sections_combined    OpenMP Runtime Support, 273 starpu_omp_set_default_device
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value    OpenMP Runtime Support, 268 starpu_omp_sched_value    OpenMP Runtime Support, 268 starpu_omp_sections    OpenMP Runtime Support, 273 starpu_omp_sections_combined    OpenMP Runtime Support, 273 starpu_omp_set_default_device    OpenMP Runtime Support, 279
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value    OpenMP Runtime Support, 268 starpu_omp_sched_value    OpenMP Runtime Support, 268 starpu_omp_sections    OpenMP Runtime Support, 273 starpu_omp_sections_combined    OpenMP Runtime Support, 273 starpu_omp_set_default_device    OpenMP Runtime Support, 279 starpu_omp_set_dynamic    OpenMP Runtime Support, 276 starpu_omp_set_lock
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value    OpenMP Runtime Support, 268 starpu_omp_sched_value    OpenMP Runtime Support, 268 starpu_omp_sections    OpenMP Runtime Support, 273 starpu_omp_sections_combined    OpenMP Runtime Support, 273 starpu_omp_set_default_device    OpenMP Runtime Support, 279 starpu_omp_set_dynamic    OpenMP Runtime Support, 276 starpu_omp_set_lock    OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels    OpenMP Runtime Support, 278
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_teads	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_threads     OpenMP Runtime Support, 275	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 278
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_threads     OpenMP Runtime Support, 275  starpu_omp_get_num_threads     OpenMP Runtime Support, 275  starpu_omp_get_proc_bind	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 282 starpu_omp_set_nest_lock     OpenMP Runtime Support, 282 starpu_omp_set_nested
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_threads     OpenMP Runtime Support, 275	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 278
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_threads     OpenMP Runtime Support, 275  starpu_omp_get_num_threads     OpenMP Runtime Support, 275  starpu_omp_get_proc_bind	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 282 starpu_omp_set_nest_lock     OpenMP Runtime Support, 282 starpu_omp_set_nested
OpenMP Runtime Support, 280  starpu_omp_get_dynamic     OpenMP Runtime Support, 276  starpu_omp_get_level     OpenMP Runtime Support, 278  starpu_omp_get_max_active_levels     OpenMP Runtime Support, 278  starpu_omp_get_max_threads     OpenMP Runtime Support, 275  starpu_omp_get_nested     OpenMP Runtime Support, 277  starpu_omp_get_num_devices     OpenMP Runtime Support, 280  starpu_omp_get_num_procs     OpenMP Runtime Support, 276  starpu_omp_get_num_teams     OpenMP Runtime Support, 280  starpu_omp_get_num_treads     OpenMP Runtime Support, 280  starpu_omp_get_num_threads     OpenMP Runtime Support, 275  starpu_omp_get_proc_bind     OpenMP Runtime Support, 279	OpenMP Runtime Support, 269 starpu_omp_proc_bind_value     OpenMP Runtime Support, 268 starpu_omp_sched_value     OpenMP Runtime Support, 268 starpu_omp_sections     OpenMP Runtime Support, 273 starpu_omp_sections_combined     OpenMP Runtime Support, 273 starpu_omp_set_default_device     OpenMP Runtime Support, 279 starpu_omp_set_dynamic     OpenMP Runtime Support, 276 starpu_omp_set_lock     OpenMP Runtime Support, 281 starpu_omp_set_max_active_levels     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 278 starpu_omp_set_nest_lock     OpenMP Runtime Support, 282 starpu_omp_set_nested     OpenMP Runtime Support, 276

Codelet And Tasks, 237 Performance Model, 252 starpu_opencl_get_context starpu_perfmodel_init	OpenMP Runtime Support, 277	starpu_opencl_get_current_context
starpu_omp_single OpenMP Runtime Support, 270 starpu_omp_single_copyprivate OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_begin OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_begin OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_dod OpenMP Runtime Support, 271 starpu_omp_lask_region OpenMP Runtime Support, 274 starpu_omp_lask_group_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskyroup_inline_begin OpenMP Runtime Support, 282 starpu_omp_laskyroup_inline_begin OpenMP Runtime Support, 282 starpu_omp_laskyroup_inline_begin OpenMP Runtime Support, 283 starpu_omp_laskyroup_inline_begin OpenMP Runtime Support, 284 starpu_omp_unset_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 284 starpu_omp_unset_lock OpenMP Runtime Support, 284 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_opy_opencl_lo_ram OpenCL Extensions, 263 starpu_opencl_opy_opencl_lo_ram OpenCL Extensions, 263 starpu_opencl_dopy_ram to_opencl_opy_opencl_lo_ram OpenCL Extensions, 262 starpu_opencl_dopy_ram to_opencl_opy_ram to_opencl_opy_ram to_opencl_opy_ram to_opencl_opy_ram to_opencl_opencl_dopy_ram to_opencl_opencl_dopy_ram to_opencl_opencl_dopy_ram to_opencl_opencl_dopy_ram to_opencl_opencl_dopy_ram to_opencl_opencl_dopy_ram to_opencl_opencl_dopy_	starpu_omp_shutdown	OpenCL Extensions, 261
OpenMP Runtime Support, 270 starpu_omp_single_copyprivate OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 270 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 270 starpu_omp_task_region OpenMP Runtime Support, 274 starpu_omp_taskgroup OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 284 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 284 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 284 starpu_opend_lask_tarrie_init_n Parallel Tasks, 303 starpu_parallel_task_barrier_i	OpenMP Runtime Support, 269	starpu_opencl_get_current_queue
starpu_omp_single_copyprivate	starpu_omp_single	OpenCL Extensions, 261
Starpu_omp_single_copyprivate_inline_begin OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 270 starpu_omp_single_inline OpenMP Runtime Support, 270 starpu_omp_task_region OpenMP Runtime Support, 274 starpu_omp_task_group OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskyroup_inline_end OpenMP Runtime Support, 282 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 283 starpu_omp_lose_lock OpenMP Runtime Support, 284 starpu_opencl_lood_epend OpenCL Extensions, 263 starpu_opend_clood_epend OpenCL Extensions, 263 starpu_opend_clood_epend OpenCL Extensions, 263 starpu_opend_clood_epend OpenCL Extensions, 263 starpu_opend_complie_opend_from_file OpenCL Extensions, 263 starpu_opend_complie_opend_from_string OpenCL Extensions, 263 starpu_opend_loopy_copend_to_opend OpenCL Extensions, 263 starpu_opend_loopy_primate_from_string OpenCL Extensions, 263 starpu_opend_loopy_pri	OpenMP Runtime Support, 270	starpu_opencl_get_device
Starpu_omp_single_copyprivate_inline_begin OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 270 starpu_omp_single_inline OpenMP Runtime Support, 270 starpu_omp_task_region OpenMP Runtime Support, 274 starpu_omp_task_group OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskyroup_inline_end OpenMP Runtime Support, 282 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 283 starpu_omp_lose_lock OpenMP Runtime Support, 284 starpu_opencl_lood_epend OpenCL Extensions, 263 starpu_opend_clood_epend OpenCL Extensions, 263 starpu_opend_clood_epend OpenCL Extensions, 263 starpu_opend_clood_epend OpenCL Extensions, 263 starpu_opend_complie_opend_from_file OpenCL Extensions, 263 starpu_opend_complie_opend_from_string OpenCL Extensions, 263 starpu_opend_loopy_copend_to_opend OpenCL Extensions, 263 starpu_opend_loopy_primate_from_string OpenCL Extensions, 263 starpu_opend_loopy_pri	starpu omp single copyprivate	OpenCL Extensions, 261
starpu_omp_single_copyprivate_inline_begin OpenMP Runtime Support, 271 starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 271 starpu_omp_single_inline OpenMP Runtime Support, 270 starpu_omp_task_region OpenMP Runtime Support, 274 starpu_omp_taskgroup OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_unset_look OpenMP Runtime Support, 283 starpu_omp_unset_look OpenMP Runtime Support, 284 starpu_omp_unset_look OpenMP Runtime Support, 284 starpu_omp_unset_look OpenMP Runtime Support, 284 starpu_opencl_oolect_stansions, 263 starpu_opencl_oolect_stansions, 263 starpu_opencl_collect_stats OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 263 starpu_opencl_copy_encl_from_file OpenCL Extensions, 263 starpu_opencl_copy_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_from_string OpenCL Extensions, 263 starpu_opencl_dopopencl_from_string OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions,		•
OpenMP Runtime Support, 271 starpu_omp_single_copyrrivate_inline_end OpenMP Runtime Support, 271 starpu_omp_single_inline OpenMP Runtime Support, 270 starpu_omp_lask_region OpenMP Runtime Support, 274 starpu_omp_lask_region OpenMP Runtime Support, 274 starpu_omp_lask_group_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_suport, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_suport, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_suport, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_end OpenMP Runtime Support, 274 starpu_omp_laskyoup_inline_begin OpenCL Extensions, 262 starpu_open_laskyoup_inline_begin OpenCL Extensions, 261 starpu_opencl_load_pencl_from_string OpenCL Extensions, 262 starpu_opencl_load_pencl_from_string OpenCL Extensions, 263 starpu_opencl_load_pencl_from_string OpenCL Extensions, 262 st	·	
starpu_omp_single_copyprivate_inline_end OpenMP Runtime Support, 270 starpu_omp_lask_region OpenMP Runtime Support, 274 starpu_omp_taskgroup OpenMP Runtime Support, 274 starpu_omp_laskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_laskgroup_inline_did OpenMP Runtime Support, 274 starpu_omp_laskwait OpenMP Runtime Support, 274 starpu_omp_laskwait OpenMP Runtime Support, 274 starpu_omp_lest_lock OpenMP Runtime Support, 282 starpu_omp_lest_lock OpenMP Runtime Support, 283 starpu_omp_lest_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 284 starpu_opencl_online_opencl OpenCL Extensions, 262 starpu_opencl_ollect stats OpenCL Extensions, 262 starpu_opencl_collect stats OpenCL Extensions, 262 starpu_opencl_copy_epencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_fixency OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_ope		•
OpenMP Runtime Support, 271 starpu_omp_ingle_inline OpenMP Runtime Support, 270 starpu_omp_task_region OpenMP Runtime Support, 274 starpu_omp_task_group OpenMP Runtime Support, 274 starpu_omp_task_group OpenMP Runtime Support, 274 starpu_omp_task_group_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_nest_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_opencl_ock OpenMP Runtime Support, 282 starpu_opencl_clock OpenMP Runtime Support, 281 starpu_opencl_dock OpenMP Runtime Support, 282 starpu_opencl_clock OpenMP Runtime Support, 281 starpu_opencl_dock OpenMP Runtime Support, 282 starpu_opencl_clock OpenMP Runtime Support, 281 starpu_opencl_dock OpenCl_Extensions, 262 starpu_opencl_comple_opencl_from_string OpenCl_Extensions, 263 starpu_opencl_docypu_opencl_docypu_opencl_docypu_ope	·	OpenCL Extensions, 262
starpu_omp_ single_inline OpenMP Runtime Support, 270 starpu_omp_ task_region OpenMP Runtime Support, 274 starpu_omp_taskgroup OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 281 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 282 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_finc_t Codelt And Tasks, 237 starpu_opencl_filet, 1 Codelt And Tasks, 237 starpu_opencl_filet, 2 Codelt And Tasks, 237 starpu_opencl_det_(bistory_based_expected_p Performance Model, 251 starpu_perfmodel_history_based_expected_p Performance Model, 251		•
OpenMP Runtime Support, 270  starpu_omp_task_region OpenMP Runtime Support, 274  starpu_omp_taskgroup OpenMP Runtime Support, 274  starpu_omp_taskgroup OpenMP Runtime Support, 274  starpu_omp_taskgroup inline_begin OpenMP Runtime Support, 274  starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274  starpu_omp_taskwait OpenMP Runtime Support, 282  starpu_omp_test_lock OpenMP Runtime Support, 283  starpu_omp_unset_lock OpenMP Runtime Support, 283  starpu_omp_unset_lock OpenMP Runtime Support, 281  starpu_omp_unset_lock OpenMP Runtime Support, 282  starpu_omp_unset_lock OpenMP Runtime Support, 282  starpu_omp_unset_lock OpenMP Runtime Support, 284  starpu_opencl_allocate_memory OpenCL Extensions, 263  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263  starpu_opencl_copy_opencl_lo_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_lo_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_lo_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_lo_ram OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_file, 363  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_file, 363  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_file, 363  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 263  starpu_	·	
starpu_omp_task_region OpenMP Runtime Support, 274 starpu_omp_taskgroup OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_open_unset_lock OpenMP Runtime Support, 282 starpu_open_lates_ens_lock OpenMP Runtime Support, 284 starpu_open_lates_ens_lock OpenMP Runtime Support, 284 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_comp_opencl_from_file OpenCL Extensions, 263 starpu_opencl_comp_opencl_to_popencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_popencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 263 starpu_opencl_d		•
OpenMP Runtime Support, 274 starpu_omp_taskgroup inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_nest_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock OpenMP Runtime Support, 282 starpu_omp_vector_annotate OpenMP Runtime Support, 284 starpu_opencl_dallocate_memory OpenCL Extensions, 263 starpu_opencl_colloct_stats OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_from_string OpenCL Extensions, 263 starpu_opencl_opencl_from_string	·	
starpu_omp_taskgroup OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_task_mait OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 282 starpu_omp_unset_nest_lock OpenMP Runtime Support, 282 starpu_omp_vector_annotate OpenMP Runtime Support, 284 starpu_opencl_dn, 360 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_oet_context starpu_perfmodel_init starpu_perfmodel_init	· - ·	•
OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_opencl_unload_opencl Starpu_opencl_worker_get_count Workers Properties, 181 starpu_opencl_worker_get_count Workers Properties, 181 starpu_opencl_worker_get_count Workers Properties, 181 starpu_opennl_h, 361 starpu_opend_lallocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_opencl_do_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_diplay_error OpenCL Extensions, 262 starpu_opencl_diplay_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_ontext starpu_perfmodel_linit starpu_perfmodel_init	·	
starpu_omp_taskgroup_inline_begin OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_opencl_wnload_opencl OpenCL Extensions, 261 starpu_opencl_opencl_from OpenMP Runtime Support, 284 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_cpencl_to_ram OpenCL Extensions, 263 starpu_opencl_diplay_error OpenCL Extensions, 263 starpu_opencl_diplay_error OpenCL Extensions, 262 starpu_opencl_di		•
OpenMP Runtime Support, 274 starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_test_nest_lock OpenMP Runtime Support, 282 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock OpenMP Runtime Support, 282 starpu_omp_vector annotate OpenMP Runtime Support, 282 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_dopy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_dopencl_dopencl OpenCL Extensions, 263 starpu_opencl_dopencl_dopencl OpenCL Extensions, 263 starpu_opencl_dopencl_dopencl OpenCL Extensions, 263 starpu_opencl_dopencl_dopencl OpenCL Extensions, 263 starpu_opencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dopencl_dop	• • • • • • • • • • • • • • • • • • • •	
starpu_omp_taskgroup_inline_end OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_test_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 282 starpu_omp_unset_lock OpenMP Runtime Support, 282 starpu_omp_unset_lock OpenMP Runtime Support, 282 starpu_opencl_n, 360 OpenMP Runtime Support, 284 starpu_opencl_allocate_memory OpenMP Runtime Support, 284 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_directory Performance Model, 251 starpu_perfmodel _get_arch_name Performance Model, 251 starpu_opencl_directory Performance Model, 251 starpu_opencl_directory Performance Model, 251 starpu_opencl_directory Performance Model, 251 starpu_opencl_directory Performance Model, 251		•
OpenMP Runtime Support, 274 starpu_omp_taskwait OpenMP Runtime Support, 274 starpu_omp_test_lock OpenMP Runtime Support, 282 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 282 starpu_omp_vector_annotate OpenMP Runtime Support, 282 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_opy_opencl_stiring OpenCL Extensions, 263 starpu_opencl_dopy_ram_to_opencl OpenCL Extensions, 262 starpu_opencl_dopy_copencl_dopy_ram_to_opencl OpenCL Extensions, 262 starpu_opencl_dopy_c	·	. – . – –
starpu_omp_taskwait		•
OpenMP Runtime Support, 274  starpu_omp_test_lock OpenMP Runtime Support, 282  starpu_omp_test_nest_lock OpenMP Runtime Support, 283  starpu_omp_unset_lock OpenMP Runtime Support, 283  starpu_omp_unset_lock OpenMP Runtime Support, 281  starpu_omp_unset_lock OpenMP Runtime Support, 281  starpu_omp_unset_lock OpenMP Runtime Support, 281  starpu_omp_unset_lock OpenMP Runtime Support, 282  starpu_omp_vector_annotate OpenMP Runtime Support, 284  starpu_opencl_h, 360  starpu_opencl_dllocate_memory OpenCL Extensions, 263  starpu_opencl_cllect_stats OpenCL Extensions, 263  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263  starpu_opencl_coppy_async_sync OpenCL Extensions, 263  starpu_opencl_coppy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_coppy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_distory_based_expected_p Performance Model, 251  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_ontext  starpu_opencl_distory_based_expected_p Performance Model, 251  starpu_opencl_ontext  starpu_opencl_ontext	·	. – . – . –
starpu_omp_test_lock	• — • —	•
Starpu_omp_test_nest_lock OpenMP Runtime Support, 283 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_lock OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock OpenMP Runtime Support, 282 starpu_omp_vector_annotate OpenMP Runtime Support, 284 starpu_opencl_h, 360 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_ferror_string OpenCL Extensions, 262 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_ferror_string		
starpu_omp_test_nest_lock     OpenMP Runtime Support, 283 starpu_omp_unset_lock     OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock     OpenMP Runtime Support, 281 starpu_omp_unset_nest_lock     OpenMP Runtime Support, 282 starpu_omp_vector_annotate     OpenMP Runtime Support, 284 starpu_opencl_h, 360 starpu_opencl_allocate_memory     OpenCL Extensions, 263 starpu_opencl_collect_stats     OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file     OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string     OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string     OpenCL Extensions, 263 starpu_opencl_copy_async_sync     OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl     OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl     OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram     OpenCL Extensions, 263 starpu_opencl_display_error     OpenCL Extensions, 262 starpu_opencl_display_error     OpenCL Extensions, 262 starpu_opencl_error_string     OpenCL Exten		•
Starpu_opencl_worker_get_count Starpu_omp_unset_lock OpenMP Runtime Support, 281 Starpu_omp_unset_nest_lock OpenMP Runtime Support, 282 Starpu_omp_vector_annotate OpenMP Runtime Support, 284 Starpu_opencl_h, 360 Starpu_opencl_h, 360 Starpu_opencl_h, 360 Starpu_opencl_h, 360 Starpu_opencl_lalks_barrier_init Parallel Tasks, 303 Starpu_opencl_latsk_barrier_init_n Parallel Tasks, 303 Starpu_opencl_lalocate_memory OpenCL Extensions, 263 Starpu_opencl_collect_stats OpenCL Extensions, 262 Starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 Starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 Starpu_opencl_copy_async_sync OpenCL Extensions, 263 Starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 Starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 Starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 Starpu_opencl_display_error OpenCL Extensions, 262 Starpu_opencl_display_error OpenCL Extensions, 262 Starpu_opencl_derror_string OpenCL Extensions, 262 Starpu_opencl_display_error OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 263 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 263 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 263 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_fron_fle OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 263 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 263 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 263 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu	·	. – . – .
starpu_omp_unset_lock		•
OpenMP Runtime Support, 281  starpu_omp_unset_nest_lock	·	· - ·
starpu_omp_unset_nest_lock OpenMP Runtime Support, 282 starpu_omp_vector_annotate OpenMP Runtime Support, 284 starpu_opencl.h, 360 starpu_opencl allocate _memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_from_t OpenCL Extensions, 262 starpu_opencl_from_string OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_get_context starpu_perfmodel_init starpu_perfmodel_init		•
Starpu_omp_vector_annotate OpenMP Runtime Support, 284  starpu_opencl.h, 360  starpu_opencl_allocate_memory OpenCL Extensions, 263  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263  starpu_opencl_copy_async_sync OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_opencl OpenCL Extensions, 263  starpu_opencl_diplay_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init	·	. –
starpu_omp_vector_annotate OpenMP Runtime Support, 284 starpu_opencl.h, 360 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_get_context starpu_openfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init		
Starpu_opencl_h, 360  starpu_opencl_allocate_memory OpenCL Extensions, 263  starpu_opencl_collect_stats OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 263  starpu_opencl_copy_async_sync OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  Parallel Tasks, 303  starpu_pause Initialization and Termination, 161  starpu_perfmodel  cost_function, 248  cost_function, 248  cost_function, 248  starpu_perfmodel  starpu_perfmodel, 248  siz_loaded, 248  siz_loa	·	
starpu_opencl.h, 360 starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_get_context starpu_operfmodel_init  starpu_operfmodel_init  starpu_operfmodel_init  starpu_operfmodel_init  starpu_operfmodel_init		
starpu_opencl_allocate_memory OpenCL Extensions, 263 starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_diplay_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_get_context  Initialization and Termination, 161 starpu_perfmodel starpu_perfmodel starpu_perfmodel starpu_perfmodel starpu_perfmodel is, 248 siz_loaded, 248 siz_loade	·	•
Starpu_opencl_collect_stats OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_copy_async_sync OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  cost_function, 248  footprint, 248  is_init, 248  is_inded, 25  is_int, 248  is_int, 248  is_inded, 25  is_int, 248  is_int, 248  is_int, 248		
starpu_opencl_collect_stats OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_get_context  cost_function, 248 sis_iont, 248 sis_loaded, 248 sis_loaded_pales sis_loaded_pales sis_loaded_pales sis_loaded_pales sis_loaded_pales sis_loaded_pales sis_loaded_pales sis_loaded_pales	· - · ·	
OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_file OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_copy_async_sync OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  footoprint, 248  is_init, 248  is_loaded, 251  starpu_perfmodel_diebugfilepath  Performance Model, 251  starpu_perfmodel_history_based_expected_p  Performance Model, 252  starpu_opencl_get_context  starpu_perfmodel_init		. —
starpu_opencl_compile_opencl_from_file     OpenCL Extensions, 262	. – . – –	— · · · · · · · · · · · · · · · · · · ·
OpenCL Extensions, 262  starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262  starpu_opencl_copy_async_sync OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  is_loaded, 248  size_base, 248  symbol, 248  starpu_perfmodel.h, 363  starpu_perfmodel_h, 363  starpu_perfmodel_debugfilepath Performance Model, 251  starpu_perfmodel_directory Performance Model, 251  starpu_perfmodel_get_archtype_name Performance Model, 251  starpu_opencl_func_t Starpu_perfmodel_history_based_expected_p Performance Model, 252  starpu_opencl_get_context  starpu_perfmodel_init	•	·
starpu_opencl_compile_opencl_from_string OpenCL Extensions, 262 starpu_opencl_copy_async_sync OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 263 starpu_opencl_display_error OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_error_string OpenCL Extensions, 262 starpu_opencl_func_t Codelet And Tasks, 237 starpu_opencl_get_context starpu_perfmodel_init size_base, 248 symbol, 248 starpu_perfmodel_h, 363 starpu_perfmodel_debugfilepath Performance Model, 251 starpu_perfmodel_directory Performance Model, 251 starpu_perfmodel_get_arch_name Performance Model, 251 starpu_perfmodel_get_archtype_name Performance Model, 251 starpu_perfmodel_history_based_expected_p Performance Model, 252 starpu_opencl_get_context starpu_perfmodel_init		
OpenCL Extensions, 262  starpu_opencl_copy_async_sync OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  starpu_perfmodel_init  starpu_perfmodel_nistory_based_expected_p Performance Model, 252  starpu_opencl_get_context  starpu_perfmodel_init	•	
starpu_opencl_copy_async_sync  OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  type, 248  starpu_perfmodel_h, 363  starpu_perfmodel_debugfilepath Performance Model, 251  starpu_perfmodel_directory Performance Model, 251  starpu_perfmodel_get_arch_name Performance Model, 251  starpu_perfmodel_get_archtype_name Performance Model, 251  starpu_perfmodel_history_based_expected_p Performance Model, 252  starpu_opencl_get_context  starpu_perfmodel_init		<del>-</del> · · ·
OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl     OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_opencl     OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram     OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl     OpenCL Extensions, 263  starpu_opencl_display_error     OpenCL Extensions, 262  starpu_opencl_error_string     OpenCL Extensions, 262  starpu_opencl_error_string     OpenCL Extensions, 262  starpu_opencl_func_t     Codelet And Tasks, 237  starpu_opencl_get_context  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init  starpu_perfmodel_init	•	
starpu_opencl_copy_opencl_to_opencl     OpenCL Extensions, 263  starpu_opencl_copy_opencl_to_ram     OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl     OpenCL Extensions, 263  starpu_opencl_copy_ram_to_opencl     OpenCL Extensions, 263  starpu_opencl_display_error     OpenCL Extensions, 262  starpu_opencl_error_string     OpenCL Extensions, 262  starpu_opencl_error_string     OpenCL Extensions, 262  starpu_opencl_func_t     Codelet And Tasks, 237  starpu_opencl_get_context  starpu_perfmodel_debugfilepath     Performance Model, 251  starpu_perfmodel_directory     Starpu_perfmodel_free_sampling_directories     Performance Model, 250  starpu_perfmodel_get_arch_name     Performance Model, 251  starpu_perfmodel_distory_name     Performance Model, 251  starpu_perfmodel_history_based_expected_p     Performance Model, 252  starpu_opencl_get_context  starpu_perfmodel_init		
OpenCL Extensions, 263  Starpu_opencl_copy_opencl_to_ram OpenCL Extensions, 263  Starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  Starpu_opencl_display_error OpenCL Extensions, 262  Starpu_opencl_error_string OpenCL Extensions, 262  Starpu_opencl_error_string OpenCL Extensions, 262  Starpu_opencl_func_t Codelet And Tasks, 237  Starpu_opencl_get_context  Performance Model, 251  Starpu_perfmodel_get_archtype_name Performance Model, 251  Starpu_perfmodel_history_based_expected_p Starpu_opencl_get_context  Starpu_perfmodel_init	•	• —
starpu_opencl_copy_opencl_to_ram		
OpenCL Extensions, 263  Starpu_opencl_copy_ram_to_opencl OpenCL Extensions, 263  Starpu_opencl_display_error OpenCL Extensions, 262  Starpu_opencl_error_string OpenCL Extensions, 262  Starpu_opencl_error_string OpenCL Extensions, 262  Starpu_opencl_func_t Codelet And Tasks, 237  Starpu_opencl_get_context  Performance Model, 251  Starpu_perfmodel_mistory_based_expected_p Performance Model, 252  Starpu_opencl_get_context  Starpu_perfmodel_init		
starpu_opencl_copy_ram_to_opencl     OpenCL Extensions, 263     starpu_opencl_display_error     OpenCL Extensions, 262     starpu_opencl_error_string     OpenCL Extensions, 262     starpu_opencl_error_string     OpenCL Extensions, 262     starpu_opencl_func_t     Codelet And Tasks, 237     starpu_opencl_get_context     starpu_opencl_get_context     starpu_perfmodel_init     starpu_perfmodel_init     starpu_perfmodel_init     starpu_perfmodel_init		
OpenCL Extensions, 263  starpu_opencl_display_error OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  Performance Model, 251  starpu_perfmodel_history_based_expected_p  Performance Model, 252  starpu_opencl_get_context  Starpu_perfmodel_init	•	
starpu_opencl_display_error OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_error_string OpenCL Extensions, 262 Starpu_opencl_func_t Codelet And Tasks, 237 Starpu_opencl_get_context Starpu_opencl_get_context Starpu_opencl_get_context Starpu_perfmodel_init Starpu_perfmodel_init		
OpenCL Extensions, 262  starpu_opencl_error_string OpenCL Extensions, 262  starpu_opencl_func_t Codelet And Tasks, 237  starpu_opencl_get_context  Performance Model, 251  starpu_perfmodel_history_based_expected_p Performance Model, 252  starpu_opencl_get_context  Starpu_perfmodel_init	•	
starpu_opencl_error_string starpu_perfmodel_get_archtype_name OpenCL Extensions, 262 Performance Model, 251 starpu_opencl_func_t starpu_perfmodel_history_based_expected_p Codelet And Tasks, 237 Performance Model, 252 starpu_opencl_get_context starpu_perfmodel_init		·
OpenCL Extensions, 262  starpu_opencl_func_t  Codelet And Tasks, 237  starpu_opencl_get_context  Performance Model, 251  starpu_perfmodel_history_based_expected_p  Performance Model, 252  starpu_opencl_get_context  starpu_perfmodel_init	•	
starpu_opencl_func_t starpu_perfmodel_history_based_expected_p Codelet And Tasks, 237 Performance Model, 252 starpu_opencl_get_context starpu_perfmodel_init		
Codelet And Tasks, 237 Performance Model, 252 starpu_opencl_get_context starpu_perfmodel_init	•	
starpu_opencl_get_context starpu_perfmodel_init		starpu_perfmodel_history_based_expected_perf
	· - ·	
OpenCL Extensions, 260 Performance Model, 250	OpenCL Extensions, 260	Performance Model, 250

starpu_perfmodel_list	Threads, 173
Performance Model, 251	starpu_pthread_cond_timedwait
starpu_perfmodel_load_file	Threads, 174
Performance Model, 250	starpu_pthread_cond_wait
starpu_perfmodel_load_symbol	Threads, 174
Performance Model, 250	starpu_pthread_create
starpu_perfmodel_print	Threads, 171
Performance Model, 251	starpu_pthread_exit
starpu_perfmodel_print_all	Threads, 172
Performance Model, 251	starpu_pthread_getspecific
starpu_perfmodel_type	Threads, 173
Performance Model, 250	starpu pthread join
starpu_perfmodel_unload_model	Threads, 172
Performance Model, 250	starpu_pthread_key_create
starpu_perfmodel_update_history	Threads, 173
Performance Model, 251	starpu_pthread_key_delete
starpu_prefetch_task_input_on_node	Threads, 173
Scheduling Policy, 321	starpu_pthread_mutex_destroy
	Threads, 172
starpu_private starpu_task, 234	
• =	starpu_pthread_mutex_init
starpu_profiling.h, 365	Threads, 172
starpu_profiling_bus_helper_display_summary	starpu_pthread_mutex_lock
Profiling, 255	Threads, 172
starpu_profiling_init	starpu_pthread_mutex_trylock
Profiling, 254	Threads, 173
starpu_profiling_set_id	starpu_pthread_mutex_unlock
Profiling, 254	Threads, 172
starpu_profiling_status_get	starpu_pthread_mutexattr_destroy
Profiling, 254	Threads, 173
starpu_profiling_status_set	starpu_pthread_mutexattr_gettype
Profiling, 254	Threads, 173
starpu_profiling_worker_get_info	starpu_pthread_mutexattr_init
Profiling, 254	Threads, 173
starpu_profiling_worker_helper_display_summary	starpu_pthread_mutexattr_settype
Profiling, 255	Threads, 173
starpu_progression_hook_deregister	starpu_pthread_rwlock_destroy
Expert Mode, 305	Threads, 174
starpu_progression_hook_register	starpu_pthread_rwlock_init
Expert Mode, 305	Threads, 174
starpu_pthread_attr_destroy	starpu_pthread_rwlock_rdlock
Threads, 172	Threads, 174
starpu_pthread_attr_init	starpu_pthread_rwlock_tryrdlock
Threads, 172	Threads, 174
starpu_pthread_attr_setdetachstate	starpu_pthread_rwlock_trywrlock
Threads, 172	Threads, 174
starpu_pthread_barrier_destroy	starpu_pthread_rwlock_unlock
Threads, 175	Threads, 175
starpu_pthread_barrier_init	starpu_pthread_rwlock_wrlock
Threads, 175	Threads, 174
starpu_pthread_barrier_wait	starpu_pthread_setspecific
Threads, 175	Threads, 173
starpu_pthread_cond_broadcast	starpu_pthread_spin_destroy
Threads, 174	Threads, 175
starpu_pthread_cond_destroy	starpu_pthread_spin_init
Threads, 174	Threads, 175
starpu_pthread_cond_init	starpu_pthread_spin_lock
Threads, 173	Threads, 175
starpu_pthread_cond_signal	starpu_pthread_spin_trylock

Threads, 175	starpu_sched_component_composed_recipe_destroy
starpu_pthread_spin_unlock	Modularized Scheduler Interface, 341
Threads, 175	starpu_sched_component_connect
starpu_push_local_task	Modularized Scheduler Interface, 338
Scheduling Policy, 319	starpu_sched_component_destroy
starpu_push_task_end	Modularized Scheduler Interface, 338
Scheduling Policy, 319	starpu_sched_component_destroy_rec
starpu_rand.h, 366	Modularized Scheduler Interface, 338
starpu_resume	starpu_sched_component_execute_preds
Initialization and Termination, 161	Modularized Scheduler Interface, 339
starpu_scc.h, 367	starpu_sched_component_fifo_create
starpu_scc_func_symbol_t	Modularized Scheduler Interface, 340
SCC Extensions, 286	starpu_sched_component_heft_create
starpu_scc_func_t	Modularized Scheduler Interface, 341
Codelet And Tasks, 237	starpu_sched_component_is_combined_worker
starpu_scc_get_kernel	Modularized Scheduler Interface, 339
SCC Extensions, 286	starpu_sched_component_is_eager
starpu_scc_kernel_t	Modularized Scheduler Interface, 340
Codelet And Tasks, 237	starpu sched component is eager calibration
	Modularized Scheduler Interface, 340
starpu_scc_register_kernel	
SCC Extensions, 286	starpu_sched_component_is_fifo
starpu_scc_worker_get_count	Modularized Scheduler Interface, 340
Workers' Properties, 181	starpu_sched_component_is_heft
starpu_sched_component	Modularized Scheduler Interface, 341
add_child, 334	starpu_sched_component_is_mct
add_parent, 334	Modularized Scheduler Interface, 340
can_pull, 335	starpu_sched_component_is_perfmodel_select
can_push, 335	Modularized Scheduler Interface, 341
children, 334	starpu_sched_component_is_prio
data, 334	Modularized Scheduler Interface, 340
deinit_data, 335	starpu_sched_component_is_random
estimated_end, 335	Modularized Scheduler Interface, 340
estimated_load, 335	starpu_sched_component_is_simple_worker
nchildren, 334	Modularized Scheduler Interface, 339
notify_change_workers, 335	starpu_sched_component_is_work_stealing
nparents, 334	Modularized Scheduler Interface, 340
obj, 335	starpu_sched_component_is_worker
parents, 334	Modularized Scheduler Interface, 339
properties, 335	starpu_sched_component_make_scheduler
pull_task, 335	Modularized Scheduler Interface, 341
push_task, 335	starpu_sched_component_mct_create
remove child, 334	Modularized Scheduler Interface, 340
remove_parent, 334	starpu_sched_component_perfmodel_select_create
tree, 334	Modularized Scheduler Interface, 341
workers, 334	starpu_sched_component_prio_create
workers_in_ctx, 334	Modularized Scheduler Interface, 340
starpu_sched_component_can_execute_task	starpu sched component properties
Modularized Scheduler Interface, 339	Modularized Scheduler Interface, 337
	starpu_sched_component_transfer_length
starpu_sched_component_composed_component	
create	Modularized Scheduler Interface, 339
Modularized Scheduler Interface, 341	starpu_sched_component_worker_get
starpu_sched_component_composed_recipe_add	Modularized Scheduler Interface, 339
Modularized Scheduler Interface, 341	starpu_sched_component_worker_get_workerid
starpu_sched_component_composed_recipe_create	Modularized Scheduler Interface, 339
Modularized Scheduler Interface, 341	starpu_sched_component_worker_post_exec_hook
starpu_sched_component_composed_recipe_create	Modularized Scheduler Interface, 339
singleton	starpu_sched_component_worker_pre_exec_hook
Modularized Scheduler Interface, 341	Modularized Scheduler Interface, 339

starpu_sched_ctx.h, 367	notify_post_exec_task, 312
starpu_sched_ctx_add_workers	notify_pushed_task, 312
Scheduling Contexts, 313	notify_submitted_job, 312
starpu_sched_ctx_call_pushed_task_cb	starpu_sched_ctx_register_close_callback
Scheduling Contexts, 315	Scheduling Contexts, 313
starpu_sched_ctx_check_if_hypervisor_exists	starpu_sched_ctx_remove_workers
Scheduling Contexts, 316	Scheduling Contexts, 313
starpu_sched_ctx_contains_worker	starpu_sched_ctx_set_context
Scheduling Contexts, 314	Scheduling Contexts, 314
starpu_sched_ctx_create	starpu_sched_ctx_set_inheritor
Scheduling Contexts, 313	Scheduling Contexts, 313
starpu_sched_ctx_create_inside_interval	starpu_sched_ctx_set_max_priority
Scheduling Contexts, 313	Scheduling Contexts, 315
starpu_sched_ctx_create_worker_collection	starpu_sched_ctx_set_min_priority
Scheduling Contexts, 315	Scheduling Contexts, 314
_	
starpu_sched_ctx_delete	starpu_sched_ctx_set_perf_counters
Scheduling Contexts, 313	Scheduling Contexts, 315
starpu_sched_ctx_delete_worker_collection	starpu_sched_ctx_set_policy_data
Scheduling Contexts, 315	Scheduling Contexts, 316
starpu_sched_ctx_display_workers	starpu_sched_ctx_stop_task_submission
Scheduling Contexts, 313	Scheduling Contexts, 314
starpu_sched_ctx_exec_parallel_code	starpu_sched_ctx_worker_get_id
Scheduling Contexts, 316	Scheduling Contexts, 314
starpu_sched_ctx_finished_submit	starpu_sched_ctx_worker_shares_tasks_lists
Scheduling Contexts, 314	Scheduling Policy, 321
starpu_sched_ctx_get_context	starpu_sched_get_max_priority
Scheduling Contexts, 314	Scheduling Policy, 319
starpu_sched_ctx_get_max_priority	starpu_sched_get_min_priority
Scheduling Contexts, 315	Scheduling Policy, 319
starpu_sched_ctx_get_min_priority	starpu_sched_get_predefined_policies
Scheduling Contexts, 315	Scheduling Policy, 318
starpu_sched_ctx_get_nready_flops	starpu_sched_policy
Scheduling Contexts, 316	add_workers, 318
starpu_sched_ctx_get_nready_tasks	deinit_sched, 318
Scheduling Contexts, 316	init_sched, 318
starpu_sched_ctx_get_nshared_workers	policy_description, 318
Scheduling Contexts, 314	policy_name, 318
starpu_sched_ctx_get_nworkers	pop_every_task, 318
Scheduling Contexts, 314	pop_task, 318
starpu_sched_ctx_get_policy_data	post_exec_hook, 318
Scheduling Contexts, 316	pre_exec_hook, 318
starpu_sched_ctx_get_worker_collection	push_task, 318
Scheduling Contexts, 315	push_task_notify, 318
starpu_sched_ctx_get_workers_list	remove_workers, 318
Scheduling Contexts, 314	starpu_sched_set_max_priority
starpu_sched_ctx_hypervisor.h, 369	Scheduling Policy, 319
starpu_sched_ctx_max_priority_is_set	starpu_sched_set_min_priority
Scheduling Contexts, 315	Scheduling Policy, 319
starpu_sched_ctx_min_priority_is_set	starpu_sched_tree_add_workers
Scheduling Contexts, 315	Modularized Scheduler Interface, 338
starpu_sched_ctx_notify_hypervisor_exists	starpu_sched_tree_create
Scheduling Contexts, 316	Modularized Scheduler Interface, 338
starpu_sched_ctx_overlapping_ctxs_on_worker	starpu_sched_tree_destroy
Scheduling Contexts, 314	Modularized Scheduler Interface, 338
starpu_sched_ctx_performance_counters	starpu_sched_tree_push_task
notify_delete_context, 312	Modularized Scheduler Interface, 338
notify_idle_cycle, 312	starpu_sched_tree_remove_workers
notify_poped_task, 312	Modularized Scheduler Interface, 338

starpu_sched_tree_update_workers	prologue_callback_arg_free, 232
Modularized Scheduler Interface, 338	prologue_callback_func, 232
starpu_sched_tree_update_workers_in_ctx	regenerate, 233
Modularized Scheduler Interface, 338	sched_ctx, 234
starpu_sched_tree_work_stealing_push_task	scheduled, 233
Modularized Scheduler Interface, 340	sequential_consistency, 232
starpu_scheduler.h, 369	starpu_private, 234
starpu_shutdown	status, 234
Initialization and Termination, 161	synchronous, 232
starpu_sink.h, 370	tag_id, 232
starpu_stdlib.h, 370	use_tag, 232
starpu_tag_declare_deps	workerid, 233
Explicit Dependencies, 244	workerorder, 233
starpu_tag_declare_deps_array	starpu_task.h, 371
Explicit Dependencies, 244	STARPU_CUDA_ASYNC, 373
starpu_tag_notify_from_apps	starpu_task_build
Explicit Dependencies, 245	Insert_Task, 243
starpu_tag_remove	starpu task bundle.h, 373
Explicit Dependencies, 245	starpu_task_bundle_close
·	Task Bundles, 300
starpu_tag_restart	
Explicit Dependencies, 245	starpu_task_bundle_create
starpu_tag_t	Task Bundles, 300
Explicit Dependencies, 244	starpu_task_bundle_expected_data_transfer_time
starpu_tag_wait	Task Bundles, 300
Explicit Dependencies, 245	starpu_task_bundle_expected_length
starpu_tag_wait_array	Task Bundles, 300
Explicit Dependencies, 245	starpu_task_bundle_expected_power
starpu_task	Task Bundles, 300
bundle, 234	starpu_task_bundle_insert
callback_arg, 232	Task Bundles, 300
callback_arg_free, 232	starpu_task_bundle_remove
callback_func, 232	Task Bundles, 300
cl, 230	starpu_task_bundle_t
cl_arg, 231	Task Bundles, 300
cl_arg_free, 232	starpu_task_clean
cl_arg_size, 231	Codelet And Tasks, 238
destroy, 233	starpu_task_create
detach, 233	Codelet And Tasks, 238
dyn_handles, 231	starpu_task_data_footprint
dyn_interfaces, 231	Scheduling Policy, 320
dyn_modes, 231	starpu_task_declare_deps_array
execute_on_a_specific_worker, 233	Explicit Dependencies, 244
flops, 234	starpu_task_destroy
handles, 231	Codelet And Tasks, 239
hypervisor_tag, 234	starpu_task_dup
interfaces, 231	Codelet And Tasks, 238
magic, 234	starpu_task_expected_conversion_time
mf_skip, 233	Scheduling Policy, 320
modes, 231	starpu_task_expected_data_transfer_time
name, 230	Scheduling Policy, 320
nbuffers, 231	starpu_task_expected_length
next, 234	Scheduling Policy, 320
predicted, 234	starpu_task_expected_power
predicted_transfer, 234	Scheduling Policy, 320
prev, 234	starpu_task_footprint
priority, 233	Scheduling Policy, 320
profiling_info, 234	starpu_task_get_current
prologue_callback_arg, 232	Codelet And Tasks, 240

starpu_task_get_implementation	starpu timing now
Codelet And Tasks, 240	Miscellaneous Helpers, 287
starpu task get task succs	starpu_timing_timespec_delay_us
Explicit Dependencies, 244	Profiling, 255
starpu_task_init	starpu timing timespec to us
Codelet And Tasks, 238	Profiling, 255
starpu task insert	starpu_top.h, 378
Insert Task, 242	starpu_top_add_data_boolean
starpu_task_list.h, 373	StarPU-Top Interface, 308
starpu_task_list_back	starpu_top_add_data_float
Task Lists, 302	StarPU-Top Interface, 308
starpu_task_list_begin	starpu_top_add_data_integer
Task Lists, 302	StarPU-Top Interface, 308
starpu_task_list_empty	starpu_top_data_type
Task Lists, 302	StarPU-Top Interface, 307
starpu_task_list_erase	starpu_top_debug_lock
Task Lists, 302	StarPU-Top Interface, 310
	•
starpu_task_list_front	starpu_top_debug_log
Task Lists, 302	StarPU-Top Interface, 309
starpu_task_list_init	starpu_top_init_and_wait
Task Lists, 301	StarPU-Top Interface, 309
starpu_task_list_next	starpu_top_message_type
Task Lists, 302	StarPU-Top Interface, 308
starpu_task_list_pop_back	starpu_top_param
Task Lists, 302	callback, 307
starpu_task_list_pop_front	double_max_value, 307
Task Lists, 302	double_min_value, 307
starpu_task_list_push_back	enum_values, 307
Task Lists, 302	id, 307
starpu_task_list_push_front	int_max_value, 307
Task Lists, 301	int_min_value, 307
starpu_task_nready	name, 307
Codelet And Tasks, 240	nb_values, 307
starpu_task_nsubmitted	next, 307
Codelet And Tasks, 240	type, 307
starpu_task_set_implementation	value, 307
Codelet And Tasks, 240	starpu_top_param_type
starpu_task_status	StarPU-Top Interface, 307
Codelet And Tasks, 238	starpu_top_register_parameter_boolean
starpu_task_submit	StarPU-Top Interface, 308
Codelet And Tasks, 239	starpu_top_register_parameter_enum
starpu_task_submit_to_ctx	StarPU-Top Interface, 309
Codelet And Tasks, 239	starpu_top_register_parameter_float
starpu_task_util.h, 374	StarPU-Top Interface, 308
starpu_task_wait	starpu_top_register_parameter_integer
Codelet And Tasks, 239	StarPU-Top Interface, 309
starpu_task_wait_for_all	starpu_top_task_prevision
Codelet And Tasks, 239	StarPU-Top Interface, 309
starpu_task_wait_for_all_in_ctx	starpu_top_update_data_boolean
Codelet And Tasks, 239	StarPU-Top Interface, 309
starpu_task_wait_for_n_submitted	starpu_top_update_data_float
Codelet And Tasks, 239	StarPU-Top Interface, 309
starpu_task_wait_for_n_submitted_in_ctx	starpu_top_update_data_integer
Codelet And Tasks, 239	StarPU-Top Interface, 309
starpu_task_wait_for_no_ready	starpu_top_update_parameter
Codelet And Tasks, 240	StarPU-Top Interface, 309
starpu_thread.h, 375	starpu_topology_print
starpu_thread_util.h, 377	Initialization and Termination, 162
	aaaaaaaaaaaa.

starpu_transfer_bandwidth	add, 179
Performance Model, 252	deinit, 179
starpu_transfer_latency	get_next, 179
Performance Model, 252	has_next, 179
starpu_transfer_predict	init, 179
Performance Model, 252	init_iterator, 179
starpu_tree.h, 379	nworkers, 178
starpu_tree_free	remove, 179
Tree, 322	type, 179
starpu_tree_get	workerids, 178
Tree, 322	starpu_worker_collection_type
starpu_tree_get_neighbour	Workers' Properties, 180
Tree, 322	starpu_worker_get_by_devid
starpu_tree_insert	Workers' Properties, 181
Tree, 322	starpu_worker_get_by_type
starpu_tree_reset_visited	Workers' Properties, 181
Tree, 322	starpu_worker_get_count
starpu_util.h, 379	Workers' Properties, 180
starpu_variable_data_register	starpu_worker_get_count_by_type
Data Interfaces, 205	Workers' Properties, 180
starpu_variable_get_elemsize	starpu_worker_get_devid
Data Interfaces, 208	Workers' Properties, 181
starpu_variable_get_local_ptr	starpu_worker_get_id
Data Interfaces, 208	Workers' Properties, 181
starpu_variable_ptr_register	starpu_worker_get_ids_by_type
Data Interfaces, 205	Workers' Properties, 181
starpu_vector_data_register	starpu_worker_get_memory_node
Data Interfaces, 205	Workers' Properties, 182
starpu_vector_filter_block	starpu_worker_get_name
Data Partition, 216	Workers' Properties, 182
starpu_vector_filter_block_shadow	starpu_worker_get_perf_archtype
Data Partition, 216	Performance Model, 251
starpu_vector_filter_divide_in_2	starpu_worker_get_relative_speedup
Data Partition, 217	Scheduling Policy, 320
starpu vector filter list	starpu_worker_get_sched_condition
Data Partition, 217	Scheduling Policy, 319
starpu_vector_get_elemsize	starpu_worker_get_type
Data Interfaces, 208	Workers' Properties, 182
starpu_vector_get_local_ptr	starpu_worker_get_type_as_string
Data Interfaces, 208	Workers' Properties, 182
starpu_vector_get_nx	starpufft.h, 384
Data Interfaces, 208	starpufft_cleanup
starpu_vector_ptr_register	FFT Support, 290
Data Interfaces, 206	starpufft destroy plan
starpu_void_data_register	FFT Support, 290
Data Interfaces, 205	starpufft_execute
starpu_wake_all_blocked_workers	FFT Support, 290
Expert Mode, 304	starpufft_execute_handle
starpu_worker.h, 381	FFT Support, 290
starpu_worker_archtype	starpufft_free
Workers' Properties, 180	FFT Support, 289
starpu_worker_can_execute_task	starpufft_malloc
Scheduling Policy, 319	FFT Support, 289
starpu_worker_can_execute_task_first_impl	starpufft_plan_dft_1d
Scheduling Policy, 320	FFT Support, 289
starpu_worker_can_execute_task_impl	starpufft_plan_dft_2d
Scheduling Policy, 319	FFT Support, 289
starpu_worker_collection	starpufft_start
·	

FFT Support, 290	starpu_pthread_attr_destroy, 172
starpufft_start_handle	starpu_pthread_attr_init, 172
FFT Support, 290	starpu_pthread_attr_setdetachstate, 172
status	starpu_pthread_barrier_destroy, 175
starpu_task, 234	starpu_pthread_barrier_init, 175
symbol	starpu_pthread_barrier_wait, 175
starpu_perfmodel, 248	starpu_pthread_cond_broadcast, 174
synchronous	starpu_pthread_cond_destroy, 174
starpu_task, 232	starpu pthread cond init, 173
	starpu_pthread_cond_signal, 173
TOP_TYPE_CONTINUE	starpu pthread cond timedwait, 174
StarPU-Top Interface, 308	starpu_pthread_cond_wait, 174
TOP_TYPE_DEBUG	starpu_pthread_create, 171
StarPU-Top Interface, 308	starpu_pthread_exit, 172
TOP_TYPE_DISABLE	starpu_pthread_getspecific, 173
StarPU-Top Interface, 308	
TOP_TYPE_ENABLE	starpu_pthread_join, 172
StarPU-Top Interface, 308	starpu_pthread_key_create, 173
TOP_TYPE_GO	starpu_pthread_key_delete, 173
StarPU-Top Interface, 308	starpu_pthread_mutex_destroy, 172
TOP TYPE SET	starpu_pthread_mutex_init, 172
StarPU-Top Interface, 308	starpu_pthread_mutex_lock, 172
TOP TYPE UNKNOW	starpu_pthread_mutex_trylock, 173
StarPU-Top Interface, 308	starpu_pthread_mutex_unlock, 172
tag_id	starpu_pthread_mutexattr_destroy, 173
starpu_task, 232	starpu_pthread_mutexattr_gettype, 173
Task Bundles, 299	starpu_pthread_mutexattr_init, 173
starpu_task_bundle_close, 300	starpu_pthread_mutexattr_settype, 173
starpu_task_bundle_create, 300	starpu_pthread_rwlock_destroy, 174
starpu_task_bundle_expected_data_transfer_time,	starpu_pthread_rwlock_init, 174
	starpu_pthread_rwlock_rdlock, 174
300	starpu_pthread_rwlock_tryrdlock, 174
starpu_task_bundle_expected_length, 300	starpu_pthread_rwlock_trywrlock, 174
starpu_task_bundle_expected_power, 300	starpu_pthread_rwlock_unlock, 175
starpu_task_bundle_insert, 300	starpu_pthread_rwlock_wrlock, 174
starpu_task_bundle_remove, 300	starpu_pthread_setspecific, 173
starpu_task_bundle_t, 300	starpu_pthread_spin_destroy, 175
Task Lists, 301	starpu_pthread_spin_init, 175
starpu_task_list_back, 302	starpu_pthread_spin_lock, 175
starpu_task_list_begin, 302	starpu_pthread_spin_trylock, 175
starpu_task_list_empty, 302	
starpu_task_list_erase, 302	starpu_pthread_spin_unlock, 175
starpu_task_list_front, 302	Toolbox, 165
starpu_task_list_init, 301	STARPU_ABORT, 167
starpu_task_list_next, 302	STARPU_ABORT_MSG, 167
starpu_task_list_pop_back, 302	STARPU_ASSERT, 167
starpu_task_list_pop_front, 302	STARPU_ASSERT_MSG, 167
starpu_task_list_push_back, 302	STARPU_GNUC_PREREQ, 166
starpu_task_list_push_front, 301	STARPU_LIKELY, 166
test_request	STARPU_MAX, 167
starpu_disk_ops, 221	STARPU_MIN, 167
Theoretical Lower Bound on Execution Time, 256	STARPU_POISON_PTR, 167
starpu_bound_compute, 256	STARPU_RMB, 167
starpu_bound_print, 256	STARPU UNLIKELY, 166
starpu_bound_print_dot, 256	STARPU_WMB, 167
starpu_bound_print_lp, 256	starpu_get_env_number, 168
starpu_bound_print_mps, 256	Tree, 321
starpu_bound_start, 256	starpu_tree_free, 322
starpu_bound_stop, 256	starpu_tree_get, 322
Threads, 168	starpu_tree_get, 322 starpu_tree_get_neighbour, 322
rinoada, roo	starpu_tree_yet_nergribbut, 322

	starpu_tree_insert, 322	starpu_node_get_kind, 182
	starpu_tree_reset_visited, 322	starpu_node_kind, 179
tree		starpu_opencl_worker_get_count, 181
	starpu_sched_component, 334	starpu_scc_worker_get_count, 181
type		starpu_worker_archtype, 180
	starpu_codelet, 226	starpu_worker_collection_type, 180
	starpu_perfmodel, 248	starpu_worker_get_by_devid, 181
	starpu_top_param, 307	starpu_worker_get_by_type, 181
t	starpu_worker_collection, 179	starpu_worker_get_count, 180
туре	s_of_workers, 389	starpu_worker_get_count_by_type, 180
unna	ack_data	starpu_worker_get_devid, 181 starpu_worker_get_id, 181
unpe	starpu_data_interface_ops, 193	starpu_worker_get_ids_by_type, 181
unpl	• – – •	starpu_worker_get_ids_by_type, 101 starpu_worker_get_memory_node, 182
up.	starpu_disk_ops, 220	starpu_worker_get_name, 182
use_		starpu_worker_get_type, 182
	starpu_task, 232	starpu_worker_get_type, 102 starpu_worker_get_type_as_string, 182
		write
value	Э	starpu_disk_ops, 220
	starpu_top_param, 307	ota.pa_diot_opo, 220
Vers	ioning, 157	
	STARPU_MAJOR_VERSION, 157	
	STARPU_MINOR_VERSION, 157	
	starpu_get_version, 157	
wait_	_request	
	starpu_disk_ops, 221	
whe		
	starpu_codelet, 226	
work		
work	starpu_task, 233 erids	
WOIR		
work	starpu_worker_collection, 178 serorder	
WOIR		
work	starpu_task, 233	
WOIR	starpu_sched_component, 334	
work	ers_in_ctx	
WOIN	starpu_sched_component, 334	
W∩rl	kers' Properties, 177	
VVOII	STARPU_ANY_WORKER, 180	
	STARPU CPU RAM, 180	
	STARPU CPU WORKER, 180	
	STARPU CUDA RAM, 180	
	STARPU CUDA WORKER, 180	
	STARPU MIC RAM, 180	
	STARPU MIC WORKER, 180	
	STARPU OPENCL RAM, 180	
	STARPU OPENCL WORKER, 180	
	STARPU SCC RAM, 180	
	STARPU SCC SHM, 180	
	STARPU SCC WORKER, 180	
	STARPU UNUSED, 180	
	STARPU WORKER LIST, 180	
	STARPU NMAXWORKERS, 179	
	starpu_cpu_worker_get_count, 180	
	starpu_cuda_worker_get_count, 180	
	starpu mic device get count, 181	

starpu\_mic\_worker\_get\_count, 181