# Package 'oce'

January 28, 2018

**Depends** R ( $\geq$  2.15), utils, methods, gsw, testthat Suggests ocedata, foreign, ncdf4, tiff, akima, RSQLite, DBI, rgdal (>= 1.1-9), R.utils, knitr, rmarkdown, marmap, lubridate BugReports https://github.com/dankelley/oce/issues Description Supports the analysis of Oceanographic data, including 'ADCP' measurements, measurements made with 'argo' floats, 'CTD' measurements, sectional data, sea-level time series, coastline and topographic data, etc. Provides specialized functions for calculating seawater properties such as potential temperature in either the 'UNESCO' or 'TEOS-10' equation of state. Produces graphical displays that conform to the conventions of the Oceanographic literature. License GPL (>= 2) **Encoding UTF-8** URL https://dankelley.github.io/oce LazyData false RoxygenNote 6.0.1 BuildVignettes true VignetteBuilder knitr **NeedsCompilation** yes Author Dan Kelley [aut, cre], Clark Richards [aut], Chantelle Layton [ctb] (curl() coauthor), British Geological Survey [ctb, cph] (magnetic-field subroutine) Repository CRAN

Type Package

**Version** 0.9-23

Title Analysis of Oceanographic Data

Maintainer Dan Kelley < Dan. Kelley@Dal.Ca>

**Date/Publication** 2018-01-28 21:13:31 UTC

# $\mathsf{R}$ topics documented:

abbreviateTimeLabels	
addColumn	
adp	. 13
adp-class	
adpEnsembleAverage	. 18
adv	. 19
adv-class	. 20
airRho	. 21
amsr-class	. 22
angleRemap	. 23
applyMagneticDeclination	. 24
approx3d	. 25
argo	. 26
argo-class	. 27
argoGrid	. 28
argoNames2oceNames	. 29
argShow	. 31
as.adp	. 32
as.argo	. 33
as.cm	. 34
as.coastline	. 35
as.ctd	. 36
as.echosounder	. 39
as.gps	. 40
as.ladp	. 41
as.lisst	
as.lobo	. 43
as.met	. 44
as.oce	. 45
as.rsk	. 46
as.sealevel	. 47
as.section	
as.topo	
as.unit	. 51
as.windrose	
bcdToInteger	. 53
beamName	
beamToXyz	. 55
beamToXyzAdp	
beamToXyzAdv	
beamUnspreadAdp	
binApply1D	
binApply2D	
binAverage	
binCount1D	
hinCount2D	64

100 T 17T 1	120
equatorialToLocalHorizontal	
errorbars	
fillGap	
findBottom	
findInOrdered	
firstFinite	
formatCI	
formatPosition	
fullFilename	
g1sst-class	
geodDist	
geodGc	
geodXy	
geodXyInverse	
GMTOffsetFromTz	
gps-class	
grad	
gravity	
handleFlags	
handleFlags,argo-method	
handleFlags,ctd-method	
handleFlags,section-method	
handleFlags, vector-method	
head.oce	
imagep	
integerToAscii	
integrateTrapezoid	
interpBarnes	
julianCenturyAnomaly	
julianDay	
ladp-class	
•	
landsat	
landsat-class	
landsatAdd	
landsatTrim	
latFormat	
latlonFormat	
lisst	
lisst-class	
lobo	
lonFormat	
<u> </u>	
lonlat2utm	
lowpass	
magneticField	
makeFilter	

makeSection	. 181
map2lonlat	. 182
mapArrows	. 183
mapAxis	. 184
mapContour	. 186
mapCoordinateSystem	. 187
mapDirectionField	. 188
mapGrid	. 190
mapImage	. 191
mapLines	. 194
mapLocator	. 196
mapLongitudeLatitudeXY	. 196
mapMeridians	. 197
mapPlot	. 198
mapPoints	. 207
mapPolygon	. 208
mapScalebar	. 209
mapText	. 210
mapTissot	. 211
mapZones	. 212
matchBytes	. 213
matrixShiftLongitude	. 214
matrixSmooth	. 214
met	. 215
met-class	. 216
metNames2oceNames	. 217
moonAngle	. 217
numberAsHMS	. 220
numberAsPOSIXct	. 221
oce	. 222
oce-class	. 223
oce-deprecated	. 224
oce.as.POSIXlt	. 225
oce.as.raw	. 226
oce.axis.POSIXct	. 227
oce.colorsGebco	. 229
oce.colorsTwo	. 229
oce.contour	. 231
oce.grid	. 233
oce.plot.ts	. 234
oce.write.table	. 236
oceApprox	. 237
oceConvolve	. 238
oceCRS	. 239
oceDebug	. 240
oceDeleteData	. 241
oceDeleteMetadata	. 242
oceEdit	242

oceFilter
oceGetData
oceGetMetadata
oceMagic
oceNames2whpNames
ocePmatch
oceSetData
oceSetMetadata
oceSmooth
oceSpectrum
oceUnits2whpUnits
odf-class
ODF2oce
ODFNames2oceNames
parseLatLon
plot,adp-method
plot,adv-method
plot,amsr-method
plot,argo-method
plot,bremen-method
plot,cm-method
plot, coastline-method
plot,ctd-method
plot,echosounder-method
plot,gps-method
plot,ladp-method
plot,landsat-method
plot,lisst-method
plot,lobo-method
plot,met-method
plot,oce-method
plot,odf-method
plot,rsk-method
plot,satellite-method
plot,sealevel-method
plot,section-method
plot,tidem-method
plot,topo-method
plot,windrose-method
plotInset
plotPolar
plotProfile
plotScan
plotSticks
plotTaylor
plotTS
predict.tidem
prettyPosition

processingLog<	
processingLogAppend	. 322
processingLogItem	. 322
processingLogShow	. 323
pwelch	. 323
rangeExtended	. 325
rangeLimit	. 325
read.ad2cp	. 326
read.adp	. 328
read.adp.nortek	. 329
read.adp.rdi	. 331
read.adp.sontek	. 334
read.adp.sontek.serial	. 335
read.adv	. 337
read.adv.nortek	. 342
read.adv.sontek.adr	. 346
read.adv.sontek.serial	. 351
read.adv.sontek.text	. 356
read.amsr	. 361
read.aquadopp	. 362
read.aquadoppHR	. 363
read.aquadoppProfiler	. 365
read.argo	. 367
read.bremen	. 370
read.cm	. 371
read.coastline	. 373
read.coastline.openstreetmap	
read.coastline.shapefile	
read.ctd	. 376
read.ctd.itp	
read.ctd.odf	
read.ctd.sbe	. 381
read.ctd.woce	
read.ctd.woce.other	
read.echosounder	. 386
read.g1sst	. 388
read.gps	. 389
read.index	. 390
read.landsat	
read.lisst	. 393
read.lobo	. 394
read.met	. 395
read.netcdf	
read.oce	
read.odf	
read.rsk	
read.sealevel	
read section	403

read.topo	
renameData	. 406
rescale	. 406
resizableLabel	. 407
retime	. 408
rsk	. 409
rsk-class	. 410
rsk2ctd	. 411
rskPatm	. 412
rskToc	. 413
runlm	. 414
satellite-class	. 415
sealevel	. 416
sealevel-class	. 417
sealevelTuktoyaktuk	. 417
secondsToCtime	. 419
section	. 420
section-class	. 421
sectionAddStation	
sectionGrid	
sectionSmooth	
sectionSort	
shiftLongitude	
showMetadataItem	
siderealTime	
standardDepths	
standardizeLongitude	
subset,adp-method	
subset,adv-method	
subset,amsr-method	
subset,argo-method	
subset,cm-method	
subset, coastline-method	
subset,ctd-method	
subset,echosounder-method	
subset,lobo-method	
subset,met-method	
subset,oce-method	
subset,odf-method	
subset,rsk-method	
subset, sealevel-method	
subset, section-method	
subset,topo-method	
subtractBottomVelocity	
summary,adp-method	
summary,adv-method	
summary,amsr-method	
summary,argo-method	

$summary, bremen-method \ \dots \ $
summary,cm-method
summary,coastline-method
summary,ctd-method
summary,echosounder-method
summary,gps-method
summary,ladp-method
summary,landsat-method
summary,lisst-method
summary,lobo-method
summary,met-method
summary,oce-method
summary,odf-method
summary,rsk-method
summary, satellite-method
summary, sealevel-method
summary, section-method
summary,tidem-method
summary,topo-method
summary, windrose-method
sunAngle
swAbsoluteSalinity
swAlpha
swAlphaOverBeta
swBeta
swConservativeTemperature
swCSTp
swDepth
swDynamicHeight
swLapseRate
swN2
swPressure
swRho
swRrho
swSCTp
swSigma
swSigma0
swSigma1
swSigma2
swSigma3
swSigma4
swSigmaT
swSigmaTheta
swSoundAbsorption
swSoundSpeed
swSpecificHeat
swSpice
swSTrho 501

wTFreeze	502
wThermalConductivity	504
wTheta	505
wTSrho	507
wViscosity	508
wZ	509
Г68fromТ90	510
Г90fromT48	511
Г90fromT68	512
ail.oce	513
hreenum	513
idedata	514
idem	515
idem-class	519
idemAstron	519
idemVuf	
itleCase	521
oEnu	521
oEnuAdp	
oEnuAdv	523
opo-class	524
opoInterpolate	524
opoWorld	525
rimString	
ınabbreviate Year	
ındriftTime	
ınduplicateNames	
ıngrid	529
ınitFromString	
ınitFromStringRsk	
ınwrapAngle	
seHeading	
ısrLonLat	
ıtm2lonlat	
vectorShow	
velocityStatistics	
vebtide	537
vind	
vindow.oce	
vindrose-class	
voceNames2oceNames	
voceUnit2oceUnit	
vrite.ctd	
xyzToEnu	
xyzToEnuAdp	
xyzToEnuAdv	
[,adp-method	
[,adv-method	550

Rι	opics	documented	!
----	-------	------------	---

[,amsr-method	
[,argo-method	
[,bremen-method	
[,cm-method	
[,coastline-method	
[,ctd-method	560
[,echosounder-method	563
[,g1sst-method	564
[,gps-method	566
[,ladp-method	567
[,landsat-method	569
[,lisst-method	570
[,lobo-method	571
[,met-method	573
[,oce-method	574
[,odf-method	575
[,rsk-method	576
[,sealevel-method	577
[,section-method	579
[,tidem-method	581
[,topo-method	582
[,windrose-method	584
[<-,adp-method	585
[<-,adv-method	586
[<-,amsr-method	588
[<-,argo-method	589
[<-,bremen-method	591
[<-,cm-method	592
<pre>[&lt;-,coastline-method</pre>	593
[<-,ctd-method	594
[<-,echosounder-method	596
[<-,g1sst-method	597
[<-,gps-method	598
[<-,lisst-method	599
[<-,lobo-method	600
[<-,met-method	601
[<-,oce-method	603
[<-,odf-method	604
[<-,rsk-method	605
[<-,sealevel-method	606
[<-,section-method	607
[<-,tidem-method	609
[<-,topo-method	610
<pre>[&lt;-,windrose-method</pre>	611

12 addColumn

# Description

Abbreviate a vector of times by removing commonalities (e.g. year)

# Usage

```
abbreviateTimeLabels(t, ...)
```

## **Arguments**

t vector of times.

... optional arguments passed to the format, e.g. format.

## Value

None.

## Author(s)

Dan Kelley, with help from Clark Richards

## See Also

This is used by various functions that draw time labels on axes, e.g. plot, adp-method.

addColumn

Add a Column to the Data Slot of an Oce object [deprecated]

## **Description**

**WARNING:** This function will be removed soon; see oce-deprecated. Use oceSetData instead of the present function.

# Usage

```
addColumn(x, data, name)
```

# **Arguments**

x A ctd object, e.g. as read by read.ctd.

data the data. The length of this item must match that of the existing data entries in

the data slot).

name the name of the column.

adp 13

## Value

An object of class oce, with a new column.

## Author(s)

Dan Kelley

## See Also

Please use oceSetData instead of the present function.

Other functions that will be removed soon: ctdAddColumn, ctdUpdateHeader, mapMeridians, mapZones, oce.as.POSIXlt

adp

ADP (acoustic-doppler profiler) dataset

## **Description**

This is degraded subsample of measurements that were made with an upward-pointing ADP manufactured by Teledyne-RDI, as part of the St Lawrence Internal Wave Experiment (SLEIWEX).

#### Usage

data(adp)

## Source

This file came from the SLEIWEX-2008 experiment.

#### See Also

Other datasets provided with oce: adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

#### **Examples**

```
## Not run:
library(oce)
data(adp)

# Velocity components. (Note: we should probably trim some bins at top.)
plot(adp)

# Note that tides have moved the mooring.
plot(adp, which=15:18)

## End(Not run)
```

adp-class

Class to Hold ADP (ADCP) Data

## **Description**

This class stores data from acoustic Doppler profilers. Some manufacturers call these ADCPs, while others call them ADPs; here the shorter form is used by analogy to ADVs.

#### **Details**

The metadata slot contains various items relating to the dataset, including source file name, sampling rate, velocity resolution, velocity maximum value, and so on. Some of these are particular to particular instrument types, and prudent researchers will take a moment to examine the whole contents of the metadata, either in summary form (with str(adp[["metadata"]])) or in detail (with adp[["metadata"]]). Perhaps the most useful general properties are adp[["bin1Distance"]] (the distance, in metres, from the sensor to the bottom of the first bin), adp[["cellSize"]] (the cell height, in metres, in the vertical direction, *not* along the beam), and adp[["beamAngle"]] (the angle, in degrees, between beams and an imaginary centre line that bisects all beam pairs).

The diagram provided below indicates the coordinate-axis and beam-numbering conventions for three- and four-beam ADP devices, viewed as though the reader were looking towards the beams being emitted from the transducers.

The bin geometry of a four-beam profiler is illustrated below, for adp[["beamAngle"]] equal to 20 degrees, adp[["bin1Distance"]] equal to 2m, and adp[["cel1Size"]] equal to 1m. In the diagram, the viewer is in the plane containing two beams that are not shown, so the two visible beams are separated by 40 degrees. Circles indicate the centres of the range-gated bins within the beams. The lines enclosing those circles indicate the coverage of beams that spread plus and minus 2.5 degrees from their centreline.

Note that adp[["oceCoordinate"]] stores the present coordinate system of the object, and it has possible values "beam", "xyz", "sfm" or "enu". (This should not be confused with adp[["originalCoordinate"]], which stores the coordinate system used in the original data file.)

The data slot holds some standardized items, and many that vary from instrument to instrument. One standard item is adp[["v"]], a three-dimensional numeric array of velocities in m/s. In this

matrix, the first index indicates time, the second bin number, and the third beam number. The meaning of beams number depends on whether the object is in beam coordinates, frame coordinates, or earth coordinates. For example, if in earth coordinates, then beam 1 is the eastward component of velocity. Thus, for example,

```
library(oce)
data(adp)
t <- adp[['time']]
d <- adp[['distance']]
eastward <- adp[['v']][,,1]
imagep(t, d, eastward, missingColor="gray")</pre>
```

plots an image of the eastward component of velocity as a function of time (the x axis) and distance from sensor (y axis), since the adp dataset is in earth coordinates. Note the semidurnal tidal signal, and the pattern of missing data at the ocean surface (gray blotches at the top).

Corresponding to the velocity array are two arrays of type raw, and identical dimension, accessed by adp[["a"]] and adp[["q"]], holding measures of signal strength and data quality quality, respectively. (The exact meanings of these depend on the particular type of instrument, and it is assumed that users will be familiar enough with instruments to know both the meanings and their practical consequences in terms of data-quality assessment, etc.)

In addition to the arrays, there are time-based vectors. The vector adp[["time"]] (of length equal to the first index of adp[["v"]], etc.) holds times of observation. Depending on type of instrument and its configuration, there may also be corresponding vectors for sound speed (adp[["soundSpeed"]]), pressure (adp[["pressure"]]), temperature (adp[["temperature"]]), heading (adp[["heading"]]) pitch (adp[["pitch"]]), and roll (adp[["roll"]]), depending on the setup of the instrument.

The precise meanings of the data items depend on the instrument type. All instruments have v (for velocity), q (for a measure of data quality) and a (for a measure of backscatter amplitude, also called echo intensity). Teledyne-RDI profilers have an additional item g (for percent-good).

VmDas-equipped Teledyne-RDI profilers additional navigation data, with details listed in the table below; note that the RDI documentation [2] and the RDI gui use inconsistent names for most items.

DDI daa nama

DDI CIII nama

Oce name	RDI doc name	RDI GUI name
avgSpeed	Avg Speed	Speed/Avg/Mag
avgMagnitudeVelocityEast	Avg Mag Vel East	?
avgMagnitudeVelocityNorth	Avg Mag Vel North	?
avgTrackMagnetic	Avg Track Magnetic	Speed/Avg/Dir (?)
avgTrackTrue	Avg Track True	Speed/Avg/Dir (?)
avgTrueVelocityEast	Avg True Vel East	?
avgTrueVelocityNorth	Avg True Vel North	?
directionMadeGood	Direction Made Good	Speed/Made Good/Dir
firstLatitude	First latitude	Start Lat
firstLongitude	First longitude	Start Lon
firstTime	UTC Time of last fix	End Time
lastLatitude	Last latitude	End Lat
lastLongitude	Last longitude	End Lon
lastTime	UTC Time of last fix	End Time
numberOfHeadingSamplesAveraged	Number heading samples averaged	?

numberOfMagneticTrackSamplesAveraged	Number of magnetic track samples averaged	?
numberOfPitchRollSamplesAvg	Number of magnetic track samples averaged	?
numberOfSpeedSamplesAveraged	Number of speed samples averaged	?
numberOfTrueTrackSamplesAvg	Number of true track samples averaged	?
primaryFlags	Primary Flags	?
shipHeading	Heading	?
shipPitch	Pitch	?
shipRoll	Roll	?
speedMadeGood	Speed Made Good	Speed/Made Good/Mag
speedMadeGoodEast	Speed MG East	?
speedMadeGoodNorth	Speed MG North	?

For Teledyne-RDI profilers, there are four three-dimensional arrays holding beamwise data. In these, the first index indicates time, the second bin number, and the third beam number (or coordinate number, for data in xyz, sfm, enu or other coordinate systems). In the list below, the quoted phrases are quantities as defined in Figure 9 of reference 1.

- v is "velocity" in m/s, inferred from two-byte signed integer values (multiplied by the scale factor that is stored in velocityScale in the metadata).
- q is "correlation magnitude" a one-byte quantity stored as type raw in the object. The values may range from 0 to 255.
- a is "backscatter amplitude", also known as "echo intensity" a one-byte quantity stored as type raw in the object. The values may range from 0 to 255.
- g is "percent good" a one-byte quantity stored as raw in the object. The values may range from 0 to 100.

Finally, there is a vector adp[["distance"]] that indicates the bin distances from the sensor, measured in metres along an imaginary centre line bisecting beam pairs. The length of this vector equals dim(adp[["v"]])[2].

The processingLog slot is in standard form and needs little comment.

## Teledyne-RDI Sentinel V ADCPs

As of 2016-09-27 there is provisional support for the TRDI "SentinelV" ADCPs, which are 5 beam ADCPs with a vertical centre beam. Relevant vertical beam fields are called adp[["vv"]], adp[["vq"]], adp[["vq"]], and adp[["vg"]] in analogy with the standard 4-beam fields.

## Accessing and altering information within adp-class objects

Extracting values Matrix data may be accessed as illustrated above, e.g. or an adp object named adv, the data are provided by adp[["v"]], adp[["a"]], and adp[["q"]]. As a convenience, the last two of these can be accessed as numeric (as opposed to raw) values by e.g. adp[["a", "numeric"]]. The vectors are accessed in a similar way, e.g. adp[["heading"]], etc. Quantities in the metadata slot are also available by name, e.g. adp[["velocityResolution"]], etc.

Assigning values. This follows the standard form, e.g. to increase all velocity data by 1 cm/s, use adp[["v"]] < -0.01 + adp[["v"]].

Overview of contents The show method (e.g. show(d)) displays information about an ADP object named d.

## Dealing with suspect data

There are many possibilities for confusion with adp devices, owing partly to the flexibility that manufacturers provide in the setup. Prudent users will undertake many tests before trusting the details of the data. Are mean currents in the expected direction, and of the expected magnitude, based on other observations or physical constraints? Is the phasing of currents as expected? If the signals are suspect, could an incorrect scale account for it? Could the transformation matrix be incorrect? Might the data have exceeded the maximum value, and then "wrapped around" to smaller values? Time spent on building confidence in data quality is seldom time wasted.

#### References

- 1. Teledyne-RDI, 2007. WorkHorse commands and output data format. P/N 957-6156-00 (November 2007).
- 2. Teledyne-RDI, 2012. VmDas User's Guide, Ver. 1.46.5.

#### See Also

A file containing ADP data is usually recognized by Oce, and so read.oce will usually read the data. If not, one may use the general ADP function read.adp or specialized variants read.adp.rdi, read.adp.nortek or read.adp.sontek.serial.

ADP data may be plotted with plot, adp-method, which is a generic function so it may be called simply as plot.

Statistical summaries of ADP data are provided by the generic function summary, while briefer overviews are provided with show.

Conversion from beam to xyz coordinates may be done with beamToXyzAdp, and from xyz to enu (east north up) may be done with xyzToEnuAdp. toEnuAdp may be used to transfer either beam or xyz to enu. Enu may be converted to other coordinates (e.g. aligned with a coastline) with enuToOtherAdp.

Other classes provided by oce: adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to adp data: [[,adp-method, [[<-,adp-method, adpEnsembleAverage, adp, as.adp, beamName, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

adpEnsembleAverage

Ensemble Average an ADP Object in Time

#### **Description**

Ensemble averaging of adp objects is often necessary to reduce the uncertainty in velocity estimates from single pings. Many types of ADPs can be configured to perform the ensemble averaging during the data collection, due to memory limitations for long deployments. In cases where the instrument is not memory limited, it may be desirable to perform the ensemble averaging during post-processing, thereby reducing the overall size of the data set and decreasing the uncertainty of the velocity estimates (by averaging out Doppler noise).

## Usage

```
adpEnsembleAverage(x, n = 5, leftover = FALSE, na.rm = TRUE, ...)
```

## Arguments

x an adp object, i.e. one inheriting from adp-class.

n number of pings to average together.

leftover a logical value indicating how to proceed in cases where n does not divide evenly

into the number of ensembles in x. If leftover is FALSE (the default) then any extra ensembles at the end of x are ignored. Otherwise, they are used to create a

final ensemble in the returned value.

na.rm a logical value indicating whether NA values should be stripped before the com-

putation proceeds

... extra arguments to be passed to the mean() function.

#### Value

A reduced object of adp-class with ensembles averaged as specified. E.g. for an adp object with 100 pings and n=5 the number of rows of the data arrays will be reduced by a factor of 5.

## Author(s)

Clark Richards and Dan Kelley

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adp, as.adp, beamName, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.adp.method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

adv 19

## **Examples**

```
library(oce)
data(adp)
adpAvg <- adpEnsembleAverage(adp, n=2)
plot(adpAvg)</pre>
```

adv

ADV (acoustic-doppler velocimeter) dataset

## **Description**

This adv-class object is a sampling of measurements made with a Nortek Vector acoustic Doppler velocimeter deployed as part of the St Lawrence Internal Wave Experiment (SLEIWEX). Various identifying features have been redacted.

## Usage

```
data(adv)
```

#### **Source**

This file came from the SLEIWEX-2008 experiment.

## See Also

```
Other datasets provided with oce: adp, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to adv data: [[,adv-method, [[<-,adv-method,adv-class, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot,adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset,adv-method, summary,adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu
```

## **Examples**

```
## Not run:
library(oce)
data(adv)

# Velocity time-series
plot(adv)

# Spectrum of upward component of velocity, with ``turbulent'' reference line
s <- spectrum(adv[["v"]][,3],plot=FALSE)
plot(log10(s$freq), log10(s$spec), type='l')
for (a in seq(-20, 20, by=1))
    abline(a=a, b=-5/3, col='gray', lty='dotted')</pre>
```

20 adv-class

## End(Not run)

adv-class

Class to Hold adv Data

#### **Description**

This class holds data from acoustic-Doppler velocimeters.

#### **Details**

The metadata slot contains various items relating to the dataset, including source file name, sampling rate, velocity resolution and scale, etc. The processingLog is in standard form and needs little comment. The data slot holds a numeric matrix v of velocities in m/s, with the first index indicating time and the second indicating beam number. The meanings of the beams depends on whether the object is in beam coordinates, frame coordinates, or earth coordinates. The data slot also contains identically-dimensioned raw matrices a and q, holding measures of signal strength and data quality quality, respectively. It also contains a series of vectors, e.g. time, temperature and pressure, etc., depending on what sensors are included in the package. For all of these quantities, the details can be different for different instrument types, and it is assumed that the user will be familiar with the details.

Data may be extracted with [[, adv-method and inserted with [[<-, adv-method. Type?"[[, adv-method" or ?"[[<-, adv-method" to learn more.

#### See Also

A file containing ADV data is usually recognized by Oce, and so read.oce will usually read the data. If not, one may use the general ADV function read.adv or specialized variants read.adv.nortek, read.adv.sontek.adr or read.adv.sontek.text.

ADV data may be plotted with plot, adv-method function, which is a generic function so it may be called simply as plot(x), where x is an object inheriting from adv-class.

Statistical summaries of ADV data are provided by the generic function summary, adv-method.

Conversion from beam to xyz coordinates may be done with beamToXyzAdv, and from xyz to enu (east north up) may be done with xyzToEnuAdv. toEnuAdv may be used to transfer either beam or xyz to enu. Enu may be converted to other coordinates (e.g. aligned with a coastline) with enuToOtherAdv.

Other classes provided by oce: adp-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

airRho 21

## **Examples**

```
data(adv)  adv[["v"]] <- \ 0.001 \ + \ adv[["v"]] \ \# \ add \ 1mm/s \ to \ all \ velocity \ components
```

airRho

Air density

## **Description**

Compute,  $\rho$ , the *in-situ* density of air.

## Usage

```
airRho(temperature, pressure, humidity)
```

## Arguments

temperature

*in-situ* temperature [°C]

pressure

pressure in Pa (NOT kPa) - ignored at present

humidity

ignored at present

## **Details**

This will eventually be a proper equation of state, but for now it's just returns something from wikipedia (i.e. not trustworthy), and not using humidity.

## Value

*In-situ* air density [kg/m<sup>3</sup>].

## Author(s)

Dan Kelley

## References

National Oceanographic and Atmospheric Agency, 1976. U.S. Standard Atmosphere, 1976. NOAA-S/T 76-1562. (A PDF of this document may be available at http://ntrs.nasa.gov/archive/nasa/casi.ntrs.nasa.gov/orhttp://www.dtic.mil/cgi-bin/GetTRDoc?Location=U2&doc=GetTRDoc.pdf&AD=ADA035728 although neither link has proven to be reliable.)

# Examples

```
degC <- seq(0,30,length.out=100)
p <- seq(98,102,length.out=100) * 1e3
contour(x=degC, y=p, z=outer(degC,p,airRho), labcex=1)</pre>
```

22 amsr-class

amsr-class

Class to Hold amsr Data

#### **Description**

The Advanced Microwave Scanning Radiometer (AMSR-2) is in current operation on the Japan Aerospace Exploration Agency (JAXA) GCOM-W1 space craft, launched in May 2012. Data are processed by Remote Sensing Systems. The satellite completes an ascending and descending pass during local daytime and nighttime hours respectively. Each daily file contains 7 daytime and 7 nighttime maps of variables named as follows within the data slot of amsr objects: timeDay, SSTDay, LFwindDay (wind at 10m sensed in the 10.7GHz band), MFwindDay (wind at 10m sensed at 18.7GHz), vaporDay, cloudDay, and rainDay, along with similarly-named items that end in Night. See [1] for additional information on the instrument, how to cite the data source in a paper, etc.

#### **Details**

The bands are stored in raw form, to save storage. The accessor function [[, amsr-method can provide these values in raw form or in physical units; plot, amsr-method, and summary, amsr-method work with physical units.

## Author(s)

Dan Kelley and Chantelle Layton

#### References

- 1. Information on the satellite, how to cite the data, etc. is provided at <a href="http://www.remss.com/missions/amsr/">http://www.remss.com/missions/amsr/</a>.
- 2. A simple interface for viewing and downloading data is at http://images.remss.com/amsr/amsr2\_data\_daily.html.

#### See Also

landsat-class for handling data from the Landsat-8 satellite.

Other things related to amsr data: [[<-,amsr-method,composite,amsr-method,download.amsr,plot,amsr-method,read.amsr,subset,amsr-method,summary,amsr-method

angleRemap 23

angleRemap

Convert angles from 0:360 to -180:180

# Description

This is mostly used for instrument heading angles, in cases where the instrument is aligned nearly northward, so that small variations in heading (e.g. due to mooring motion) can yield values that swing from small angles to large angles, because of the modulo-360 cut point. The method is to use the cosine and sine of the angle in order to find "x" and "y" values on a unit circle, and then to use atan2 to infer the angles.

## Usage

```
angleRemap(theta)
```

## **Arguments**

theta

an angle (in degrees) that is in the range from 0 to 360 degrees

## Value

A vector of angles, in the range -180 to 180.

## Author(s)

Dan Kelley

## **Examples**

```
library(oce)
## fake some heading data that lie near due-north (0 degrees)
n <- 20
heading <- 360 + rnorm(n, sd=10)
heading <- ifelse(heading > 360, heading - 360, heading)
x <- 1:n
plot(x, heading, ylim=c(-10, 360), type='l', col='lightgray', lwd=10)
lines(x, angleRemap(heading))</pre>
```

applyMagneticDeclination

Earth magnetic declination

## **Description**

Instruments that use magnetic compasses to determine current direction need to have corrections applied for magnetic declination, to get currents with the y component oriented to geographic, not magnetic, north. Sometimes, and for some instruments, the declination is specified when the instrument is set up, so that the velocities as recorded are already. Other times, the data need to be adjusted. This function is for the latter case.

## Usage

```
applyMagneticDeclination(x, declination = 0, debug = getOption("oceDebug"))
```

# **Arguments**

x an oce object.

declination magnetic declination (to be added to the heading)

debug a debugging flag, set to a positive value to get debugging.

## Value

Object, with velocity components adjusted to be aligned with geographic north and east.

## Author(s)

Dan Kelley

## References

```
'https://www.ngdc.noaa.gov/IAGA/vmod/igrf.html'
```

#### See Also

Use magneticField to determine the declination, inclination and intensity at a given spot on the world, at a given time.

Other things related to magnetism: magneticField

approx3d 25

approx3d	Trilinear interpolation in a 3D array
----------	---------------------------------------

## **Description**

Interpolate within a 3D array, using the trilinear approximation.

## Usage

```
approx3d(x, y, z, f, xout, yout, zout)
```

## **Arguments**

X	vector of x values for grid (must be equi-spaced)
у	vector of y values for grid (must be equi-spaced)
z	vector of z values for grid (must be equi-spaced)
f	matrix of rank 3, with the gridd values mapping to the x values (first index of f), etc.
xout	vector of x values for output.
yout	vector of y values for output (length must match that of xout).
zout	vector of z values for output (length must match that of xout).

## **Details**

Trilinear interpolation is used to interpolate within the f array, for those (xout, yout and zout) triplets that are inside the region specified by x, y and z. Triplets that lie outside the range of x, y or z result in NA values.

## Value

A vector of interpolated values (or NA values), with length matching that of xout.

## Author(s)

Dan Kelley and Clark Richards

# **Examples**

```
## set up a grid
library(oce)
n <- 5
x <- seq(0, 1, length.out=n)
y <- seq(0, 1, length.out=n)
z <- seq(0, 1, length.out=n)
f <- array(1:n^3, dim=c(length(x), length(y), length(z)))
## interpolate along a diagonal line
m <- 100</pre>
```

26 argo

```
xout <- seq(0, 1, length.out=m)
yout <- seq(0, 1, length.out=m)
zout <- seq(0, 1, length.out=m)
approx <- approx3d(x, y, z, f, xout, yout, zout)
## graph the results
plot(xout, approx, type='l')
points(xout[1], f[1, 1, 1])
points(xout[m], f[n,n,n])</pre>
```

argo

ARGO float dataset

## **Description**

This holds data from ARGO 6900388 in the North Atlantic.

#### Details

To quote Argo's website: "These data were collected and made freely available by the International Argo Program and the national programs that contribute to it. (http://www.argo.ucsd.edu, http://argo.jcommops.org). The Argo Program is part of the Global Ocean Observing System."

Below is the official citation (note that this DOI has web links for downloads): Argo (2017). Argo float data and metadata from Global Data Assembly Centre (Argo GDAC) - Snapshot of Argo GDAC of July, 8st 2017. SEANOE. http://doi.org/10.17882/42182#50865

## Source

This file was downloaded using the unix command

```
ftp ftp://ftp.ifremer.fr/ifremer/argo/dac/bodc/6900388/6900388_prof.nc
issued on 2017 July 7.
```

## See Also

Other datasets provided with oce: adp, adv, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, as.argo, handleFlags,argo-method, plot,argo-method, read.argo, subset,argo-method, summary,argo-method

argo-class 27

## **Examples**

```
## Not run:
library(oce)
data(argo)
summary(argo)
data(coastlineWorld)
plot(argo, which="trajectory", coastline=coastlineWorld)
## End(Not run)
```

argo-class

Class to hold Argo data

## **Description**

This class stores data from argo floats.

## **Details**

An argo object may be read with read.argo or created with as.argo. Argo data can be gridded to constant pressures with argoGrid. Plots can be made with plot,argo-method, while summary,argo-method produces statistical summaries and show produces overviews. The usual oce generic functions are available, e.g. [[,argo-method may be used to extract data, and [[<-,argo-method may be used to insert data.

See <a href="http://www.argo.ucsd.edu/Gridded\_fields.html">http://www.argo.ucsd.edu/Gridded\_fields.html</a> for some argo-related datasets that may be useful in a wider context.

## Author(s)

Dan Kelley and Clark Richards

## See Also

Other classes provided by oce: adp-class, adv-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to argo data: [[,argo-method,[[<-,argo-method,argoGrid,argoNames2oceNames,argo,as.argo,handleFlags,argo-method,plot,argo-method,read.argo,subset,argo-method,summary,argo-method

28 argoGrid

argoGrid	Grid Argo float data

## **Description**

Grid an Argo float, by interpolating to fixed pressure levels. The gridding is done with approx. If there is sufficient user demand, other methods may be added, by analogy to sectionGrid.

## Usage

```
argoGrid(argo, p, debug = getOption("oceDebug"), ...)
```

## **Arguments**

argo	A argo object to be gridded.
p	Optional indication of the pressure levels to which interpolation should be done. If this is not supplied, the pressure levels will be calculated based on the existing values, using medians. If p="levitus", then pressures will be set to be those of the Levitus atlas, given by standardDepths, trimmed to the maximum pressure in argo. If p is a single numerical value, it is taken as the number of subdivisions to use in a call to seq that has range from 0 to the maximum pressure in argo. Finally, if a vector numerical values is provided, then it is used as is.
debug	A flag that turns on debugging. Higher values provide deeper debugging.
	Optional arguments to approx, which is used to do the gridding.

## Value

An object of argo-class that contains a pressure matrix with constant values along the first index.

## A note about flags

Data-quality flags contained within the original object are ignored by this function, and the returned value contains no such flags. This is because such flags represent an assessment of the original data, not of quantities derived from those data. This function produces a warning to this effect. The recommended practice is to use handleFlags or some other means to deal with flags before calling the present function.

## Author(s)

Dan Kelley and Clark Richards

## See Also

Other things related to argo data: [[,argo-method,[[<-,argo-method,argo-class,argoNames2oceNames,argo,as.argo,handleFlags,argo-method,plot,argo-method,read.argo,subset,argo-method,summary,argo-method

argoNames2oceNames 29

#### **Examples**

```
library(oce)
data(argo)
g <- argoGrid(argo, p=seq(0, 100, 1))
par(mfrow=c(2,1))
t <- g[["time"]]
z <- -g[["pressure"]][,1]
## Set zlim because of spurious temperatures.
imagep(t, z, t(g[['temperature']]), ylim=c(-100,0), zlim=c(0,20))
imagep(t, z, t(g[['salinity']]), ylim=c(-100,0))</pre>
```

argoNames2oceNames

Convert Argo Data Name to Oce Name

## Description

This function is used internally by read.argo to convert Argo-convention data names to oce-convention names. Users should not call this directly, since its return value may be changed at any moment (e.g. to include units as well as names).

## Usage

```
argoNames2oceNames(names, ignore.case = TRUE)
```

## **Arguments**

names vector of character strings containing names in the Argo convention.

ignore.case a logical value passed to gsub, indicating whether to ignore the case of input

strings. The default is set to TRUE because some data files use lower-case names,

despite the fact that the Argo documentation specifies upper-case.

## **Details**

The inference of names was done by inspection of some data files, using [1] as a reference. It should be noted, however, that the data files examined contain some names that are not undocumented in [1], and others that are listed only in its changelog, with no actual definitions being given. For example, the files had six distinct variable names that seem to relate to phase in the oxygen sensor, but these are not translated by the present function because these variable names are not defined in [1], or not defined uniquely in [2].

The names are converted with gsub, using the ignore.case argument of the present function. The procedure is to first handle the items listed in the following table, with string searches anchored to the start of the string. After that, the qualifiers \_ADJUSTED, \_ERROR and \_QC, are translated to Adjusted, Error, and QC, respectively.

Argo nameoce nameBBPbbp

BETA\_BACKSCATTERING betaBackscattering

BPHASE\_OXY bphase0xygen

CDOM CDOM

CNDC conductivity
CHLA chlorophyllA
CP beamAttenuation
CYCLE\_NUMBER cycleNumber
DATA\_CENTRE dataCentre
DATA\_MODE dataMode

DATA\_STATE\_INDICATOR dataStateIndicator

DC\_REFERENCE DCReference
DIRECTION direction

DOWN\_IRRADIANCE downwellingIrradiance

DOWNWELLING\_PAR downwellingPAR
FIRMWARE\_VERSION firmwareVersion
FIT\_ERROR\_NITRATE fitErrorNitrate
FLUORESCENCE\_CDOM fluorescenceCDOM

FLUORESCENCE\_CHLA fluorescenceChlorophyllA

INST\_REFERENCE instReference

JULD juld (and used to compute time)

JULD\_QC\_LOCATION juldQCLocation
LATITUDE latitude
LONGITUDE longitude

MOLAR\_DOXY oxygenUncompensated

PH\_IN\_SITU\_FREE pHFree
PH\_IN\_SITU\_TOTAL pH
PI\_NAME PIName
PLATFORM\_NUMBER id

POSITION\_ACCURACY positionAccuracy POSITIONING\_SYSTEM positioningSystem

PROFILE profile PROJECT\_NAME projectName

RAW\_DOWNWELLING\_IRRADIANCE rawDownwellingIrradiance
RAW\_DOWNWELLING\_PAR rawDownwellingPAR
RAW\_UPWELLING\_RADIANCE rawUpwellingRadiance
STATION\_PARAMETERS stationParameters

TEMP temperature

TEMP\_CPU\_CHLA temperatureCPUChlorophyllA

TEMP\_DOXY temperatureOxygen
TEMP\_NITRATE temperatureNitrate
TEMP\_PH temperaturePH

 ${\tt TEMP\_SPECTROPHOTOMETER\_NITRATE} \quad temperature Spectrophotometer Nitrate$ 

TILT tilt turbidity

UP\_RADIANCE upwellingRadiance UV\_INTENSITY UVIntensity

UV\_INTENSITY\_DARK\_NITRATE UVIntensityDarkNitrate UV\_INTENSITY\_NITRATE UVIntensityNitrate

argShow 31

VRS_PH	VRSpH
WMO_INST_TYPE	WMOInstType

#### Value

A character vector of the same length as names, but with replacements having been made for all known quantities.

#### References

- 1. Argo User's Manual Version 3.2, Dec 29th, 2015, available at https://archimer.ifremer.fr/doc/00187/29825/40575.pdf (but note that this is a draft; newer versions may have replaced this by now).
- 2. Argo list of parameters in an excel spreadsheet, available at https://www.argodatamgt.org/content/download/27444 (but note that the certificate at this website was noticed to be invalid on December 17, 2016, so exercise caution in downloading the file).

## See Also

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argo, as.argo, handleFlags, argo-method, plot, argo-method, read.argo, subset, argo-method, summary, argo-method

argShow

Show an argument to a function, e.g. for debugging

# Description

Show an argument to a function, e.g. for debugging

# Usage

```
argShow(x, nshow = 2, last = FALSE, sep = "=")
```

## **Arguments**

X	the argument
nshow	number of values to show at first (if length( $x$ )> 1)
last	indicates whether this is the final argument to the function
sep	the separator between name and value

32 as.adp

as.adp	Create an ADP Object	

## **Description**

Create an ADP Object

## Usage

```
as.adp(time, distance, v, a = NULL, q = NULL, orientation = "upward",
  coordinate = "enu")
```

## **Arguments**

time	of observations in POSIXct format
distance	to centre of bins
V	array of velocities, with first index for time, second for bin number, and third for beam number
a	amplitude, a raw array with dimensions matching u
q	quality, a raw array with dimensions matching u
orientation	a string indicating sensor orientation, e.g. "upward" and "downward"
coordinate	a string indicating the coordinate system, "enu", "beam", "xy", or "other"

## **Details**

Construct an object of adp-class. Only a basic subset of the typical data slot is represented in the arguments to this function, on the assumption that typical usage in reading data is to set up a nearly-blank adp-class object, the data slot of which is then inserted. However, in some testing situations it can be useful to set up artificial adp objects, so the other arguments may be useful.

## Value

An object of adp-class.

## Author(s)

Dan Kelley

## See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, beamName, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

as.argo 33

## **Examples**

```
data(adp)
t <- adp[["time"]]
d <- adp[["distance"]]
v <- adp[["v"]]
a <- as.adp(time=t, distance=d, v=v)
## Not run:
plot(a)
## End(Not run)</pre>
```

as.argo

Coerce Data Into an Argo Dataset

# Description

Coerce a dataset into an argo dataset. This is not the right way to read official argo datasets, which are provided in NetCDF format and may be read with read.argo.

## Usage

```
as.argo(time, longitude, latitude, salinity, temperature, pressure,
  units = NULL, id, filename = "", missingValue)
```

## **Arguments**

vector of POSIXct times. time longitude vector of longitudes. latitude vector of latitudes. salinity vector of salinities. vector of temperatures. temperature vector of pressures. pressure units optional list containing units. If NULL, the default, then "degree east" is used for longitude, "degree north" for latitude, "" for salinity, "ITS-90" for temperature, and "dbar" for pressure. id identifier. filename source filename.

Optional missing value, indicating data values that should be taken as NA.

## Value

An object of argo-class.

missingValue

34 as.cm

## Author(s)

Dan Kelley

#### See Also

The documentation for argo-class explains the structure of argo objects, and also outlines the other functions dealing with them.

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, handleFlags, argo-method, plot, argo-method, read.argo, subset, argo-method, summary, argo-method

as.cm

Coerce data into a CM object

# **Description**

Coerce data into a CM object

## Usage

```
as.cm(time, u = NULL, v = NULL, pressure = NULL, conductivity = NULL,
temperature = NULL, salinity = NULL, longitude = NA, latitude = NA,
filename = "", debug = getOption("oceDebug"))
```

# Arguments

time	A vector of times of observation, or an oce object that holds time, in addition to either both u and v, or both directionTrue and speedHorizontal.
u	either a numerical vector containing the eastward component of velocity, in m/s, or an oce object that can can be coerced into a cm object. In the second case, the other arguments to the present function are ignored.
V	vector containing the northward component of velocity in m/s.
pressure	vector containing pressure in dbar. Ignored if the first argument contains an oce object holding pressure.
conductivity	Optional vector of conductivity. Ignored if the first argument contains an oce object holding pressure.
temperature	Optional vector of temperature. Ignored if the first argument contains an oce object holding temperature
salinity	Optional vector of salinity, assumed to be Practical Salinity. Ignored if the first argument contains an oce object holding salinity
longitude	Optional longitude in degrees East. Ignored if the first argument contains an oce object holding longitude.
latitude	Latitude in degrees North. Ignored if the first argument contains an oce object holding latitude.

as.coastline 35

filename Optional source file name

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## See Also

Other things related to cm data: [[,cm-method,[[<-,cm-method,cm-class,cm,plot,cm-method,read.cm,subset,cm-method,summary,cm-method

as.coastline

Coerce Data into a Coastline Object

## Description

Coerces a sequence of longitudes and latitudes into a coastline dataset. This may be used when read.coastline cannot read a file, or when the data have been manipulated.

#### Usage

```
as.coastline(longitude, latitude, fillable = FALSE)
```

## **Arguments**

longitude the longitude in decimal degrees, positive east of Greenwich, or a data frame

with columns named latitude and longitude, in which case these values are

extracted from the data frame and the second argument is ignored.

latitude the latitude in decimal degrees, positive north of the Equator.

fillable boolean indicating whether the coastline can be drawn as a filled polygon.

## Value

An object of class "coastline" (for details, see read.coastline).

#### Author(s)

Dan Kelley

#### See Also

Other things related to coastline data: [[,coastline-method,[[<-,coastline-method,coastline-class,coastlineBest,coastlineCut,coastlineWorld,download.coastline,plot,coastline-method,read.coastline.openstreetmap,read.coastline.shapefile,subset,coastline-method,summary,coastline-method

36 as.ctd

as.ctd

Coerce data into CTD object

## **Description**

Assemble data into a ctd-class dataset.

#### **Usage**

```
as.ctd(salinity, temperature = NULL, pressure = NULL, conductivity = NULL,
    scan = NULL, time = NULL, other = NULL, units = NULL, flags = NULL,
    missingValue = NULL, type = "", serialNumber = "", ship = NULL,
    cruise = NULL, station = NULL, startTime = NULL, longitude = NULL,
    latitude = NULL, deploymentType = "unknown", pressureAtmospheric = 0,
    sampleInterval = NA, profile = NULL, debug = getOption("oceDebug"))
```

# Arguments

salinity

There are several distinct choices for salinity. (1) It can be a vector indicating the practical salinity through the water column. In that case, as.ctd employs the other arguments listed below. (2) it can be something (a data frame, a list or an oce object) from which practical salinity, temperature, pressure, and conductivity can be inferred. In this case, the relevant information is extracted and the other arguments to as.ctd are ignored, except for pressureAtmospheric. If the first argument has salinity, etc., in matrix form (as can happen with some objects of argo-class), then only the first column is used, and a warning to that effect is given, unless the profile argument is specified and then that specific profile is extracted. (3) It can be an object of rsk-class, (see "Converting rsk objects" for details). (4) It can be unspecified, in which case conductivity becomes a mandatory argument, because it will be needed for computing actual salinity, using swSCTp.

temperature

*in-situ* temperature [° degC], defined on the ITS-90 scale; see "Temperature units" in the documentation for swRho.

pressure

scan

Vector of pressure values, one for each salinity and temperature pair, or just a single pressure, which is repeated to match the length of salinity.

conductivity

electrical conductivity ratio through the water column (optional). To convert from raw conductivity in milliSeimens per centimeter divide by 42.914 to get

optional scan number. If not provided, this will be set to 1:length(salinity).

conductivity ratio (see Culkin and Smith, 1980).

time optional vector of times of observation

other optional list of other data columns that are not in the standard list

units an optional list containing units. If not supplied, defaults are set for pressure,

temperature, salinity, and conductivity. Since these are simply guesses,

users are advised strongly to supply units. See "Examples".

as.ctd 37

flags if supplied, this is a list containing data-quality flags. The elements of this list

must have names that match the data provided to the object.

missing Value optional missing value, indicating data that should be taken as NA. Set to NULL

to turn off this feature.

type optional type of CTD, e.g. "SBE" serialNumber optional serial number of instrument

ship optional string containing the ship from which the observations were made.

cruise optional string containing a cruise identifier. station optional string containing a station identifier.

startTime optional indication of the start time for the profile, which is used in some several

plotting functions. This is best given as a POSIXt time, but it may also be a character string that can be converted to a time with as.POSIXct, using UTC as

the timezone.

longitude optional numerical value containing longitude in decimal degrees, positive in the

eastern hemisphere. If this is a single number, then it is stored in the metadata slot of the returned value; if it is a vector of numbers, they are stored in data

and a mean value is stored in metadata.

latitude optional numerical value containing the latitude in decimal degrees, positive in

the northern hemisphere. See the note on length, for the longitude argument.

deploymentType character string indicating the type of deployment. Use "unknown" if this is

not known, "profile" for a profile (in which the data were acquired during a downcast, while the device was lowered into the water column, perhaps also including an upcast; "moored" if the device is installed on a fixed mooring, "thermosalinograph" (or "tsg") if the device is mounted on a moving vessel, to record near-surface properties, or "towyo" if the device is repeatedly lowered

and raised.

pressureAtmospheric

A numerical value (a constant or a vector), that is subtracted from pressure before storing it in the return value. (This altered pressure is also used in calculating salinity, if that is to be computed from conductivity, etc., using swSCTp

(see salinity above).

sampleInterval optional numerical value indicating the time between samples in the profile.

profile optional positive integer specifying the number of the profile to extract from an

object that has data in matrices, such as for some argo objects. Currently the

profile argument is only utilized for argo-class objects.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### Value

An object of ctd-class.

38 as.ctd

#### Converting rsk objects

If the salinity argument is an object of rsk-class, then as.ctd passes it, pressureAtmospheric, longitude, latitude ship, cruise, station and deploymentType to rsk2ctd, which builds the ctd object that is returned by as.ctd. The other arguments to as.ctd are ignored in this instance, because rsk objects already contain their information. If required, any data or metadata element can be added to the value returned by as.ctd using oceSetData or oceSetMetadata, respectively.

The returned rsk-class object contains pressure in a form that may need to be adjusted, because rsk objects may contain either absolute pressure or sea pressure. This adjustment is handled automatically by as.ctd, by examination of the metadata item named pressureType (described in the documentation for read.rsk). Once the sea pressure is determined, adjustments may be made with the pressureAtmospheric argument, although in that case it is better considered a pressure adjustment than the atmospheric pressure.

rsk-class objects may store sea pressure or absolute pressure (the sum of sea pressure and atmospheric pressure), depending on how the object was created with as.rsk or read.rsk. However, ctd-class objects store sea pressure, which is needed for plotting, calculating density, etc. This poses no difficulties, however, because as.ctd automatically converts absolute pressure to sea pressure, if the metadata in the rsk-class object indicates that this is appropriate. Further alteration of the pressure can be accomplished with the pressureAtmospheric argument, as noted above.

#### Author(s)

Dan Kelley

#### References

Culkin, F., and Norman D. Smith, 1980. Determination of the concentration of potassium chloride solution having the same electrical conductivity, at 15 C and infinite frequency, as standard seawater of salinity 35.0000 ppt (Chlorinity 19.37394 ppt). *IEEE Journal of Oceanic Engineering*, **5**, pp 22-23.

#### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

```
library(oce)
## 1. fake data, with default units
pressure <- 1:50
temperature <- 10 - tanh((pressure - 20) / 5) + 0.02*rnorm(50)
salinity <- 34 + 0.5*tanh((pressure - 20) / 5) + 0.01*rnorm(50)
ctd <- as.ctd(salinity, temperature, pressure)
# Add a new column
fluo <- 5 * exp(-pressure / 20)
ctd <- oceSetData(ctd, name="fluorescence", value=fluo,</pre>
```

as.echosounder 39

```
unit=list(unit=expression(mg/m^3), scale=""))
summary(ctd)

## 2. fake data, with supplied units (which are the defaults, actually)
ctd <- as.ctd(salinity, temperature, pressure,
    units=list(salinity=list(unit=expression(), scale="PSS-78"),
    temperature=list(unit=expression(degree*C), scale="ITS-90"),
    pressure=list(unit=expression(dbar), scale=""")))</pre>
```

as.echosounder

Coerce Data into an Echosounder Object

# Description

Coerces a dataset into a echosounder dataset.

## Usage

```
as.echosounder(time, depth, a, src = "", sourceLevel = 220, receiverSensitivity = -55.4, transmitPower = 0, pulseDuration = 400, beamwidthX = 6.5, beamwidthY = 6.5, frequency = 41800, correction = 0)
```

## **Arguments**

time times of pings

depth depths of samples within pings

a matrix of amplitudes

src optional string indicating data source

sourceLevel source level, in dB (uPa at 1m), denoted s1 in [1 p15], where it is in units 0.1dB (uPa at 1m)

receiverSensitivity

receiver sensivity of the main element, in dB(counts/uPa), denoted rs in [1 p15],

where it is in units of 0.1dB(counts/uPa)

transmitPower transmit power reduction factor, in dB, denoted tpow in [1 p10], where it is in

units 0.1 dB.

pulseDuration duration of transmitted pulse in us

beamwidthX x-axis -3dB one-way beamwidth in deg, denoted bwx in [1 p16], where the unit

is 0.2 deg

beamwidthY y-axis -3dB one-way beamwidth in deg, denoted bwx in [1 p16], where the unit

is 0.2 deg

frequency transducer frequency in Hz, denoted fq in [1 p16]

correction user-defined calibration correction in dB, denoted corr in [1 p14], where the

unit is 0.01dB.

40 as.gps

## **Details**

Creates an echosounder file. The defaults for e.g. transmitPower are taken from the echosounder dataset, and they are unlikely to make sense generally.

## Value

An object of class "echosounder"; for details of this data type, see echosounder-class).

## Author(s)

Dan Kelley

#### See Also

Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, echosounder-class, echosounder, findBottom, plot, echosounder-method, read.echosounder, subset, echosounder-method, summary, echosounder-method

as.gps

Coerce data into a GPS dataset

# Description

Coerces a sequence of longitudes and latitudes into a GPS dataset. This may be used when read.gps cannot read a file, or when the data have been manipulated.

# Usage

```
as.gps(longitude, latitude, filename = "")
```

#### **Arguments**

longitude the longitude in decimal degrees, positive east of Greenwich, or a data frame

with columns named latitude and longitude, in which case these values are

extracted from the data frame and the second argument is ignored.

latitude the latitude in decimal degrees, positive north of the Equator.

filename name of file containing data (if applicable).

# Value

An object of gps-class.

## Author(s)

Dan Kelley

as.ladp 41

## See Also

Other things related to gps data: [[,gps-method,[[<-,gps-method,gps-class,plot,gps-method,read.gps, summary,gps-method]

as.ladp

Coerce data into an ladp object

# Description

This function assembles vectors of pressure and velocity, possibly also with shears, salinity, temperature, etc.

# Usage

```
as.ladp(longitude, latitude, station, time, pressure, u, v, uz, vz, salinity, temperature, ...)
```

# Arguments

longitude longitude in degrees east, or an oce object that contains the data otherwise given by longitude and the other arguments. latitude latitude in degrees east (use negative in southern hemisphere). number or string indicating station ID. station time time at the start of the profile, constructed by e.g. as.POSIXct. pressure in decibars, through the water column. pressure eastward velocity (m/s). u northward velocity (m/s). vertical derivative of eastward velocity (1/s). 117

vz vertical derivative of northward velocity (1/s).
salinity salinity through the water column, in practical salinity units.

sammy amough the water column, in practical sammy amo

temperature through the water column.
... optional additional data columns.

#### Value

An object of ladp-class.

## Author(s)

Dan Kelley

#### See Also

 $Other\ things\ related\ to\ ladp\ data:\ \verb|[[],ladp-method,ladp-class,plot,ladp-method,summary,ladp-method]|$ 

42 as.lisst

Coerce Data Into a LISST Object

## **Description**

Coerce data into a lisst object If data contains fewer than 42 columns, an error is reported. If it contains more than 42 columns, only the first 42 are used. This is used by read.lisst, the documentation on which explains the meanings of the columns.

## Usage

```
as.lisst(data, filename = "", year = 0, tz = "UTC", longitude = NA,
  latitude = NA)
```

## **Arguments**

data	A table (or matrix) containing 42 columns, as in a LISST data file.
filename	Name of file containing the data.

year Year in which the first observation was made. This is necessary because LISST

timestamps do not indicate the year of observation. The default value is odd

enough to remind users to include this argument.

tz Timezone of observations. This is necessary because LISST timestamps do not

indicate the timezone.

longitude Longitude of observation.

Latitude Latitude of observation.

## Value

An object of lisst-class.

## Author(s)

Dan Kelley

## See Also

```
Other things related to lisst data: [[,lisst-method, [[<-,lisst-method, lisst-class, plot,lisst-method, read.lisst, summary,lisst-method
```

as.lobo 43

as.lobo	Coerce Data into a Lobo Obje	ect
45.1000	coerce Build uno a Bood Goje	

# Description

Coerce a dataset into a lobo dataset.

# Usage

```
as.lobo(time, u, v, salinity, temperature, pressure, nitrate, fluorescence,
  filename = "")
```

# Arguments

time	vector of times of observation
u	vector of x velocity component observations
V	vector of y velocity component observations
salinity	vector of salinity observations
temperature	vector of temperature observations
pressure	vector of pressure observations
nitrate	vector of nitrate observationss
fluorescence	vector of fluoresence observations

source filename

# Value

An object of lobo-class.

# Author(s)

Dan Kelley

filename

# See Also

Other things related to lobo data: [[,lobo-method,[[<-,lobo-method,lobo-class,lobo,plot,lobo-method,subset,lobo-method,summary,lobo-method]

44 as.met

as.met

Coerce Data into met Object

## **Description**

Coerces a dataset into a met dataset. This fills in only a few of the typical data fields, so the returned object is much sparser than the output from read.met. Also, almost no metadata fields are filled in, so the resultant object does not store station location, units of the data, data-quality flags, etc. Anyone working with data from Environment Canada [2] is advised to use read.met instead of the present function.

# Usage

```
as.met(time, temperature, pressure, u, v,
  filename = "(constructed from data)")
```

# **Arguments**

time Either a vector of observation times (or character strings that can be coerced into

times) or the output from canadaHCD::hcd\_hourly (see [1]).

temperature vector of temperatures.
pressure vector of pressures.

vector of eastward wind speed in m/s.vector of northward wind speed in m/s.filename optional string indicating data source

## Value

An object of met-class.

#### Author(s)

Dan Kelley

#### References

- 1. The canadaHCD package is in development by Gavin Simpson; see https://github.com/gavinsimpson/canadaHCD for instructions on how to download and install from GitHub.
- 2. Environment Canada website for Historical Climate Data <a href="http://climate.weather.gc.ca/index\_e.html">http://climate.weather.gc.ca/index\_e.html</a>

#### See Also

Other things related to met data: [[,met-method, [[<-,met-method, download.met, met-class, met, plot,met-method, read.met, subset,met-method, summary,met-method

as.oce 45

as.oce

Coerce Something Into an Oce Object

## **Description**

Coerce Something Into an Oce Object

## Usage

```
as.oce(x, ...)
```

## **Arguments**

x an item containing data. This may be data frame, list, or an oce object.

... optional extra arguments, passed to conversion functions as.coastline or ODF2oce, if these are used.

#### **Details**

This function is limited and not intended for common use. In most circumstances, users should employ a function such as as.ctd to construct specialized oce sub-classes.

as.oce creates an oce object from data contained within its first argument, which may be a list, a data frame, or an object of oce-class. (In the last case, x is simply returned, without modification.)

If x is a list containing items named longitude and latitude, then as.coastline is called (with the specified ... value) to create a coastline object.

If x is a list created by read\_odf from the (as yet unreleased) ODF package developed by the Bedford Institute of Oceanography, then ODF2oce is called (with no arguments other than the first) to calculate a return value. If the sub-class inference made by ODF2oce is incorrect, users should call that function directly, specifying a value for its coerce argument.

If x has not been created by read\_odf, then the names of the items it contains are examined, and used to try to infer the proper return value. There are only a few cases (although more may be added if there is sufficient user demand). The cases are as follows.

- If x contains items named temperature, pressure and either salinity or conductivity, then an object of type ctd-class will be returned.
- If x contains columns named longitude and latitude, but no other columns, then an object of class coastline-class is returned.

## Value

as.oce returns an object inheriting from oce-class.

46 as.rsk

as.rsk

Coerce Data Into a Rsk Object

## **Description**

Create a rsk object.

# Usage

```
as.rsk(time, columns, filename = "", instrumentType = "rbr",
   serialNumber = "", model = "", sampleInterval = NA,
   debug = getOption("oceDebug"))
```

## **Arguments**

time a vector of times for the data.

columns a list or data frame containing the measurements at the indicated times; see

"Details".

filename optional name of file containing the data.

instrumentType type of instrument.

serialNumber serial number for instrument.

model instrument model type, e.g. "RBRduo".

sampleInterval sampling interval. If given as NA, then this is estimated as the median difference

in times.

debug a flag that can be set to TRUE to turn on debugging.

#### **Details**

The contents of columns are be copied into the data slot of the returned object directly, so it is critical that the names and units correspond to those expected by other code dealing with rsk-class objects. If there is a conductivity, it must be called conductivity, and it must be in units of mS/cm. If there is a temperature, it must be called temperature, and it must be an in-situ value recorded in ITS-90 units. And if there is a pressure, it must be *absolute* pressure (sea pressure plus atmospheric pressure) and it must be named pressure. No checks are made within as.rsk on any of these rules, but if they are broken, you may expect problems with any further processing.

#### Value

```
An object of rsk-class "rsk".
```

# Author(s)

Dan Kelley

as.sealevel 47

#### See Also

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, plot,rsk-method, read.rsk, rsk-class, rskPatm, rskToc, rsk, subset,rsk-method, summary,rsk-method

as.sealevel

Coerce Data Into a Sealevel Object

## **Description**

Coerces a dataset (minimally, a sequence of times and heights) into a sealevel dataset. The arguments are based on the standard data format, as were described in a file formerly available at [1].

## Usage

```
as.sealevel(elevation, time, header = NULL, stationNumber = NA,
   stationVersion = NA, stationName = NULL, region = NULL, year = NA,
   longitude = NA, latitude = NA, GMTOffset = NA, decimationMethod = NA,
   referenceOffset = NA, referenceCode = NA, deltat)
```

# **Arguments**

elevation a list of sea-level heights in metres, in an hourly sequence.

time optional list of times, in POSIXct format. If missing, the list will be constructed

assuming hourly samples, starting at 0000-01-01 00:00:00.

header a character string as read from first line of a standard data file.

stationNumber three-character string giving station number.

stationVersion single character for version of station.

stationName the name of station (at most 18 characters).

region the name of the region or country of station (at most 19 characters).

year the year of observation.

longitude the longitude in decimal degrees, positive east of Greenwich.

the latitude in decimal degrees, positive north of the equator.

GMTOffset offset from GMT, in hours.

decimationMethod

a coded value, with 1 meaning filtered, 2 meaning a simple average of all sam-

ples, 3 meaning spot readings, and 4 meaning some other method.

referenceOffset

?

referenceCode

deltat optional interval between samples, in hours (as for the ts timeseries function).

If this is not provided, and t can be understood as a time, then the difference between the first two times is used. If this is not provided, and t cannot be

understood as a time, then 1 hour is assumed.

48 as.section

#### Value

```
An object of class "sealevel" (for details, see read. sealevel).
```

#### Author(s)

Dan Kelley

#### References

http://ilikai.soest.hawaii.edu/rqds/hourly.fmt (this link worked for years but failed at least temporarily on December 4, 2016).

#### See Also

The documentation for sealevel-class explains the structure of sealevel objects, and also outlines the other functions dealing with them.

Other things related to sealevel data: [[, sealevel-method, [[<-, sealevel-method, plot, sealevel-method, read. sealevel, sealevel-class, sealevelTuktoyaktuk, sealevel, subset, sealevel-method, summary, sealevel-method

## **Examples**

```
library(oce)

# Construct a year of M2 tide, starting at the default time
# 0000-01-01T00:00:00.
h <- seq(0, 24*365)
elevation <- 2.0 * sin(2*pi*h/12.4172)
sl <- as.sealevel(elevation)
summary(sl)

# As above, but start at the Y2K time.
time <- as.POSIXct("2000-01-01") + h * 3600
sl <- as.sealevel(elevation, time)
summary(sl)</pre>
```

as.section

Create a Section

## **Description**

Create a section based on columnar data, or a set of oce-class objects that can be coerced to a section. There are three cases.

Case 1. If the first argument is a numerical vector, then it is taken to be the salinity, and factor is applied to station to break the data up into chunks that are assembled into ctd-class objects with as.ctd and combined to make a section-class object to be returned. This mode of operation is provided as a convenience for datasets that are already partly processed; if original CTD data are

as.section 49

available, the next mode is preferred, because it permits the storage of much more data and metadata in the CTD object.

Case 2. If the first argument is a list containing oce objects, then those objects are taken as profiles of something. A requirement for this to work is that every element of the list contains both longitude and latitude in either the metadata or data slot (in the latter case, the mean value is recorded in the section object) and that every element also contains pressure in its data slot.

Case 3. If the first argument is a argo-class object, then the profiles it contains are turned into ctd-class objects, and these are assembled into a section to be returned.

## Usage

```
as.section(salinity, temperature, pressure, longitude, latitude, station,
  sectionId = "")
```

# Arguments

salinity This may be a numerical vector, in which case it is interpreted as the salinity,

and the other arguments are used for the other components of ctd-class objects. Alternatively, it may be one of a variety of other objects from which the CTD objects can be inferred, in which case the other arguments are ignored; see

'Details'.

temperature Temperature, in a vector holding values for all stations.

pressure Pressure, in a vector holding values for all stations.

longitude Longitude, in a vector holding values for all stations.

latitude Latitude, in a vector holding values for all stations.

station Station identifiers, in a vector holding values for all stations.

sectionId Section identifier.

## Value

An object of section-class.

## Author(s)

Dan Kelley

## See Also

Other things related to section data: [[, section-method, [[<-, section-method, handleFlags, section-method, plot, section-method, read. section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method

50 as.topo

## **Examples**

```
library(oce)
data(ctd)
## vector of names of CTD objects
fake <- ctd
fake[["temperature"]] <- ctd[["temperature"]] + 0.5</pre>
fake[["salinity"]] <- ctd[["salinity"]] + 0.1</pre>
fake[["longitude"]] <- ctd[["longitude"]] + 0.01</pre>
fake[["station"]] <- "fake"</pre>
sec1 <- as.section(c("ctd", "fake"))</pre>
summary(sec1)
## vector of CTD objects
ctds <- vector("list", 2)</pre>
ctds[[1]] <- ctd
ctds[[2]] <- fake
sec2 <- as.section(ctds)</pre>
summary(sec2)
## argo data (a subset)
data(argo)
sec3 <- as.section(subset(argo, profile<5))</pre>
summary(sec3)
```

as.topo

Coerce Data into Topo Object

# **Description**

Coerce Data into Topo Object

# Usage

```
as.topo(longitude, latitude, z, filename = "")
```

# **Arguments**

longitude Either a vector of longitudes (in degrees east, and bounded by -180 and 180), or a bathy object created by getNOAA.bathy() from the marmap package; in the

second case, all other arguments are ignored.

latitude A vector of latitudes.

A matrix of heights (positive over land). z

Name of data (used when called by read. topo. filename

# Value

An object of topo-class.

as.unit 51

## Author(s)

Dan Kelley

## See Also

Other things related to topo data: [[,topo-method,[[<-,topo-method,download.topo,plot,topo-method,read.topo,subset,topo-method,summary,topo-method,topo-class,topoInterpolate,topoWorld

as.unit

Convert a String to a Unit

# Description

Convert a String to a Unit

# Usage

```
as.unit(u, default = list(unit = expression(), scale = ""))
```

## **Arguments**

u A character string indicating a variable name. The following names are recog-

nized: "DBAR", "IPTS-68", "ITS-90", "PSS-78", and "UMOL/KG". All other

names yield a return value equal to the value of the default argument.

default A default to be used for the return value, if u is not a recognized string.

#### **Details**

This function is not presently used by any oce functions, and is provided as a convenience function for users.

## Value

A list with elements unit, an expression, and scale, a string.

52 as.windrose

as.windrose	Create a Windrose Object	
-------------	--------------------------	--

# **Description**

Create a wind-rose object, typically for plotting with plot, windrose-method.

## Usage

```
as.windrose(x, y, dtheta = 15, debug = getOption("oceDebug"))
```

## **Arguments**

x	The x component of wind speed (or stress) <i>or</i> an object of class met (see met-class), in which case the u and v components of that object are used for the components of wind speed, and y here is ignored.
y	The y component of wind speed (or stress).
dtheta	The angle increment (in degrees) within which to classify the data.
debug	A flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

## Value

An object of windrose-class that contains the standard oce slots named data, metadata and proxessingLog. The data slot contains

```
n the number of x values
```

x.mean the mean of the x values

y.mean the mean of the y values

theta the central angle (in degrees) for the class

count the number of observations in this class

mean the mean of the observations in this class

fivenum the fivenum vector for observations in this class (the min, the lower hinge, the median, the upper hinge, and the max)

#### Author(s)

Dan Kelley, with considerable help from Alex Deckmyn.

#### See Also

Other things related to windrose data: [[,windrose-method, [[<-,windrose-method, plot,windrose-method, summary,windrose-method, windrose-class

bcdToInteger 53

# **Examples**

```
library(oce)
xcomp <- rnorm(360) + 1
ycomp <- rnorm(360)
wr <- as.windrose(xcomp, ycomp)
summary(wr)
plot(wr)</pre>
```

bcdToInteger

Decode BCD to integer

# Description

Decode BCD to integer

# Usage

```
bcdToInteger(x, endian = c("little", "big"))
```

## **Arguments**

x a raw value, or vector of raw values, coded in binary-coded decimal.

endian character string indicating the endian-ness ("big" or "little"). The PC/intel con-

vention is to use "little", and so most data files are in that format.

# Value

An integer, or list of integers.

# Author(s)

Dan Kelley

```
library(oce)
twenty.five <- bcdToInteger(as.raw(0x25))
thirty.seven <- as.integer(as.raw(0x25))</pre>
```

54 beamName

beamName

Get names of Acoustic-Doppler Beams

# **Description**

Get names of Acoustic-Doppler Beams

# Usage

```
beamName(x, which)
```

# **Arguments**

x An adp object, i.e. one inheriting from adp-class.

which an integer indicating beam number.

#### Value

A character string containing a reasonable name for the beam, of the form "beam 1", etc., for beam coordinates, "east", etc. for enu coordinates, "u", etc. for "xyz", or "u'", etc., for "other" coordinates. The coordinate system is determined with x[["coordinate"]].

#### Author(s)

Dan Kelley

#### See Also

This is used by read.oce.

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi,read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

Other things related to adv data: [[,adv-method, [[<-,adv-method,adv-class,adv,beamToXyz,enuToOtherAdv,enuToOther,plot,adv-method,read.adv.nortek,read.adv.sontek.adr,read.adv.sontek.serial,read.adv.sontek.text,read.adv,subset,adv-method,summary,adv-method,toEnuAdv,toEnu,velocityStatistics,xyzToEnuAdv,xyzToEnu

beamToXyz 55

beamToXyz

Change ADV or ADP coordinate systems

# Description

Convert velocity data from an acoustic-Doppler velocimeter or acoustic-Doppler profiler from one coordinate system to another.

## Usage

```
beamToXyz(x, ...)
```

## **Arguments**

- x an adp or adv object, i.e. one inheriting from adp-class or adv-class.
- ... extra arguments that are passed on to beamToXyzAdp or beamToXyzAdv.

## Value

An object of the same type as x, but with velocities in xyz coordinates instead of beam coordinates.

## Author(s)

Dan Kelley

## See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.adpopPHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

56 beamToXyzAdp

beamToXyzAdp

Convert ADP From Beam to XYZ Coordinates

# **Description**

Convert ADP velocity components from a beam-based coordinate system to a xyz-based coordinate system.

#### Usage

```
beamToXyzAdp(x, debug = getOption("oceDebug"))
```

## **Arguments**

x an object of class "adp".

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### **Details**

The action depends on the type of object.

For a 3-beam aquadopp object, the beams are transformed into velocities using the matrix stored in the header.

For 4-beam rdi object, the beams are converted to velocity components using formulae from section 5.5 of *RD Instruments* (1998), viz. the along-beam velocity components  $B_1$ ,  $B_2$ ,  $B_3$ , and  $B_4$  are used to calculate velocity components in a cartesian system referenced to the instrument using the following formulae:  $u = ca(B_1 - B_2)$ ,  $v = ca(B_4 - B_3)$ ,  $w = -b(B_1 + B_2 + B_3 + B_4)$ , and an estimate of the error in velocity is calculated using  $e = d(B_1 + B_2 - B_3 - B_4)$ 

(Note that the multiplier on e is subject to discussion; RDI suggests one multiplier, but some oceanographers favour another.)

In the above, c=1 if the beam geometry is convex, and c=-1 if the beam geometry is concave,  $a=1/(2\sin\theta),\ b=1/(4\cos\theta)$  and  $d=a/\sqrt{2}$ , where  $\theta$  is the angle the beams make to the instrument "vertical".

## Value

An object with the first 3 velocity indices having been altered to represent velocity components in xyz (or instrument) coordinates. (For rdi data, the values at the 4th velocity index are changed to represent the "error" velocity.)

To indicate the change, the value of metadata\$oce.orientation is changed from beam to xyz.

beamToXyzAdv 57

#### Author(s)

Dan Kelley

#### References

- 1. R D Instruments, 1998. ADP Coordinate Transformation, formulas and calculations. P/N 951-6079-00 (July 1998).
- 2. WHOI/USGS-provided Matlab code for beam-enu transformation 'http://woodshole.er.usgs.gov/pubs/of2005-142

#### See Also

See read. adp for other functions that relate to objects of class "adp".

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamName, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

beamToXyzAdv

Convert ADV from Beam to XYZ Coordinates

## **Description**

Convert ADV velocity components from a beam-based coordinate system to a xyz-based coordinate system.

# Usage

```
beamToXyzAdv(x, debug = getOption("oceDebug"))
```

#### **Arguments**

x an object of class "adv".

debug a flag that, if non-zero, turns on debugging. Higher values yield more extensive

debugging.

#### **Details**

The coordinate transformation is done using the transformation matrix contained in transformation.matrix in the metadata slot, which is normally inferred from the header in the binary file. If there is no such matrix (e.g. if the data were streamed through a data logger that did not capture the header), beamToXyzAdv the user will need to store one in x, e.g. by doing something like the following:

```
x[["transformation.matrix"]] <- rbind(c(11100, -5771, -5321),
c( #' 291, 9716, -10002),
c( 1409, 1409, 1409)) / 4096
```

58 beamUnspreadAdp

#### Author(s)

Dan Kelley

#### References

http://www.nortek-as.com/lib/forum-attachments/coordinate-transformation

#### See Also

See read.adv for notes on functions relating to "adv" objects.

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.adpopPRR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

beamUnspreadAdp

Adjust ADP Signal for Spherical Spreading

## Description

Compensate ADP signal strength for spherical spreading.

#### **Usage**

```
beamUnspreadAdp(x, count2db = c(0.45, 0.45, 0.45, 0.45), asMatrix = FALSE, debug = getOption("oceDebug"))
```

# Arguments

X	An adp object,	ie one	inheriting	from ad	n-class
^	Till dup object,	i.c. one	micriting	II OIII ac	p cruss.

count2db a set of coefficients, one per beam, to convert from beam echo intensity to deci-

bels.

asMatrix a boolean that indicates whether to return a numeric matrix, as opposed to re-

turning an updated object (in which the matrix is cast to a raw value).

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

beamUnspreadAdp 59

#### **Details**

First, beam echo intensity is converted from counts to decibels, by multiplying by count2db. Then, the signal decrease owing to spherical spreading is compensated for by adding the term  $20 \log 10(r)$ , where r is the distance from the sensor head to the water from which scattering is occurring. r is given by x[["distance"]].

#### Value

```
An object of class "adp".
```

## Author(s)

Dan Kelley

#### References

The coefficient to convert to decibels is a personal communication. The logarithmic term is explained in textbooks on acoustics, optics, etc.

#### See Also

```
Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamName, beamToXyzAdp, beamToXyzAdv, beamToXyz, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu
```

```
library(oce)
data(adp)
plot(adp, which=5) # beam 1 echo intensity
adp.att <- beamUnspreadAdp(adp)
plot(adp.att, which=5) # beam 1 echo intensity
## Profiles
par(mar=c(4, 4, 1, 1))
a <- adp[["a", "numeric"]] # second arg yields matrix return value
distance <- adp[["distance"]]
plot(apply(a,2,mean), distance, type='1', xlim=c(0,256))
lines(apply(a,2,median), distance, type='1',col='red')
legend("topright",lwd=1,col=c("black","red"),legend=c("original","attenuated"))
## Image
plot(adp.att, which="amplitude",col=oce.colorsJet(100))</pre>
```

60 binApply1D

binA	nn <sup>-</sup>	1 v1	Γ
DILLIV	PΡ-	⊥.у і	$\mathbf{L}$

Apply a function to vector data

# Description

The function FUN is applied to f in bins specified by xbreaks. (If FUN is mean, consider using binMean2D instead, since it should be faster.)

#### Usage

```
binApply1D(x, f, xbreaks, FUN, ...)
```

#### **Arguments**

x a vector of numerical values.

f a vector of data to which the elements of FUN may be supplied

xbreaks values of x at the boundaries between bins; calculated using pretty if not sup-

plied.

FUN function to apply to the data

... arguments to pass to the function FUN

#### Value

A list with the following elements: the breaks in x and y (xbreaks and ybreaks), the break midpoints (xmids and ymids), and a matrix containing the result of applying function FUN to f subsetted by these breaks.

#### Author(s)

Dan Kelley

#### See Also

Other bin-related functions: binApply2D, binAverage, binCount1D, binCount2D, binMean1D, binMean2D

```
library(oce)
## salinity profile with median and quartile 1 and 3
data(ctd)
p <- ctd[["pressure"]]
S <- ctd[["salinity"]]
q1 <- binApply1D(p, S, pretty(p, 30), function(x) quantile(x, 1/4))
q3 <- binApply1D(p, S, pretty(p, 30), function(x) quantile(x, 3/4))
plotProfile(ctd, "salinity", col='gray', type='n')
polygon(c(q1$result, rev(q3$result)),
c(q1$xmids, rev(q1$xmids)), col='gray')
points(S, p, pch=20)</pre>
```

binApply2D 61

binApply2D	Apply a function to matrix data

# **Description**

The function FUN is applied to f in bins specified by xbreaks and ybreaks. (If FUN is mean, consider using binMean2D instead, since it should be faster.)

# Usage

```
binApply2D(x, y, f, xbreaks, ybreaks, FUN, ...)
```

## **Arguments**

X	a vector of numerical values.
у	a vector of numerical values.
f	a vector of data to which the elements of FUN may be supplied
xbreaks	values of x at the boundaries between bins; calculated using pretty if not supplied.
ybreaks	values of y at the boundaries between bins; calculated using pretty if not supplied.
FUN	function to apply to the data
	arguments to pass to the function FUN

## Value

A list with the following elements: the breaks in x and y (xbreaks and ybreaks), the break midpoints (xmids and ymids), and a matrix containing the result of applying function FUN to f subsetted by these breaks.

# Author(s)

Dan Kelley

#### See Also

Other bin-related functions: binApply1D, binAverage, binCount1D, binCount2D, binMean1D, binMean2D

```
library(oce)
## Not run:
## secchi depths in lat and lon bins
if (require(ocedata)) {
    data(secchi, package="ocedata")
```

62 binAverage

```
col <- rev(oce.colorsJet(100))[rescale(secchi$depth,</pre>
                                            xlow=0, xhigh=20,
                                            rlow=1, rhigh=100)]
   zlim < - c(0, 20)
   breaksPalette <- seq(min(zlim), max(zlim), 1)</pre>
   colPalette <- rev(oce.colorsJet(length(breaksPalette)-1))</pre>
    drawPalette(zlim, "Secchi Depth", breaksPalette, colPalette)
    data(coastlineWorld)
   mapPlot(coastlineWorld, longitudelim=c(-5, 20), latitudelim=c(50, 66),
      grid=5, fill='gray', projection="+proj=lcc +lat_1=50 +lat_2=65")
    bc <- binApply2D(secchi$longitude, secchi$latitude,</pre>
                     pretty(secchi$longitude, 80),
                     pretty(secchi$latitude, 40),
                     f=secchi$depth, FUN=mean)
    mapImage(bc$xmids, bc$ymids, bc$result, zlim=zlim, col=colPalette)
   mapPolygon(coastlineWorld, col='gray')
}
## End(Not run)
```

binAverage

Bin-average a vector y, based on x values

## **Description**

The y vector is averaged in bins defined for x. Missing values in y are ignored.

# Usage

```
binAverage(x, y, xmin, xmax, xinc)
```

# Arguments

X	a vector of numerical values.
У	a vector of numerical values.
xmin	x value at the lower limit of first bin; the minimum x will be used if this is not provided.
xmax	x value at the upper limit of last bin; the maximum x will be used if this is not provided.
xinc	width of bins, in terms of x value; 1/10th of xmax-xmin will be used if this is not provided.

# Value

A list with two elements: x, the mid-points of the bins, and y, the average y value in the bins.

## Author(s)

Dan Kelley

binCount1D 63

## See Also

Other bin-related functions: binApply1D, binApply2D, binCount1D, binCount2D, binMean1D, binMean2D

## **Examples**

```
library(oce)
## A. fake linear data
x < - seq(0, 100, 1)
y < -1 + 2 * x
plot(x, y, pch=1)
ba <- binAverage(x, y)</pre>
points(ba$x, ba$y, pch=3, col='red', cex=3)
## B. fake quadratic data
y < -1 + x^2
plot(x, y, pch=1)
ba <- binAverage(x, y)</pre>
points(ba$x, ba$y, pch=3, col='red', cex=3)
## C. natural data
data(co2)
plot(co2)
avg <- binAverage(time(co2), co2, 1950, 2000, 2)</pre>
points(avg$x, avg$y, col='red')
```

binCount1D

Bin-count vector data

# **Description**

Count the number of elements of a given vector that fall within successive pairs of values within a second vector.

# Usage

```
binCount1D(x, xbreaks)
```

## **Arguments**

x Vector of numerical values.

xbreaks Vector of values of x at the boundaries between bins, calculated using pretty if not supplied.

#### Value

A list with the following elements: the breaks (xbreaks, midpoints (xmids) between those breaks, and the count (number) of x values between successive breaks.

64 binCount2D

## Author(s)

Dan Kelley

#### See Also

Other bin-related functions: binApply1D, binApply2D, binAverage, binCount2D, binMean1D, binMean2D

binCount2D

Bin-count matrix data

# **Description**

Count the number of elements of a given matrix z=z(x,y) that fall within successive pairs of breaks in x and y.

# Usage

```
binCount2D(x, y, xbreaks, ybreaks, flatten = FALSE)
```

# Arguments

Х	Vector of numerical values.
У	Vector of numerical values.
xbreaks	Vector of values of $x$ at the boundaries between bins, calculated using pretty( $x$ ) if not supplied.
ybreaks	Vector of values of y at the boundaries between bins, calculated using pretty(y) if not supplied.
flatten	A logical value indicating whether the return value also contains equilength vectors x, y, z and n, a flattened representation of xmids, ymids, result and number.

## Value

A list with the following elements: the breaks (xbreaks and ybreaks), the midpoints (xmids and ymids) between those breaks, and the count (number) of f values in the boxes defined between successive breaks.

# Author(s)

Dan Kelley

## See Also

Other bin-related functions: binApply1D, binApply2D, binAverage, binCount1D, binMean1D, binMean2D

binmapAdp 65

binmapAdp Bin-map an ADP object
---------------------------------

**Description** 

# Bin-map an ADP object, by interpolating velocities, backscatter amplitudes, etc., to uniform depth bins, thus compensating for the pitch and roll of the instrument. This only makes sense for ADP objects that are in beam coordinates.

# Usage

```
binmapAdp(x, debug = getOption("oceDebug"))
```

# Arguments

x an adp object, i.e. one inheriting from adp-class.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

# Value

An object of class "adp".

## Bugs

This only works for 4-beam RDI ADP objects.

#### Author(s)

Dan Kelley and Clark Richards

#### References

The method was devised by Clark Richards for use in his PhD work at Department of Oceanography at Dalhousie University.

## See Also

See adp-class for a discussion of adp objects and notes on the many functions dealing with them.

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamName, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

66 binMean1D

## **Examples**

binMean1D

Bin-average f=f(x)

# **Description**

Average the values of a vector f in bins defined on another vector x. A common example might be averaging CTD profile data into pressure bins (see "Examples").

# Usage

```
binMean1D(x, f, xbreaks)
```

## **Arguments**

x Vector of numerical values.

f Vector of numerical values.

xbreaks Vector of values of x at the boundaries between bins, calculated using pretty if

not supplied.

## Value

A list with the following elements: the breaks (xbreaks, midpoints (xmids) between those breaks, the count (number) of x values between successive breaks, and the resultant average (result) of f, classified by the x breaks.

# Author(s)

Dan Kelley

binMean2D 67

# See Also

Other bin-related functions: binApply1D, binApply2D, binAverage, binCount1D, binCount2D, binMean2D

# **Examples**

```
library(oce)
data(ctd)
z <- ctd[["z"]]
T <- ctd[["temperature"]]
plot(T, z)
TT <- binMean1D(z, T, seq(-100, 0, 1))
lines(TT$result, TT$xmids, col='red')</pre>
```

binMean2D

Bin-average f=f(x,y)

# Description

Average the values of a vector f(x,y) in bins defined on vectors x and y. A common example might be averaging spatial data into location bins.

# Usage

```
binMean2D(x, y, f, xbreaks, ybreaks, flatten = FALSE, fill = FALSE,
  fillgap = -1)
```

# **Arguments**

Х	Vector of numerical values.
У	Vector of numerical values.
f	Matrix of numerical values, a matrix $f=f(x,y)$ .
xbreaks	Vector of values of $x$ at the boundaries between bins, calculated using $pretty(x)$ if not supplied.
ybreaks	Vector of values of y at the boundaries between bins, calculated using pretty(y) if not supplied.
flatten	A logical value indicating whether the return value also contains equilength vectors $x$ , $y$ , $z$ and $n$ , a flattened representation of xmids, ymids, result and number.
fill	Logical value indicating whether to fill NA-value gaps in the matrix. Gaps will be filled as the average of linear interpolations across rows and columns. See fillgap, which works together with this.
fillgap	Integer controlling the size of gap that can be filled across. If this is negative (as in the default), gaps will be filled regardless of their size. If it is positive, then gaps exceeding this number of indices will not be filled.

68 bound125

## Value

A list with the following elements: the midpoints (renamed as x and y), the count (number) of f(x,y) values for x and y values that lie between corresponding breaks, and the resultant average (f) of f(x,y), classified by the x and y breaks.

# Author(s)

Dan Kelley

#### See Also

Other bin-related functions: binApply1D, binApply2D, binAverage, binCount1D, binCount2D, binMean1D

# **Examples**

```
library(oce)
x <- runif(500)
y <- runif(500)
f <- x + y
xb <- seq(0, 1, 0.1)
yb <- seq(0, 1, 0.2)
m <- binMean2D(x, y, f, xb, yb)
plot(x, y)
contour(m$xmids, m$ymids, m$result, add=TRUE, levels=seq(0, 2, 0.5), labcex=1)</pre>
```

bound125

Calculate a rounded bound, rounded up to matissa 1, 2, or 5

## **Description**

Calculate a rounded bound, rounded up to matissa 1, 2, or 5

# Usage

```
bound125(x)
```

## **Arguments**

Х

a single positive number

# Value

for positive x, a value exceeding x that has mantissa 1, 2, or 5; otherwise, x

69 bremen-class

bremen-class

Class for data stored in a format used at Bremen

## **Description**

Class for data stored in a format used at Bremen. This is somewhat unusual amongst oce classes, in that it does not map to a particular instrument. Although some functions are provided for dealing with these data (see "Details"), the most common action is to read the data with read.bremen, and then to coerce the object to another storage class (e.g. using as.ctd for CTD-style data) so that specialized functions can be used thereafter.

The main function is read, bremen. A simple plotting method is provided with plot, bremen-method, and summary, bremen-method provides summaries. Data may be retrieved with [[, bremen-method or replaced with [[<-,bremen-method.

#### Author(s)

Dan Kelley

#### See Also

Other classes provided by oce: adp-class, adv-class, argo-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to bremen data: [[,bremen-method, [[<-,bremen-method, plot,bremen-method, read.bremen, summary, bremen-method

byteToBinary

Format bytes as binary

## **Description**

**WARNING:** The endian argument will soon be removed from this function; see oce-deprecated. This is because the actions for endian="little" made no sense in practical work. The default value for endian was changed to "big" on 2017 May 6.

#### **Usage**

```
byteToBinary(x, endian)
```

#### **Arguments**

х an integer to be interpreted as a byte.

endian character string indicating the endian-ness ("big" or "little"). This argument

will be removed in the upcoming CRAN release.

70 cm

## Value

A character string representing the bit strings for the elements of x, in order of significance for the endian="big" case. (The nibbles, or 4-bit sequences, are interchanged in the now-deprecated "little" case.) See "Examples" for how this relates to the output from rawToBits.

#### Author(s)

Dan Kelley

# **Examples**

```
library(oce)
## Note comparison with rawToBits():
a <- as.raw(0x0a)
byteToBinary(a, "big") # "00001010"
rev(rawToBits(a)) # 00 00 00 01 00 01 00</pre>
```

cm

A CM Record

## **Description**

The result of using read.cm on a current meter file holding measurements made with an InterOcean S4 device. See read.cm for some general cautionary notes on reading such files. Note that the salinities in this sample dataset are known to be incorrect, perhaps owing to a lack of calibration of an old instrument that had not been used in a long time.

## Usage

data(cm)

#### See Also

Other datasets provided with oce: adp, adv, argo, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to cm data: [[,cm-method, [[<-,cm-method, as.cm, cm-class, plot,cm-method, read.cm, subset,cm-method, summary,cm-method

```
## Not run:
library(oce)
data(cm)
summary(cm)
plot(cm)
## End(Not run)
```

71 cm-class

cm-class

Class to Store Current Meter (CM) Data

## **Description**

Class to store current meter data, e.g. from an Interocean/S4 device or an Aanderaa/RCM device. A file containing Interocean/S4 data may be read with read.cm. Alternatively, as.cm can be used to create cm objects. Objects of this class can be plotted with plot, cm-method or summarized with summary, cm-method. Data may be retrieved with [[, cm-method or replaced with \ [[<-,cm-method.

## Author(s)

Dan Kelley

#### See Also

Other things related to cm data: [[,cm-method, [[<-,cm-method, as.cm, cm, plot,cm-method, read.cm, subset, cm-method, summary, cm-method

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

cnvName2oceName

Infer variable name, units and scale from a Seabird (.cnv) header line

# **Description**

This function is used by read.ctd.sbe to infer data names and units from the coding used by Teledyne/Seabird (SBE) . cnv files. Lacking access to documentation on the SBE format, the present function is based on inspection of a suite of CNV files available to the oce developers.

#### Usage

```
cnvName2oceName(h, columns = NULL, debug = getOption("oceDebug"))
```

## **Arguments**

The header line.

columns Optional list containing name correspondances, as described for read.ctd.sbe. debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

72 cnvName2oceName

#### **Details**

A few sample header lines that have been encountered are:

```
# name 4 = t068: temperature, IPTS-68 [deg C]
# name 3 = t090C: Temperature [ITS-90, deg C]
# name 4 = t190C: Temperature, 2 [ITS-90, deg C]
```

Examination of several CNV files suggests that it is best to try to infer the name from the characters between the "=" and ":" characters, because the material after the colon seems to vary more between sample files.

The table given below indicates the translation patterns used. These are taken from [1]. The .cnv convention for multiple sensors is to include optional extra digits in the name, and these are indicated with ~ in the table; their decoding is done with grep.

It is important to note that this table is by no means complete, since there are a great many SBE names listed in their document [1], plus names not listed there but present in data files supplied by prominent archiving agencies. If an SBE name is not recognized, then the oce name is set to that SBE name. This can cause problems in some other processing steps (e.g. if swRho or a similar function is called with an oce object as first argument), and so users are well-advised to rename the items as appropriate. The first step in doing this is to pass the object to summary(), to discover the SBE names in question. Then consult the SBE documentation to find an appropriate name for the data, and either manipulate the names in the object data slot directly or use renameData to rename the elements. Finally, please publish an 'issue' on the oce Github site https://github.com/dankelley/oce/issues so that the developers can add the data type in question. (To save development time, there is no plan to add all possible data types without a reasonable and specific expression user interest. Oxygen alone has over forty variants.)

Key	Result	Unit;scale	Notes
alt	altimeter	m	
altM	altimeter	m	
accM	acceleration	m/s^2	
bat~	beamAttenuation	1/m	
C2-C1S/m	conductivityDifference	S/m	
C2-C1mS/cm	conductivityDifference	mS/cm	
C2-C1uS/cm	conductivityDifference	uS/cm	
c~mS/cm	conductivity	mS/cm	
c~S/m	conductivity	S/m	
c~uS/cm	conductivity	uS/cm	
CStarAt~	beamAttenuation	1/m	
CStarTr~	beamTransmission	percent	
density~~	density	kg/m^3	
depS	depth	m	
depSM	depth	m	
depF	depth	m	
depFM	depth	m	
dz/dtM	descentRate	m/s	
f~	frequency	Hz	
f~~	frequency	Hz	
flC~	fluorescence	ug/l; Chelsea Aqua 3	

cnvName2oceName 73

flCM flCUVA~ flEC-AFL~ flS flScufa~	fluorescence fluorescence fluorescence fluorescence fluorescence	ug/l; Chelsea Mini Chl Con ug/l; Chelsea UV Aquatracka mg/m^3; WET Labs ECO-AFL/FLtab -; Seatech -; Turner SCUFA [RFU]	
flsP	fluorescence	-; Seapoint	
flSPR	fluorescence	-; Seapoint, Rhodamine	
flSPuv	fluorescence	-; Seapoint, UV	
flT	fluorescence	-; Turner 10-005 flT	
gpa latitude	geopotentialAnomaly latitude	-; J/kg	
longitude	longitude	degN degE	
n2satML/L	nitrogenSaturation	ml/l	
n2satMg/L	nitrogenSaturation	mg/l	
n2satumol/kg	nitrogenSaturation	umol/kg	
nbin	nbin	umorkg	
obsscufa~	backscatter	NTU; Turner SCUFA	
opoxMg/L	oxygen	mg/l; Optode, Anderaa	
opoxML/L	oxygen	ml/l; Optode, Anderaa	
opoxMm/L	oxygen	umol/l; Optode, Anderaa	
opoxPS	oxygen	percent; Optode, Anderaa	
oxsatML/L	oxygen	ml/l; Weiss	
oxsatMg/L	oxygen	mg/l; Weiss	
oxsatMm/Kg	oxygen	umol/kg; Weiss	
oxsolML/L	oxygen	ml/l; Garcia-Gordon	
oxsolMg/L	oxygen	mg/l; Garcia-Gordon	
oxsolMm/Kg	oxygen	umol/kg; Garcia-Gordon	
par~	PAR	-; Biospherical/Licor	
par/log	PAR	log; Satlantic	
ph	pH	-	
potemp~68C	thetaM	degC; IPTS-68	
potemp~90C	thetaM	degC; ITS-90	
pr	pressure	dbar	1
prM	pressure	dbar	
pr50M	pressure	dbar; SBE50	
prSM	pressure	dbar	
prDM	pressure	dbar; digiquartz	2
prdE	pressure	psi; strain gauge	2 2
prDE	pressure	psi; digiquartz dbar; strain gauge	2
prdM prSM	pressure	dbar; strain gauge	
ptempC	<pre>pressure pressureTemperature</pre>	degC; ITS-90	3
pumps	pumpStatus	dege, 113-90	3
rhodflTC~	Rhodamine	ppb; Turner Cyclops	
sal~~	salinity	-, PSS-78	4
sbeox~ML/L	oxygen	ml/l; SBE43	7
sbeox Mm/Kg	oxygen	umol/kg; SBE43	
sbeox~Mm/L	oxygen	umol/l; SBE43	
5555X 1111/ L	2.750		

74 cnvName2oceName

sbeox~PS	oxygen	percent; SBE43	
sbeox~V	oxygenRaw	V; SBE43	
scan	scan	-	
seaTurbMtr~	turbidity	FTU; SeaPoint	
secS-priS	salinityDifference	-, PSS-78	
sigma-t	sigmaT	kg/m^3	
sigma-theta	sigmaTheta	kg/m^3	5
sigma-é	sigmaTheta	kg/m^3	5
spar	spar	-	
specc	conductivity	uS/cm	
sva	specificVolumeAnomaly	1e-8 m^3/kg;	
svCM~	soundSpeed	m/s; Chen-Millero	
T2~68C	temperatureDifference	degC; IPTS-68	
T2~90C	temperatureDifference	degC; ITS-90	
t~68	temperature	degC; IPTS-68	
t~90	temperature	degC; ITS-90	
t~68	temperature	degC; IPTS-68	
t~68C	temperature	degC; IPTS-68	
t~90C	temperature	degC; ITS-90	
t090Cm	temperature	degC; ITS-90	
t4990C	temperature	degC; ITS-90	
tnc90C	temperature	degC; ITS-90	
tsa	thermostericAnomaly	1e-8 m^3/kg	
tv290C	temperature	degC; ITS-90	
t4968C	temperature	degC; IPTS-68	
tnc68C	temperature	degC; IPTS-68	
tv268C	temperature	degC; IPTS-68	
t190C	temperature	degC; ITS-90	
tnc290C	temperature	degC; ITS-90	
tnc268C	temperature	degC; IPTS-68	
t3890C~	temperature	degC; ITS-90	
t38~90C	temperature	degC; ITS-90	
t3868C~	temperature	degC; IPTS-68	
t38~38C	temperature	degC; IPTS-68	
timeH	time	hour; elapsed	
timeJ	time	day; elapsed	
timeK	time	s; since Jan 1, 2000	
timeM	time	minute; elapsed	
timeN	time	s; NMEA since Jan 1, 1970	
timeQ	time	s; NMEA since Jan 1, 2000	
timeS	time	s; elapsed	
turbflTC~	turbidity	NTU; Turner Cyclops	
turbflTCdiff	turbidityDifference	NTU; Turner Cyclops	
turbWETbb~	turbidity	1/(m*sr); WET Labs ECO	
turbWETbbdiff	turbidityDifference	1/(m*sr); WET Labs ECO	
turbWETntu~	turbidity	NTU; WET Labs ECO	
turbWETntudiff	turbidityDifference	NTU; WET Labs ECO	
upoly~	upoly	-	
· •	· ·		

cnvName2oceName 75

user~ user V v~~ voltage 1/m; WET Labs AC3 wetBAttn beamAttenuation wetBTrans beamTransmission percent; WET Labs AC3 wetCDOM~ fluorescence mg/m<sup>3</sup>; WET Labs CDOM wetCDOMdiff fluorescenceDifference mg/m<sup>3</sup>; WET Labs CDOM wetChAbs fluorescence 1/m; WET Labs AC3 absorption fluorescence mg/m<sup>3</sup>; WET Labs WETstar wetStar~ fluorescenceDifference mg/m^3; WET Labs WETstar wetStardiff xmiss beamTransmission percent; Chelsea/Seatech xmiss~ beamTransmission percent; Chelsea/Seatech

#### Notes:

- 1: 'pr' is in a Dalhousie-generated data file but seems not to be in [1].
- 2: this is an odd unit, and so if sw\* functions are called on an object containing this, a conversion will be made before performing the computation. Be on the lookout for errors, since this is a rare situation.
- 3: assume ITS-90 temperature scale, since sample . cnv file headers do not specify it.
- 4: some files have PSU for this. Should we handle that? And are there other S scales to consider?
- 5: 'theta' may appear in different ways with different encoding configurations, set up within R or in the operating system.

## Value

a list containing name (the oce name), nameOriginal (the SBE name) and unit.

## Author(s)

Dan Kelley

### References

1. A SBE data processing manual is at http://www.seabird.com/document/sbe-data-processing-manual.

#### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other functions that interpret variable names and units from headers: ODFNames2oceNames, oceNames2whpNames, oceUnits2whpUnits, unitFromStringRsk, unitFromString, woceNames2oceNames, woceUnit2oceUnit

76 coastlineBest

## **Description**

Class to store coastline data, which may be read with read.coastline or constructed with as.coastline, plotted with plot, coastline-method or summarized with summary, coastline-method. Data within coastline objects may be retrieved with [[, coastline-method or replaced with [[<-, coastline-method.

#### Author(s)

Dan Kelley

#### See Also

```
Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to coastline data: [[, coastline-method, [[<-, coastline-method, as.coastline, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method, summary, coastline-method
```

## Description

Find the name of the most appropriate coastline for a given locale Checks coastlineWorld, coastlineWorldFine and coastlineWorldCoarse, in that order, to find the one most appropriate for the locale.

## **Usage**

```
coastlineBest(lonRange, latRange, span, debug = getOption("oceDebug"))
```

## **Arguments**

lonRange range of longitude for locale range of latitude for locale

span span of domain in km (if provided, previous two arguments are ignored).

debug set to a positive value to get debugging information during processing.

#### Value

The name of a coastline that can be loaded with data().

coastlineCut 77

## Author(s)

Dan Kelley

#### See Also

Other things related to coastline data: [[,coastline-method,[[<-,coastline-method,as.coastline, coastline-class, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method, summary, coastline-met

coastlineCut

Cut a Coastline Object at Specified Longitude

## **Description**

This can be helpful in preventing mapPlot from producing ugly horizontal lines in world maps. These lines occur when a coastline segment is intersected by longitude lon\_0+180. Since the coastline files in the oce and ocedata packages are already "cut" at longitudes of -180 and 180, the present function is not needed for default maps, which have +lon\_0=0. However, may help with other values of lon\_0.

## Usage

```
coastlineCut(coastline, lon_0 = 0)
```

### **Arguments**

coastline original coastline object

longitude as would be given in a +lon\_0= item in a call to project in the rgdal

package.

# Value

a new coastline object

#### **Caution**

This function is provisional. Its behaviour, name and very existence may change. Part of the development plan is to see if there is common ground between this and the clipPolys function in the **PBSmapping** package.

#### See Also

```
Other things related to coastline data: [[,coastline-method,[[<-,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method, summary, coastline-m
```

78 coastlineWorld

## **Examples**

```
library(oce)
data(coastlineWorld)
## Not run:
mapPlot(coastlineCut(coastlineWorld, lon_0=100), proj="+proj=robin +lon_0=100")#, col='gray')
## End(Not run)
```

coastlineWorld

World Coastline

### **Description**

This is a coarse resolution coastline at scale 1:110M, with 10,696 points, suitable for world-scale plots plotted at a small size, e.g. inset diagrams. Finer resolution coastline files are provided in the ocedata package.

# Installing your own datasets

Follow the procedure along the lines described in "Details", where of course your source file will differ. Also, you should change the name of the coastline object from coastlineWorld, to avoid conflicts with the built-in dataset. Save the .rda file to some directory of your choosing, e.g. perhaps /data/coastlines or ~/data/coastlines on a unix-type machine. Then, whenever you need the file, use load to load it. Most users find it convenient to do the loading in an Rprofile startup file.

## Author(s)

Dan Kelley

#### Source

Downloaded from <a href="http://www.naturalearthdata.com">http://www.naturalearthdata.com</a>, in ne\_110m\_admin\_0\_countries.shp in July 2015, with an update on December 16, 2017.

#### See Also

```
Other datasets provided with oce: adp, adv, argo, cm, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind
```

Other things related to coastline data: [[,coastline-method,[[<-,coastline-method,as.coastline, coastline-class, coastlineBest, coastlineCut, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method, summary, summa

colormap 79

colormap	Calculate colour map

#### **Description**

Map values to colours, for use in palettes and plots. There are many ways to use this function, and some study of the arguments should prove fruitful in cases that extend far beyond the examples.

### Usage

```
colormap(z = NULL, zlim, zclip = FALSE, breaks, col = oce.colorsJet, name,
    x0, x1, col0, col1, blend = 0, missingColor,
    debug = getOption("oceDebug"))
```

## **Arguments**

Z	an optional vector or other set of numerical values to be examined. If z is given,
	the return value will contain an item named zcol that will be a vector of the
	same length as z, containing a colour for each point. If z is not given, zcol will
	contain just one item, the colour "hlack"

contain just one item, the colour "black".

optional vector containing two numbers that specify the z limits for the colour scale. If provided, it overrides defaults as describe in the following. If name

is given, then the range of numerical values contained therein will be used for zlim. Otherwise, if z is given, then its rangeExtended sets zlim. Otherwise, if x0 and x1 are given, then their range sets zlim. Otherwise, there is no way to infer zlim and indeed there is no way to construct a colormap, so an error is reported. It is an error to specify both zlim and breaks, if the length of the

latter does not equal 1.

logical, with TRUE indicating that z values outside the range of zlim or breaks should be painted with missingColor and FALSE indicating that these values

should be painted with the nearest in-range colour.

an optional indication of break points between colour levels (see image). If this is provided, the arguments name through blend are all ignored (see "Details"). If it is provided, then it may either be a vector of break points, or a single number indicating the desired number of break points to be computed with pretty(z, breaks). In either case of non-missing breaks, the resultant break points must number 1 plus the number of colours (see col).

either a vector of colours or a function taking a numerical value as its single argument and returning a vector of colours. The value of col is ignored if name is provided, or if x0 through col1 are provided.

an optional string naming a built-in colormap (one of "gmt\_relief", "gmt\_ocean", "gmt\_globe" or "gmt\_gebco") or the name of a file or URL that contains a colour map specification in GMT format, e.g. one of the .cpt files from http://www.beamreach.org/maps/gmt/share/cpt). If name is provided, then x0, x1, col0 and col1 are all ignored.

zlim

zclip

breaks

col

name

80 colormap

x0, x1, col0, col1

Vectors that specify a colour map. They must all be the same length, with x0 and x1 being numerical values, and col0 and col1 being colours. The colours may be strings (e.g. "red") or colours as defined by rgb or hsv.

blend

a number indicating how to blend colours within each band. This is ignored except when x0 through col1 are supplied. A value of 0 means to use col0[i] through the interval x0[i] to x1[i]. A value of 1 means to use col1[i] in that interval. A value between 0 and 1 means to blend between the two colours according to the stated fraction. Values exceeding 1 are an error at present, but there is a plan to use this to indicate subintervals, so a smooth palette can be created from a few colours.

missingColor

colour to use for missing values. If not provided, this will be "gray", unless name is given, in which case it comes from that colour table.

debug

a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

#### **Details**

This is a multi-purpose function that generally links ("maps") numerical values to colours. The return value can specify colours for points on a graph, or breaks and col vectors that are suitable for use by drawPalette, imagep or image.

There are three ways of specifying colour schemes, and colormap works by checking for each condition in turn.

- Case A. Supply z but nothing else. In this case, breaks will be set to pretty(z, 10) and things are otherwise as in case B.
- Case B. Supply breaks. In this case, breaks and col are used together to specify a colour scheme. If col is a function, then it is expected to take a single numerical argument that specifies the number of colours, and this number will be set to length(breaks)-1. Otherwise, col may be a vector of colours, and its length must be one less than the number of breaks. (NB. if breaks is given, then all other arguments except col and missingColor are ignored.)
- Case C. Do not supply breaks, but supply name instead. This name may be the name of a predefined colour palette ("gmt\_relief", "gmt\_ocean", "gmt\_globe" or "gmt\_gebco"), or it may be the name of a file (including a URL) containing a colour map in the GMT format (see "References"). (NB. if name is given, then all other arguments except z and missingColor are ignored.)
- Case D. Do not supply either breaks or name, but instead supply each of x0, x1, col0, and col1. These values are specify a value-colour mapping that is similar to that used for GMT colour maps. The method works by using seq to interpolate between the elements of the x0 vector. The same is done for x1. Similarly, colorRampPalette is used to interpolate between the colours in the col0 vector, and the same is done for col1.

#### Value

A list containing the following (not necessarily in this order)

• zcol, a vector of colours for z, if z was provided, otherwise "black"

colormap 81

 zlim, a two-element vector suitable as the argument of the same name supplied to image or imagep

- breaks and col, vectors of breakpoints and colours, suitable as the same-named arguments to image or imagep
- zclip the provided value of zclip.
- x0 and x1, numerical vectors of the sides of colour intervals, and col0 and col1, vectors of corresponding colours. The meaning is the same as on input. The purpose of returning these four vectors is to permit users to alter colour mapping, as in example 3 in "Examples".
- missingColor, a colour that could be used to specify missing values, e.g. as the same-named argument to imagep. If this is supplied as an argument, its value is repeated in the return value. Otherwise, its value is either "gray" or, in the case of name being given, the value in the GMT colour map specification.

#### Author(s)

Dan Kelley

#### References

Information on GMT software is given at http://gmt.soest.hawaii.edu (link worked for years but failed 2015-12-12). Diagrams showing the GMT colour schemes are at http://www.geos.ed.ac.uk/it/howto/GMT/CP (link worked for years but failed 2015-12-08), and numerical specifications for some colour maps are at http://www.beamreach.org/maps/gmt/share/cpt, http://soliton.vm.bytemark.co.uk/pub/cpt-city, and other sources.

## See Also

Other things related to colors: colors, oce.colorsGebco, oce.colorsTwo

# **Examples**

```
## Example 1. colour scheme for points on xy plot
x \leftarrow seq(0, 1, length.out=40)
y \leftarrow \sin(2 * pi * x)
par(mar=c(3, 3, 1, 1))
mar <- par('mar') # prevent margin creep by drawPalette()</pre>
## First, default breaks
c <- colormap(y)</pre>
drawPalette(c$zlim, col=c$col, breaks=c$breaks)
plot(x, y, bg=c$zcol, pch=21, cex=1)
grid()
par(mar=mar)
## Second, 100 breaks, yielding a smoother palette
c <- colormap(y, breaks=100)</pre>
drawPalette(c$zlim, col=c$col, breaks=c$breaks)
plot(x, y, bg=c$zcol, pch=21, cex=1)
grid()
par(mar=mar)
```

82 colors

```
## Example 2. topographic image with a standard colour scheme
par(mfrow=c(1,1))
data(topoWorld)
cm <- colormap(name="gmt_globe")</pre>
imagep(topoWorld, breaks=cm$breaks, col=cm$col)
## Example 3. topographic image with modified colours,
## black for depths below 4km.
cm <- colormap(name="gmt_globe")</pre>
deep <- cm$x0 < -4000
cm$col0[deep] <- 'black'</pre>
cm$col1[deep] <- 'black'
cm <- colormap(x0=cm$x0, x1=cm$x1, col0=cm$col0, col1=cm$col1)
imagep(topoWorld, breaks=cm$breaks, col=cm$col)
## Example 4. image of world topography with water colorized
## smoothly from violet at 8km depth to blue
## at 4km depth, then blending in 0.5km increments
## to white at the coast, with tan for land.
cm <- colormap(x0=c(-8000, -4000, 0, 100),
                              0, 100, 5000),
               x1=c(-4000,
               col0=c("violet","blue","white","tan"),
               col1=c("blue","white","tan","yelloe"),
               blend=c(100, 8, 0))
lon <- topoWorld[['longitude']]</pre>
lat <- topoWorld[['latitude']]</pre>
z <- topoWorld[['z']]</pre>
imagep(lon, lat, z, breaks=cm$breaks, col=cm$col)
contour(lon, lat, z, levels=0, add=TRUE)
message("colormap() example 4 is broken")
## Example 5. visualize GMT style colour map
cm <- colormap(name="gmt_globe", debug=4)</pre>
plot(seq_along(cm$x0), cm$x0, pch=21, bg=cm$col0)
grid()
points(seq_along(cm$x1), cm$x1, pch=21, bg=cm$col1)
## End(Not run)
```

colors

Data that define some colour palettes

#### **Description**

The colors dataset is a list containing vectors of colour-scheme names, e.g. colors\$viridis holds colours for the colour palette known as Viridis, which in 2015 became the default colour palette in the matplotlib 2.0 Python library [1].

composite 83

### Author(s)

Authored by matplotlib contributes, packaged in oce by Dan Kelley

#### Source

The data come from the code in matplotlib [1].

#### References

1. Matplotlib is developed on github; see https://github.com/matplotlib/matplotlib

#### See Also

oceColorsViridis uses this dataset.

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to colors: colormap, oce.colorsGebco, oce.colorsTwo

composite

Create a composite object by averaging across good data

## **Description**

Items within the data slots of the objects that are supplied as arguments are averaged in a way that makes sense for the object class, i.e. taking into account the particular bad-data codes of that particular class.

## Usage

```
composite(object, ...)
```

## **Arguments**

object Either a list of oce-class objects, in which case this is the only argument, or a

single oce-class object, in which case at least one other argument (an object of

the same size) must be supplied.

... Ignored, if object is a list. Otherwise, one or more oce-class objects of the

same sub-class as the first argument.

## See Also

Other functions that create composite objects: composite, amsr-method, composite, list-method

composite, amsr-method Create a composite of amsr satellite data

## **Description**

Items within the data slots of the objects that are supplied as arguments are averaged in a way that makes sense for the object class, i.e. taking into account the particular bad-data codes of that particular class.

### Usage

```
## S4 method for signature 'amsr'
composite(object, ...)
```

## **Arguments**

object An object inheriting from amsr-class.

... Other amsr objects.

#### **Details**

Form averages for each item in the data slot of the supplied objects, taking into account the baddata codes. If none of the objects has good data at any particular pixel (i.e. particular latitude and longitude), the resultant will have the bad-data code of the last item in the argument list. The metadata in the result are taken directly from the metadata of the final argument, except that the filename is set to a comma-separated list of the component filenames.

## See Also

Other things related to amsr data: [[<-,amsr-method,amsr-class,download.amsr,plot,amsr-method,read.amsr,subset,amsr-method,summary,amsr-method

Other functions that create composite objects: composite, list-method, composite

composite, list-method Composite by Averaging Across Data

## **Description**

This is done by calling a specialized version of the function defined in the given class. In the present version, the objects must inherit from amsr-class, so the action is to call composite, amsr-method.

Items within the data slots of the objects that are supplied as arguments are averaged in a way that makes sense for the object class, i.e. taking into account the particular bad-data codes of that particular class.

coriolis 85

## Usage

```
## S4 method for signature 'list'
composite(object)
```

## **Arguments**

object A list of oce-class objects.

## See Also

Other functions that create composite objects: composite, amsr-method, composite

coriolis

Coriolis parameter on rotating earth

# Description

Compute f, the Coriolis parameter as a function of latitude [1], assuming earth siderial angular rotation rate omega=7292115e-11 rad/s. See [1] for general notes, and see [2] for comments on temporal variations of omega.

# Usage

```
coriolis(latitude, degrees = TRUE)
```

# Arguments

latitude Vector of latitudes in °N or radians north of the equator.

degrees Flag indicating whether degrees are used for latitude; if set to FALSE, radians are

used.

## Value

Coriolis parameter [radian/s].

## Author(s)

Dan Kelley

#### References

- 1. Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.
- 2. Groten, E., 2004: Fundamental Parameters and Current, 2004. Best Estimates of the Parameters of Common Relevance to Astronomy, Geodesy, and Geodynamics. Journal of Geodesy, 77:724-797. (downloaded from http://www.iag-aig.org/attach/e354a3264d1e420ea0a9920fe762f2a0/51-groten.pdf March 11, 2017).

86 ctd

## **Examples**

```
C <- coriolis(45) # 1e-4
```

ctd

A CTD profile in Halifax Harbour

## **Description**

This is a CTD profile measured in Halifax Harbour in 2003, based on ctdRaw, but trimmed to just the downcast with ctdTrim, using indices inferred by inspection of the results from plotScan.

## Usage

data(ctd)

#### **Details**

This station was sampled by students enrolled in the Dan Kelley's Physical Oceanography class at Dalhousie University. The data were acquired near the centre of the Bedford Basin of the Halifax Harbour, during an October 2003 field trip of Dalhousie University's Oceanography 4120/5120 class. The original .cnv data file had temperature in the IPTS-68 scale, but this was converted to the more modern scale using T90fromT68.

#### See Also

The full profile (not trimmed to the downcast) is available as data(ctdRaw).

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

# **Examples**

```
## Not run:
library(oce)
data(ctd)
plot(ctd)
## End(Not run)
```

ctd-class 87

ctd-class

Class to Store CTD (or general hydrographic) Data

# **Description**

Class to store hydrographic data such as measured with a CTD (conductivity, temperature, depth) instrument, or with other systems that produce similar data. Data repositories may store conductivity, temperature and depth, as in the instrument name, but it is also common to store salinity, temperature and pressure instead (or in addition). For this reason, ctd objects are required to hold salinity, temperature and pressure in their data slot, with other data being optional. Formulae are available for converting between variants of these data triplets, e.g. swSCTp can calculate salinity given conductivity, temperature and pressure, and these are used by the main functions that create ctd objects. For example, if read.ctd.sbe is used to read a Seabird file that contains only conductivity, temperature and pressure, then that function will automatically append a data item to hold salinity. as.ctd acts similarly. The result this is that all ctd objects hold salinity, temperature and pressure, which are henceforth called the three basic quantities.

## **Details**

Different units and scales are permitted for the three basic quantities, and most oce functions check those units and scales before doing calculations (e.g. of seawater density), because those calculations demand certain units and scales. The way this is handled is that the accessor function <code>[[,ctd-method</code> returns values in standardized form. For example, a ctd object might hold temperature defined on the IPTS-68 scale, but e.g. ctd[["temperature"]] returns a value on the ITS-90 scale. (The conversion is done with T90fromT68.) Similarly, pressure may be stored in either dbars or PSI, but e.g. ctd[["pressure"]] returns a value in dbars, after multiplying by 0.689476 if the value is stored in PSI. Luckily, there is (as of early 2016) only one salinity scale in common use in data files, namely PSS-78.

The TEOS-10 notation for these quantities also works, with ctd[["SP"]], ctd[["t"]] and ctd[["p"]] returning identical values to those returned for the longer names.

After the names listed above have been checked, the remaining names in the data slot are checked using pmatch, so that e.g. ctd[["sal"]] will recover practical salinity, ctd[["sc"]] will recover scan (if it exists), etc.

#### Accessing data

Data may be extracted with <code>[[,ctd-method</code> and inserted with <code>[[<-,ctd-method</code>. As noted above, <code>[[,ctd-method</code> returns temperature in the ITS-90 scale and pressure in dbar, regardless of the scale and unit of the data within the object. Type <code>?"[[,ctd-method"</code> or <code>?"[[<-,ctd-method"</code> to learn more.

Depth is accessed with e.g. ctd[["depth"]], while its negative, the vertical coordinate, is accessed with e.g. ctd[["z"]]; note that these are calculated using swDepth and swZ, and that any values that may have been read in a data file are ignored.

Potential temperature defined according to UNESCO-1980 is calculated with ctd[["theta"]] or ctd[["potential temperature"]]. Salinity is retrieved with ctd[["S"]] or ctd[["salinity"]].

88 ctd-class

Conservative Temperature defined according to TEOS-2010 is calculated with ctd[["CT"]] or ctd[["conservative temperature"]]. Absolute salinity is calculated with ctd[["SA"]] or ctd[["absolute salinity"]]. Note that the CT, SA and Sstar calculations require latitude and longitude, and so errors result if these items are sought for a ctd object that lacks latitude or longitude. (Until 2017 May 14, defaults of 300E and 30N were used if position was not stored in the object.)

The square of buoyancy frequency is retrieved with ctd[["N2"]] or swN2, density ratio with ctd[["Rrho"]] and spiciness with ctd[["spice"]].

### **Extracting values**

Items stored in the object may be altered with e.g. ctd[["salinity"]] <- rep(35,10). For obvious reasons, this does not work with derived quantities such as conservative temperature, etc.

# Reading/creating data

A file containing CTD profile data may be read with read.ctd, and a CTD object can also be created with as.ctd. See read.ctd for references on data formats used in CTD files. Data can also be assembled into ctd objects with as.ctd.

Statistical summaries are provided by summary, ctd-method, while show displays an overview.

CTD objects may be plotted with plot,ctd-method, which does much of its work by calling plotProfile or plotTS, both of which can also be called by the user, to get fine control over the plots.

A CTD profile can be isolated from a larger record with ctdTrim, a task made easier when plotScan is used to examine the results. Towyow data can be split up into sets of profiles (ascending or descending) with ctdFindProfiles. CTD data may be smoothed and/or cast onto specified pressure levels with ctdDecimate.

As with all oce objects, low-level manipulation may be done with oceSetData and oceSetMetadata. Additionally, many of the contents of CTD objects may be altered with the [[,ctd-method scheme discussed above, and skilled users may also manipulate the contents directly.

### Author(s)

Dan Kelley

### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

ctdAddColumn 89

ctdAddColumn Add a Column to the Data Slot of a CTD Object [deprecated]
---

# Description

**WARNING:** This function will be removed soon; see oce-deprecated. Use oceSetData instead of the present function.

# Usage

```
ctdAddColumn(x, column, name, label, unit = NULL, log = TRUE,
  originalName = "", debug = getOption("oceDebug"))
```

# **Arguments**

A ctd object, i.e. one inheriting from ctd-class.  column A column of data to be inserted, in the form of a numeric vector, whose length matches that of columns in the object.  name Character string indicating the name this column is to have in the data slot of x.  label Optional character string or expression indicating the name of the column, as it will appear in plot labels. (If not given, name will be used.)  unit Optional indication of the unit, in the form of a list containing items unit, which is an expression, and scale, which is a character string. For example, modern measurements of temperature have unit list(name=expression(degree*C), scale="ITS-96")  log A logical value indicating whether to store an entry in the processing log that indicates this insertion.  originalName string indicating the name of the data element as it was originally. This makes sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.		
matches that of columns in the object.  Character string indicating the name this column is to have in the data slot of x.  Optional character string or expression indicating the name of the column, as it will appear in plot labels. (If not given, name will be used.)  unit Optional indication of the unit, in the form of a list containing items unit, which is an expression, and scale, which is a character string. For example, modern measurements of temperature have unit list(name=expression(degree*C), scale="ITS=96")  log A logical value indicating whether to store an entry in the processing log that indicates this insertion.  originalName string indicating the name of the data element as it was originally. This makes sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	х	A ctd object, i.e. one inheriting from ctd-class.
Optional character string or expression indicating the name of the column, as it will appear in plot labels. (If not given, name will be used.)  unit Optional indication of the unit, in the form of a list containing items unit, which is an expression, and scale, which is a character string. For example, modern measurements of temperature have unit list(name=expression(degree*C), scale="ITS-96") A logical value indicating whether to store an entry in the processing log that indicates this insertion.  originalName string indicating the name of the data element as it was originally. This makes sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	column	· · · · · · · · · · · · · · · · · · ·
will appear in plot labels. (If not given, name will be used.)  unit  Optional indication of the unit, in the form of a list containing items unit, which is an expression, and scale, which is a character string. For example, modern measurements of temperature have unit list(name=expression(degree*C), scale="ITS-96" log  A logical value indicating whether to store an entry in the processing log that indicates this insertion.  originalName string indicating the name of the data element as it was originally. This makes sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	name	Character string indicating the name this column is to have in the data slot of x.
is an expression, and scale, which is a character string. For example, modern measurements of temperature have unit list(name=expression(degree*C), scale="ITS-90") log  A logical value indicating whether to store an entry in the processing log that indicates this insertion.  originalName string indicating the name of the data element as it was originally. This makes sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	label	
indicates this insertion.  originalName string indicating the name of the data element as it was originally. This makes sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	unit	· ·
sense only for data being read from a file, where e.g. WOCE or SBE names might be used.  debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	log	· · · · · · · · · · · · · · · · · · ·
processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by	originalName	sense only for data being read from a file, where e.g. WOCE or SBE names
	debug	processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

# **Details**

Add a column to the data slot of an object of ctd-class, also updating the metadata slot as appropriate.

# Value

A ctd object.

90 ctdDecimate

### Author(s)

Dan Kelley

#### See Also

The documentation for ctd-class explains the structure of CTD objects, and also outlines the other functions dealing with them.

Other functions that will be removed soon: addColumn, ctdUpdateHeader, mapMeridians, mapZones, oce.as.POSIXlt

## **Examples**

```
library(oce)
data(ctd)
F <- 32 + (9/5)*ctd[["temperature"]]
ctdNew <- ctdAddColumn(ctd, F, "temperatureF",</pre>
    unit=list(unit=expression(degree*F), scale="ITS-90"))
```

ctdDecimate

Decimate a CTD profile

## **Description**

Interpolate a CTD profile to specified pressure values.

# Usage

```
ctdDecimate(x, p = 1, method = "boxcar", rule = 1, e = 1.5,
  debug = getOption("oceDebug"))
```

#### **Arguments**

р

Х

A ctd object, i.e. one inheriting from ctd-class.

pressure increment, or vector of pressures. In the first case, pressures from Odbar to the rounded maximum pressure are used, incrementing by p dbars. If a vector of pressures is given, interpolation is done to these pressures.

method

the method to be used for calculating decimated values. This may be a function or a string naming a built-in method. The built-in methods are "boxcar" (based on a local average), "approx" (based on linear interpolation between neighboring points, using approx with the rule argument specified here), "lm" (based on local regression, with e setting the size of the local region), "rr" (for the Reiniger and Ross method, carried out with oce.approx) and "unesco" (for the UNESCO method, carried out with. oce.approx. If method is a function, then it must take three arguments, the first being pressure, the second being an arbitrary variable in another column of the data, and the third being a vector of target pressures at which the calculation is carried out, and the return value must be a vector. See "Examples".

ctdDecimate 91

rule an integer that is passed to approx, in the case where method is "approx". Note

that the default value for rule is 1, which will inhibit extrapolation beyond the observed pressure range. This is a change from the behaviour previous to May

8, 2017, when a rule of 2 was used (without stating so as an argument).

is an expansion coefficient used to calculate the local neighbourhoods for the "boxcar" and "lm" methods. If e=1, then the neighbourhood for the i-th pressure extends from the (i-1)-th pressure to the (i+1)-th pressure. At the endpoints it is assumed that the outside bin is of the same pressure range as the first inside bin. For other values of e, the neighbourhood is expanded linearly in each direction. If the "lm" method produces warnings about "prediction from a

rank-deficient fit", a larger value of "e" should be used.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### **Details**

е

The "approx" method is best for bottle data, in which the usual task is to interpolate from a coarse sampling grid to a finer one. For CTD data, the "boxcar" method is the more common choice, because the task is normally to sub-sample, and some degree of smoothing is usually desired. (The "1m" method is quite slow, and the results are similar to those of the boxcar method.)

Note that a sort of numerical cabeling effect can result from this procedure, but it can be avoided as follows

```
xd <- ctdDecimate(x)
xd[["sigmaTheta"]] <- swSigmaTheta(xd[["salinity"]],xd[["temperature"]],xd[["pressure"]])</pre>
```

### Value

An object of ctd-class, with pressures that are as set by the "p" parameter and all other properties modified appropriately.

#### A note about flags

Data-quality flags contained within the original object are ignored by this function, and the returned value contains no such flags. This is because such flags represent an assessment of the original data, not of quantities derived from those data. This function produces a warning to this effect. The recommended practice is to use handleFlags or some other means to deal with flags before calling the present function.

# Author(s)

Dan Kelley

92 ctdFindProfiles

#### References

R.F. Reiniger and C.K. Ross, 1968. A method of interpolation with application to oceanographic data. *Deep Sea Research*, **15**, 185-193.

#### See Also

The documentation for ctd-class explains the structure of CTD objects, and also outlines the other functions dealing with them.

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

## **Examples**

ctdFindProfiles

Find Profiles within a Tow-Yow CTD Record

## **Description**

Examine the pressure record looking for extended periods of either ascent or descent, and return either indices to these events or a vector of CTD records containing the events.

## Usage

```
ctdFindProfiles(x, cutoff = 0.5, minLength = 10, minHeight = 0.1 *
    diff(range(x[["pressure"]])), smoother = smooth.spline,
    direction = c("descending", "ascending"), breaks, arr.ind = FALSE,
    distinct, debug = getOption("oceDebug"), ...)
```

ctdFindProfiles 93

#### **Arguments**

x A ctd object, i.e. one inheriting from ctd-class.

cutoff criterion on pressure difference; see "Details".

minLength lower limit on number of points in candidate profiles.

minHeight lower limit on height of candidate profiles.

smoother The smoothing function to use for identifying down/up casts. The default is

smooth.spline, which performs well for a small number of cycles; see "Examples" for a method that is better for a long tow-yo. The return value from smoother must be either a list containing an element named y or something that can be coerced to a vector with as.vector. To turn smoothing off, so that cycles in pressure are determined by simple first difference, set smoother to NULL.

direction String indicating the travel direction to be selected.

breaks optional integer vector indicating the indices of last datum in each profile stored

within x. Thus, the first profile in the return value will contain the x data from indices 1 to breaks[1]. If breaks is given, then all other arguments except x are ignored. Using breaks is handy in cases where other schemes fail, or when the author has independent knowledge of how the profiles are strung together in

x; see example 3 for how breaks might be used for towyo data.

arr.ind Logical indicating whether the array indices should be returned; the alternative

is to return a vector of ctd objects.

distinct An optional string indicating how to identify profiles by unique values. Use

"location" to find profiles by a change in longitude and latitude, or use the name of any of item in the data slot in x. In these cases, all the other arguments except x are ignored. However, if distinct is not supplied, the other arguments

are handled as described above.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

... Optional extra arguments that are passed to the smoothing function, smoother.

### Details

The method works by examining the pressure record. First, this is smoothed using smoother() (see "Arguments"), and then the result is first-differenced using diff. Median values of the positive and negative first-difference values are then multiplied by cutoff. This establishes criteria for any given point to be in an ascending profile, a descending profile, or a non-profile. Contiguous regions are then found, and those that have fewer than minLength points are discarded. Then, those that have pressure ranges less than minHeight are discarded.

Caution: this method is not well-suited to all datasets. For example, the default value of smoother is smooth.spline, and this works well for just a few profiles, but poorly for a tow-yo with a long sequence of profiles; in the latter case, it can be preferable to use simpler smoothers (see "Examples"). Also, depending on the sampling protocol, it is often necessary to pass the resultant

94 ctdFindProfiles

profiles through ctdTrim, to remove artifacts such as an equilibration phase, etc. Generally, one is well-advised to use the present function for a quick look at the data, relying on e.g. plotScan to identify profiles visually, for a final product.

#### Value

If arr.ind=TRUE, a data frame with columns start and end, the indices of the downcasts. Otherwise, a vector of ctd objects. In this second case, the station names are set to a form like "10/3", for the third profile within an original ctd object with station name "10", or to "3", if the original ctd object had no station name defined.

## Author(s)

Dan Kelley and Clark Richards

#### See Also

The documentation for ctd-class explains the structure of CTD objects, and also outlines the other functions dealing with them.

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

# **Examples**

```
## Not run:
library(oce)
## Example 1.
d <- read.csv("towyow.csv", header=TRUE)</pre>
towyow <- as.ctd(d$salinity, d$temperature, d$pressure)</pre>
casts <- ctdFindProfiles(towyow)</pre>
par(mfrow=c(length(casts), 3))
for (cast in casts) {
 plotProfile(cast, "salinity")
 plotProfile(cast, "temperature")
 plotTS(cast, type='o')
}
## Example 2.
## Using a moving average to smooth pressure, instead of the default
## smooth.spline() method. This avoids a tendency of smooth.spline()
## to smooth out the profiles in a tow-yo with many (dozens or more) cycles.
movingAverage <- function(x, n = 11, ...)
{
   f \leftarrow rep(1/n, n)
   stats::filter(x, f, ...)
casts <- ctdFindProfiles(towyo, smoother=movingAverage)</pre>
```

ctdRaw 95

```
## Example 3: glider data, with profiles separated by >10dbar jump.
breaks <- which(diff(ctd[["pressure"]]) > 10))
profiles <- ctdFindProfiles(ctd, breaks=breaks)
## End(Not run)</pre>
```

ctdRaw

Seawater CTD Profile, Without Trimming of Extraneous Data

## **Description**

This is sample CTD profile provided for testing. It includes not just the (useful) portion of the dataset during which the instrument was being lowered, but also data from the upcast and from time spent near the surface. Spikes are also clearly evident in the pressure record. With such real-world wrinkles, this dataset provides a good example of data that need trimming with ctdTrim.

### **Usage**

data(ctdRaw)

## **Details**

This station was sampled by students enrolled in the Dan Kelley's Physical Oceanography class at Dalhousie University. The data were acquired near the centre of the Bedford Basin of the Halifax Harbour, during an October 2003 field trip of Dalhousie University's Oceanography 4120/5120 class. The original .cnv data file had temperature in the IPTS-68 scale, but this was converted to the more modern scale using T90fromT68.

#### See Also

A similar dataset (trimmed to the downcast) is available as data(ctd).

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

96 ctdTrim

ctdTrim

Trim Beginning and Ending of a CTD cast

### **Description**

Often in CTD profiling, the goal is to isolate only the downcast, discarding measurements made in the air, in an equilibration phase in which the device is held below the water surface, and then the upcast phase that follows the downcast. This is handled reasonably well by ctdTrim with method="downcast", although it is almost always best to use plotScan to investigate the data, and then use the method="index" or method="scan" method based on visual inspection of the data.

## Usage

```
ctdTrim(x, method, removeDepthInversions = FALSE, parameters = NULL,
  debug = getOption("oceDebug"))
```

## **Arguments**

Χ

A ctd object, i.e. one inheriting from ctd-class.

method

A string (or a vector of two strings) specifying the trimming method, or a function to be used to determine data indices to keep. If method is not provided, "downcast" is assumed. See "Details".

removeDepthInversions

Logical value indicating whether to remove any levels at which depth is less than, or equal to, a depth above. (This is needed if the object is to be assembled into a section, unless ctdDecimate will be used, which will remove the inversions.

parameters

A list whose elements depend on the method; see "Details".

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

#### **Details**

ctdTrim begins by examining the pressure differences between subsequent samples. If these are all of the same value, then the input ctd object is returned, unaltered. This handles the case of pressure-binned data. However, if the pressure difference varies, a variety of approaches are taken to trimming the dataset.

• If method[1] is "downcast" then an attempt is made to keep only data for which the CTD is descending. This is done in stages, with variants based on method[2], if supplied. *Step 1*. The pressure data are despiked with a smooth() filter with method "3R". This removes wild spikes that arise from poor instrument connections, etc. *Step 2*. If no parameters are given, then

ctdTrim 97

any data with negative pressures are deleted. If there is a parameter named pmin, then that pressure (in decibars) is used instead as the lower limit. This is a commonly-used setup, e.g. ctdTrim(ctd, parameters=list(pmin=1)) removes the top decibar (roughly 1m) from the data. Specifying pmin is a simple way to remove near-surface data, such as a shallow equilibration phase, and if specified will cause ctdTrim to skip step 4 below. Step 3. The maximum pressure is determined, and data acquired subsequent to that point are deleted. This removes the upcast and any subsequent data. Step 4. If the pmin parameter is not specified, an attempt is made to remove an initial equilibrium phase by a regression of pressure on scan number. There are three variants to this, depending on the value of the second method element. If it is "A" (or not given), the procedure is to call nls to fit a piecewise linear model of pressure as a function of scan, in which pressure is constant for scan less than a critical value, and then linearly varying for with scan. This is meant to handle the common situation in which the CTD is held at roughly constant depth (typically a metre or so) to equilibrate, before it is lowered through the water column. Case "B" is the same, except that the pressure in the surface region is taken to be zero (this does not make much sense, but it might help in some cases). Note that, prior to early 2016, method "B" was called method "C"; the old "B" method was judged useless and was removed.

- If method="upcast", a sort of reverse of "downcast" is used. This was added in late April 2017 and has not been well tested yet.
- If method="sbe", a method similar to that described in the SBE Data Processing manual is used to remove the "soak" period at the beginning of a cast (see Section 6 under subsection "Loop Edit"). The method is based on the soak procedure whereby the instrument sits at a fixed depth for a period of time, after which it is raised toward the surface before beginning the actual downcast. This enables equilibration of the sensors while still permitting reasonably good near-surface data. Parameters for the method can be passed using the parameters argument, which include minSoak (the minimum depth for the soak) and maxSoak the maximum depth of the soak. The method finds the minimum pressure prior to the maxSoak value being passed, each of which occurring after the scan in which the minSoak value was reached. For the method to work, the pre-cast pressure minimum must be less than the minSoak value. The default values of minSoak and maxSoak are 1 and 20 dbar, respectively.
- If method="index" or "scan", then each column of data is subsetted according to the value of parameters. If the latter is a logical vector of length matching data column length, then it is used directly for subsetting. If parameters is a numerical vector with two elements, then the index or scan values that lie between parameters[1] and parameters[2] (inclusive) are used for subsetting. The two-element method is probably the most useful, with the values being determined by visual inspection of the results of plotScan. While this may take a minute or two, the analyst should bear in mind that a deep-water CTD profile might take 6 hours, corresponding to ship-time costs exceeding a week of salary.
- If method="range" then data are selected based on the value of the column named parameters\$item. This may be by range or by critical value. By range: select values between parameters\$from (the lower limit) and parameters\$to (the upper limit) By critical value: select if the named column exceeds the value. For example, ctd2 <- ctdTrim(ctd, "range", parameters=list(item="scan", from starts at scan number 5 and continues to the end, while ctdTrim(ctd, "range", parameters=list(item="scan", from also starts at scan 5, but extends only to scan 100.
- If method is a function, then it must return a vector of logical values, computed based on two arguments: data (a list), and parameters as supplied to ctdTrim. Both inferWaterDepth and removeInversions are ignored in the function case. See "Examples".

98 ctdUpdateHeader

#### Value

An object of ctd-class, with data having been trimmed in some way.

#### Author(s)

Dan Kelley and Clark Richards

### References

The Seabird CTD instrument is described at http://www.seabird.com/products/spec\_sheets/19plusdata.htm. Seasoft V2: SBE Data Processing, SeaBird Scientific, 05/26/2016

#### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

## **Examples**

```
## Not run:
library(oce)
data(ctdRaw)
plot(ctdRaw) # barely recognizable, due to pre- and post-cast junk
plot(ctdTrim(ctdRaw)) # looks like a real profile ...
plot(ctdDecimate(ctdTrim(ctdRaw),method="boxcar")) # ... smoothed
# Demonstrate use of a function. The scan limits were chosen
# by using locator(2) on a graph made by plotScan(ctdRaw).
trimByIndex<-function(data, parameters) {
   parameters[1] < data$scan & data$scan < parameters[2]
}
trimmed <- ctdTrim(ctdRaw, trimByIndex, parameters=c(130, 380))
plot(trimmed)
## End(Not run)</pre>
```

ctdUpdateHeader

Update a CTD Header [deprecated]

## **Description**

**WARNING:** This function will be removed soon; see oce-deprecated.

#### Usage

```
ctdUpdateHeader(x, debug = FALSE)
```

ctimeToSeconds 99

# Arguments

x A ctd object, i.e. one inheriting from ctd-class.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### **Details**

Update the header of a ctd object, e.g. adjusting nvalues and the span of each column. This is done automatically by ctdTrim, for example.

### Value

A new ctd-class object.

## Author(s)

Dan Kelley

#### References

The Seabird CTD instrument is described at http://www.seabird.com/products/spec\_sheets/19plusdata.htm.

## See Also

Other functions that will be removed soon: addColumn, ctdAddColumn, mapMeridians, mapZones, oce.as.POSIXlt

# Examples

```
library(oce)
data(ctd)
ctd[["pressure"]] <- ctd[["pressure"]] + 3
ctdNew <- ctdUpdateHeader(ctd)</pre>
```

ctimeToSeconds

Interpret a character string as a time interval

## **Description**

Interpret a character string as a time interval Strings are of the form MM:SS or HH:MM:SS.

100 curl

## Usage

```
ctimeToSeconds(ctime)
```

# **Arguments**

ctime

a character string (see 'Details'.

# Value

A numeric value, the number of seconds represented by the string.

# Author(s)

Dan Kelley

# See Also

See secondsToCtime, the inverse of this.

Other things related to time: julianCenturyAnomaly, julianDay, numberAsHMS, numberAsPOSIXct, secondsToCtime, unabbreviateYear

# **Examples**

curl

Curl of 2D vector field

# **Description**

Calculate the z component of the curl of an x-y vector field.

# Usage

```
curl(u, v, x, y, geographical = FALSE, method = 1)
```

curl 101

### **Arguments**

u	matrix containing the 'x' component of a vector field
V	matrix containing the 'y' component of a vector field
X	the $x$ values for the matrices, a vector of length equal to the number of rows in $u$ and $v$ .
У	the y values for the matrices, a vector of length equal to the number of cols in $\boldsymbol{u}$ and $\boldsymbol{v}$ .
geographical	logical value indicating whether x and y are longitude and latitude, in which case spherical trigonometry is used.
method	A number indicating the method to be used to calculate the first-difference approximations to the derivatives. See "Details".

#### **Details**

The computed component of the curl is defined by  $\partial v/\partial x - \partial u/\partial y$  and the estimate is made using first-difference approximations to the derivatives. Two methods are provided, selected by the value of method.

- For method=1, a centred-difference, 5-point stencil is used in the interior of the domain. For example,  $\partial v/\partial x$  is given by the ratio of  $v_{i+1,j}-v_{i-1,j}$  to the x extent of the grid cell at index j. (The cell extents depend on the value of geographical.) Then, the edges are filled in with nearest-neighbour values. Finally, the corners are filled in with the adjacent value along a diagonal. If geographical=TRUE, then x and y are taken to be longitude and latitude in degrees, and the earth shape is approximated as a sphere with radius 6371km. The resultant x and y are identical to the provided values, and the resultant curl is a matrix with dimension identical to that of u.
- For method=2, each interior cell in the grid is considered individually, with derivatives calculated at the cell center. For example,  $\partial v/\partial x$  is given by the ratio of  $0.5*(v_{i+1,j}+v_{i+1,j+1})-0.5*(v_{i,j}+v_{i,j+1})$  to the average of the x extent of the grid cell at indices j and j+1. (The cell extents depend on the value of <code>geographical</code>.) The returned x and y values are the midpoints of the supplied values. Thus, the returned x and y are shorter than the supplied values by 1 item, and the returned <code>curl</code> matrix dimensions are similarly reduced compared with the dimensions of u and v.

### Value

A list containing vectors x and y, along with matrix curl. See "Details" for the lengths and dimensions, for various values of method.

# Development status.

This function is under active development as of December 2014 and is unlikely to be stabilized until February 2015.

#### Author(s)

Dan Kelley and Chantelle Layton

102 dataLabel

## See Also

Other functions relating to vector calculus: grad

## **Examples**

```
library(oce)
## 1. Shear flow with uniform curl.
x < -1:4
y < -1:10
u \leftarrow outer(x, y, function(x, y) y/2)
v \leftarrow outer(x, y, function(x, y) -x/2)
C <- curl(u, v, x, y, FALSE)
## 2. Rankine vortex: constant curl inside circle, zero outside
rankine <- function(x, y)
    r \leftarrow sqrt(x^2 + y^2)
    theta \leftarrow atan2(y, x)
    speed <- ifelse(r < 1, 0.5*r, 0.5/r)
    list(u=-speed*sin(theta), v=speed*cos(theta))
}
x \leftarrow seq(-2, 2, length.out=100)
y <- seq(-2, 2, length.out=50)
u \leftarrow outer(x, y, function(x, y) rankine(x, y)$u)
v <- outer(x, y, function(x, y) rankine(x, y)$v)</pre>
C \leftarrow curl(u, v, x, y, FALSE)
## plot results
par(mfrow=c(2, 2))
imagep(x, y, u, zlab="u", asp=1)
imagep(x, y, v, zlab="v", asp=1)
imagep(x, y, C$curl, zlab="curl", asp=1)
hist(C$curl, breaks=100)
```

dataLabel

Try to associate data names with units, for use by summary()

# Description

Note that the whole object is not being given as an argument; possibly this will reduce copying and thus storage impact.

## Usage

```
dataLabel(names, units)
```

# Arguments

names the names of data within an object units the units from metadata

decimate 103

# Value

a vector of strings, with blank entries for data with unknown units

## **Examples**

```
library(oce)
data(ctd)
dataLabel(names(ctd@data), ctd@metadata$units)
```

decimate

Smooth and Decimate, or Subsample, an Oce Object

# Description

Later on, other methods will be added, and ctdDecimate will be retired in favour of this, a more general, function. The filtering is done with the filter function of the stats package.

## Usage

```
decimate(x, by = 10, to, filter, debug = getOption("oceDebug"))
```

## **Arguments**

Х	an oce object containing a data element.
by	an indication of the subsampling. If this is a single number, then it indicates the spacing between elements of x that are selected. If it is two numbers (a condition only applicable if x is an echosounder object, at present), then the first number indicates the time spacing and the second indicates the depth spacing.
to	Indices at which to subsample. If given, this over-rides by.
filter	optional list of numbers representing a digital filter to be applied to each variable in the data slot of x, before decimation is done. If not supplied, then the decimation is done strictly by sub-sampling.
debug	a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

# Value

An object of class "oce" that has been subsampled appropriately.

# **Bugs**

Only a preliminary version of this function is provided in the present package. It only works for objects of class echosounder, for which the decmation is done after applying a running median filter and then a boxcar filter, each of length equal to the corresponding component of by.

104 decodeHeaderNortek

### Author(s)

Dan Kelley

#### See Also

Filter coefficients may be calculated using makeFilter. (Note that ctdDecimate will be retired when the present function gains equivalent functionality.)

## **Examples**

```
library(oce)
data(adp)
plot(adp)
adpDec <- decimate(adp,by=2,filter=c(1/4, 1/2, 1/4))
plot(adpDec)</pre>
```

decodeHeaderNortek

Decode a Nortek Header

## **Description**

Decode data in a Nortek ADV or ADP header.

## Usage

```
decodeHeaderNortek(buf, type = c("aquadoppHR", "aquadoppProfiler", "aquadopp",
    "vector"), debug = getOption("oceDebug"), ...)
```

# Arguments

buf a "raw" buffer containing the header

type type of device

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

## Details

Decodes the header in a binary-format Nortek ADV/ADP file. This function is designed to be used by read.adp and read.adv, but can be used directly as well. The code is based on information in the Nortek System Integrator Guide (2008) and on postings on the Nortek "knowledge center" discussion board. One might assume that the latter is less authoritative than the former. For example, the inference of cell size follows advice found at http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717 (downloaded June 2012)), which contains a typo in an early posting that is corrected later on.

decodeTime 105

## Value

A list containing elements hardware, head, user and offset. The easiest way to find the contents of these is to run this function with debug=3.

#### Author(s)

Dan Kelley and Clark Richards

#### References

- 1. Information on Nortek profilers (including the System Integrator Guide, which explains the data format byte-by-byte) is available at <a href="http://www.nortekusa.com/">http://www.nortekusa.com/</a>. (One must join the site to see the manuals.)
- 2. The Nortek Knowledge Center <a href="http://www.nortekusa.com/en/knowledge-center">http://www.nortekusa.com/en/knowledge-center</a> may be of help if problems arise in dealing with data from Nortek instruments.

## See Also

Most users should employ the functions read.adp and read.adv instead of this one.

decodeTime

Oce Version of as.POSIXct

# Description

Oce Version of as.POSIXct

#### **Usage**

```
decodeTime(time, timeFormats, tz = "UTC")
```

## Arguments

time Character string with an indication of the time.

timeFormats Optional vector of time formats to use, as for as.POSIXct.

tz Time zone.

## **Details**

Each format in timeFormats is used in turn as the format argument to as.POSIXct, and the first that produces a non-NA result is used. If timeFormats is missing, the following formats are tried, in the stated order:

```
• "%b %d %Y %H:%M:%S" (e.g. "Jul 1 2013 01:02:03")
```

- "%b %d %Y" (e.g. "Jul 1 2013")
- "%B %d %Y %H:%M:%S" (e.g. "July 1 2013 01:02:03")

106 decodeTime

- "%B %d %Y" (e.g. "July 1 2013")
- "%d %b %Y %H:%M:%S" (e.g. "1 Jul 2013 01:02:03")
- "%d %b %Y" (e.g. "1 Jul 2013")
- "%d %B %Y %H:%M:%S" (e.g. "1 July 2013 01:02:03")
- "%d %B %Y" (e.g. "1 July 2013")
- "%Y-%m-%d %H:%M:%S" (e.g. "2013-07-01 01:02:03")
- "%Y-%m-%d" (e.g. "2013-07-01")
- "%Y-%b-%d %H:%M:%S" (e.g. "2013-July-01 01:02:03")
- "%Y-%b-%d" (e.g. "2013-Jul-01")
- "%Y-%B-%d %H:%M:%S" (e.g. "2013-July-01 01:02:03")
- "%Y-%B-%d" (e.g. "2013-July-01")
- "%d-%b-%Y %H:%M:%S" (e.g. "01-Jul-2013 01:02:03")
- "%d-%b-%Y" (e.g. "01-Jul-2013")
- "%d-%B-%Y %H:%M:%S" (e.g. "01-July-2013 01:02:03")
- "%d-%B-%Y" (e.g. "01-July-2013")
- "%Y/%b/%d %H:%M:%S" (e.g. "2013/Jul/01 01:02:03")
- "%Y/%b/%d" (e.g. "2013/Jul/01")
- "%Y/%B/%d %H:%M:%S" (e.g. "2013/July/01 01:02:03")
- "%Y/%B/%d" (e.g. "2013/July/01")
- "%Y/%m/%d %H:%M:%S" (e.g. "2013/07/01 01:02:03")
- "%Y/%m/%d" (e.g. "2013/07/01")

#### Value

A time as returned by as.POSIXct.

## Author(s)

Dan Kelley

## See Also

Other functions relating to time: GMTOffsetFromTz

## **Examples**

```
decodeTime("July 1 2013 01:02:03")
decodeTime("Jul 1 2013 01:02:03")
decodeTime("1 July 2013 01:02:03")
decodeTime("1 Jul 2013 01:02:03")
decodeTime("2013-07-01 01:02:03")
decodeTime("2013/07/01 01:02:03")
decodeTime("2013/07/01")
```

despike 107

es		

Remove spikes from a time series

### **Description**

The method identifies spikes with respect to a "reference" time-series, and replaces these spikes with the reference value, or with NA according to the value of action; see "Details".

## Usage

```
despike(x, reference = c("median", "smooth", "trim"), n = 4, k = 7,
  min = NA, max = NA, replace = c("reference", "NA"), skip)
```

### Arguments

X	a vector of (time-series) values, a list of vectors, a data frame, or an object that inherits from class oce.
reference	indication of the type of reference time series to be used in the detection of spikes; see 'Details'.
n	an indication of the limit to differences between x and the reference time series, used for reference="median" or reference="smooth"; see 'Details.'
k	length of running median used with reference="median", and ignored for other values of reference.
min	minimum non-spike value of x, used with reference="trim".
max	maximum non-spike value of x, used with reference="trim".
replace	an indication of what to do with spike values, with "reference" indicating to replace them with the reference time series, and "NA" indicating to replace them with NA.
skip	optional vector naming columns to be skipped. This is ignored if x is a simple vector. Any items named in skip will be passed through to the return value without modification. In some cases, despike will set up reasonable defaults for skip, e.g. for a ctd object, skip will be set to c("time", "scan", "pressure") if it is not supplied as an argument.

#### **Details**

Three modes of operation are permitted, depending on the value of reference.

• For reference="median", the first step is to linearly interpolate across any gaps (spots where x==NA), using approx with rule=2. The second step is to pass this through runmed to get a running median spanning k elements. The result of these two steps is the "reference" timeseries. Then, the standard deviation of the difference between x and the reference is calculated. Any x values that differ from the reference by more than n times this standard deviation are considered to be spikes. If replace="reference", the spike values are replaced with the reference, and the resultant time series is returned. If replace="NA", the spikes are replaced with NA, and that result is returned.

108 detrend

• For reference="smooth", the processing is the same as for "median", except that smooth is used to calculate the reference time series.

• For reference="trim", the reference time series is constructed by linear interpolation across any regions in which x<min or x>max. (Again, this is done with approx with rule=2.) In this case, the value of n is ignored, and the return value is the same as x, except that spikes are replaced with the reference series (if replace="reference" or with NA, if replace="NA".

#### Value

A new vector in which spikes are replaced as described above.

## Author(s)

Dan Kelley

## **Examples**

```
n <- 50
x <- 1:n
y <- rnorm(n=n)</pre>
                                  # 10 standard deviations
y[n/2] <- 10
plot(x, y, type='l')
lines(x, despike(y), col='red')
lines(x, despike(y, reference="smooth"), col='darkgreen')
lines(x, despike(y, reference="trim", min=-3, max=3), col='blue')
legend("topright", lwd=1, col=c("black", "red", "darkgreen", "blue"),
       legend=c("raw", "median", "smooth", "trim"))
# add a spike to a CTD object
data(ctd)
plot(ctd)
T <- ctd[["temperature"]]</pre>
T[10] \leftarrow T[10] + 10
ctd[["temperature"]] <- T</pre>
CTD <- despike(ctd)
plot(CTD)
```

detrend

Detrend a set of observations

# Description

Detrends y by subtracting a linear trend in x, to create a vector that is zero for its first and last finite value. If the second parameter (y) is missing, then x is taken to be y, and a new x is constructed with seq\_along. Any NA values are left as-is.

#### Usage

```
detrend(x, y)
```

download.amsr 109

# Arguments

- x a vector of numerical values. If y is not given, then x is taken for y.
- y an optional vector

#### **Details**

A common application is to bring the end points of a time series down to zero, prior to applying a digital filter. (See examples.)

### Value

A list containing Y, the detrended version of y, and the intercept a and slope b of the linear function of x that is subtracted from y to yield Y.

### Author(s)

Dan Kelley

## **Examples**

```
x <- seq(0, 0.9 * pi, length.out=50)
y <- sin(x)
y[1] <- NA
y[10] <- NA
plot(x, y, ylim=c(0, 1))
d <- detrend(x, y)
points(x, d$Y, pch=20)
abline(d$a, d$b, col='blue')
abline(h=0)
points(x, d$Y + d$a + d$b * x, col='blue', pch='+')</pre>
```

download.amsr

Download and Cache an amsr File

# Description

If the file is already present in destdir, then it is not downloaded again. The default destdir is the present directory, but it probably makes more sense to use something like "~/data/amsr" to make it easy for scripts in other directories to use the cached data. The file is downloaded with download.file.

# Usage

```
download.amsr(year, month, day, destdir = ".",
    server = "http://data.remss.com/amsr2/bmaps_v08")
```

110 download.amsr

#### **Arguments**

year, month, day

Numerical values of the year, month, and day of the desired dataset. Note that one file is archived per day, so these three values uniquely identify a dataset. If day and month are not provided but day is, then the time is provided in a relative sense, based on the present date, with day indicating the number of days in the past. Owing to issues with timezones and the time when the data are uploaded to the server, day=3 may yield the most recent available data. For this reason, there is a third option, which is to leave day unspecified, which works as though day=3 had been given.

destdir

A string naming the directory in which to cache the downloaded file. The default is to store in the present directory, but many users find it more helpful to use something like "~/data/amsr" for this, to collect all downloaded amsr files in one place.

server

A string naming the server from which data are to be acquired. See "History".

#### Value

A character value indicating the filename of the result; if there is a problem of any kind, the result will be the empty string.

#### History

Until 25 March 2017, the default server was "ftp.ssmi.com/amsr2/bmaps\_v07.2", but this was changed when the author discovered that this FTP site had been changed to require users to create accounts to register for downloads. The default was changed to "http://data.remss.com/amsr2/bmaps\_v07.2" on the named date. This site was found by a web search, but it seems to provide proper data. It is assumed that users will do some checking on the best source.

On 23 January 2018, it was noticed that the server-url naming convention had changed, e.g. http://data.remss.com/amsr2becoming http://data.remss.com/amsr2/bmaps\_v08/y2017/m01/f34\_20170114v8.gz

### References

http://images.remss.com/amsr/amsr2\_data\_daily.html provides daily images going back to 2012. Three-day, monthly, and monthly composites are also provided on that site.

#### See Also

```
Other functions that download files: download.coastline, download.met, download.topo

Other things related to amsr data: [[<-,amsr-method, amsr-class, composite,amsr-method, plot,amsr-method, read.amsr, subset,amsr-method, summary,amsr-method
```

```
## Not run:
## The download takes several seconds.
f <- download.amsr(2017, 1, 14) # Jan 14, 2017
d <- read.amsr(f)</pre>
```

111 download.coastline

```
plot(d)
mtext(d[["filename"]], side=3, line=0, adj=0)
## End(Not run)
```

download.coastline

Download a coastline File

### **Description**

Constructs a query to the NaturalEarth server [1] to download coastline data (or lake data, river data, etc) in any of three resolutions.

# Usage

```
download.coastline(resolution, item = "coastline", destdir = ".", destfile,
  server = "naturalearth", debug = getOption("oceDebug"))
```

# **Arguments**

resolution	A character value	specifying the desi	red resolution. T	he permitted choices are
------------	-------------------	---------------------	-------------------	--------------------------

"10m" (for 1:10M resolution, the most detailed), "50m" (for 1:50M resolution) and "110m" (for 1:110M resolution). If resolution is not supplied, "50m" will

item A character value indicating the quantity to be downloaded. This is normally

> one of "coastline", "land", "ocean", "rivers\_lakes\_centerlines", or "lakes", but the NaturalEarth server has other types, and advanced users can discover their names by inspecting the URLs of links on the NaturalEarth site, and use them for item. If item is not supplied, it defaults to "coastline".

destdir Optional string indicating the directory in which to store downloaded files. If not

supplied, "." is used, i.e. the data file is stored in the present working directory.

destfile Optional string indicating the name of the file. If not supplied, the file name is constructed from the other parameters of the function call, so subsequent calls

> with the same parameters will yield the same result, thus providing the key to the caching scheme.

A character value specifying the server that is to supply the data. At the moment, server

the only permitted value is "naturalearth", which is the default if server is

not supplied.

an integer specifying whether debugging information is to be printed during the debug

> processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

112 download.met

### Value

A character value indicating the filename of the result; if there is a problem of any kind, the result will be the empty string.

### References

1. The NaturalEarth server is at http://www.naturalearthdata.com

#### See Also

The work is done with download, file.

Other functions that download files: download.amsr, download.met, download.topo

Other things related to coastline data: [[,coastline-method,[[<-,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineCut, coastlineWorld, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method, summary, coastline-method,

# **Examples**

```
## Not run:
library(oce)
# User must create directory ~/data/coastline first.
# As of September 2016, the downloaded file, named
# "ne_50m_coastline.zip", occupies 443K bytes.
filename <- download.coastline(destdir="~/data/coastline")
coastline <- read.coastline(filename)
plot(coastline)
## End(Not run)</pre>
```

download.met

Download and Cache a met File

# **Description**

Data are downloaded from <a href="http://climate.weather.gc.ca">http://climate.weather.gc.ca</a> and cached locally.

# Usage

```
download.met(id, year, month, deltat, destdir = ".", destfile,
  debug = getOption("oceDebug"))
```

download.met 113

### **Arguments**

id A number giving the "Station ID" of the station of interest. If not provided, id defaults to 6358, for Halifax International Airport. See "Details". A number giving the year of interest. Ignored unless deltat is "hour". If year year is not given, it defaults to the present year. A number giving the month of interest. Ignored unless deltat is "hour". If month month is not given, it defaults to the present month. deltat Optional character string indicating the time step of the desired dataset. This may be "hour" or "month". If deltat is not given, it defaults to "hour". destdir Optional string indicating the directory in which to store downloaded files. If not supplied, "." is used, i.e. the data file is stored in the present working directory. destfile Optional string indicating the name of the file. If not supplied, the file name is constructed from the other parameters of the function call, so subsequent calls with the same parameters will yield the same result, thus providing the key to the caching scheme. debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

### **Details**

The data are downloaded with download.file pointed to the Environment Canada website [1] using queries that had to be devised by reverse-engineering, since the agency does not provide documentation about how to construct queries. Caution: the query format changes from time to time, so download.met may work one day, and fail the next.

The constructed query contains Station ID, as provided in the id argument. Note that this seems to be a creation of Environment Canada, alone; it is distinct from the more standard "Climate ID" and "WMO ID". To make things more difficult, Environment Canada states that the Station ID is subject to change over time. (Whether this applies to existing data is unclear.)

Given these difficulties with Station ID, users are advised to consult the Environment Canada website [1] before downloading any data, and to check it from time to time during the course of a research project, to see if the Station ID has changed. Another approach would be to use Gavin Simpson's canadaHCD package [2] to look up Station IDs. This package maintains a copy of the Environment Canada listing of stations, and its find\_station function provides an easy way to determine Station IDs. After that, its hcd\_hourly function (and related functions) make it easy to read data. These data can then be converted to the met class with as.met, although doing so leaves many important metadata blank.

## Value

String indicating the full pathname to the downloaded file.

114 download.topo

## Author(s)

Dan Kelley

#### References

- 1. Environment Canada website for Historical Climate Data <a href="http://climate.weather.gc.ca/index\_e.html">http://climate.weather.gc.ca/index\_e.html</a>
- 2. Gavin Simpon's canadaHCD package on GitHub https://github.com/gavinsimpson/canadaHCD

#### See Also

The work is done with download. file.

Other functions that download files: download.amsr, download.coastline, download.topo

Other things related to met data: [[,met-method, [[<-,met-method, as.met, met-class, met, plot,met-method, read.met, subset,met-method, summary,met-method

## **Examples**

```
## Not run:
library(oce)
## Download data for Halifax International Airport, in September
## of 2003. (This dataset is used for data(met) provided with oce.)
metFile <- download.met(6358, 2003, 9, destdir=".")
met <- read.met(metFile)
## End(Not run)</pre>
```

download.topo

Download and Cache a topo File

## **Description**

Data are downloaded (from 'https://maps.ngdc.noaa.gov/viewers/wcs-client/', by default) and a string containing the full path to the downloaded file is returned. Typically, this return value is used with read.topo to read the data. Subsequent calls to download.topo with identical parameters will simply return the name of the cached file, assuming the user has not deleted it in the meantime. For convenience, if destfile is not given, then download.topo will construct a filename from the other arguments, rounding longitude and latitude limits to 0.01 degrees.

### Usage

```
download.topo(west, east, south, north, resolution, destdir, destfile, format,
   server, debug = getOption("oceDebug"))
```

download.topo 115

#### **Arguments**

west, east Longitudes of the western and eastern sides of the box. south, north Latitudes of the southern and northern sides of the box.

resolution Optional grid spacing, in minutes. If not supplied, a default value of 4 (cor-

responding to 7.4km, or 4 nautical miles) is used. Note that (as of August 2016) the original data are on a 1-minute grid, which limits the possibilities

for resolution.

destdir Optional string indicating the directory in which to store downloaded files. If not

supplied, "." is used, i.e. the data file is stored in the present working directory.

destfile Optional string indicating the name of the file. If not supplied, the file name is

constructed from the other parameters of the function call, so subsequent calls with the same parameters will yield the same result, thus providing the key to

the caching scheme.

format Optional string indicating the type of file to download. If not supplied, this

defaults to "gmt". See "Details".

server Optional string indicating the server from which to get the data. If not supplied,

the default "https://gis.ngdc.noaa.gov/cgi-bin/public/wcs/etopo1.xyz"

will be used.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### **Details**

The data are downloaded with download. file, using a URL devised from reverse engineering webbased queries constructed by the default server used here. Note that the data source is "etopo1", which is a 1 arc-second file [1.2].

Three values are permitted for format, each named after the targets of menu items on the NOAA website (as of August 2016): (1) "aaigrid" (for the menu item "ArcGIS ASCII Grid"), which yields a text file, (2) "netcdf" (the default, for the menu item named "NetCDF"), which yields a NetCDF file and (3) "gmt" (for the menu item named "GMT NetCDF"), which yields a NetCDF file in another format. All of these file formats are recognized by read. topo. (The NOAA server has more options, and if read. topo is extended to handle them, they will also be added here.)

#### Value

String indicating the full pathname to the downloaded file.

#### Webserver history

All versions of download. topo to date have used a NOAA server as the data source, but the URL has not been static. A list of the servers that have been used is provided below, in hopes that it can help users to make guesses for server, should download. topo fail because of a fail to download

116 drawDirectionField

the data. Another hint is to look at the source code for getNOAA.bathy in the **marmap** package, which is also forced to track the moving target that is NOAA.

- August 2016. 'http://maps.ngdc.noaa.gov/mapviewer-support/wcs-proxy/wcs.groovy'
- December 2016. 'http://mapserver.ngdc.noaa.gov/cgi-bin/public/wcs/etopo1.xyz'
- June-September 2017. 'https://gis.ngdc.noaa.gov/cgi-bin/public/wcs/etopo1.xyz'

# Author(s)

Dan Kelley

#### References

- 1. 'https://www.ngdc.noaa.gov/mgg/global/global.html'
- 2. Amante, C. and B.W. Eakins, 2009. ETOPO1 1 Arc-Minute Global Relief Model: Procedures, Data Sources and Analysis. NOAA Technical Memorandum NESDIS NGDC-24. National Geophysical Data Center, NOAA. doi:10.7289/V5C8276M [access date: Aug 30, 2017].

#### See Also

The work is done with download.file.

Other functions that download files: download.amsr, download.coastline, download.met

Other things related to topo data: [[,topo-method, [[<-,topo-method, as.topo, plot,topo-method, read.topo, subset,topo-method, summary,topo-method, topo-class, topoInterpolate, topoWorld

drawDirectionField 117

# **Description**

The direction field is indicated variously, depending on the value of type:

• For type=1, each indicator is drawn with a symbol, according to the value of pch (either supplied globally, or as an element of the . . . list) and of size cex, and colour col. Then, a line segment is drawn for each, and for this lwd and col may be set globally or in the . . . list.

• For type=2, the points are not drawn, but arrows are drawn instead of the line segments. Again, 1wd and col control the type of the line.

## Usage

```
drawDirectionField(x, y, u, v, scalex, scaley, skip, length = 0.05,
  add = FALSE, type = 1, col = par("fg"), pch = 1, cex = par("cex"),
  lwd = par("lwd"), lty = par("lty"), xlab = "", ylab = "",
  debug = getOption("oceDebug"), ...)
```

### **Arguments**

xlab, ylab

debug

. . .

x and y axis labels

٤	,uments	
	x, y	coordinates at which velocities are specified. The length of $x$ and $y$ depends on the form of $u$ and $v$ (vectors or matrices).
	u, v	velocity components in the $x$ and $y$ directions. Can be either vectors with the same length as $x$ , $y$ , or matrices, of dimension length( $x$ ) by length( $y$ ).
	scalex, scaley	scale to be used for the velocity arrows. Exactly one of these must be specified. Arrows that have $u^2+v^2=1$ will have length scalex along the x axis, or scaley along the y axis, according to which argument is given.
	skip	either an integer, or a two-element vector indicating the number of points to skip when plotting arrows (for the matrix $u$ , $v$ case). If a single value, the same skip is applied to both the $x$ and $y$ directions. If a two-element vector, specifies different values for the $x$ and $y$ directions.
	length	indication of <b>width</b> of arrowheads. The somewhat confusing name of this argument is a consequence of the fact that it is passed to arrows for drawing arrows. Note that the present default is smaller than the default used by arrows.
	add	if TRUE, the arrows are added to an existing plot; otherwise, a new plot is started by calling $plot$ with x, y and type="n". In other words, the plot will be very basic. In most cases, the user will probably want to draw a diagram first, and add the direction field later.
	type	indication of the style of arrow-like indication of the direction.
	col	colour of line segments or arrows
	pch, cex	plot character and expansion factor, used for type=1
	lwd, lty	line width and type, used for type=2

debugging value; set to a positive integer to get debugging information. other arguments to be passed to plotting functions (e.g. axis labels, etc).

118 drawIsopycnals

### Value

None.

#### Author(s)

Dan Kelley and Clark Richards

# **Examples**

drawIsopycnals

Add Isopycnal Curves to TS Plot

### **Description**

Adds isopycnal lines to an existing temperature-salinity plot. This is called by plotTS, and may be called by the user also, e.g. if an image plot is used to show TS data density.

# Usage

```
drawIsopycnals(nlevels = 6, levels, rotate = TRUE, rho1000 = FALSE,
  digits = 2, eos = getOption("oceEOS", default = "gsw"), cex = 0.75 *
  par("cex"), col = "darkgray", lwd = par("lwd"), lty = par("lty"))
```

### **Arguments**

nlevels	suggested number of density levels (i.e. isopycnal curves); ignored if levels is supplied.
levels	optional density levels to draw.
rotate	boolean, set to TRUE to write all density labels horizontally.
rho1000	boolean, set to TRUE to write isopycnal labels as e.g. 1024 instead of 24.

drawPalette 119

digits	number of decimal digits to use in label (supplied to round).
eos	equation of state to be used, either "unesco" or "gsw".
cex	size for labels.
col	colour for lines and labels.
lwd	line width for isopcynal curves
lty	line type for isopcynal curves

#### Value

None.

# Author(s)

Dan Kelley

### See Also

plotTS, which calls this.

drawPalette

Draw a palette, leaving margins suitable for accompanying plot

# **Description**

Draw a palette, leaving margins suitable for accompanying plot.

# Usage

```
drawPalette(zlim, zlab = "", breaks, col, colormap, mai,
  cex.axis = par("cex.axis"), pos = 4, labels = NULL, at = NULL, levels,
  drawContours = FALSE, plot = TRUE, fullpage = FALSE,
  drawTriangles = FALSE, axisPalette, tformat,
  debug = getOption("oceDebug"), ...)
```

# Arguments

zlim	two-element vector containing the lower and upper limits of z. This may also be a vector of any length exceeding 1, in which case its range is used.
zlab	label for the palette scale.
breaks	the z values for breaks in the colour scheme.
col	either a vector of colours corresponding to the breaks, of length 1 less than the number of breaks, or a function specifying colours, e.g. oce.colorsJet for a rainbow.
colormap	a colour map as created by colormap. If provided, this takes precedence over breaks and col.

120 drawPalette

mai margins for palette, as defined in the usual way; see par. If not given, reasonable

values are inferred from the existence of a non-blank zlab.

cex.axis character-expansion value for text labels

an integer indicating the location of the palette within the plotting area, 1 for pos

near the bottom, 2 for near the left-hand side, 3 for near the top side, and 4 (the

default) for near the right-hand side.

labels optional vector of labels for ticks on palette axis (must correspond with at)

at optional vector of positions for the labels

levels optional contour levels, in preference to breaks values, to be added to the image

if drawContours is TRUE.

drawContours logical value indicating whether to draw contours on the palette, at the colour

logical value indicating whether to plot the palette, the default, or whether to plot

> just alter the margins to make space for where the palette would have gone. The latter case may be useful in lining up plots, as in example 1 of "Examples".

logical value indicating whether to draw the palette filling the whole plot width fullpage

(apart from mai, of course). This can be helpful if the palette panel is to be

created with layout, as illustrated in the "Examples".

drawTriangles logical value indicating whether to draw triangles on the top and bottom of the

> palette. If a single value is provide, it applies to both ends of the palette. If a pair is provided, the first refers to the lower range of the palette, and the second

to the upper range.

axisPalette optional replacement function for axis(), e.g. for exponential notation on large

or small values.

tformat optional format for axis labels, if the variable is a time type (ignored otherwise).

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

optional arguments passed to plotting functions.

#### **Details**

In the normal use, drawPalette draws an image palette near the right-hand side of the plotting device, and then adjusts the global margin settings in such a way as to cause the next plot to appear (with much larger width) to the left of the palette. The function can also be used, if zlim is not provided, to adjust the margin without drawing anything; this is useful in lining up the x axes of a stack of plots, some some of which will have palettes and others not.

The plot positioning is done entirely with margins, not with par(mfrow) or other R schemes for multi-panel plots. This means that the user is free to use those schemes without worrying about nesting or conflicts.

#### Value

None.

drawPalette 121

# Use with multi-panel plots

An important consequence of the margin adjustment is that multi-panel plots require that the initial margin be stored prior to the first call to drawPalette, and reset after each palette-plot pair. This method is illustrated in "Examples".

#### Author(s)

Dan Kelley, with help from Clark Richards

#### See Also

This is used by imagep.

```
library(oce)
par(mgp=getOption("oceMgp"))
## 1. A three-panel plot
par(mfrow=c(3, 1), mar=c(3, 3, 1, 1))
omar <- par('mar')</pre>
                                   # save initial margin
## 1a. top panel: simple case
drawPalette(zlim=c(0, 1), col=oce.colorsJet(10))
plot(1:10, 1:10, col=oce.colorsJet(10)[1:10],pch=20,cex=3,xlab='x', ylab='y')
par(mar=omar)
                                   # reset margin
## 1b. middle panel: colormap
cm <- colormap(name="gmt_globe")</pre>
drawPalette(colormap=cm)
icol <- seq_along(cm$col)</pre>
plot(icol, cm$breaks[icol], pch=20, cex=2, col=cm$col,
     xlab="Palette index", ylab="Palette breaks")
par(mar=omar)
                                   # reset margin
## 1c. bottom panel: space for palette (to line up graphs)
drawPalette(plot=FALSE)
plot(1:10, 1:10, col=oce.colorsJet(10)[1:10],pch=20,cex=3,xlab='x', ylab='y')
par(mar=omar)
                                    # reset margin
# 2. Use layout to mimic the action of imagep(), with the width
# of the palette region being 14 percent of figure width.
d < -0.14
layout(matrix(1:2,nrow=1), widths=c(1-d,d))
image(volcano, col=oce.colorsJet(100), zlim=c(90, 200))
contour(volcano, add=TRUE)
drawPalette(c(90, 200), fullpage=TRUE, col=oce.colorsJet)
```

122 echosounder-class

echosounder

Echosounder Dataset

# **Description**

This is degraded subsample of measurements that were made with a Biosonics scientific echosounder, as part of the St Lawrence Internal Wave Experiment (SLEIWEX).

# Author(s)

Dan Kelley

#### **Source**

This file came from the SLEIWEX-2008 experiment, and was decimated using decimate with by=c().

### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, as.echosounder, echosounder-class, findBottom, plot,echosounder-method, read.echosounder, subset,echosounder-method, summary,echosounder-method

echosounder-class

Class to Store Echosounder Data

# Description

Class to store echosounder data.

### **Details**

The data slot is a list containing

- An infrequently updated record of the intrument position, in timeSlow, longitudeSlow and latitudeSlow. These are used in plotting maps with plot, echosounder-method.
- An interpolated record of the instrument position, in time, longitude, and latitude. Linear interpolation is used to infer the longitude and latitude from the variables listed above.
- depth, vector of depths of echo samples (measured positive downwards in the water column).
   This is calculated from the inter-sample time interval and the sound speed provided as the soundSpeed argument to read.echosounder, so altering the value of the latter will alter the echosounder plots provided by plot, echosounder-method.

echosounder-class 123

• The echosounder signal amplitude a, a matrix whose number of rows matches the length of time, etc., and number of columns equal to the length of depth. Thus, for example, a[100,] represents the depth-dependent amplitude at the time of the 100th ping.

- A matrix named b exists for dual-beam and split-beam cases. For dual-beam data, this is the
  wide-beam data, whereas a is the narrow-beam data. For split-beam data, this is the x-angle
  data
- A matrix named c exists for split-beam data, containing the y-angle data.
- In addition to these matrices, ad-hoc calculated matrices named Sv and TS may be accessed as explained in the next section.

#### Methods

Accessing values. Data may be accessed as e.g. echosounder[["time"]], echosounder[["depth"]], echosounder[["a"]], etc. Items in metadata must be specified by full name, but those in data may be abbreviated, so long as the abbreviation is unique. In addition to the actual data, some derived fields are also available: echosounder[["distance"]] calls geodDist to compute calculate distance along the ship track, echosounder[["Sv"]] returns a matrix of backscatter strength in DB, and echosounder[["TS"]] returns a matrix of target strength in dB.

Assigning values. Everything that may be accessed may also be assigned, e.g. echosounder[["time"]] <- 3600 + echosounder adds an hour to time.

### Author(s)

Dan Kelley

Statistical summaries are provided by summary, echosounder-method, while show displays an overview. The findBottom function infers the ocean bottom from tracing the strongest reflector from ping to ping.

Echosounder objects may be plotted with plot, echosounder-method.

The contents of echosounder objects may be altered with subset, echosounder-method, or with the [[]] scheme discussed in the previous section; skilled users may also manipulate the contents directly, but this is not recommended because it is brittle to changes in the data structure.

# See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, as.echosounder, echosounder, findBottom, plot,echosounder-method, read.echosounder, subset,echosounder-method, summary,echosounder-method

eclipticalToEquatorial

Convert ecliptical to equatorial coordinate

### **Description**

Convert from ecliptical to equatorial coordinates, using equations 8.3 and 8.4 of [1], or, equivalently, equations 12.3 and 12.4 of [2].

# Usage

```
eclipticalToEquatorial(lambda, beta, epsilon)
```

# **Arguments**

lambda longitude, in degrees, or a data frame containing lambda, beta, and epsilon, in

which case the next to arguments are ignored.

beta geocentric latitude, in degrees

epsilon obliquity of the ecliptic, in degrees

### Value

A data frame containing columns rightAscension and declination both in degrees.

### Author(s)

Dan Kelley, based on formulae in [1] and [2].

### References

- 1. Meeus, Jean, 1982. Astronomical formulae for Calculators. Willmann-Bell. Richmond VA, USA. 201 pages.
- 2. Meeus, Jean, 1991. Astronomical algorithms. Willmann-Bell, Richmond VA, USA. 429 pages. The code is based on [1]; see help(moonAngle,"oce") for comments on the differences in formulae found in [2]. Indeed, [2] is only cited here in case readers want to check the ideas of the formulae; DK has found that [2] is available to him via his university library inter-library loan system, whereas he owns a copy of [1].

# See Also

Other things related to astronomy: equatorialToLocalHorizontal, julianCenturyAnomaly, julianDay, moonAngle, siderealTime, sunAngle

enuToOther 125

enuToOther

Rotate acoustic-Doppler data to a new coordinate system

# Description

Rotate acoustic-Doppler data to a new coordinate system

## Usage

```
enuToOther(x, ...)
```

# Arguments

- x an adp or adv object, i.e. one inheriting from adp-class or adv-class.
- ... extra arguments that are passed on to enuToOtherAdp or enuToOtherAdv.

#### Value

An object of the same type as x, but with velocities in the rotated coordinate system

#### See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.adp.read.adppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

enuToOtherAdp

Convert ADP ENU to Rotated Coordinate

### **Description**

Convert ADP velocity components from an enu-based coordinate system to another system, perhaps to align axes with the coastline.

#### **Usage**

```
enuToOtherAdp(x, heading = 0, pitch = 0, roll = 0)
```

126 enuToOtherAdp

# **Arguments**

x An adp object, i.e. one inheriti	ng from adp-class.
------------------------------------	--------------------

heading number or vector of numbers, giving the angle, in degrees, to be added to the

heading. See "Details".

pitch as heading but for pitch.
roll as heading but for roll.

#### **Details**

The supplied angles specify rotations to be made around the axes for which heading, pitch, and roll are defined. For example, an eastward current will point southeast if heading=45 is used.

The returned value has heading, pitch, and roll matching those of x, so these angles retain their meaning as the instrument orientation.

NOTE: this function works similarly to xyzToEnuAdp, except that in the present function, it makes no difference whether the instrument points up or down, etc.

#### Value

An object with datav[,1:3,] altered appropriately, and metadatace.coordinate changed from enu to other.

### Author(s)

Dan Kelley

#### References

RD Instruments, 1998. ADP Coordinate Transformation, formulas and calculations. P/N 951-6079-00 (July 1998)

# See Also

See read. adp for other functions that relate to objects of class "adp".

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.adp.rdi, read.adpopProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

```
library(oce)
data(adp)
o <- enuToOtherAdp(adp, heading=-31.5)
plot(o, which=1:3)</pre>
```

enuToOtherAdv 127

|--|

## **Description**

Convert ADV velocity components from an enu-based coordinate system to another system, perhaps to align axes with the coastline.

# Usage

```
enuToOtherAdv(x, heading = 0, pitch = 0, roll = 0,
  debug = getOption("oceDebug"))
```

# Arguments

x An adv object, i.e. one inheriting from adv-class.

heading number or vector of numbers, giving the angle, in degrees, to be added to the

heading. If this has length less than the number of velocity sampling times, then

it will be extended using rep.

pitch as heading but for pitch.
roll as heading but for roll.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## **Details**

The supplied angles specify rotations to be made around the axes for which heading, pitch, and roll are defined. For example, an eastward current will point southeast if heading=45 is used.

The returned value has heading, pitch, and roll matching those of x, so these angles retain their meaning as the instrument orientation.

NOTE: this function works similarly to xyzToEnuAdv, except that in the present function, it makes no difference whether the instrument points up or down, etc.

### Author(s)

Dan Kelley

## See Also

```
Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOther, plot,adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset,adv-method, summary,adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu
```

equatorialToLocalHorizontal

Convert equatorial to local horizontal coordinate

# **Description**

Convert from equatorial coordinates to local horizontal coordinates, i.e. azimuth and altitude. The method is taken from equations 8.5 and 8.6 of [1], or, equivalently, from equations 12.5 and 12.6 of [2].

### Usage

equatorialToLocalHorizontal(rightAscension, declination, t, longitude, latitude)

# Arguments

rightAscension right ascension, e.g. calculated with eclipticalToEquatorial.

declination declination, e.g. calculated with eclipticalToEquatorial.

t time of observation.

longitude longitude of observation, positive in eastern hemisphere.

latitude latitude of observation, positive in northern hemisphere.

## Value

A data frame containing columns altitude (angle above horizon, in degrees) and azimuth (angle anticlockwise from south, in degrees).

# Author(s)

Dan Kelley, based on formulae in [1] and [2].

### References

- 1. Meeus, Jean, 1982. Astronomical formulae for Calculators. Willmann-Bell. Richmond VA, USA. 201 pages.
- 2. Meeus, Jean, 1991. Astronomical algorithms. Willmann-Bell, Richmond VA, USA. 429 pages.

## See Also

Other things related to astronomy: eclipticalToEquatorial, julianCenturyAnomaly, julianDay, moonAngle, siderealTime, sunAngle

errorbars 129

errorbars	Draw error bars on an existing xy diagram	

# Description

Draw error bars on an existing xy diagram

# Usage

```
errorbars(x, y, xe, ye, percent = FALSE, style = 0, length = 0.025, ...)
```

# Arguments

X	x coordinates of points on the existing plot.
у	y coordinates of points on the existing plot.
xe	error on x coordinates of points on the existing plot, either a single number or a vector of length identical to that of y.
ye	as xe but for y coordinate.
percent	boolean flag indicating whether $xe$ and $ye$ are in terms of percent of the corresponding $x$ and $y$ values.
style	indication of the style of error bar. Using style=0 yields simple line segments (drawn with segments) and style=1 yields line segments with short perpendicular endcaps.
length	length of endcaps, for style=1 only; it is passed to arrows, which is used to draw that style of error bars.
	graphical parameters passed to the code that produces the error bars, e.g. to $segments$ for $style=0$ .

# Author(s)

Dan Kelley

```
library(oce)
data(ctd)
S <- ctd[["salinity"]]
T <- ctd[["temperature"]]
plot(S, T)
errorbars(S, T, 0.05, 0.5)</pre>
```

130 fillGap

fillGap

Fill a gap in an oce object

# **Description**

Sequences of NA values, are filled by linear interpolation between the non-NA values that bound the gap.

### Usage

```
fillGap(x, method = c("linear"), rule = 1)
```

# **Arguments**

x an oce object.

method to use; see "Details".

rule integer controlling behaviour at start and end of x. If rule=1, NA values at the

ends are left in the return value. If rule=2, they are replaced with the nearest

non-NA point.

### Value

A new oce object, with gaps removed.

### **Bugs**

- 1. Eventually, this will be expanded to work with any oce object. But, for now, it only works for vectors that can be coerced to numeric.
- 2. If the first or last point is NA, then x is returned unaltered.
- 3. Only method linear is permitted now.

## Author(s)

Dan Kelley

```
library(oce)
# Integers
x <- c(1:2, NA, NA, 5:6)
y <- fillGap(x)
print(data.frame(x,y))
# Floats
x <- x + 0.1
y <- fillGap(x)
print(data.frame(x,y))</pre>
```

findBottom 131

findDattam	Find the Ocean Pottom in an Follogounday Object
findBottom	Find the Ocean Bottom in an Echosounder Object

## **Description**

Finds the depth in a Biosonics echosounder file, by finding the strongest reflector and smoothing its

## Usage

```
findBottom(x, ignore = 5, clean = despike)
```

# **Arguments**

x an object of class echosounder

ignore number of metres of data to ignore, near the surface clean a function to clean the inferred depth of spikes

#### Value

A list with elements: the time of a ping, the depth of the inferred depth in metres, and the index of the inferred bottom location, referenced to the object's depth vector.

### Author(s)

Dan Kelley

### See Also

The documentation for echosounder-class explains the structure of echosounder objects, and also outlines the other functions dealing with them.

Other things related to echosounder data: [[,echosounder-method,[[<-,echosounder-method, as.echosounder,echosounder-class,echosounder,plot,echosounder-method,read.echosounder,subset,echosounder-method,summary,echosounder-method

findInOrdered	Find indices of times in an ordered vector [deprecated]	

# Description

**WARNING:** This function will be removed soon; see oce-deprecated. The replacement is trivial: just change a call like e.g. findInOrdered(x, f) to findInterval(f, x) (which is what the function started doing, on 2017-09-07, after a major bug was found).

132 firstFinite

# Usage

```
findInOrdered(x, f)
```

# **Arguments**

- x a numeric vector, in increasing order by value.
- f a numeric vector of items whose indices are sought.

#### **Details**

The indices point to the largest items in x that are less than or equal the values in f. This works by simply calling findInterval(x=f, vec=x), and users are probably better off using findInterval directly.

# Value

A numerical vector indicating the indices of left-sided neighbors.

# Author(s)

Dan Kelley

# **Examples**

```
findInOrdered(seq(0, 10, 1), c(1.2, 7.3))
```

firstFinite

Get first finite value in a vector or array, or NULL if none

# Description

Get first finite value in a vector or array, or NULL if none

# Usage

```
firstFinite(v)
```

# **Arguments**

v A numerical vector or array.

formatCI 133

formatCI	Confidence interval in parenthetic notation	
. 0	confidence and rail in parenment notation	

### **Description**

Format a confidence interval in parenthetic notation.

#### Usage

```
formatCI(ci, style = c("+/-", "parentheses"), model, digits = NULL)
```

## **Arguments**

ci optional vector of length 2 or 3.

style string indicating notation to be used.

model optional regression model, e.g. returned by lm or nls.

digits optional number of digits to use; if not supplied, getOption("digits") is used.

#### **Details**

If a model is given, then ci is ignored, and a confidence interval is calculated using confint with level set to 0.6914619. This level corresponds to a range of plus or minus one standard deviation, for the t distribution and a large number of degrees of freedom (since qt(0.6914619, 100000) is 0.5).

If model is missing, ci must be provided. If it contains 3 elements, then first and third elements are taken as the range of the confidence interval (which by convention should use the level stated in the previous paragraph), and the second element is taken as the central value. Alternatively, if ci has 2 elements, they are taken to be bounds of the confidence interval and their mean is taken to be the central value.

In the +/- notation, e.g.  $a \pm b$  means that the true value lies between a-b and a+b with a high degree of certainty. Mills et al. (1993, section 4.1 on page 83) suggest that b should be set equal to 2 times the standard uncertainty or standard deviation. JCGM (2008, section 7.2.2 on pages 25 and 26), however, suggest that b should be set to the standard uncertainty, while also recommending that the  $\pm$  notation be avoided altogether.

The parentheses notation is often called the compact notation. In it, the digits in parentheses indicate the uncertainty in the corresponding digits to their left, e.g. 12.34(3) means that the last digit (4) has an uncertainty of 3. However, as with the  $\pm$  notation, different authorities offer different advice on defining this uncertainty; Mills et al. (1993, section 4.1 on page 83) provide an example in which the parenthetic notation has the same value as the  $\pm$  notation, while JCM (2008, section 7.2.2 on pages 25 and 26) suggest halving the number put in parentheses.

The foramtci function is based on the JCM (2008) notation, i.e. formatCI(ci=c(8,12), style="+/-") yields "10+-2", and formatCI(ci=c(8,12), style="parentheses") yields "10(2)".

Note: if the confidence range exceeds the value, the parentheses format reverts to +/- format.

134 formatPosition

#### Value

If ci is given, the result is a character string with the estimate and its uncertainty, in plus/minus or parenthetic notation. If model is given, the result is a 1-column matrix holding character strings, with row names corresponding to the parameters of the model.

### Author(s)

Dan Kelley

#### References

JCGM, 2008. Evaluation of measurement data - Guide to the expression of uncertainty in measurement (JCGM 100:2008), published by the Joint Committee for Guides in Metrology. [http://www.bipm.org/en/publications/guides/gum.html] (See section 7.2.2 for a summary of notation, which shows equal values to the right of a +- sign and in parentheses.)

I. Mills, T. Cvitas, K. Homann, N. Kallay, and K. Kuchitsu, 1993. *Quantities, Units and Symbols in Physical Chemistry*, published Blackwell Science for the International Union of Pure and Applied Chemistry. (See section 4.1, page 83, for a summary of notation, which shows that a value to the right of a +- sign is to be halved if put in

## **Examples**

```
x <- seq(0, 1, length.out=300)
y <- rnorm(n=300, mean=10, sd=1) * x
m <- lm(y~x)
print(formatCI(model=m))</pre>
```

formatPosition

Format Geographical Position in Degrees and Minutes

#### **Description**

Format geographical positions to degrees, minutes, and hemispheres

### Usage

```
formatPosition(latlon, isLat = TRUE, type = c("list", "string",
   "expression"), showHemi = TRUE)
```

#### **Arguments**

latlon a vector of latitudes or longitudes

isLat a boolean that indicates whether the quantity is latitude or longitude

type a string indicating the type of return value (see below)
showHemi a boolean that indicates whether to indicate the hemisphere

fullFilename 135

# Value

A list containing degrees, minutes, seconds, and hemispheres, or a vector of strings or (broken) a vector of expressions.

# Author(s)

Dan Kelley

# **Examples**

```
library(oce)
formatPosition(10+1:10/60+2.8/3600)
formatPosition(10+1:10/60+2.8/3600, type="string")
```

fullFilename

Full name of file, including path

# Description

Determines the full name of a file, including the path. Used by many read.X routines, where X is the name of a class of object. This is a wrapper around normalizePath, with warnings turned off so that messages are not printed for unfound files (e.g. URLs).

# Usage

```
fullFilename(filename)
```

# **Arguments**

filename

name of file

### Value

Full file name

# Author(s)

Dan Kelley

136 geodDist

g1sst-class

Class to Hold G1SST Satellite-model Data

### **Description**

G1SST is an acronym for global 1-km sea surface temperature, a product that combines satellite data with the model output. It is provided by the JPO ROMS (Regional Ocean Modelling System) modelling group. See the JPL website [1] to learn more about the data, and see the read.g1sst documentation for an example of downloading and plotting.

#### **Details**

It is important not to regard G1SST data in the same category as, say, amsr-class data, because the two products differ greatly with respect to cloud cover. The satellite used by amsr-class has the ability to sense water temperature even if there is cloud cover, whereas g1sst fills in cloud gaps with model simulations. It can be helpful to consult [1] for a given time, clicking and then unclicking the radio button that turns off the model-based filling of cloud gaps.

#### Author(s)

Dan Kelley

#### References

1. JPO OurOcean Portal http://ourocean.jpl.nasa.gov/SST/ (link worked in 2016 but was seen to fail 2017 Feb 2).

#### See Also

Other things related to satellite data: plot, satellite-method, read.g1sst, satellite-class, summary, satellite-method

geodDist

Compute Geodesic Distance on Surface of Earth

# **Description**

This calculates geodesic distance between points on the earth, i.e. distance measured along the (presumed ellipsoidal) surface. The method involves the solution of the geodetic inverse problem, using T. Vincenty's modification of Rainsford's method with Helmert's elliptical terms.

### Usage

```
geodDist(longitude1, latitude1 = NULL, longitude2 = NULL,
  latitude2 = NULL, alongPath = FALSE)
```

geodDist 137

### **Arguments**

longitude1	longitude or a vector of longitudes, <b>or</b> a section object, from which longitude and latitude are extracted and used instead of the next three arguments	
latitude1	latitude or vector of latitudes (ignored if longitude1 is a section object)	
longitude2	optional longitude or vector of longitudes (ignored if alongPath=TRUE)	
latitude2	tude2 optional latitude or vector of latitudes (ignored if alongPath=TRUE)	
alongPath	boolean indicating whether to compute distance along the path, as opposed to distance from the reference point. If alongPath=TRUE, any values provided for latitude2 and longitude2 will be ignored.	

#### **Details**

The function may be used in several different ways.

Case 1: longitude1 is a section object. The values of latitude1, longitude2, and latitude2 arguments are ignored, and the behaviour depends on the value of the alongPath argument. If alongPath=FALSE, the return value contains the geodetic distances of each station from the first one. If alongPath=TRUE, the return value is the geodetic distance along the path connecting the stations, in the order in which they are stored in the section.

Case 2: longitude1 is a vector. If longitude2 and latitude2 are not given, then the return value is a vector containing the distances of each point from the first one, *or* the distance along the path connecting the points, according to the value of alongPath. On the other hand, if both longitude2 and latitude2 are specified, then the return result depends on the length of these arguments. If they are each of length 1, then they are taken as a reference point, from which the distances to longitude1 and latitude1 are calculated (ignoring the value of alongPath). However, if they are of the same length as longitude1 and latitude1, then the return value is the distance between corresponding (longitude1,latitude1) and (longitude2,latitude2) values.

## Value

Vector of distances in kilometres.

### Author(s)

Dan Kelley based this on R code sent to him by Darren Gillis, who in 2003 had modified Fortran code that, according to comments in the source, had been written in 1974 by L. Pfeifer and J. G. Gergen.

### References

T. Vincenty, "Direct and Inverse Solutions of Ellipsoid on the Ellipsoid with Application of Nested Equations", *Survey Review*, April 1975. (As of early 2009, this document is available at <a href="http://www.ngs.noaa.gov/PUBS\_LIB/inverse.pdf">http://www.ngs.noaa.gov/PUBS\_LIB/inverse.pdf</a>.)

### See Also

### geodXy

Other functions relating to geodesy: geodGc, geodXyInverse, geodXy

138 geodGc

## **Examples**

```
library(oce)
km <- geodDist(100, 45, 100, 46)
data(section)
geodDist(section)
geodDist(section, alongPath=TRUE)</pre>
```

geodGc

Great-circle Segments Between Points on Earth

# **Description**

Each pair in the longitude and latitude vectors is considered in turn. For long vectors, this may be slow.

# Usage

```
geodGc(longitude, latitude, dmax)
```

# **Arguments**

longitude vector of longitudes, in degrees east latitude vector of latitudes, in degrees north

dmax maximum angular separation to tolerate between sub-segments, in degrees.

#### Value

Data frame of longitude and latitude.

# Author(s)

Dan Kelley, based on code from Clark Richards, in turn based on formulae provided by Ed Williams [1].

## References

1. http://williams.best.vwh.net/avform.htm#Intermediate (link worked for years but failed 2017-01-16).

# See Also

Other functions relating to geodesy: geodDist, geodXyInverse, geodXy

geodXy 139

### **Examples**

geodXy

Convert From Geographical to Geodesic Coordinates

# Description

The method, which may be useful in determining coordinate systems for a mooring array or a ship transects, calculates (x,y) from distance calculations along geodesic curves. See "Caution".

# Usage

```
geodXy(longitude, latitude, longitudeRef, latitudeRef,
  debug = getOption("oceDebug"))
```

#### **Arguments**

longitude, latitude

vector of longitude and latitude

longitudeRef, latitudeRef

numeric reference location. Poor results will be returned if these values are not close to the locations described by longitude and latitude. A sensible approach might be to set longitudeRef to longitude[1], etc.

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

# **Details**

The calculation is as follows. Consider the i-th point in the longitude and latitude vectors. To calculate x[i], geodDist is used is to find the distance *along a geodesic curve* connecting (longitude[i], latitude[i]) with (longitudeRef, latitude[i]). The resultant distance is multiplied by -1 if longitude[i]-longitudeRef is negative, and the result is assigned to x[i]. A similar procedure is used for y[i].

geodXy

#### Value

geodXy returns a data frame of x and y, geodesic distance components, measured in metres.

#### Caution

This scheme is without known precedent in the literature, and users should read the documentation carefully before deciding to use it.

# Change history

On 2015-11-02, the names of the arguments were changed from lon, etc., to longitude, etc., to be in keeping with other oce functions.

On 2017-04-05, four changes were made. 1. Default values of longitudeRef and latitudeRef were removed, since the old defaults were inappropriate to most work. 2. The argument called rotate was eliminated, because it only made sense if the mean resultant x and y were zero. 3. The example was made more useful. 4. Pointers were made to lonlat2utm, which may be more useful.

#### Author(s)

Dan Kelley

#### See Also

#### geodDist

Other functions relating to geodesy: geodDist, geodGc, geodXyInverse

```
## Not run:
# Develop a transect-based axis system for final data(section) stations
library(oce)
data(section)
lon <- tail(section[["longitude", "byStation"]], 26)</pre>
lat <- tail(section[["latitude", "byStation"]], 26)</pre>
lonR <- tail(lon, 1)</pre>
latR <- tail(lat, 1)</pre>
data(coastlineWorld)
mapPlot(coastlineWorld, proj="+proj=merc",
        longitudelim=c(-75,-65), latitudelim=c(35,43), col="gray")
mapPoints(lon, lat)
XY <- geodXy(lon,lat,mean(lon), mean(lat))</pre>
angle <- 180/pi*atan(coef(lm(y~x, data=XY))[2])
mapCoordinateSystem(lonR, latR, 500, angle, col=2)
# Compare UTM calculation
UTM <- lonlat2utm(lon, lat, zone=18) # we need to set the zone for this task!
angleUTM <- 180/pi*atan(coef(lm(northing~easting, data=UTM))[2])</pre>
mapCoordinateSystem(lonR, latR, 500, angleUTM, col=3)
legend("topright", lwd=1, col=2:3, bg="white", title="Axis Rotation Angle",
       legend=c(sprintf("geod: %.1f deg", angle), sprintf("utm: %.1f deg",angleUTM)))
## End(Not run)
```

geodXyInverse 141

geodXyInverse	Inverse Geodesic Calculation

## **Description**

The calculation is done by finding a minimum value of a cost function that is the vector difference between (x,y) and the corresponding values returned by geodXy. See "Caution".

### Usage

```
geodXyInverse(x, y, longitudeRef, latitudeRef, debug = getOption("oceDebug"))
```

### **Arguments**

value of x in metres, as given by geodXy
 value of y in metres, as given by geodXy
 longitudeRef
 reference longitude, as supplied to geodXy
 reference latitude, as supplied to geodXy

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## **Details**

The minimum is calculated in C for speed, using the nmmin function that is the underpinning for the Nelder-Meade version of the R function optim. If you find odd results, try setting debug=1 and rerunning, to see whether this optimizer is having difficulty finding a minimum of the mismatch function.

#### Value

a data frame containing longitude and latitude

#### Caution

This scheme is without known precedent in the literature, and users should read the documentation carefully before deciding to use it.

### See Also

Other functions relating to geodesy: geodDist, geodGc, geodXy

142 gps-class

GMTOffsetFromTz

Determine time offset from timezone

# **Description**

The data are from <a href="http://www.timeanddate.com/library/abbreviations/timezones/">http://www.timeanddate.com/library/abbreviations/timezones/</a> and were hand-edited to develop this code, so there may be errors. Also, note that some of these contradict; if you examine the code, you'll see some commented-out portions that represent solving conflicting definitions by choosing the more common timezone abbreviation over a the less common one.

# Usage

```
GMTOffsetFromTz(tz)
```

### **Arguments**

tz

a timezone, e.g. UTC.

#### Value

Number of hours in offset, e.g. AST yields 4.

# Author(s)

Dan Kelley

### See Also

Other functions relating to time: decodeTime

### **Examples**

```
library(oce)
cat("Atlantic Standard Time is ", GMTOffsetFromTz("AST"), "hours after UTC")
```

gps-class

Class to Store GPS Data

# Description

Class to store gps data. These objects may be read with read.gps or assembled with as.gps.

# Author(s)

Dan Kelley

grad 143

### See Also

Other things related to gps data: [[,gps-method, [[<-,gps-method, as.gps, plot,gps-method, read.gps, summary,gps-method

grad

Calculate the grad of a matrix by first differences

## **Description**

In the interior of the matrix, centred second-order differences are used to infer the components of the grad. Along the edges, first-order differences are used.

# Usage

```
grad(h, x, y)
```

# Arguments

```
h a matrix x x values y y values
```

#### Value

A list containing gx and gy, matrices of the same dimension as h.

### Author(s)

Dan Kelley, based on advice of Clark Richards, and mimicking a matlab function.

### See Also

Other functions relating to vector calculus: curl

```
## Geostrophic flow around an eddy
library(oce)
dx <- 5e3
dy <- 10e3
x <- seq(-200e3, 200e3, dx)
y <- seq(-200e3, 200e3, dy)
R <- 100e3
h <- outer(x, y, function(x, y) 500*exp(-(x^2+y^2)/R^2))
grad <- grad(h, x, y)
par(mfrow=c(2, 2), mar=c(3, 3, 1, 1), mgp=c(2, 0.7, 0))
contour(x,y,h,asp=1, main=expression(h))
f <- 1e-4</pre>
```

144 gravity

```
gprime <- 9.8 * 1 / 1024
u <- -(gprime / f) * grad$gy
v <- (gprime / f) * grad$gx
contour(x, y, u, asp=1, main=expression(u))
contour(x, y, v, asp=1, main=expression(v))
contour(x, y, sqrt(u^2+v^2), asp=1, main=expression(speed))</pre>
```

gravity

Acceleration due to earth gravity

# Description

Compute g, the acceleration due to gravity, as a function of latitude.

## Usage

```
gravity(latitude = 45, degrees = TRUE)
```

# Arguments

latitude Latitude in °N or radians north of the equator.

degrees Flag indicating whether degrees are used for latitude; if set to FALSE, radians are

used.

# **Details**

Value not verified yet, except roughly.

### Value

Acceleration due to gravity  $[m^2/s]$ .

### Author(s)

Dan Kelley

### References

Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.

Caution: Fofonoff and Millard (1983 UNESCO) use a different formula.

```
g <- gravity(45) # 9.8
```

145 handleFlags

handleFlags

Handle flags in oce objects

### **Description**

Data-quality flags are stored in the metadata slot of oce-class objects in a list named flags. The present function (a generic that has specialized versions for various data classes) provides a way to manipulate the core data based on the data-quality flags. For example, a common operation is to replace suspicious or erroneous data with NA.

If metadata\$flags in the object supplied as the first argument is empty, then that object is returned, unaltered. Otherwise, handleFlags analyses the data-quality flags within the object, in relation to the flags argument, and interprets the action argument to select an action to be applied to matched

Reasonable defaults are used if flags and actions are not supplied (see 'Details'), but different schemes are used in different data archives, so it is risky to rely on these defaults. It is usually necessary to tailor flags and actions to the data and the analysis goals.

#### Usage

```
handleFlags(object, flags = NULL, actions = NULL,
  debug = options("oceDebug"))
```

### **Arguments**

object An object of oce.

flags An optional list containing (a) items with names of entries in the data slot of object, or (b) a single unnamed item. In the first case, the attention is focussed

on the named items, while in the second case the all the data in the object's data slot are examined. Each element in the list must be set to an integer or vector of integers, specifying conditions to be met before actions are to be taken.

See "Details" for the default that is used if flags is not supplied.

actions An optional list that contains items with names that match those in the flags

> argument. If actions is not supplied, the default will be to set all values identified by flags to NA; this can also be specified by specifying actions=list("NA"). It is also possible to specify functions that calculate replacement values. These are provided with object as the single argument, and must return a replacement for the data item in question. See "Details" for the default that is used if actions

is not supplied.

An optional integer specifying the degree of debugging, with value 0 meaning to skip debugging and 1 or higher meaning to print some information about the

arguments and the data. It is usually a good idea to set this to 1 for initial work with a dataset, to see which flags are being handled for each data item. If not

supplied, this defaults to the value of getOption("oceDebug").

debug

#### **Details**

Each specialized variant of this function has its own defaults for flags and actions.

#### See Also

Other functions that handle data-quality flags: handleFlags, argo-method, handleFlags, ctd-method, handleFlags, section-method

handleFlags, argo-method

Handle Flags in ARGO Objects

## **Description**

Data-quality flags are stored in the metadata slot of oce-class objects in a list named flags. The present function (a generic that has specialized versions for various data classes) provides a way to manipulate the core data based on the data-quality flags. For example, a common operation is to replace suspicious or erroneous data with NA.

If metadata\$flags in the object supplied as the first argument is empty, then that object is returned, unaltered. Otherwise, handleFlags analyses the data-quality flags within the object, in relation to the flags argument, and interprets the action argument to select an action to be applied to matched data.

Reasonable defaults are used if flags and actions are not supplied (see 'Details'), but different schemes are used in different data archives, so it is risky to rely on these defaults. It is usually necessary to tailor flags and actions to the data and the analysis goals.

## Usage

```
## S4 method for signature 'argo'
handleFlags(object, flags = list(), actions = list(),
  debug = integer())
```

## **Arguments**

object An object of argo-class.

flags An optional list containing (a) items with names of entries in the data slot of

object, or (b) a single unnamed item. In the first case, the attention is focussed on the named items, while in the second case the all the data in the object's data slot are examined. Each element in the list must be set to an integer or vector of integers, specifying conditions to be met before actions are to be taken.

See "Details" for the default that is used if flags is not supplied.

actions An optional list that contains items with names that match those in the flags

argument. If actions is not supplied, the default will be to set all values identified by flags to NA; this can also be specified by specifying actions=list("NA"). It is also possible to specify functions that calculate replacement values. These

are provided with object as the single argument, and must return a replacement for the data item in question. See "Details" for the default that is used if actions is not supplied.

debug

An optional integer specifying the degree of debugging, with value 0 meaning to skip debugging and 1 or higher meaning to print some information about the arguments and the data. It is usually a good idea to set this to 1 for initial work with a dataset, to see which flags are being handled for each data item. If not supplied, this defaults to the value of getOption("oceDebug").

### **Details**

If flags and actions are not provided, the default is to use ARGO flags [1], in which the value 1 indicates good data, and other values indicate either unchecked, suspicious, or bad data. Any data not flagged as good are set to NA in the returned value. Since Argo flag codes run from 0 to 9, with 1 indicating the highest level of confidence in the data, the defaults are flags=list(c(0,2:9)) and actions=list("NA").

#### References

1. http://www.argo.ucsd.edu/Argo\_date\_guide.html#dmodedata

#### See Also

Other functions that handle data-quality flags: handleFlags,ctd-method, handleFlags,section-method, handleFlags

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, as.argo, plot,argo-method, read.argo, subset,argo-method, summary,argo-method

## **Examples**

```
## Not run:
library(oce)
data(argo)
# 1. Default: anything not flagged as 1 is set to NA, to focus
# solely on 'good', in the Argo scheme.
argoNew <- handleFlags(argo)</pre>
# demonstrate replacement, looking at the second profile
f <- argo[["salinityFlag"]][,2] # first column with a flag=4 entry</pre>
df <- data.frame(flag=f, orig=argo[["salinity"]][,2], new=argoNew[["salinity"]][,2])</pre>
df[11:15,]
##
      flag orig
                     new
## 11
        1 35.207 35.207
## 12
        1 35.207 35.207
## 13
        4 35.209
## 14
         1 35.207 35.207
         1 35.207 35.207
# 2. A less restrictive case: include also 'questionable' data,
# and only apply this action to salinity.
```

```
argoNew <- handleFlags(argo, flags=list(salinity=4))
## End(Not run)</pre>
```

handleFlags,ctd-method

Handle Flags in CTD Objects

## **Description**

Data-quality flags are stored in the metadata slot of oce-class objects in a list named flags. The present function (a generic that has specialized versions for various data classes) provides a way to manipulate the core data based on the data-quality flags. For example, a common operation is to replace suspicious or erroneous data with NA.

If metadata\$flags in the object supplied as the first argument is empty, then that object is returned, unaltered. Otherwise, handleFlags analyses the data-quality flags within the object, in relation to the flags argument, and interprets the action argument to select an action to be applied to matched data.

Reasonable defaults are used if flags and actions are not supplied (see 'Details'), but different schemes are used in different data archives, so it is risky to rely on these defaults. It is usually necessary to tailor flags and actions to the data and the analysis goals.

## Usage

```
## S4 method for signature 'ctd'
handleFlags(object, flags = list(), actions = list(),
  debug = integer())
```

### Arguments

object A ctd object, i.e. one inheriting from ctd-class.

flags An optional list containing (a) items with names of entries in the data slot of

object, or (b) a single unnamed item. In the first case, the attention is focussed on the named items, while in the second case the all the data in the object's data slot are examined. Each element in the list must be set to an integer or vector of integers, specifying conditions to be met before actions are to be taken.

See "Details" for the default that is used if flags is not supplied.

An optional list that contains items with names that match those in the flags argument. If actions is not supplied, the default will be to set all values identified by flags to NA; this can also be agreeifed by apprinting actions list ("NA")

fied by flags to NA; this can also be specified by specifying actions=list("NA"). It is also possible to specify functions that calculate replacement values. These are provided with object as the single argument, and must return a replacement for the data item in question. See "Details" for the default that is used if actions

is not supplied.

debug

An optional integer specifying the degree of debugging, with value 0 meaning to skip debugging and 1 or higher meaning to print some information about the arguments and the data. It is usually a good idea to set this to 1 for initial work with a dataset, to see which flags are being handled for each data item. If not supplied, this defaults to the value of getOption("oceDebug").

#### **Details**

If flags and actions are not provided, the default is to use WHP (World Hydrographic Program) flags [1], in which the value 2 indicates good data, and other values indicate either unchecked, suspicious, or bad data. Any data not flagged as good are set to NA in the returned value. (An exception is for salinity: if the item named salinity has a bad flag but salinityBottle has a good flag, then the bottle value is substituted, and a warning is issued.) Since WHP flag codes run from 1 to 9, this default is equivalent to setting flags=list(all=c(1, 3:9)) along with action=list("NA").

#### References

```
1. https://www.nodc.noaa.gov/woce/woce_v3/wocedata_1/whp/exchange/exchange_format_
desc.htm
```

#### See Also

Other functions that handle data-quality flags: handleFlags, argo-method, handleFlags, section-method, handleFlags

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

## **Examples**

```
library(oce)
data(section)
stn <- section[["station", 100]]</pre>
# 1. Default: anything not flagged as 2 is set to NA, to focus
# solely on 'good', in the World Hydrographic Program scheme.
STN <- handleFlags(stn)</pre>
data.frame(old=stn[['salinity']], flag=stn[['salinityFlag']], new=STN[['salinity']])
# 2. A less restrictive case: include also 'questionable' data,
# and only apply this action to salinity.
STN <- handleFlags(stn, flags=list(salinity=c(1, 4:9)))
# 3. A Canadian Department of Fisheries and Oceans convention for
# some of its data files lists flags as 0=unchecked, 1=good,
# 2=uncertain, 3=doubtful, 4=wrong, and 5=changed, so a
# trusting arrangement would be to discard 2:4, and a more
# cautious approach would be to also discard 0.
STN <- handleFlags(stn, flags=list(2:4))</pre>
```

```
STN <- handleFlags(stn, flags=list(c(0,2:4)))
# 4. Use smoothed TS relationship to nudge questionable data.
# This is not a recommended procedure, but rather just a simple
# illustration of how to supply a function for an action.
f<-function(x) {
 S <- x[["salinity"]]</pre>
 T <- x[["temperature"]]</pre>
 df <- 0.5 * length(S) # smooths a bit
 sp <- smooth.spline(T, S, df=df)</pre>
 0.5 * (S + predict(sp, T)$y)
par(mfrow=c(1,2))
STN <- handleFlags(stn, flags=list(salinity=c(1,3:9)), action=list(salinity=f))
plotProfile(stn, "salinity", mar=c(3, 3, 3, 1))
p <- stn[['pressure']]</pre>
par(mar=c(3, 3, 3, 1))
plot(STN[['salinity']] - stn[['salinity']], p, ylim=rev(range(p)))
```

handleFlags, section-method

Handle flags in Section Objects

## **Description**

Data-quality flags are stored in the metadata slot of oce-class objects in a list named flags. The present function (a generic that has specialized versions for various data classes) provides a way to manipulate the core data based on the data-quality flags. For example, a common operation is to replace suspicious or erroneous data with NA.

If metadata\$flags in the object supplied as the first argument is empty, then that object is returned, unaltered. Otherwise, handleFlags analyses the data-quality flags within the object, in relation to the flags argument, and interprets the action argument to select an action to be applied to matched data

Reasonable defaults are used if flags and actions are not supplied (see 'Details'), but different schemes are used in different data archives, so it is risky to rely on these defaults. It is usually necessary to tailor flags and actions to the data and the analysis goals.

## Usage

```
## S4 method for signature 'section'
handleFlags(object, flags = list(), actions = list(),
  debug = integer())
```

## Arguments

object An object of section-class.

flags An optional list containing (a) items with names of entries in the data slot of

object, or (b) a single unnamed item. In the first case, the attention is focussed on the named items, while in the second case the all the data in the object's data slot are examined. Each element in the list must be set to an integer or vector of integers, specifying conditions to be met before actions are to be taken.

See "Details" for the default that is used if flags is not supplied.

actions An optional list that contains items with names that match those in the flags

argument. If actions is not supplied, the default will be to set all values identified by flags to NA; this can also be specified by specifying actions=list("NA"). It is also possible to specify functions that calculate replacement values. These are provided with object as the single argument, and must return a replacement for the data item in question. See "Details" for the default that is used if actions

is not supplied.

debug An optional integer specifying the degree of debugging, with value 0 meaning

to skip debugging and 1 or higher meaning to print some information about the arguments and the data. It is usually a good idea to set this to 1 for initial work with a dataset, to see which flags are being handled for each data item. If not

supplied, this defaults to the value of getOption("oceDebug").

#### **Details**

If flags and actions are not provided, the default is to use WHP (World Hydrographic Program) flags [1], in which the value 2 indicates good data, and other values indicate either unchecked, suspicious, or bad data. Any data not flagged as good are set to NA in the returned value. Since WHP flag codes run from 1 to 9, this default is equivalent to setting flags=list(all=c(1, 3:9)) along with action=list("NA").

## References

```
1. https://www.nodc.noaa.gov/woce/woce_v3/wocedata_1/whp/exchange/exchange_format_
desc.htm
```

#### See Also

Other functions that handle data-quality flags: handleFlags, argo-method, handleFlags, ctd-method, handleFlags

Other things related to section data: [[,section-method, [[<-,section-method, as.section, plot, section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method

## **Examples**

```
library(oce)
data(section)
section2 <- handleFlags(section)
par(mfrow=c(2, 1))
plotTS(section)
plotTS(section2)</pre>
```

head.oce

```
handleFlags, vector-method
```

Signal erroneous application to non-oce objects

# **Description**

Signal erroneous application to non-oce objects

## Usage

```
## S4 method for signature 'vector'
handleFlags(object, flags = list(), actions = list(),
  debug = integer())
```

## **Arguments**

object A vector, which cannot be the case for oce objects.

flags Ignored. actions Ignored. debug Ignored.

head.oce

Extract The Start of an Oce Object

## **Description**

Extract The Start of an Oce Object

## Usage

```
## S3 method for class 'oce' head(x, n = 6L, ...)
```

## **Arguments**

x An oce object of a suitable class (presently only adp is permitted).

n Number of elements to extract.

... ignored

## See Also

tail.oce, which yields the end of an oce object.

imagep

Plot an Image with a Color Palette

#### **Description**

Plot an image with a colour palette, in a way that does not conflict with par(mfrow) or layout. To plot just a palette, e.g. to get an x-y plot with points coloured according to a palette, use drawPalette and then draw the main diagram.

#### Usage

```
imagep(x, y, z, xlim, ylim, zlim, zclip = FALSE, flipy = FALSE, xlab = "",
 ylab = "", zlab = "", zlabPosition = c("top", "side"),
 decimate = TRUE, breaks, col, colormap, labels = NULL, at = NULL,
 drawContours = FALSE, drawPalette = TRUE, drawTriangles = FALSE,
 tformat, drawTimeRange = getOption("oceDrawTimeRange"),
 filledContour = FALSE, missingColor = NULL, useRaster,
 mgp = getOption("oceMgp"), mar, mai.palette, xaxs = "i", yaxs = "i",
 asp = NA, cex = par("cex"), axes = TRUE, main = "", axisPalette,
 add = FALSE, debug = getOption("oceDebug"), ...)
```

#### **Arguments**

х, у

These have different meanings in different modes of operation. *Mode 1*. One mode has them meaning the locations of coordinates along which values matrix z are defined. In this case, both x and y must be supplied and, within each, the values must be finite and distinct; if values are out of order, they (and z) will be transformed to put them in order. ordered in a matching way). Mode 2. If z is provided but not x and y, then the latter are constructed to indicate the indices of the matrix, in contrast to the range of 0 to 1, as is the case for image. *Mode* 3. If x is a list, its components x\$x and x\$y are used for x and y, respectively. If the list has component z this is used for z. (NOTE: these arguments are meant to mimic those of image, which explains the same description here.) Mode 4. There are also some special cases, e.g. if x is a topographic object such as can be created with read. topo or as. topo, then longitude and latitude are used for axes, and topographic height is drawn.

Z

A matrix containing the values to be plotted (NAs are allowed). Note that x can be used instead of z for convenience. (NOTE: these arguments are meant to mimic those of image, which explains the same description here.)

xlim, ylim

Limits on x and y axes.

zlim

If missing, the z scale is determined by the range of the data. If provided, zlim may take several forms. First, it may be a pair of numbers that specify the limits for the colour scale. Second, it could be the string "histogram", to yield a flattened histogram (i.e. to increase contrast). Third, it could be the string "symmetric", to yield limits that are symmetric about zero, which can be helpful in drawing velocity fields, for which a zero value has a particular meaning (in which case, a good colour scheme might be col=oceColorsTwo).

zclip Logical, indicating whether to clip the colours to those corresponding to zlim.

This only works if zlim is provided. Clipped regions will be coloured with missingColor. Thus, clipping an image is somewhat analogous to clipping in an xy plot, with clipped data being ignored, which in an image means to be be

coloured with missingColor.

flipy Logical, with TRUE indicating that the image should be flipped top to bottom (e.g.

to produce a profile image for a downward-looking acoustic-doppler profile).

xlab, ylab, zlab

Names for x axis, y axis, and the image values.

zlabPosition String indicating where to put the label for the z axis, either at the top-right of

the main image, or on the side, in the axis for the palette.

decimate Controls whether the image will be decimated before plotting, in three possible

cases. Case 1. If decimate=FALSE then every grid cell in the matrix will be represented by a pixel in the image. Case 2 (the default). If decimate=TRUE, then decimation will be done in the horizontal or vertical direction (or both) if the length of the corresponding edge of the z matrix exceeds 800. (This also creates a warning message.) The decimation factor is computed as the integer just below the ratio of z dimension to 400. Thus, no decimation is done if the dimension is less than 800, but if the dimension s between 800 and 1199, only every second grid point is mapped to a pixel in the image. Case 3. If decimate is an integer, then that z is subsampled at seq.int(1L, dim(z)[1], by=decimate) (as is x), and the same is done for the y direction. Case 4. If decimate is a vector of two integers, the first is used for the first index of z, and the second is used for

the second index.

breaks The z values for breaks in the colour scheme. If this is of length 1, the value indi-

cates the desired number of breaks, which is supplied to pretty, in determining clean break points.

Either a vector of colours corresponding to the breaks, of length 1 plus the number of breaks, or a function specifying colours, e.g. oce.colorsJet for a rain-

colormap A colour map as created by colormap. If provided, then colormap\$breaks and colormap\$col take precedence over the present arguments breaks and col.

(All of the other contents of colormap are ignored, though.)

labels Optional vector of labels for ticks on palette axis (must correspond with at).

Optional vector of positions for the labels.

Logical value indicating whether to draw contours on the image, and palette, at the colour breaks. Images with a great deal of high-wavenumber variation look

poor with contours.

drawPalette Indication of the type of palette to draw, if any. If drawPalette=TRUE, a palette is drawn at the right-hand side of the main image. If drawPalette=FALSE,

no palette is drawn, and the right-hand side of the plot has a thin margin. If drawPalette="space", then no palette is drawn, but space is put in the righthand margin to occupy the region in which the palette would have been drawn. This last form is useful for producing stacked plots with uniform left and right

margins, but with palettes on only some of the images.

col

at

drawContours

drawTriangles Logical value indicating whether to draw triangles on the top and bottom of the

palette. This is passed to drawPalette.

tformat Optional argument passed to oce.plot.ts, for plot types that call that function.

(See strptime for the format used.)

drawTimeRange Logical, only used if the x axis is a time. If TRUE, then an indication of the time

range of the data (not the axis) is indicated at the top-left margin of the graph. This is useful because the labels on time axes only indicate hours if the range is

less than a day, etc.

filledContour Boolean value indicating whether to use filled contours to plot the image.

missingColor A colour to be used to indicate missing data, or NULL for transparent (to see this,

try setting par("bg")<-"red").

useRaster A logical value passed to image, in cases where filledContour is FALSE. Set-

ting useRaster=TRUE can alleviate some anti-aliasing effects on some plot de-

vices; see the documentation for image.

mgp A 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar A 4-element Value to be used with par ("mar"). If not given, a reasonable value

is calculated based on whether xlab and ylab are empty strings.

mai.palette Palette margin corrections (in inches), added to the mai value used for the palette.

Use with care.

xaxs Character indicating whether image should extend to edge of x axis (with value

"i") or not; see par("xaxs").

yaxs As xaxs but for y axis.

asp Aspect ratio of the plot, as for plot.default. If x inherits from topo-class

and asp=NA (the default) then asp is redefined to be the reciprocal of the mean latitude in x, as a way to reduce geographical distortion. Otherwise, if asp is not

NA, then it is used directly.

cex Size of labels on axes and palette; see par("cex").

axes Logical, set TRUE to get axes on the main image.

main Title for plot.

axisPalette Optional replacement function for axis(), passed to drawPalette.

add Logical value indicating whether to add to an existing plot. The default value,

FALSE indicates that a new plot is to be created. However, if add is TRUE, the idea is to add an image (but not its palette or its axes) to an existing plot. Clearly, then, arguments such xlim are to be ignored. Indeed, if add=TRUE, the only arguments examined are x (which must be a vector; the mode of providing a matrix or oce object does not work), y, z, decimate, plus either colormap or

both breaks and col.

debug A flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

. . . Optional arguments passed to plotting functions.

#### **Details**

By default, creates an image with a colour palette to the right. The effect is similar to filled.contour except that with imagep it is possible to set the layout outside the function, which enables the creation of plots with many image-palette panels. Note that the contour lines may not coincide with the colour transitions, in the case of coarse images.

Note that this does not use layout or any of the other screen splitting methods. It simply manipulates margins, and draws two plots together. This lets users employ their favourite layout schemes.

NOTE: imagep is an analogue of image, and from that it borrows a the convention that the number of rows in the matrix corresponds to to x axis, not the y axis. (Actually, image permits the length of x to match either nrow(z) or 1+nrow(z), but here only the first is permitted.)

#### Value

A list is silently returned, containing xat and yat, values that can be used by oce.grid to add a grid to the plot.

## Author(s)

Dan Kelley and Clark Richards

#### See Also

This uses drawPalette, and is used by plot,adp-method, plot,landsat-method, and other image-generating functions.

## **Examples**

```
library(oce)
# 1. simplest use
imagep(volcano)
# 2. something oceanographic (internal-wave speed)
h \leftarrow seq(0, 50, length.out=100)
drho <- seq(1, 3, length.out=200)</pre>
speed <- outer(h, drho, function(drho, h) sqrt(9.8 * drho * h / 1024))</pre>
imagep(h, drho, speed, xlab="Equivalent depth [m]",
ylab=expression(paste(Delta*rho, " [kg/m^3]")),
zlab="Internal-wave speed [m/s]")
# 3. fancy labelling on atan() function
x < - seq(0, 1, 0.01)
y < - seq(0, 1, 0.01)
angle <- outer(x,y,function(x,y) atan2(y,x))</pre>
imagep(x, y, angle, filledContour=TRUE, breaks=c(0, pi/4, pi/2),
       col=c("lightgray", "darkgray"),
       at=c(0, pi/4, pi/2),
       labels=c(0, expression(pi/4), expression(pi/2)))
# 4. a colormap case
```

integerToAscii 157

```
data(topoWorld)
cm <- colormap(name="gmt_globe")
imagep(topoWorld, colormap=cm)</pre>
```

integerToAscii

Decode integer to corresponding ASCII code

# **Description**

Decode integer to corresponding ASCII code

# Usage

```
integerToAscii(i)
```

# Arguments

i

an integer, or integer vector.

#### Value

A character, or character vector.

## Author(s)

Dan Kelley

# Examples

```
library(oce)
A <- integerToAscii(65)
cat("A=", A, "\n")</pre>
```

integrate Trapezoid

Trapezoidal Integration

# Description

Estimate the integral of one-dimensional function using the trapezoidal rule.

# Usage

```
integrateTrapezoid(x, y, type = c("A", "dA", "cA"), xmin, xmax)
```

158 interpBarnes

### **Arguments**

x, y vectors of x and y values. In the normal case, these vectors are both supplied, and of equal length. There are also two special cases. First, if y is missing, then x is taken to be y, and a new x is constructed as seq\_along(y). Second, if length(x) is 1 and length(y) exceeds 1, then x is replaced by x\*seq\_along(y).

type Flag indicating the desired return value (see "Value").

xmin, xmax Optional numbers indicating the range of the integration. These values may be

used to restrict the range of integration, or to extend it; in either case, approx

with rule=2 is used to create new x and y vectors.

#### Value

If type="A" (the default), a single value is returned, containing the estimate of the integral of y=y(x). If type="dA", a numeric vector of the same length as x, of which the first element is zero, the second element is the integral between x[1] and x[2], etc. If type="cA", the result is the cumulative sum (as in cumsum) of the values that would be returned for type="dA". See "Examples".

## **Bugs**

There is no handling of NA values.

### Author(s)

Dan Kelley

# Examples

```
x <- seq(0, 1, length.out=10) # try larger length.out to see if area approaches 2
y <- 2*x + 3*x^2
A <- integrateTrapezoid(x, y)
dA <- integrateTrapezoid(x, y, "dA")
cA <- integrateTrapezoid(x, y, "cA")
print(A)
print(sum(dA))
print(tail(cA, 1))
print(integrateTrapezoid(diff(x[1:2]), y))
print(integrateTrapezoid(y))</pre>
```

interpBarnes

Grid data using Barnes algorithm

# Description

The algorithm follows that described by Koch et al. (1983), with the addition of the ability to blank out the grid in spots where data are sparse, using the trim argument, and the ability to pre-grid, with the pregrid argument.

159 interpBarnes

#### Usage

```
interpBarnes(x, y, z, w, xg, yg, xgl, ygl, xr, yr, gamma = 0.5,
 iterations = 2, trim = 0, pregrid = FALSE,
 debug = getOption("oceDebug"))
```

## **Arguments**

xg, yg

gamma

iterations

x, y	a vector of x and ylocations.
z	a vector of z values, one at each (x,y) location.
W	a optional vector of weights at the $(x,y)$ location. If not supplied, then a weight of 1 is used for each point, which means equal weighting. Higher weights give data points more influence.

optional vectors defining the x and y grids. If not supplied, these values are inferred from the data, using e.g. pretty(x, n=50).

optional lengths of the x and y grids, to be constructed with seq spanning the xgl, ygl data range. These values xgl are only examined if xg and yg are not supplied.

optional values defining the width of the radius ellipse in the x and y directions. xr, yr If not supplied, these are calculated as the span of x and y over the square root of the number of data.

grid-focussing parameter. At each iteration, xr and yr are reduced by a factor

of sqrt(gamma). number of iterations.

trim a number between 0 and 1, indicating the quantile of data weight to be used as

a criterion for blanking out the gridded value (using NA). If 0, the whole zg grid is returned. If >0, any spots on the grid where the data weight is less than the

trim-th quantile are set to NA. See examples.

pregrid an indication of whether to pre-grid the data. If FALSE, this is not done, i.e.

> conventional Barnes interpolation is performed. Otherwise, then the data are first averaged within grid cells using binMean2D. If pregrid is TRUE or 4, then this averaging is done within a grid that is 4 times finer than the grid that will be used for the Barnes interpolation. Otherwise, pregrid may be a single integer indicating the grid refinement (4 being the result if TRUE had been supplied), or a vector of two integers, for the grid refinement in x and y. The purpose of using pregrid is to speed processing on large datasets, and to remove spatial bias (e.g. with a single station that is repeated frequently in an otherwise seldom-sampled region). A form of pregridding is done in the World Ocean Atlas, for example.

debug a flag that turns on debugging. Set to 0 for no debugging information, to 1 for

more, etc; the value is reduced by 1 for each descendent function call.

#### Value

A list containing: xg, a vector holding the x-grid); yg, a vector holding the y-grid; zg, a matrix holding the gridded values; wg, a matrix holding the weights used in the interpolation at its final iteration; and zd, a vector of the same length as x, which holds the interpolated values at the data points.

interpBarnes

## Author(s)

Dan Kelley

#### References

S. E. Koch and M. DesJardins and P. J. Kocin, 1983. "An interactive Barnes objective map analysis scheme for use with satellite and conventional data," *J. Climate Appl. Met.*, vol 22, p. 1487-1503.

#### See Also

See wind.

### **Examples**

```
library(oce)
# 1. contouring example, with wind-speed data from Koch et al. (1983)
data(wind)
u <- interpBarnes(wind$x, wind$y, wind$z)</pre>
contour(u$xg, u$yg, u$zg, labcex=1)
text(wind$x, wind$y, wind$z, cex=0.7, col="blue")
title("Numbers are the data")
# 2. As 1, but blank out spots where data are sparse
u <- interpBarnes(wind$x, wind$y, wind$z, trim=0.1)</pre>
contour(u$xg, u$yg, u$zg, level=seq(0, 30, 1))
points(wind$x, wind$y, cex=1.5, pch=20, col="blue")
# 3. As 1, but interpolate back to points, and display the percent mismatch
u <- interpBarnes(wind$x, wind$y, wind$z)</pre>
contour(u$xg, u$yg, u$zg, labcex=1)
mismatch <- 100 * (wind$z - u$zd) / wind$z
text(wind$x, wind$y, round(mismatch), col="blue")
title("Numbers are percent mismatch between grid and data")
# 4. As 3, but contour the mismatch
mismatchGrid <- interpBarnes(wind$x, wind$y, mismatch)</pre>
contour(mismatchGrid$xg, mismatchGrid$yg, mismatchGrid$zg, labcex=1)
# 5. One-dimensional example, smoothing a salinity profile
data(ctd)
p <- ctd[["pressure"]]</pre>
y \leftarrow rep(1, length(p)) # fake y data, with arbitrary value
S <- ctd[["salinity"]]</pre>
pg <- pretty(p, n=100)
g <- interpBarnes(p, y, S, xg=pg, xr=1)</pre>
plot(S, p, cex=0.5, col="blue", ylim=rev(range(p)))
lines(g$zg, g$xg, col="red")
```

julianCenturyAnomaly

julianCenturyAnomaly Julian-Day number to Julian century

## **Description**

Convert a Julian-Day number to a time in julian centuries since noon on January 1, 1900. The method follows Meese (1982 equation 15.1). The example reproduces the example provided by Meeuse (1982 example 15.a), with fractional error 3e-8.

## Usage

```
julianCenturyAnomaly(jd)
```

### **Arguments**

jd

a julian day number, e.g. as given by julianDay.

### Value

Julian century since noon on January 1, 1900.

### Author(s)

Dan Kelley

### References

Meeus, Jean, 1982. Astronomical formuae for Calculators. Willmann-Bell. Richmond VA, USA. 201 pages

#### See Also

Other things related to astronomy: eclipticalToEquatorial, equatorialToLocalHorizontal, julianDay, moonAngle, siderealTime, sunAngle

Other things related to time: ctimeToSeconds, julianDay, numberAsHMS, numberAsPOSIXct, secondsToCtime, unabbreviateYear

# **Examples**

```
t <- ISOdatetime(1978, 11, 13, 4, 35, 0, tz="UTC")
jca <- julianCenturyAnomaly(julianDay(t))
cat(format(t), "is Julian Century anomaly", format(jca, digits=8), "\n")</pre>
```

julianDay

julianDay

Convert a POSIXt time to a Julian day

### **Description**

Convert a POSIXt time to a Julian day, using the method provided in Chapter 3 of Meeus (1982). It should be noted that Meeus and other astronomical treatments use fractional days, whereas the present code follows the R convention of specifying days in whole numbers, with hours, minutes, and seconds also provided as necessary. Conversion is simple, as illustrated in the example for 1977 April 26.4, for which Meeus calculates julian day 2443259.9. Note that the R documentation for julian suggests another formula, but the point of the present function is to match the other Meeus formulae, so that suggestion is ignored here.

## Usage

```
julianDay(t, year = NA, month = NA, day = NA, hour = NA, min = NA,
  sec = NA, tz = "UTC")
```

## **Arguments**

t	a time, in POSIXt format, e.g. as created by as.POSIXct, as.POSIXlt, or numberAsPOSIXct. If this is provided, the other arguments are ignored.
year	year, to be provided along with month, etc., if t is not provided.
month	month, numbered with January being 1.
day	day in month, starting at 1.
hour	hour of day.
min	minute of hour
sec	second of hour
tz	timezone

## Value

A Julian-Day number, in astronomical convention as explained in Meeus.

## Author(s)

Dan Kelley

# References

Meeus, Jean, 1982. Astronomical formuae for Calculators. Willmann-Bell. Richmond VA, USA. 201 pages

ladp-class 163

### See Also

Other things related to astronomy: eclipticalToEquatorial, equatorialToLocalHorizontal, julianCenturyAnomaly, moonAngle, siderealTime, sunAngle

Other things related to time: ctimeToSeconds, julianCenturyAnomaly, numberAsHMS, numberAsPOSIXct, secondsToCtime, unabbreviateYear

## **Examples**

```
t <- ISOdatetime(1977, 4, 26, hour=0, min=0, sec=0, tz="ET")+0.4*86400 jd <- julianDay(t) cat(format(t), "is Julian Day", format(jd, digits=14), "\n")
```

ladp-class

Class to store lowered-adp data

## **Description**

Class to store data measured with a lowered ADP (also known as ADCP) device.

# Accessing data

Consider an object named ladp.

Metadata (contained in the S4 slot named metadata) may be retrieved or set by name, ladp[["longitude"]] <- ladp["l

Column data may be accessed by name, e.g. ladp[["u"]], ladp[["v"]], ladp[["pressure"]], etc. There may also be columns for "temperature" and "salinity", and possibly other things. Use names (ladp@data) to find the names of the data.

## Author(s)

Dan Kelley

#### See Also

Other things related to ladp data: [[,ladp-method, as.ladp, plot,ladp-method, summary,ladp-method

164 landsat-class

landsat

Sample landsat Dataset

### **Description**

This is a subset of the Landsat-8 image designated LC80080292014065LGN00, an image from March 2014 that covers Nova Scotia and portions of the Bay of Fundy and the Scotian Shelf. The image is decimated to reduce the memory requirements of this package, yielding a spatial resolution of about 2km.

#### **Details**

The original data were downloaded from the USGS earthexplorer website, although other sites can also be used to uncover it by name. The original data were decimation by a factor of 100 to reduce the file size from about 1GB to under 100Kb.

### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to landsat data: [[,landsat-method,landsat-class,landsatAdd,landsatTrim, plot,landsat-method,read.landsat,summary,landsat-method

landsat-class

Class to Hold landsat Data

#### **Description**

This class has the standard slots of an oce-class object. Landsat data are available at several websites (e.g. [1]). Although the various functions may work for other satellites, the discussion here focusses on Landsat 8 and Landsat 7.

## Data storage

The data are stored with 16-bit resolution. Oce breaks these 16 bits up into most-significant and least-significant bytes. For example, the aerosol band of a Landsat object named x are contained within x@data\$aerosol\$msb and x@data\$aerosol\$lsb, each of which is a matrix of raw values. The results may be combined as e.g.

256L\*as.integer(x@data[[i]]\$msb) + as.integer(x@data[[i]]\$lsb)

landsat-class 165

and this is what is returned by executing x[["aerosol"]].

Landsat data files typically occupy approximately a gigabyte of storage. That means that corresponding Oce objects are about the same size, and this can pose significant problems on computers with less than 8GB of memory. It is sensible to specify bands of interest when reading data with read.landsat, and also to use landsatTrim to isolate geographical regions that need processing.

Experts may need to get direct access to the data, and this is easy because all Landsat objects (regardless of satellite) use a similar storage form. Band information is stored in byte form, to conserve space. Two bytes are used for each pixel in Landsat-8 objects, with just one for other objects. For example, if a Landsat-8 object named L contains the tirs1 band, the most- and least-significant bytes will be stored in matrices L@data\$tirs1\$msb and L@data\$tirs1\$lsb. A similar Landsat-7 object would have the same items, but msb would be just the value 0x00.

Derived bands, which may be added to a landsat object with landsatAdd, are not stored in byte matrices. Instead they are stored in numerical matrices, which means that they use 4X more storage space for Landsat-8 images, and 8X more storage space for other satellites. A computer needs at least 8GB of RAM to work with such data.

Landsat 8

The Landsat 8 satellite has 11 frequency bands, listed below (see [2]).

	Band   No.	Band Contents			İ	(microme	ters)	İ	Resolution   (meters)
1	 1	Coastal aerosol	- <del>-</del> -	aerosol	 	0.43 -			30
-	2	Blue		blue		0.45 -	0.51	I	30
-	3	Green	1	green	I	0.53 -	0.59	I	30
-	4	Red	1	red	I	0.64 -	0.67	I	30
-	5	Near Infrared (NIR)	1	nir	1	0.85 -	0.88	1	30
-	6	SWIR 1		swir1	I	1.57 -	1.65	1	30
-	7	SWIR 2		swir2	I	2.11 -	2.29	1	30
-	8	Panchromatic		panchromatic	I	0.50 -	0.68	1	15
	9	Cirrus		cirrus		1.36 -	1.38		30
	10	Thermal Infrared (TIRS) 1		tirs1		10.60 -	11.19		100
١	11	Thermal Infrared (TIRS) 2		tirs2	1	11.50 -	12.51		100

In addition to the above, setting band="terralook" may be used as an abbreviation for band=c("red", "green", "nir").

Band 8 is panchromatic, and has the highest resolution. For convenience of programming, read.landsat subsamples the tirs1 and tirs2 bands to the 30m resolution of the other bands. See Reference [3] for information about the evolution of Landsat 8 calibration coefficients, which as of summer 2014 are still subject to change.

#### Landsat 7

Band information is as follows (from [8]). The names are not official, but are set up to roughly correspond with Landsat-8 names, according to wavelength. An exception is the Landsat-7 bands named tirs1 and tirs2, which are at two different gain settings, with identical wavelength span

166 landsat-class

for each, which roughly matches the range of the Landsat-8 bands tirs1 and tirs2 combined. This may seem confusing, but it lets code like plot(im, band="tirs1") to work with both Landsat-8 and Landsat-7.

Band     No.	Band Contents		•	Waveleng (microme		•	•
2		blue   green   red   nir		0.45 - 0.52 - 0.63 - 0.77 -	0.60 0.69	İ	30   30   30   30
5     6     7     8	SWIR Thermal IR	swir1   tirs1	   	1.55 - 10.4 - 10.4 - 2.09 -	1.75 12.50 12.50 2.35	     	30   30   30   30   30   15

### Author(s)

Dan Kelley and Clark Richards

#### References

- 1. See the USGS "glovis" web site.
- 2. see landsat.gsfc.nasa.gov/?page\_id=5377
- 3. see landsat.usgs.gov/calibration\_notices.php
- 4. http://dankelley.github.io/r/2014/07/01/landsat.html
- 5. http://scienceofdoom.com/2010/12/27/emissivity-of-the-ocean/
- 6. see landsat.usgs.gov/Landsat8\_Using\_Product.php
- 7. see landsathandbook.gsfc.nasa.gov/pdfs/Landsat7\_Handbook.pdf
- 8. see landsat.usgs.gov/band\_designations\_landsat\_satellites.php
- 9. Yu, X. X. Guo and Z. Wu., 2014. Land Surface Temperature Retrieval from Landsat 8 TIRS-Comparison between Radiative Transfer Equation-Based Method, Split Window Algorithm and Single Channel Method, *Remote Sensing*, 6, 9829-9652. http://www.mdpi.com/2072-4292/6/10/9829
- 10. Rajeshwari, A., and N. D. Mani, 2014. Estimation of land surface temperature of Dindigul district using Landsat 8 data. *International Journal of Research in Engineering and Technology*, 3(5), 122-126. http://www.academia.edu/7655089/ESTIMATION\_OF\_LAND\_SURFACE\_TEMPERATURE\_OF\_DINDIGUL\_DISTRICT\_
- 11. Konda, M. Imasato N., Nishi, K., and T. Toda, 1994. Measurement of the Sea Surface Emissivity. *Journal of Oceanography*, 50, 17:30. http://www.terrapub.co.jp/journals/J0/pdf/5001/50010017.pdf

landsatAdd 167

### See Also

Data from AMSR satellites are handled with amsr-class.

A file containing Landsat data may be read with read.landsat or read.oce, and one such file is provided by the **ocedata** package as a dataset named landsat.

Plots may be made with plot,landsat-method. Since plotting can be quite slow, decimation is available both in the plotting function and as the separate function decimate. Images may be subsetted with landsatTrim.

landsat-class for handling data from the Landsat-8 satellite.

Other things related to landsat data: [[,landsat-method, landsatAdd, landsatTrim, landsat, plot,landsat-method, read.landsat, summary,landsat-method

Other things related to landsat data: [[,landsat-method, landsatAdd, landsatTrim, landsat, plot,landsat-method, read.landsat, summary,landsat-method

landsatAdd

Add a Band to a landsat Object

## **Description**

Add a band to an object of landsat-class. Note that it will be stored in numeric form, not raw form, and therefore it will require much more storage than data read with read.landsat.

#### Usage

```
landsatAdd(x, data, name, debug = getOption("oceDebug"))
```

#### Arguments

X	A landsat object, e.g. as read by read.landsat.
data	A matrix of data, with dimensions matching that of entries already in x.
name	The name to be used for the data, i.e. the data can later be accessed with d[[name]] where d is the name of the return value from the present function.
debug	A flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or a higher value for more debugging.

## Value

An object of landsat-class, with a new data band.

## Author(s)

Dan Kelley

168 landsatTrim

### See Also

The documentation for landsat-class explains the structure of landsat objects, and also outlines the other functions dealing with them.

Other things related to landsat data: [[,landsat-method,landsat-class,landsatTrim,landsat,plot,landsat-method,read.landsat,summary,landsat-method

landsatTrim	Trim a landsat Image to a Geographical Region	

## **Description**

Trim a landsat image to a latitude-longitude box. This is only an approximate operation, because landsat images are provided in x-y coordinates, not longitude-latitude coordinates.

## Usage

```
landsatTrim(x, 11, ur, box, debug = getOption("oceDebug"))
```

## **Arguments**

Х	A landsat object, e.g. as read by read.landsat.
11	A list containing longitude and latitude, for the lower-left corner of the portion of the image to retain, or a vector with first element longitude and second element latitude. If provided, then ur must also be provided, but box cannot.
ur	A list containing longitude and latitude, for the upper-right corner of the portion of the image to retain, or a vector with first element longitude and second element latitude. If provided, then ll must also be provided, but box cannot.
box	A list containing x and y (each of length 2), corresponding to the values for 11 and ur, such as would be produced by a call to locator(2). If provided, neither 11 nor ur may be provided.
debug	A flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or a higher value for more debugging.

## **Details**

As of June 25, 2015, the matrices storing the image data are trimmed to indices determined by linear interpolation based on the location of the 11 and ur corners within the lon-lat corners specified in the image data. (A previous version trimmed in UTM space, and in fact this may be done in future also, if a problem in lonlat/utm conversion is resolved.) An error results if there is no intersection between the trimming box and the image box.

## Value

An object of landsat-class, with data having been trimmed approximately as specified.

latFormat 169

### Author(s)

Dan Kelley and Clark Richards

## See Also

The documentation for landsat-class explains the structure of landsat objects, and also outlines the other functions dealing with them.

Other things related to landsat data: [[,landsat-method,landsat-class,landsatAdd,landsat,plot,landsat-method,read.landsat,summary,landsat-method

latFormat

Format a latitude

# Description

Format a latitude, using "S" for negative latitude.

#### Usage

```
latFormat(lat, digits = max(6, getOption("digits") - 1))
```

# Arguments

latitude in °N north of the equator.

digits the number of significant digits to use when printing.

## Value

A character string.

## Author(s)

Dan Kelley

## See Also

lonFormat and latlonFormat.

170 lisst

latlonFormat

Format a latitude-longitude pair

# Description

Format a latitude-longitude pair, using "S" for negative latitudes, etc.

## Usage

```
latlonFormat(lat, lon, digits = max(6, getOption("digits") - 1))
```

## **Arguments**

lat latitude in °N north of the equator.lon longitude in °N east of Greenwich.

digits the number of significant digits to use when printing.

### Value

A character string.

## Author(s)

Dan Kelley

## See Also

latFormat and lonFormat.

lisst

LISST Dataset

# Description

LISST (Laser in-situ scattering and transmissometry) dataset, constructed artificially.

# Usage

```
data(lisst)
```

## Author(s)

Dan Kelley

lisst-class 171

### Source

This was constructed artificially using as.lisst,

### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

lisst-class

Class to Store LISST Data

## **Description**

Class to store LISST (Laser in-situ scattering and transmissometry) data.

### **Details**

One may read lisst objects with read.lisst, generate them with as.lisst, plot them with plot,lisst-method, and summarize them with summary,lisst-method. Elements may be extracted with [[,lisst-method or replaced with [[<-,lisst-method.

### Author(s)

Dan Kelley

#### References

A users's manual for the LISST-100 instrument is available at the manufacturer's website <a href="http://www.sequoiasci.com">http://www.sequoiasci.com</a>.

# See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to lisst data: [[,lisst-method, [[<-,lisst-method, as.lisst, plot,lisst-method, read.lisst, summary,lisst-method

172 lobo-class

lobo

LOBO Dataset

## **Description**

This is sample lobo dataset obtained in the Northwest Arm of Halifax by Satlantic.

#### Author(s)

Dan Kelley

#### **Source**

The data were downloaded from a web interface at Satlantic LOBO web server and then read with read.lobo.

### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to lobo data: [[,lobo-method, [[<-,lobo-method, as.lobo, lobo-class, plot,lobo-method, subset,lobo-method, summary,lobo-method

## **Examples**

```
## Not run:
library(oce)
data(lobo)
summary(lobo)
plot(lobo)
## End(Not run)
```

lobo-class

Class to Store LOBO Data

# Description

Class to store LOBO data. A lobo object may be read with read.lobo or constructed with as.lobo. Plots can be made with plot,lobo-method, while summary,lobo-method produces statistical summaries. Data within a lobo object may be retrieved with [[,lobo-method and altered with [[,lobo-method.

IonFormat 173

### Author(s)

Dan Kelley

## See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to lobo data: [[,lobo-method, [[<-,lobo-method, as.lobo, lobo, plot,lobo-method, subset,lobo-method, summary,lobo-method

lonFormat

Format a longitude

# Description

Format a longitude, using "W" for west longitude.

## Usage

```
lonFormat(lon, digits = max(6, getOption("digits") - 1))
```

## **Arguments**

lon longitude in °N east of Greenwich.

digits the number of significant digits to use when printing.

### Value

A character string.

### Author(s)

Dan Kelley

#### See Also

latFormat and latlonFormat.

174 lonlat2map

lonlat2map	Convert Longitude and Latitude to X and Y	

## **Description**

If a projection is already being used (e.g. as set by mapPlot) then only longitude and latitude should be given, and the other arguments will be inferred by lonlat2map. This is important because otherwise, if a new projection is called for, it will ruin any additions to the existing plot.

## Usage

```
lonlat2map(longitude, latitude, projection = "",
  debug = getOption("oceDebug"))
```

#### **Arguments**

longitude a vector containing decimal longitudes, or a list containing items named longitude

and latitude, in which case the indicated values are used, and next argument

is ignored.

latitude a vector containing decimal latitude (ignored if longitude is a list, as described

above).

projection optional indication of projection. This must be character string in the format

used by the rgdal package; see mapPlot.)

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### Value

A list containing x and y.

### Author(s)

Dan Kelley

## See Also

mapLongitudeLatitudeXY is a safer alternative, if a map has already been drawn with mapPlot, because that function cannot alter an existing projection. map2lonlat is an inverse to map2lonlat.

Other functions related to maps: lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

Ionlat2utm 175

## **Examples**

```
## Not run:
library(oce)
## Cape Split, in the Minas Basin of the Bay of Fundy
cs <- list(longitude=-64.49657, latitude=45.33462)
xy <- lonlat2map(cs, projection="+proj=merc")
map2lonlat(xy)
## End(Not run)</pre>
```

lonlat2utm

Convert Longitude and Latitude to UTM

## **Description**

Convert Longitude and Latitude to UTM

#### **Usage**

```
lonlat2utm(longitude, latitude, zone, km = FALSE)
```

## **Arguments**

longitude decimal longitude. May also be a list containing items named longitude and

latitude, in which case the indicated values are used, and next argument is

ignored.

latitude decimal latitude (ignored if longitude is a list containing both coordinates)

zone optional indication of UTM zone. Normally this is inferred from the longitude,

but specifying it can be helpful in dealing with Landsat images, which may cross

zones and which therefore are described by a single zone.

km logical value indicating whether easting and northing are in kilometers or

meters.

#### Value

A list containing easting, northing, zone and hemisphere.

### Author(s)

Dan Kelley

#### References

http://en.wikipedia.org/wiki/Universal\_Transverse\_Mercator\_coordinate\_system, downloaded May 31, 2014.

176 lookWithin

### See Also

utm2lonlat does the inverse operation. For general projections and their inverses, use lonlat2map and map2lonlat.

Other functions related to maps: lonlat2map, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

## **Examples**

```
library(oce)
## Cape Split, in the Minas Basin of the Bay of Fundy
lonlat2utm(-64.496567, 45.334626)
```

lookWithin

Look Within the First Element of a List for Replacement Values

#### **Description**

Look Within the First Element of a List for Replacement Values

#### Usage

```
lookWithin(list)
```

#### **Arguments**

list

A list of elements, typically arguments that will be used in sw functions.

#### **Details**

This is a helper function used by various seawater functions. It is used for a call like swRho(ctd), in which the first argument, which is normally salinity may be an object that contains salinity plus the other items that swRho expects to see as arguments. This shorthand is very helpful in calls to the suite of sw functions. If this first argument is an object of this sort, then the other arguments are ignored *except* for two special cases:

- an item named eos is copied directly from list
- if the object stores temperature defined with the IPTS-68 scale, then T90fromT68 is used to convert to the ITS-90 scale, because this is what is expected in most seawater functions. (For example, the RMS difference between these temperature variants is 0.002C for the ctd dataset.)

### Value

A list with elements of the same names but possibly filled in from the first element.

lowpass 177

lowpass Perform lowpass digital filtering	lowpass	Perform lowpass digital filtering	
---	---------	-----------------------------------	--

# Description

The filter coefficients are constructed using standard definitions, and then filter in the **stats** package is used to filter the data. This leaves NA values within half the filter length of the ends of the time series, but these may be replaced with the original x values, if the argument replace is set to TRUE.

## Usage

```
lowpass(x, filter = "hamming", n, replace = TRUE, coefficients = FALSE)
```

## **Arguments**

x	a vector to be smoothed
filter	name of filter; at present, "hamming", "hanning", and "boxcar" are permitted.
n	length of filter (must be an odd integer exceeding 1)
replace	a logical value indicating whether points near the ends of x should be copied into the end regions, replacing the NA values that would otherwise be placed there by filter.
coefficients	logical value indicating whether to return the filter coefficients, instead of the filtered values. In accordance with conventions in the literature, the returned values are not normalized to sum to 1, although of course that normalization is done in the actual filtering.

## Value

By default, lowpass returns a filtered version of x, but if coefficients is TRUE then it returns the filter coefficients.

## **Caution**

This function was added in June of 2017, and it may be extended during the rest of 2017. New arguments may appear between n and replace, so users are advised to call this function with named arguments, not positional arguments.

## Author(s)

Dan Kelley

178 magneticField

## **Examples**

```
library(oce)
par(mfrow=c(1, 2), mar=c(4, 4, 1, 1))
coef <- lowpass(n=5, coefficients=TRUE)
plot(-2:2, coef, ylim=c(0, 1), xlab="Lag", ylab="Coefficient")
x <- seq(-5, 5) + rnorm(11)
plot(1:11, x, type='o', xlab="time", ylab="x and X")
X <- lowpass(x, n=5)
lines(1:11, X, col=2)
points(1:11, X, col=2)</pre>
```

magneticField

Earth magnetic declination, inclination, and intensity

## Description

Implements the 12th generation International Geomagnetic Reference Field (IGRF), based on a reworked version of a Fortran program downloaded from a NOAA website [1]. The code (subroutine igrf12syn) seems to have been written by Susan Macmillan of the British Geological Survey. Comments in the code indicate that it employs coefficients agreed to in December 2014 by the IAGA Working Group V-MOD. Comments in the igrf12syn source code also suggest that the valid time interval is from years 1900 to 2020, with only the values from 1945 to 2010 being considered definitive.

## Usage

```
magneticField(longitude, latitude, time)
```

## **Arguments**

longitude longitude in degrees east (negative for degrees west). The dimensions must

conform to lat.

latitude latitude in degrees north, a number, vector, or matrix.

time either a decimal year or a POSIX time corresponding to the longitude and

latitude values, or a vector or matrix matching these location values.

#### Value

A list containing declination, inclination, and intensity.

# Author(s)

Dan Kelley wrote the R code and a fortran wrapper to the igrf12.f subroutine, which was written by Susan Macmillan of the British Geological Survey and distributed "without limitation" (email from SM to DK dated June 5, 2015).

makeFilter 179

#### References

1. The underlying Fortran code is from igrf12.f, downloaded the NOAA website ('https://www.ngdc.noaa.gov/IAGA/vi on June 7, 2015. (That website suggests that there have been no update to the algorithm as of March 29, 2017.)

#### See Also

Other things related to magnetism: applyMagneticDeclination

### **Examples**

```
library(oce)
# Halifax NS
magneticField(-(63+36/60), 44+39/60, 2013)
## Not run:
## map of North American values
data(coastlineWorld)
mapPlot(coastlineWorld, longitudelim=c(-130,-55), latitudelim=c(35,60),
        projection="+proj=lcc +lat_0=20 +lat_1=60 +lon_0=-100")
lon <- seq(-180, 180, 1)
lat <- seq(-90, 90)
lonm <- rep(lon, each=length(lat))</pre>
latm <- rep(lat, times=length(lon))</pre>
## Note the counter-intuitive nrow argument
decl <- matrix(magneticField(lonm, latm, 2013)$declination,</pre>
               nrow=length(lon), byrow=TRUE)
mapContour(lon, lat, decl, col='red', levels=seq(-90, 90, 5))
incl <- matrix(magneticField(lonm, latm, 2013)$inclination,</pre>
               nrow=length(lon), byrow=TRUE)
mapContour(lon, lat, incl, col='blue', levels=seq(-90, 90, 5))
## End(Not run)
```

makeFilter

Make a digital filter

## Description

The filter is suitable for use by filter, convolve or (for the asKernal=TRUE case) with kernapply. Note that convolve should be faster than filter, but it cannot be used if the time series has missing values. For the Blackman-Harris filter, the half-power frequency is at 1/m cycles per time unit, as shown in the "Examples" section. When using filter or kernapply with these filters, use circular=TRUE.

# Usage

```
makeFilter(type = c("blackman-harris", "rectangular", "hamming", "hann"), m,
  asKernel = TRUE)
```

180 makeFilter

#### **Arguments**

type

a string indicating the type of filter to use. (See Harris (1978) for a comparison of these and similar filters.)

- "blackman-harris" yields a modified raised-cosine filter designated as "4-Term (-92 dB) Blackman-Harris" by Harris (1978; coefficients given in the table on page 65). This is also called "minimum 4-sample Blackman Harris" by that author, in his Table 1, which lists figures of merit as follows: highest side lobe level -92dB; side lobe fall off -6 db/octave; coherent gain 0.36; equivalent noise bandwidth 2.00 bins; 3.0-dB bandwidth 1.90 bins; scallop loss 0.83 dB; worst case process loss 3.85 dB; 6.0-db bandwidth 2.72 bins; overlap correlation 46 percent for 75% overlap and 3.8 for 50% overlap. Note that the equivalent noise bandwidth is the width of a spectral peak, so that a value of 2 indicates a cutoff frequency of 1/m, where m is as given below.
- "rectangular" for a flat filter. (This is just for convenience. Note that kernel("daniell",....) gives the same result, in kernel form.) "hamming" for a Hamming filter (a raised-cosine that does not taper to zero at the ends)
- "hann" (a raised cosine that tapers to zero at the ends).

m

length of filter. This should be an odd number, for any non-rectangular filter.

asKernel

boolean, set to TRUE to get a smoothing kernel for the return value.

#### Value

If asKernel is FALSE, this returns a list of filter coefficients, symmetric about the midpoint and summing to 1. These may be used with filter, which should be provided with argument circular=TRUE to avoid phase offsets. If asKernel is TRUE, the return value is a smoothing kernel, which can be applied to a timeseries with kernapply, whose bandwidth can be determined with bandwidth.kernel, and which has both print and plot methods.

#### Author(s)

Dan Kelley

#### References

F. J. Harris, 1978. On the use of windows for harmonic analysis with the discrete Fourier Transform. *Proceedings of the IEEE*, 66(1), 51-83 (http://web.mit.edu/xiphmont/Public/windows.pdf.)

## **Examples**

```
library(oce)

# 1. Demonstrate step-function response
y <- c(rep(1, 10), rep(-1, 10))
x <- seq_along(y)
plot(x, y, type='o', ylim=c(-1.05, 1.05))
BH <- makeFilter("blackman-harris", 11, asKernel=FALSE)</pre>
```

makeSection 181

```
H <- makeFilter("hamming", 11, asKernel=FALSE)</pre>
yBH <- stats::filter(y, BH)</pre>
points(x, yBH, col=2, type='o')
yH <- stats::filter(y, H)</pre>
points(yH, col=3, type='o')
legend("topright", col=1:3, cex=2/3, pch=1,
       legend=c("input", "Blackman Harris", "Hamming"))
# 2. Show theoretical and practical filter gain, where
     the latter is based on random white noise, and
     includes a particular value for the spans
     argument of spectrum(), etc.
## Not run: # need signal package for this example
r <- rnorm(2048)
rh <- stats::filter(r, H)</pre>
rh <- rh[is.finite(rh)] # kludge to remove NA at start/end</pre>
sR <- spectrum(r, plot=FALSE, spans=c(11, 5, 3))</pre>
sRH <- spectrum(rh, plot=FALSE, spans=c(11, 5, 3))
par(mfrow=c(2, 1), mar=c(3, 3, 1, 1), mgp=c(2, 0.7, 0))
plot(sR$freq, sRH$spec/sR$spec, xlab="Frequency", ylab="Power Transfer",
     type='l', lwd=5, col='gray')
theory <- freqz(H, n=seq(0,pi,length.out=100))</pre>
# Note we must square the modulus for the power spectrum
lines(theory$f/pi/2, Mod(theory$h)^2, lwd=1, col='red')
grid()
legend("topright", col=c("gray", "red"), lwd=c(5, 1), cex=2/3,
       legend=c("Practical", "Theory"), bg="white")
plot(log10(sR$freq), log10(sRH$spec/sR$spec),
     xlab="log10 Frequency", ylab="log10 Power Transfer",
     type='l', lwd=5, col='gray')
theory <- freqz(H, n=seq(0,pi,length.out=100))</pre>
# Note we must square the modulus for the power spectrum
lines(log10(theory$f/pi/2), log10(Mod(theory$h)^2), lwd=1, col='red')
grid()
legend("topright", col=c("gray", "red"), lwd=c(5, 1), cex=2/3,
       legend=c("Practical", "Theory"), bg="white")
## End(Not run)
```

makeSection

Make a Section (DEFUNCT)

# **Description**

This is a defunct function; use as. section instead, and see oce-defunct for more on the oce procedure for retiring functions.

```
makeSection(item, ...)
```

map2lonlat

# **Arguments**

item	Ignored, since this function is defunct
	Ignored, since this function is defunct

map2lonlat	Convert X and Y to Longitude and Latitude
------------	---

# Description

Convert from x-y coordinates to longitude and latitude. This is normally called internally within oce; see 'Bugs'.

# Usage

```
map2lonlat(x, y, init = c(0, 0))
```

# Arguments

Х	vector containing the x component of points in the projected space, or a list containing items named x and y, in which case the next argument is ignored.
У	vector containing the y coordinate of points in the projected space (ignored if x is a list, as described above).
init	vector containing the initial guesses for longitude and latitude, presently ignored.

# **Details**

A projection must already have been set up, by a call to mapPlot or lonlat2map. It should be noted that not all projections are handled well; see 'Bugs'.

### Value

A list containing longitude and latitude, with NA values indicating points that are off the globe as displayed.

# **Bugs**

oce uses project in the **rgdal** package to handle projections. Only those projections that have inverses are permitted within oce, and even those can sometimes yield errors, owing to limitations in **rgdal**.

# Author(s)

Dan Kelley

mapArrows 183

### See Also

lonlat2map does the inverse operation.

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

# **Examples**

```
## Not run:
library(oce)
## Cape Split, in the Minas Basin of the Bay of Fundy
cs <- list(longitude=-64.49657, latitude=45.33462)
xy <- lonlat2map(cs, projection="+proj=merc")
map2lonlat(xy)
## End(Not run)</pre>
```

mapArrows

Add Arrows to a Map

## **Description**

Plot arrows on an existing map, e.g. to indicate a place location. This is not well-suited for drawing direction fields, e.g. of velocities; for that, see mapDirectionField.

### Usage

```
mapArrows(longitude0, latitude0, longitude1 = longitude0,
  latitude1 = latitude0, length = 0.25, angle = 30, code = 2,
  col = par("fg"), lty = par("lty"), lwd = par("lwd"), ...)
```

#### **Arguments**

```
longitude0, latitude0
                  starting points for arrows.
longitude1, latitude1
                  ending points for arrows.
length
                  length of the arrow heads, passed to arrows.
angle
                  angle of the arrow heads, passed to arrows.
code
                  numerical code indicating the type of arrows, passed to arrows.
col
                  arrow colour, passed to arrows.
lty
                  arrow line type, passed to arrows.
lwd
                  arrow line width, passed to arrows.
                  optional arguments passed to arrows.
```

184 mapAxis

### **Details**

Adds arrows to an existing map, by analogy to arrows.

# Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

## **Examples**

mapAxis

Add Axis Labels to an Existing Map

# **Description**

Plot axis labels on an existing map.

```
mapAxis(side = 1:2, longitude = NULL, latitude = NULL, tick = TRUE,
  line = NA, pos = NA, outer = FALSE, font = NA, lty = "solid",
  lwd = 1, lwd.ticks = lwd, col = NULL, col.ticks = NULL, hadj = NA,
  padj = NA, tcl = -0.3, cex.axis = 1, mgp = c(0, 0.5, 0),
  debug = getOption("oceDebug"))
```

mapAxis 185

# **Arguments**

side the side at which labels are to be drawn. If not provided, sides 1 and 2 will be

used (i.e. bottom and left-hand sides).

longitude vector of longitudes to indicate. If not provided, and if a grid has already been

drawn, then the labels will be at the intersections of the grid lines with the plot-

ting box.

latitude vector of latitudes to indicate. If not provided, and if a grid has already been

drawn, then the labels will be at the interesections of the grid lines with the

plotting box.

tick parameter passed to axis. line parameter passed to axis. parameter passed to axis. pos outer parameter passed to axis. axis font, passed to axis. font axis line type, passed to axis. lty lwd axis line width, passed to axis). lwd.ticks tick line width, passed to axis. col axis colour, passed to axis.

hadj an argument that is transmitted to axis.
padj an argument that is transmitted to axis.

tcl axis-tick size (see par).

cex.axis axis-label expansion factor (see par).

mgp three-element numerical vector describing axis-label placement (see par). It

usually makes sense to set the first and third elements to zero.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

axis tick colour, passed to axis.

### **Details**

This function is still in development, and the argument list as well as the action taken are both subject to change, hence the brevity of this help page.

Note that if a grid line crosses the axis twice, only one label will be drawn.

# Author(s)

Dan Kelley

col.ticks

# See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

186 mapContour

# **Examples**

mapContour

Add Contours on a Existing map

# **Description**

Plot contours on an existing map.

## Usage

```
mapContour(longitude = seq(0, 1, length.out = nrow(z)), latitude = seq(0, 1,
  length.out = ncol(z)), z, nlevels = 10, levels = pretty(range(z, na.rm =
  TRUE), nlevels), col = par("fg"), lty = par("lty"), lwd = par("lwd"))
```

# **Arguments**

longitude	vector of longitudes of points to be plotted, or an object of class topo (see topo-class), in which case longitude, latitude and z are inferred from that object.
latitude	vector of latitudes of points to be plotted.
z	matrix to be contoured.
nlevels	number of contour levels, if and only if levels is not supplied.
levels	vector of contour levels.
col	line colour.
lty	line type.
lwd	line width.

### **Details**

Adds contour lines to an existing map, using mapLines. The arguments are based on those to contour and contourLines.

## **Bugs**

As with mapLines, long lines should be subdivided into multiple segments so that e.g. great circle lines will be curved.

### Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

# **Examples**

mapCoordinateSystem

Draw a coordinate system

# Description

Draws arrows on a map to indicate a coordinate system, e.g. for an to indicate a coordinate system set up so that one axis is parallel to a coastline.

```
mapCoordinateSystem(longitude, latitude, L = 100, phi = 0, ...)
```

188 mapDirectionField

# Arguments

longitude numeric value of longitude in degrees.

latitude numeric value of latitude in degrees.

L axis length in km.

phi angle, in degrees counterclockwise, that the "x" axis makes to a line of latitude.
... plotting arguments, passed to mapArrows; see "Examples" for how to control

the arrow-head size.

### **Details**

This is a preliminary version of this function. It only works if the lines of constant latitude are horizontal on the plot.

# Author(s)

Chantelle Layton

### **Examples**

mapDirectionField

Add a Direction Field to an Existing Map

# **Description**

Plot a direction field on a existing map.

```
mapDirectionField(longitude, latitude, u, v, scale = 1, length = 0.05,
  code = 2, col = par("fg"), ...)
```

mapDirectionField 189

# Arguments

```
longitude, latitude
                   vectors of the starting points for arrows.
                   components of a vector to be shown as a direction field.
u, v
                   latitude degrees per unit of u or v.
scale
length
                   length of arrow heads, passed to arrows.
code
                   code of arrows, passed to arrows.
col
                   colour of arrows. This may be a single colour, or a matrix of colours of the same
                   dimension as u.
                   optional arguments passed to arrows, e.g. angle and lwd can be useful in dif-
. . .
                   ferentiating different fields.
```

### **Details**

Adds arrows for a direction field on an existing map. There are different possibilities for how longitude, latitude and u and v match up. In one common case, all four of these are matrices, e.g. output from a numerical model. In another, longitude and latitude are the coordinates along the matrices, and are thus stored in vectors with lengths that match appropriately.

# Author(s)

Dan Kelley

## See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

190 mapGrid

```
# Color code by longitude, using thick lines
col <- colormap(lonm)$zcol
mapDirectionField(lonm, latm, 1, 0, scale=3, col=col, lwd=2)
## End(Not run)</pre>
```

mapGrid

Add a Longitude and Latitude Grid to a Map

### **Description**

Plot longitude and latitude grid on an existing map.

### Usage

```
mapGrid(dlongitude = 15, dlatitude = 15, longitude, latitude,
  col = "darkgray", lty = "solid", lwd = 0.5 * par("lwd"),
  polarCircle = 0, longitudelim, latitudelim, debug = getOption("oceDebug"))
```

## **Arguments**

dlongitude increment in longitude, ignored if longitude is supplied, but otherwise deter-

mines the longitude sequence.

dlatitude increment in latitude, ignored if latitude is supplied, but otherwise determines

the latitude sequence.

longitude vector of longitudes, or NULL to prevent drawing longitude lines.

latitude vector of latitudes, or NULL to prevent drawing latitude lines.

col colour of lines
lty line type
lwd line width

polarCircle a number indicating the number of degrees of latitude extending from the poles,

within which zones are not drawn.

longitudelim optional argument specifying suggested longitude limits for the grid. If this is

not supplied, grid lines are drawn for the whole globe, which can yield excessively slow drawing speeds for small-region plots. This, and latitudelim, are both set by mapPlot if the arguments of the same name are passed to that func-

tion.

latitudelim similar to longitudelim.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

#### **Details**

This is somewhat analogous to grid, except that the first two arguments of the latter supply the number of lines in the grid, whereas the present function has increments for the first two arguments.

mapImage 191

# **Plans**

At the moment, the function cannot determine which lines might work with labels on axes, but this could perhaps be added later, making this more analogous with grid.

# Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

# **Examples**

```
## Not run:
library(oce)
data(coastlineWorld)
mapPlot(coastlineWorld, type='l', grid=FALSE,
longitudelim=c(-80, 10), latitudelim=c(0, 120),
projection="+proj=ortho")
mapGrid(15, 15, polarCircle=15)
## End(Not run)
```

mapImage

Add an Image to a Map

### **Description**

Plot an image on an existing map that was created with mapPlot. (See example 4 for a way to start with a blank map.)

```
mapImage(longitude, latitude, z, zlim, zclip = FALSE, breaks, col, colormap,
border = NA, lwd = par("lwd"), lty = par("lty"), missingColor = NA,
filledContour = FALSE, gridder = "binMean2D",
debug = getOption("oceDebug"))
```

192 mapImage

#### **Arguments**

latitude vector of longitudes corresponding to z matrix.

latitude vector of latitudes corresponding to z matrix.

z matrix to be represented as an image.

zlim limit for z (colour).

zclip A logical value, TRUE indicating that out-of-range z values should be painted

with missingColor and FALSE indicating that these values should be painted with the nearest in-range colour. If zlim is given then its min and max set the range. If zlim is not given but breaks is given, then the min and max of breaks sets the range used for z. If neither zlim nor breaks is given, clipping is not

done, i.e. the action is as if zclip were FALSE.

breaks The z values for breaks in the colour scheme. If this is of length 1, the value indi-

cates the desired number of breaks, which is supplied to pretty, in determining

clean break points.

col Either a vector of colours corresponding to the breaks, of length 1 plus the num-

ber of breaks, or a function specifying colours, e.g. oce.colorsJet for a rain-

bow.

colormap optional colormap, as created by colormap. If a colormap is provided, then

its properties takes precedence over breaks, col, missingColor, and zclip

specified to mapImage.

border Colour used for borders of patches (passed to polygon); the default NA means

no border.

lwd line width, used if borders are drawn.lty line type, used if borders are drawn.

missingColor a colour to be used to indicate missing data, or NA to skip the drawing of such

regions (which will retain whatever material has already been drawn at the re-

gions).

filledContour either a logical value indicating whether to use filled contours to plot the image,

or a numerical value indicating the resampling rate to be used in interpolating from lon-lat coordinates to x-y coordinates. See "Details" for how this interacts

with gridder.

gridder Name of gridding function used if filledContour is TRUE. This can be either

"binMean2D" to select binMean2D or "interp" for interp. If not provided, then a selection is made automatically, with binMean2D being used if there are more than 10,000 data points in the present graphical view. This "binMean2D"

method is much faster than "interp".

debug A flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

# Details

Adds an image to an existing map, by analogy to image.

The data are on a regular grid in lon-lat space, but not in the projected x-y space. This means that image cannot be used. Instead, there are two approaches, depending on the value of filledContour.

mapImage 193

If filledContour is FALSE, the image "pixels" are with polygon, which can be prohibitively slow for fine grids. However, if filledContour is TRUE or a numerical value, then the "pixels" are remapped into a regular grid and then displayed with .filled.contour. The remapping starts by converting the regular lon-lat grid to an irregular x-y grid using lonlat2map. This irregular grid is then interpolated onto a regular x-y grid with binMean2D or with interp from the akima package, as determined by the gridder argument. If filledContour is TRUE, the dimensions of the regular x-y grid is the same as that of the original lon-lat grid; otherwise, the number of rows and columns are multiplied by the numerical value of filledContour, e.g. the value 2 means to make the grid twice as fine.

Filling contours can produce aesthetically-pleasing results, but the method involves interpolation, so the data are not represented exactly and analysts are advised to compare the results from the two methods (and perhaps various grid refinement values) to guard against misinterpretation.

If a png device is to be used, it is advised to supply arguments type="cairo" and antialias="none"; see [1].

### Author(s)

Dan Kelley

#### References

1. http://codedocean.wordpress.com/2014/02/03/anti-aliasing-and-image-plots/

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

```
## Not run:
library(oce)
data(coastlineWorld)
data(topoWorld)
## 1. topography
par(mfrow=c(2, 1), mar=c(2, 2, 1, 1))
lonlim <- c(-70, -50)
latlim <- c(40, 50)
topo <- decimate(topoWorld, by=2) # coarse to illustrate filled contours
topo <- subset(topo, latlim[1] < latitude & latitude < latlim[2])</pre>
topo <- subset(topo, lonlim[1] < longitude & longitude < lonlim[2])</pre>
mapPlot(coastlineWorld, type='l',
        longitudelim=lonlim, latitudelim=latlim,
        projection="+proj=lcc +lat_1=40 +lat_2=50 +lon_0=-60")
breaks <- seq(-5000, 1000, 500)
mapImage(topo, col=oce.colorsGebco, breaks=breaks)
```

194 mapLines

```
mapLines(coastlineWorld)
box()
mapPlot(coastlineWorld, type='l',
        longitudelim=lonlim, latitudelim=latlim,
        projection="+proj=lcc +lat_1=40 +lat_2=50 +lon_0=-60")
mapImage(topo, filledContour=TRUE, col=oce.colorsGebco, breaks=breaks)
mapLines(coastlineWorld)
## 2. Northern polar region, with colour-coded bathymetry
par(mfrow=c(1,1))
drawPalette(c(-5000, 0), zlim=c(-5000, 0), col=oce.colorsJet)
mapPlot(coastlineWorld, projection="+proj=stere +lat_0=90",
        longitudelim=c(-180,180), latitudelim=c(60,120))
mapImage(topoWorld, zlim=c(-5000, 0), col=oce.colorsJet)
mapLines(coastlineWorld[['longitude']], coastlineWorld[['latitude']])
## 3. Levitus SST
par(mfrow=c(1,1))
data(levitus, package='ocedata')
lon <- levitus$longitude</pre>
lat <- levitus$latitude</pre>
SST <- levitus$SST
par(mar=rep(1, 4))
Tlim <- c(-2, 30)
drawPalette(Tlim, col=oce.colorsJet)
mapPlot(coastlineWorld, projection="+proj=moll", grid=FALSE)
mapImage(lon, lat, SST, col=oce.colorsJet, zlim=Tlim)
mapPolygon(coastlineWorld, col='gray')
## 4. Topography without drawing a coastline first
data(topoWorld)
cm <- colormap(topoWorld[['z']], name='gmt_relief')</pre>
drawPalette(colormap=cm)
mapPlot(c(-180,180), c(-90,90), type="n") # defaults to moll projection
mapImage(topoWorld, colormap=cm)
## End(Not run)
```

mapLines

Add Lines to a Map

# **Description**

Plot lines on an existing map

```
mapLines(longitude, latitude, greatCircle = FALSE, ...)
```

mapLines 195

# **Arguments**

longitude vector of longitudes of points to be plotted, or an object from which longitude and latitude can be inferred (e.g. a coastline file, or the return value from mapLocator), in which case the following two arguments are ignored.

latitude vector of latitudes of points to be plotted.

greatCircle a logical value indicating whether to render line segments as great circles. (Ignored.)

... optional arguments passed to lines.

#### **Details**

Adds lines to an existing map, by analogy to lines.

#### Author(s)

Dan Kelley

### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

mapLocator

Locate Points on a Map

#### **Description**

Locate points on an existing map.

## Usage

```
mapLocator(n = 512, type = "n", ...)
```

# **Arguments**

n number of points to locate; see locator.

type type of connector for the points; see locator.

extra arguments passed to locator (and either mapPoints or mapLines, if ap-

propriate) if type is not 'n'.

#### **Details**

This uses map2lonlat to infer the location in geographical space; see the documentation for that function on its limitations.

### Author(s)

Dan Kelley

### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

mapLongitudeLatitudeXY

Convert From Longitude and Latitude to X and Y

## **Description**

Find (x, y) values corresponding to (longitude, latitude) values, using the present projection.

```
mapLongitudeLatitudeXY(longitude, latitude)
```

mapMeridians 197

# **Arguments**

longitude vector of the longitudes of points, or an object from which both latitude and lon-

gitude can be inferred (e.g. a coastline file, or the return value from mapLocator),

in which case the following two arguments are ignored.

latitude vector of latitudes of points, needed only if they cannot be inferred from the first

argument.

### **Details**

This is mainly a wrapper around lonlat2map.

#### Value

A list containing x and y.

### Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

## **Examples**

```
## Not run:
library(oce)
data(coastlineWorld)
par(mfrow=c(2, 1), mar=rep(2, 4))
mapPlot(coastlineWorld, projection="+proj=moll") # sets a projection
xy <- mapLongitudeLatitudeXY(coastlineWorld)
plot(xy, type='l', asp=1)
## End(Not run)</pre>
```

mapMeridians

Add Meridians on a Map [deprecated]

# **Description**

**WARNING:** This function will be removed soon; see oce-deprecated. Use mapGrid instead of the present function.

### Usage

```
mapMeridians(latitude, lty = "solid", lwd = 0.5 * par("lwd"),
  col = "darkgray", ...)
```

### Arguments

latitude	either a logical value indicating whether to draw a meridian grid, or a vector of latitudes at which to draw meridians.
lty	line type.
lwd	line width.
col	line colour.
	optional arguments passed to lines.

#### **Details**

Plot meridians (lines of constant latitude) on an existing map.

This function should not be used, since it will be removed soon. Please use mapGrid() instead.

### Author(s)

Dan Kelley

#### See Also

Other functions that will be removed soon: addColumn, ctdAddColumn, ctdUpdateHeader, mapZones, oce.as.POSIXlt

Draw a Map
------------

# Description

Plot coordinates as a map, using one of the subset of projections provided by the **rgdal** package. The projection information specified with the mapPlot call is stored so that can be retrieved by related functions, making it easy to add more items so the map, including points, lines, text, images and contours.

```
mapPlot(longitude, latitude, longitudelim, latitudelim, grid = TRUE, bg, fill,
border = NULL, col = NULL, clip = TRUE, type = "polygon",
axes = TRUE, cex, cex.axis = 1, mgp = c(0, 0.5, 0), drawBox = TRUE,
showHemi = TRUE, polarCircle = 0, lonlabel = NULL, latlabel = NULL,
sides = NULL, projection = "+proj=moll", tissot = FALSE, trim = TRUE,
debug = getOption("oceDebug"), ...)
```

#### **Arguments**

longitude either a vector of longitudes of points to be plotted, or something (an oce object,

a list, or a data frame) from which both longitude and latitude may be inferred (in which case the latitude argument is ignored). If longitude is missing,

both it and latitude are taken from coastlineWorld.

latitude vector of latitudes of points to be plotted (ignored if the first argument contains

both latitude and longitude).

longitudelim optional vector of length two, indicating the longitude limits of the plot. This

value is used in the selection of longitude lines that are shown (and possibly labelled on the axes). In some cases, e.g. for polar views, this can lead to odd results, with some expected longitude lines being left out of the plot. Altering longitudelim can often help in such cases, e.g. longitudelim=c(-180, 180)

will force the drawing of lines all around the globe.

latitudelim optional vector of length two, indicating the latitude limits of the plot. This,

together with longitudelim (and, importantly, the geometry of the plot device)

is used in the selection of map scale.

grid either a number (or pair of numbers) indicating the spacing of longitude and

latitude lines, in degrees, or a logical value (or pair of values) indicating whether to draw an auto-scaled grid, or whether to skip the grid drawing. In the case of numerical values, NA can be used to turn off the grid in longitude or latitude. Grids are set up based on examination of the scale used in middle 10 percent of the plot area, and for most projections this works quite well. If not, one may set

grid=FALSE and add a grid later with mapGrid.

bg colour of the background (ignored).

fill (deprecated) is a deprecated argument; see oce-deprecated.

border colour of coastlines and international borders (ignored unless type="polygon".

col either the colour for filling polygons (if type="polygon") or the colour of the

points and line segments (if type="p", type="1", or type="o"). If col=NULL then a default will be set: no coastline filling for the type="polygon" case, or

black coastlines, for type="p", type="l", or type="o".

clip logical value indicating whether to trim any coastline elements that lie wholly

outside the plot region. This can prevent e.g. a problem of filling the whole plot area of an Arctic stereopolar view, because the projected trace for Antarctica lies outside all other regions so the whole of the world ends up being "land". Setting clip=FALSE disables this action, which may be of benefit in rare instances in the line connecting two points on a coastline may cross the plot domain, even if

those points are outside that domain.

type indication of type; may be "polygon", for a filled polygon, "p" for points, "1"

for line segments, or "o" for points overlain with line segments.

axes logical value indicating whether to draw longitude and latitude values in the

lower and left margin, respectively. This may not work well for some projections

or scales.

cex character expansion factor for plot symbols, used if type='p' or any other value

that yields symbols.

cex.axis axis-label expansion factor (see par).

mgp three-element numerical vector describing axis-label placement, passed to mapAxis.

drawBox logical value indicating whether to draw a box around the plot. This is helpful

for many projections at sub-global scale.

showHemi logical value indicating whether to show the hemisphere in axis tick labels.

polarCircle a number indicating the number of degrees of latitude extending from the poles,

within which zones are not drawn.

lonlabel, latlabel, sides

Optional vectors of longitude and latitude to label on the indicated sides of plot, passed to plot, coastline-method. Using these arguments permits reasonably simple customization. If they are are not provided, reasonable defaults will be

used.

projection optional indication of projection, in one of two forms. First, it may be a charac-

ter string in the "CRS" format that is used by the rgdal package (and in much of modern computer-based cartography). For example, projection="+proj=merc" specifies a Mercator projection. The second format is the output from CRS in the sp package, which is an object with a slot named projarg that gets used as a

projection string. See "Details".

tissot logical value indicating whether to use mapTissot to plot Tissot indicatrices,

i.e. ellipses at grid intersection points, which indicate map distortion.

trim logical value indicating whether to trim islands or lakes containing only points

that are off-scale of the current plot box. This solves the problem of Antarctica overfilling the entire domain, for an Arctic-centred stereographic projection. It is not a perfect solution, though, because the line segment joining two off-scale

points might intersect the plotting box.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... optional arguments passed to some plotting functions. This can be useful in

many ways, e.g. Example 5 shows how to use xlim etc to reproduce a scale

exactly between two plots.

#### **Details**

Creates a map using the indicated projection. As noted in the information on the projection argument, projections are specified in the notation used by project() in the rgdal package; see "Available Projections" for a list of possibilities.

Once a projection is set, other map\* functions may be used to add to the map.

Further details on map projections are provided by [1,11], an exhaustive treatment that includes many illustrations, an overview of the history of the topic, and some notes on the strengths and weaknesses of the various formulations. See especially pages 2 through 7, which define terms and provide recommendations. Reference [2] is also useful, especially regarding datum shifts; [3] and [4] are less detailed and perhaps better for novices. See [8] for a gallery of projections.

### **Available Projections**

Map projections are provided by the rgdal package, but not all projections in that package are available. The available list is given in the table below. The cartographic community has set up a naming scheme in a coded scheme, e.g. projection="+proj=aea" selects the Albers equal area projection.

The allowed projections include those PROJ.4 projections provided by rgdal that have inverses, minus a few that cause problems: alsk overdraws coastlineWorld, and is a niche projection for Alaska; calcofi is not a real projection, but rather a coordinate system; gs48 overdraws coastlineWorld, and is a niche projection for the USA; gs50 overdraws coastlineWorld, and is a niche projection for the USA; gstmerc overdraws coastlineWorld; isea causes segmentation faults on OSX systems; krovak overdraws coastlineWorld, and is a niche projection for the Czech Republic; labrd returns NaN for most of the world, and is a niche projection for Madagascar; lee\_os overdraws coastlineWorld; and nzmg overdraws coastlineWorld.

The information in the table is reformatted from the output of the unix command proj -1P, where proj is provided by version 4.9.0 of the PROJ.4 system. Most of the arguments listed have default values. In addition, most projections can handle arguments lon\_0 and lat\_0, for shifting the reference point, although in some cases shifting the longitude can yield poor filling of coastlines.

Further details of the projections and the controlling arguments are provided at several websites, because PROJ.4 has been incorporated into rgdal and other R packages, plus many other software systems; a good starting point for learning is [6].

See "Examples" for suggested projections for some common applications, and [8] for a gallery indicating how to use every projection.

Projection	Code	Arguments
Albers equal area	aea	lat_1, lat_2
Azimuthal equidistant	aeqd	lat_0, guam
Aitoff	aitoff	-
Mod. stererographics of Alaska	alsk	-
Bipolar conic of western hemisphere	bipc	-
Bonne Werner	bonne	lat_1
Cassini	cass	-
Central cylindrical	СС	-
Equal area cylindrical	cea	lat_ts
Collignon	collg	-
Craster parabolic Putnins P4	crast	-
Eckert I	eck1	-
Eckert II	eck2	-
Eckert III	eck3	-
Eckert IV	eck4	-
Eckert V	eck5	-
Eckert VI	eck6	-
Equidistant cylindrical plate (Caree)	eqc	lat_ts, lat_0
Equidistant conic	eqdc	lat_1, lat_2
Euler	euler	lat_1, lat_2
Extended transverse Mercator	etmerc	lat_ts, lat_0
Fahey	fahey	-
Foucaut	fouc	=

Foucaut sinusoidal	fouc_s	-
Gall stereographic	gall	-
Geostationary satellite view	geos	h
General sinusoidal series	gn_sinu	m, n
Gnomonic	gnom	-
Goode homolosine	goode	-
Hatano asymmetrical equal area	hatano	-
HEALPix	healpix	-
rHEALPix	rhealpix	north_square, south_square
Interrupted Goode homolosine	igh	-
Kavraisky V	kav5	-
Kavraisky VII	kav7	-
Lambert azimuthal equal area	laea	-
Longitude and latitude	lonlat	-
Longitude and latitude	longlat	-
Longitude and latitude	latlon	-
Lambert conformal conic	lcc	lat_1, lat_2, lat_0
Lambert equal area conic	leac	lat_1, south
Loximuthal	loxim	
Space oblique for Landsat	lsat	lsat, path
McBryde-Thomas flat-polar sine, no. 1	mbt_s	
McBryde-Thomas flat-polar sine, no. 2	mbt_fps	
McBryde-Thomas flat-polar parabolic	mbtfpp	
McBryde-Thomas flat-polar quartic	mbtfpq	
McBryde-Thomas flat-polar sinusoidal	mbtfps	
Mercator	merc	lat_ts
Miller oblated stereographic	mil_os	
Miller cylindrical	mill	
Mollweide	mol1	
Murdoch I	murd1	lat_1, lat_2
Murdoch II	murd2	lat_1, lat_2
murdoch III	murd3	lat_1, lat_2
Natural earth	natearth	
Nell	nell	
Nell-Hammer	nell_h	
Near-sided perspective	nsper	h
New Zealand map grid	nzmg	
General oblique transformation	ob_tran	o_proj, o_lat_p, o_lon_p, o_alpha, o_lon_c
-		o_lat_c, o_lon_1, o_lat_1, o_lon_2, o_lat_2
Oblique cylindrical equal area	ocea	lat_1, lat_2, lon_1, lon_2
Oblated equal area	oea	n, m, theta
Oblique Mercator	omerc	alpha, gamma, no_off, lonc, lon_1,
_		lat_1, lon_2, lat_2
Orthographic	ortho	-
Perspective conic	pconic	lat_1, lat_2
Polyconic American	poly	-
Putnins P1	putp1	-
Putnins P2	putp2	-

Putnins P3	putp3	-
Putnins P3'	putp3p	-
Putnins P4'	putp4p	-
Putnins P5	putp5	-
Putnins P5'	putp5p	-
Putnins P6	putp6	-
Putnins P6'	putp6p	-
Quartic authalic	qua_aut	-
Quadrilateralized spherical cube	qsc	-
Robinson	robin	-
Roussilhe stereographic	rouss	-
Sinusoidal aka Sanson-Flamsteed	sinu	-
Swiss. oblique Mercator	somerc	-
Stereographic	stere	lat_ts
Oblique stereographic alternative	sterea	-
Transverse cylindrical equal area	tcea	-
Tissot	tissot	lat_1, lat_2
Transverse Mercator	tmerc	-
Two point equidistant	tpeqd	lat_1, lon_1, lat_2, lon_2
Tilted perspective	tpers	tilt, azi, h
Universal polar stereographic	ups	south
Urmaev flat-polar sinusoidal	urmfps	n
Universal transverse Mercator	utm	zone, south
van der Grinten I	vandg	-
Vitkovsky I	vitk1	lat_1, lat_2
Wagner I Kavraisky VI	wag1	-
Wagner II	wag2	-
Wagner III	wag3	lat_ts
Wagner IV	wag4	-
Wagner V	wag5	-
Wagner VI	wag6	-
Werenskiold I	weren	-
Winkel I	wink1	lat_ts
Winkel Tripel	wintri	lat_ts

# Available ellipse formulations

In the PROJ.4 system of specifying projections, the following ellipse models are available: MERIT, SGS85, GRS80, IAU76, airy, APL4.9, NWL9D, mod\_airy, andrae, aust\_SA, GRS67, bessel, bess\_nam, clrk66, clrk80, clrk80ign, CPM, delmbr, engelis, evrst30, evrst48, evrst56, evrst69, evrstSS, fschr60, fschr60m, fschr68, helmert, hough, intl, krass, kaula, lerch, mprts, new\_intl, plessis, SEasia, walbeck, WGS60, WGS66, WGS72, WGS84, and sphere (the default). For example, use projection="+proj=aea +ellps=WGS84" for an Albers Equal Area projection using the most recent of the World Geodetic System model. It is unlikely that changing the ellipse will have a visible effect on plotted material at the plot scale appropriate to most oceanographic applications.

### Available datum formulations

In the PROJ.4 system of specifying projections, the following datum formulations are available: WGS84, GGRS87, Greek\_Geodetic\_Reference\_System\_1987, NAD83, North\_American\_Datum\_1983, NAD27, North\_American\_Datum\_1927, potsdam, Potsdam, carthage, Carthage, hermannskogel, Hermannskogel, ire65, Ireland, nzgd49, New, OSGB36, and Airy. It is unlikely that changing the datum will have a visible effect on plotted material at the plot scale appropriate to most oceanographic applications.

### Choosing a projection

The best choice of projection depends on the application. Readers may find projection="+proj=moll" useful for world-wide plots, ortho for hemispheres viewed from the equator, stere for polar views, lcc for wide meridional ranges in mid latitudes, and merc in limited-area cases where angle preservation is important.

#### **Issues**

Map projection is a complicated matter that is addressed here in a limited and pragmatic way. For example, mapPlot tries to draw axes along a box containing the map, instead of trying to find spots along the "edge" of the map at which to put longitude and latitude labels. This design choice greatly simplifies the coding effort, freeing up time to work on issues regarded as more pressing. Chief among those issues are (a) the occurrence of horizontal lines in maps that have prime meridians (b) inaccurate filling of land regions that (again) occur with shifted meridians and (c) inaccurate filling of Antarctica in some projections. Generally, issues are tackled first for commonly used projections, such as those used in the examples.

# Changes

- 2017-11-19: imw\_p removed, because it has problems doing inverse calculations. This is a also problem in the standalone PROJ.4 application version 4.9.3, downloaded and built on OSX. See https://github.com/dankelley/oce/issues/1319 for details.
- 2017-11-17: 1sat removed, because it does not work in rgdal or in the latest standalone PROJ.4 application. This is a also problem in the standalone PROJ.4 application version 4.9.3, downloaded and built on OSX. See https://github.com/dankelley/oce/issues/1337 for details.
- 2017-09-30: 1cca removed, because its inverse was wildly inaccurate in a Pacific Antarctic-Alaska application (see https://github.com/dankelley/oce/issues/1303).

#### Author(s)

Dan Kelley and Clark Richards

### References

- 1. Snyder, John P., 1987. Map Projections: A Working Manual. USGS Professional Paper: 1395 (available at pubs.usgs.gov/pp/1395/report.pdf).
- 2. Natural Resources Canada http://www.nrcan.gc.ca/earth-sciences/geography/topographic-information/maps/9805

- 3. Wikipedia page http://en.wikipedia.org/wiki/List\_of\_map\_projections
- 4. Radical Cartography website http://www.radicalcartography.net/?projectionref (This URL worked prior to Nov 16, 2016, but was found to fail on that date.)
- 5. The PROJ.4 website is <a href="http://trac.osgeo.org/proj">http://trac.osgeo.org/proj</a>, and it is the place to start to learn about the code.
- 6. PROJ.4 projection details were once at http://www.remotesensing.org/geotiff/proj\_list/but it was discovered on Dec 18, 2016, that this link no longer exists. Indeed, there seems to have been significant reorganization of websites related to this. The base website seems to be https://trac.osgeo.org/geotiff/ and that lists only what is called an unofficial listing, on the wayback web-archiverserver http://web.archive.org/web/20160802172057/http://www.remotesensing.org/geotiff/proj\_list/
- 7. A gallery of map plots is provided at http://dankelley.github.io/r/2015/04/03/oce-proj.html
- 8. A fascinating historical perspective is provided by Snyder, J. P. (1993). Two thousand years of map projections. University of Chicago Press.

#### See Also

Points may be added to a map with mapPoints, lines with mapLines, text with mapText, polygons with mapPolygon, images with mapImage, and scale bars with mapScalebar. Points on a map may be determined with mouse clicks using mapLocator. Great circle paths can be calculated with geodGc. See [8] for a demonstration of the available map projections (with graphs).

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

```
## Not run:
library(oce)
data(coastlineWorld)
# Example 1.
# Mollweide ([1] page 54) is an equal-area projection that works well
# for whole-globe views, below shown in a Pacific-focus view.
# Note that filling is not employed when the prime meridian
# is shifted, because this causes a problem with Antarctica
par(mfrow=c(2, 1), mar=c(3, 3, 1, 1))
mapPlot(coastlineWorld, projection="+proj=moll", col='gray')
mtext("Mollweide", adj=1)
cl180 <- coastlineCut(coastlineWorld, lon_0=-180)</pre>
mapPlot(cl180, projection="+proj=moll +lon_0=-180")
mtext("Mollweide", adj=1)
par(mfrow=c(1, 1))
# Example 2.
# Orthographic projections resemble a globe, making them attractive for
# non-technical use, but they are neither conformal nor equal-area, so they
```

```
# are somewhat limited for serious use on large scales. See Section 20 of
# [1]. Note that filling is not employed because it causes a problem with
# Antarctica.
par(mar=c(3, 3, 1, 1))
mapPlot(coastlineWorld, projection="+proj=ortho +lon_0=-180")
mtext("Orthographic", adj=1)
# Example 3.
# The Lambert conformal conic projection is an equal-area projection
# recommended by [1], page 95, for regions of large east-west extent
# away from the equator, here illustrated for the USA and Canada.
par(mar=c(3, 3, 1, 1))
mapPlot(coastlineCut(coastlineWorld, -100),
        longitudelim=c(-130,-55), latitudelim=c(35, 60),
        projection="+proj=lcc +lat_0=30 +lat_1=60 +lon_0=-100", col='gray')
mtext("Lambert conformal", adj=1)
# Example 4.
# The stereographic projection [1], page 120, is conformal, used
# below for an Arctic view with a Canadian focus. Note the trick of going
# past the pole: the second latitudelim value is 180 minus the first, and the
# second longitudelim is 180 plus the first; this uses image points "over"
# the pole.
par(mar=c(3, 3, 1, 1))
mapPlot(coastlineCut(coastlineWorld, -135),
        longitudelim=c(-130, 50), latitudelim=c(70, 110),
        proj="+proj=stere +lat_0=90 +lon_0=-135", col='gray')
mtext("Stereographic", adj=1)
# Example 5.
# Spinning globe: create PNG files that can be assembled into a movie
png("globe-%03d.png")
lons <- seq(360, 0, -15)
par(mar=rep(0, 4))
for (i in seq_along(lons)) {
   p <- paste("+proj=ortho +lat_0=30 +lon_0=", lons[i], sep="")</pre>
    if (i == 1) {
        mapPlot(coastlineCut(coastlineWorld, lons[i]),
                projection=p, col="lightgray")
        xlim <- par("usr")[1:2]</pre>
        ylim <- par("usr")[3:4]</pre>
    } else {
        mapPlot(coastlineCut(coastlineWorld, lons[i]),
                projection=p, col="lightgray",
                xlim=xlim, ylim=ylim, xaxs="i", yaxs="i")
    }
}
dev.off()
## End(Not run)
```

mapPoints 207

mai	oPoints	

Add Points to a Map

#### **Description**

Plot points on an existing map.

# Usage

```
mapPoints(longitude, latitude, debug = getOption("oceDebug"), ...)
```

# **Arguments**

longitude Longitudes of points to be plotted, or an object from which longitude and lat-

itude can be inferred in which case the following two arguments are ignored.

This objects that are possible include those of type coastline.

latitude Latitudes of points to be plotted.

debug A flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... Optional arguments passed to points.

### **Details**

Adds points to an existing map, by analogy to points.

## Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

208 mapPolygon

```
## End(Not run)
```

mapPolygon

Add a Polygon to a Map

# Description

Plot a polygon on an existing map.

### Usage

```
mapPolygon(longitude, latitude, density = NULL, angle = 45, border = NULL,
col = NA, lty = par("lty"), ..., fillOddEven = FALSE)
```

# Arguments

longitude longitudes of points to be plotted, or an object from which longitude and latitude

can be inferred (e.g. a coastline file, or the return value from mapLocator), in

which case the following two arguments are ignored.

latitude latitudes of points to be plotted.

density as for polygon.
angle as for polygon.
border as for polygon.
col as for polygon.
lty as for polygon.
... as for polygon.
fillOddEven as for polygon.

## **Details**

Adds a polygon to an existing map, by analogy to polygon. Used by mapImage.

## Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

mapScalebar 209

mapScalebar	Add a Scalebar to a Map

### **Description**

Draw a scalebar on an existing map.

### Usage

```
mapScalebar(x, y = NULL, length, lwd = 1.5 * par("lwd"), cex = par("cex"),
  col = "black")
```

## **Arguments**

x, y	position of the scalebar. Eventually this may be similar to the corresponding arguments in legend, but at the moment y must be NULL and x must be "topleft".
length	the distance to indicate, in kilometres. If not provided, a reasonable choice is made, based on the underlying map.
lwd	line width of the scalebar.
cex	character expansion factor for the scalebar text.
col	colour of the scalebar.

### **Details**

The scale is appropriate to the centre of the plot, and will become increasingly inaccurate away from that spot, with the error depending on the projection and the fraction of the earth that is shown.

# Author(s)

Dan Kelley

#### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

```
## Not run:
library(oce)
data(coastlineWorld)
## Arctic Ocean
par(mar=c(2.5, 2.5, 1, 1))
mapPlot(coastlineWorld, latitudelim=c(60, 120), longitudelim=c(-130,-50),
```

210 mapText

```
col="lightgray", projection="+proj=stere +lat_0=90")
mapScalebar()
## End(Not run)
```

mapText

Add Text to a Map

## **Description**

Plot text on an existing map.

### Usage

```
mapText(longitude, latitude, labels, ...)
```

## **Arguments**

longitude vector of longitudes of text to be plotted.

latitude vector of latitudes of text to be plotted.

labels vector of labels of text to be plotted.

... optional arguments passed to text, e.g. adj, pos, etc.

#### **Details**

Adds text to an existing map, by analogy to text.

### Author(s)

Dan Kelley

### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapTissot, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

mapTissot 211

```
projection="+proj=merc")
lon <- -63.5744 # Halifax
lat <- 44.6479
mapPoints(lon, lat, pch=20, col="red")
mapText(lon, lat, "Halifax", col="red", pos=1, offset=1)
## End(Not run)</pre>
```

mapTissot

Add Tissot Indicatrices to a Map

# **Description**

Plot ellipses at grid intersection points, as a method for indicating the distortion inherent in the projection [1]. (Each ellipse is drawn with 64 segments.)

# Usage

```
mapTissot(grid = rep(15, 2), scale = 0.2, crosshairs = FALSE, ...)
```

# **Arguments**

grid	numeric vector of length 2, specifying the increment in longitude and latitude for the grid. Indicatrices are drawn at e.g. longitudes seq(-180, 180, grid[1]).
scale	numerical scale factor for ellipses. This is multiplied by min(grid) and the result is the radius of the circle on the earth, in latitude degrees.
crosshairs	logical value indicating whether to draw constant-latitude and constant-longitude crosshairs within the ellipses. (These are drawn with 10 line segments each.) This can be helpful in cases where it is not desired to use mapGrid to draw the longitude/latitude grid.
	extra arguments passed to plotting functions, e.g. col="red" yields red indicatrices.

# Details

The purpose and interpretation are outlined in [1], but should also be self-explanatory.

## Author(s)

Dan Kelley

#### References

1. Snyder, John P., 1987. Map Projections: A Working Manual. USGS Professional Paper: 1395 (available at pubs.usgs.gov/pp/1395/report.pdf).

212 mapZones

### See Also

A map must first have been created with mapPlot.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, oceCRS, shiftLongitude, usrLonLat, utm2lonlat

## **Examples**

```
## Not run:
library(oce)
data(coastlineWorld)
par(mfrow=c(1, 1), mar=c(2, 2, 1, 1))
p <- "+proj=aea +lat_1=10 +lat_2=60 +lon_0=-45"
mapPlot(coastlineWorld, projection=p, col="gray",
longitudelim=c(-90,0), latitudelim=c(0, 50))
mapTissot(c(15, 15), col='red')
## End(Not run)</pre>
```

mapZones

Add Zones to a Map [deprecated]

# **Description**

**WARNING:** This function will be removed soon; see oce-deprecated.

#### Usage

```
mapZones(longitude, polarCircle = 0, lty = "solid", lwd = 0.5 *
   par("lwd"), col = "darkgray", ...)
```

# Arguments

longitude	either a logical indicating whether to draw a zonal grid, or a vector of longitudes at which to draw zones.
polarCircle	a number indicating the number of degrees of latitude extending from the poles, within which zones are not drawn.
lty	line type.
lwd	line width.
col	line colour.
	optional arguments passed to lines.

matchBytes 213

# **Details**

Use mapGrid instead of the present function.

Plot zones (lines of constant longitude) on a existing map.

This function should not be used, since it will be removed soon. Please use mapGrid() instead.

# Author(s)

Dan Kelley

# See Also

 $Other functions that will be removed soon: addColumn, \verb|ctdAddColumn|, \verb|ctdUpdateHeader|, mapMeridians|, oce.as.| POSIX1t$ 

matchBytes

Locate byte sequences in a raw vector

# **Description**

Find spots in a raw vector that match a given byte sequence.

# Usage

```
matchBytes(input, b1, ...)
```

# Arguments

input a vector of raw (byte) values.

b1 a vector of bytes to match (must be of length 2 or 3 at present; for 1-byte, use

which).

... additional bytes to match for (up to 2 permitted)

# Value

List of the indices of input that match the start of the bytes sequence (see example).

# Author(s)

Dan Kelley

```
buf <- as.raw(c(0xa5, 0x11, 0xaa, 0xa5, 0x11, 0x00))
match <- matchBytes(buf, 0xa5, 0x11)
print(buf)
print(match)</pre>
```

214 matrixSmooth

matrixShiftLongitude Rearrange areal matrix so Greenwich is near the centre

# **Description**

Sometimes datasets are provided in matrix form, with first index corresponding to longitudes ranging from 0 to 360. matrixShiftLongitude cuts such matrices at longitude=180, and swaps the pieces so that the dateline is at the left of the matrix, not in the middle.

# Usage

```
matrixShiftLongitude(m, longitude)
```

### **Arguments**

m The matrix to be modified.

longitude A vector containing the longitude in the 0-360 convention. If missing, this is

constructed to range from 0 to 360, with as many elements as the first index of

m.

#### Value

A list containing m and longitude, both rearranged as appropriate.

### See Also

shiftLongitude and standardizeLongitude.

matrixSmooth Smooth a Matrix

# **Description**

The values on the edge of the matrix are unaltered. For interior points, the result is defined in terms in terms of the original as follows.  $r_{i,j} = (2m_{i,j} + m_{i-1,j} + m_{i+1,j} + m_{i,j-1} + m_{i,j+1})/6$ . Note that missing values propagate to neighbours.

# Usage

```
matrixSmooth(m, passes = 1)
```

### **Arguments**

a matrix to be smoothed.

passes an integer specifying the number of times the smoothing is to be applied.

met 215

### Value

A smoothed matrix.

#### Author(s)

Dan Kelley

# **Examples**

```
library(oce)
opar <- par(no.readonly = TRUE)
m <- matrix(rep(seq(0, 1, length.out=5), 5), nrow=5, byrow=TRUE)
m[3, 3] <- 2
m1 <- matrixSmooth(m)
m2 <- matrixSmooth(m1)
m3 <- matrixSmooth(m2)
par(mfrow=c(2, 2))
image(m, col=rainbow(100), zlim=c(0, 4), main="original image")
image(m1, col=rainbow(100), zlim=c(0, 4), main="smoothed 1 time")
image(m2, col=rainbow(100), zlim=c(0, 4), main="smoothed 2 times")
image(m3, col=rainbow(100), zlim=c(0, 4), main="smoothed 3 times")
par(opar)</pre>
```

met

Sample met Object

# **Description**

This is sample met object containing data for Halifax, Nova Scotia, during September of 2003 (the period during which Hurricane Juan struck the city).

#### **Details**

The data file was downloaded with

Using download.met avoids having to navigate the the awkward Environment Canada website, but it imposes the burden of having to know the station number. See the documentation for download.met for more details on station numbers.

#### **Source**

Environment Canada website on February 1, 2017

216 met-class

#### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to met data: [[,met-method, [[<-,met-method, as.met, download.met, met-class, plot,met-method, read.met, subset,met-method, summary,met-method

met-class

Class to Store Meteorological Data

#### Description

Class to store meteorological data, with standard slots metadata, data and processingLog. For objects created with read.met, the data slot will contain all the columns within the original file (with some guesses as to units) in addition to several calculated quantities such as u and v, which are velocities in m/s (not the km/h stored in typical data files), and which obey the oceanographic convention that u>0 is a wind towards the east.

#### Methods

Accessing values. For an object named m, temperature (in degC) may be accessed as m[["temperature"]], dew point (in degC) as m[["dewPoint"]], pressure (in kPa) as m[["pressure"]], eastward wind component (in m/s) as m[["u"]], northward wind component (in m/s) as m[["v"]], and wind direction (in degrees clockwise of North) as "direction". The filename from which the data came (if any) may be found with m[["filename"]]. Items in metadata must be specifield by full name, but those in data may be abbreviated, so long as the abbreviation is unique.

Assigning values. Everything that may be accessed may also be assigned, e.g.

```
m[["temperature"]] <- 1 + m[["temperature"]]</pre>
```

increases temperature by 1C.

### Author(s)

Dan Kelley

#### See Also

```
Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class
```

Other things related to met data: [[,met-method, [[<-,met-method, as.met, download.met, met, plot,met-method, read.met, subset,met-method, summary,met-method

metNames2oceNames 217

metNames2oceNames

Convert met Data Name to Oce Name

### **Description**

Convert met Data Name to Oce Name

#### Usage

metNames2oceNames(names, scheme)

### **Arguments**

names a vector of character strings with original names

scheme an optional indication of the scheme that is employed. This may be "ODF", in

which case ODFNames 20ceNames is used, or "met", in which case some tentative

code for met files is used.

#### **Details**

Interoperability between oce functions requires that standardized data names be used, e.g. "temperature" for in-situ temperature. Very few data-file headers name the temperature column in exactly that way, however, and this function is provided to try to guess the names. The task is complicated by the fact that Environment Canada seems to change the names of the columns, e.g. sometimes a symbol is used for the degree sign, other times not.

Several quantities in the returned object differ from their values in the source file. For example, speed is converted from km/h to m/s, and angles are converted from tens of degrees to degrees. Also, some items are created from scratch, e.g. u and v, the eastward and northward velocity, are computed from speed and direction. (Note that e.g. u is positive if the wind blows to the east; the data are thus in the normal Physics convention.)

# Value

Vector of strings for the decoded names. If an unknown scheme is provided, this will just be names.

moonAngle

Lunar Angle as Function of Space and Time

218 moonAngle

### **Description**

The calculations are based on formulae provided by Meeus [1982], primarily in chapters 6, 18, and 30. The first step is to compute sidereal time as formulated in Meeus [1982] chapter 7, which in turn uses Julian day computed according to as formulae in Meeus [1982] chapter 3. Using these quantities, formulae in Meeus [1982] chapter 30 are then used to compute geocentric longitude (lambda, in the Meeus notation), geocentric latitude (beta), and parallax. Then the obliquity of the ecliptic is computed with Meeus [1982] equation 18.4. Equatorial coordinates (right ascension and declination) are computed with equations 8.3 and 8.4 from Meeus [1982], using eclipticalToEquatorial. The hour angle (H) is computed using the unnumbered equation preceding Meeus's [1982] equation 8.1. Finally, Meeus [1982] equations 8.5 and 8.6 are used to calculate the local azimuth and altitude of the moon, using equatorialToLocalHorizontal.

### Usage

```
moonAngle(t, longitude = 0, latitude = 0, useRefraction = TRUE)
```

#### **Arguments**

t time, a POSIXt object (converted to timezone "UTC", if it is not already in that

timezone), or a numeric value that corresponds to such a time.

longitude observer longitude in degrees east observer latitude in degrees north

useRefraction boolean, set to TRUE to apply a correction for atmospheric refraction. (Ignored

at present.)

#### Value

A list containing the following.

time time

azimuth moon azimuth, in degrees eastward of north, from 0 to 360. Note: this is not the

convention used by Meeus, who uses degrees westward of South. (See diagram

below.)

altitude moon altitude, in degrees from -90 to 90. (See diagram below.)

rightAscension right ascension, in degrees declination declination, in degrees

lambda geocentric longitude, in degrees
beta geocentric latitude, in degrees
diameter lunar diameter, in degrees.

distance earth-moon distance, in kilometers)

illuminatedFraction

fraction of moon's visible disk that is illuminated

phase phase of the moon, defined in equation 32.3 of Meeus [1982]. The fractional

part of which is 0 for new moon, 1/4 for first quarter, 1/2 for full moon, and 3/4

for last quarter.

moonAngle 219

#### Alternate formulations

Formulae provide by Meeus [1982] are used for all calculations here. Meeus [1991] provides formulae that are similar, but that differ in the 5th or 6th digits. For example, the formula for ephemeris time in Meeus [1991] differs from that in Meeus [1992] at the 5th digit, and almost all of the approximately 200 coefficients in the relevant formulae also differ in the 5th and 6th digits. Discussion of the changing formulations is best left to members of the astronomical community. For the present purpose, it may be sufficient to note that moonAngle, based on Meeus [1982], reproduces the values provided in example 45.a of Meeus [1991] to 4 significant digits, e.g. with all angles matching to under 2 minutes of arc.

#### Author(s)

Dan Kelley, based on formulae in Meeus [1982].

#### References

Meeus, Jean, 1982. Astronomical formulae for calculators. Willmann-Bell. Richmond VA, USA. 201 pages.

Meeus, Jean, 1991. Astronomical algorithms. Willmann-Bell, Richmond VA, USA. 429 pages.

#### See Also

The equivalent function for the sun is sunAngle.

Other things related to astronomy: eclipticalToEquatorial, equatorialToLocalHorizontal, julianCenturyAnomaly, julianDay, siderealTime, sunAngle

```
library(oce)
par(mfrow=c(3,2))
y <- 2012
m < -4
days <- 1:3
## Halifax sunrise/sunset (see e.g. http://www.timeanddate.com/worldclock)
rises <- ISOdatetime(y, m, days,c(13,15,16), c(55, 04, 16),0,tz="UTC") + 3 * 3600 # ADT
sets <- ISOdatetime(y, m,days,c(3,4,4), c(42, 15, 45),0,tz="UTC") + 3 \times 3600
azrises <- c(69, 75, 82)
azsets <- c(293, 288, 281)
latitude <- 44.65
longitude <- -63.6
for (i in 1:3) {
    t \leftarrow ISOdatetime(y, m, days[i],0,0,0,tz="UTC") + seq(0, 24*3600, 3600/4)
    ma <- moonAngle(t, longitude, latitude)</pre>
    oce.plot.ts(t, ma$altitude, type='l', mar=c(2, 3, 1, 1), cex=1/2, ylab="Altitude")
    abline(h=0)
    points(rises[i], 0, col='red', pch=3, lwd=2, cex=1.5)
    points(sets[i], 0, col='blue', pch=3, lwd=2, cex=1.5)
    oce.plot.ts(t, ma$azimuth, type='l', mar=c(2, 3, 1, 1), cex=1/2, ylab="Azimuth")
    points(rises[i], -180+azrises[i], col='red', pch=3, lwd=2, cex=1.5)
```

220 numberAsHMS

```
points(sets[i], -180+azsets[i], col='blue', pch=3, lwd=2, cex=1.5)
}
```

numberAsHMS

Convert a Numeric Time to Hour, Minute, and Second

# Description

Convert a Numeric Time to Hour, Minute, and Second

# Usage

```
numberAsHMS(t, default = 0)
```

# Arguments

t a vector of factors or character strings, in the format 1200 for 12:00, 0900 for

09:00, etc.

default value to be used for the returned hour, minute and second if there is something

wrong with the input value (e.g. its length exceeds 4 characters, or it contains

non-numeric characters)

### Value

A list containing hour, minute, and second, the last of which is always zero.

### Author(s)

Dan Kelley

### See Also

 $Other things \ related \ to \ time: \ ctimeToSeconds, julianCenturyAnomaly, julianDay, numberAsPOSIXct, secondsToCtime, unabbreviateYear$ 

```
t <- c("0900", "1234")
numberAsHMS(t)
```

numberAsPOSIXct 221

nu	mher	٠٨٠٥	UC.	TV.	<u>~+</u>

Convert a Numeric Time to a POSIXct Time

### **Description**

There are many varieties, according to the value of type as defined in 'Details'.

# Usage

```
numberAsPOSIXct(t, type = c("unix", "matlab", "gps", "argo", "ncep1", "ncep2",
    "sas", "spss", "yearday"), tz = "UTC")
```

### **Arguments**

t an integer corresponding to a time, in a way that depends on type.

type the type of time (see "Details").

tz a string indicating the time zone, used only for unix and matlab times, since GPS

times are always referenced to the UTC timezone.

#### **Details**

- "unix" employs Unix times, measured in seconds since the start of the year 1970.
- "matlab" employs Matlab times, measured in days since what MathWorks [1] calls "January 0,0000" (i.e. ISOdatetime(0, 1, 1, 0,0, 0) in R notation).
- "gps" employs the GPS convention. For this, t is a two-column matrix, with the first column being the the GPS "week" (referenced to 1999-08-22) and the second being the GPS "second" (i.e. the second within the week). Since the GPS satellites do not handle leap seconds, the R-defined .leap.seconds is used for corrections.
- "argo" employs Argo times, measured in days since the start of the year 1900.
- "ncep1" employs NCEP times, measured in hours since the start of the year 1800.
- "ncep2" employs NCEP times, measured in days since the start of the year 1. (Note that, for reasons that are unknown at this time, a simple R expression of this definition is out by two days compared with the UDUNITS library, which is used by NCEP. Therefore, a two-day offset is applied. See [2, 3].)
- "sas" employs SAS times, indicated by type="sas", have origin at the start of 1960.
- "spss" employs SPSS times, in seconds after 1582-10-14.
- "yearday" employs a convention in which t is a two-column matrix, with the first column being the year, and the second the yearday (starting at 1 for the first second of January 1, to match the convention used by Sea-Bird CTD software).

#### Value

A POSIXct time vector.

222 oce

### Author(s)

Dan Kelley

#### References

```
[1] Matlab times: http://www.mathworks.com/help/matlab/ref/datenum.html
[2] NCEP times: https://www.esrl.noaa.gov/psd/data/gridded/faq.html#3
[3] problem with NCEP times: https://github.com/dankelley/oce/issues/738
```

#### See Also

#### numberAsHMS

Other things related to time: ctimeToSeconds, julianCenturyAnomaly, julianDay, numberAsHMS, secondsToCtime, unabbreviateYear

### **Examples**

oce

oce: A Package for Oceanographic Analysis

### **Description**

The oce package provides functions for working with Oceanographic data, for calculations that are specific to Oceanography, and for producing graphics that match the conventions of the field.

### **Specialized functions**

A key function is read.oce, which will attempt to read Oceanographic data in raw format. This uses oceMagic to try to detect the file type, based on the file name and contents. If it proves impossible to detect the type, users should next try a more specialized function, e.g. read.ctd for CTD files, or read.ctd.sbe for Teledyne-Seabird files.

### Generic methods

A list of the generic methods in oce is provided by 'methods(class="oce")'; a few that are used frequently are as follows.

oce-class 223

[[ Find the value of an item in the object's metadata or data slot. If the item does not exist, but can be calculated from the other items, then the calculated value is returned. As an example of the latter, consider the built-in ctd dataset, which does not contain potential temperature, "theta". Using ctd[["theta"]] therefore causes swTheta to be called, to calculate theta. See [[,oce-method or type?"[[,oce-method" to learn more.

- [[<- Alters the named item in the object's metadata or data slot. If the item does not exist, it is created. See [[<-,oce-method or type ?"[[<-,oce-method" to learn more.
- **summary** Displays some information about the object named as an argument, including a few elements from its metadata slot and some statistics of the contents of its data slot. See <a href="mailto:summary,oce-method">summary,oce-method</a> or type ?"summary,oce-method" to learn more.

**subset** Takes a subset of an oce object. See <u>subset</u>,oce-method or type?"subset,oce-method" to learn more.

### Oceanographic data types handled

Over a dozen specialized data types are handled by oce, with generic plots and summaries for each, along with the specialized functions needed for typical Oceanographic analysis.

### Oce object structure

See oce-class for a summary of the class structure and links to documentation for the many subclasses of oce objects, each aligned with a class of instrument or or type of dataset.

oce-class

Base Class for oce Objects

## **Description**

This is mainly used within oce to create sub-classes, although users can use new("oce") to create a blank oce object, if desired.

#### **Slots**

metadata A list containing information about the data. The contents vary across sub-classes, e.g. an adp-class object has information about beam patterns, which obviously would not make sense for a ctd-class object. In addition, all classes have items named units and flags, used to store information on the units of the data, and the data quality.

data A list containing the data.

processingLog A list containing time-stamped processing steps, typically stored in the object by oce functions.

### See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, odf-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

224 oce-deprecated

### **Examples**

```
str(new("oce"))
```

oce-deprecated

Deprecated and Defunct Elements of package 'oce'

## **Description**

Certain functions and function arguments are still provided for compatibility with older versions of 'oce', but will be removed soon. The 'oce' scheme for removing functions is similar to that used by 'Bioconductor': items are marked as "deprecated" in one release, marked as "defunct" in the next, and removed in the next after that. This goal is to provide a gentle migration path for users who keep their packages reasonably up-to-date.

#### **Details**

Several 'oce' functions are marked "deprecated" in the present release of oce. Please use the replacement functions as listed below. The next CRAN release of 'oce' will designate these functions as "defunct".

Deprecated	Replacement	Notes
<pre>findInOrdered(x,f)</pre>	<pre>findInterval(f,x)</pre>	Deprecated 2017-09-07
mapZones	mapGrid	Deprecated 2016-02-13
mapMeridians	mapGrid	Deprecated 2016-02-13
addColumn	oceSetData	Deprecated 2016-08-01
oce.magic	oceMagic	Deprecated 2016-09-01
ctdAddColumn	oceSetData	Deprecated 2016-11-11
ctdUpdateHeader	-	Deprecated 2016-11-11
oce.as.POSIXlt	parse_date_time	Deprecated 2016-12-17

The following are marked "defunct", so calling them in the the present version produces an error message that hints at a replacement function. Once a function is marked "defunct" on one CRAN release, it will be slated for outright deletion in a subsequent release.

Defunct	Replacement	Notes
makeSection	as.section	Improve utility and name sensibility
columns	read.ctd	Unnecessary; never worked

The following were removed in recent years.

<b>Function</b>	Replacement	Notes
FILL IN	FILL IN	FILL IN

oce.as.POSIXlt 225

Several 'oce' function arguments are considered "deprecated", which means they will be marked "defunct" in the next CRAN release. These are normally listed in the help page for the function in question. A few that may be of general interest are also listed below.

- The endian argument of byteToBinary will be removed sometime in the year 2017, and should be set to "big" in the meantime.
- The parameters argument of plot, ctd-method was deprecated on 2016-12-30. It was once used by plot, coastline-method but has been ignored by that function since February 2016.
- The orientation argument of plot, ctd-method was deprecated on 2016-12-30. It was once used by plot, coastline-method but has been ignored by that function since February 2016.

Several 'oce' function arguments are considered "defunct", which means they will be removed in the next CRAN release. They are as follows.

- The date argument of as.ctd was discovered to have been unused in early 2016. Since the startTime actually fills its role, date was considered to be deprecated in June 2016.
- The quality flag of as.ctd was marked as deprecated in March 2016.
- The fill argument of mapPlot was confusing to users, so it was designated as deprecated in June 2016. (The confusion stemmed from subtle differences between plot and polygon, and the problem is that mapPlot can use either of these functions, according to whether coastlines are to be filled.) The functionality is preserved, in the col argument.

#### See Also

The 'Bioconductor' scheme for removing functions is described at https://www.bioconductor.org/developers/how-to/deprecation/ and it is extended here to function arguments.

oce.as.POSIXlt

Oce Variant of as.POSIXlt [deprecated]

## **Description**

**WARNING:** This function will be removed soon; see oce-deprecated. It was realized in December of 2016 that this function was not used within oce, and also that parse\_date\_time in the **lubridate** package was superior and therefore a better choice for "oce" users.

#### Usage

```
oce.as.POSIXlt(x, tz = "")
```

#### **Arguments**

x a date, as for as.POSIX1t, but also including forms in which the month name appears.

tz the timezone, as for as . POSIX1t

226 oce.as.raw

## Value

A POSIXIt object.

## Author(s)

Dan Kelley

## See Also

 $Other \ functions \ that \ will \ be \ removed \ soon: \ add Column, \ ctd Add Column, \ ctd Update Header, \ map Meridians, \ map Zones$ 

oce.as.raw

Version of as.raw() that clips data

# Description

A version of as.raw() that clips data to prevent warnings

# Usage

```
oce.as.raw(x)
```

### **Arguments**

Χ

values to be converted to raw

### **Details**

Negative values are clipped to 0, while values above 255 are clipped to 255; the result is passed to as.raw and returned.

### Value

Raw values corresponding to x.

# Author(s)

Dan Kelley

```
x <- c(-0.1, 0, 1, 255, 255.1)
data.frame(x, oce.as.raw(x))</pre>
```

oce.axis.POSIXct 227

oce.axis.POSIXct

Oce Version of axis.POSIXct

### **Description**

A specialized variant of axis. POSIXct that produces results with less ambiguity in axis labels.

### Usage

```
oce.axis.POSIXct(side, x, at, tformat, labels = TRUE, drawTimeRange,
  abbreviateTimeRange = FALSE, drawFrequency = FALSE, cex = par("cex"),
 cex.axis = par("cex.axis"), cex.main = par("cex.main"),
 mar = par("mar"), mgp = par("mgp"), main = "",
 debug = getOption("oceDebug"), ...)
```

### **Arguments**

side as for axis.POSIXct. as for axis.POSIXct. х as for axis.POSIXct. at

tformat as format for axis. POSIXct for now, but may eventually have new features for

multiline labels, e.g. day on one line and month on another.

labels as for axis.POSIXct.

drawTimeRange Optional indication of whether/how to draw the time range in the margin on

the side of the the plot opposite the time axis. If this is not supplied, it defaults to the value returned by getOption("oceDrawTimeRange"), and if that option is not set, it defaults to TRUE. No time range is drawn if drawTimeRange is FALSE. If it is TRUE, the range will be shown. This range refers to range of the x axis (not the data). The format of the elements of that range is set by getOption("oceTimeFormat") (or with the default value of an empty string, if this option has not been set). The timezone will be indicated if the time range is under a week. For preliminary work, it makes sense to use drawTimeRange=TRUE, but for published work it can be better to drop this label and indicate something

about the time in the figure caption.

abbreviateTimeRange

boolean, TRUE to abbreviate the second number in the time range, e.g. dropping

the year if it is the same in the first number.

boolean, TRUE to show the frequency of sampling in the data drawFrequency

size of labels on axes; see par("cex"). cex

cex.axis see par("cex.axis"). see par("cex.main"). cex.main value for par(mar) for axis mar

value for par(mgp) for axis mgp

228 oce.axis.POSIXct

main title of plot

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

... as for axis.POSIXct.

#### **Details**

The tick marks are set automatically based on examination of the time range on the axis. The scheme was devised by constructing test cases with a typical plot size and font size, and over a wide range of time scales. In some categories, both small tick marks are interspersed between large ones.

The user may set the format of axis numbers with the tformat argument. If this is not supplied, the format is set based on the time span of the axis:

- If this time span is less than a minute, the time axis labels are in seconds (fractional seconds, if the interval is less than 2 seconds), with leading zeros on small integers. (Fractional seconds are enabled with a trick: the usual R format "%S" is supplemented with a new format e.g. "%. 2S", meaning to use two digits after the decimal.)
- If the time span exceeds a minute but is less than 1.5 days, the label format is "%H:%M:%S".
- If the time span exceeds 1.5 days but is less than 1 year, the format is "%b %d" (e.g. Jul 15) and, again, the tick marks are set up for several subcategories.
- If the time span exceeds a year, the format is "%Y", i.e. the year is displayed with 4 digits.

It should be noted that this scheme differs from the R approach in several ways. First, R writes day names for some time ranges, in a convention that is seldom seen in the literature. Second, R will write nn:mm for both HH:MM and MM:SS, an ambiguity that might confuse readers. Third, the use of both large and small tick marks is not something that R does.

Bear in mind that tformat may be set to alter the number format, but that the tick mark scheme cannot (presently) be controlled.

#### Value

A vector of times corresponding to axis ticks is returned silently.

# Author(s)

Dan Kelley

#### See Also

This is used mainly by oce.plot.ts.

oce.colorsGebco 229

$\cap \cap \cap$	colorsGebo	Λ

Gebco Colors

# Description

Gebco Colors

## Usage

```
oce.colorsGebco(n = 9, region = c("water", "land", "both"),
  type = c("fill", "line"))
```

# Arguments

n Number of colors to return

region String indicating application region, one of "water", "land", or "both".

type String indicating the purpose, one of "fill" or "line".

## See Also

Other things related to colors: colormap, colors, oce.colorsTwo

oce.colorsTwo

Create a Palette of Colours

# Description

Create a palette of colours.

## Usage

```
oce.colorsTwo(n, low = 2/3, high = 0, smax = 1, alpha = 1)
```

## Arguments

n	the number of col-	ours $(>1)$ to be	e in the palette.

low the hue, in [0, 1], for the low end of a oce.colorsTwo scale. high the hue, in [0, 1], for the high end of a oce.colorsTwo scale.

smax the maximum saturation, in [0, 1], for the colours of oce.colorsTwo.

alpha the alpha value, in [0, 1], for the colours of oce.colorsTwo.

230 oce.colorsTwo

#### **Details**

oce.colorsPalette provides a variety of pre-defined palettes. which=1 yields the ColorBrewer diverging red/blue scheme while which=2 yields the ColorBrewer diverging RYB scheme [1].

A family of nine-colour schemes is as follows: which="jet" (or which="9A" or which=9.01 for the Jet scheme; which="9B" or which=9.02 for a scheme similar to Jet but omitting the green, and somewhat desaturating the yellow and cyan.

oce.colorsGebco provides palettes that mimic the GEBCO atlas colours, with shades of blue for water and of brown for land. The blue values go from dark to light, and the brown ones from light to dark; in this way, topographic images have light values near sea-level, and get darker in either deeper water or higher terrain.

oce.colorsJet provides a palette similar to the Matlab "jet" palette.

oce.colorsTwo provides a two-tone palette that fades to white at central values.

oce.colorsViridis provides a matplotlib (python) colour scheme that became the standard in 2015; see [2]. This is a blue-yellow transition that is designed to reproduce well in black-and-white, and also to be interpretable by those with certain forms of colour blindness [3, 4, 5].

oce.colorsCDOM, oce.colorsChlorophyll, oce.colorsDensity, oce.colorsFreesurface, oce.colorsOxygen, oce.colorsPhase, oce.colorsSalinity, oce.colorsTemperature, oce.colorsTurbidity, oce.colorsVelocity and oce.colorsVorticity are based on RGB values set up by Kristen M. Thyng for her Python package named cmcolor [7].

#### Author(s)

Dan Kelley

#### References

- [1] Color Brewer. http://colorbrewer2.org/
- [2] A blog item on the Viridis (and related) matplotlib colour scales is at http://bids.github.io/colormap/.
- [3] Light, A., and P. J. Bartlein, 2004. The End of the Rainbow? Color Schemes for Improved Data Graphics. *Eos Trans. AGU*, 85(40), doi:10.1029/2004EO400002.
- [4] Martin Jakobsson, Ron Macnab, and Members of the Editorial Board, IBCAO. Selective comparisons of GEBCO (1979) and IBCAO (2000) maps. 'https://www.ngdc.noaa.gov/mgg/bathymetry/arctic/ibcao\_ge
- [5] Stephenson, David B., 2005. Comment on "Color schemes for improved data graphics," by A. Light and P. J. Bartlein. *Eos Trans. AGU*, 86(20).
- [6] The Geography department at the University of Oregon has good resources on colour schemes; see e.g. http://geography.uoregon.edu/datagraphics/color\_scales.htm(This URL worked prior to December 8, 2015, but was found to fail on that date; it is included here in case users want to search for themselves.)
- [7] The cmocean Python package, written by Kristen M Thyng, is available at https://github.com/kthyng/cmocean.

#### See Also

Other things related to colors: colormap, colors, oce.colorsGebco

oce.contour 231

#### **Examples**

```
library(oce)
opar <- par(no.readonly = TRUE)</pre>
# 1. Show a few palettes
x \leftarrow array(1:1000, dim=c(1, 1000))
par(mfrow=c(1, 5), mar=c(1, 3, 3, 1))
image(x, col=oce.colorsTwo(200), main="oce.colorsTwo")
image(x, col=oce.colorsJet(200), main="oce.colorsJet")
image(x, col=oce.colorsGebco(200), main="oce.colorsGebco")
image(x, col=oce.colorsPalette(200), main="oce.colorsPalette")
image(x, col=oce.colorsViridis(200), main="oce.colorsViridis")
# 4. Kristen M Thyng's 'cmocean' colours, specialised for oceanography.
par(mfrow=c(3, 4), mar=c(1, 3, 3, 1))
image(x, col=oce.colorsCDOM(200), main="oce.colorsCDOM")
image(x, col=oce.colorsChlorophyll(200), main="oce.colorsChlorophyll")
image(x, col=oce.colorsDensity(200), main="oce.colorsDensity")
image(x, col=oce.colorsFreesurface(200), main="oce.colorsFreesurface")
image(x, col=oce.colorsOxygen(200), main="oce.colorsOxygen")
image(x, col=oce.colorsPAR(200), main="oce.colorsPAR")
image(x, col=oce.colorsPhase(200), main="oce.colorsPhase")
image(x, col=oce.colorsSalinity(200), main="oce.colorsSalinity")
image(x, col=oce.colorsTemperature(200), main="oce.colorsTemperature")
image(x, col=oce.colorsTurbidity(200), main="oce.colorsTurbidity")
image(x, col=oce.colorsVelocity(200), main="oce.colorsVelocity")
image(x, col=oce.colorsVorticity(200), main="oce.colorsVorticity")
# 3. Acoustic-Doppler profiler data; note that plot,adp-method() puts makes
# zlim be symmetric about zero velocity.
par(mfrow=c(1, 1))
data(adp)
plot(adp, which='u1')
# 4. Contrast Jet with Viridis, using standard Volcano dataset;
# try printing the results in black and white.
par(mfrow=c(2, 1))
imagep(volcano, col=oce.colorsJet)
imagep(volcano, col=oce.colorsViridis)
```

oce.contour

Oce Variant of contour

# **Description**

This provides something analagous to contour, but with the ability to flip x and y. Setting revy=TRUE can be helpful if the y data represent pressure or depth below the surface.

oce.contour

## Usage

```
oce.contour(x, y, z, revx = FALSE, revy = FALSE, add = FALSE, tformat,
  drawTimeRange = getOption("oceDrawTimeRange"),
  debug = getOption("oceDebug"), ...)
```

## **Arguments**

x	values for x grid.
У	values for y grid.
Z	matrix for values to be contoured. The first dimension of $z$ must equal the number of items in $x$ , etc.
revx	set to TRUE to reverse the order in which the labels on the x axis are drawn
revy	set to TRUE to reverse the order in which the labels on the y axis are drawn
add	logical value indicating whether the contours should be added to a pre-existing plot.
tformat	time format; if not supplied, a reasonable choice will be made by oce.axis.POSIXct, which draws time axes.
drawTimeRange	logical, only used if the x axis is a time. If TRUE, then an indication of the time range of the data (not the axis) is indicated at the top-left margin of the graph. This is useful because the labels on time axes only indicate hours if the range is less than a day, etc.
debug	a flag that turns on debugging; set to 1 to information about the processing.

### Author(s)

. . .

Dan Kelley

## **Examples**

```
library(oce)
data(topoWorld)
## coastline now, and in last glacial maximum
lon <- topoWorld[["longitude"]]
lat <- topoWorld[["latitude"]]
z <- topoWorld[["z"]]
oce.contour(lon, lat, z, levels=0, drawlabels=FALSE)
oce.contour(lon, lat, z, levels=-130, drawlabels=FALSE, col='blue', add=TRUE)</pre>
```

optional arguments passed to plotting functions.

oce.grid 233

### Description

Add a Grid to an Existing Oce Plot

### Usage

```
oce.grid(xat, yat, col = "lightgray", lty = "dotted", lwd = par("lwd"))
```

### Arguments

xat	either a list of x values at which to draw the grid, or the return value from an oce plotting function
yat	a list of y values at which to plot the grid (ignored if gx was a return value from an oce plotting function)
col	colour of grid lines (see par)
lty	type for grid lines (see par)
lwd	width for grid lines (see par)

### **Details**

For plots not created by oce functions, or for missing xat and yat, this is the same as a call to grid with missing nx and ny. However, if xat is the return value from certain oce functions, a more sophisticated grid is constructed. The problem with grid is that it cannot handle axes with non-uniform grids, e.g. those with time axes that span months of differing lengths.

As of early February 2015, oce.grid handles xat produced as the return value from the following functions: imagep and oce.plot.ts, plot,adp-method, plot,echosounder-method, and plotTS. It makes no sense to try to use oce.grid for multipanel oce plots, e.g. the default plot from plot,adp-method.

```
library(oce)
i <- imagep(volcano)
oce.grid(i, lwd=2)

data(sealevel)
i <- oce.plot.ts(sealevel[["time"]], sealevel[["elevation"]])
oce.grid(i, col='red')

data(ctd)
i <- plotTS(ctd)
oce.grid(i, col='red')

data(adp)</pre>
```

234 oce.plot.ts

```
i <- plot(adp, which=1)
oce.grid(i, col='gray', lty=1)

data(echosounder)
i <- plot(echosounder)
oce.grid(i, col='pink', lty=1)</pre>
```

oce.plot.ts

Oce Variant of plot.ts

## **Description**

Plot a time-series, obeying the timezone and possibly drawing the range in the top-left margin.

# Usage

```
oce.plot.ts(x, y, type = "1", xlim, ylim, xlab, ylab, drawTimeRange,
  fill = FALSE, xaxs = par("xaxs"), yaxs = par("yaxs"),
  cex = par("cex"), cex.axis = par("cex.axis"),
  cex.main = par("cex.main"), mgp = getOption("oceMgp"), mar = c(mgp[1] +
  if (nchar(xlab) > 0) 1.5 else 1, mgp[1] + 1.5, mgp[2] + 1, mgp[2] + 3/4),
  main = "", despike = FALSE, axes = TRUE, tformat,
  marginsAsImage = FALSE, grid = FALSE, grid.col = "darkgray",
  grid.lty = "dotted", grid.lwd = 1, debug = getOption("oceDebug"), ...)
```

# Arguments

x	the times of observations.
у	the observations.
type	plot type, "1" for lines, "p" for points.
xlim	optional limit for x axis. This has an additional effect, beyond that for conventional R functions: it effectively windows the data, so that autoscaling will yield limits for y that make sense within the window.
ylim	optional limit for y axis.
xlab	name for x axis; defaults to "".
ylab	name for y axis; defaults to the plotted item.
drawTimeRange	an optional indication of whether/how to draw a time range, in the top-left margin of the plot; see oce.axis.POSIXct for details.
fill	boolean, set TRUE to fill the curve to zero (which it does incorrectly if there are missing values in y).
xaxs	control x axis ending; see par("xaxs").
yaxs	control y axis ending; see par("yaxs").
cex	size of labels on axes; see par("cex").

oce.plot.ts 235

cex.axis see par("cex.axis").
cex.main see par("cex.main").

mgp 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar value to be used with par("mar") to set margins. The default value uses sig-

nificantly tighter margins than is the norm in R, which gives more space for the data. However, in doing this, the existing par("mar") value is ignored, which contradicts values that may have been set by a previous call to drawPalette. To get plot with a palette, first call drawPalette, then call oce.plot.ts with

mar=par("mar").

main title of plot.

despike boolean flag that can turn on despiking with despike.

axes boolean, set to TRUE to get axes plotted tformat optional format for labels on the time axis

marginsAsImage boolean indicating whether to set the right-hand margin to the width normally

taken by an image drawn with imagep.

grid if TRUE, a grid will be drawn for each panel. (This argument is needed, because

calling grid after doing a sequence of plots will not result in useful results for

the individual panels.

grid.col colour of grid
grid.lty line type of grid
grid.lwd line width of grid

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... graphical parameters passed down to plot.

### **Details**

Depending on the version of R, the standard plot and plot.ts routines will not obey the time zone of the data. This routine gets around that problem. It can also plot the time range in the top-left margin, if desired; this string includes the timezone, to remove any possible confusion. The time axis is drawn with oce.axis.POSIXct.

### Value

A list is silently returned, containing xat and yat, values that can be used by oce.grid to add a grid to the plot.

# Author(s)

Dan Kelley

236 oce.write.table

### **Examples**

```
library(oce)
t0 <- as.POSIXct("2008-01-01", tz="UTC")
t <- seq(t0, length.out=48, by="30 min")
y <- sin(as.numeric(t - t0) * 2 * pi / (12 * 3600))
oce.plot.ts(t, y, type='l', xaxs='i')</pre>
```

oce.write.table

Write the Data Portion of Object to a File

## **Description**

The output has a line containing the names of the columns in x\$data, each enclosed in double quotes. After that line are lines for the data themselves. The default is to separate data items by a single space character, but this can be altered by using a sep argument in the ... list (see write.table).

### Usage

```
oce.write.table(x, file = "", ...)
```

#### **Arguments**

```
    an oce object that contains a data table.
    file file name, as passed to write.table. Use "" to get a listing in the terminal window.
    optional arguments passed to write.table.
```

#### **Details**

This function is little more than a thin wrapper around write.table, the only difference being that row names are omitted here, making for a file format that is more conventional in Oceanography.

# Value

The value of write. table is returned.

### Author(s)

Dan Kelley

### See Also

write.table, which does the actual work.

oceApprox 237

oceApprox

Interpolate 1D Data with UNESCO or Reiniger-Ross Algorithm

#### **Description**

Interpolate one-dimensional data using schemes that permit curvature but tends minimize extrema that are not well-indicated by the data.

### Usage

```
oceApprox(x, y, xout, method = c("rr", "unesco"))
```

### Arguments

x the independent variable (z or p, usually).

y the dependent variable.

xout the values of the independent variable at which interpolation is to be done.

method method to use. See "Details".

#### **Details**

Setting method="rr" yields the weighted-parabola algorithm of Reiniger and Ross (1968). For procedure is as follows. First, the interpolant for any xout value that is outside the range of x is set to NA. Next, linear interpolation is used for any xout value that has only one smaller neighboring x value, or one larger neighboring value. For all other values of xout, the 4 neighboring points x are sought, two smaller and two larger. Then two parabolas are determined, one from the two smaller points plus the nearest larger point, and the other from the nearest smaller point and the two larger points. A weighted sum of these two parabolas provides the interpolated value. Note that, in the notation of Reiniger and Ross (1968), this algorithm uses m=2 and n=1. (A future version of this routine might provide the ability to modify these values.)

Setting method="unesco" yields the method that is used by the U.S. National Oceanographic Data Center. It is described in pages 48-50 of reference 2; reference 3 presumably contains the same information but it is not as easily accessible. The method works as follows.

- If there are data above 5m depth, then the surface value is taken to equal to the shallowest recorded value.
- Distance bounds are put on the four neighboring points, and the Reiniger-Ross method is used for interpolated points with sufficiently four close neighbors. The bounds are described in table 15 of reference 2 only for so-called standard depths; in the present instance they are transformed to the following rules. Inner neighbors must be within 5m for data above 10m, 50m above 250m 100m above 900m, 200m above 2000m, or within 1000m otherwise. Outer neighbors must be within 200m above 500m, 400m above 1300m, or 1000m otherwise. If two or more points meet these criteria, Lagrangian interpolation is used. If not, NA is used as the interpolant.

After these rules are applied, the interpolated value is compared with the values immediately above and below it, and if it is outside the range, simple linear interpolation is used.

238 oceConvolve

#### Value

A vector of interpolated values, corresponding to the xout values and equal in number.

#### Author(s)

Dan Kelley

#### References

- 1. R.F. Reiniger and C.K. Ross, 1968. A method of interpolation with application to oceanographic data. *Deep Sea Research*, **15**, 185-193.
- Daphne R. Johnson, Tim P. Boyer, Hernan E. Garcia, Ricardo A. Locarnini, Olga K. Baranova, and Melissa M. Zweng, 2011. World Ocean Database 2009 Documentation. NODC Internal report 20. Ocean Climate Laboratory, National Oceanographic Data Center. Silver Spring, Maryland.
- 3. UNESCO, 1991. Processing of oceanographic station data, 138 pp., Imprimerie des Presses Universitaires de France, United Nations Educational, Scientific and Cultural Organization, France.

### **Examples**

```
library(oce)
if (require(ocedata)) {
    data(RRprofile)
    zz <- seq(0, 2000, 2)
    plot(RRprofile$temperature, RRprofile$depth, ylim=c(500, 0), xlim=c(2, 11))
    ## Contrast two methods
    a1 <- oce.approx(RRprofile$depth, RRprofile$temperature, zz, "rr")
    a2 <- oce.approx(RRprofile$depth, RRprofile$temperature, zz, "unesco")
    lines(a1, zz)
    lines(a2, zz, col='red')
    legend("bottomright",lwd=1,col=1:2, legend=c("rr","unesco"),cex=3/4)
}</pre>
```

oceConvolve

Convolve two time series

# Description

Convolve two time series, using a backward-looking method. This function provides a straightforward convolution, which may be useful to those who prefer not to use convolve and filter in the stats package.

#### Usage

```
oceConvolve(x, f, end = 2)
```

oceCRS 239

#### **Arguments**

x a numerical vector of observations.f a numerical vector of filter coefficients.

end a flag that controls how to handle the points of the x series that have indices less

than the length of f. If end=0, the values are set to 0. If end=1, the original x values are used there. If end=2, that fraction of the f values that overlap with x

are used.

#### Value

A vector of the convolution output.

### Author(s)

Dan Kelley

## **Examples**

```
library(oce)
t <- 0:1027
n <- length(t)
signal <- ifelse(sin(t * 2 * pi / 128) > 0, 1, 0)
tau <- 10
filter <- exp(-seq(5*tau, 0) / tau)
filter <- filter / sum(filter)
observation <- oce.convolve(signal, filter)
plot(t, signal, type='l')
lines(t, observation, lty='dotted')</pre>
```

oceCRS

Coordinate Reference System strings for some oceans

### **Description**

Create a coordinate reference string (CRS), suitable for use as a projection argument to mapPlot or plot, coastline-method.

## Usage

```
oceCRS(region)
```

## **Arguments**

region

character string indicating the region. This must be in the following list (or a string that matches to just one entry, with pmatch): "North Atlantic", "South Atlantic", "Atlantic", "North Pacific", "South Pacific", "Pacific", "Arctic", and "Antarctic".

240 oceDebug

#### Value

string contain a CRS, which can be used as projection in mapPlot.

### Caution

This is a preliminary version of this function, with the results being very likely to change through the autumn of 2016, guided by real-world usage.

### Author(s)

Dan Kelley

### See Also

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, shiftLongitude, usrLonLat, utm2lonlat

### **Examples**

```
## Not run:
library(oce)
data(coastlineWorld)
par(mar=c(2, 2, 1, 1))
plot(coastlineWorld, proj=oceCRS("Atlantic"), span=12000)
plot(coastlineWorld, proj=oceCRS("North Atlantic"), span=8000)
plot(coastlineWorld, proj=oceCRS("South Atlantic"), span=8000)
plot(coastlineWorld, proj=oceCRS("Arctic"), span=4000)
plot(coastlineWorld, proj=oceCRS("Antarctic"), span=10000)
# Avoid ugly horizontal lines, an artifact of longitude shifting.
# Note: we cannot fill the land once we shift, either.
pacific <- coastlineCut(coastlineWorld, -180)</pre>
plot(pacific, proj=oceCRS("Pacific"), span=15000, col=NULL)
plot(pacific, proj=oceCRS("North Pacific"), span=12000, col=NULL)
plot(pacific, proj=oceCRS("South Pacific"), span=12000, col=NULL)
## End(Not run)
```

oceDebug

Print a debugging message

## **Description**

Print an indented debugging message. Many oce functions decrease the debug level by 1 when they call other functions, so the effect is a nesting, with more space for deeper function level.

oceDeleteData 241

### **Usage**

```
oceDebug(debug = 0, ..., unindent = 0)
```

## **Arguments**

debug an integer, less than or equal to zero for no message, and greater than zero for

increasing levels of debugging. Values greater than 4 are treated like 4.

... items to be supplied to cat, which does the printing. Almost always, this should

include a trailing newline.

unindent Number of levels to un-indent, e.g. for start and end lines from a called function.

#### Author(s)

Dan Kelley

## **Examples**

```
foo <- function(debug)
{
   oceDebug(debug, "in function foo\n")
}
debug <- 1
oceDebug(debug, "in main")
foo(debug=debug-1)</pre>
```

oceDeleteData

Delete data from an oce object

# **Description**

Return a copy of the supplied object that lacks the named element in its data slot, and that has a note about the deletion in its processing log.

# Usage

```
oceDeleteData(object, name)
```

# **Arguments**

object an oce object

name String indicating the name of the item to be deleted.

242 oceEdit

	tadata from an oce object	Delete m	oceDeleteMetadata
--	---------------------------	----------	-------------------

# Description

Return a copy of the supplied object that lacks the named element in its metadata slot, and that has a note about the deletion in its processing log.

# Usage

```
oceDeleteMetadata(object, name)
```

# Arguments

object an oce object

name String indicating the name of the item to be deleted.

oceEdit Edit an Oce Object

## **Description**

Edit an element of an oce object, inserting a note in the processing log of the returned object.

# Usage

```
oceEdit(x, item, value, action, reason = "", person = "",
  debug = getOption("oceDebug"))
```

## **Arguments**

X	an oce object. The exact action of oceEdit depends on the class of $x$ .
item	if supplied, a character string naming an item in the object's metadata or data slot, the former being checked first. An exception is if item starts with "data@" or "metadata@", in which case the named slot is updated with a changed value of the contents of item after the @ character.
value	new value for item, if both supplied.
action	optional character string containing R code to carry out some action on the object.
reason	character string giving the reason for the change.
person	character string giving the name of person making the change.
debug	an integer that specifies a level of debugging, with 0 or less indicating no debugging, and 1 or more indicating debugging.

oceFilter 243

#### **Details**

There are several ways to use this function.

• Case 1. If both an item and value are supplied, then either the object's metadata or data slot may be altered. There are two ways in which this can be done.

- Case 1A. If the item string does not contain an @ character, then the metadata slot is examined for an entry named item, and that is modified if so. Alternatively, if item is found in metadata, then that value is modified. However, if item is not found in either metadata or data, then an error is reported (see 1B for how to add something that does not yet exist).
- Case 1B. If the item string contains the @ character, then the text to the left of that character must be either "metadata" or "data", and it names the slot in which the change is done. In contrast with case 1A, this will *create* a new item, if it is not already in existence.
- Case 2. If item and value are not supplied, then action must be supplied. This is a character string specifying some action to be performed on the object, e.g. a manipulation of a column. The action must refer to the object as x; see Examples.

In any case, a log entry is stored in the object, to document the change. Indeed, this is the main benefit to using this function, instead of altering the object directly. The log entry will be most useful if it contains a brief note on the reason for the change, and the name of the person doing the work.

#### Value

An object of class "oce", altered appropriately, and with a log item indicating the nature of the alteration.

### Author(s)

Dan Kelley

#### **Examples**

oceFilter

Filter a time-series

## Description

Filter a time-series, possibly recursively

244 oceFilter

#### Usage

```
oceFilter(x, a = 1, b, zero.phase = FALSE)
```

### **Arguments**

x a vector of numeric values, to be filtered as a time series.

a a vector of numeric values, giving the a coefficients (see "Details").

b a vector of numeric values, giving the b coefficients (see "Details").

zero.phase boolean, set to TRUE to run the filter forwards, and then backwards, thus remov-

ing any phase shifts associated with the filter.

#### **Details**

The filter is defined as e.g. y[i] = b[1] \* x[i] + b[2] \* x[i-1] + b[3] \* x[i-2] + ... - a[2] \* y[i-1] - a[3] \* y[i-2] - a[4] \* y[i-3] - ..., where some of the illustrated terms will be omitted if the lengths of a and b are too small, and terms are dropped at the start of the time series where the index on x would be less than 1.

By contrast with the filter function of R, oce.filter lacks the option to do a circular filter. As a consequence, oce.filter introduces a phase lag. One way to remove this lag is to run the filter forwards and then backwards, as in the "Examples". However, the result is still problematic, in the sense that applying it in the reverse order would yield a different result. (Matlab's filtfilt shares this problem.)

### Value

A numeric vector of the filtered results, y, as denoted in "Details".

#### Note

The first value in the a vector is ignored, and if length(a) equals 1, a non-recursive filter results.

#### Author(s)

Dan Kelley

```
library(oce)
par(mar=c(4, 4, 1, 1))
b <- rep(1, 5)/5
a <- 1
x <- seq(0, 10)
y <- ifelse(x == 5, 1, 0)
f1 <- oce.filter(y, a, b)
plot(x, y, ylim=c(-0, 1.5), pch="o", type='b')
points(x, f1, pch="x", col="red")
# remove the phase lag</pre>
```

oceGetData 245

oceGetData

Get data from an oce object

### **Description**

In contrast to the various [[ functions, this is guaranteed to look only within the data slot. If the named item is not found, NULL is returned.

# Usage

```
oceGetData(object, name)
```

## Arguments

object an oce object

name String indicating the name of the item to be found.

oceGetMetadata

Get metadata element from an oce object

# Description

In contrast to the various [[ functions, this is guaranteed to look only within the metadata slot. If the named item is not found, NULL is returned.

# Usage

```
oceGetMetadata(object, name)
```

# Arguments

object an oce object

name String indicating the name of the item to be found.

246 oceMagic

oceMagic

Find the Type of an Oceanographic Data File

### **Description**

oceMagic tries to infer the file type, based on the data within the file, the file name, or a combination of the two.

### Usage

```
oceMagic(file, debug = getOption("oceDebug"))
```

# **Arguments**

file a connection or a character string giving the name of the file to be checked.

debug an integer, set non-zero to turn on debugging. Higher values indicate more de-

bugging.

#### **Details**

oceMagic was previously called oce.magic, but that alias will be removed towards the end of the year 2016; see oce-deprecated.

### Value

A character string indicating the file type, or "unknown", if the type cannot be determined. If the result contains "/" characters, these separate a list describing the file type, with the first element being the general type, the second element being the manufacturer, and the third element being the manufacturer's name for the instrument. For example, "adp/nortek/aquadopp" indicates a acoustic-doppler profiler made by NorTek, of the model type called AquaDopp.

## Author(s)

Dan Kelley

### See Also

This is used mainly by read.oce.

oceNames2whpNames

Translate Oce Data Names to WHP Data Names

### **Description**

Translate oce-style names to WOCE names, using gsub to match patterns. For example, the pattern "oxygen" is taken to mean "CTDOXY".

### Usage

oceNames2whpNames(names)

#### **Arguments**

names

vector of strings holding oce-style names.

#### Value

vector of strings holding WHP-style names.

### Author(s)

Dan Kelley

### References

Several online sources list WHP names. An example is  $https://geo.h2o.ucsd.edu/documentation/manuals/pdf/90_1/chap4.pdf$ 

### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other functions that interpret variable names and units from headers: ODFNames2oceNames, cnvName2oceName, oceUnits2whpUnits, unitFromStringRsk, unitFromString, woceNames2oceNames, woceUnit2oceUnit

248 ocePmatch

ocePmatch	Partial matching of strings or numbers

## **Description**

An extended version of pmatch that allows x to be numeric or string-based. As with pmatch, partial string matches are handled. This is a wrapper that is useful mainly for which arguments to plotting functions.

## Usage

```
ocePmatch(x, table, nomatch = NA_integer_, duplicates.ok = FALSE)
```

# Arguments

X	a code, or vector of codes. This may be numeric, in which case it is simply returned without further analysis of the other arguments, or it may be string-based, in which case pmatch is used to find numeric matches.	
table	a list that maps strings to numbers; pmatch is used on names(table). If the name contains characters that are normally not permitted in a variable name, use quotes, e.g. list(salinity=1, temperature=2, "salinity+temperature"=3).	
nomatch	value to be returned for cases of no match (passed to pmatch.	
duplicates.ok	code for the handling of duplicates (passed to pmatch).	

# Value

A number, or vector of numbers, corresponding to the matches. Non-matches are indicated with NA values, or whatever value is given by the NA argument.

# Author(s)

Dan Kelley

### See Also

Since pmatch is used for the actual matching, its documentation should be consulted.

```
library(oce)
oce.pmatch(c("s", "at", "te"), list(salinity=1, temperature=3.1))
```

oceSetData 249

oceSetData	Set something in the data slot of an oce object

#### **Description**

Set something in the data slot of an oce object

### Usage

```
oceSetData(object, name, value, unit, originalName, note = "")
```

#### **Arguments**

object an oce object

name String indicating the name of the item to be set.

value Value for the item.

unit An optional indication of the units for the item. This has three possible forms

(see "Details").

originalName Optional character string giving an 'original' name (e.g. as stored in the header

of a data file).

note A note to be stored in the processing log. If an empty string (the default) then

an entry will be constructed from the function call. If NULL, then no entry will

be added to the processing log.

#### **Details**

There are three possibilities for unit:

- Case 1. unit is a named or unnamed list that contains two items. If the list is named, the names must be unit and scale. If the list is unnamed, the stated names are assigned to the items, in the stated order. Either way, the unit item must be an expression that specifies the unit, and the scale item must be a string that describes the scale. For example, modern temperatures have unit=list(unit=expression(degree\*C), scale="ITS-90").
- Case 2. unit is an expression giving the unit as above. In this case, the scale will be set to "".
- Case 3. unit is a character string that is converted into an expression with parse(text=unit), and the scale set to "".

```
data(ctd)
Tf <- swTFreeze(ctd)
ctd <- oceSetData(ctd, "freezing", Tf, list(unit=expression(degree*C), scale="ITS-90"))
feet <- swDepth(ctd) / 0.3048
ctd <- oceSetData(ctd, name="depthInFeet", value=feet, expression("feet"))
fathoms <- feet / 6
ctd <- oceSetData(ctd, "depthInFathoms", fathoms, "fathoms")</pre>
```

250 oceSmooth

oceSetMetadata	Set someth

Set something in the metadata slot of an oce object

# Description

Set something in the metadata slot of an oce object

# Usage

```
oceSetMetadata(object, name, value, note = "")
```

### **Arguments**

object an oce object

name String indicating the name of the item to be set.

value Value for the item.

note A note to be stored in the processing log.

oceSmooth Smooth an Oce Object

# Description

Each data element is smoothed as a timeseries. For ADP data, this is done along time, not distance. Time vectors, if any, are not smoothed. A good use of oce. smooth is for despiking noisy data.

## Usage

```
oceSmooth(x, ...)
```

### **Arguments**

x an oce object.

... parameters to be supplied to smooth, which does the actual work.

#### Value

An object of class "oce" that has been smoothed appropriately.

# Author(s)

Dan Kelley

oceSpectrum 251

### See Also

The work is done with smooth, and the . . . arguments are handed to it directly by oce.smooth.

### **Examples**

```
library(oce)
data(ctd)
d <- oce.smooth(ctd)
plot(d)</pre>
```

oceSpectrum

Wrapper to give normalized spectrum

# Description

This is a wrapper around the R spectrum function, which returns spectral values that are adjusted so that the integral of those values equals the variance of the input x.

# Usage

```
oceSpectrum(x, ...)
```

# Arguments

x As for spectrum, a univariate or multivariate time series.

... extra arguments passed on to spectrum.

### Value

A spectrum that has values that integrate to the variance.

### Author(s)

Dan Kelley

### See Also

spectrum.

```
x <- rnorm(1e3)
s <- spectrum(x, plot=FALSE)
ss <- oce.spectrum(x, plot=FALSE)
cat("variance of x=", var(x), "\n")
cat("integral of spectrum=", sum(s$spec)*diff(s$freq[1:2]), "\n")
cat("integral of oce.spectrum=", sum(ss$spec)*diff(ss$freq[1:2]), "\n")</pre>
```

252 oceUnits2whpUnits

oceUnits2whpUnits

Translate oce unit to WHP unit

### **Description**

Translate oce units to WHP-style strings, to match patterns. For example, the pattern "oxygen" is taken to mean "CTDOXY".

### Usage

```
oceUnits2whpUnits(units, scales)
```

# **Arguments**

units vector of expressions for units in oce notation.
scales vector of strings for scales in oce notation.

#### Value

vector of strings holding WOCE-style names.

# Author(s)

Dan Kelley

### References

Several online sources list WOCE names. An example is  $https://geo.h2o.ucsd.edu/documentation/manuals/pdf/90_1/chap4.pdf$ 

#### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other functions that interpret variable names and units from headers: ODFNames2oceNames, cnvName2oceName, oceNames2whpNames, unitFromStringRsk, unitFromString, woceNames2oceNames, woceUnit2oceUnit

odf-class 253

odf-class

Class to Store ODF data

#### **Description**

Class for data stored in a format used at Canadian Department of Fisheries and Oceans laboratories. This is somewhat unusual amongst oce classes, in that it does not map to a particular instrument, but rather to a storage type; in that sense, it is similar to the bremen-class.

### Methods

Consider an ODF object named odf.

Accessing metadata.

Metadata (contained in the S4 slot named metadata) may be retrieved or set by name, odf[["longitude"]] <- odf[["long corrects a one-degree error.

Accessing measured data.

Column data may be accessed by name, e.g. odf[["salinity"]], odf[["temperature"]], odf[["pressure"]], etc. It is up to the user to realize what is in the object.

Assigning values.

Items stored in the object may be altered with e.g. odf[["salinity"]] <- rep(35,10).

Overview of contents.

The show method (e.g. show(odf)) displays information about the object.

# Author(s)

Dan Kelley

# See Also

```
Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, [[<-,odf-method, plot,odf-method, read.ctd.odf, read.odf, subset,odf-method, summary,odf-method
```

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, rsk-class, sealevel-class, section-class, topo-class, windrose-class

ODF2oce

ODF2oce Create ODF object from the output of OD	DF::read_ODF()
---	----------------

## **Description**

As of August 11, 2015, ODF::read\_ODF returns a list with 9 elements, one named DATA, which is a data.frame containing the columnar data, the others being headers of various sorts. The present function constructs an oce object from such data, facilitating processing and plotting with the general oce functions. This involves storing the 8 headers verbatim in the odfHeaders in the metadata slot, and also copying some of the header information into more standard names (e.g. metadata@longitude is a copy of metadata@odfHeader\$EVENT\_HEADER\$INITIAL\_LATITUDE). As for the DATA, they are stored in the data slot, after renaming from ODF to oce convention using ODFNames2oceNames.

### Usage

```
ODF2oce(ODF, coerce = TRUE, debug = getOption("oceDebug"))
```

### Arguments

ODF A list as returned by read\_ODF in the ODF package

coerce A logical value indicating whether to coerce the return value to an appropriate

object type, if possible.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

#### Value

An oce object, possibly coerced to a subtype.

## Caution

This function may change as the ODF package changes. Since ODF has not been released yet, this should not affect any users except those involved in the development of oce and ODF.

## Author(s)

Dan Kelley

#### See Also

Other things related to odf data: ODFNames2oceNames, [[,odf-method, [[<-,odf-method, odf-class, plot,odf-method, read.ctd.odf, read.odf, subset,odf-method, summary,odf-method

ODFNames2oceNames 255

ODFNames2oceNames Translate from ODF Names to Oce Names	
---	--

## Description

Translate data names in the ODF convention to similar names in the Oce convention.

## Usage

```
ODFNames2oceNames(ODFnames, ODFunits = NULL, columns = NULL,
    PARAMETER_HEADER = NULL, debug = getOption("oceDebug"))
```

# **Arguments**

ODF names Vector of strings holding ODF names.

ODF units Vector of strings holding ODF units.

columns Optional list containing name correspondances, as described for read.ctd.odf.

PARAMETER\_HEADER

Optional list containing information on the data variables.

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

#### **Details**

The following table gives the regular expressions that define recognized ODF names, along with the translated names as used in oce objects. If an item is repeated, then the second one has a 2 appended at the end, etc. Note that quality-control columns (with names starting with "QQQQ") are not handled with regular expressions. Instead, if such a flag is found in the i-th column, then a name is constructed by taking the name of the (i-1)-th column and appending "Flag".

Regexp	Result	Notes
ALTB_*.*	altimeter	
BATH_*.*	barometricDepth	Barometric depth (of sensor? of water column?)
BEAM_*.*	a	Used in adp objects
CNTR_*.*	scan	Used in ctd objects
CRAT_*.*	conductivity	Conductivity ratio
COND_*.*	conductivity	Conductivity in mS/cm or S/m (unit detected)
CNDC_*.*	conductivity	Conductivity in mS/cm or S/m (unit detected)
DEPH_*.*	pressure	Sensor depth below sea level
DOXY_*.*	oxygen	Used mainly in ctd objects
ERRV_*.*	error	Used in adp objects
EWCT_*.*	u	Used in adp and cm objects

256 ODFNames2oceNames

FFFF_*.*	flagArchaic	Old flag name, replaced by QCFF
FLOR_*.*	fluorometer	Used mainly in ctd objects
FWETLABS	fwetlabs	Used in ??
HCDM	directionMagnetic	
HCDT	directionTrue	
HCSP	speedHorizontal	
LATD_*.*	latitude	
LOND_*.*	longitude	
NSCT_*.*	V	Used in adp objects
OCUR_*.*	oxygenCurrent	Used mainly in ctd objects
OSAT_*.*	oxygenSaturation	Used mainly in ctd objects
OTMP_*.*	oxygenTemperature	Used mainly in ctd objects
0XYV_*.*	oxygenVoltage	Used mainly in ctd objects
PHPH_*.*	рН	
POTM_*.*	theta	Used mainly in ctd objects
PRES_*.*	pressure	Used mainly in ctd objects
PSAL_*.*	salinity	Used mainly in ctd objects
PSAR_*.*	par	Used mainly in ctd objects
QCFF_*.*	flag	Overall flag
SIGP_*.*	sigmaTheta	Used mainly in ctd objects
SIGT_*.*	sigmat	Used mainly in ctd objects
SNCN_*.*	scanCounter	Used mainly in ctd objects
SYTM_*.*	time	Used in many objects
TE90_*.*	temperature	Used mainly in ctd objects
TEMP_*.*	temperature	Used mainly in ctd objects
TOTP_*.*	pressureAbsolute	Used mainly in ctd objects
UNKN_*.*	-	The result is context-dependent
VCSP_*.*	W	Used in adp objects

Any code not shown in the list is transferred to the oce object without renaming, apart from the adjustment of suffix numbers. The following code have been seen in data files from the Bedford Institute of Oceanography: ALTB, PHPH and QCFF.

### Value

A vector of strings.

### A note on unit conventions

Some older ODF files contain non-standard units for conductivity, including mho/m, mmho/cm, and mmHo. As the units for conductivity are important for derived quantities (e.g. salinity), such units are converted to standard units (e.g. S/m and mS/cm), with a warning.

# **Consistency warning**

There are disagreements on variable names. For example, the "DFO Common Data Dictionary" [1] has unit millmole/m^3 for NODC and MEDS, but it has unit mL/L for BIO and IML.

parseLatLon 257

## Author(s)

Dan Kelley

#### References

1. The Department of Fisheries and Oceans Common Data Dictionary may be available at http://www.isdm.gc.ca/isdm-g although that link seems to be unreliable. As of September 2017, the link https://slgo.ca/app-sgdo/en/docs\_reference/format\_odf.html seems to be a good place to start.

#### See Also

Other functions that interpret variable names and units from headers: cnvName2oceName, oceNames2whpNames, oceUnits2whpUnits, unitFromStringRsk, unitFromString, woceNames2oceNames, woceUnit2oceUnit

Other things related to odf data: ODF2oce, [[, odf-method, [[<-, odf-method, odf-class, plot, odf-method, read.odf, read.odf, subset, odf-method, summary, odf-method

parseLatLon

Parse a Latitude or Longitude String

## **Description**

Parse a latitude or longitude string, e.g. as in the header of a CTD file The following formats are understood (for, e.g. latitude)

```
*
NMEA Latitude = 47 54.760 N ** Latitude: 47 53.27 N
```

# Usage

```
parseLatLon(line, debug = getOption("oceDebug"))
```

## **Arguments**

line a character string containing an indication of latitude or longitude.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

## Value

A numerical value of latitude or longitude.

## Author(s)

Dan Kelley

### See Also

Used by read.ctd.

plot,adp-method

Plot ADP Data

# **Description**

Create a summary plot of data measured by an acoustic doppler profiler.

# Usage

```
## S4 method for signature 'adp'
plot(x, which = 1:dim(x@data$v)[3], mode = c("normal",
   "diagnostic"), col, breaks, zlim, titles, lwd = par("lwd"), type = "l",
   ytype = c("profile", "distance"),
   drawTimeRange = getOption("oceDrawTimeRange"), useSmoothScatter,
   missingColor = "gray", mgp = getOption("oceMgp"), mar = c(mgp[1] + 1.5,
   mgp[1] + 1.5, 1.5, 1.5), mai.palette = rep(0, 4), tformat,
   marginsAsImage = FALSE, cex = par("cex"), cex.axis = par("cex.axis"),
   cex.main = par("cex.main"), xlim, ylim, control, useLayout = FALSE,
   coastline = "coastlineWorld", span = 300, main = "", grid = FALSE,
   grid.col = "darkgray", grid.lty = "dotted", grid.lwd = 1,
   debug = getOption("oceDebug"), ...)
```

#### **Arguments**

mode

col

x An adp object, i.e. one inheriting from adp-class.

which list of desired plot types. These are graphed in panels running down from the

top of the page. See "Details" for the meanings of various values of which.

top of the page. See Details for the meanings of various various

a string indicating whether to plot the conventional signal (normal) or or, in the special case of Aquadopp single-bin profilers, possibly the diagnostic signal. This argument is ignored except in the case of Aquadopp instruments. Perhaps a third option will become available in the future, for the burst mode that some

instruments provide.

optional indication of colour(s) to use. If not provided, the default for images is

oce.colorsPalette(128,1), and for lines and points is black.

breaks optional breaks for colour scheme

zlim a range to be used as the zlim parameter to the imagep call that is used to create the image. If omitted, zlim is set for each panel individually, to encompass the

data of the panel and to be centred around zero. If provided as a two-element vector, then that is used for each panel. If provided as a two-column matrix, then each panel of the graph uses the corresponding row of the matrix; for example, setting zlim=rbind(c(-1,1),c(-1,1),c(-.1,.1)) might make sense for which=1:3, so that the two horizontal velocities have one scale, and the

smaller vertical velocity has another.

titles optional vector of character strings to be used as labels for the plot panels. For

images, these strings will be placed in the right hand side of the top margin. For timeseries, these strings are ignored. If this is provided, its length must equal

that of which.

lwd if the plot is of a time-series or scattergraph format with lines, this is used in the

usual way; otherwise, e.g. for image formats, this is ignored.

type if the plot is of a time-series or scattergraph format, this is used in the usual way,

e.g. "1" for lines, etc.; otherwise, as for image formats, this is ignored.

ytype character string controlling the type of the y axis for images (ignored for time

series). If "distance", then the y axis will be distance from the sensor head, with smaller distances nearer the bottom of the graph. If "profile", then this will still be true for upward-looking instruments, but the y axis will be flipped for downward-looking instruments, so that in either case, the top of the graph

will represent the sample nearest the sea surface.

drawTimeRange boolean that applies to panels with time as the horizontal axis, indicating whether

to draw the time range in the top-left margin of the plot.

useSmoothScatter

boolean that indicates whether to use smoothScatter in various plots, such as which="uv". If not provided a default is used, with smoothScatter being used

if there are more than 2000 points to plot.

missingColor colour used to indicate NA values in images (see imagep); set to NULL to avoid

this indication.

mgp A 3-element numerical vector used with par("mgp") to control the spacing of

axis elements. The default is tighter than the R default.

mar A 4-element numerical vector used with par ("mar") to control the plot margins.

The default is tighter than the R default.

mai.palette margins, in inches, to be added to those calculated for the palette; alter from the

default only with caution

tformat optional argument passed to oce.plot.ts, for plot types that call that function.

(See strptime for the format used.)

marginsAsImage boolean, TRUE to put a wide margin to the right of time-series plots, even if there

are no images in the which list. (The margin is made wide if there are some

images in the sequence.)

cex size of labels on axes; see par("cex").

cex.axis see par("cex.axis").
cex.main see par("cex.main").

xlim optional 2-element list for xlim, or 2-column matrix, in which case the rows are

used, in order, for the panels of the graph.

ylim optional 2-element list for ylim, or 2-column matrix, in which case the rows are

used, in order, for the panels of the graph.

control optional list of parameters that may be used for different plot types. Possibilities

are drawBottom (a boolean that indicates whether to draw the bottom) and bin (a numeric giving the index of the bin on which to act, as explained in "Details").

useLayout set to FALSE to prevent using layout to set up the plot. This is needed if the call

is to be part of a sequence set up by e.g. par(mfrow).

coastline a coastline object, or a character string naming one. This is used only for

which="map". See notes at plot, ctd-method for more information on built-in

coastlines.

span approximate span of map in km

main main title for plot, used just on the top panel, if there are several panels.

grid if TRUE, a grid will be drawn for each panel. (This argument is needed, because

calling grid after doing a sequence of plots will not result in useful results for

the individual panels.

grid.col colour of grid
grid.lty line type of grid
grid.lwd line width of grid

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

... optional arguments passed to plotting functions. For example, supplying despike=TRUE

will cause time-series panels to be de-spiked with despike. Another common action is to set the colour for missing values on image plots, with the argument missingColor (see imagep). Note that it is an error to give breaks in ..., if the formal argument zlim was also given, because they could contradict each other.

### **Details**

The plot may have one or more panels, with the content being controlled by the which argument.

- which=1:4 (or which="u1" to "u4") yield a distance-time image plot of a velocity component. If x is in beam coordinates (signalled by metadata\$oce.coordinate=="beam"), this will be the beam velocity, labelled b[1] etc. If x is in xyz coordinates (sometimes called frame coordinates, or ship coordinates), it will be the velocity component to the right of the frame or ship (labelled u etc). Finally, if x is in "enu" coordinates, the image will show the the eastward component (labelled east). If x is in "other" coordinates, it will be component corresponding to east, after rotation (labelled u\'). Note that the coordinate is set by read.adp, or by beamToXyzAdp, xyzToEnuAdp, or enuToOtherAdp.
- which=5:8 (or which="a1" to "a4") yield distance-time images of backscatter intensity of the respective beams. (For data derived from Teledyn-RDI instruments, this is the item called "echo intensity.")
- which=9:12 (or which="q1" to "q4") yield distance-time images of signal quality for the respective beams. (For RDI data derived from instruments, this is the item called "correlation magnitude.")
- which=60 or which="map" draw a map of location(s).

• which=70:73 (or which="g1" to "g4") yield distance-time images of percent-good for the respective beams. (For data derived from Teledyne-RDI instruments, which are the only instruments that yield this item, it is called "percent good.")

- which=80:83 (or which="vv", which="va", which="vq", and which="vg") yield distance-time images of the vertical beam fields for a 5 beam "SentinelV" ADCP from Teledyne RDI.
- which="vertical" yields a two panel distance-time image of vertical beam velocity and amplitude.
- which=13 (or which="salinity") yields a time-series plot of salinity.
- which=14 (or which="temperature") yields a time-series plot of temperature.
- which=15 (or which="pressure") yields a time-series plot of pressure.
- which=16 (or which="heading") yields a time-series plot of instrument heading.
- which=17 (or which="pitch") yields a time-series plot of instrument pitch.
- which=18 (or which="roll") yields a time-series plot of instrument roll.
- which=19 yields a time-series plot of distance-averaged velocity for beam 1, rightward velocity, eastward velocity, or rotated-eastward velocity, depending on the coordinate system.
- which=20 yields a time-series of distance-averaged velocity for beam 2, foreward velocity, northward velocity, or rotated-northward velocity, depending on the coordinate system.
- which=21 yields a time-series of distance-averaged velocity for beam 3, up-frame velocity, upward velocity, or rotated-upward velocity, depending on the coordinate system.
- which=22 yields a time-series of distance-averaged velocity for beam 4, for beam coordinates, or velocity estimate, for other coordinates. (This is ignored for 3-beam data.)
- which=23 yields a progressive-vector diagram in the horizontal plane, plotted with asp=1.
   Normally, the depth-averaged velocity components are used, but if the control list contains an item named bin, then the depth bin will be used (with an error resulting if the bin is out of range).
- which=24 yields a time-averaged profile of the first component of velocity (see which=19 for the meaning of the component, in various coordinate systems).
- which=25 as for 24, but the second component.
- which=26 as for 24, but the third component.
- which=27 as for 24, but the fourth component (if that makes sense, for the given instrument).
- which=28 or "uv" yields velocity plot in the horizontal plane, i.e. u[2] versus u[1]. If the number of data points is small, a scattergraph is used, but if it is large, smoothScatter is used.
- which=29 or "uv+ellipse" as the "uv" case, but with an added indication of the tidal ellipse, calculated from the eigen vectors of the covariance matrix.
- which=30 or "uv+ellipse+arrow" as the "uv+ellipse" case, but with an added arrow indicating the mean current.
- which=40 or "bottomRange" for average bottom range from all beams of the instrument.
- which=41 to 44 (or "bottomRange1" to "bottomRange4") for bottom range from beams 1 to 4.
- which=50 or "bottomVelocity" for average bottom velocity from all beams of the instrument.

• which=51 to 54 (or "bottomVelocity1" to "bottomVelocity4") for bottom velocity from beams 1 to 4.

- which=55 (or "heaving") for time-integrated, depth-averaged, vertical velocity, i.e. a time series of heaving.
- which=100 (or "soundSpeed") for a time series of sound speed.

In addition to the above, there are some groupings defined:

- which="velocity" equivalent to which=1:3 (velocity components)
- which="amplitude" equivalent to which=5:7 (backscatter intensity components)
- which="quality" equivalent to which=9:11 (quality components)
- which="hydrography" equivalent to which=14:15 (temperature and pressure)
- which="angles" equivalent to which=16:18 (heading, pitch and roll)

The colour scheme for image plots (which in 1:12) is provided by the col argument, which is passed to image to do the actual plotting. See "Examples" for some comparisons.

A common quick-look plot to assess mooring movement is to use which=15:18 (pressure being included to signal the tide, and tidal currents may dislodge a mooring or cause it to settle).

By default, plot, adp-method uses a zlim value for the image that is constructed to contain all the data, but to be symmetric about zero. This is done on a per-panel basis, and the scale is plotted at the top-right corner, along with the name of the variable being plotted. You may also supply zlim as one of the ... arguments, but be aware that a reasonable limit on horizontal velocity components is unlikely to be of much use for the vertical component.

A good first step in the analysis of measurements made from a moored device (stored in d, say) is to do plot(d, which=14:18). This shows time series of water properties and sensor orientation, which is helpful in deciding which data to trim at the start and end of the deployment, because they were measured on the dock or on the ship as it travelled to the mooring site.

#### Value

A list is silently returned, containing xat and yat, values that can be used by oce.grid to add a grid to the plot.

### Author(s)

Dan Kelley

### See Also

Other functions that plot oce data: plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method,plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,

enuToOtherAdp, enuToOther, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

### **Examples**

```
library(oce)
data(adp)
plot(adp, which=1:3)
plot(adp, which='temperature', tformat='%H:%M')
```

plot,adv-method

Plot ADV data

### **Description**

Plot ADV data, i.e. stored in an adv-class object.

### Usage

```
## S4 method for signature 'adv'
plot(x, which = c(1:3, 14, 15), col, titles, type = "l",
  lwd = par("lwd"), drawTimeRange = getOption("oceDrawTimeRange"),
  drawZeroLine = FALSE, useSmoothScatter, mgp = getOption("oceMgp"),
  mar = c(mgp[1] + 1.5, mgp[1] + 1.5, 1.5, 1.5), tformat,
  marginsAsImage = FALSE, cex = par("cex"), cex.axis = par("cex.axis"),
  cex.main = par("cex.main"), xlim, ylim, brushCorrelation,
  colBrush = "red", main = "", debug = getOption("oceDebug"), ...)
```

#### **Arguments**

X	An adv object, i.e. one inheriting from adv-class.
which	List of desired plot types. These are graphed in panels running down from the top of the page. See "Details" for the meanings of various values of which.
col	Optional indication of colour(s) to use. If not provided, the default for images is oce.colorsPalette(128,1), and for lines and points is black.
titles	Optional vector of character strings to be used as labels for the plot panels. For images, these strings will be placed in the right hand side of the top margin. For timeseries, these strings are ignored. If this is provided, its length must equal that of which.
type	Type of plot, as for plot.
lwd	If the plot is of a time-series or scattergraph format with lines, this is used in the usual way; otherwise, e.g. for image formats, this is ignored.
drawTimeRange	Boolean that applies to panels with time as the horizontal axis, indicating whether to draw the time range in the top-left margin of the plot.

drawZeroLine Logical value indicating whether to draw zero lines on velocities. useSmoothScatter

Logical value indicating whether to use smoothScatter in various plots, such as which="uv". If not provided a default is used, with smoothScatter being used if there are more than 2000 points to plot.

3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar Value to be used with par("mar").

tformat Optional argument passed to oce.plot.ts, for plot types that call that function.

(See strptime for the format used.)

marginsAsImage Logical value indicating whether to put a wide margin to the right of time-series

plots, matching the space used up by a palette in an imagep plot.

cex Size of labels on axes; see par("cex").

cex.axis See par("cex.axis").
cex.main See par("cex.main").

xlim Optional 2-element list for xlim, or 2-column matrix, in which case the rows are

used, in order, for the panels of the graph.

ylim Optional 2-element list for ylim, or 2-column matrix, in which case the rows are

used, in order, for the panels of the graph.

brushCorrelation

mgp

Optional number between 0 and 100, indicating a per-beam correlation threshold below which data are to be considered suspect. If the plot type is p, the suspect points (velocity, backscatter amplitude, or correlation) will be coloured

red; otherwise, this argument is ignored.

colBrush Colour to use for brushed (bad) data, if brushCorrelation is active.

main Main title for plot, used just on the top panel, if there are several panels.

debug A flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... Optional arguments passed to plotting functions.

# **Details**

Creates a multi-panel summary plot of data measured by an ADV. The panels are controlled by the which argument. (Note the gaps in the sequence, e.g. 4 and 8 are not used.)

- which=1 to 3 (or "u1" to "u3") yield timeseries of the first, second, and third components of velocity (in beam, xyz or enu coordinates).
- which=4 is not permitted (since ADV are 3-beam devices)
- which=5 to 7 (or "a1" to "a3") yield timeseries of the amplitudes of beams 1 to 3. (Note that the data are called data\$a[,1], data\$a[,2] and data\$a[,3], for these three timeseries.)
- which=8 is not permitted (since ADV are 3-beam devices)

• which=9 to 11 (or "q1" to "q3") yield timeseries of correlation for beams 1 to 3. (Note that the data are called data\$c[,1], data\$c[,2] and data\$c[,3], for these three timeseries.)

- which=12 is not permitted (since ADVs are 3-beam devices)
- which=13 is not permitted (since ADVs do not measure salinity)
- which=14 or which="temperature" yields a timeseries of temperature.
- which=15 or which="pressure" yields a timeseries of pressure.
- which=16 or which="heading" yields a timeseries of heading.
- which=17 or which="pitch" yields a timeseries of pitch.
- which=18 or which="roll" yields a timeseries of roll.
- which=19 to 21 yields plots of correlation versus amplitude, for beams 1 through 3, using smoothScatter.
- which=22 is not permitted (since ADVs are 3-beam devices)
- which=23 or "progressive vector" yields a progressive-vector diagram in the horizontal plane, plotted with asp=1, and taking beam1 and beam2 as the eastward and northward components of velocity, respectively.
- which=28 or "uv" yields velocity plot in the horizontal plane, i.e. u[2] versus u[1]. If the number of data points is small, a scattergraph is used, but if it is large, smoothScatter is used.
- which=29 or "uv+ellipse" as the "uv" case, but with an added indication of the tidal ellipse, calculated from the eigen vectors of the covariance matrix.
- which=30 or "uv+ellipse+arrow" as the "uv+ellipse" case, but with an added arrow indicating the mean current.
- which=50 or "analog1" plots a time series of the analog1 signal, if there is one.
- which=51 or "analog2" plots a time series of the analog2 signal, if there is one.
- which=100 or "voltage" plots the voltage as a timeseries, if voltage exists in the dataset.

In addition to the above, there are some groupings defined:

- which="velocity" equivalent to which=1:3 (three velocity components)
- which="amplitude" equivalent to which=5:7 (three amplitude components)
- which="backscatter" equivalent to which=9:11 (three backscatter components)
- which="hydrography" equivalent to which=14:15 (temperature and pressure)
- which="angles" equivalent to which=16:18 (heading, pitch and roll)

#### Author(s)

Dan Kelley

266 plot,amsr-method

#### See Also

The documentation for adv-class explains the structure of ADV objects, and also outlines the other functions dealing with them.

Other functions that plot oce data: plot,adp-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method,plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

### **Examples**

library(oce)
data(adv)
plot(adv)

plot,amsr-method

Plot an amsr Object

# **Description**

Plot an amsr Object

#### **Usage**

#### **Arguments**

x An object inheriting from amsr-class.

y String indicating the name of the band to plot; if not provided, SST is used; see

amsr-class for a list of bands.

asp Optional aspect ratio for plot.

missingColor List of colours for problem cases. The names of the elements in this list must be

as in the default, but the colours may be changed to any desired values. These default values work reasonably well for SST images, which are the default image, and which employ a blue-white-red blend of colours, no mixture of which

matches the default values in missingColor.

plot,argo-method 267

```
debug A debugging flag, integer.
... extra arguments passed to imagep, e.g. set col to control colours.
```

### Author(s)

Dan Kelley

### See Also

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class
```

Other things related to amsr data: [[<-,amsr-method, amsr-class, composite,amsr-method, download.amsr, read.amsr, subset,amsr-method, summary,amsr-method

# **Examples**

```
## Not run:
d <- read.amsr("f34_20160102v7.2.gz")
asp <- 1/cos(pi*40/180)
plot(d, "SST", col=oceColorsJet, xlim=c(-80,0), ylim=c(20,60), asp=asp)
data(coastlineWorldMedium, package="ocedata")
lines(coastlineWorldMedium[['longitude']], coastlineWorldMedium[['latitude']])
## End(Not run)</pre>
```

plot, argo-method

Plot Argo Data

## **Description**

Plot a summary diagram for argo data.

## Usage

```
## S4 method for signature 'argo'
plot(x, which = 1, level, coastline = c("best",
   "coastlineWorld", "coastlineWorldMedium", "coastlineWorldFine", "none"),
   cex = 1, pch = 1, type = "p", col, fill = FALSE, projection = NULL,
   mgp = getOption("oceMgp"), mar = c(mgp[1] + 1.5, mgp[1] + 1.5, 1.5, 1.5),
   tformat, debug = getOption("oceDebug"), ...)
```

268 plot,argo-method

#### **Arguments**

Χ

object inheriting from argo-class.

which

list of desired plot types, one of the following. Note that oce.pmatch is used to try to complete partial character matches, and that an error will occur if the match is not complete (e.g. "salinity" matches to both "salinity ts" and "salinity profile".).

- which=1 or which="trajectory" gives a plot of the argo trajectory, with the coastline, if one is provided.
- which=2 or "salinity ts" gives a time series of salinity at the indicated level(s)
- which=3 or "temperature ts" gives a time series of temperature at the indicated level(s)
- which=4 or "TS" gives a TS diagram at the indicated level(s)
- which=5 or "salinity profile" gives a salinity profile of all the data (with S and p trimmed to the 1 and 99 percentiles)
- which=6 or "temperature profile" gives a temperature profile (with T and p trimmed to the 1 and 99 percentiles)

level

depth pseudo-level to plot, for which=2 and higher. May be an integer, in which case it refers to an index of depth (1 being the top) or it may be the string "all" which means to plot all data.

coastline

character string giving the coastline to be used in an Argo-location map, or "best" to pick the one with highest resolution, or "none" to avoid drawing the coastline.

cex pch size of plotting symbols to be used if type='p'. type of plotting symbols to be used if type='p'.

type

plot type, either "1" or "p".

col

optional list of colours for plotting.

fill

Either a logical, indicating whether to fill the land with light-gray, or a colour name. Owing to problems with some projections, the default is not to fill.

projection

indication of the projection to be used in trajectory maps. If this is NULL, no projection is used, although the plot aspect ratio will be set to yield zero shape distortion at the mean float latitude. If projection="automatic", then one of two projections is used: stereopolar (i.e. "+proj=stere +lon\_0=X" where X is the mean longitude), or Mercator (i.e. "+proj=merc") otherwise. Otherwise, projection must be a character string specifying a projection in the notation used by project in the **rgdal**; this will be familiar to many readers as the PROJ.4 notation; see mapPlot.

mgp

3-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.

mar

value to be used with par("mar").

tformat

optional argument passed to oce.plot.ts, for plot types that call that function. (See strptime for the format used.)

debug

debugging flag.

. . .

optional arguments passed to plotting functions.

plot,bremen-method 269

#### Value

None.

#### Author(s)

Dan Kelley

#### References

```
http://www.argo.ucsd.edu/
```

#### See Also

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, as.argo, handleFlags, argo-method, read.argo, subset, argo-method, summary, argo-method

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class

### **Examples**

plot, bremen-method

Plot a Bremen Object

### **Description**

Plot a bremen object, i.e. one inheriting from bremen-class. If x seems to be a CTD dataset, uses plot,ctd-method; otherwise, x is assumed to be a lowered-adp object, and a two-panel plot is created with plot,ladp-method to show velocity variation with pressure.

# Usage

```
## S4 method for signature 'bremen'
plot(x, type, ...)
```

270 plot,cm-method

## Arguments

x A bremen object, e.g. as read by read.bremen.

type Optional string indicating the type to which x should be coerced before plotting.

The choices are ctd and ladp.

... Other arguments, passed to plotting functions.

#### Author(s)

Dan Kelley

#### See Also

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class

Other things related to bremen data: [[,bremen-method, [[<-,bremen-method, bremen-class, read.bremen, summary,bremen-method

plot,cm-method Plot CM data

### Description

Creates a multi-panel summary plot of data measured by a current meter.

# Usage

```
## S4 method for signature 'cm'
plot(x, which = c(1:2, 7:9), type = "1",
    drawTimeRange = getOption("oceDrawTimeRange"), drawZeroLine = FALSE,
    mgp = getOption("oceMgp"), mar = c(mgp[1] + 1.5, mgp[1] + 1.5, 1.5, 1.5),
    small = 2000, main = "", tformat, debug = getOption("oceDebug"), ...)
```

# **Arguments**

x an cm object, e.g. as read by read.cm.

which list of desired plot types. These are graphed in panels running down from the

top of the page. See "Details" for the meanings of various values of which.

type type of plot, as for plot.

drawTimeRange boolean that applies to panels with time as the horizontal axis, indicating whether

to draw the time range in the top-left margin of the plot.

drawZeroLine boolean that indicates whether to draw zero lines on velocities.

plot,cm-method 271

mgp	3-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.
mar	value to be used with par("mar").
small	an integer indicating the size of data set to be considered "small", to be plotted with points or lines using the standard plot function. Data sets with more than small points will be plotted with smoothScatter instead.
main	main title for plot, used just on the top panel, if there are several panels.
tformat	optional argument passed to oce.plot.ts, for plot types that call that function. (See strptime for the format used.)
debug	a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.
	Optional arguments passed to plotting functions.

#### **Details**

The panels are controlled by the which argument, as follows.

- which=1 or which="u" for a time-series graph of eastward velocity, u, as a function of time.
- which=2 or which="v" for a time-series graph of northward velocity, u, as a function of time.
- which=3 or "progressive vector" for progressive-vector plot
- which=4 or "uv" for a plot of v versus u. (Dots are used for small datasets, and smoothScatter for large ones.)
- which=5 or "uv+ellipse" as the "uv" case, but with an added indication of the tidal ellipse, calculated from the eigen vectors of the covariance matrix.
- which=6 or "uv+ellipse+arrow" as the "uv+ellipse" case, but with an added arrow indicating the mean current.
- which=7 or "pressure" for pressure
- which=8 or "salinity" for salinity
- which=9 or "temperature" for temperature
- which=10 or "TS" for a TS diagram
- which=11 or "conductivity" for conductivity
- which=20 or "direction" for the direction of flow

# Author(s)

Dan Kelley

### See Also

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method,plot,coastline-method,plot,ctd-method,plot,gps-method, plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method,plot,odf-method, plot,rsk-method,plot,satellite-method,plot,sealevel-method,plot,section-method,

272 plot,coastline-method

```
plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS,
tidem-class
```

Other things related to cm data: [[,cm-method, [[<-,cm-method, as.cm, cm-class, cm, read.cm, subset, cm-method, summary, cm-method

# **Examples**

```
library(oce)
data(cm)
summary(cm)
plot(cm)
```

plot, coastline-method *Plot a Coastline* 

## **Description**

This function plots a coastline. An attempt is made to fill the space of the plot, and this is done by limiting either the longitude range or the latitude range, as appropriate, by modifying the eastern or northern limit, as appropriate.

#### **Usage**

```
## S4 method for signature 'coastline'
plot(x, xlab = "", ylab = "", showHemi = TRUE, asp,
    clongitude, clatitude, span, lonlabel = NULL, latlabel = NULL,
    sides = NULL, projection = NULL, expand = 1,
    mgp = getOption("oceMgp"), mar = c(mgp[1] + 1, mgp[1] + 1, 1, 1), bg,
    fill, type = "polygon", border = NULL, col = NULL, axes = TRUE,
    cex.axis = par("cex.axis"), add = FALSE, inset = FALSE,
    geographical = 0, longitudelim, latitudelim,
    debug = getOption("oceDebug"), ...)
```

# **Arguments**

X	A coastline object, as read by read.coastline or created by as.coastline,
	or a list containing items named langitude and latitude

or a list containing items named longitude and latitude.

xlab label for x axis ylab label for y axis

showHemi logical indicating whether to show the hemisphere in axis tick labels.

Aspect ratio for plot. The default is for plot, coastline-method to set the aspect ratio to give natural latitude-longitude scaling somewhere near the centre latitude on the plot. Often, it makes sense to set asp yourself, e.g. to get correct shapes at 45N, use asp=1/cos(45\*pi/180). Note that the land mass is not

symmetric about the equator, so to get good world views you should set asp=1

plot, coastline-method 273

> or set ylim to be symmetric about zero. Any given value of asp is ignored, if clongitude and clatitude are given (or if the latter two are inferred from projection.

clongitude, clatitude

optional center latitude of map, in decimal degrees. If both clongitude and clatitude are provided, or alternatively if they can be inferred from substrings +lon\_0 and +lat\_0 in projection, then any provided value of asp is ignored, and instead the plot aspect ratio is computed based on the center latitude. If clongitude and clatitude are known, then span must also be provided, and in this case, it is not permitted to also specify longitudelim and latitudelim.

span

optional suggested diagonal span of the plot, in kilometers. The plotted span is usually close to the suggestion, although the details depend on the plot aspect ratio and other factors, so some adjustment may be required to fine-tune a plot. A value for span must be supplied, if clongitude and clatitude are supplied (or inferred from projection).

lonlabel, latlabel, sides

optional vectors of longitude and latitude to label on the indicated sides of plot, passed to plot, coastline-method. Using these arguments permits reasonably simple customization. If they are are not provided, reasonable defaults will be used.

projection

optional map projection to use (see the mapPlot argument of the same name). If set to FALSE then no projection is used, and the data are plotted in a cartesion frame, with aspect ratio set to reduce distortion near the middle of the plot. This option is useful if the coastline produces spurious horizontal lines owing to islands crossing the plot edges (a problem that plagues map projections). If projection is not set, a Mercator projection is used for latitudes below about 70 degrees, as if projection="+proj=merc" had been supplied, or a Stereopolar one is used as if projection="+proj=stere". Otherwise, projection must be a character string identifying a projection accepted by mapPlot.

expand

numerical factor for the expansion of plot limits, showing area outside the plot, e.g. if showing a ship track as a coastline, and then an actual coastline to show the ocean boundary. The value of expand is ignored if either xlim or ylim is given.

mgp

3-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.

value to be used with par("mar"). mar

optional colour to be used for the background of the map. This comes in handy bg for drawing insets (see "details").

fill a legacy parameter that will be permitted only temporarily; see "History".

indication of type; may be "polygon", for a filled polygon, "p" for points, "1" type

for line segments, or "o" for points overlain with line segments.

border colour of coastlines and international borders (ignored unless type="polygon".

either the colour for filling polygons (if type="polygon") or the colour of the

points and line segments (if type="p", type="1", or type="o").

col

274 plot, coastline-method

axes boolean, set to TRUE to plot axes.

cex.axis value for axis font size factor.

add boolean, set to TRUE to draw the coastline on an existing plot. Note that this

retains the aspect ratio of that existing plot, so it is important to set that correctly, e.g. with asp=1/cos(lat \* pi / 180), where clat is the central latitude of

the plot.

inset set to TRUE for use within plotInset. The effect is to prevent the present func-

tion from adjusting margins, which is necessary because margin adjustment is

the basis for the method used by plotInset.

geographical flag indicating the style of axes. If geographical=0, the axes are conventional,

with decimal degrees as the unit, and negative signs indicating the southern and western hemispheres. If geographical=1, the signs are dropped, with axis values being in decreasing order within the southern and western hemispheres. If geographical=2, the signs are dropped and the axes are labelled with degrees, minutes and seconds, as appropriate, and hemispheres are indicated with letters. If geographical=3, things are the same as for geographical=2, but the

hemisphere indication is omitted.

longitudelim this and latitudelim provide a second way to suggest plot ranges. Note that

these may not be supplied if clongitude, clatitude and span are given.

latitudelim see longitudelim.

debug set to TRUE to get debugging information during processing.

... optional arguments passed to plotting functions. For example, set yaxp=c(-90,90,4)

for a plot extending from pole to pole.

### **Details**

If longitudelim, latitudelim and projection are all given, then these arguments are passed to mapPlot to produce the plot. (The call uses bg for col, and uses col, fill and border directly.) If the results need further customization, users should use mapPlot directly.

If projection is provided without longitudelim or latitudelim, then mapPlot is still called, but longitudelim and latitudelim are computed from clongitude, clatitude and span.

If projection is not provided, much simpler plots are produced. These are Cartesian, with aspect ratio set to minimize shape distortion at the central latitude. Although these are crude, they have the benefit of always working, which cannot be said of true map projections, which can be problematic in various ways owing to difficulties in inverting projection calculations.

To get an inset map inside another map, draw the first map, do par(new=TRUE), and then call plot, coastline-method with a value of mar that moves the inset plot to a desired location on the existing plot, and with bg="white".

## Value

None.

#### **History**

Until February, 2016, plot, coastline-method relied on a now-defunct argument fill to control colours; col is to be used now, instead. Also, in February, 2016, the arguments named parameters and orientation were both removed, as they had become nonfunctional about a year previously, in the transition to using the rgdal package to carry out map projections.

## Author(s)

Dan Kelley

#### See Also

The documentation for coastline-class explains the structure of coastline objects, and also outlines the other functions dealing with them.

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class
```

Other things related to coastline data: [[,coastline-method,[[<-,coastline-method,as.coastline,coastline,coastline-class,coastlineBest,coastlineCut,coastlineWorld,download.coastline,read.coastline.openstread.coastline.shapefile,subset,coastline-method,summary,coastline-method

### **Examples**

plot,ctd-method

Plot CTD Data

# Description

Plot CTD data, by default in a four-panel display showing (a) profiles of salinity and temperature, (b) profiles of density and the square of buoyancy frequency, (c) a TS diagram and (d) a coastline diagram indicating the station location.

### Usage

```
## S4 method for signature 'ctd'
plot(x, which, col = par("fg"), fill, borderCoastline = NA,
    colCoastline = "lightgray", eos = getOption("oceEOS", default = "gsw"),
    ref.lat = NaN, ref.lon = NaN, grid = TRUE, coastline = "best", Slim,
    Clim, Tlim, plim, densitylim, N2lim, Rrholim, dpdtlim, timelim, lonlim,
    latlim, drawIsobaths = FALSE, clongitude, clatitude, span,
    showHemi = TRUE, lonlabel = NULL, latlabel = NULL, sides = NULL,
    projection = NULL, parameters = NULL, orientation = NULL,
    latlon.pch = 20, latlon.cex = 1.5, latlon.col = "red", cex = 1,
    cex.axis = par("cex.axis"), pch = 1, useSmoothScatter = FALSE, df,
    keepNA = FALSE, type = "l", mgp = getOption("oceMgp"), mar = c(mgp[1] + 1.5, mgp[1] + 1.5, mgp[1] + 1.5, mgp[1] + 1), inset = FALSE,
    add = FALSE, debug = getOption("oceDebug"), ...)
```

#### **Arguments**

х

A ctd object, i.e. one inheriting from ctd-class.

which

List of desired plot types, as given below. If which is not supplied, a default will be used. This default will be c(1,2,3,5) if the CTD is in profiling mode (i.e. if deploymentType in the metadata slot equals "profile", or is missing) or "moored"/"thermosalinograph", the default will be c(30, 3, 31, 5). If it is "towyo", c(30, 31, 32, 3) will be used. Details are as follows.

- which=1 or which="salinity+temperature" gives a combined profile of temperature and salinity
- which=2 or which="density+N2" gives a combined profile of  $\sigma_{\theta}$  and  $N^2$
- which=3 or which="TS" gives a TS plot
- which=4 or which="text" gives a textual summary of some aspects of the data
- which=5 or which="map" gives a map plotted with plot, coastline-method, with a dot for the station location. Notes near the top boundary of the map give the station number, the sampling date, and the name of the chief scientist, if these are known. Note that the longitude will be converted to a value between -180 and 180 before plotting. (See also notes about span.)
- which=5.1 as for which=5, except that the file name is drawn above the map
- which=6 or which="density+dpdt" gives a profile of density and dP/dt, which is useful for evaluating whether the instrument is dropping properly through the water column
- which=7 or which="density+time" gives a profile of density and time
- which=8 or which="index" gives a profile of index number (especially useful for ctdTrim)
- which=9 or which="salinity" gives a salinity profile
- which=10 or which="temperature" gives a temperature profile
- which=11 or which="density" gives a density profile
- which=12 or which="N2" gives an  $N^2$  profile

• which=13 or which="spice" gives a spiciness profile

• which=14 or which="tritium" gives a tritium profile

• which=15 or which="Rrho" gives an Rrho profile

• which=16 or which="RrhoSF" gives an RrhoSF profile

• which=17 or which="conductivity" gives a conductivity profile

• which=20 or which="CT" gives a Conservative Temperature profile

• which=21 or which="SA" gives an Absolute Salinity profile

• which=30 gives a time series of Salinity

• which=31 gives a time series of Temperature

• which=32 gives a time series of pressure

• which=33 gives a time series of sigmaTheta

col Colour of lines or symbols.

fill A legacy parameter that will be permitted only temporarily; see "History".

borderCoastline

Colour of coastlines and international borders, passed to plot, coastline-method

if a map is included in which.

colCoastline Fill colour of coastlines and international borders, passed to plot, coastline-method

if a map is included in which. Set to NULL to avoid filling.

eos String indicating the equation of state to be used, either "unesco" or "gsw".

ref.lat Latitude of reference point for distance calculation. ref.lon Longitude of reference point for distance calculation.

Set TRUE to get a grid on all plots. grid

coastline A specification of the coastline to be used for which="map". This may be a

> coastline object, whether built-in or supplied by the user, or a character string. If the later, it may be the name of a built-in coastline ("coastlineWorld", "coastlineWorldFine", or "coastlineWorldCoarse"), or "best", to choose a suitable coastline for the locale, or "none" to prevent the drawing of a coastline. There is a speed penalty for providing coastline as a character string, because it forces plot, coastline-method to load it on every call. So, if plot, coastline-method is to be called several times for a given coastline, it makes sense to load it in before the first call, and to supply the object as an

argument, as opposed to the name of the object.

Optional limits of salinity axes. Slim

Clim Optional limits of conductivity axes. Tlim Optional limits of temperature axes. plim Optional limits of pressure axes.

Optional limits of density axis, whether that axis be horizontal or vertical. densitylim

Optional limits of  $N^2$  axis. N2lim Rrholim Optional limits of  $R_r ho$  axis. dpdtlim Optional limits of dP/dt axis. timelim Optional limits of delta-time axis.

lonlim Optional limits of longitude axis of map (ignored if no map plotted) DEPRE-

CATED 2014-01-07.

latlim Optional limits of latitude axis of map (ignored if no map plotted) DEPRE-

CATED 2014-01-07.

drawIsobaths An indication of whether to draw depth contours on maps, in addition to the

coastline. The argument has no effect except for panels in which the value of which equals "map" or the equivalent numerical code, 5. If drawIsobaths is FALSE, then no contours are drawn. If drawIsobaths is TRUE, then contours are selected automatically, using pretty(c(0,300)) if the station depth is under 100m or pretty(c(0,5500)) otherwise. If drawIsobaths is a numerical vector, then the indicated depths are drawn. For plots drawn with projection set to NULL, the contours are added with contour and otherwise mapContour is used. To customize the resultant contours, e.g. setting particular line types or colours, users should call these functions directly (see e.g. Example 2).

clongitude Center longitude.

span Optional span of map, in km. If not given, this will be determined as a small

multiple of the distance to the nearest point of land, in an attempt to show some

coastline in the plot.

Center latitude.

showHemi Logical indicating whether to show hemisphere in axis tick labels.

lonlabel, latlabel, sides

clatitude

Optional vectors of longitude and latitude to label on the indicated sides of plot, passed to plot, coastline-method. Using these arguments permits reasonably simple customization. If they are are not provided, reasonable defaults will be

used.

projection Projection for map, if desired. If this is NULL, no projection will be used; the map

will simply show longitude and latitude in a cartesian frame, scaled to retain shapes at the centre. If this is the string "automatic", then either a Mercator or Stereographic projection will be used, depending on whether the CTD station is within 70 degrees of the equator or at higher latitudes. Finally, if this is a string

in the format used by mapPlot, then it is is passed to that function.

parameters a **deprecated** argument that has been ignored since February 2016; see oce-

deprecated.

orientation a **deprecated** argument that has been ignored since February 2016; see oce-

deprecated.

latlon.pch Symbol code for sample location (ignored if no map plotted).

latlon.cex Symbol expansion factor for sample location (ignored if no map plotted).

latlon.col Colour of symbol for sample location (ignored if no map plotted).

cex Size to be used for plot symbols (see par).

cex.axis Size factor for axis labels (see par).

pch Code for plotting symbol (see par).

useSmoothScatter

Boolean, set to TRUE to use smoothScatter instead of plot to draw the plot.

df Optional argument that is ignored except for plotting buoyancy frequency; in that case, it is passed to swN2 as the argument named df. keepNA Flag indicating whether to keep NA values in linegraphs, which will yield breaks in the lines. type The type of plot to draw, using the same scheme as plot. Three-element numerical vector specifying axis-label geometry, passed to par. mgp The default establishes tighter margins than in the usual R setup. Four-element numerical vector specifying margin geometry, passed to par. The mar default establishes tighter margins than in the usual R setup. inset Set to TRUE for use within plotInset. The effect is to prevent the present function from adjusting margins, which is necessary because margin adjustment is the basis for the method used by plotInset. add Logical, indication of whether to add to an existing plot. This only works if length(which)=1, and it will yield odd results if the value of which does not match that in the previous plots. debug an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values. Optional arguments passed to plotting functions. A common example is to set df, for use in swN2 calculations.

#### **Details**

Creates a multi-panel summary plot of data measured in a CTD cast. The default values of which and other arguments are chosen to be useful for quick overviews of data. However, for detailed work it is common to call the present function with just a single value of which, e.g. with four calls to get four panels. The advantage of this is that it provides much more control over the display, and also it permits the addition of extra display elements (lines, points, margin notes, etc.) to the individual panels.

Note that panels that draw more than one curve (e.g. which="salinity+temperature" draws temperature and salinity profiles in one graph), the value of par("usr") is established by the second profile to have been drawn. Some experimentation will reveal what this profile is, for each permitted which case, although it seems unlikely that this will help much ... the simple fact is that drawing two profiles in one graph is useful for a quick overview, but not useful for e.g. interactive analysis with locator to flag bad data, etc.

# History

Until February, 2016, plot, ctd-method relied on a now-defunct argument fill to control colours; colCoastline is to be used now, instead. Also, now it is possible to set the colour of coasts and international boundaries, with borderCoastline.

#### Author(s)

Dan Kelley

### See Also

The documentation for ctd-class explains the structure of CTD objects, and also outlines the other functions dealing with them.

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method,plot,cm-method,plot,coastline-method,plot,gps-method, plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method,plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class
```

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

### **Examples**

```
## 1. simple plot
library(oce)
data(ctd)
plot(ctd)
## 2. how to customize depth contours
par(mfrow=c(1,2))
data(section)
stn <- section[["station", 105]]</pre>
plot(stn, which='map', drawIsobaths=TRUE)
plot(stn, which='map')
data(topoWorld)
tlon <- topoWorld[["longitude"]]</pre>
tlat <- topoWorld[["latitude"]]</pre>
tdep <- -topoWorld[["z"]]</pre>
contour(tlon, tlat, tdep, drawlabels=FALSE,
        levels=seq(1000,6000,1000), col='lightblue', add=TRUE)
contour(tlon, tlat, tdep, vfont=c("sans serif", "bold"),
        levels=stn[['waterDepth']], col='red', lwd=2, add=TRUE)
```

plot, echosounder-method

Plot Echosounder Data

## **Description**

Plot echosounder data. Simple linear approximation is used when a newx value is specified with the which=2 method, but arguably a gridding method should be used, and this may be added in the future.

# Usage

```
## S4 method for signature 'echosounder'
plot(x, which = 1, beam = "a", newx, xlab, ylab,
    xlim, ylim, zlim, type = "l", col = oce.colorsJet, lwd = 2,
    despike = FALSE, drawBottom, ignore = 5, drawTimeRange = FALSE,
    drawPalette = TRUE, radius, coastline, mgp = getOption("oceMgp"),
    mar = c(mgp[1] + 1, mgp[1] + 1, mgp[1] + 1, mgp[1] + 1), atTop, labelsTop,
    tformat, debug = getOption("oceDebug"), ...)
```

# **Arguments**

guments	
x	An echosounder object, e.g. as read by read.echosounder, or created by as.echosounder.
which	list of desired plot types: which=1 or which="zt image" gives a z-time image, which=2 or which="zx image" gives a z-distance image, and which=3 or which="map" gives a map showing the cruise track. In the image plots, the display is of log10 of amplitude, trimmed to zero for any amplitude values less than 1 (including missing values, which equal 0). Add 10 to the numeric codes to get the secondary data (non-existent for single-beam files,
beam	a more detailed specification of the data to be plotted. For single-beam data, this may only be "a". For dual-beam data, this may be "a" for the narrow-beam signal, or "b" for the wide-beam signal. For split-beam data, this may be "a" for amplitude, "b" for x-angle data, or "c" for y-angle data.
newx	optional vector of values to appear on the horizontal axis if which=1, instead of time. This must be of the same length as the time vector, because the image is remapped from time to newx using approx.
xlab, ylab	optional labels for the horizontal and vertical axes; if not provided, the labels depend on the value of which.
xlim	optional range for x axis.
ylim	optional range for y axis.
zlim	optional range for colour scale.
type	type of graph, "1" for line, "p" for points, or "b" for both.
col	colour scale for image, a function
lwd	line width (ignored if type="p")
despike	remove vertical banding by using smooth to smooth across image columns, row by row.
drawBottom	optional flag used for section images. If TRUE, then the bottom is inferred as a smoothed version of the ridge of highest image value, and data below that are

grayed out after the image is drawn. If drawBottom is a colour, then that colour

is used, instead of white. The bottom is detected with findBottom, using the

ignore value described next.

ignore optional flag specifying the thickness in metres of a surface region to be ignored

during the bottom-detection process. This is ignored unless drawBottom=TRUE.

drawTimeRange if TRUE, the time range will be drawn at the top. Ignored except for which=2,

i.e. distance-depth plots.

drawPalette if TRUE, the palette will be drawn.

radius radius to use for maps; ignored unless which=3 or which="map".

coastline coastline to use for maps; ignored unless which=3 or which="map".

mgp 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar value to be used with par("mar").

atTop optional vector of time values, for labels at the top of the plot produced with

which=2. If labelsTop is provided, then it will hold the labels. If labelsTop is not provided, the labels will be constructed with the format function, and these

may be customized by supplying a format in the ... arguments.

labelsTop optional vector of character strings to be plotted above the atTop times. Ignored

unless atTop was provided.

tformat optional argument passed to imagep, for plot types that call that function. (See

strptime for the format used.)

debug set to an integer exceeding zero, to get debugging information during processing.

... optional arguments passed to plotting functions. For example, for maps, it is

possible to specify the radius of the view in kilometres, with radius.

## Value

A list is silently returned, containing xat and yat, values that can be used by oce.grid to add a grid to the plot.

### Author(s)

Dan Kelley, with extensive help from Clark Richards

#### See Also

Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, as.echosounder, echosounder-class, echosounder, findBottom, read.echosounder, subset, echosounder-method, summary, echosounder-method

# Examples

```
## Not run:
library(oce)
data(echosounder)
```

283 plot,gps-method

```
plot(echosounder, which=c(1,2), drawBottom=TRUE)
## End(Not run)
```

plot, gps-method

Plot a GPS Object

### **Description**

This function plots a gps object. An attempt is made to use the whole space of the plot, and this is done by limiting either the longitude range or the latitude range, as appropriate, by modifying the eastern or northern limit, as appropriate. To get an inset map inside another map, draw the first map, do par(new=TRUE), and then call plot.gps with a value of mar that moves the inset plot to a desired location on the existing plot, and with bg="white".

### **Usage**

```
## S4 method for signature 'gps'
plot(x, xlab = "", ylab = "", asp, clongitude, clatitude,
  span, projection, parameters = NULL, orientation = NULL, expand = 1,
 mgp = getOption("oceMgp"), mar = c(mgp[1] + 1, mgp[1] + 1, 1, 1), bg,
  axes = TRUE, cex.axis = par("cex.axis"), add = FALSE, inset = FALSE,
  geographical = 0, debug = getOption("oceDebug"), ...)
```

# **Arguments**

asp

A gps object, as read by read.gps or created by as.gps, or a list containing

items named longitude and latitude.

label for x axis xlab ylab label for y axis

> Aspect ratio for plot. The default is for plot. gps to set the aspect ratio to give natural latitude-longitude scaling somewhere near the centre latitude on the plot.

Often, it makes sense to set asp yourself, e.g. to get correct shapes at 45N, use asp=1/cos(45\*pi/180). Note that the land mass is not symmetric about the equator, so to get good world views you should set asp=1 or set ylim to be symmetric about zero. Any given value of asp is ignored, if clongitude and

clatitude are given.

clongitude, clatitude

optional center latitude of map, in decimal degrees. If both clongitude and clatitude are provided, then any provided value of asp is ignored, and instead the plot aspect ratio is computed based on the center latitude. If clongitude

and clatitude are provided, then span must also be provided.

optional suggested span of plot, in kilometers. The suggestion is an upper limit span on the scale; depending on the aspect ratio of the plotting device, the radius may

be smaller than span. A value for span must be supplied, if clongitude and

clatitude are supplied.

284 plot,gps-method

projection optional map projection to use (see mapPlot); if not given, a cartesian frame is

used, scaled so that gps shapes near the centre of the plot are preserved. If a projection is provided, the coordinate system will bear an indirect relationship to longitude and longitude, and further adornment of the plot must be done with

e.g. mapPoints instead of points.

parameters optional parameters to map projection (see mapPlot. orientation optional orientation of map projection (see mapPlot.

expand numerical factor for the expansion of plot limits, showing area outside the plot,

e.g. if showing a ship track as a gps, and then an actual gps to show the ocean boundary. The value of expand is ignored if either xlim or ylim is given.

mgp 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar value to be used with par("mar").

bg optional colour to be used for the background of the map. This comes in handy

for drawing insets (see "details").

axes boolean, set to TRUE to plot axes. cex.axis value for axis font size factor.

add boolean, set to TRUE to draw the gps on an existing plot. Note that this retains

the aspect ratio of that existing plot, so it is important to set that correctly, e.g. with asp=1/cos(lat \* pi / 180), where clat is the central latitude of the

plot.

inset set to TRUE for use within plotInset. The effect is to prevent the present func-

tion from adjusting margins, which is necessary because margin adjustment is

the basis for the method used by plotInset.

geographical flag indicating the style of axes. If geographical=0, the axes are conventional,

with decimal degrees as the unit, and negative signs indicating the southern and western hemispheres. If geographical=1, the signs are dropped, with axis values being in decreasing order within the southern and western hemispheres. If geographical=2, the signs are dropped and the axes are labelled with degrees,

minutes and seconds, as appropriate.

debug set to TRUE to get debugging information during processing.

... optional arguments passed to plotting functions. For example, set yaxp=c(-90,90,4)

for a plot extending from pole to pole.

# Author(s)

Dan Kelley

#### See Also

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, ladp-method, plot, lisst-method, plot, lobo-method, plot, met-method, plot, odf-method, plot, rsk-method, plot, satellite-method, plot, sealevel-method, plot, section-method,

```
\verb|plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS,tidem-class|
```

Other things related to gps data: [[,gps-method,[[<-,gps-method,as.gps,gps-class,read.gps,summary,gps-method]

plot, ladp-method

Plot an ladp object

## **Description**

Uses plotProfile to create panels of depth variation of easterly and northerly velocity components.

# Usage

```
## S4 method for signature 'ladp'
plot(x, which = c("u", "v"), ...)
```

# **Arguments**

x A ladp object, e.g. as read by as.ladp.
which Vector of names of items to be plotted.
... Other arguments, passed to plotting functions.

#### Author(s)

Dan Kelley

### See Also

```
Other things related to ladp data: [[,ladp-method, as.ladp, ladp-class, summary, ladp-method
```

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class
```

286 plot,landsat-method

plot, landsat-method Plot a landsat Object

## **Description**

Plot the data within a landsat image, or information computed from the data. The second category includes possibilities such as an estimate of surface temperature and the "terralook" estimate of a natural-colour view.

#### Usage

```
## S4 method for signature 'landsat'
plot(x, band, which = 1, decimate = TRUE, zlim,
   utm = FALSE, col = oce.colorsPalette, drawPalette = TRUE,
   showBandName = TRUE, alpha.f = 1, red.f = 1.7, green.f = 1.5,
   blue.f = 6, offset = c(0, -0.05, -0.2, 0), transform = diag(c(red.f, green.f, blue.f, alpha.f)), debug = getOption("oceDebug"), ...)
```

#### **Arguments**

x A landsat object, e.g. as read by read.landsat.

band

If given, the name of the band. For Landsat-8 data, this may be one of: "aerosol", "blue", "green", "red", "nir", "swir1", "swir2", "panchromatic", "cirrus", "tirs1", or "tirs2". For Landsat-7 data, this may be one of "blue", "green", "red", "nir", "swir1", "tirs1", "tirs2", "swir2", or "panchromatic". For Landsat data prior to Landsat-7, this may be one of "blue", "green", "red", "nir", "swir1", "tirs1", "tirs2", or "swir2". If band is not given, the ("tirs1") will be used if it exists in the object data, or otherwise the first band will be used. In addition to the above, using band="temperature" will plot an estimate of at-satellite brightness temperature, computed from the tirs1 band, and band="terralook" will plot a sort of natural colour by combining the red, green, blue and nir bands according to the formula provided at https://lta.cr.usgs.gov/terralook/what\_is\_terralook (a website that worked once, but failed as of Feb 2, 2017).

which

Desired plot type; 1=image, 2=histogram.

decimate

An indication of the desired decimation, passed to image for image plots. The default yields faster plotting. Some decimation is sensible for full-size images, since no graphical displays can show 16 thousand pixels on a side.

zlim

Either a pair of numbers giving the limits for the colourscale, or "histogram" to have a flattened histogram (i.e. to maximally increase contrast throughout the domain.) If not given, the 1 and 99 percent quantiles are calculated and used as limits.

utm

A logical value indicating whether to use UTS (easting and northing) instead of longitude and latitude on plot.

plot,landsat-method 287

col	Either a function yielding colours, taking a single integer argument with the desired number of colours, or the string "natural", which combines the information in the red, green and blue bands and produces a natural-hue image. In the latter case, the band designation is ignored, and the object must contain the three colour bands.
drawPalette	Indication of the type of palette to draw, if any. See imagep for details.
showBandName	A logical indicating whether the band name is to plotted in the top margin, near the right-hand side.
alpha.f	Argument used if col="natural", to adjust colours with adjustcolor.
red.f	Argument used if col="natural", to adjust colours with adjustcolor. Higher values of red.f cause red hues to be emphasized (e.g. dry land).
green.f	Argument used if col="natural", to adjust colours with adjustcolor. Higher values of green. f emphasize green hues (e.g. forests).
blue.f	Argument used if band="terralook", to adjust colours with adjustcolor. Higher values of blue.f emphasize blue hues (e.g. ocean).
offset	Argument used if band="terralook", to adjust colours with adjustcolor.
transform	Argument used if band="terralook", to adjust colours with adjustcolor.
debug	Set to a positive value to get debugging information during processing.
	optional arguments passed to plotting functions.

#### **Details**

```
For Landsat-8 data, the band may be one of: "aerosol", "blue", "green", "red", "nir", "swir1", "swir2", "panchromatic", "cirrus", "tirs1", or "tirs2".
```

For Landsat-7 data, band may be one of "blue", "green", "red", "nir", "swir1", "tirs1", "tirs2", "swir2", or "panchromatic".

For Landsat data prior to Landsat-7, band may be one of "blue", "green", "red", "nir", "swir1", "tirs1", "tirs2", or "swir2".

If band is not given, the ("tirs1") will be used if it exists in the object data, or otherwise the first band will be used.

In addition to the above there are also some pseudo-bands that can be plotted, as follows.

- Setting band="temperature" will plot an estimate of at-satellite brightness temperature, computed from the tirs1 band.
- Setting band="terralook" will plot a sort of natural colour by combining the red, green, blue and nir bands according to the formula provided at https://lta.cr.usgs.gov/terralook/what\_is\_terraloo (a website that worked once, but failed as of Feb 2, 2017), namely that the red-band data are provided as the red argument of the rgb function, while the green argument is computed as 2/3 of the green-band data plus 1/3 of the nir-band data, and the blue argument is computed as 2/3 of the green-band data minus 1/3 of the nir-band data. (This is not a typo: the blue band is not used.)

#### Author(s)

Dan Kelley

288 plot,lisst-method

### See Also

Other things related to landsat data: [[,landsat-method,landsat-class,landsatAdd,landsatTrim,landsat,read.landsat,summary,landsat-method

plot,lisst-method Plot LISST data

## **Description**

Creates a multi-panel summary plot of data measured by LISST instrument.

# Usage

```
## S4 method for signature 'lisst'
plot(x, which = c(16, 37, 38), tformat,
  debug = getOption("oceDebug"), ...)
```

# **Arguments**

X	a lisst object, e.g. as read by read.lisst.
which	list of desired plot types. These are graphed in panels running down from the top of the page. See "Details" for the meanings of various values of which.
tformat	optional argument passed to oce.plot.ts, for plot types that call that function. (See strptime for the format used.)
debug	a flag that turns on debugging. The value indicates the depth within the call stack to which debugging applies.
	optional arguments passed to plotting functions.

### **Details**

The panels are controlled by the which argument, as follows.

- which=1 to 32, or which="C1" to "C32" for a time-series graph of the named column (a size class).
- which=33 or which="lts" for a time-series plot of laser transmission sensor.
- which=34 or which="voltage" for a time-series plot of instrument voltage.
- which=35 or which="aux" for a time-series plot of the external auxiliary input.
- which=36 or which="lrs" for a time-series plot of the laser reference sensor.
- which=37 or which="pressure" for a time-series plot of pressure.
- which=38 or which="temperature" for a time-series plot of temperature.
- which=41 or which="transmission" for a time-series plot of transmission, in percent.
- which=42 or which="beam" for a time-series plot of beam-C, in 1/metre.

plot,lobo-method 289

#### Author(s)

Dan Kelley

#### See Also

The documentation for lisst-class explains the structure of lisst objects, and also outlines the other functions dealing with them.

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot,gps-method, plot,ladp-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to lisst data: [[,lisst-method, [[<-,lisst-method, as.lisst, lisst-class, read.lisst, summary, lisst-method

## **Examples**

```
library(oce)
data(lisst)
plot(lisst)
```

plot, lobo-method

Plot LOBO data

#### Description

Plot a summary diagram for lobo data.

## Usage

```
## S4 method for signature 'lobo'
plot(x, which = c(1, 2, 3), mgp = getOption("oceMgp"),
  mar = c(mgp[2] + 1, mgp[1] + 1, 1, mgp[1] + 1.25),
  debug = getOption("oceDebug"), ...)
```

## **Arguments**

Χ

A lobo object, e.g. as read by read. lobo.

which

A vector of numbers or character strings, indicating the quantities to plot. These are stacked in a single column. The possible values for which are as follows: 1 or "temperature" for a time series of temperature; 2 or "salinity" for salinity; 3 or "TS" for a TS diagram (which uses eos="unesco"), 4 or "u" for a timeseries of the u component of velocity; 5 or "v" for a timeseries of the v component of velocity; 6 or "nitrate" for a timeseries of nitrate concentration; 7 or "fluorescence" for a timeseries of fluorescence value.

290 plot,met-method

mgp 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar value to be used with par("mar").

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

... optional arguments passed to plotting functions.

## Author(s)

Dan Kelley

#### See Also

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,ladp-method, plot,lisst-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to lobo data: [[,lobo-method, [[<-,lobo-method, as.lobo, lobo-class, lobo, subset,lobo-method, summary,lobo-method

plot, met-method

Plot met Data

## **Description**

Creates a multi-panel summary plot of data measured in a meteorological data set. cast. The panels are controlled by the which argument.

#### Usage

```
## S4 method for signature 'met'
plot(x, which = 1:4, mgp, mar, tformat,
  debug = getOption("oceDebug"))
```

plot,met-method 291

#### **Arguments**

x A met object, e.g. as read by read.met, or a list containing items named salinity and temperature.

which list of desired plot types.

- which=1 gives a time-series plot of temperature
- which=2 gives a time-series plot of pressure
- which=3 gives a time-series plot of the x (eastward) component of velocity
- which=4 gives a time-series plot of the y (northward) component of velocity
- which=5 gives a time-series plot of speed
- which=6 gives a time-series plot of direction (degrees clockwise from north; note that the values returned by met[["direction"]] must be multiplied by 10 to get the direction plotted)

mgp A 3-element numerical vector used with par ("mgp") to control the spacing of

axis elements. The default is tighter than the R default.

mar A 4-element numerical vector used with par ("mar") to control the plot margins.

The default is tighter than the R default.

tformat optional argument passed to oce.plot.ts, for plot types that call that function.

(See strptime for the format used.)

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## Details

If more than one panel is drawn, then on exit from plot.met, the value of par will be reset to the value it had before the function call. However, if only one panel is drawn, the adjustments to par made within plot.met are left in place, so that further additions may be made to the plot.

## Author(s)

Dan Kelley

#### See Also

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to met data: [[,met-method, [[<-,met-method, as.met, download.met, met-class, met, read.met, subset, met-method, summary, met-method

292 plot,oce-method

## **Examples**

```
library(oce)
data(met)
plot(met, which=3:4)
## Wind speed and direction during Hurricane Juan
## Compare with the final figure in a white paper by Chris Fogarty
## (available at http://www.novaweather.net/Hurricane_Juan_files/McNabs_plot.pdf
## downloaded 2017-01-02).
library(oce)
data(met)
t0 <- as.POSIXct("2003-09-29 04:00:00", tz="UTC")
dt <- 12 * 3600
juan <- subset(met, t0 - dt <= time & time <= t0 + dt)</pre>
par(mfrow=c(2,1))
plot(juan, which=5)
abline(v=t0)
plot(juan, which=6)
abline(v=t0)
```

plot, oce-method

Plot an oce Object

## Description

This creates a pairs plot of the elements in the data slot, if there are more than 2 elements there, or a simple xy plot if 2 elements, or a histogram if 1 element.

## Usage

```
## S4 method for signature 'oce'
plot(x, y, ...)
```

## **Arguments**

A basic oce object, i.e. one inheriting from oce-class, but not from any subclass of that (because these subclasses go to the subclass plot methods, e.g. a ctd-class object would go to plot, ctd-method.

y Ignored; only present here because S4 object for generic plot need to have a second parameter before the . . . parameter.

... Passed to hist, plot, or to

plot,odf-method 293

## **Examples**

```
library(oce)
o <- new("oce")
o <- oceSetData(o, 'x', rnorm(10))
o <- oceSetData(o, 'y', rnorm(10))
o <- oceSetData(o, 'z', rnorm(10))
plot(o)</pre>
```

plot, odf-method

Plot an ODF Object

## **Description**

Plot data contained within an ODF object, using oce.plot.ts to create panels of time-series plots for all the columns contained in the odf object (or just those that contain at least one finite value, if blanks is FALSE). If the object's data slot does not contain time, then pairs is used to plot all the elements in the data slot that contain at least one finite value. These actions are both crude and there are no arguments to control the behaviour, but this function is really just a stop-gap measure, since in practical work odf objects are usually cast to other types, and those types tend to have more useful plots.

## Usage

```
## S4 method for signature 'odf'
plot(x, blanks = TRUE, debug = getOption("oceDebug"))
```

## **Arguments**

x A odf object, e.g. one inheriting from odf-class.

blanks A logical value that indicates whether to include dummy plots for data items

that lack any finite values.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## Author(s)

Dan Kelley

294 plot,rsk-method

#### See Also

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method,plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class

Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, [[<-,odf-method, odf-class, read.ctd.odf, read.odf, subset,odf-method, summary,odf-method

plot, rsk-method

Plot Rsk Data

## **Description**

Rsk data may be in many forms, and it is not easy to devise a general plotting strategy for all of them. The present function is quite crude, on the assumption that users will understand their own datasets, and that they can devise plots that are best-suited to their applications. Sometimes, the sensible scheme is to coerce the object into another form, e.g. using plot(as.ctd(rsk)) if the object contains CTD-like data. Other times, users should extract data from the rsk object and construct plots themselves. The idea is to use the present function mainly to get an overview, and for that reason, the default plot type (set by which) is a set of time-series plots, because the one thing that is definitely known about rsk objects is that they contain a time vector in their data slot.

## Usage

```
## S4 method for signature 'rsk'
plot(x, which = "timeseries", tlim, ylim, xlab, ylab, tformat,
   drawTimeRange = getOption("oceDrawTimeRange"),
   abbreviateTimeRange = getOption("oceAbbreviateTimeRange"),
   useSmoothScatter = FALSE, mgp = getOption("oceMgp"), mar = c(mgp[1] +
   1.5, mgp[1] + 1.5, 1.5, 1.5), main = "", debug = getOption("oceDebug"),
   ...)
```

## Arguments

X	rsk object, typically result of read.rsk.
which	character indicating desired plot types. These are graphed in panels running down from the top of the page. See "Details" for the meanings of various values of which.
tlim	optional limits for time axis. If not provided, the value will be inferred from the data.
ylim	optional limits for the y axis. If not provided, the value will be inferred from the data. (It is helpful to specify this, if the auto-scaled value will be inappropriate, e.g. if more lines are to be added later). Note that this is ignored, unless

plot,rsk-method 295

length(which) == 1 and which corresponds to one of the data fields. If a multipanel plot of a specific subset of the data fields is desired with ylim control, it

should be done panel by panel (see Examples).

xlab optional label for x axis. ylab optional label for y axis.

tformat optional argument passed to oce.plot.ts, for plot types that call that function.

(See strptime for the format used.)

drawTimeRange boolean that applies to panels with time as the horizontal axis, indicating whether

to draw the time range in the top-left margin of the plot.

abbreviateTimeRange

boolean that applies to panels with time as the horizontal axis, indicating whether to abbreviate the second time in the time range (e.g. skipping the year, month,

day, etc. if it's the same as the start time).

useSmoothScatter

a boolean to cause smoothScatter to be used for profile plots, instead of plot.

mgp 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar value to be used with par("mar").

main main title for plot, used just on the top panel, if there are several panels.

debug a flag that turns on debugging, if it exceeds 0.
... optional arguments passed to plotting functions.

#### Details

Plots produced are time series plots of the data in the object. The default, which="timeseries" plots all data fields, and over-rides any other specification. Specific fields can be plotted by naming the field, e.g. which="temperature" to plot a time series of just the temperature field.

## Author(s)

Dan Kelley and Clark Richards

#### See Also

The documentation for rsk-class explains the structure of rsk objects, and also outlines the other functions dealing with them.

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, read.rsk, rsk-class, rskPatm, rskToc, rsk, subset, rsk-method, summary, rsk-method

296 plot,satellite-method

## **Examples**

```
library(oce)
data(rsk)
plot(rsk) # default timeseries plot of all data fields

## A multipanel plot of just pressure and temperature with ylim
par(mfrow=c(2, 1))
plot(rsk, which="pressure", ylim=c(10, 30))
plot(rsk, which="temperature", ylim=c(2, 4))
```

plot, satellite-method Plot a satellite object

## **Description**

For an example using g1sst data, see read.g1sst.

#### Usage

```
## S4 method for signature 'satellite'
plot(x, y, asp, debug = getOption("oceDebug"), ...)
```

# Arguments

An object inherting from satellite-class.
 String indicating the quantity to be plotted.
 Optional aspect ratio for plot.
 debug
 A debugging flag, integer.
 extra arguments passed to imagep, e.g. set col to control colours.

## Author(s)

Dan Kelley

#### See Also

```
Other things related to satellite data: g1sst-class, read.g1sst, satellite-class, summary, satellite-method Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method,plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method, plot,odf-method,plot,rsk-method,plot,sealevel-method,plot,section-method,plot,tidem-method,plot,topo-method,plot,windrose-method,plotProfile,plotScan,plotTS, tidem-class
```

plot,sealevel-method 297

```
plot, sealevel-method Plot Sealevel Data
```

## **Description**

Creates a plot for a sea-level dataset, in one of two varieties. Depending on the length of which, either a single-panel or multi-panel plot is drawn. If there is just one panel, then the value of par used in plot, sealevel-method is retained upon exit, making it convenient to add to the plot. For multi-panel plots, par is returned to the value it had before the call.

## Usage

```
## S4 method for signature 'sealevel'
plot(x, which = 1:3,
   drawTimeRange = getOption("oceDrawTimeRange"), mgp = getOption("oceMgp"),
   mar = c(mgp[1] + 0.5, mgp[1] + 1.5, mgp[2] + 1, mgp[2] + 3/4),
   marginsAsImage = FALSE, debug = getOption("oceDebug"), ...)
```

## **Arguments**

X	an object of class "sealevel", e.g. as read by read. sealevel.
which	a numerical or string vector indicating desired plot types, with possibilities 1 or "all" for a time-series of all the data, 2 or "month" for a time-series of just the first month, 3 or "spectrum" for a power spectrum (truncated to frequencies below $0.1$ cycles per hour, or 4 or "cumulativespectrum" for a cumulative integral of the power spectrum.
drawTimeRange	boolean that applies to panels with time as the horizontal axis, indicating whether to draw the time range in the top-left margin of the plot.
mgp	3-element numerical vector to use for $par(mgp)$ , and also for $par(mar)$ , computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.
mar	value to be used with par("mar").
marginsAsImage	boolean, TRUE to put a wide margin to the right of time-series plots, matching the space used up by a palette in an imagep plot.
debug	a flag that turns on debugging, if it exceeds 0.
	optional arguments passed to plotting functions.

## Value

None.

## Author(s)

Dan Kelley

298 plot, section-method

#### References

The example refers to Hurricane Juan, which caused a great deal of damage to Halifax in 2003. Since this was in the era of the digital photo, a casual web search will uncover some spectacular images of damage, from both wind and storm surge. A map of the path of Hurricane Juan across Nova Scotia is at <a href="http://ec.gc.ca/ouragans-hurricanes/default.asp?lang=En&n=222F51F7-1">http://ec.gc.ca/ouragans-hurricanes/default.asp?lang=En&n=222F51F7-1</a>. Landfall, very near the site of this sealevel gauge, was between 00:10 and 00:20 Halifax local time on Monday, Sept 29, 2003.

## See Also

The documentation for sealevel-class explains the structure of sealevel objects, and also outlines the other functions dealing with them.

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot, met-method, plot,odf-method, plot,rsk-method, plot, satellite-method, plot, section-method, plot, tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to sealevel data: [[, sealevel-method, [[<-, sealevel-method, as.sealevel, read.sealevel-method, sealevel-method, summary, sealevel-method
```

## **Examples**

```
library(oce)
data(sealevel)
## local Halifax time is UTC + 4h; see [2] on timing
juan <- as.POSIXct("2003-09-29 00:15:00", tz="UTC")+4*3600
plot(sealevel, which=1, xlim=juan+86400*c(-7, 7))
abline(v=juan, col='red')</pre>
```

```
plot, section-method Plot a Section
```

#### **Description**

Creates a summary plot for a CTD section, with one panel for each value of which.

## Usage

```
## S4 method for signature 'section'
plot(x, which = c(1, 2, 3, 99), eos, at = NULL,
  labels = TRUE, grid = FALSE, contourLevels = NULL,
  contourLabels = NULL, stationIndices, coastline = "best", xlim = NULL,
  ylim = NULL, zlim = NULL, map.xlim = NULL, map.ylim = NULL,
  clongitude, clatitude, span, projection = NULL, xtype = "distance",
  ytype = "depth", ztype = "contour", zbreaks = NULL, zcol = NULL,
```

plot,section-method 299

```
legend.loc = "bottomright", showStations = FALSE, showStart = TRUE,
showBottom = TRUE, axes = TRUE, mgp, mar, col, cex, pch, debug, ...)
```

# Arguments

guments	
X	a section object, e.g. as created by as.section or read.section.
which	a list of desired plot types, as explained in "Details". There may be up to four panels in total, and the desired plots are placed in these panels, in reading order. If only one panel is plotted, par is not adjusted, which makes it easy to add to the plot with subsequent plotting commands.
eos	Character indication of the seawater equation of state to use. The permitted choices are "gsw" and "unesco". If eos is not supplied, it defaults to getOption("oceEOS", default="g
at	If NULL (the default), the x axis will indicate the distance of the stations from the first in the section. (This may give errors in the contouring routine, if the stations are not present in a geographical order.) If a list, then it indicates the values at which stations will be plotted.
labels	Either a logical, indicating whether to put labels on the x axis, or a vector that is a list of labels to be placed at the x positions indicated by at.
grid	If TRUE, points are drawn at data locations.
contourLevels	Optional contour levels.
contourLabels	Optional contour labels.
stationIndices	Optional list of the indices of stations to use. Note that an index is <i>not</i> a station number, e.g. to show the first 4 stations, use station.indices=1:4.
coastline	String giving the coastline to be used in a station map The permitted choices are "best" (the default) to pick a variant that suits the scale, "coastlineWorld" for the coarse version that is provided by oce, "coastlineWorldMedium" or "coastlineWorldFine" for two coastlines provided by the ocedata package, or "none", to avoid drawing a coastline.
xlim	Optional limit for x axis (only in sections, not map).
ylim	Optional limit for y axis (only in sections, not map)
zlim	Optional two-element numerical vector specifying the limit on the plotted field. This is used only if ztype="image"; see also zbreaks and zcol.
map.xlim, map.y	Optional limits for station map; map.ylim is ignored if map.xlim is provided.
clongitude, cla	optional map centre position and span (km).
projection	Parameter specifying map projection; see mapPlot. If projection="automatic", however, a projection is devised from the data, with stereographic if the mean latitude exceeds 70N and mollweide otherwise.
xtype	Type of x axis, for contour plots, either "distance" for distance (in km) to the first point in the section, "track" for distance along the cruise track, "longitude", "latitude", or "time". Note that if the x values are not in order, they will be put in order (which may make no sense) and a warning will be printed.

300 plot, section-method

ytype Type of y axis for contour plots, either "pressure" for pressure (in dbar, with zero at the surface) or "depth" for depth (in m below the surface, calculated

from pressure with swDepth).

ztype String indicating whether to how to indicate the "z" data (in the R sense, i.e.

this could be salinity, temperature, etc; it does not mean the vertical coordinate) The choices are: "contour" for contours, "image" for an image (drawn with imagep with filledContours=TRUE), or "points" to draw points. In the first two cases, the data must be gridded, with identical pressures at each station.

zbreaks, zcol Indication of breaks and colours to be used if ztype="points" or "image". If

not provided, reasonable default are used. If zlim is given but breaks is not given, then breaks is computed to run from zlim[1] to zlim[2]. If zcol is a function, it will be invoked with an argument equal to 1+length(zbreaks).

legend. loc Location of legend, as supplied to legend, or set to the empty string to avoid

plotting a legend.

showStations Logical indicating whether to draw station numbers on maps.

showStart Logical indicating whether to indicate the first station with a different symbol

than the others.

showBottom An indication of whether (and how) to indicate the ocean bottom. If FALSE, then

the bottom is not rendered. If TRUE, then it is rendered with a gray polygon. If showBottom is a character string, then there are three possibilities: is the string is "polygon" then a polygon is drawn, if it is "lines" then a line is drawn, and if it is "points" then points are drawn. If showBottom is an object inheriting from topo-class then the station locations are interpolated to that topography and the results are shown with a polygon. In this last case, the interpolation is set at a grid that is roughly in accordance with the resolution of the latitudes in

the topo object. See "Examples".

axes Logical value indicating whether to draw axes.

mgp A 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. If not provided, this defaults to getOption("oceMgp").

mar Value to be used with par("mar"). If not provided, a default is set up.

col Colour, which defaults to par("col").

cex Numerical character-expansion factor, which defaults to par ("cex").

pch Indication of symbol type; defaults to par("pch").

debug an integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If debug is not supplied, it defaults to

getOption("oceDebug").

... Optional arguments passed to the contouring function, e.g. using labcex=1 will

increase the size of contour labels.

## Details

The type of plot is governed by which, as follows.

plot,section-method 301

- which=0 or "potential temperature" for temperature contours
- which=1 or "temperature" for temperature contours (the default)
- which=2 or "salinity" for salinity contours
- which=3 or "sigmaTheta" for sigma-theta contours
- which=4 or "nitrate" for nitrate concentration contours
- which=5 or "nitrite" for nitrite concentration contours
- which=6 or "oxygen" for oxygen concentration contours
- which=7 or "phosphate" for phosphate concentration contours
- which=8 or "silicate" for silicate concentration contours
- which=9 or "u" for eastward velocity
- which=10 or "uz" for vertical derivative of eastward velocity
- which=11 or "v" for northward velocity
- which=12 or "vz" for vertical derivative of northward velocity
- which=20 or "data" for a dot for each data location
- which=99 or "map" for a location map

The y-axis for the contours is pressure, plotted in the conventional reversed form, so that the water surface appears at the top of the plot. The x-axis is more complicated. If at is not supplied, then the routine calculates x as the distance between the first station in the section and each of the other stations. (This will produce an error if the stations are not ordered geographically, because the contour routine cannot handle non-increasing axis coordinates.) If at is specified, then it is taken to be the location, in arbitrary units, along the x-axis of labels specified by labels; the way this works is designed to be the same as for axis.

#### Value

If the original section was gridded, the return value is that section. Otherwise, the gridded section that was constructed for the plot is returned. In both cases, the value is returned silently. The purpose of returning the section is to enable subsequent processing of the grid, including adding elements to the plot (see example 5).

#### Author(s)

Dan Kelley

#### See Also

The documentation for section-class explains the structure of section objects, and also outlines the other functions dealing with them.

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags,section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, subset,section-method, summary,section-method

302 plot,tidem-method

## **Examples**

```
library(oce)
data(section)
sg <- sectionGrid(section)</pre>
## 1. AO3 section, default fields.
plot(section)
## 2. Gulf Stream
GS <- subset(section, 109<=stationId&stationId<=129)
GSg <- sectionGrid(GS, p=seq(0, 2000, 100))
plot(GSg, which=c(1, 99), map.ylim=c(34, 42))
par(mfrow=c(2, 1))
plot(GS, which=1, ylim=c(2000, 0), ztype='points',
     zbreaks=seq(0,30,2), pch=20, cex=3)
plot(GSg, which=1, ztype='image', zbreaks=seq(0,30,2))
par(mfrow=c(1, 1))
## 3. Image, with coloured dots to indicate grid-data mismatch.
plot(GSg, which=1, ztype='image')
T <- GS[['temperature']]</pre>
col <- oce.colorsJet(100)[rescale(T, rlow=1, rhigh=100)]</pre>
points(GS[['distance']],GS[['depth']],pch=20,cex=3,col='white')
points(GS[['distance']],GS[['depth']],pch=20,cex=2.5,col=col)
## Not run:
## 4. Image of Absolute Salinity, with 4-minute bathymetry
## It's easy to calculate the desired area for the bathymetry,
## but for brevity we'll hard-code it. Note that download.topo()
## caches the file locally.
f <- download.topo(west=-80, east=0, south=35, north=40, resolution=4)</pre>
t <- read.topo(f)
plot(section, which="SA", xtype="longitude", ztype="image", showBottom=t)
## End(Not run)
## Not run:
## 5. Temperature with salinity added in red
s <- plot(section, which="temperature")</pre>
distance <- s[["distance", "byStation"]]</pre>
depth <- s[["station", 1]][["depth"]]</pre>
salinity <- matrix(s[["salinity"]], byrow=TRUE, nrow=length(s[["station"]]))</pre>
contour(distance, depth, salinity, col=2, add=TRUE)
## End(Not run)
```

plot,tidem-method 303

## **Description**

Plot a summary diagram for a tidal fit.

## Usage

```
## S4 method for signature 'tidem'
plot(x, which = 1, constituents = c("SA", "01", "K1",
    "M2", "S2", "M4"), sides = NULL, col = "blue", log = "",
    mgp = getOption("oceMgp"), mar = c(mgp[1] + 1, mgp[1] + 1, mgp[2] + 0.25,
    mgp[2] + 1), ...)
```

## **Arguments**

x	A tidem object, i.e. one inheriting from tidem-class.
which	integer flag indicating plot type, 1 for stair-case spectral, 2 for spike spectral.
constituents	a character vector of constituents that are to be drawn and label. If NULL, then no constituents will be shown. Consult the built-in dataset tidedata for the permissible constituent names and their frequencies.
sides	an integer vector of length equal to that of constituents, designating the side on which the constituent labels are to be drawn. As in all R graphics, the value 1 indicates the bottom of the plot, and 3 indicates the top. If sides=NULL, the default, then all labels are drawn at the top. Any value of sides that is not either 1 or 3 is converted to 3.
col	a character vector naming colours to be used for constituents. Ignored if sides=3. Repeated to be of the same length as constituents, otherwise.
log	if set to "x", the frequency axis will be logarithmic.
mgp	3-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.
mar	value to be used with par("mar").
	optional arguments passed to plotting functions.

## Historical note

An argument named labelIf was removed in July 2016, because it was discovered never to have worked as documented, and because the more useful argument constituents had been added.

## Author(s)

Dan Kelley

## See Also

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method,plot,bremen-method,plot,cm-method,plot,coastline-method,plot,ctd-method,plot,gps-method,plot,ladp-method,plot,lisst-method,plot,lobo-method,plot,met-method,
```

304 plot,topo-method

```
plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,topo-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to tidem data: [[,tidem-method, [[<-,tidem-method, predict.tidem, summary,tidem-method, tidedata, tidem-class, tidemAstron, tidemVuf, tidem
```

## **Examples**

```
## Not run:
library(oce)
data(sealevel)
tide <- tidem(sealevel)
plot(tide)
## End(Not run)</pre>
```

plot, topo-method

Plot a Topo Object

#### **Description**

This plots contours of topographic elevation. The plot aspect ratio is set based on the middle latitude in the plot. The line properties, such as land.lwd, may either be a single item, or a vector; in the latter case, the length must match the length of the corresponding properties, e.g. land.z.

## Usage

```
## S4 method for signature 'topo'
plot(x, xlab = "", ylab = "", asp, clongitude, clatitude,
    span, expand = 1.5, water.z, col.water, lty.water, lwd.water, land.z,
    col.land, lty.land, lwd.land, geographical = FALSE, location = "topright",
    mgp = getOption("oceMgp"), mar = c(mgp[1] + 1, mgp[1] + 1, 1, 1),
    debug = getOption("oceDebug"), ...)
```

## **Arguments**

X	A topo object, i.e. inheriting from topo-class.
xlab, ylab	Character strings giving a label for the x and y axes.
asp	Aspect ratio for plot. The default is for plot.coastline to set the aspect ratio to give natural latitude-longitude scaling somewhere near the centre latitude on the plot. Often, it makes sense to set asp yourself, e.g. to get correct shapes at 45N, use asp=1/cos(45*pi/180). Note that the land mass is not symmetric about the equator, so to get good world views you should set asp=1 or set ylim to be symmetric about zero. Any given value of asp is ignored, if clongitude and clatitude are given.
clongitude	Optional center longitude of map, in degrees east; see clatitude.

plot,topo-method 305

clatitude	Optional center latitude of map, in degrees north. If this and clongitude are provided, then any provided value of asp is ignored, and instead the plot aspect ratio is computed based on the center latitude. Also, if clongitude and clatitude are provided, then span must be, also.
span	Optional suggested span of plot, in kilometers (must be supplied, if clongitude and clatitude are supplied).
expand	Numerical factor for the expansion of plot limits, showing area outside the plot, e.g. if showing a ship track as a coastline, and then an actual coastline to show the ocean boundary. The value of expand is ignored if either xlim or ylim is given.
water.z	Depths at which to plot water contours. If not provided, these are inferred from the data.
col.water	Colours corresponding to water.z values. If not provided, these will be "fill" colours from oce.colorsGebco.
lty.water	Line type(s) for water contours.
lwd.water	Line width(s) for water contours.
land.z	Depths at which to plot land contours. If not provided, these are inferred from the data. If set to NULL, no land contours will be plotted.
col.land	Colours corresponding to land.z values. If not provided, these will be "fill" colours from oce.colorsGebco.
lty.land	Line type(s) for land contours.
lwd.land	Line width(s) for land contours.
geographical	Logical, indicating whether to plot latitudes and longitudes without minus signs.
location	Location for a legend (or "none", for no legend).
mgp	3-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.
mar	Four-element numerical vector to be used with par("mar").
debug	Numerical value, with positive values indicating higher levels of debugging.
	Additional arguments passed on to plotting functions.

#### Author(s)

Dan Kelley

## See Also

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot,bremen-method, plot,cm-method, plot,coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,windrose-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to topo data: [[,topo-method,[[<-,topo-method,as.topo,download.topo,read.topo,subset,topo-method,summary,topo-method,topo-class,topoInterpolate,topoWorld
```

306 plot, windrose-method

## **Examples**

```
library(oce)
data(topoWorld)
plot(topoWorld, clongitude=-60, clatitude=45, span=10000)
```

plot, windrose-method *Plot Windrose data* 

## **Description**

Plot a windrose object, i.e. one inheriting from windrose-class.

#### **Usage**

```
## S4 method for signature 'windrose'
plot(x, type = c("count", "mean", "median", "fivenum"),
   convention = c("meteorological", "oceanographic"),
   mgp = getOption("oceMgp"), mar = c(mgp[1], mgp[1], 1 + mgp[1], mgp[1]),
   col, ...)
```

## **Arguments**

Y	A windrose object, e.g. inheriting from windrose-class.

type The thing to be plotted, either the number of counts in the angle interval, the

mean of the values in the interval, the median of the values, or a fivenum repre-

sentation of the values.

convention String indicating whether to use meteorological convention or oceanographic

convention for the arrows that emanate from the centre of the rose. In meteorological convection, an arrow emanates towards the right on the diagram if the wind is from the east; in oceanographic convention, such an arrow indicates

flow to the east.

mgp Three-element numerical vector to use for par(mgp), and also for par(mar),

computed from this. The default is tighter than the R default, in order to use

more space for the data and less for the axes.

mar Four-element numerical vector to be used with par("mar").

col Optional list of colours to use. If not set, the colours will be c("red", "pink", "blue", "lightgray").

For the first three types of plot, the first colour in this list is used to fill in the rose, the third is used for the petals of the rose, and the fourth is used for grid lines. For the "fivenum" type, the first colour is used for the inter-quartile range, the second is used outside this range, the third is used for the median, and the fourth

is, again, used for the grid lines.

. . . Optional arguments passed to plotting functions.

plotInset 307

#### Author(s)

Dan Kelley

#### See Also

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot, met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot, sealevel-method, plot, section-method, plot,tidem-method, plot,topo-method, plotProfile, plotScan, plotTS, tidem-class

Other things related to windrose data: [[,windrose-method, [[<-,windrose-method, as.windrose, summary,windrose-method, windrose-class]
```

## **Examples**

```
library(oce)
opar <- par(no.readonly = TRUE)
xcomp <- rnorm(360) + 1
ycomp <- rnorm(360)
wr <- as.windrose(xcomp, ycomp)
par(mfrow=c(1, 2))
plot(wr)
plot(wr, "fivenum")
par(opar)</pre>
```

plotInset

Plot an Inset Diagram

## **Description**

Adds an inset diagram to an existing plot. Note that if the inset is a map or coastline, it will be necessary to supply inset=TRUE to prevent the inset diagram from occupying the whole device width. After plotInset() has been called, any further plotting will take place within the inset, so it is essential to finish a plot before drawing an inset.

## Usage

```
plotInset(xleft, ybottom, xright, ytop, expr, mar = c(2, 2, 1, 1),
  debug = getOption("oceDebug"))
```

## **Arguments**

xleft location of left-hand of the inset diagram, in the existing plot units. (PROVI-SIONAL FEATURE: this may also be "bottomleft", to put the inset there. Eventually, other positions may be added.)

ybottom location of bottom side of the inset diagram, in the existing plot units.

308 plotPolar

xright location of right-hand side of the inset diagram, in the existing plot units.

ytop location of top side of the inset diagram, in the existing plot units.

An expression that draws the inset plot. This may be a single plot command, or a sequence of commands enclosed in curly braces.

mar margins, in line heights, to be used at the four sides of the inset diagram. (This is often helpful to save space.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

## Author(s)

Dan Kelley

## **Examples**

plotPolar

Draw a Polar Plot

# **Description**

Creates a crude polar plot.

## Usage

```
plotPolar(r, theta, debug = getOption("oceDebug"), ...)
```

## Arguments

r radii of points to plot.

theta angles of points to plot, in degrees.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

optional arguments passed to the lower-level plotting functions.

#### Author(s)

Dan Kelley

## **Examples**

```
library(oce)
r <- rnorm(50, mean=2, sd=0.1)
theta <- runif(50, 0, 360)
plotPolar(r, theta)</pre>
```

plotProfile

Plot a CTD Profile

## **Description**

Plot a profile, showing variation of some quantity (or quantities) with pressure, using the oceano-graphic convention of putting lower pressures nearer the top of the plot. This works for any oce object that has a pressure column in its data slot. The colours (col.salinity, etc.) are only used if two profiles appear on a plot.

#### Usage

```
plotProfile(x, xtype = "salinity+temperature", ytype = "pressure",
    eos = getOption("oceEOS", default = "gsw"), lty = 1, xlab = NULL,
    ylab = NULL, col = "black", col.salinity = "darkgreen",
    col.temperature = "red", col.rho = "blue", col.N2 = "brown",
    col.dpdt = "darkgreen", col.time = "darkgreen", pt.bg = "transparent",
    grid = TRUE, col.grid = "lightgray", lty.grid = "dotted", Slim, Clim,
    Tlim, densitylim, N2lim, Rrholim, dpdtlim, timelim, plim, xlim, ylim,
    lwd = par("lwd"), xaxs = "r", yaxs = "r", cex = 1, pch = 1,
    useSmoothScatter = FALSE, df, keepNA = FALSE, type = "l",
    mgp = getOption("oceMgp"), mar, add = FALSE, inset = FALSE,
    debug = getOption("oceDebug", 0), ...)
```

#### **Arguments**

x A ctd object, i.e. one inheriting from ctd-class.

xtype Item(s) plotted on the x axis, either a vector of length equal to that of pressure in the data slot, or a text code from the list below.

- "salinity" Profile of salinity.
- "conductivity" Profile of conductivity.
- "temperature" Profile of *in-situ* temperature.
- "theta" Profile of potential temperature.
- "density" Profile of density (expressed as  $\sigma_{\theta}$ ).
- "index" Index of sample (useful for working with ctdTrim).
- "salinity+temperature" Profile of salinity and temperature within a single axis frame.
- "N2" Profile of square of buoyancy frequency  $N^2$ , calculated with swN2 with an optional argument setting of df=length(x[["pressure"]])/4 to do some smoothing.
- "density+N2" Profile of sigma0 and the square of buoyancy frequency within a single axis frame.
- "density+dpdt" Profile of sigma0 and dP/dt for the sensor. The latter is useful in indicating problems with the deployment. It is calculated by first differencing pressure and then using a smoothing spline on the result (to avoid grid-point wiggles that result because the SBE software only writes 3 decimal places in pressure). Note that dP/dt may be off by a scale factor; this should not be a problem if there is a time column in the data slot, or a sample.rate in the metadata slot.
- "sigma0", "sigma1", "sigma2", "sigma3" and "sigma4" Profile of potential density referenced to Odbar (i.e. the surface), 1000dbar, 2000dbar, 3000dbar, and 4000dbar.
- "spice" Profile of spice.
- "Rrho" Profile of Rrho, defined in the diffusive sense.
- "RrhoSF" Profile of Rrho, defined in the salt-finger sense.

ytype variable to use on y axis. The valid choices are: "pressure" (the default), "z", "depth" and "sigmaTheta".

eos equation of state to be used, either "unesco" or "gsw".

lty line type for the profile.

xlab optional label for x axis (at top of plot).

ylab optional label for y axis. Set to "" to prevent labelling the axis.

col colour for a general profile.

col. salinity colour for salinity profile (see "Details").

col.temperature

colour for temperature (see "Details").

col.rho colour for density (see "Details").

col. N2 colour for square of buoyancy frequency (see "Details").

col.dpdt colour for dP/dt.
col.time colour for delta-time.

pt.bg inside colour for symbols with pch in 21:25

grid logical, set to TRUE to get a grid.

col.grid colour for grid.

lty.grid line type for grid.

Slim Optional limit for S axis

Clim Optional limit for conductivity axis

Tlim Optional limit for T axis

densitylim Optional limit for density axis

N2lim Optional limit for N2 axis

Rrholim Optional limit for Rrho axis

dpdtlim Optional limit for dp/dt axis

timelim Optional limit for delta-time axis

plim Optional limit for pressure axis, ignored unless ytype=="pressure", in which

case it takes precedence over ylim.

xlim Optional limit for x axis, which can apply to any plot type. This is ignored if

the plotted x variable is something for which a limit may be specified with an argument, e.g. xlim is ignored for a salinity profile, because Slim ought to be

given in such a case.

ylim Optional limit for y axis, which can apply to any plot type, although is overrid-

den by plimif ytype is "pressure" or by densitylimif ytype is "sigmaTheta".

lwd value for data line

value of par xaxs to use

value of par yaxs to use

cex size to be used for plot symbols (see par)

pch code for plotting symbol (see par).

useSmoothScatter

boolean, set to TRUE to use smoothScatter instead of plot to draw the plot.

df optional argument, passed to swN2 if provided, and if a plot using  $N^2$  is re-

quested.

keepNA FALSE

type type of plot to draw, using the same scheme as plot.

mgp 3-element numerical vector to use for par(mgp), and also for par(mar), com-

puted from this. The default is tighter than the R default, in order to use more

space for the data and less for the axes.

mar Four-element numerical value to be used to set the plot margins, with a call to

par(mar) prior to the plot. If this is not supplied, a reasonable default will be

set up.

add	A logical value that controls whether to add to an existing plot. (It makes sense to use add=TRUE in the panel argument of a coplot, for example.)
inset	A logical value indicating whether to draw an inset plot. Setting this to TRUE will prevent the present function from adjusting the margins, which is necessary because margin adjustment is the basis for the method used by plotInset.
debug	a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.
	optional arguments passed to other functions. A common example is to set df, for use in swN2 calculations.

#### Value

None.

#### Author(s)

Dan Kelley

#### See Also

read.ctd scans ctd information from a file, plot,ctd-method is a general plotting function for ctd objects, and plotTS plots a temperature-salinity diagrams.

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotScan, plotTS, tidem-class
```

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

## **Examples**

```
library(oce)
data(ctd)
plotProfile(ctd, xtype="temperature")
```

plotScan 313

plotScan Plot CTD data in a Low-Level Fashion
---

## **Description**

Plot CTD data as time-series against scan number, to help with trimming extraneous data from a CTD cast.

# Usage

```
plotScan(x, which = 1, xtype = "scan", type = "l",
   mgp = getOption("oceMgp"), mar = c(mgp[1] + 1.5, mgp[1] + 1.5, mgp[1],
   mgp[1]), ...)
```

## **Arguments**

х	A ctd object, i.e. one inheriting from ctd-class.
which	Numerical vector numerical codes specifying the panels to draw: 1 for pressure vs scan, 2 for diff(pressure) vs scan, 3 for temperature vs scan, and 4 for salinity vs scan.
xtype	Character string indicating variable for the x axis. May be "scan" (the default) or "time". In the former case, a scan variable will be created using seq_along, if necessary. In the latter case, an error results if the data slot of x lacks a variable called time.
type	Character indicating the line type, as for plot.default. The default is "1", meaning to connect data with line segments. Another good choice is "o", to add points at the data.
mgp	Three-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.
mar	Four-element vector be used with par("mar"). If set to NULL, then par("mar") is used. A good choice for a TS diagram with a palette to the right is mar=par("mar")+c(0, 0, 0, 1)).
	Optional arguments passed to plotting functions.

## Author(s)

Dan Kelley

## See Also

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,topo-method, plot,windrose-method, plotProfile, plotTS, tidem-class
```

314 plotSticks

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

## **Examples**

```
library(oce)
data(ctdRaw)
plotScan(ctdRaw)
abline(v=c(130, 350), col='red') # useful for ctdTrim()
```

plotSticks

Draw a Stick Plot

## **Description**

The arrows are drawn with directions on the graph that match the directions indicated by the u and v components. The arrow size is set relative to the units of the y axis, according to the value of yscale, which has the unit of v divided by the unit of y. The interpretation of diagrams produced by plotSticks can be difficult, owing to overlap in the arrows. For this reason, it is often a good idea to smooth u and v before using this function.

## Usage

```
plotSticks(x, y, u, v, yscale = 1, add = FALSE, length = 1/20,
   mgp = getOption("oceMgp"), mar = c(mgp[1] + 1, mgp[1] + 1, 1, 1 +
   par("cex")), xlab = "", ylab = "", col = 1, ...)
```

## **Arguments**

x	x coordinates of stick origins.
У	y coordinates of stick origins. If not supplied, $0$ will be used; if length is less than that of $x$ , the first number is repeated and the rest are ignored.
u	x component of stick length.
V	y component of stick length.
yscale	scale from u and v to y (see "Description").
add	boolean, set TRUE to add to an existing plot.
length	value to be provided to arrows; here, we set a default that is smaller than normally used, because these plots tend to be crowded in oceanographic applications.
mgp	3-element numerical vector to use for par(mgp), and also for par(mar), computed from this. The default is tighter than the R default, in order to use more space for the data and less for the axes.

plotTaylor 315

value to be used with par("mar").
 xlab, ylab labels for the plot axes. The default is not to label them.
 col colour of sticks, in either numerical or character format. This is made to have length matching that of x by a call to rep, which can be handy in e.g. colourizing a velocity field by day.
 graphical parameters passed down to arrows. It is common, for example, to use smaller arrow heads than arrows uses; see "Examples".

## Author(s)

Dan Kelley

## **Examples**

```
library(oce)
# Flow from a point source
n <- 16
x \leftarrow rep(0, n)
y \leftarrow rep(0, n)
theta <- seq(0, 2*pi, length.out=n)
u <- sin(theta)</pre>
v <- cos(theta)</pre>
plotSticks(x, y, u, v, xlim=c(-2, 2), ylim=c(-2, 2))
rm(n, x, y, theta, u, v)
# Oceanographic example
data(met)
t <- met[["time"]]</pre>
u <- met[["u"]]
v <- met[["v"]]</pre>
p <- met[["pressure"]]</pre>
oce.plot.ts(t, p)
plotSticks(t, 99, u, v, yscale=25, add=TRUE)
```

plotTaylor

Plot a Model-data Comparison Diagram

## **Description**

Creates a diagram as described by Taylor (2001). The graph is in the form of a semicircle, with radial lines and spokes connecting at a focus point on the flat (lower) edge. The radius of a point on the graph indicates the standard deviation of the corresponding quantity, i.e. x and the columns in y. The angle connecting a point on the graph to the focus provides an indication of correlation coefficient with respect to x. The "east" side of the graph indicates R=1, while R=0 is at the "north edge" and R=-1 is at the "west" side. The x data are indicated with a bullet on the graph, appearing on the lower edge to the right of the focus at a distance indicating the standard deviation

316 plotTaylor

of x. The other points on the graph represent the columns of y, coded automatically or with the supplied values of pch and col. The example shows two tidal models of the Halifax sealevel data, computed with tidem with just the M2 component and the S2 component; the graph indicates that the M2 model is much better than the S2 model.

## Usage

```
plotTaylor(x, y, scale, pch, col, labels, pos, ...)
```

## **Arguments**

X	a vector of reference values of some quantity, e.g. measured over time or space.
У	a matrix whose columns hold values of values to be compared with those in $x$ . (If $y$ is a vector, it is converted first to a one-column matrix).
scale	optional scale, interpreted as the maximum value of standard deviation.
pch	list of characters to plot, one for each column of y.
col	list of colours for points on the plot, one for each column of y.
labels	optional vector of strings to use for labelling the points.
pos	optional vector of positions for labelling strings. If not provided, labels will be to the left of the symbols.
	optional arguments passed by plotTaylor to more child functions.

## Author(s)

Dan Kelley

## References

Taylor, Karl E., 2001. Summarizing multiple aspects of model performance in a single diagram, *J. Geophys. Res.*, 106:D7, 7183–7192.

## **Examples**

```
library(oce)
data(sealevel)
x <- sealevel[["elevation"]]
M2 <- predict(tidem(sealevel, constituents="M2"))
S2 <- predict(tidem(sealevel, constituents=c("S2")))
plotTaylor(x, cbind(M2, S2))</pre>
```

plotTS 317

plotTS	Plot Temperature-Salinity Diagram
--------	-----------------------------------

## **Description**

Creates a temperature-salinity plot for a CTD cast, with labeled isopycnals.

## Usage

```
plotTS(x, inSitu = FALSE, type = "p", referencePressure = 0,
    nlevels = 6, levels, grid = TRUE, col.grid = "lightgray",
    lty.grid = "dotted", rho1000 = FALSE, eos = getOption("oceEOS", default
    = "gsw"), cex = par("cex"), col = par("col"), pch = par("pch"), bg,
    pt.bg = "transparent", col.rho = "darkgray", cex.rho = 3/4 * par("cex"),
    rotate = TRUE, useSmoothScatter = FALSE, xlab, ylab, Slim, Tlim,
    drawFreezing = TRUE, mgp = getOption("oceMgp"), mar = c(mgp[1] + 1.5,
    mgp[1] + 1.5, mgp[1], mgp[1]), lwd = par("lwd"), lty = par("lty"),
    lwd.rho = par("lwd"), lty.rho = par("lty"), add = FALSE,
    inset = FALSE, debug = getOption("oceDebug"), ...)
```

# Arguments

x	A ctd object, i.e. one inheriting from ctd-class.	
inSitu	A boolean indicating whether to use in-situ temperature or (the default) potential temperature, calculated with reference pressure given by referencePressure. This is ignored if eos="gsw", because those cases the y axis is necessarily the conservative formulation of temperature.	
type	representation of data, "p" for points, "1" for connecting lines, or "n" for no indication.	
referencePressure		
	reference pressure, to be used in calculating potential temperature, if inSitu is FALSE.	
nlevels	Number of automatically-selected isopycnal levels (ignored if levels is supplied).	
levels	Optional vector of desired isopycnal levels.	
grid	a flag that can be set to TRUE to get a grid.	
col.grid	colour for grid.	
lty.grid	line type for grid.	
rho1000	if TRUE, label isopycnals as e.g. 1024; if FALSE, label as e.g. 24	
eos	equation of state to be used, either "unesco" or "gsw".	
cex	character-expansion factor for symbols, as in par("cex").	
col	colour for symbols.	
pch	symbol type, as in par("pch").	

318 plotTS

bg optional colour to be painted under plotting area, before plotting. (This is useful for cases in which inset=TRUE.) inside colour for symbols with pch in 21:25 pt.bg col.rho colour for isopycnal lines. cex.rho size of isopycnal labels. rotate if TRUE, labels in right-hand margin are written vertically useSmoothScatter if TRUE, use smoothScatter to plot the points. xlab optional label for the x axis, with default "Salinity [PSU]". optional label for the y axis, with default "Temperature [C]". ylab Slim optional limits for salinity axis, otherwise inferred from data. Tlim optional limits for temperature axis, otherwise inferred from data. drawFreezing logical indication of whether to draw a freezing-point line. This is based on zero pressure. If eos="unesco" then swTFreeze is used to compute the curve, whereas if eos="gsw" then gsw\_CT\_freezing is used; in each case, zero pressure is used. 3-element numerical vector to use for par(mgp), and also for par(mar), commgp puted from this. The default is tighter than the R default, in order to use more space for the data and less for the axes. value to be used with par("mar"). If set to NULL, then par("mar") is used. A mar good choice for a TS diagram with a palette to the right is mar=par("mar")+c(0, 0, 0, 1). lwd line width of lines or symbols. line type of lines or symbols. lty lwd.rho line width for density curves. ltv.rho line type for density curves. a flag that controls whether to add to an existing plot. (It makes sense to use add add=TRUE in the panel argument of a coplot, for example.) set to TRUE for use within plotInset. The effect is to prevent the present funcinset tion from adjusting margins, which is necessary because margin adjustment is the basis for the method used by plotInset. debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more. optional arguments passed to plotting functions.

#### Value

A list is silently returned, containing xat and yat, values that can be used by oce.grid to add a grid to the plot.

#### Author(s)

Dan Kelley

predict.tidem 319

#### See Also

```
summary, ctd-method summarizes the information, while read.ctd scans it from a file.
```

summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot, ctd-method, plot, gps-method, plot, ladp-method, plot, lisst-method, plot, lobo-method, plot, met-method, plot, odf-method, plot, rsk-method, plot, satellite-method, plot, sealevel-method, plot, section-method, plot, tidem-method, plot, topo-method, plot, windrose-method, plotProfile, plotScan, tidem-class

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method,

#### **Examples**

library(oce)
data(ctd)
plotTS(ctd)

predict.tidem

Predict a Time Series from a Tidem Tidal Model

## Description

Predict a time series from a tidal model. This is a wrapper around the predict method for object\$model.

## Usage

```
## S3 method for class 'tidem
predict(object, newdata, ...)
```

## **Arguments**

object A tidem object, i.e. one inheriting from tidem-class.

newdata optional vector of POSIXt times at which to make the prediction. If not present,

predict. tidem uses the times that were provided in the original call to tidem.

... optional arguments passed on to children.

## Value

A vector of predictions.

#### Author(s)

Dan Kelley

320 prettyPosition

## See Also

Other things related to tidem data: [[,tidem-method, [[<-,tidem-method, plot,tidem-method, summary,tidem-method, tidedata, tidem-class, tidemAstron, tidemVuf, tidem

## **Examples**

```
## Not run:
library(oce)
# 1. tidal anomaly
data(sealevelTuktoyaktuk)
time <- sealevelTuktoyaktuk[["time"]]</pre>
elevation <- sealevelTuktoyaktuk[["elevation"]]</pre>
oce.plot.ts(time, elevation, type='l', ylab="Height [m]", ylim=c(-2, 6))
tide <- tidem(sealevelTuktoyaktuk)</pre>
lines(time, elevation - predict(tide), col="red")
abline(h=0, col="red")
# 2. prediction at specified times
data(sealevel)
m <- tidem(sealevel)</pre>
## Check fit over 2 days (interpolating to finer timescale)
look <- 1:48
time <- sealevel[["time"]]</pre>
elevation <- sealevel[["elevation"]]</pre>
oce.plot.ts(time[look], elevation[look])
# 360s = 10 minute timescale
t \leftarrow seq(from=time[1], to=time[max(look)], by=360)
lines(t, predict(m,newdata=t), col='red')
legend("topright", col=c("black","red"),
legend=c("data","model"),lwd=1)
## End(Not run)
```

prettyPosition

Pretty lat/lon in deg, min, sec

## **Description**

Round a geographical positions in degrees, minutes, and seconds Depending on the range of values in x, rounding is done to degrees, half-degrees, minutes, etc.

# Usage

```
prettyPosition(x, debug = getOption("oceDebug"))
```

processingLog<- 321

## **Arguments**

x a series of one or more values of a latitude or longitude, in decimal degrees debug set to a positive value to get debugging information during processing.

## Value

A vector of numbers that will yield good axis labels if formatPosition is used.

# Author(s)

Dan Kelley

## **Examples**

```
library(oce)
formatPosition(prettyPosition(10+1:10/60+2.8/3600))
```

processingLog<-

Add an item to a processing log (in place)

## **Description**

Add an item to a processing log (in place)

# Usage

```
processingLog(x) <- value</pre>
```

# **Arguments**

x An oce object.

value A character string with the description of the logged activity.

# Examples

```
data(ctd)
processingLogShow(ctd)
processingLog(ctd) <- "test"
processingLogShow(ctd)</pre>
```

322 processingLogItem

processingLogAppend

Append an item to a processing log

# Description

Append an item to a processing log

## Usage

```
processingLogAppend(h, value = "")
```

## **Arguments**

h either the processingLog slot of an object, or an oce object from which the

processingLog will be extracted

value A string indicating the text of the log entry.

## Value

An list containing items named time and value, i.e. the times of entries and the text notations of those entries..

processingLogItem

Create an item that can be inserted into a processing log

# **Description**

A function is used internally to initialize processing logs. Users will probably prefer to use processingLogAppend instead.

## Usage

```
processingLogItem(value = "")
```

## **Arguments**

value

A string that will be used for the item.k

#### Value

A list containing time, which is the Sys.time at the moment the function is called and value, a string that is set to the argument of the same name.

processingLogShow 323

processingLogShow	Show the processing log of an oce object	

## **Description**

Show the processing log of an oce object

## Usage

```
processingLogShow(x)
```

# Arguments

x An oce object.

pwelch Welch periodogram

## **Description**

Compute periodogram using the Welch (1967) method. First, x is broken up into chunks, overlapping as specified by noverlap. These chunks are then detrended with detrend, multiplied by the window, and then passed to spectrum. The resulting spectra are then averaged, with the results being stored in spec of the return value. Other entries of the return value mimic those returned by spectrum.

## Usage

```
pwelch(x, window, noverlap, nfft, fs, spectrumtype, esttype, plot = TRUE,
  debug = getOption("oceDebug"), ...)
```

# Arguments

x	a vector or timeseries to be analyzed. If a timeseries, then there is no need to specify fs.
window	window specification, either a single value giving the number of windows to use, or a vector of window coefficients. If not specified, then 8 windows are used, each with a Hamming (raised half-cosine) window.
noverlap	number of points to overlap between windows. If not specified, this will be set to half the window length.
nfft	length of FFT. This cannot be given if window is given, and the latter is a single integer.
fs	frequency of time-series. If $x$ is a time-series, and if $f$ s is supplied, then time-series is altered to have frequency $f$ s.

324 pwelch

spectrumtype	not used (yet)
esttype	not used (yet)
plot	logical, set to TRUE to plot the spectrum.
debug	a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.
	optional extra arguments to be passed to spectrum. Unless specified in this list, spectrum is called with plot=FALSE to prevent plotting the separate spectra, and with taper=0, which is not needed with the default Hanning window. However, the other defaults of spectrum are used, e.g. detrend=TRUE.

#### Value

List mimicking the return value from spectrum, containing frequency freq, spectral power spec, degrees of freedom df, bandwidth bandwidth, etc.

## Bugs

Both bandwidth and degrees of freedom are just copied from the values for one of the chunk spectra, and are thus incorrect. That means the cross indicated on the graph is also incorrect.

## Author(s)

Dan Kelley

#### References

Welch, P. D., 1967. The Use of Fast Fourier Transform for the Estimation of Power Spectra: A Method Based on Time Averaging Over Short, Modified Periodograms. *IEEE Transactions on Audio Electroacoustics*, AU-15, 70–73.

## **Examples**

```
library(oce)
Fs <- 1000
t < - seq(0, 0.296, 1/Fs)
x <- \cos(2 * pi * t * 200) + rnorm(n=length(t))
xts <- ts(x, frequency=Fs)</pre>
s <- spectrum(xts, spans=c(3,2), main="random + 200 Hz", log='no')
w <- pwelch(xts, plot=FALSE)</pre>
lines(w$freq, w$spec, col="red")
w2 <- pwelch(xts, nfft=75, plot=FALSE)
lines(w2$freq, w2$spec, col='green')
abline(v=200, col="blue", lty="dotted")
cat("Checking spectral levels with Parseval's theorem:\n")
cat("var(x)
                                         = ", var(x), "\n")
cat("2 * sum(s\$spec) * diff(s\$freq[1:2]) = ", 2 * sum(s\$spec) * diff(s\$freq[1:2]), "\n")
cat("sum(w\$spec) * diff(s\$freq[1:2]) = ", sum(w\$spec) * diff(w\$freq[1:2]), "\n")
cat("sum(w2\$spec) * diff(s\$freq[1:2]) = ", sum(w2\$spec) * diff(w2\$freq[1:2]), "\n")
## co2
```

rangeExtended 325

rangeExtended

Calculate Range, Extended a Little, as is Done for Axes

## **Description**

This is analogous to what is done as part of the R axis range calculation, in the case where xaxs="r".

## Usage

```
rangeExtended(x, extend = 0.04)
```

## **Arguments**

x a numeric vector.

extend fraction to extend on either end

## Value

A two-element vector with the extended range of x.

## Author(s)

Dan Kelley

rangeLimit

Substitute NA for data outside a range

## **Description**

Substitute NA for data outside a range, e.g. to remove wild spikes in data.

## Usage

```
rangeLimit(x, min, max)
```

326 read.ad2cp

## **Arguments**

X	vector of values
min	minimum acceptable value. If not supplied, and if $\max$ is also not supplied, a $\min$ of the 0.5 percentile will be used.

maximum acceptable value. If not supplied, and if min is also not supplied, a

min of the 0.995 percentile will be used.

## Author(s)

max

Dan Kelley

## **Examples**

```
ten.to.twenty <- rangeLimit(1:100, 10, 20)</pre>
```

read.ad2cp

Read an AD2CP File

## **Description**

This function, introduced in April 2017, is just a temporary interface for separate interpretation code that lives in the 1219 issue directory. THIS IS ONLY FOR DEVELOPERS.

## Usage

```
read.ad2cp(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  longitude = NA, latitude = NA, orientation, distance, monitor = FALSE,
 despike = FALSE, processingLog, debug = getOption("oceDebug"), ...)
```

# **Arguments**

to

file	a connection or a character string giving the name of the file to load. (For read.adp.sontek.serial, this is generally a list of files, which will be concatenated.)
from	indication of the first profile to read. This can be an integer, the sequence number of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC

timezone). See "Examples", and make careful note of the use of the tz argument. If from is not supplied, it defaults to 1.

an optional indication of the last profile to read, in a format as described for from. As a special case, to=0 means to read the file to the end. If to is not supplied, then it defaults to 0.

read.ad2cp 327

by an optional indication of the stride length to use while walking through the file.

If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files *only*, there are some extra features to avoid running out of memory; see "Memory

considerations".)

tz character string indicating time zone to be assumed in the data.

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

orientation Optional character string specifying the orientation of the sensor, provided for

those cases in which it cannot be inferred from the data file. The valid choices

are "upward", "downward", and "sideward".

distance Optional vector holding the distances of bin centres from the sensor. This argu-

ment is ignored except for Nortek profilers, and need not be given if the function determines the distances correctly from the data. The problem is that the distance is poorly documented in the Nortek System Integrator Guide (2008 edition, page 31), so the function must rely on word-of-mouth formulae that do not

work in all cases.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

#### Value

An adp object, i.e. one inheriting from adp-class.

## Author(s)

Dan Kelley

# See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamName, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

328 read.adp

## **Examples**

```
## Not run:
f <- "/Users/kelley/Dropbox/oce_ad2cp/labtestsig3.ad2cp"
d <- read.ad2cp(f, 1, 10, 1)
## End(Not run)</pre>
```

read.adp

Read an ADP File

# **Description**

Read an ADP data file, producing an adp object, i.e. one inheriting from adp-class.

## Usage

```
read.adp(file, from, to, by, tz = getOption("oceTz"), longitude = NA,
  latitude = NA, manufacturer = c("rdi", "nortek", "sontek"),
  monitor = FALSE, despike = FALSE, processingLog,
  debug = getOption("oceDebug"), ...)
```

## **Arguments**

guments	
file	a connection or a character string giving the name of the file to load. (For read.adp.sontek.serial, this is generally a list of files, which will be concatenated.)
from	indication of the first profile to read. This can be an integer, the sequence number of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argument. If from is not supplied, it defaults to 1.
to	an optional indication of the last profile to read, in a format as described for from. As a special case, to=0 means to read the file to the end. If to is not supplied, then it defaults to 0.
by	an optional indication of the stride length to use while walking through the file. If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files <i>only</i> , there are some extra features to avoid running out of memory; see "Memory considerations".)
tz	character string indicating time zone to be assumed in the data.
longitude	optional signed number indicating the longitude in degrees East.
latitude	optional signed number indicating the latitude in degrees North.
manufacturer	a character string indicating the manufacturer, used by the general function

read.adp to select a subsidiary function to use, such as read.adp.nortek.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

## **Details**

Several file types can be handled. Some of these functions are wrappers that map to device names, e.g. read.aquadoppProfiler does its work by calling read.adp.nortek; in this context, it is worth noting that the "aquadopp" instrument is a one-cell profiler that might just as well have been documented under the heading read.adv.

#### Value

An adp object, i.e. one inheriting from adp-class.

#### Author(s)

Dan Kelley and Clark Richards

#### See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

read.adp.nortek

Read a Nortek ADP File

#### **Description**

Read a Nortek ADP File

## Usage

```
read.adp.nortek(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  longitude = NA, latitude = NA, type = c("aquadoppHR",
  "aquadoppProfiler", "aquadopp"), orientation, distance, monitor = FALSE,
  despike = FALSE, processingLog, debug = getOption("oceDebug"), ...)
```

#### **Arguments**

file a connection or a character string giving the name of the file to load. (For

read.adp.sontek.serial, this is generally a list of files, which will be con-

catenated.)

from indication of the first profile to read. This can be an integer, the sequence num-

ber of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argu-

ment. If from is not supplied, it defaults to 1.

to an optional indication of the last profile to read, in a format as described for

from. As a special case, to=0 means to read the file to the end. If to is not

supplied, then it defaults to 0.

by an optional indication of the stride length to use while walking through the file.

If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files *only*, there are some extra features to avoid running out of memory; see "Memory

considerations".)

tz character string indicating time zone to be assumed in the data.

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

type a character string indicating the type of instrument.

orientation optional character string specifying the orientation of the sensor, provided for

those cases in which it cannot be inferred from the data file. The valid choices

are "upward", "downward", and "sideward".

distance optional vector holding the distances of bin centres from the sensor. This argu-

ment is ignored except for Nortek profilers, and need not be given if the function determines the distances correctly from the data. The problem is that the distance is poorly documented in the Nortek System Integrator Guide (2008 edition, page 31), so the function must rely on word-of-mouth formulae that do not

work in all cases.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

## Value

An adp object, i.e. one inheriting from adp-class.

read.adp.rdi 331

### Author(s)

Dan Kelley

#### References

1. Information on Nortek profilers (including the System Integrator Guide, which explains the data format byte-by-byte) is available at <a href="http://www.nortekusa.com/">http://www.nortekusa.com/</a>. (One must join the site to see the manuals.)

2. The Nortek Knowledge Center http://www.nortekusa.com/en/knowledge-center may be of help if problems arise in dealing with data from Nortek instruments.

#### See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.adp.radp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

read.adp.rdi

Read a Teledyne/RDI ADP File

## Description

Read a Teledyne/RDI ADCP file (called 'adp' in oce).

### Usage

```
read.adp.rdi(file, from, to, by, tz = getOption("oceTz"), longitude = NA,
  latitude = NA, type = c("workhorse"), monitor = FALSE,
  despike = FALSE, processingLog, testing = FALSE,
  debug = getOption("oceDebug"), ...)
```

## **Arguments**

file a connection or a character string giving the name of the file to load. (For

read.adp.sontek.serial, this is generally a list of files, which will be con-

catenated.)

from indication of the first profile to read. This can be an integer, the sequence num-

ber of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argu-

ment. If from is not supplied, it defaults to 1.

to an optional indication of the last profile to read, in a format as described for

from. As a special case, to=0 means to read the file to the end. If to is not

supplied, then it defaults to 0.

332 read.adp.rdi

by an optional indication of the stride length to use while walking through the file.

If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files *only*, there are some extra features to avoid running out of memory; see "Memory

considerations".)

tz character string indicating time zone to be assumed in the data.

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

type character string indicating the type of instrument.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

testing logical value (IGNORED).

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

### **Details**

As of 2016-09-25, this function has provisional functionality to read data from the new "SentinelV" series ADCP – essentially a combination of a 4 beam workhorse with an additional vertical centre beam.

If a heading bias had been set with the EB command during the setup for the deployment, then a heading bias will have been stored in the file's header. This value is stored in the object's metadata as metadata\$heading.bias. **Importantly**, this value is subtracted from the headings stored in the file, and the result of this subtraction is stored in the objects heading value (in data\$heading). It should be noted that read.adp.rdi() was tested for firmware version 16.30. For other versions, there may be problems. For example, the serial number is not recognized properly for version 16.28.

In Teledyne/RDI ADP data files, velocities are coded to signed 2-byte integers, with a scale factor being used to convert to velocity in metres per second. These two facts control the maximum recordable velocity and the velocity resolution, values that may be retrieved for an ADP object name d with d[["velocityMaximum"]] and d[["velocityResolution"]].

# Value

An adp object, i.e. one inheriting from adp-class.

### **Memory considerations**

For RDI files only, and only in the case where by is not specified, an attempt is made to avoid running out of memory by skipping some profiles in large input files. This only applies if from and to are both integers; if they are times, none of the rest of this section applies.

read.adp.rdi 333

A key issue is that RDI files store velocities in 2-byte values, which is not a format that R supports. These velocities become 8-byte (numeric) values in R. Thus, the R object created by read.adp.rdi will require more memory than that of the data file. A scale factor can be estimated by ignoring vector quantities (e.g. time, which has just one value per profile) and concentrating on matrix properties such as velocity, backscatter, and correlation. These three elements have equal dimensions. Thus, each 4-byte slide in the data file (2 bytes + 1 byte + 1 byte) corresponds to 10 bytes in the object (8 bytes + 1 byte + 1 byte). Rounding up the resultant 10/4 to 3 for safety, we conclude that any limit on the size of the R object corresponds to a 3X smaller limit on file size.

Various things can limit the size of objects in R, but a strong upper limit is set by the space the operating system provides to R. The least-performant machines in typical use appear to be Microsoft-Windows systems, which limit R objects to about 2e6 bytes [3]. Since R routinely duplicates objects for certain tasks (e.g. for call-by-value in function evaluation), read.adp.rdi uses a safety factor in its calculation of when to auto-decimate a file. This factor is set to 3, based partly on the developers' experience with datasets in their possession. Multiplied by the previously stated safety factor of 3, this suggests that the 2 GB limit on R objects corresponds to approximately a 222 MB limit on file size. In the present version of read.adp.rdi, this value is lowered to 200 MB for simplicity. Larger files are considered to be "big", and are decimated unless the user supplies a value for the by argument.

The decimation procedure has two cases.

- 1. Case 1. If from=1 and to=0 (or if neither from or to is given), then the intention is to process the full span of the data. If the input file is under 200 MB, then by defaults to 1, so that all profiles are read. For larger files, by is set to the ceiling of the ratio of input file size to 200 MB.
- 2. Case 2. If from exceeds 1, and/or to is nonzero, then the intention is to process only an interior subset of the file. In this case, by is calculated as the ceiling of the ratio of bbp\*(1+to-from) to 200 MB, where bbp is the number of file bytes per profile. Of course, by is set to 1, if this ratio is less than 1.

If the result of these calculations is that by exceeds 1, then messages are printed to alert the user that the file will be decimated, and also monitor is set to TRUE, so that a textual progress bar is shown.

## Author(s)

Dan Kelley and Clark Richards

## References

- 1. Teledyne-RDI, 2007. WorkHorse commands and output data format. P/N 957-6156-00 (November 2007). (Section 5.3 h details the binary format, e.g. the file should start with the byte 0x7f repeated twice, and each profile starts with the bytes 0x80, followed by 0x00, followed by the sequence number of the profile, represented as a little-endian two-byte short integer. read.adp.rdi uses these sequences to interpret data files.)
- 2. Teledyne-RDI, 2015. V Series output data format. P/N 95D-6022-00 (May 2015).
- 3. See Memory-limits for more on the 2 GB limit for R on windows machines (but note that this documentation erroneously states the unit as Gb, which is typically used for gigabits).

read.adp.sontek

## See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.sontek.serial,read.adp.sontek,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

read.adp.sontek

Read a Sontek ADP File

## **Description**

Read a Sontek acoustic-Doppler profiler file [1].

## Usage

```
read.adp.sontek(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  longitude = NA, latitude = NA, type = c("adp", "pcadp"),
  monitor = FALSE, despike = FALSE, processingLog,
  debug = getOption("oceDebug"), ...)
```

## **Arguments**

file	a connection or a character string giving the name of the file to load. (For read.adp.sontek.serial, this is generally a list of files, which will be concatenated.)
from	indication of the first profile to read. This can be an integer, the sequence number of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argument. If from is not supplied, it defaults to 1.
to	an optional indication of the last profile to read, in a format as described for from. As a special case, to=0 means to read the file to the end. If to is not supplied, then it defaults to 0.
by	an optional indication of the stride length to use while walking through the file. If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files <i>only</i> , there are some extra features to avoid running out of memory; see "Memory considerations".)
tz	character string indicating time zone to be assumed in the data.
longitude	optional signed number indicating the longitude in degrees East.
latitude	optional signed number indicating the latitude in degrees North.
type	A character string indicating the type of instrument.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

### Value

An adp object, i.e. one inheriting from adp-class.

## Author(s)

Dan Kelley and Clark Richards

#### References

1. Information about Sontek profilers is available at

```
http://www.sontek.com.
```

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

```
read.adp.sontek.serial
```

Read a serial Sontek ADP file

## Description

Read a Sontek acoustic-Doppler profiler file, in a serial form that is possibly unique to Dalhousie University.

## Usage

```
read.adp.sontek.serial(file, from = 1, to, by = 1,
  tz = getOption("oceTz"), longitude = NA, latitude = NA,
  type = c("adp", "pcadp"), beamAngle = 25, orientation, monitor = FALSE,
  processingLog, debug = getOption("oceDebug"))
```

## **Arguments**

file a connection or a character string giving the name of the file to load. (For

read.adp.sontek.serial, this is generally a list of files, which will be con-

catenated.)

from indication of the first profile to read. This can be an integer, the sequence num-

ber of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argu-

ment. If from is not supplied, it defaults to 1.

to an optional indication of the last profile to read, in a format as described for

from. As a special case, to=0 means to read the file to the end. If to is not

supplied, then it defaults to 0.

by an optional indication of the stride length to use while walking through the file.

If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files *only*, there are some extra features to avoid running out of memory; see "Memory

considerations".)

tz character string indicating time zone to be assumed in the data.

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

type a character string indicating the type of instrument.

beamAngle angle between instrument axis and beams, in degrees.

orientation optional character string specifying the orientation of the sensor, provided for

those cases in which it cannot be inferred from the data file. The valid choices

are "upward", "downward", and "sideward".

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

### Value

An adp object, i.e. one inheriting from adp-class.

## Author(s)

Dan Kelley and Clark Richards

## See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

read.adv

Read an ADV data file

## **Description**

Read an ADV data file, producing an object of type adv. This function works by transferring control to a more specialized function, e.g. read.adp.nortek and read.adp.sontek, and in many cases users will find it preferable to either use these or the several even more specialized functions, if the file type is known.

## Usage

```
read.adv(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  type = c("nortek", "sontek", "sontek.adr", "sontek.text"), header = TRUE,
  longitude = NA, latitude = NA, start = NULL, deltat = NA,
  debug = getOption("oceDebug"), monitor = FALSE, processingLog = NULL)
```

## Arguments

file	a connection or a character string giving the name of the file to load. It is also possible to give file as a vector of filenames, to handle the case of data split into files by a data logger. In the multi-file case, header must be FALSE, start must be a vector of times, and deltat must be provided.
from	index number of the first profile to be read, or the time of that profile, as created with as .POSIXct (hint: use tz="UTC"). This argument is ignored if header==FALSE. See "Examples".
to	indication of the last profile to read, in a format matching that of from. This is ignored if header==FALSE.
by	an indication of the stride length to use while walking through the file. This is ignored if header==FALSE. Otherwise, if this is an integer, then by-1 profiles are skipped between each pair of profiles that is read. This may not make much sense, if the data are not equi-spaced in time. If by is a string representing a time interval, in colon-separated format, then this interval is divided by the sampling interval, to get the stride length. <i>BUG:</i> by only partially works; see the "Bugs" section below.
tz	character string indicating time zone to be assumed in the data.
type	character string indicating type of file, and used by read. adv to dispatch to one of the speciality functions.

header A logical value indicating whether the file starts with a header. (This will not be

the case for files that are created by data loggers that chop the raw data up into

a series of sub-files, e.g. once per hour.)

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

start the time of the first sample, typically created with as .POSIXct. This may be a

vector of times, if filename is a vector of file names.

deltat the time between samples. (This is mandatory if header=FALSE.)

debug a flag that turns on debugging. The value indicates the depth within the call

stack to which debugging applies. For example, read.adv.nortek() calls read.header.nortek(), so that read.adv.nortek(...,debug=2) provides information about not just the main body of the data file, but also the details

of the header.

monitor boolean, set to TRUE to provide an indication of every data burst read.

processingLog if provided, the action item to be stored in the log. This parameter is typically

only provided for internal calls; the default that it provides is better for normal

calls by a user.

#### **Details**

Files *without* headers may be created in experiments in which a data logger was set up to monitor the serial data stream from an instrument. The lack of header information places a burden on the user, who must supply such basic information as the times of observations, the instrument orientation, the instrument coordinate system, etc. Example 3 below shows how to deal with such files. Three things should be noted.

- 1. The user must choose the appropriate read.adv variant corresponding to the instrument in question. (This is necessary because oceMagic, which is used by the generic read.oce routine, cannot determine the type of instrument by examining a file that lacks a header.)
- 2. The call to the read function must include a start time (start) and the number of seconds between data (deltat), again, because the instrument data stream may lack those things when the device is set to a serial mode. Also, of course, it is necessary to set header=FALSE in the function call.
- 3. Once the file has been read in, the user will be obliged to specify other information, for the object to be well-formed. For example, the read function will have no way of knowing the instrument orientation, the coordinate system being used, the transformation matrix to go from "beam" to "xyz" coordinates, or the instrument heading, pitch, and roll, to go from "xyz" coordinates to "enu" coordinates. Such things are illustrated in example 3 below.

In ADV data files, velocities are coded to signed 2-byte integers, with a scale factor being used to convert to velocity in metres per second. These two facts control the maximum recordable velocity and the velocity resolution, values that may be retrieved for an ADV object name d with d[["velocityMaximum"]] and d[["velocityResolution"]].

#### Value

An object of adv-class that contains measurements made with an ADV device.

The metadata contains information as given in the following table. The "Nortek name" is the name used in the Nortek System Integrator Guide [reference 1] and the "Sontek name" is the name used in the relevant Sontek documentation. References are given in square brackets.

metadata <b>name</b>	Nortek name	Sontek name	Meaning
manufacturer	-	-	Either "nortek" or "sontek"
instrumentType	-	-	Either "vector" or "adv"
filename	-	-	Name of data file(s)
latitude	-	-	Latitude of mooring (if applicable)
longitude	-	-	Longitude of mooring (if applicable)
numberOfSamples	-	-	Number of data samples in file
numberOfBeams	NBeams [1 p18]	-	Number of beams (always 3)
numberOfBeamSequencesPerBurst	NPings	-	number of beam sequences per burst
measurementInterval	MeasInterval [1 p31]	-	
samplingRate	512/(AvgInterval) [1 p30; 4]	_	

The data list contains items with names corresponding to adp objects, with an exception for Nortek data. Nortek instruments report some things at a time interval that is longer than the velocity sampling, and these are stored in data as timeSlow, headingSlow, pitchSlow, rollSlow, and temperatureSlow; if burst sampling was used, there will also be items recordsBurst and timeBurst.

The processingLog is in the standard format.

#### Nortek files

## Sampling-rate and similar issues

The data format is inferred from the System Integrator Guide [1A] and System Integrator Manual [1B]. These document lacks clarity in spots, and so read.adv.nortek contains some assumptions that are noted here, so that users will be aware of possible problems.

A prominent example is the specification of the sampling rate, stored in metadata\$sampingRate in the return value. Repeated examination of the System Integrator Guide [1] failed to indicate where this value is stored in the various headers contained in Vector datasets. After some experimentation with a few data files, read.adv.nortek was set up to calculate metadata\$samplingRate as 512/AvgInterval where AvgInterval is a part of the "User Configuration" header [1 p30], where the explanation is "average interval in seconds"). This formula was developed through trial and error, but it was confirmed later on the Nortek discussion group, and it should appear in upcoming versions of [1].

Another basic issue is the determination of whether an instrument had recorded in continuous mode or burst mode. One might infer that TimCtrlReg in the "User Configuration" header [1 p30] determines this, in bits 1 and 2. However, this was the case in test files available to the author. For this reason, read.adv.nortek infers the mode by reverse engineering of data files of known configuration. The present version of read.adv.nortek determines the sampling mode from the "NRecords" item of the "Vector Velocity Data" header, which seems to be 0 for data collected continuously, and non-zero for data collected in bursts.

Taking these things together, we come upon the issue of how to infer sampling times for Nortek instruments. There do not seem to be definitive documents on this, and so read.adv.nortek is based partly on information (of unknown quality) found on Nortek discusson boards. The present version of read.adv.nortek infers the times of velocity observations differently, depending on whether the instrument was set to record in burst mode or continuous mode. For burst mode, times stated in the burst headers are used, but for continuous mode, times stated in the "vector system data" are used. On the advice found on a Nortek discussion board, the burst-mode times are offset by 2 seconds to allow for the instrument warm-up period.

### Handling IMU (inertial measurement unit) data

Starting in March 2016, read.adv.nortek has offered some support for handling IMU (inertial measurement unit) data incorporated into Nortek binary files. This is not described in the Nortek document named "System Integrator Guide" (2008 [1A]) but it appeared in "System Integrator Manual" (2014 [1B]; 2016 [1C]). Confusingly, 1B described 3 varieties of data, whereas 1C does not describe any of these, but describes instead a fourth variety. As of March 2016, read.adv.nortek handles all 4 varieties, because files in the various schemes appear to exist. In oce, the varieties are named after the byte code that flags them. (Variety c3 is the one described in [1C]; the others were described in [1B].) The variety is stored in the metadata slot of the returned object as a string named IMUtype.

For each variety, the reader is cautioned that strong tests have not been performed on the code. One way to test the code is to compare with textual data files produced by the Nortek software. In March 2016, an oce user shared a dataset of the c3 variety, and this permitted detailed comparison between the text file and the values inferred by read.adv.nortek. The test suggested agreement (to within the resolution printed in the text file) for velocity (v in the data slot), signal amplitude (a), correlation (q), pressure (p), the three components of IMU delta angle (IMUdeltaAngleX etc), and all components of the rotation matrix (IMUrotation). However, the delta velocity signals did not match, with IMUdeltaVelocityX disagreeing in the second decimal place, IMUdeltaVelocityY component disagreeing in the first, and IMUdeltaVelocityZ being out by a factor of about 10. This is github issue 893 (https://github.com/dankelley/oce/issues/893).

- Variety c3 (signalled by byte 5 of a sequence being 0xc3) provides information on what Nortek calls DeltaAngle, DeltaVelocity and Orientation Matrix. (Apart from the orientation matrix, Nortek provides no documentation on what these quantities mean.) In the object returned by read.adv.nortek, these are stored in the data slot as IMUdeltaAngleX, IMUdeltaAngleY, IMUdeltaVelocityX, IMUdeltaVelocityY, IMUdeltaVelocityZ, and IMUrotation, all vectors except the last, which is a 3D array. In addition to these, IMUtimestamp is a time-stamp, which is not defined in the Nortek documents but seems, from IMU documents [5], to be defined based on a clock that ticks once per 16 microseconds. Caution may be required in dealing with this timestamp, since it seemed sensible in one test case (variety d3) but kept reseting to zero in another (variety c3). The lack of Nortek documentation on most of these quantities is a roadblock to implementing oce functions dealing with IMU-enabled datasets
- Variety cc (signalled by byte 5 of a sequence being 0xcc) provides information on acceleration, angular rotation rate, magnetic vector and orientation matrix. Each is a timeseries. Acceleration is stored in the data slot as IMUaccelX, IMUaccelY, IMUaccelz. The angular rotation components are IMUngrtX, IMUngrtY and IMUngrtz. The magnetic data are in IMUmagrtx, IMUmagrty and IMUmagrtz. Finally, IMUmatrix is a rotation matrix made up from elements named M11, M12, etc in the Nortek documentation. In addition to all of these, IMUtime stores time in seconds (with an origin whose definition is not stated in [1B]).

Variety d2 (signalled by byte 5 being 0xd2) provides information on gyro-stabilized acceleration, angular rate and magnetometer vectors. The data stored MUaccelX, IMUangrtX, IMUmagrtX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

Variety d3 (signalled by byte 5 being 0xd3) provides information on DeltaAngle, DeltaVelocity and magnetometer vectors, stored in IMUdeltaAngleX, IMUdeltaVelocityX, and IMUdeltaMagVectorX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

#### Author(s)

Dan Kelley

#### References

- 1A. Nortek AS. System Integrator Guide (paradopp family of products). June 2008. (Doc No: PSI00-0101-0608). (Users may find it helpful to also examine newer versions of the guide.)
- 1B. Nortek AS. System Integrator Manual. Dec 2014. (system-integrator-manual\_Dec2014\_jan.pdf)
- 1C. Nortek AS. System Integrator Manual. March 2016. (system-integrator-manual\_Mar2016.pdf)
- 2. SonTek/YSI ADVField/Hydra Acoustic Doppler Velocimeter (Field) Technical Documentation (Sept 1, 2001).
- 3. Appendix 2.2.3 of the Sontek ADV operation Manual, Firmware Version 4.0 (Oct 1997).
- 4. Nortek Knowledge Center http://www.nortekusa.com/en/knowledge-center
- 5. A document describing an IMU unit that seems to be close to the one named in [1B,C] as being an adjunct to Nortek Vector systems is at http://files.microstrain.com/3DM-GX3-35-Data-Communications-Protocol.

### See Also

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

### **Examples**

read.adv.nortek

Read an ADV data file

## **Description**

Read an ADV data file, producing an object of type adv. This function works by transferring control to a more specialized function, e.g. read.adp.nortek and read.adp.sontek, and in many cases users will find it preferable to either use these or the several even more specialized functions, if the file type is known.

## Usage

```
read.adv.nortek(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  header = TRUE, longitude = NA, latitude = NA, type = c("vector",
  "aquadopp"), haveAnalog1 = FALSE, haveAnalog2 = FALSE,
  debug = getOption("oceDebug"), monitor = FALSE, processingLog = NULL)
```

## **Arguments**

latitude

type

file	a connection or a character string giving the name of the file to load. It is also possible to give file as a vector of filenames, to handle the case of data split into files by a data logger. In the multi-file case, header must be FALSE, start must be a vector of times, and deltat must be provided.
from	index number of the first profile to be read, or the time of that profile, as created with as .POSIXct (hint: use tz="UTC"). This argument is ignored if header==FALSE. See "Examples".
to	indication of the last profile to read, in a format matching that of from. This is ignored if header==FALSE.
by	an indication of the stride length to use while walking through the file. This is ignored if header==FALSE. Otherwise, if this is an integer, then by-1 profiles are skipped between each pair of profiles that is read. This may not make much sense, if the data are not equi-spaced in time. If by is a string representing a time interval, in colon-separated format, then this interval is divided by the sampling interval, to get the stride length. <i>BUG:</i> by only partially works; see the "Bugs" section below.
tz	character string indicating time zone to be assumed in the data.
header	A logical value indicating whether the file starts with a header. (This will not be the case for files that are created by data loggers that chop the raw data up into a series of sub-files, e.g. once per hour.)
longitude	optional signed number indicating the longitude in degrees East.

optional signed number indicating the latitude in degrees North.

A string indicating which type of Nortek device produced the data file, vector

haveAnalog1 A logical value indicating whether the data file has 'analog1' data.

or aquadopp.

haveAnalog2 A logical value indicating whether the data file has 'analog2' data.

debug a flag that turns on debugging. The value indicates the depth within the call stack to which debugging applies. For example, read.adv.nortek() calls read.header.nortek(), so that read.adv.nortek(...,debug=2) provides information about not just the main body of the data file, but also the details of the header.

monitor boolean, set to TRUE to provide an indication of every data burst read.

processingLog if provided, the action item to be stored in the log. This parameter is typically only provided for internal calls; the default that it provides is better for normal calls by a user.

#### **Details**

Files *without* headers may be created in experiments in which a data logger was set up to monitor the serial data stream from an instrument. The lack of header information places a burden on the user, who must supply such basic information as the times of observations, the instrument orientation, the instrument coordinate system, etc. Example 3 below shows how to deal with such files. Three things should be noted.

- 1. The user must choose the appropriate read.adv variant corresponding to the instrument in question. (This is necessary because oceMagic, which is used by the generic read.oce routine, cannot determine the type of instrument by examining a file that lacks a header.)
- 2. The call to the read function must include a start time (start) and the number of seconds between data (deltat), again, because the instrument data stream may lack those things when the device is set to a serial mode. Also, of course, it is necessary to set header=FALSE in the function call.
- 3. Once the file has been read in, the user will be obliged to specify other information, for the object to be well-formed. For example, the read function will have no way of knowing the instrument orientation, the coordinate system being used, the transformation matrix to go from "beam" to "xyz" coordinates, or the instrument heading, pitch, and roll, to go from "xyz" coordinates to "enu" coordinates. Such things are illustrated in example 3 below.

In ADV data files, velocities are coded to signed 2-byte integers, with a scale factor being used to convert to velocity in metres per second. These two facts control the maximum recordable velocity and the velocity resolution, values that may be retrieved for an ADV object name d with d[["velocityMaximum"]] and d[["velocityResolution"]].

### Value

An object of adv-class that contains measurements made with an ADV device.

The metadata contains information as given in the following table. The "Nortek name" is the name used in the Nortek System Integrator Guide [reference 1] and the "Sontek name" is the name used in the relevant Sontek documentation. References are given in square brackets.

metadata <b>name</b>	Nortek name	Sontek name	Meaning
manufacturer	-	-	Either "nortek" or "sontek"
instrumentType	-	-	Either "vector" or "adv"
filename	-	-	Name of data file(s)

latitude--Latitude of mooring (if applicable)longitude--Longitude of mooring (if applicable)numberOfSamples--Number of data samples in filenumberOfBeamsNBeams [1 p18]-Number of beams (always 3)numberOfBeamSequencesPerBurstNPings-number of beam sequences per burstmeasurementIntervalMeasInterval [1 p31]-

The data list contains items with names corresponding to adp objects, with an exception for Nortek data. Nortek instruments report some things at a time interval that is longer than the velocity sampling, and these are stored in data as timeSlow, headingSlow, pitchSlow, rollSlow, and temperatureSlow; if burst sampling was used, there will also be items recordsBurst and

512/(AvgInterval) [1 p30; 4]

The processingLog is in the standard format.

#### Nortek files

samplingRate

timeBurst.

## Sampling-rate and similar issues

The data format is inferred from the System Integrator Guide [1A] and System Integrator Manual [1B]. These document lacks clarity in spots, and so read.adv.nortek contains some assumptions that are noted here, so that users will be aware of possible problems.

A prominent example is the specification of the sampling rate, stored in metadata\$sampingRate in the return value. Repeated examination of the System Integrator Guide [1] failed to indicate where this value is stored in the various headers contained in Vector datasets. After some experimentation with a few data files, read.adv.nortek was set up to calculate metadata\$samplingRate as 512/AvgInterval where AvgInterval is a part of the "User Configuration" header [1 p30], where the explanation is "average interval in seconds"). This formula was developed through trial and error, but it was confirmed later on the Nortek discussion group, and it should appear in upcoming versions of [1].

Another basic issue is the determination of whether an instrument had recorded in continuous mode or burst mode. One might infer that TimCtrlReg in the "User Configuration" header [1 p30] determines this, in bits 1 and 2. However, this was the case in test files available to the author. For this reason, read.adv.nortek infers the mode by reverse engineering of data files of known configuration. The present version of read.adv.nortek determines the sampling mode from the "NRecords" item of the "Vector Velocity Data" header, which seems to be 0 for data collected continuously, and non-zero for data collected in bursts.

Taking these things together, we come upon the issue of how to infer sampling times for Nortek instruments. There do not seem to be definitive documents on this, and so read.adv.nortek is based partly on information (of unknown quality) found on Nortek discusson boards. The present version of read.adv.nortek infers the times of velocity observations differently, depending on whether the instrument was set to record in burst mode or continuous mode. For burst mode, times stated in the burst headers are used, but for continuous mode, times stated in the "vector system data" are used. On the advice found on a Nortek discussion board, the burst-mode times are offset by 2 seconds to allow for the instrument warm-up period.

## Handling IMU (inertial measurement unit) data

Starting in March 2016, read.adv.nortek has offered some support for handling IMU (inertial measurement unit) data incorporated into Nortek binary files. This is not described in the Nortek document named "System Integrator Guide" (2008 [1A]) but it appeared in "System Integrator Manual" (2014 [1B]; 2016 [1C]). Confusingly, 1B described 3 varieties of data, whereas 1C does not describe any of these, but describes instead a fourth variety. As of March 2016, read.adv.nortek handles all 4 varieties, because files in the various schemes appear to exist. In oce, the varieties are named after the byte code that flags them. (Variety c3 is the one described in [1C]; the others were described in [1B].) The variety is stored in the metadata slot of the returned object as a string named IMUtype.

For each variety, the reader is cautioned that strong tests have not been performed on the code. One way to test the code is to compare with textual data files produced by the Nortek software. In March 2016, an oce user shared a dataset of the c3 variety, and this permitted detailed comparison between the text file and the values inferred by read.adv.nortek. The test suggested agreement (to within the resolution printed in the text file) for velocity (v in the data slot), signal amplitude (a), correlation (q), pressure (p), the three components of IMU delta angle (IMUdeltaAngleX etc), and all components of the rotation matrix (IMUrotation). However, the delta velocity signals did not match, with IMUdeltaVelocityX disagreeing in the second decimal place, IMUdeltaVelocityY component disagreeing in the first, and IMUdeltaVelocityZ being out by a factor of about 10. This is github issue 893 (https://github.com/dankelley/oce/issues/893).

- Variety c3 (signalled by byte 5 of a sequence being 0xc3) provides information on what Nortek calls DeltaAngle, DeltaVelocity and Orientation Matrix. (Apart from the orientation matrix, Nortek provides no documentation on what these quantities mean.) In the object returned by read.adv.nortek, these are stored in the data slot as IMUdeltaAngleX, IMUdeltaAngleY, IMUdeltaAngleZ, IMUdeltaVelocityX, IMUdeltaVelocityY, IMUdeltaVelocityZ, and IMUrotation, all vectors except the last, which is a 3D array. In addition to these, IMUtimestamp is a time-stamp, which is not defined in the Nortek documents but seems, from IMU documents [5], to be defined based on a clock that ticks once per 16 microseconds. Caution may be required in dealing with this timestamp, since it seemed sensible in one test case (variety d3) but kept reseting to zero in another (variety c3). The lack of Nortek documentation on most of these quantities is a roadblock to implementing oce functions dealing with IMU-enabled datasets
- Variety cc (signalled by byte 5 of a sequence being 0xcc) provides information on acceleration, angular rotation rate, magnetic vector and orientation matrix. Each is a timeseries. Acceleration is stored in the data slot as IMUaccelX, IMUaccelY, IMUaccelz. The angular rotation components are IMUngrtX, IMUngrtY and IMUngrtz. The magnetic data are in IMUmagrtx, IMUmagrty and IMUmagrtz. Finally, IMUmatrix is a rotation matrix made up from elements named M11, M12, etc in the Nortek documentation. In addition to all of these, IMUtime stores time in seconds (with an origin whose definition is not stated in [1B]).
- Variety d2 (signalled by byte 5 being 0xd2) provides information on gyro-stabilized acceleration, angular rate and magnetometer vectors. The data stored MUaccelX, IMUangrtX, IMUmagrtX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.
- Variety d3 (signalled by byte 5 being 0xd3) provides information on DeltaAngle, DeltaVelocity and magnetometer vectors, stored in IMUdeltaAngleX, IMUdeltaVelocityX, and IMUdeltaMagVectorX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

### Author(s)

Dan Kelley

#### References

1A. Nortek AS. System Integrator Guide (paradopp family of products). June 2008. (Doc No: PSI00-0101-0608). (Users may find it helpful to also examine newer versions of the guide.)

1B. Nortek AS. System Integrator Manual. Dec 2014. (system-integrator-manual\_Dec 2014\_jan.pdf)

1C. Nortek AS. System Integrator Manual. March 2016. (system-integrator-manual\_Mar2016.pdf)

- 2. SonTek/YSI ADVField/Hydra Acoustic Doppler Velocimeter (Field) Technical Documentation (Sept 1, 2001).
- 3. Appendix 2.2.3 of the Sontek ADV operation Manual, Firmware Version 4.0 (Oct 1997).
- 4. Nortek Knowledge Center http://www.nortekusa.com/en/knowledge-center
- 5. A document describing an IMU unit that seems to be close to the one named in [1B,C] as being an adjunct to Nortek Vector systems is at http://files.microstrain.com/3DM-GX3-35-Data-Communications-Protocol.

#### See Also

```
Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu
```

## **Examples**

read.adv.sontek.adr Read an ADV data file

## **Description**

Read an ADV data file, producing an object of type adv. This function works by transferring control to a more specialized function, e.g. read.adp.nortek and read.adp.sontek, and in many cases users will find it preferable to either use these or the several even more specialized functions, if the file type is known.

#### Usage

```
read.adv.sontek.adr(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  header = TRUE, longitude = NA, latitude = NA,
  debug = getOption("oceDebug"), monitor = FALSE, processingLog = NULL)
```

#### **Arguments**

file a connection or a character string giving the name of the file to load. It is also possible to give file as a vector of filenames, to handle the case of data split

into files by a data logger. In the multi-file case, header must be FALSE, start

must be a vector of times, and deltat must be provided.

from index number of the first profile to be read, or the time of that profile, as created

with as . POSIXct (hint: use tz="UTC"). This argument is ignored if header==FALSE.

See "Examples".

to indication of the last profile to read, in a format matching that of from. This is

ignored if header==FALSE.

by an indication of the stride length to use while walking through the file. This is

ignored if header==FALSE. Otherwise, if this is an integer, then by-1 profiles are skipped between each pair of profiles that is read. This may not make much sense, if the data are not equi-spaced in time. If by is a string representing a time interval, in colon-separated format, then this interval is divided by the sampling interval, to get the stride length. *BUG*: by only partially works; see the "Bugs"

section below.

tz character string indicating time zone to be assumed in the data.

header A logical value indicating whether the file starts with a header. (This will not be

the case for files that are created by data loggers that chop the raw data up into

a series of sub-files, e.g. once per hour.)

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

debug a flag that turns on debugging. The value indicates the depth within the call

stack to which debugging applies. For example, read.adv.nortek() calls read.header.nortek(), so that read.adv.nortek(...,debug=2) provides information about not just the main body of the data file, but also the details

of the header.

monitor boolean, set to TRUE to provide an indication of every data burst read.

processingLog if provided, the action item to be stored in the log. This parameter is typically

only provided for internal calls; the default that it provides is better for normal

calls by a user.

#### **Details**

Files *without* headers may be created in experiments in which a data logger was set up to monitor the serial data stream from an instrument. The lack of header information places a burden on the user, who must supply such basic information as the times of observations, the instrument orientation, the instrument coordinate system, etc. Example 3 below shows how to deal with such files. Three things should be noted.

1. The user must choose the appropriate read.adv variant corresponding to the instrument in question. (This is necessary because oceMagic, which is used by the generic read.oce routine, cannot determine the type of instrument by examining a file that lacks a header.)

- 2. The call to the read function must include a start time (start) and the number of seconds between data (deltat), again, because the instrument data stream may lack those things when the device is set to a serial mode. Also, of course, it is necessary to set header=FALSE in the function call.
- 3. Once the file has been read in, the user will be obliged to specify other information, for the object to be well-formed. For example, the read function will have no way of knowing the instrument orientation, the coordinate system being used, the transformation matrix to go from "beam" to "xyz" coordinates, or the instrument heading, pitch, and roll, to go from "xyz" coordinates to "enu" coordinates. Such things are illustrated in example 3 below.

In ADV data files, velocities are coded to signed 2-byte integers, with a scale factor being used to convert to velocity in metres per second. These two facts control the maximum recordable velocity and the velocity resolution, values that may be retrieved for an ADV object name d with d[["velocityMaximum"]] and d[["velocityResolution"]].

## Value

An object of adv-class that contains measurements made with an ADV device.

The metadata contains information as given in the following table. The "Nortek name" is the name used in the Nortek System Integrator Guide [reference 1] and the "Sontek name" is the name used in the relevant Sontek documentation. References are given in square brackets.

metadata <b>name</b>	Nortek name	Sontek name	Meaning
manufacturer	-	-	Either "nortek" or "sontek"
instrumentType	-	-	Either "vector" or "adv"
filename	-	-	Name of data file(s)
latitude	-	-	Latitude of mooring (if applicable)
longitude	-	-	Longitude of mooring (if applicable)
numberOfSamples	-	-	Number of data samples in file
numberOfBeams	NBeams [1 p18]	-	Number of beams (always 3)
number Of Beam Sequences Per Burst	NPings	-	number of beam sequences per burst
measurementInterval	MeasInterval [1 p31]	-	
samplingRate	512/(AvgInterval) [1 p30; 4]	-	

The data list contains items with names corresponding to adp objects, with an exception for Nortek data. Nortek instruments report some things at a time interval that is longer than the velocity sampling, and these are stored in data as timeSlow, headingSlow, pitchSlow, rollSlow, and temperatureSlow; if burst sampling was used, there will also be items recordsBurst and timeBurst.

The processingLog is in the standard format.

## Nortek files

Sampling-rate and similar issues

The data format is inferred from the System Integrator Guide [1A] and System Integrator Manual [1B]. These document lacks clarity in spots, and so read.adv.nortek contains some assumptions that are noted here, so that users will be aware of possible problems.

A prominent example is the specification of the sampling rate, stored in metadata\$sampingRate in the return value. Repeated examination of the System Integrator Guide [1] failed to indicate where this value is stored in the various headers contained in Vector datasets. After some experimentation with a few data files, read.adv.nortek was set up to calculate metadata\$samplingRate as 512/AvgInterval where AvgInterval is a part of the "User Configuration" header [1 p30], where the explanation is "average interval in seconds"). This formula was developed through trial and error, but it was confirmed later on the Nortek discussion group, and it should appear in upcoming versions of [1].

Another basic issue is the determination of whether an instrument had recorded in continuous mode or burst mode. One might infer that TimCtrlReg in the "User Configuration" header [1 p30] determines this, in bits 1 and 2. However, this was the case in test files available to the author. For this reason, read.adv.nortek infers the mode by reverse engineering of data files of known configuration. The present version of read.adv.nortek determines the sampling mode from the "NRecords" item of the "Vector Velocity Data" header, which seems to be 0 for data collected continuously, and non-zero for data collected in bursts.

Taking these things together, we come upon the issue of how to infer sampling times for Nortek instruments. There do not seem to be definitive documents on this, and so read.adv.nortek is based partly on information (of unknown quality) found on Nortek discusson boards. The present version of read.adv.nortek infers the times of velocity observations differently, depending on whether the instrument was set to record in burst mode or continuous mode. For burst mode, times stated in the burst headers are used, but for continuous mode, times stated in the "vector system data" are used. On the advice found on a Nortek discussion board, the burst-mode times are offset by 2 seconds to allow for the instrument warm-up period.

## Handling IMU (inertial measurement unit) data

Starting in March 2016, read.adv.nortek has offered some support for handling IMU (inertial measurement unit) data incorporated into Nortek binary files. This is not described in the Nortek document named "System Integrator Guide" (2008 [1A]) but it appeared in "System Integrator Manual" (2014 [1B]; 2016 [1C]). Confusingly, 1B described 3 varieties of data, whereas 1C does not describe any of these, but describes instead a fourth variety. As of March 2016, read.adv.nortek handles all 4 varieties, because files in the various schemes appear to exist. In oce, the varieties are named after the byte code that flags them. (Variety c3 is the one described in [1C]; the others were described in [1B].) The variety is stored in the metadata slot of the returned object as a string named IMUtype.

For each variety, the reader is cautioned that strong tests have not been performed on the code. One way to test the code is to compare with textual data files produced by the Nortek software. In March 2016, an oce user shared a dataset of the c3 variety, and this permitted detailed comparison between the text file and the values inferred by read.adv.nortek. The test suggested agreement (to within the resolution printed in the text file) for velocity (v in the data slot), signal amplitude (a), correlation (q), pressure (p), the three components of IMU delta angle (IMUdeltaAngleX etc), and all components of the rotation matrix (IMUrotation). However, the delta velocity signals did not match, with IMUdeltaVelocityX disagreeing in the second decimal place, IMUdeltaVelocityY component disagreeing in the first, and IMUdeltaVelocityZ being out by a factor of about 10. This is github issue 893 (https://github.com/dankelley/oce/issues/893).

• Variety c3 (signalled by byte 5 of a sequence being 0xc3) provides information on what Nortek calls DeltaAngle, DeltaVelocity and Orientation Matrix. (Apart from the orientation matrix, Nortek provides no documentation on what these quantities mean.) In the object returned by read.adv.nortek, these are stored in the data slot as IMUdeltaAngleX, IMUdeltaAngleY, IMUdeltaAngleZ, IMUdeltaVelocityX, IMUdeltaVelocityY, IMUdeltaVelocityZ, and IMUrotation, all vectors except the last, which is a 3D array. In addition to these, IMUtimestamp is a time-stamp, which is not defined in the Nortek documents but seems, from IMU documents [5], to be defined based on a clock that ticks once per 16 microseconds. Caution may be required in dealing with this timestamp, since it seemed sensible in one test case (variety d3) but kept reseting to zero in another (variety c3). The lack of Nortek documentation on most of these quantities is a roadblock to implementing oce functions dealing with IMU-enabled datasets

- Variety cc (signalled by byte 5 of a sequence being 0xcc) provides information on acceleration, angular rotation rate, magnetic vector and orientation matrix. Each is a timeseries. Acceleration is stored in the data slot as IMUaccelX, IMUaccelY, IMUaccelz. The angular rotation components are IMUngrtX, IMUngrtY and IMUngrtz. The magnetic data are in IMUmagrtx, IMUmagrty and IMUmagrtz. Finally, IMUmatrix is a rotation matrix made up from elements named M11, M12, etc in the Nortek documentation. In addition to all of these, IMUtime stores time in seconds (with an origin whose definition is not stated in [1B]).
- Variety d2 (signalled by byte 5 being 0xd2) provides information on gyro-stabilized acceleration, angular rate and magnetometer vectors. The data stored MUaccelX, IMUangrtX, IMUmagrtX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.
- Variety d3 (signalled by byte 5 being 0xd3) provides information on DeltaAngle, DeltaVelocity and magnetometer vectors, stored in IMUdeltaAngleX, IMUdeltaVelocityX, and IMUdeltaMagVectorX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

## Author(s)

Dan Kelley

#### References

- 1A. Nortek AS. System Integrator Guide (paradopp family of products). June 2008. (Doc No: PSI00-0101-0608). (Users may find it helpful to also examine newer versions of the guide.)
- 1B. Nortek AS. System Integrator Manual. Dec 2014. (system-integrator-manual\_Dec2014\_jan.pdf)
- 1C. Nortek AS. System Integrator Manual. March 2016. (system-integrator-manual\_Mar2016.pdf)
- 2. SonTek/YSI ADVField/Hydra Acoustic Doppler Velocimeter (Field) Technical Documentation (Sept 1, 2001).
- 3. Appendix 2.2.3 of the Sontek ADV operation Manual, Firmware Version 4.0 (Oct 1997).
- 4. Nortek Knowledge Center http://www.nortekusa.com/en/knowledge-center
- 5. A document describing an IMU unit that seems to be close to the one named in [1B,C] as being an adjunct to Nortek Vector systems is at http://files.microstrain.com/3DM-GX3-35-Data-Communications-Protocol.

## See Also

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

## Examples

Description

Read an ADV data file, producing an object of type adv. This function works by transferring control to a more specialized function, e.g. read.adp.nortek and read.adp.sontek, and in many cases users will find it preferable to either use these or the several even more specialized functions, if the file type is known.

## Usage

```
read.adv.sontek.serial(file, from = 1, to, by = 1,
  tz = getOption("oceTz"), longitude = NA, latitude = NA, start = NULL,
  deltat = NULL, debug = getOption("oceDebug"), monitor = FALSE,
  processingLog = NULL)
```

## **Arguments**

file	a connection or a character string giving the name of the file to load. It is also possible to give file as a vector of filenames, to handle the case of data split into files by a data logger. In the multi-file case, header must be FALSE, start must be a vector of times, and deltat must be provided.
from	index number of the first profile to be read, or the time of that profile, as created with as . POSIXct (hint: use tz="UTC"). This argument is ignored if header==FALSE. See "Examples".
to	indication of the last profile to read, in a format matching that of from. This is ignored if header==FALSE.

by an indication of the stride length to use while walking through the file. This is

ignored if header==FALSE. Otherwise, if this is an integer, then by-1 profiles are skipped between each pair of profiles that is read. This may not make much sense, if the data are not equi-spaced in time. If by is a string representing a time interval, in colon-separated format, then this interval is divided by the sampling interval, to get the stride length. *BUG*: by only partially works; see the "Bugs"

section below.

tz character string indicating time zone to be assumed in the data.
longitude optional signed number indicating the longitude in degrees East.
latitude optional signed number indicating the latitude in degrees North.

start the time of the first sample, typically created with as POSIXct. This may be a

vector of times, if filename is a vector of file names.

deltat the time between samples.

debug a flag that turns on debugging. The value indicates the depth within the call

stack to which debugging applies. For example, read.adv.nortek() calls read.header.nortek(), so that read.adv.nortek(...,debug=2) provides information about not just the main body of the data file, but also the details

of the header.

monitor boolean, set to TRUE to provide an indication of every data burst read.

processingLog if provided, the action item to be stored in the log. This parameter is typically

only provided for internal calls; the default that it provides is better for normal

calls by a user.

## Details

Files *without* headers may be created in experiments in which a data logger was set up to monitor the serial data stream from an instrument. The lack of header information places a burden on the user, who must supply such basic information as the times of observations, the instrument orientation, the instrument coordinate system, etc. Example 3 below shows how to deal with such files. Three things should be noted.

- 1. The user must choose the appropriate read.adv variant corresponding to the instrument in question. (This is necessary because oceMagic, which is used by the generic read.oce routine, cannot determine the type of instrument by examining a file that lacks a header.)
- 2. The call to the read function must include a start time (start) and the number of seconds between data (deltat), again, because the instrument data stream may lack those things when the device is set to a serial mode. Also, of course, it is necessary to set header=FALSE in the function call.
- 3. Once the file has been read in, the user will be obliged to specify other information, for the object to be well-formed. For example, the read function will have no way of knowing the instrument orientation, the coordinate system being used, the transformation matrix to go from "beam" to "xyz" coordinates, or the instrument heading, pitch, and roll, to go from "xyz" coordinates to "enu" coordinates. Such things are illustrated in example 3 below.

In ADV data files, velocities are coded to signed 2-byte integers, with a scale factor being used to convert to velocity in metres per second. These two facts control the maximum recordable velocity and the velocity resolution, values that may be retrieved for an ADV object name d with d[["velocityMaximum"]] and d[["velocityResolution"]].

#### Value

An object of adv-class that contains measurements made with an ADV device.

The metadata contains information as given in the following table. The "Nortek name" is the name used in the Nortek System Integrator Guide [reference 1] and the "Sontek name" is the name used in the relevant Sontek documentation. References are given in square brackets.

metadata <b>name</b>	Nortek name	Sontek name	Meaning
manufacturer	-	-	Either "nortek" or "sontek"
instrumentType	-	-	Either "vector" or "adv"
filename	-	-	Name of data file(s)
latitude	-	-	Latitude of mooring (if applicable)
longitude	-	-	Longitude of mooring (if applicable)
numberOfSamples	-	-	Number of data samples in file
numberOfBeams	NBeams [1 p18]	-	Number of beams (always 3)
numberOfBeamSequencesPerBurst	NPings	-	number of beam sequences per burst
measurementInterval	MeasInterval [1 p31]	-	
samplingRate	512/(AvgInterval) [1 p30; 4]	-	

The data list contains items with names corresponding to adp objects, with an exception for Nortek data. Nortek instruments report some things at a time interval that is longer than the velocity sampling, and these are stored in data as timeSlow, headingSlow, pitchSlow, rollSlow, and temperatureSlow; if burst sampling was used, there will also be items recordsBurst and timeBurst.

The processingLog is in the standard format.

#### Nortek files

## Sampling-rate and similar issues

The data format is inferred from the System Integrator Guide [1A] and System Integrator Manual [1B]. These document lacks clarity in spots, and so read.adv.nortek contains some assumptions that are noted here, so that users will be aware of possible problems.

A prominent example is the specification of the sampling rate, stored in metadata\$sampingRate in the return value. Repeated examination of the System Integrator Guide [1] failed to indicate where this value is stored in the various headers contained in Vector datasets. After some experimentation with a few data files, read.adv.nortek was set up to calculate metadata\$samplingRate as 512/AvgInterval where AvgInterval is a part of the "User Configuration" header [1 p30], where the explanation is "average interval in seconds"). This formula was developed through trial and error, but it was confirmed later on the Nortek discussion group, and it should appear in upcoming versions of [1].

Another basic issue is the determination of whether an instrument had recorded in continuous mode or burst mode. One might infer that TimCtrlReg in the "User Configuration" header [1 p30] determines this, in bits 1 and 2. However, this was the case in test files available to the author. For this reason, read.adv.nortek infers the mode by reverse engineering of data files of known configuration. The present version of read.adv.nortek determines the sampling mode from the "NRecords" item of the "Vector Velocity Data" header, which seems to be 0 for data collected continuously, and non-zero for data collected in bursts.

Taking these things together, we come upon the issue of how to infer sampling times for Nortek instruments. There do not seem to be definitive documents on this, and so read.adv.nortek is based partly on information (of unknown quality) found on Nortek discusson boards. The present version of read.adv.nortek infers the times of velocity observations differently, depending on whether the instrument was set to record in burst mode or continuous mode. For burst mode, times stated in the burst headers are used, but for continuous mode, times stated in the "vector system data" are used. On the advice found on a Nortek discussion board, the burst-mode times are offset by 2 seconds to allow for the instrument warm-up period.

### Handling IMU (inertial measurement unit) data

Starting in March 2016, read.adv.nortek has offered some support for handling IMU (inertial measurement unit) data incorporated into Nortek binary files. This is not described in the Nortek document named "System Integrator Guide" (2008 [1A]) but it appeared in "System Integrator Manual" (2014 [1B]; 2016 [1C]). Confusingly, 1B described 3 varieties of data, whereas 1C does not describe any of these, but describes instead a fourth variety. As of March 2016, read.adv.nortek handles all 4 varieties, because files in the various schemes appear to exist. In oce, the varieties are named after the byte code that flags them. (Variety c3 is the one described in [1C]; the others were described in [1B].) The variety is stored in the metadata slot of the returned object as a string named IMUtype.

For each variety, the reader is cautioned that strong tests have not been performed on the code. One way to test the code is to compare with textual data files produced by the Nortek software. In March 2016, an oce user shared a dataset of the c3 variety, and this permitted detailed comparison between the text file and the values inferred by read.adv.nortek. The test suggested agreement (to within the resolution printed in the text file) for velocity (v in the data slot), signal amplitude (a), correlation (q), pressure (p), the three components of IMU delta angle (IMUdeltaAngleX etc), and all components of the rotation matrix (IMUrotation). However, the delta velocity signals did not match, with IMUdeltaVelocityX disagreeing in the second decimal place, IMUdeltaVelocityY component disagreeing in the first, and IMUdeltaVelocityZ being out by a factor of about 10. This is github issue 893 (https://github.com/dankelley/oce/issues/893).

- Variety c3 (signalled by byte 5 of a sequence being 0xc3) provides information on what Nortek calls DeltaAngle, DeltaVelocity and Orientation Matrix. (Apart from the orientation matrix, Nortek provides no documentation on what these quantities mean.) In the object returned by read.adv.nortek, these are stored in the data slot as IMUdeltaAngleX, IMUdeltaAngleY, IMUdeltaVelocityX, IMUdeltaVelocityY, IMUdeltaVelocityZ, and IMUrotation, all vectors except the last, which is a 3D array. In addition to these, IMUtimestamp is a time-stamp, which is not defined in the Nortek documents but seems, from IMU documents [5], to be defined based on a clock that ticks once per 16 microseconds. Caution may be required in dealing with this timestamp, since it seemed sensible in one test case (variety d3) but kept reseting to zero in another (variety c3). The lack of Nortek documentation on most of these quantities is a roadblock to implementing oce functions dealing with IMU-enabled datasets
- Variety cc (signalled by byte 5 of a sequence being 0xcc) provides information on acceleration, angular rotation rate, magnetic vector and orientation matrix. Each is a timeseries. Acceleration is stored in the data slot as IMUaccelX, IMUaccelY, IMUaccelz. The angular rotation components are IMUngrtX, IMUngrtY and IMUngrtz. The magnetic data are in IMUmagrtx, IMUmagrty and IMUmagrtz. Finally, IMUmatrix is a rotation matrix made up from elements named M11, M12, etc in the Nortek documentation. In addition to all of these, IMUtime stores time in seconds (with an origin whose definition is not stated in [1B]).

Variety d2 (signalled by byte 5 being 0xd2) provides information on gyro-stabilized acceleration, angular rate and magnetometer vectors. The data stored MUaccelX, IMUangrtX, IMUmagrtX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

Variety d3 (signalled by byte 5 being 0xd3) provides information on DeltaAngle, DeltaVelocity and magnetometer vectors, stored in IMUdeltaAngleX, IMUdeltaVelocityX, and IMUdeltaMagVectorX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

#### Author(s)

Dan Kelley

#### References

- 1A. Nortek AS. System Integrator Guide (paradopp family of products). June 2008. (Doc No: PSI00-0101-0608). (Users may find it helpful to also examine newer versions of the guide.)
- 1B. Nortek AS. System Integrator Manual. Dec 2014. (system-integrator-manual\_Dec2014\_jan.pdf)
- 1C. Nortek AS. System Integrator Manual. March 2016. (system-integrator-manual\_Mar2016.pdf)
- 2. SonTek/YSI ADVField/Hydra Acoustic Doppler Velocimeter (Field) Technical Documentation (Sept 1, 2001).
- 3. Appendix 2.2.3 of the Sontek ADV operation Manual, Firmware Version 4.0 (Oct 1997).
- 4. Nortek Knowledge Center http://www.nortekusa.com/en/knowledge-center
- 5. A document describing an IMU unit that seems to be close to the one named in [1B,C] as being an adjunct to Nortek Vector systems is at http://files.microstrain.com/3DM-GX3-35-Data-Communications-Protocol.

### See Also

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot,adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.text, read.adv, subset,adv-method, summary,adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

## **Examples**

```
read.adv.sontek.text Read an ADV data file
```

## **Description**

Read an ADV data file, producing an object of type adv. This function works by transferring control to a more specialized function, e.g. read.adp.nortek and read.adp.sontek, and in many cases users will find it preferable to either use these or the several even more specialized functions, if the file type is known.

## Usage

```
read.adv.sontek.text(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  originalCoordinate = "xyz", transformationMatrix, longitude = NA,
  latitude = NA, debug = getOption("oceDebug"), monitor = FALSE,
  processingLog = NULL)
```

## **Arguments**

file	a connection or a character string giving the name of the file to load. It is also
	possible to give file as a vector of filenames, to handle the case of data split

possible to give file as a vector of filenames, to handle the case of data split into files by a data logger. In the multi-file case, header must be FALSE, start

must be a vector of times, and deltat must be provided.

from index number of the first profile to be read, or the time of that profile, as created

with as . POSIXct (hint: use tz="UTC"). This argument is ignored if header==FALSE.

See "Examples".

to indication of the last profile to read, in a format matching that of from. This is

ignored if header==FALSE.

by an indication of the stride length to use while walking through the file. This is

ignored if header==FALSE. Otherwise, if this is an integer, then by-1 profiles are skipped between each pair of profiles that is read. This may not make much sense, if the data are not equi-spaced in time. If by is a string representing a time interval, in colon-separated format, then this interval is divided by the sampling interval, to get the stride length. *BUG*: by only partially works; see the "Bugs"

section below.

tz character string indicating time zone to be assumed in the data.

originalCoordinate

character string indicating coordinate system, one of "beam", "xyz", "enu" or "other". (This is needed for the case of multiple files that were created by a data logger, because the header information is normally lost in such instances.)

transformationMatrix

transformation matrix to use in converting beam coordinates to xyz coordinates. This will over-ride the matrix in the file header, if there is one. An example is

rbind(c(2.710, -1.409,-1.299), c(0.071, 2.372, -2.442), c(0.344, 0.344, 0.344)).

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

debug a flag that turns on debugging. The value indicates the depth within the call stack to which debugging applies. For example, read.adv.nortek() calls read.header.nortek(), so that read.adv.nortek(...,debug=2) provides information about not just the main body of the data file, but also the details of the header.

monitor boolean, set to TRUE to provide an indication of every data burst read.

processingLog if provided, the action item to be stored in the log. This parameter is typically only provided for internal calls; the default that it provides is better for normal calls by a user.

#### **Details**

Files *without* headers may be created in experiments in which a data logger was set up to monitor the serial data stream from an instrument. The lack of header information places a burden on the user, who must supply such basic information as the times of observations, the instrument orientation, the instrument coordinate system, etc. Example 3 below shows how to deal with such files. Three things should be noted.

- 1. The user must choose the appropriate read.adv variant corresponding to the instrument in question. (This is necessary because oceMagic, which is used by the generic read.oce routine, cannot determine the type of instrument by examining a file that lacks a header.)
- 2. The call to the read function must include a start time (start) and the number of seconds between data (deltat), again, because the instrument data stream may lack those things when the device is set to a serial mode. Also, of course, it is necessary to set header=FALSE in the function call.
- 3. Once the file has been read in, the user will be obliged to specify other information, for the object to be well-formed. For example, the read function will have no way of knowing the instrument orientation, the coordinate system being used, the transformation matrix to go from "beam" to "xyz" coordinates, or the instrument heading, pitch, and roll, to go from "xyz" coordinates to "enu" coordinates. Such things are illustrated in example 3 below.

In ADV data files, velocities are coded to signed 2-byte integers, with a scale factor being used to convert to velocity in metres per second. These two facts control the maximum recordable velocity and the velocity resolution, values that may be retrieved for an ADV object name d with d[["velocityMaximum"]] and d[["velocityResolution"]].

### Value

An object of adv-class that contains measurements made with an ADV device.

The metadata contains information as given in the following table. The "Nortek name" is the name used in the Nortek System Integrator Guide [reference 1] and the "Sontek name" is the name used in the relevant Sontek documentation. References are given in square brackets.

metadata <b>name</b>	Nortek name	Sontek name	Meaning
manufacturer	-	=	Either "nortek" or "sontek"
instrumentType	-	-	Either "vector" or "adv"
filename	-	-	Name of data file(s)

latitude--Latitude of mooring (if applicable)longitude--Longitude of mooring (if applicable)numberOfSamples--Number of data samples in filenumberOfBeamsNBeams [1 p18]-Number of beams (always 3)numberOfBeamSequencesPerBurstNPings-number of beam sequences per burstmeasurementIntervalMeasInterval [1 p31]-

The data list contains items with names corresponding to adp objects, with an exception for Nortek data. Nortek instruments report some things at a time interval that is longer than the velocity sampling, and these are stored in data as timeSlow, headingSlow, pitchSlow, rollSlow, and temperatureSlow; if burst sampling was used, there will also be items recordsBurst and

512/(AvgInterval) [1 p30; 4]

The processingLog is in the standard format.

#### Nortek files

samplingRate

timeBurst.

### Sampling-rate and similar issues

The data format is inferred from the System Integrator Guide [1A] and System Integrator Manual [1B]. These document lacks clarity in spots, and so read.adv.nortek contains some assumptions that are noted here, so that users will be aware of possible problems.

A prominent example is the specification of the sampling rate, stored in metadata\$sampingRate in the return value. Repeated examination of the System Integrator Guide [1] failed to indicate where this value is stored in the various headers contained in Vector datasets. After some experimentation with a few data files, read.adv.nortek was set up to calculate metadata\$samplingRate as 512/AvgInterval where AvgInterval is a part of the "User Configuration" header [1 p30], where the explanation is "average interval in seconds"). This formula was developed through trial and error, but it was confirmed later on the Nortek discussion group, and it should appear in upcoming versions of [1].

Another basic issue is the determination of whether an instrument had recorded in continuous mode or burst mode. One might infer that TimCtrlReg in the "User Configuration" header [1 p30] determines this, in bits 1 and 2. However, this was the case in test files available to the author. For this reason, read.adv.nortek infers the mode by reverse engineering of data files of known configuration. The present version of read.adv.nortek determines the sampling mode from the "NRecords" item of the "Vector Velocity Data" header, which seems to be 0 for data collected continuously, and non-zero for data collected in bursts.

Taking these things together, we come upon the issue of how to infer sampling times for Nortek instruments. There do not seem to be definitive documents on this, and so read.adv.nortek is based partly on information (of unknown quality) found on Nortek discusson boards. The present version of read.adv.nortek infers the times of velocity observations differently, depending on whether the instrument was set to record in burst mode or continuous mode. For burst mode, times stated in the burst headers are used, but for continuous mode, times stated in the "vector system data" are used. On the advice found on a Nortek discussion board, the burst-mode times are offset by 2 seconds to allow for the instrument warm-up period.

## Handling IMU (inertial measurement unit) data

Starting in March 2016, read.adv.nortek has offered some support for handling IMU (inertial measurement unit) data incorporated into Nortek binary files. This is not described in the Nortek document named "System Integrator Guide" (2008 [1A]) but it appeared in "System Integrator Manual" (2014 [1B]; 2016 [1C]). Confusingly, 1B described 3 varieties of data, whereas 1C does not describe any of these, but describes instead a fourth variety. As of March 2016, read.adv.nortek handles all 4 varieties, because files in the various schemes appear to exist. In oce, the varieties are named after the byte code that flags them. (Variety c3 is the one described in [1C]; the others were described in [1B].) The variety is stored in the metadata slot of the returned object as a string named IMUtype.

For each variety, the reader is cautioned that strong tests have not been performed on the code. One way to test the code is to compare with textual data files produced by the Nortek software. In March 2016, an oce user shared a dataset of the c3 variety, and this permitted detailed comparison between the text file and the values inferred by read.adv.nortek. The test suggested agreement (to within the resolution printed in the text file) for velocity (v in the data slot), signal amplitude (a), correlation (q), pressure (p), the three components of IMU delta angle (IMUdeltaAngleX etc), and all components of the rotation matrix (IMUrotation). However, the delta velocity signals did not match, with IMUdeltaVelocityX disagreeing in the second decimal place, IMUdeltaVelocityY component disagreeing in the first, and IMUdeltaVelocityZ being out by a factor of about 10. This is github issue 893 (https://github.com/dankelley/oce/issues/893).

- Variety c3 (signalled by byte 5 of a sequence being 0xc3) provides information on what Nortek calls DeltaAngle, DeltaVelocity and Orientation Matrix. (Apart from the orientation matrix, Nortek provides no documentation on what these quantities mean.) In the object returned by read.adv.nortek, these are stored in the data slot as IMUdeltaAngleX, IMUdeltaAngleY, IMUdeltaVelocityX, IMUdeltaVelocityY, IMUdeltaVelocityZ, and IMUrotation, all vectors except the last, which is a 3D array. In addition to these, IMUtimestamp is a time-stamp, which is not defined in the Nortek documents but seems, from IMU documents [5], to be defined based on a clock that ticks once per 16 microseconds. Caution may be required in dealing with this timestamp, since it seemed sensible in one test case (variety d3) but kept reseting to zero in another (variety c3). The lack of Nortek documentation on most of these quantities is a roadblock to implementing oce functions dealing with IMU-enabled datasets
- Variety cc (signalled by byte 5 of a sequence being 0xcc) provides information on acceleration, angular rotation rate, magnetic vector and orientation matrix. Each is a timeseries. Acceleration is stored in the data slot as IMUaccelX, IMUaccelY, IMUaccelz. The angular rotation components are IMUngrtX, IMUngrtY and IMUngrtz. The magnetic data are in IMUmagrtx, IMUmagrty and IMUmagrtz. Finally, IMUmatrix is a rotation matrix made up from elements named M11, M12, etc in the Nortek documentation. In addition to all of these, IMUtime stores time in seconds (with an origin whose definition is not stated in [1B]).
- Variety d2 (signalled by byte 5 being 0xd2) provides information on gyro-stabilized acceleration, angular rate and magnetometer vectors. The data stored MUaccelX, IMUangrtX, IMUmagrtX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.
- Variety d3 (signalled by byte 5 being 0xd3) provides information on DeltaAngle, DeltaVelocity and magnetometer vectors, stored in IMUdeltaAngleX, IMUdeltaVelocityX, and IMUdeltaMagVectorX, with similar for Y and Z. Again, time is in IMUtime. This data type has not been tested as of mid-March 2016, because the developers do not have a test file with which to test.

## Note on file name

The file argument does not actually name a file. It names a basename for a file. The actual file names are created by appending suffix .hd1 for one file and .ts1 for another.

### Author(s)

Dan Kelley

## References

- 1A. Nortek AS. System Integrator Guide (paradopp family of products). June 2008. (Doc No: PSI00-0101-0608). (Users may find it helpful to also examine newer versions of the guide.)
- 1B. Nortek AS. System Integrator Manual. Dec 2014. (system-integrator-manual\_Dec2014\_jan.pdf)
- 1C. Nortek AS. System Integrator Manual. March 2016. (system-integrator-manual\_Mar2016.pdf)
- 2. SonTek/YSI ADVField/Hydra Acoustic Doppler Velocimeter (Field) Technical Documentation (Sept 1, 2001).
- 3. Appendix 2.2.3 of the Sontek ADV operation Manual, Firmware Version 4.0 (Oct 1997).
- 4. Nortek Knowledge Center http://www.nortekusa.com/en/knowledge-center
- 5. A document describing an IMU unit that seems to be close to the one named in [1B,C] as being an adjunct to Nortek Vector systems is at http://files.microstrain.com/3DM-GX3-35-Data-Communications-Protocol.

## See Also

```
Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu
```

## **Examples**

read.amsr 361

read.amsr

Read an amsr File

# **Description**

Read a compressed amsr file, generating an object that inherits from amsr-class. Note that only compressed files are read in this version.

## Usage

```
read.amsr(file, debug = getOption("oceDebug"))
```

## **Arguments**

file String indicating the name of a compressed file. See "File sources".

debug A debugging flag, integer.

#### File sources

AMSR files are provided at the FTP site ftp://ftp.ssmi.com/amsr2/bmaps\_v07.2/ and login as "guest", enter a year-based directory (e.g. y2016 for the year 2016), then enter a month-based directory (e.g. m08 for August, the 8th month), and then download a file for the present date, e.g. f34\_20160803v7.2.gz for August 3rd, 2016. Do not uncompress this file, since read.amsr can only read uncompressed files. If read.amsr reports an error on the number of chunks, try downloading a similarly-named file (e.g. in the present example, read.amsr("f34\_20160803v7.2\_d3d.gz") will report an error about inability to read a 6-chunk file, but read.amsr("f34\_20160803v7.2.gz") will work properly.

# Author(s)

Dan Kelley and Chantelle Layton

# See Also

plot, amsr-method for an example.

Other things related to amsr data: [[<-,amsr-method, amsr-class, composite,amsr-method, download.amsr, plot,amsr-method, subset,amsr-method, summary,amsr-method

362 read.aquadopp

# Description

The R code is based on information in the Nortek System Integrator Guide (2008) and on postings on the Nortek "knowledge center" discussion board. One might assume that the latter is less authoritative than the former. For example, the inference of cell size follows advice found at <a href="http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717">http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717</a> (downloaded June 2012), which contains a typo in an early posting that is corrected later on.

# Usage

```
read.aquadopp(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  longitude = NA, latitude = NA, orientation, distance, monitor = FALSE,
  despike = FALSE, processingLog, debug = getOption("oceDebug"), ...)
```

# Arguments

r	guments	
	file	a connection or a character string giving the name of the file to load. (For read.adp.sontek.serial, this is generally a list of files, which will be concatenated.)
	from	indication of the first profile to read. This can be an integer, the sequence number of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argument. If from is not supplied, it defaults to 1.
	to	an optional indication of the last profile to read, in a format as described for from. As a special case, to=0 means to read the file to the end. If to is not supplied, then it defaults to $0$ .
	by	an optional indication of the stride length to use while walking through the file. If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files <i>only</i> , there are some extra features to avoid running out of memory; see "Memory considerations".)
	tz	character string indicating time zone to be assumed in the data.
	longitude	optional signed number indicating the longitude in degrees East.
	latitude	optional signed number indicating the latitude in degrees North.
	orientation	Optional character string specifying the orientation of the sensor, provided for those cases in which it cannot be inferred from the data file. The valid choices are "upward", "downward", and "sideward".
	distance	Optional vector holding the distances of bin centres from the sensor. This argument is ignored except for Nortek profilers, and need not be given if the function determines the distances correctly from the data. The problem is that the

read.aquadoppHR 363

distance is poorly documented in the Nortek System Integrator Guide (2008 edition, page 31), so the function must rely on word-of-mouth formulae that do not

work in all cases.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

... additional arguments, passed to called routines.

#### Value

An adp object, i.e. one inheriting from adp-class.

#### Author(s)

Dan Kelley

#### References

- 1. Information on Nortek profilers (including the System Integrator Guide, which explains the data format byte-by-byte) is available at <a href="http://www.nortekusa.com/">http://www.nortekusa.com/</a>. (One must join the site to see the manuals.)
- 2. The Nortek Knowledge Center <a href="http://www.nortekusa.com/en/knowledge-center">http://www.nortekusa.com/en/knowledge-center</a> may be of help if problems arise in dealing with data from Nortek instruments.

# See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

read.aquadoppHR

Read Nortek Aquadopp-HR File

# Description

The R code is based on information in the Nortek System Integrator Guide (2008) and on postings on the Nortek "knowledge center" discussion board. One might assume that the latter is less authoritative than the former. For example, the inference of cell size follows advice found at <a href="http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717">http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717</a> (downloaded June 2012)), which contains a typo in an early posting that is corrected later on.

364 read.aquadoppHR

### Usage

```
read.aquadoppHR(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  longitude = NA, latitude = NA, orientation = orientation, distance,
  monitor = FALSE, despike = FALSE, processingLog,
  debug = getOption("oceDebug"), ...)
```

#### Arguments

file a connection or a character string giving the name of the file to load. (For

read.adp.sontek.serial, this is generally a list of files, which will be con-

catenated.)

from indication of the first profile to read. This can be an integer, the sequence num-

ber of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argu-

ment. If from is not supplied, it defaults to 1.

to an optional indication of the last profile to read, in a format as described for

from. As a special case, to=0 means to read the file to the end. If to is not

supplied, then it defaults to 0.

by an optional indication of the stride length to use while walking through the file.

If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files *only*, there are some extra features to avoid running out of memory; see "Memory

considerations".)

tz character string indicating time zone to be assumed in the data.

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

orientation Optional character string specifying the orientation of the sensor, provided for

those cases in which it cannot be inferred from the data file. The valid choices

are "upward", "downward", and "sideward".

distance Optional vector holding the distances of bin centres from the sensor. This argu-

ment is ignored except for Nortek profilers, and need not be given if the function determines the distances correctly from the data. The problem is that the distance is poorly documented in the Nortek System Integrator Guide (2008 edition, page 31), so the function must rely on word-of-mouth formulae that do not

work in all cases.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

. . . additional arguments, passed to called routines.

#### Value

An adp object, i.e. one inheriting from adp-class.

## Author(s)

Dan Kelley

#### References

- 1. Information on Nortek profilers (including the System Integrator Guide, which explains the data format byte-by-byte) is available at <a href="http://www.nortekusa.com/">http://www.nortekusa.com/</a>. (One must join the site to see the manuals.)
- 2. The Nortek Knowledge Center <a href="http://www.nortekusa.com/en/knowledge-center">http://www.nortekusa.com/en/knowledge-center</a> may be of help if problems arise in dealing with data from Nortek instruments.

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aduadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

read.aquadoppProfiler Read a Nortek Aquadopp-Profiler File

# Description

The R code is based on information in the Nortek System Integrator Guide (2008) and on postings on the Nortek "knowledge center" discussion board. One might assume that the latter is less authoritative than the former. For example, the inference of cell size follows advice found at <a href="http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717">http://www.nortekusa.com/en/knowledge-center/forum/hr-profilers/736804717</a> (downloaded June 2012)), which contains a typo in an early posting that is corrected later on.

# Usage

```
read.aquadoppProfiler(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  longitude = NA, latitude = NA, orientation, distance, monitor = FALSE,
  despike = FALSE, processingLog, debug = getOption("oceDebug"), ...)
```

#### **Arguments**

file a connection or a character string giving the name of the file to load. (For

read.adp.sontek.serial, this is generally a list of files, which will be con-

catenated.)

from indication of the first profile to read. This can be an integer, the sequence num-

ber of the first profile to read, or a POSIXt time before which profiles should be skipped, or a character string that converts to a POSIXt time (assuming UTC timezone). See "Examples", and make careful note of the use of the tz argu-

ment. If from is not supplied, it defaults to 1.

to an optional indication of the last profile to read, in a format as described for

from. As a special case, to=0 means to read the file to the end. If to is not

supplied, then it defaults to 0.

by an optional indication of the stride length to use while walking through the file.

If this is an integer, then by-1 profiles are skipped between each pair of profiles that is read, e.g. the default by=1 means to read all the data. (For RDI files *only*, there are some extra features to avoid running out of memory; see "Memory

considerations".)

tz character string indicating time zone to be assumed in the data.

longitude optional signed number indicating the longitude in degrees East.

latitude optional signed number indicating the latitude in degrees North.

orientation Optional character string specifying the orientation of the sensor, provided for

those cases in which it cannot be inferred from the data file. The valid choices

are "upward", "downward", and "sideward".

distance Optional vector holding the distances of bin centres from the sensor. This argu-

ment is ignored except for Nortek profilers, and need not be given if the function determines the distances correctly from the data. The problem is that the distance is poorly documented in the Nortek System Integrator Guide (2008 edition, page 31), so the function must rely on word-of-mouth formulae that do not

work in all cases.

monitor boolean, set to TRUE to provide an indication of progress in reading the file,

either by printing a dot for each profile or by writing a textual progress bar with

txtProgressBar.

despike if TRUE, despike will be used to clean anomalous spikes in heading, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

. . . additional arguments, passed to called routines.

# Value

An adp object, i.e. one inheriting from adp-class.

read.argo 367

## Author(s)

Dan Kelley

#### References

1. Information on Nortek profilers (including the System Integrator Guide, which explains the data format byte-by-byte) is available at <a href="http://www.nortekusa.com/">http://www.nortekusa.com/</a>. (One must join the site to see the manuals.)

2. The Nortek Knowledge Center <a href="http://www.nortekusa.com/en/knowledge-center">http://www.nortekusa.com/en/knowledge-center</a> may be of help if problems arise in dealing with data from Nortek instruments.

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial, read.adp.sontek,read.adp,read.aduadoppHR,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

read.argo

Read an Argo Data File

# Description

read.argo is used to read an Argo file, producing an object of type argo. The file must be in the ARGO-style netCDF format described at in the Argo documentation [2,3].

#### Usage

```
read.argo(file, debug = getOption("oceDebug"), processingLog, ...)
```

# **Arguments**

file a character string giving the name of the file to load.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

... additional arguments, passed to called routines.

368 read.argo

#### **Details**

Metadata items such as time, longitude and latitude are inferred from the data file in a straightforward way, using ncvar\_get and data-variable names as listed in the Argo documentation [2,3]. The items listed in section 2.2.3 of [3] is read from the file and stored in the metadata slot, with the exception of longitude and latitude, which are stored in the data slot.

String data that contain trailing blanks in the argo NetCDF are trimmed using trimString. One-dimensional matrices are converted to vectors using as.vector. Items listed in section 2.2.3 of [3] are meant to be present in all files, but tests showed that this is not the case, and so read.argo sets such items to NULL before saving them in returned object.

Items are translated from upper-case Argo names to oce names using argoNames2oceNames.

It is assumed that the profile data are as listed in the NetCDF variable called STATION\_PARAMETERS. Each item can have variants, as described in Sections 2.3.4 of [3]. For example, if "PRES" is found in STATION\_PARAMETERS, then PRES (pressure) data are sought in the file, along with PRES\_QC, PRES\_ADJUSTED, PRES\_ADJUSTED\_QC, and PRES\_ERROR. The same pattern works for other profile data. The variables are stored with different names within the resultant argo-class object, to match with oce conventions. Thus, PRES gets renamed pressure, while PRES\_ADJUSTED gets renamed pressureAdjusted, and PRES\_ERROR gets renamed pressureError; all of these are stored in the data slot. Meanwhile, the quality-control flags PRES\_QC and PRES\_ADJUSTED\_QC are stored as pressure and pressureAdjusted in the metadata\$flags slot.

#### Value

An object of argo-class.

#### **Data sources**

Argo data are made available at several websites. A bit of detective work can be required to track down the data.

Some servers provide data for floats that surfaced in a given ocean on a given day, the anonymous FTP server ftp://usgodae.org/pub/outgoing/argo/geo/ being an example.

Other servers provide data on a per-float basis. A complicating factor is that these data tend to be categorized by "dac" (data archiving centre), which makes it difficult to find a particular float. For example, http://www.usgodae.org/ftp/outgoing/argo/ is the top level of a such a repository. If the ID of a float is known but not the "dac", then a first step is to download the text file http: //www.usgodae.org/ftp/outgoing/argo/ar\_index\_global\_meta.txt and search for the ID. The first few lines of that file are header, and after that the format is simple, with columns separated by slash (/). The dac is in the first such column and the float ID in the second. A simple search will reveal the dac. For example data(argo) is based on float 6900388, and the line containing that token is bodc/6900388/6900388\_meta.nc, 846, B0, 20120225005617, from which the dac is seen to be the British Oceanographic Data Centre (bodc). Armed with that information, visit http://www.usgodae.org/ftp/outgoing/argo/dac/bodc/6900388 and see a directory called 'profiles' that contains a NetCDF file for each profile the float made. These can be read with read.argo. It is also possible, and probably more common, to read a NetCDF file containing all the profiles together and for that purpose the file http://www.usgodae.org/ftp/outgoing/argo/ dac/bodc/6900388/6900388\_prof.nc should be downloaded and provided as the file argument to read.argo. This can be automated as in Example 2, although readers are cautioned that URL structures tend to change over time.

read.argo 369

Similar steps can be followed on other servers.

## Author(s)

Dan Kelley

#### References

- 1. http://www.argo.ucsd.edu/
- 2. Argo User's Manual Version 3.2, Dec 29th, 2015, available at https://archimer.ifremer.fr/doc/00187/29825/40575.pdf (but note that this is a draft; newer versions may have replaced this by now).
- 3. User's Manual (ar-um-02-01) 13 July 2010, available at http://www.argodatamgt.org/content/download/4729/34634/file/argo-dm-user-manual-version-2.3.pdf, which is the main document describing argo data.

#### See Also

The documentation for argo-class explains the structure of argo objects, and also outlines the other functions dealing with them.

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, as.argo, handleFlags, argo-method, plot, argo-method, subset, argo-method, summary, argo-method

# **Examples**

```
## Not run:
## Example 1: read from a local file
library(oce)
d <- read.argo("/data/OAR/6900388_prof.nc")</pre>
summary(d)
plot(d)
## Example 2: construct URL for download (brittle)
id <- "6900388"
url <- "http://www.usgodae.org/ftp/outgoing/argo"</pre>
if (!length(list.files(pattern="argo_index.txt")))
    download.file(paste(url, "ar_index_global_meta.txt", sep="/"), "argo_index.txt")
index <- readLines("argo_index.txt")</pre>
line <- grep(id, index)</pre>
if (0 == length(line)) stop("id ", id, " not found")
if (1 < length(line)) stop("id ", id, " found multiple times")</pre>
dac <- strsplit(index[line], "/")[[1]][1]</pre>
profile <- paste(id, "_prof.nc", sep="")</pre>
float <- paste(url, "dac", dac, id, profile, sep="/")</pre>
download.file(float, profile)
argo <- read.argo(profile)</pre>
summary(argo)
## End(Not run)
```

370 read.bremen

read.bremen

Read a Bremen File

# **Description**

Read a file in Bremen format, producing an object inheriting from bremen-class.

#### **Usage**

```
read.bremen(file)
```

#### Arguments

file

a connection or a character string giving the name of the file to load.

## **Details**

Velocities are assumed to be in cm/s, and are converted to m/s to follow the oce convention. Shears (which is what the variables named uz and vz are assumed to represent) are assumed to be in (cm/s)/m, although they could be in 1/s or something else; the lack of documentation is a problem here. Also, note that the assumed shears are not just first-difference estimates of velocity, given the results of a sample dataset:

```
> head(data.frame(b[["data"]]))
  pressure
                               uz
1
        0 0.092 -0.191
                         0.00000
                                  0.00000
2
        10 0.092 -0.191
                         0.02183 -0.35412
        20 0.092 -0.191
3
                         0.03046 -0.09458
4
        30 0.026 -0.246 -0.03948
5
        40 -0.003 -0.212 -0.02614
                                   0.03111
6
        50 -0.023 -0.169 -0.03791
```

#### Value

An object of bremen-class.

## Issues

This function may be renamed (or removed) without notice. It was created to read some data being used in a particular research project, and will be rendered useless if Bremen changes this data format.

# Author(s)

read.cm 371

# See Also

Other things related to bremen data: [[,bremen-method, [[<-,bremen-method, bremen-class, plot,bremen-method, summary,bremen-method

read.cm

Read a CM file

# Description

Read a current-meter data file, producing an object of cm-class.

# Usage

```
read.cm(file, from = 1, to, by = 1, tz = getOption("oceTz"),
  type = c("s4"), longitude = NA, latitude = NA,
  debug = getOption("oceDebug"), monitor = FALSE, processingLog, ...)
```

# **Arguments**

file	a connection or a character string giving the name of the file to load.
from	index number of the first measurement to be read, or the time of that measurement, as created with as . POSIXct (hint: use tz="UTC").
to	indication of the last measurement to read, in a format matching that of from.
by	an indication of the stride length to use while walking through the file. If this is an integer, then by-1 measurements are skipped between each pair of profiles that is read. This may not make much sense, if the data are not equi-spaced in time. If by is a string representing a time interval, in colon-separated format, then this interval is divided by the sampling interval, to get the stride length. <i>BUG:</i> if the data are not equi-spaced, then odd results will occur.
tz	character string indicating time zone to be assumed in the data.
type	character string indicating type of file (ignored at present).
longitude	optional signed number indicating the longitude in degrees East.
latitude	optional signed number indicating the latitude in degrees North.
debug	a flag that turns on debugging. The value indicates the depth within the call stack to which debugging applies.
monitor	ignored.
processingLo	g if provided, the action item to be stored in the log. This parameter is typically only provided for internal calls; the default that it provides is better for normal calls by a user.
	Optional arguments passed to plotting functions.

372 read.cm

#### **Details**

There function has been tested on only a single file, and the data-scanning algorithm was based on visual inspection of that file. Whether it will work generally is an open question. It should be noted that the sample file had several odd characteristics, some of which are listed below.

- The file contained two columns named "Cond", which was guessed to stand for conductivity. Since only the first contained data, the second was ignored, but this may not be the case for all files
- The unit for "Cond" was stated in the file to be "mS", which makes no sense, so the unit was assumed to be mS/cm.
- The file contained a column named "T-Temp", which is not something the author has seen in his career. It was assumed to stand for in-situ temperature.
- The file contained a column named "Depth", which is not something an instrument can measure. Presumably it was calculated from pressure (with what atmospheric offset, though?) and so pressure was inferred from it using swPressure.
- The file contained several columns that lacked names. These were ignored.
- The file contained several columns that seem to be derived from the actual measured data, such as "Speed", "Dir", "N-S Dist", etc. These are ignored.
- The file contained several columns that were basically a mystery to the author, e.g. "Hx", "Hy", "Vref", etc. These were ignored.

Based on such considerations, read.cm.s4() reads only the columns that were reasonably well-understood based on the sample file. Users who need more columns should contact the author. And a user who could produce a document explaining the data format would be especially appreciated!

#### Value

An object of cm-class. The data slot will contain all the data in the file, with names determined from the tokens in line 3 in that file, passed through make.names, except that Vnorth is renamed v (after conversion from cm/s to m/s), Veast is renamed u (after conversion from cm/s to m/s), Cond is renamed conductivity, T. Temp is renamed temperature and Sal is renamed salinity, and a new column named time (a POSIX time) is constructed from the information in the file header, and another named pressure is constructed from the column named Depth. At least in the single file studied in the creation of this function, there are some columns that are unnamed in line 3 of the header; these yield data items with names X, X.1, etc.

# Historical note

Prior to late July, 2016, the direction of current flow was stored in the return value, but it is no longer stored, since it can be derived from the u and v values.

## Author(s)

Dan Kelley

#### See Also

Other things related to cm data: [[,cm-method, [[<-,cm-method, as.cm, cm-class, cm, plot, cm-method, subset, cm-method, summary, cm-method

read.coastline 373

# **Examples**

```
## Not run:
    library(oce)
    cm <- read.oce("cm_interocean_0811786.s4a.tab")
    summary(cm)
    plot(cm)
## End(Not run)</pre>
```

read.coastline

Read a Coastline File

# **Description**

Read a coastline file in R, Splus, mapgen, shapefile, or openstreetmap format. The S and R formats are identical, and consist of two columns, lon and lat, with land-jump segments separated by lines with two NAs. The MapGen format is of the form

```
# -b -16.179081 28.553943 -16.244793 28.563330
```

BUG: the 'arc/info ungenerate' format is not yet understood.

#### **Usage**

```
read.coastline(file, type = c("R", "S", "mapgen", "shapefile",
  "openstreetmap"), debug = getOption("oceDebug"), monitor = FALSE,
  processingLog)
```

## **Arguments**

file name of file containing coastline data.

type of file, one of "R", "S", "mapgen", "shapefile" or "openstreetmap".

debug set to TRUE to print information about the header, etc.

monitor print a dot for every coastline segment read (ignored except for reading "shape-

file" type)

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

#### Value

An object of coastline-class.

## Author(s)

read.coastline.openstreetmap

Read a Coastline File in Openstreetmap Format

# **Description**

Read coastline data stored in the openstreetmap format [1].

# Usage

```
read.coastline.openstreetmap(file, lonlim = c(-180, 180), latlim = c(-90, 90), debug = getOption("oceDebug"), monitor = FALSE, processingLog)
```

# **Arguments**

file	name of file containing coastline data (a file ending in .shp) or a zipfile that contains such a file, with a corresponding name. The second scheme is useful for files downloaded from the NaturalEarth website [2].
lonlim	numerical vectors specifying the west and east edges (and south and north edges) of a focus window. Coastline polygons that do not intersect the defined box are skipped, which can be useful in narrowing high-resolution world-scale data to a local application.
latlim	numerical vectors specifying the west and east edges (and south and north edges) of a focus window. Coastline polygons that do not intersect the defined box are skipped, which can be useful in narrowing high-resolution world-scale data to a local application.
debug	set to TRUE to print information about the header, etc.
monitor	Logical indicating whether to print an indication of progress through the file.
processingLog	if provided, the action item to be stored in the log. (Typically only provided for internal calls; the default that it provides is better for normal calls by a user.)

## Value

An object of coastline-class

# Author(s)

Dan Kelley

# See Also

Other things related to coastline data: [[,coastline-method, [[<-,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.shapefile, subset, coastline-method, summary, coastline-method

read.coastline.shapefile 375

```
read.coastline.shapefile
```

Read a Coastline File in Shapefile Format

# **Description**

Read coastline data stored in the shapefile format [1].

## Usage

```
read.coastline.shapefile(file, lonlim = c(-180, 180), latlim = c(-90, 90),
  debug = getOption("oceDebug"), monitor = FALSE, processingLog)
```

## **Arguments**

file name of file containing coastline data (a file ending in .shp) or a zipfile that

contains such a file, with a corresponding name. The second scheme is useful

for files downloaded from the NaturalEarth website [2].

lonlim, latlim numerical vectors specifying the west and east edges (and south and north edges)

of a focus window. Coastline polygons that do not intersect the defined box are skipped, which can be useful in narrowing high-resolution world-scale data to a

local application.

debug set to TRUE to print information about the header, etc.

monitor Logical indicating whether to print an indication of progress through the file.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

#### Value

An object of coastline-class

# A hack for depth contours

The following demonstrates that this code is getting close to working with depth contours. This should be handled more internally, and a new object for depth contours should be constructed, of which coastlines could be a subset.

# Author(s)

Dan Kelley

#### References

- 1. The "shapefile" format is described in *ESRI Shapefile Technical Description*, March 1998, available at http://www.esri.com/library/whitepapers/pdfs/shapefile.pdf.
- 2. The NaturalEarth website <a href="http://www.naturalearthdata.com/downloads">http://www.naturalearthdata.com/downloads</a> provides coastline datasets in three resolutions, along with similar files lakes and rivers, for borders, etc. It is highly recommended.

376 read.ctd

#### See Also

Other things related to coastline data: [[,coastline-method, [[<-,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, subset, coastline-method, summary, coastline-method

read.ctd

Read a General CTD File

# **Description**

Read a General CTD File

#### Usage

```
read.ctd(file, type = NULL, columns = NULL, station = NULL, missingValue,
monitor = FALSE, debug = getOption("oceDebug"), processingLog, ...)
```

#### **Arguments**

file A connection or a character string giving the name of the file to load. For

read.ctd.sbe() and read.ctd.woce(), this may be a wildcard (e.g. "\*.cnv" or "\*.csv") in which case the return value is a vector containing CTD objects created by reading the files from list.files with pattern set to the specified

wildcard pattern.

type If NULL, then the first line is studied, in order to determine the file type. If

type="SBE19", then a *Seabird 19*, or similar, CTD format is assumed. If type="WOCE" then a WOCE-exchange file is assumed. If type="ITP" then an ice-tethered profiler file is assumed. If type="ODF" an ODF file is assumed. If type="ODV" an

ascii-ODV file is assumed.

columns An optional list that can be used to convert unrecognized data names to resul-

tant variable names. This is used only by read.ctd.sbe and read.ctd.odf;

see "Examples".

station Optional character string containing an identifying name or number for the sta-

tion. This can be useful if the routine cannot determine the name automatically,

or if another name is preferred.

missing Value Optional missing-value flag; data matching this value will be set to NA upon read-

ing. If this is provided, then it overrules any missing-value flag found in the data. For Seabird (.cnv) files, there is usually no need to set missingValue, because it can be inferred from the header (typically as -9.990e-29). Set missingValue=NULL to turn off missing-value detection, even in .cnv files that contain missing-value codes in their headers. If missingValue is not specified, then an attempt is made to infer such a value from the data, by testing whether salinity and/or temperature has a minimum that is under -8 in value; this should catch common values in files, without false positives. A warning will be issued in this case, and a note

inserted in the processing log of the return value.

read.ctd.itp 377

monitor Boolean, set to TRUE to provide an indication of progress. This is useful if

filename is a wildcard.

debug An integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest

that more information be printed.

processingLog If provided, the action item to be stored in the log. This is typically only pro-

vided for internal calls; the default that it provides is better for normal calls by a

user.

... additional arguments, passed to called routines.

#### **Details**

read.ctd() is a base function that in turn calls specialized functions, e.g. read.ctd.odf for the ODF data used in Fisheries and Oceans (Canada), read.ctd.woce for data in World Ocean Circulation Experiment format, read.ctd.woce.other for a variant of WOCE data, read.ctd.itp for ice-tethered-profiler data, or read.ctd.sbe for Seabird data.

#### Value

An object of ctd-class. The details of the contents depend on the source file. The metadata slot is particularly variable across data formats, because the meta-information provided in those formats varies widely.

# Author(s)

Dan Kelley

## See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

read.ctd.itp

Read an ITP-type CTD File

# **Description**

Read an ITP-type CTD File

# Usage

```
read.ctd.itp(file, columns = NULL, station = NULL, missingValue,
  monitor = FALSE, debug = getOption("oceDebug"), processingLog, ...)
```

378 read.ctd.itp

#### **Arguments**

file A connection or a character string giving the name of the file to load. For

read.ctd.sbe() and read.ctd.woce(), this may be a wildcard (e.g. "\*.cnv" or "\*.csv") in which case the return value is a vector containing CTD objects created by reading the files from list.files with pattern set to the specified

wildcard pattern.

columns An optional list that can be used to convert unrecognized data names to resul-

tant variable names. This is used only by read.ctd.sbe and read.ctd.odf;

see "Examples".

station Optional character string containing an identifying name or number for the sta-

tion. This can be useful if the routine cannot determine the name automatically,

or if another name is preferred.

missingValue Optional missing-value flag; data matching this value will be set to NA upon read-

ing. If this is provided, then it overrules any missing-value flag found in the data. For Seabird (.cnv) files, there is usually no need to set missingValue, because it can be inferred from the header (typically as -9.990e-29). Set missingValue=NULL to turn off missing-value detection, even in .cnv files that contain missing-value codes in their headers. If missingValue is not specified, then an attempt is made to infer such a value from the data, by testing whether salinity and/or temperature has a minimum that is under -8 in value; this should catch common values in files, without false positives. A warning will be issued in this case, and a note

inserted in the processing log of the return value.

monitor Boolean, set to TRUE to provide an indication of progress. This is useful if

filename is a wildcard.

debug An integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest

that more information be printed.

processingLog If provided, the action item to be stored in the log. This is typically only pro-

vided for internal calls; the default that it provides is better for normal calls by a

user.

... additional arguments, passed to called routines.

#### Details

read.ctd.itp() reads ice-tethered-profiler data that are stored in a format files used by WHOI servers as of 2016-2017. Lacking documentation on the format, the author constructed this function to work with some files that were on-hand. Whether the function will prove robust is an open question.

#### Value

An object of ctd-class. The details of the contents depend on the source file. The metadata slot is particularly variable across data formats, because the meta-information provided in those formats varies widely.

read.ctd.odf 379

## Author(s)

Dan Kelley

#### References

Information about ice-tethered profile data is provided at <a href="http://www.whoi.edu/page.do?pid=23096">http://www.whoi.edu/page.do?pid=23096</a>, which also provides a link for downloading data. Note that the present version only handles data in profiler-mode, not fixed-depth mode.

## See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

read.ctd.odf

Read a CTD file in ODF format

# **Description**

Read a CTD file in ODF format

#### Usage

```
read.ctd.odf(file, columns = NULL, station = NULL, missingValue,
  monitor = FALSE, debug = getOption("oceDebug"), processingLog, ...)
```

## **Arguments**

file	A connection or a character string giving the name of the file to load. For read.ctd.sbe() and read.ctd.woce(), this may be a wildcard (e.g. "*.cnv" or "*.csv") in which case the return value is a vector containing CTD objects created by reading the files from list.files with pattern set to the specified wildcard pattern.
columns	An optional list that can be used to convert unrecognized data names to resultant variable names. This is used only by read.ctd.sbe and read.ctd.odf; see "Examples".
station	Optional character string containing an identifying name or number for the station. This can be useful if the routine cannot determine the name automatically, or if another name is preferred.
missingValue	Optional missing-value flag; data matching this value will be set to NA upon reading. If this is provided, then it overrules any missing-value flag found in the data. For Seabird (.cnv) files, there is usually no need to set missingValue, because it can be inferred from the header (typically as -9.990e-29). Set missingValue=NULL

380 read.ctd.odf

to turn off missing-value detection, even in .cnv files that contain missing-value codes in their headers. If missingValue is not specified, then an attempt is made to infer such a value from the data, by testing whether salinity and/or temperature has a minimum that is under -8 in value; this should catch common values in files, without false positives. A warning will be issued in this case, and a note inserted in the processing log of the return value.

monitor Boolean, set to TRUE to provide an indication of progress. This is useful if

filename is a wildcard.

debug An integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest

that more information be printed.

processingLog If provided, the action item to be stored in the log. This is typically only pro-

vided for internal calls; the default that it provides is better for normal calls by a

user.

... additional arguments, passed to called routines.

#### **Details**

read.ctd.odf reads files stored in Ocean Data Format, used in some Canadian hydrographic databases.

#### Value

An object of ctd-class. The details of the contents depend on the source file. The metadata slot is particularly variable across data formats, because the meta-information provided in those formats varies widely.

#### Author(s)

Dan Kelley

# References

The ODF format, used by the Canadian Department of Fisheries and Oceans, is described to some extent in the documentation for read.odf. It is not clear that ODF format is handled correctly in read.odf, or the more general function read.odf, because the format varies between some sample files the author has encountered in his research.

#### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method,

read.ctd.sbe 381

oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, [[<-,odf-method, odf-class, plot,odf-method, read.odf, subset,odf-method, summary,odf-method

read.ctd.sbe

Read a Seabird CTD File

# Description

Read a Seabird CTD File

#### Usage

```
read.ctd.sbe(file, columns = NULL, station = NULL, missingValue,
  monitor = FALSE, debug = getOption("oceDebug"), processingLog, ...)
```

# **Arguments**

file A connection or a character string giving the name of the file to load. For

read.ctd.sbe() and read.ctd.woce(), this may be a wildcard (e.g. "\*.cnv" or "\*.csv") in which case the return value is a vector containing CTD objects created by reading the files from list.files with pattern set to the specified

wildcard pattern.

columns An optional list that can be used to convert unrecognized data names to resul-

tant variable names. This is used only by read.ctd.sbe and read.ctd.odf;

see "Examples".

station Optional character string containing an identifying name or number for the sta-

tion. This can be useful if the routine cannot determine the name automatically,

or if another name is preferred.

missingValue Optional missing-value flag; data matching this value will be set to NA upon read-

ing. If this is provided, then it overrules any missing-value flag found in the data. For Seabird (.cnv) files, there is usually no need to set missingValue, because it can be inferred from the header (typically as -9.990e-29). Set missingValue=NULL to turn off missing-value detection, even in .cnv files that contain missing-value codes in their headers. If missingValue is not specified, then an attempt is made to infer such a value from the data, by testing whether salinity and/or temperature has a minimum that is under -8 in value; this should catch common values in files, without false positives. A warning will be issued in this case, and a note

inserted in the processing log of the return value.

monitor Boolean, set to TRUE to provide an indication of progress. This is useful if

filename is a wildcard.

debug An integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest

that more information be printed.

382 read.ctd.sbe

processingLog If provided, the action item to be stored in the log. This is typically only provided for internal calls; the default that it provides is better for normal calls by a user.

... additional arguments, passed to called routines.

#### **Details**

This function reads files stored in Seabird .cnv format. Note that these files can contain multiple sensors for a given field. For example, the file might contain a column named t090C for one temperature sensor and t190C for a second. The first will be denoted temperature in the data slot of the return value, and the second will be denoted temperature1. This means that the first sensor will be used in any future processing that accesses temperature. This is for convenience of processing, and it does not pose a limitation, because the data from the second sensor are also available as e.g. x[["temperature1"]], where x is the name of the returned value. For the details of the mapping from .cnv names to ctd names, see cnvName2oceName.

The original data names as stored in file are stored within the metadata slot as dataNamesOriginal, and are displayed with summary alongside the numerical summary. See the Appendix VI of [2] for the meanings of these names (in the "Short Name" column of the table spanning pages 161 through 172).

#### Value

An object of ctd-class. The details of the contents depend on the source file. The metadata slot is particularly variable across data formats, because the meta-information provided in those formats varies widely.

#### A note on scales

The user may encounter data files with a variety of scales for temperature and salinity. Oce keeps track of these scales in the units it sets up for the stored variables. For example, if A is a CTD object, then A[["temperatureUnit"]]\$scale is a character string that will indicate the scale. Modernday data will have "ITS-90" for that scale, and old data may have "IPTS-68". The point of saving the scale in this way is so that the various formulas that deal with water properties can account for the scale, e.g. converting from numerical values saved on the "IPTS-68" scale to the newer scale, using T90fromT68 before doing calculations that are expressed in terms of the "ITS-90" scale. This is taken care of by retrieving temperatures with the accessor function, e.g. writing A[["temperature"]] will either retrieve the stored values (if the scale is ITS-90) or converted values (if the scale is IPTS-68). Even though this procedure should work, users who really care about the details of their data are well-advised to do a couple of tests after examining the first data line of their data file in an editor.

Note that reading a file that contains IPTS-68 temperatures produces a warning.

# Author(s)

read.ctd.woce 383

#### References

1. The Sea-Bird SBE 19plus profiler is described at http://www.seabird.com/products/spec\_sheets/19plusdata.htm. Some more information is given in the Sea-Bird data-processing manual http://www.seabird.com/document/sbe-data-processing-manual.

 $2.\ A\ SBE\ data\ processing\ manual\ is\ at\ http://www.seabird.com/document/sbe-data-processing-manual.$ 

#### See Also

```
Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd
```

## **Examples**

```
f <- system.file("extdata", "ctd.cnv", package="oce")
## Read the file in the normal way
d <- read.ctd(f)
## Read an imaginary file, in which salinity is named 'salt'
d <- read.ctd(f, columns=list(
    salinity=list(name="salt", unit=list(expression(), scale="PSS-78"))))</pre>
```

read.ctd.woce

Read a WOCE-type CTD file with First Word "CTD"

#### **Description**

Read a WOCE-type CTD file with First Word "CTD"

## Usage

```
read.ctd.woce(file, columns = NULL, station = NULL, missingValue,
  monitor = FALSE, debug = getOption("oceDebug"), processingLog, ...)
```

# **Arguments**

file

A connection or a character string giving the name of the file to load. For read.ctd.sbe() and read.ctd.woce(), this may be a wildcard (e.g. "\*.cnv" or "\*.csv") in which case the return value is a vector containing CTD objects created by reading the files from list.files with pattern set to the specified wildcard pattern.

columns

An optional list that can be used to convert unrecognized data names to resultant variable names. This is used only by read.ctd.sbe and read.ctd.odf; see "Examples".

384 read.ctd.woce

station Optional character string containing an identifying name or number for the sta-

tion. This can be useful if the routine cannot determine the name automatically,

or if another name is preferred.

missingValue Optional missing-value flag; data matching this value will be set to NA upon read-

ing. If this is provided, then it overrules any missing-value flag found in the data. For Seabird (.cnv) files, there is usually no need to set missingValue, because it can be inferred from the header (typically as -9.990e-29). Set missingValue=NULL to turn off missing-value detection, even in .cnv files that contain missing-value codes in their headers. If missingValue is not specified, then an attempt is made to infer such a value from the data, by testing whether salinity and/or temperature has a minimum that is under -8 in value; this should catch common values in files, without false positives. A warning will be issued in this case, and a note

inserted in the processing log of the return value.

monitor Boolean, set to TRUE to provide an indication of progress. This is useful if

filename is a wildcard.

debug An integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest

that more information be printed.

processingLog If provided, the action item to be stored in the log. This is typically only pro-

vided for internal calls; the default that it provides is better for normal calls by a

user.

... additional arguments, passed to called routines.

#### **Details**

read.ctd.woce() reads files stored in the exchange format used by the World Ocean Circulation Experiment (WOCE), in which the first 4 characters are "CTD,". It also also in a rarer format with the first 3 characters are CTD" followed by a blank or the end of the line.

# Value

An object of ctd-class. The details of the contents depend on the source file. The metadata slot is particularly variable across data formats, because the meta-information provided in those formats varies widely.

# Author(s)

Dan Kelley

#### References

The WOCE-exchange format is described at http://woce.nodc.noaa.gov/woce\_v3/wocedata\_1/whp/exchange/exchange and a sample file is at https://www.nodc.noaa.gov/woce/woce\_v3/wocedata\_1/whp/exchange/example\_ct1.csv

read.ctd.woce.other 385

#### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

read.ctd.woce.other

Read a WOCE-type CTD file with First Word "EXPOCODE"

## **Description**

Read a WOCE-type CTD file with First Word "EXPOCODE"

## Usage

```
read.ctd.woce.other(file, columns = NULL, station = NULL, missingValue,
  monitor = FALSE, debug = getOption("oceDebug"), processingLog, ...)
```

# **Arguments**

file	A connection	or a	character	string	giving	the	name	Ωf	the	file	tο	load	For
1110	11 connection	OI u	Character	Sums	8111118	uic	mamic	OI	uic	1110	w	rouu.	1 01

read.ctd.sbe() and read.ctd.woce(), this may be a wildcard (e.g. "\*.cnv" or "\*.csv") in which case the return value is a vector containing CTD objects created by reading the files from list.files with pattern set to the specified

wildcard pattern.

columns An optional list that can be used to convert unrecognized data names to resul-

tant variable names. This is used only by read.ctd.sbe and read.ctd.odf;

see "Examples".

station Optional character string containing an identifying name or number for the sta-

tion. This can be useful if the routine cannot determine the name automatically,

or if another name is preferred.

missingValue Optional missing-value flag; data matching this value will be set to NA upon read-

ing. If this is provided, then it overrules any missing-value flag found in the data. For Seabird (.cnv) files, there is usually no need to set missingValue, because it can be inferred from the header (typically as -9.990e-29). Set missingValue=NULL to turn off missing-value detection, even in .cnv files that contain missing-value codes in their headers. If missingValue is not specified, then an attempt is made to infer such a value from the data, by testing whether salinity and/or temperature has a minimum that is under -8 in value; this should catch common values in files, without false positives. A warning will be issued in this case, and a note

inserted in the processing log of the return value.

monitor Boolean, set to TRUE to provide an indication of progress. This is useful if

filename is a wildcard.

386 read.echosounder

debug An integer specifying whether debugging information is to be printed during

the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest

that more information be printed.

processingLog If provided, the action item to be stored in the log. This is typically only pro-

vided for internal calls; the default that it provides is better for normal calls by a

user.

... additional arguments, passed to called routines.

#### **Details**

read.ctd.woce.other() reads files stored in the exchange format used by the World Ocean Circulation Experiment (WOCE), in which the first word in the file is EXPOCODE.

#### Value

An object of ctd-class. The details of the contents depend on the source file. The metadata slot is particularly variable across data formats, because the meta-information provided in those formats varies widely.

#### Author(s)

Dan Kelley

# See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

read.echosounder

Read an Echosounder File

## **Description**

Reads a biosonics echosounder file. This function was written for and tested with single-beam, dual-beam, and split-beam Biosonics files of type V3, and may not work properly with other file formats.

## Usage

```
read.echosounder(file, channel = 1, soundSpeed, tz = getOption("oceTz"),
  debug = getOption("oceDebug"), processingLog)
```

read.echosounder 387

#### **Arguments**

file a connection or a character string giving the name of the file to load.

channel sequence number of channel to extract, for multi-channel files.

soundSpeed sound speed, in m/s. If not provided, this is calculated using swSoundSpeed(35, 15, 30, eos="unesco"

(In theory, it could be calculated using the temperature and salinity that are

stored in the data file, but these will just be nominal values, anyway.

tz character string indicating time zone to be assumed in the data.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

processingLog if provided, the action item to be stored in the log, typically only provided for

internal calls.

#### Value

An object of class "echosounder" with standard slots metadata, data and processingLog that are described in the documentation for the object echosounder-class.

#### **Bugs**

Only the amplitude information (in counts) is determined. A future version of this function may provide conversion to dB, etc. The handling of dual-beam and split-beam files is limited. In the dual-beam cse, only the wide beam signal is processed (I think ... it could be the narrow beam, actually, given the confusing endian tricks being played). In the split-beam case, only amplitude is read, with the x-axis and y-axis angle data being ignored.

# Author(s)

Dan Kelley, with help from Clark Richards

#### References

Various echosounder instruments provided by BioSonics are described at the company website, <a href="http://www.biosonicsinc.com/">http://www.biosonicsinc.com/</a>. The document listed as [1] below was provided to the author of this function in November 2011, which suggests that the data format was not changed since July 2010.

[1] Biosonics, 2010. DT4 Data File Format Specification. BioSonics Advanced Digital Hydroacoustics. July, 2010. SOFTWARE AND ENGINEERING LIBRARY REPORT BS&E-2004-07-0009-2.0.

#### See Also

The documentation for echosounder-class explains the structure of ctd objects, and also outlines the other functions dealing with them.

Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, as.echosounder, echosounder-class, echosounder, findBottom, plot, echosounder-method, subset, echosounder-method, summary, echosounder-method

388 read.g1sst

read.glsst

Read a G1SST file

# **Description**

Read a G1SST file in the netcdf format provided by the ERDAPP server [1].

# Usage

```
read.g1sst(filename)
```

# **Arguments**

filename

name of a netcdf file containing G1SST data.

#### **Details**

As noted in the documentation for g1sst-class, one must be aware of the incorporation of model simulations in the g1sst product. For example, the code presented below might lead one to believe that the mapped field represents observations, whereas in fact it can be verified by consulting [2] (clicking and unclicking the radio button to show just the data) that the field mostly derives from simulation.

#### Value

An object of g1sst-class.

## Author(s)

Dan Kelley

## References

1. ERDDAP Portal http://coastwatch.pfeg.noaa.gov/erddap/ 2. JPO OurOcean Portal http://ourocean.jpl.nasa.clink worked in 2016 but was seen to fail 2017 Feb 2).

#### See Also

```
Other things related to satellite data: g1sst-class, plot, satellite-method, satellite-class, summary, satellite-method
```

# **Examples**

```
## Not run:  
# Construct query, making it easier to understand and modify.  
day <- "2016-01-02"  
lon0 <- -66.5  
lon1 <- -64.0  
lat0 <- 44
```

read.gps 389

read.gps

Read a GPS File

## **Description**

Reads GPX format files by simply finding all longitudes and latitudes; in other words, information on separate tracks, or waypoints, etc., is lost.

## Usage

```
read.gps(file, type = NULL, debug = getOption("oceDebug"), processingLog)
```

# **Arguments**

file name of file containing gps data.

type type of file, which will be inferred from examination of the data if not supplied.

In the present version, the only choice for type is "gpx".

debug set to TRUE to print information about the header, etc.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

#### Value

```
An object of class "gps".
```

#### Author(s)

Dan Kelley

### See Also

```
Other things related to gps data: [[,gps-method,[[<-,gps-method,as.gps,gps-class,plot,gps-method,summary,gps-method]
```

390 read.index

read.index	Read a NOAA ocean index file

# **Description**

Read an ocean index file, in the format used by NOAA.

## Usage

```
read.index(file, format, missingValue, tz = getOption("oceTz"),
  debug = getOption("oceDebug"))
```

# **Arguments**

file a connection or a character string giving the name of the file to load. May be a

URL.

format optional character string indicating the format type. If not supplied, a guess will

be made, based on examination of the first few lines of the file. If supplied, the

possibilities are "noaa" and "ucar". See "Details".

missingValue If supplied, this is a numerical value that indicates invalid data. In some datasets,

this is -99.9, but other values may be used. If missingValue is not supplied, any data that have value equal to or less than -99 are considered invalid. Set

missing Value to TRUE to turn of the processing of missing values.

tz character string indicating time zone to be assumed in the data.

debug a flag that turns on debugging, ignored in the present version of the function.

# **Details**

Reads a text-format index file, in either of two formats. If format is missing, then the first line of the file is examined. If that line contains 2 (whitespace-separated) tokens, then "noaa" format is assumed. If it contains 13 tokens, then "ucar" format is assumed. Otherwise, an error is reported.

In the "noaa" format, the two tokens on the first line are taken to be the start year and the end year, respectively. The second line must contain a single token, the missing value. All further lines must contain 12 tokens, for the values in January, February, etc.

In the "ucar" format, all data lines must contain the 13 tokens, the first of which is the year, with the following 12 being the values for January, February, etc.

# Value

A data frame containing t, a POSIX time, and index, the numerical index. The times are set to the 15th day of each month, which is a guess that may need to be changed if so indicated by documentation (yet to be located).

#### Author(s)

391 read.landsat

#### References

See https://www.esrl.noaa.gov/psd/data/climateindices/list/ for a list of indices.

#### **Examples**

```
## Not run:
library(oce)
par(mfrow=c(2, 1))
# 1. AO, Arctic oscillation
ao <- read.index("https://www.esrl.noaa.gov/psd/data/correlation/ao.data")</pre>
aorecent \leftarrow subset(ao, t > as.POSIXct("2000-01-01"))
oce.plot.ts(aorecent$t, aorecent$index)
# 2. SOI, probably more up-to-date then data(soi, package="ocedata")
soi <- read.index("https://www.cgd.ucar.edu/cas/catalog/climind/SOI.signal.ascii")</pre>
soirecent <- subset(soi, t > as.POSIXct("2000-01-01"))
oce.plot.ts(soirecent$t, soirecent$index)
## End(Not run)
```

read.landsat

Read a landsat File Directory

# **Description**

Read a landsat data file, producing an object of landsat-class. The actual reading is done with readTIFF in the tiff package, so that package must be installed for read. landsat to work.

# Usage

```
read.landsat(file, band = "all", emissivity = 0.984, decimate,
 debug = getOption("oceDebug"))
```

#### **Arguments**

file

A connection or a character string giving the name of the file to load. This is a

directory name containing the data.

band

The bands to be read, by default all of the bands. Use 'band=NULL' to skip the reading of bands, instead reading only the image metadata, which is often enough to check if the image is of interest in a given study. See 'Details' for the names of the bands, some of which are pseudo-bands, computed from the actual

data.

emissivity

Value of the emissivity of the surface, stored as emissivity in the metadata slot of the resultant object. This is used in the calculation of surface temperature, as explained in the discussion of accessor functions for landsat-class. The default value is from Konda et al. (1994). These authors suggest an uncertainty of 0.04, but a wider range of values can be found in the literature. The value of metadata\$emissivity is easy to alter, either as a single value or as a matrix, yielding flexibility of calculation.

392 read.landsat

decimate optional positive integer indicating the degree to which the data should be sub-

sampled after reading and before storage. Setting this to 10 can speed up reading by a factor of 3 or more, but higher values have diminishing effect. In exploratory work, it is useful to set decimate=10, to plot the image to determine a

subregion of interest, and then to use landsatTrim to trim the image.

debug a flag that turns on debugging. Set to 1 to get a moderate amount of debugging

information, or to 2 to get more.

#### **Details**

Landsat data are provided in directories that contain TIFF files and header information, and read.landsat relies on a strict convention for the names of the files in those directories. Those file names were found by inspection of some data, on the assumption that similar patterns will hold for other datasets for any given satellite. This is a brittle approach and it should be born in mind if read.landsat fails for a given dataset.

For Landsat 8, there are 11 bands, with names "aerosol" (band 1), "blue" (band 2), "green" (band 3), "red" (band 4), "nir" (band 5), "swir1" (band 6), "swir2" (band 7), "panchromatic" (band 8), "cirrus" (band 9), "tirs1" (band 10), and "tirs2" (band 11). In addition to the above, setting band="terralook" may be used as an abbreviation for band=c("red", "green", "nir").

For Landsat 7, there 8 bands, with names "blue" (band 1), "green" (band 2), "red" (band 3), "nir" (band 4), "swir1" (band 5), "tir1" (band 6A), "tir2" (band 6B), "swir2" (band 7) and "panchromatic" (band 8).

For Landsat 4 and 5, the bands similar to Landsat 7 but without "panchromatic" (band 8).

# Value

An object of landsat-class, with the conventional Oce slots metadata, data and processingLog. The metadata is mainly intended for use by Oce functions, but for generality it also contains an entry named header that represents the full image header in a list (with names made lower-case). The data slot holds matrices of the data in the requested bands, and users may add extra matrices if desired, e.g. to store calculated quantities.

## Storage requirements

Landsat data files (directories, really) are large, accounting for approximately 1 gigabyte each. The storage of the Oce object is similar (see landsat-class). In R, many operations involving copying data, so that dealing with full-scale landsat images can overwhelm computers with storage under 8GB. For this reason, it is typical to read just the bands that are of interest. It is also helpful to use landsatTrim to trim the data to a geographical range, or to use decimate to get a coarse view of the domain, especially early in an analysis.

#### Author(s)

read.lisst 393

#### References

1. Konda, M. Imasato N., Nishi, K., and T. Toda, 1994. Measurement of the Sea Surface Emissivity. *Journal of Oceanography*, 50, 17:30. Available at http://www.terrapub.co.jp/journals/J0/pdf/5001/50010017.pdf as of February 2015.

#### See Also

landsat-class for more information on landsat objects, especially band information. Use landsatTrim to trim Landsat objects geographically and landsatAdd to add new "bands." The accessor operator ([[]) is used to access band information, full or decimated, and to access certain derived quantities. A sample dataset named landsat is provided by the oce package.

Other things related to landsat data: [[,landsat-method,landsat-class,landsatAdd,landsatTrim,landsat,plot,landsat-method,summary,landsat-method

read.lisst

Read a LISST File

# **Description**

Read a LISST data file, producing a lisst object, i.e. one inheriting from lisst-class. The file should contain 42 columns, with no header. If there are fewer than 42 columns, an error results. If there are more, only the first 42 are used. Note that read.oce can recognize LISST files by their having a name ending in ".asc" and by having 42 elements on the first line. Even so, it is preferred to use the present function, because it gives the opportunity to specify the year and timezone, so that times can be calculated properly.

# Usage

```
read.lisst(file, year = 0, tz = "UTC", longitude = NA, latitude = NA)
```

#### Arguments

file a connection or a character string giving the name of the file to load.

year in which the measurement of the series was made.

tz time zone.

latitude longitude of observation (stored in metadata)

#### Value

An object of lisst-class.

#### Author(s)

394 read.lobo

## See Also

Other things related to lisst data: [[,lisst-method, [[<-,lisst-method, as.lisst, lisst-class, plot,lisst-method, summary,lisst-method

read.lobo

Read a LOBO File

# **Description**

Read a data file created by a LOBO instrument.

# Usage

```
read.lobo(file, cols = 7, processingLog)
```

# **Arguments**

file a connection or a character string giving the name of the file to load.

cols number of columns in dataset.

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

# **Details**

This version of read.1obo is really quite crude, having been developed mainly for a "predict the Spring bloom" contest at Dalhousie University. In particular, the function assumes that the data columns are exactly as specified in the Examples section; if you reorder the columns or add new ones, this function is unlikely to work correctly. Furthermore, it should be noted that the file format was inferred simply by downloading files; the supplier makes no claims that the format will be fixed in time. It is also worth noting that there is no read.oce equivalent to read.1obo, because the file format has no recognizable header.

# Value

An object of lobo-class.

# Author(s)

read.met 395

## **Examples**

```
## Not run:
library(oce)
uri <- paste("http://lobo.satlantic.com/cgi-bin/nph-data.cgi?",
    "min_date=20070220&max_date=20070305",
    "&x=date&",
    "y=current_across1,current_along1,nitrate,fluorescence,salinity,temperature&",
    "data_format=text",sep="")
lobo <- read.lobo(uri)
## End(Not run)</pre>
```

read.met

Read a met File

# **Description**

Reads a comma-separated value file in the format used by the Environment Canada [1]. The agency does not publish a format for these files, so this function was based on a study of a few sample files, and it may fail for other files, if Environment Canada changes the format.

#### Usage

```
read.met(file, type = NULL, skip, tz = getOption("oceTz"),
  debug = getOption("oceDebug"))
```

# **Arguments**

file	a connection or a character string giving the name of the file to load.
type	if NULL, then the first line is studied, in order to determine the file type. If type="msc", then a file as formatted by Environment Canada is assumed.
skip	optional number of lines of header that occur before the actual data. If this is not supplied, read.met scans the file until it finds a line starting with "Date/Time", and considers all lines above that to be header.
tz	timezone assumed for time data
debug	a flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.

#### Value

An object of class "met", of which the data slot contains vectors time, temperature, pressure, u, and v. The velocity components have units m/s and are the components of the vector of wind direction. In other words, the oceanographic convention on velocity is employed, not the meteorological one; the weather forecaster's "North wind" has positive v and zero u. In addition to these things, data also contains wind (in km/h), taken straight from the data file.

396 read.netcdf

# Note

There seem to be several similar formats in use, so this function may not work in all cases.

# Author(s)

Dan Kelley

#### References

1. Environment Canada website for Historical Climate Data <a href="http://climate.weather.gc.ca/index\_e.html">http://climate.weather.gc.ca/index\_e.html</a>

## See Also

```
Other things related to met data: [[,met-method, [[<-,met-method, as.met, download.met, met-class, met, plot,met-method, subset,met-method, summary,met-method
```

# **Examples**

read.netcdf

Read a NetCDF File

# **Description**

Read a NetCDF File

# Usage

```
read.netcdf(file, ...)
```

## **Arguments**

```
file the name of a file ... unused
```

read.oce 397

#### **Details**

Read a netcdf file, trying to interpret its contents sensibly.

It is important to note that this is a preliminary version of this function, and much about it may change without notice. Indeed, it may be removed entirely.

Below are some features that may be changed.

- 1. The names of data items are not changed from those in the netcdf file on the assumption that this will offer the least surprise to the user.
- 2. An attempt is made to find some common metadata from global attributes in the netcdf file. These attributes include Longitude, Latitude, Ship and Cruise. Before they are stored in the metadata, they are converted to lower case, since that is the oce convention.

#### Value

An object of oce-class.

read.oce

Read an Oceanographic Data File

## Description

Read an oceanographic data file, auto-discovering the file type from the first line of the file. This function tries to infer the file type from the first line, using oceMagic. If it can be discovered, then an instrument-specific file reading function is called, with the file and with any additional arguments being supplied.

### Usage

```
read.oce(file, ...)
```

# Arguments

file a connection or a character string giving the name of the file to load.

arguments to be handed to whichever instrument-specific reading function is selected, based on the header.

#### Value

An object of oce-class that is specialized to the data type, e.g. ctd-class, if the data file contains ctd data.

## Author(s)

Dan Kelley

398 read.odf

#### See Also

The file type is determined by oceMagic. If the file type can be determined, then one of the following is called: read.ctd, read.coastline read.lobo, read.rsk, read.sealevel, etc.

### **Examples**

```
library(oce)
x <- read.oce(system.file("extdata", "ctd.cnv", package="oce"))
plot(x) # summary with TS and profiles
plotTS(x) # just the TS</pre>
```

read.odf

Read an ODF file

## **Description**

ODF (Ocean Data Format) is a format developed at the Bedford Institute of Oceanography and also used at other Canadian Department of Fisheries and Oceans (DFO) facilities. It can hold various types of time-series data, which includes a variety of instrument types. Thus, read.odf is used by read.ctd.odf for CTD data, etc. As of mid-2015, read.odf is still in development, with features being added as a project with DFO makes available more files.

#### Usage

```
read.odf(file, columns = NULL, debug = getOption("oceDebug"))
```

## **Arguments**

file the file containing the data.

columns An optional list that can be used to convert unrecognized data names to resul-

tant variable names. For example, columns=list(salinity=list(name="salt", unit=list(unit=ex

states that a short-name of "salt" represents salinity, and that the unit is as indicated. This is passed to cnvName2oceName or ODFNames2oceNames, as appro-

priate, and takes precedence over the lookup table in that function.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

read.odf 399

#### **Details**

Note that some elements of the metadata are particular to ODF objects, e.g. depthMin, depthMax and sounding, which are inferred from ODF items named MIN\_DEPTH, MAX\_DEPTH and SOUNDING, respectively. In addition, the more common metadata item waterDepth, which is used in ctd objects to refer to the total water depth, is set to sounding if that is finite, or to maxDepth otherwise.

The function ODFNames2oceNames is used to translate data names from the ODF file to standard oce names, and handles conversion for a few non-standard units. The documentation of ODFNames2oceNames should be consulted for more details.

#### Value

An object of class oce. It is up to a calling function to determine what to do with this object.

#### Caution

ODF files do not store information on the temperature or salinity scale, and read.odf assumes them to be ITS-90 and PSS-78, respectively. These scales will not be correct for old data files. Note that the temperature scale can be converted from old scales using T90fromT68 and T90fromT48, although the change will be in a fraction of a millidegree, which probably exceeds reasonable confidence in old data.

#### References

- [1] Anthony W. Isenor and David Kellow, 2011. ODF Format Specification Version 2.0. (This is a .doc file downloaded from a now-forgotten URL by Dan Kelley, in June 2011.)
- [2] The St Lawrence Global Observatory website has information on ODF format at https://slgo.ca/app-sgdo/en/docs\_reference/format\_odf.html

#### See Also

ODF20ce will be an alternative to this, once (or perhaps if) a ODF package is released by the Canadian Department of Fisheries and Oceans.

Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, [[<-,odf-method, odf-class, plot,odf-method, read.ctd.odf, subset,odf-method, summary,odf-method

```
library(oce)
# Read a CTD cast made on the Scotian Shelf. Note that the file's metadata
# states that conductivity is in S/m, but it is really conductivity ratio,
# so we must alter the unit before converting to a CTD object. Note that
# read.odf() on this data file produces a warning suggesting that the user
# repair the unit, using the method outlined here.
odf <- read.odf(system.file("extdata", "CTD_BCD2014666_008_1_DN.ODF", package="oce"))
odf[["conductivityUnit"]] <- list(unit=expression(), scale="")
#
# Figure 1. make a CTD, and plot (with span to show NS)
plot(as.ctd(odf), span=500)
# Figure 2. highlight bad data on TS diagram</pre>
```

400 read.rsk

```
plotTS(odf, type='o') # use a line to show loops
bad <- odf[["QCFlag"]]!=0
points(odf[['salinity']][bad],odf[['temperature']][bad],col='red',pch=20)</pre>
```

read.rsk

Read a Rsk file

# Description

Read an RBR rsk or txt file, e.g. as produced by an RBR logger, producing an object of class rsk.

## Usage

# Arguments

file	a connection or a character string giving the name of the file to load. Note that file must be a character string, because connections are not used in that case, which is instead handled with database calls.
from	indication of the first datum to read. This can a positive integer to indicate sequence number, the POSIX time of the first datum, or a character string that can be converted to a POSIX time. (For POSIX times, be careful about the tz argument.)
to	an indication of the last datum to be read, in the same format as from. If to is missing, data will be read to the end of the file.
by	an indication of the stride length to use while walking through the file. If this is an integer, then by-1 samples are skipped between each pair of samples that is read. If this is a string representing a time interval, in colon-separated format (HH:MM:SS or MM:SS), then this interval is divided by the sampling interval, to get the stride length.
type	optional file type, presently can be rsk or txt (for a text export of an RBR rsk or hex file). If this argument is not provided, an attempt will be made to infer the type from the file name and contents.
tz	time zone. The value oceTz is set at package setup.
patm	controls the handling of atmospheric pressure, an important issue for RBR instruments that record absolute pressure; see "Details".
processingLog	if provided, the action item to be stored in the log. This is typically only provided for internal calls; the default that it provides is better for normal calls by a user.
debug	a flag that can be set to TRUE to turn on debugging.

read.rsk 401

#### **Details**

This can read files produced by several RBR instruments. At the moment, five styles are understood: (1) text file produced as an export of an RBR hex or rsk file; (2) text file with columns for temperature and pressure (with sampling times indicated in the header); (3) text file with four columns, in which the date the time of day are given in the first two columns, followed by the temperature, and pressure; (4) text file with five columns, in which depth in the water column is given after the pressure; (5) an SQLite-based database format. The first four options are provided mainly for historical reasons, since RBR instruments at the date of writing commonly use the SQLite format, though the first option is common for all instruments that produce a hex file that can be read using Ruskin.

Options 2-4 are mostly obsolete, and will be removed from future versions.

A note on conductivity. RBR devices record conductivity in mS/cm, and it is this value that is stored in the object returned by read.rsk. This can be converted to conductivity ratio (which is what many other instruments report) by dividing by 42.914 (see Culkin and Smith, 1980) which will be necessary in any seawater-related function that takes conductivity ratio as an argument (see "Examples").

A note on pressure. RBR devices tend to record absolute pressure (i.e. sea pressure plus atmospheric pressure), unlike most oceanographic instruments that record sea pressure (or an estimate thereof). The handling of pressure is controlled with the patm argument, for which there are three possibilities. (1) If patm is FALSE (the default), then pressure read from the data file is stored in the data slot of return value, and the metadata item pressureType is set to the string "absolute". (2) If patm is TRUE, then an estimate of atmospheric pressure is subtracted from the raw data. For data files in the SQLite format (i.e. \*.rsk files), this estimate will be the value read from the file, or the "standard atmosphere" value 10.1325 dbar, if the file lacks this information. (3) If patm is a numerical value (or list of values, one for each sampling time), then patm is subtracted from the raw data. In cases 2 and 3, an additional column named pressureOriginal is added to the data slot to store the value contained in the data file, and pressureType is set to a string starting with "sea". See as.ctd for details of how this setup facilitates the conversion of rsk-class objects to ctd-class objects.

### Value

An object of rsk-class.

#### Author(s)

Dan Kelley and Clark Richards

### References

Culkin, F., and Norman D. Smith, 1980. Determination of the concentration of potassium chloride solution having the same electrical conductivity, at 15 C and infinite frequency, as standard seawater of salinity 35.0000 ppt (Chlorinity 19.37394 ppt). *IEEE Journal of Oceanic Engineering*, **5**, pp 22-23.

#### See Also

The documentation for rsk-class explains the structure of rsk objects, and also outlines other functions dealing with them. Since RBR has a wide variety of instruments, rsk datasets can be

402 read.sealevel

quite general, and it is common to coerce rsk objects to other forms for specialized work, e.g. as.ctd can be used to create CTD object, so that the generic plot obeys the CTD format.

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, rsk-class, rskPatm, rskToc, rsk, subset,rsk-method, summary,rsk-method

read.sealevel

Read a Sealevel File

### **Description**

Read a data file holding sea level data. BUG: the time vector assumes GMT, regardless of the GMT.offset value.

## Usage

```
read.sealevel(file, tz = getOption("oceTz"), processingLog,
  debug = getOption("oceDebug"))
```

### **Arguments**

file a connection or a character string giving the name of the file to load. See Details

for the types of files that are recognized.

tz time zone. The default value, oceTz, is set to UTC at setup. (If a time zone is

present in the file header, this will supercede the value given here.)

processingLog if provided, the action item to be stored in the log. (Typically only provided for

internal calls; the default that it provides is better for normal calls by a user.)

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### **Details**

This function starts by scanning the first line of the file, from which it determines whether the file is in one of two known formats: type 1, the format used at the Hawaii archive centre, and type 2, the comma-separated-value format used by the Marine Environmental Data Service. (The file type is inferred by checking for the existence of the string Station\_Name on the first line of the file, indicating type 2.) If the file is in neither of these formats, the user might wish to scan it directly, and then to use as . sealevel to create a sealevel object.

## Value

An object of sealevel-class.

read.section 403

## Author(s)

Dan Kelley

#### References

The Hawaii archive site at http://ilikai.soest.hawaii.edu/uhslc/datai.html provides a graphical interface for downloading sealevel data in Type 1, with format as described at http://ilikai.soest.hawaii.edu (this link worked for years but failed at least temporarily on December 4, 2016). The MEDS repository (http://www.isdm-gdsi.gc.ca/isdm-gdsi/index-eng.html) provides Type 2 data.

#### See Also

Other things related to sealevel data: [[, sealevel-method, [[<-, sealevel-method, as.sealevel, plot, sealevel-method, sealevel-class, sealevelTuktoyaktuk, sealevel, subset, sealevel-method, summary, sealevel-method

## **Examples**

```
## Not run:
library(oce)
# this yields the sealevel dataset
sl <- read.oce("h275a96.dat")
summary(sl)
plot(sl)
m <- tidem(sl)
plot(m)
## End(Not run)</pre>
```

read.section

Read a Section File

### Description

Read a file that contains a series of ctd profiles that make up an oceanographic section. Only *exchange BOT* comma-separated value format is permitted at this time, but other formats may be added later. It should also be noted that the parsing scheme was developed after inspection of the A03 data set (see Examples). This may cause problems if the format is not universal. For example, the header must name the salinity column "CTDSAL"; if not, salinity values will not be read from the file.

```
read.section(file, directory, sectionId = "", flags, ship = "",
    scientist = "", institute = "", missingValue = -999,
    debug = getOption("oceDebug"), processingLog)
```

404 read.section

### **Arguments**

file A file containing a set of CTD observations. At present, only the exchange BOT

format is accepted (see Details).

directory A character string indicating the name of a directory that contains a set of CTD

files that hold individual stations in the section.

sectionId Optional string indicating the name for the section. If not provided, the section

ID is determined by examination of the file header.

flags Ignored, and deprecated (will be disallowed in a future version).

ship Name of the ship carrying out the sampling.

scientist Name of chief scientist aboard ship.

Institute Name of chief scientist's institute.

missingValue Numerical value used to indicate missing data.

debug Logical. If TRUE, print some information that might be helpful during debug-

ging.

processingLog If provided, the action item to be stored in the log. This is typically only pro-

vided for internal calls; the default that it provides is better for normal calls by a

user.

#### Value

An object of class section-class.

## Disambiguating salinity

WOCE datasets commonly have a column named CTDSAL for salinity inferred from a CTD and SALNTY (not a typo) for salinity derived from bottle data. If only one of these is present in the data file, the data will be called salinity in the data slot of the return value. However, if both are present, then CTDSAL is stored as salinity and SALNTY is stored as salinityBottle.

### Author(s)

Dan Kelley

#### References

Several repository sites provide section data. An example that is perhaps likely to exist for years is <a href="https://cchdo.ucsd.edu">https://cchdo.ucsd.edu</a>, but a search on "WOCE bottle data" should turn up other sites, if this one ceases to exist. Only the so-called *exchange BOT* data format can be processed by read.section() at this time. Data names are inferred from column headings using woceNames2oceNames.

## See Also

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags,section-method, plot,section-method, section-class, sectionAddStation, sectionGrid,sectionSmooth,sectionSort,section,subset,section-method,summary,section-method

read.topo 405

|--|

### **Description**

Read a file that contains topographic data in the ETOPO dataset, as provided by the NOAA website (see download.topo for a good server for such files.

## Usage

```
read.topo(file, debug = getOption("oceDebug"))
```

## **Arguments**

file Name of a file containing an ETOPO-format dataset. Three types are permitted;

see "Details".

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## **Details**

The three permitted file types are as follows: (1) an ascii type described by NOAA as "?"; (2) a NetCDF format described by NOAA as "GMT NetCDF" (recognized by the presence of a variable named), and (3) another NetCDF format described by NOAA as "NetCDF" (recognized by the presence of a variable called). Files in each of these formats can be downloaded with download.topo.

### Value

An object of type topo-class that which has the following slots.

data : a data frame containing lat, lon, and z
metadata : a list containing the source filename
processingLog : a log, in the standard oce format.

## Author(s)

Dan Kelley

## See Also

Other things related to topo data: [[,topo-method, [[<-,topo-method, as.topo, download.topo, plot,topo-method, subset,topo-method, summary,topo-method,topo-class,topoInterpolate, topoWorld

406 rescale

### **Examples**

```
## Not run:
library(oce)
topoMaritimes <- read.topo("topoMaritimes.asc")
plot(topographyMaritimes)
## End(Not run)</pre>
```

renameData

Rename items in the data slot of an oce object

## Description

This function may be used to rename elements within the data slot of oce objects. It also updates the processing log of the returned object, indicating the changes.

## Usage

```
renameData(x, old = NULL, new = NULL)
```

## **Arguments**

An oce object, i.e. one inheriting from oce-class.
 Vector of strings, containing old names.
 Vector of strings, containing old names.

## **Examples**

rescale

Rescale values to lie in a given range

## **Description**

This is helpful in e.g. developing a colour scale for an image plot. It is not necessary that rlow be less than rhigh, and in fact reversing them is a good way to get a reversed colour scale for a plot.

```
rescale(x, xlow, xhigh, rlow = 0, rhigh = 1, clip = TRUE)
```

resizableLabel 407

## **Arguments**

X	a numeric vector.
xlow	$\boldsymbol{x}$ value to correspond to rlow. If not given, it will be calculated as the minimum value of $\boldsymbol{x}$
xhigh	$\boldsymbol{x}$ value to correspond to rhigh. If not given, it will be calculated as the maximum value of $\boldsymbol{x}$
rlow	value of the result corresponding to x equal to xlow.
rhigh	value of the result corresponding to x equal to xhigh.
clip	logical, set to TRUE to clip the result to the range spanned by rlow and rhigh.

### Value

A new vector, which has minimum lim[1] and maximum lim[2].

## Author(s)

Dan Kelley

# **Examples**

resizableLabel

Provide axis names in adjustable sizes

# Description

Provide axis names in adjustable sizes, e.g. using T instead of Temperature, and including units as appropriate. Used by e.g. plot, ctd-method.

```
resizableLabel(item, axis, sep, unit = NULL)
```

408 retime

## Arguments

item	code for the label. This must be an element from the following list, or an abbreviation that uniquely identifies an element through its first letters: "S", "C", "conductivity mS/cm", "conductivity S/m", "T", "theta", "sigmaTheta", "conservative temperature", "absolute salinity", "nitrate", "nitrite", "oxygen", "oxygen saturation", "oxygen mL/L", "oxygen umol/L", "oxygen umol/kg", "phosphate", "silicate", "tritium", "spice", "fluorescence", "p", "z", "distance", "distance km", "along-track distance km", "heading", "pitch", "roll", "u", "v", "w", "speed", "direction", "eastward", "northward", "depth", "elevation", "latitude", "longitude", "frequency cph", or "spectral density m2/cph".
axis	a string indicating which axis to use; must be x or y.
sep	optional character string inserted between the unit and the parentheses or brackets that enclose it. If not provided, then getOption("oceUnitSep") is checked. If that exists, then it is used as the separator; if not, no separator is used.
unit	optional unit to use, if the default is not satisfactory. This might be the case if for example temperature was not measured in Celcius.

#### Value

A character string or expression, in either a long or a shorter format, for use in the indicated axis at the present plot size. Whether the unit is enclosed in parentheses or square brackets is determined by the value of getOption("oceUnitBracket"), which may be "[" or "(". Whether spaces are used between the unit and these deliminators is set by psep or getOption("oceUnitSep").

## Author(s)

Dan Kelley

|--|

Adjust the time within Oce object

## **Description**

This function compensates for drifting instrument clocks, according to t'=t+a+b(t-t0), where t' is the true time and t is the time stored in the object. A single check on time mismatch can be described by a simple time offset, with a non-zero value of a, a zero value of b, and an arbitrary value of t0. Checking the mismatch before and after an experiment yields sufficient information to specify a linear drift, via a, b, and t0. Note that t0 is just a convenience parameter, which avoids the user having to know the "zero time" used in R and clarifies the values of the other two parameters. It makes sense for t0 to have the same timezone as the time within x.

```
retime(x, a, b, t0, debug = getOption("oceDebug"))
```

rsk 409

## Arguments

X	an oce object (presently, this must be of class adv)
а	intercept [in seconds] in linear model of time drift (see "Details").
b	slope [unitless] in linear model of time drift [unitless] (see "Details").
t0	reference time [in POSIXct format] used in linear model of time drift (see "Details").
debug	a flag that, if nonzero, turns on debugging.

#### **Details**

The returned object is computed by linear interpolation, using approx with rule=2, to avoid NA values at the start or end. The new time will be as given by the formula above. Note that if the drift is large enough, the sampling rate will be changed. It is a good idea to start with an object that has an extended time range, so that, after this is called, subset can be used to trim to a desired time range.

#### Value

A new object, with time and other data adjusted.

### Author(s)

Dan Kelley

# **Examples**

```
library(oce)
data(adv)
adv2 <- retime(adv,0,1e-4,as.POSIXct("2008-07-01 00:00:00",tz="UTC"))
plot(adv[["time"]], adv2[["time"]]-adv[["time"]], type='1')</pre>
```

rsk

Sample Rsk Dataset

## **Description**

A sample rsk object derived from a Concerto CTD manufactured by RBR Ltd.

## **Details**

The data were obtained September 2015, off the west coast of Greenland, by Matt Rutherford and Nicole Trenholm of the Ocean Research Project, in collaboration with RBR and with the NASA Oceans Melting Greenland project.

#### References

```
https://rbr-global.com/
```

410 rsk-class

## See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, sealevelTuktoyaktuk, sealevel, section, topoWorld, wind

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rsk-class, rskPatm, rskToc, subset,rsk-method, summary,rsk-method

## **Examples**

```
library(oce)
data(rsk)
## The object doesn't "know" it is CTD until told so
plot(rsk)
plot(as.ctd(rsk))
```

rsk-class

Class to Store Rsk Data

## **Description**

Class for data stored in the "Ruskin" format used by RBR [1], including both rsk SQLite files and the ASCII txt exported files.

A rsk object may be read with read.rsk or created with as.rsk. Plots can be made with plot,rsk-method, while summary,rsk-method produces statistical summaries and show produces overviews. If atmospheric pressure has not been removed from the data, the functions rskPatm may provide guidance as to its value; however, this last function is no equal to decent record-keeping at sea. Data may be retrieved with [[,rsk-method or replaced with [[<-,rsk-method.

# Author(s)

Dan Kelley and Clark Richards

#### References

1. RBR website: www.rbr-global.com/products

### See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, sealevel-class, section-class, topo-class, windrose-class

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rskPatm, rskToc, rsk, subset,rsk-method, summary,rsk-method

rsk2ctd 411

rsk2ctd

Create a ctd Object from an rsk Object

### **Description**

A new ctd object is assembled from the contents of the rsk object. The data and metadata are mostly unchanged, with an important exception: the pressure item in the data slot may altered, because rsk instruments measure total pressure, not sea pressure; see "Details".

### Usage

```
rsk2ctd(x, pressureAtmospheric = 0, longitude = NULL, latitude = NULL,
    ship = NULL, cruise = NULL, station = NULL, deploymentType = NULL,
    debug = getOption("oceDebug"))
```

### **Arguments**

x An rsk object, i.e. one inheriting from rsk-class.

pressureAtmospheric

A numerical value (a constant or a vector), that is subtracted from the pressure

in object before storing it in the return value.

latitude numerical value of longitude, in degrees East.

numerical value of latitude, in degrees North.

ship optional string containing the ship from which the observations were made.

cruise optional string containing a cruise identifier.
station optional string containing a station identifier.

deploymentType character string indicating the type of deployment (see as.ctd).

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

### **Details**

The pressureType element of the metadata of rsk objects defines the pressure type, and this controls how pressure is set up in the returned object. If object@metadata\$pressureType is "absolute" (or NULL) then the resultant pressure will be adjusted to make it into "sea" pressure. To do this, the value of object@metadata\$pressureAtmospheric is inspected. If this is present, then it is subtracted from pressure. If this is missing, then standard pressure (10.1325 dbar) will be subtracted. At this stage, the pressure should be near zero at the ocean surface, but some additional adjustment might be necessary, and this may be indicated by setting the argument pressureAtmospheric to a non-zero value to be subtracted from pressure.

412 rskPatm

rskPatm

Estimate Atmospheric Pressure in Rsk Object

## **Description**

Estimate atmospheric pressure in rsk record.

## Usage

```
rskPatm(x, dp = 0.5)
```

# Arguments

x A rsk object, or a list of pressures (in decibars).

dp Half-width of pressure window to be examined (in decibars).

#### **Details**

Pressures must be in decibars for this to work. First, a subset of pressures is created, in which the range is sap-dp to sap+dp. Here, sap=10.1325 dbar is standard sealevel atmospheric pressure. Within this window, three measures of central tendency are calculated: the median, the mean, and a weighted mean that has weight given by  $exp(-2*((p-sap)/dp)^2)$ .

### Value

A list of four estimates: sap, the median, the mean, and the weighted mean.

## Author(s)

Dan Kelley

#### See Also

The documentation for rsk-class explains the structure of rsk objects, and also outlines the other functions dealing with them.

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rsk-class, rskToc, rsk, subset,rsk-method, summary,rsk-method

```
library(oce)
data(rsk)
print(rskPatm(rsk))
```

rskToc 413

rskToc De	ecode table-of-contents File from a Rsk File
-----------	--

### **Description**

Decode table-of-contents file from a rsk file, of the sort used by some researchers at Dalhousie University.

### Usage

```
rskToc(dir, from, to, debug = getOption("oceDebug"))
```

## **Arguments**

dir	name of a directory containing a single table-of-contents file, with .TBL at the end of its file name.
from	optional POSIXct time, indicating the beginning of a data interval of interest. This must have timezone "UTC".
to	optional POSIXct time, indicating the end of a data interval of interest. This must have timezone "UTC".
debug	optional integer to control debugging, with positive values indicating to print information about the processing.

## **Details**

It is assumed that the .TBL file contains lines of the form "File \day179\SL08A179.023 started at Fri Jun 27 22:00 The first step is to parse these lines to get day and hour information, i.e. 179 and 023 in the line above. Then, recognizing that it is common to change the names of such files, the rest of the filename information in the line is ignored, and instead a new file name is constructed based on the data files that are found in the directory. (In other words, the "\day179\SL08A" portion of the line is replaced.) Once the file list is complete, with all times put into R format, then (optionally) the list is trimmed to the time interval indicated by from and to. It is important that from and to be in the UTC time zone, because that time zone is used in decoding the lines in the .TBL file.

#### Value

A list with two elements: filename, a vector of file names, and startTime, a vector of POSIXct times indicating the (real) times of the first datum in the corresponding files.

## Author(s)

Dan Kelley

### See Also

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rsk-class, rskPatm, rsk, subset,rsk-method, summary,rsk-method

414 runlm

### **Examples**

runlm

Calculate running linear models

### **Description**

The linear model is calculated from the slope of a localized least-squares regression model y=y(x). The localization is defined by the x difference from the point in question, with data at distance exceeding L/2 being ignored. With a boxcar window, all data within the local domain are treated equally, while with a hanning window, a raised-cosine weighting function is used; the latter produces smoother derivatives, which can be useful for noisy data. The function is based on internal calculation, not on 1m.

#### **Usage**

```
runlm(x, y, xout, window = c("hanning", "boxcar"), L, deriv)
```

## **Arguments**

x a vector holding x values.y a vector holding y values.

xout optional vector of x values at which the derivative is to be found. If not provided,

x is used.

window type of weighting function used to weight data within the window; see 'Details'.

width of running window, in x units. If not provided, a reasonable default will

be used.

deriv an optional indicator of the desired return value; see 'Examples'.

### Value

If deriv is not specified, a list containing vectors of output values y and y, derivative (dydx), along with the scalar length scale L. If deriv=0, a vector of values is returned, and if deriv=1, a vector of derivatives is returned.

#### Author(s)

Dan Kelley

satellite-class 415

## **Examples**

```
library(oce)
# Case 1: smooth a noisy signal
x <- 1:100
y < -1 + x/100 + \sin(x/5)
yn <- y + rnorm(100, sd=0.1)
L <- 4
calc <- runlm(x, y, L=L)</pre>
plot(x, y, type='l', lwd=7, col='gray')
points(x, yn, pch=20, col='blue')
lines(x, calc$y, lwd=2, col='red')
# Case 2: square of buoyancy frequency
data(ctd)
par(mfrow=c(1,1))
plot(ctd, which="N2")
rho <- swRho(ctd)</pre>
z <- swZ(ctd)
zz \leftarrow seq(min(z), max(z), 0.1)
N2 \leftarrow -9.8 / mean(rho) * runlm(z, rho, zz, deriv=1)
lines(N2, -zz, col='red')
legend("bottomright", lwd=2, bg="white",
       col=c("black", "red"),
       legend=c("swN2()", "using runlm()"))
```

satellite-class

Class to hold satellite data

# Description

This class holds satellite data of various types, including amsr-class and g1sst-class.

## Author(s)

Dan Kelley and Chantelle Layton

## See Also

 $Other things \ related \ to \ satellite \ data: \ g1sst-class, \ plot, satellite-method, \ read. \ g1sst, \ summary, satellite-method \ read. \ g1sst, \ summary, satellite-method \ read. \ g1sst, \ summary, \ satellite-method \ satellite-method$ 

416 sealevel

sealevel

Sealevel data for Halifax Harbour

## **Description**

This sample sea-level dataset is the 2003 record from Halifax Harbour in Nova Scotia, Canada. For reasons that are not mentioned on the data archive website, the record ends on the 8th of October.

## Author(s)

Dan Kelley

#### Source

The data were created as

```
sealevel <-
read.oce("490-01-JAN-2003_slev.csv") sealevel <- oce.edit(sealevel,
"longitude", -sealevel[["longitude"]], reason="Fix longitude hemisphere")</pre>
```

where the csv file was downloaded from [1]. Note the correction of longitude sign, which is required because the data file has no indication that this is the western hemisphere.

### References

1. Fisheries and Oceans Canada http://www.meds-sdmm.dfo-mpo.gc.ca/isdm-gdsi/index-eng.html

#### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, section, topoWorld, wind

Other things related to sealevel data: [[,sealevel-method, [[<-,sealevel-method, as.sealevel, plot,sealevel-method, read.sealevel,sealevel-class,sealevelTuktoyaktuk,subset,sealevel-method,summary,sealevel-method

sealevel-class 417

sealevel-class

Class to Store Sealevel Data

### **Description**

Class to store sealevel data, e.g. from a tide gauge, with standard slots metadata, data and processingLog.

#### Methods

Data may be accessed as e.g. sealevel[["time"]], where the string could also be e.g. "elevation" for the corresponding sea-level elevation, or e.g. "longitude" or "latitude" for scalars. Items in metadata must be specifield by full name, but those in data may be abbreviated, so long as the abbreviation is unique.

Everything that may be accessed may also be assigned, e.g. sealevel[["elevation"]] <- value.

The show method displays information about the object, while summary, sealevel-method provides a statistical summary.

#### Author(s)

Dan Kelley

## See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, section-class, topo-class, windrose-class

Other things related to sealevel data: [[,sealevel-method, [[<-,sealevel-method, as.sealevel, plot,sealevel-method, read.sealevel, sealevelTuktoyaktuk, sealevel, subset,sealevel-method, summary,sealevel-method

sealevelTuktoyaktuk

Sea-level data set acquired in 1975 at Tuktoyaktuk

### **Description**

This sea-level dataset is provided with in Appendix 7.2 of Foreman (1977) and also with the T\_TIDE package (Pawlowicz et al., 2002). It results from measurements made in 1975 at Tuktoyaktuk, Northwest Territories, Canada.

### **Details**

The data set contains 1584 points, some of which have NA for sea-level height.

Although Foreman's Appendix 7.2 states that times are in Mountain standard time, the timezone is set to UTC in the present case, so that the results will be similar to those he provides in his Appendix 7.3.

418 sealevelTuktoyaktuk

#### Historical note

Until Jan 6, 2018, the time in this dataset had been increased by 7 hours. However, this alteration was removed on this date, to make for simpler comparison of amplitude and phase output with the results obtained by Foreman (1977) and Pawlowicz et al. (2002).

#### Source

The data were based on the T\_TIDE dataset, which in turn seems to be based on Appendix 7.2 of Foreman (1977). Minor editing was on file format, and then the sealevelTuktoyaktuk object was created using as.sealevel.

#### References

Foreman, M. G. G., 1977. Manual for tidal heights analysis and prediction. Pacific Marine Science Report 77-10, Institute of Ocean Sciences, Patricia Bay, Sidney, BC, 58pp.

Pawlowicz, Rich, Bob Beardsley, and Steve Lentz, 2002. Classical tidal harmonic analysis including error estimates in MATLAB using T\_TIDE. Computers and Geosciences, 28, 929-937.

#### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevel, section, topoWorld, wind

Other things related to sealevel data: [[,sealevel-method, [[<-,sealevel-method, as.sealevel, plot,sealevel-method, read.sealevel, sealevel-class, sealevel, subset, sealevel-method, summary,sealevel-method

secondsToCtime 419

secondsToCtime

Time interval as colon-separated string

# Description

Convert a time interval to a colon-separated string

## Usage

```
secondsToCtime(sec)
```

## **Arguments**

sec

length of time interval in seconds.

### Value

A string with a colon-separated time interval.

## Author(s)

Dan Kelley

### See Also

See ctimeToSeconds, the inverse of this.

Other things related to time: ctimeToSeconds, julianCenturyAnomaly, julianDay, numberAsHMS, numberAsPOSIXct, unabbreviateYear

```
library(oce)
cat("    10 s = ", secondsToCtime(10), "\n", sep="")
cat("    61 s = ", secondsToCtime(61), "\n", sep="")
cat("86400 s = ", secondsToCtime(86400), "\n", sep="")
```

420 section

section

Hydrographic section

## **Description**

This is line A03 (ExpoCode 90CT40\_1, with nominal sampling date 1993-09-11). The chief scientist was Tereschenkov of SOI, working aboard the Russian ship Multanovsky, undertaking a westward transect from the Mediterranean outflow region across to North America, with a change of heading in the last few dozen stations to run across the nominal Gulf Stream axis. The data flags follow the WHP CTD convention, i.e. 1 for uncalibrated, 2 for an acceptable measurement, 3 for a questionable measurement, 4 for a bad measurement, etc; see https://www.nodc.noaa.gov/woce/woce\_v3/wocedata\_1/whp/exchange/exchange\_format\_desc.htm for further details.

### Usage

```
data(section)
```

#### **Source**

This is based on the WOCE file named a03\_hy1.csv, downloaded from https://cchdo.ucsd.edu/cruise/90CT40\_1, 13 April 2015.

### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, topoWorld, wind

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, subset, section-method, summary, section-method

```
## Not run:
library(oce)
# Gulf Stream
data(section)
GS <- subset(section, 109<=stationId&stationId<=129)
GSg <- sectionGrid(GS, p=seq(0, 5000, 100))
plot(GSg, map.xlim=c(-80,-60))
## End(Not run)</pre>
```

section-class 421

section-class

Class to Store Hydrographic Section Data

### **Description**

Class to store hydrographic section data, with standard slots metadata, data and processingLog.

A list of stations is retrieved by s[["station"]]. Individual stations are retrieved by providing a station number as a second argument in the index, e.g. the first station is s[["station", 1]] (which is a ctd-class object).

Aggregated values of the quantities measured at each level of the CTD profiles contained within the section may be accessed as e.g. section[["salinity"]]. This works for any quantity whose name is present in the constituent profiles.

Since it is often useful to pair such quantities with locations, section[["longitude"]] and section[["latitude"]] return vectors with values repeated for each level in each CTD (see the pairs() call in the example section). If just one latitude or longitude is desired per station, e.g. section[["latitude", "byStation"]] may be used. Station-by-station values of dynamic height are provided by e.g. section[["dynamic height"]].

The depths of all data are obtained from e.g. section[["depth"]], and the distances along the transect, measured from the first station, are obtained from e.g. section[["distance"]].

#### Author(s)

Dan Kelley

#### See Also

Sections can be read with read.section or created with read.section or created from CTD objects by using as.section or by adding a ctd station to an existing section with sectionAddStation.

Sections may be sorted with sectionSort, subsetted with subset, section-method, smoothed with sectionSmooth, and gridded with sectionGrid. Gridded sections may be plotted with plot, section-method.

Statistical summaries are provided by summary, section-method, while overviews are provided by show.

The sample dataset section contains data along WOCE line A03.

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, topo-class, windrose-class

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method

422 sectionAddStation

### **Examples**

```
library(oce)
data(section)
plot(section[['station', 1]])
pairs(cbind(z=-section[["pressure"]],T=section[["temperature"]],S=section[["salinity"]]))
## T profiles for first few stations in section, at common scale
par(mfrow=c(3,3))
Tlim <- range(section[["temperature"]])
ylim <- rev(range(section[["pressure"]]))
for (stn in section[["station", 1:9]])
    plotProfile(stn, xtype='potential temperature', ylim=ylim, Tlim=Tlim)</pre>
```

sectionAddStation

Add a CTD Station to a Section

## **Description**

Add a CTD profile to an existing section.

### Usage

```
sectionAddStation(section, station)
```

## **Arguments**

section A section to which a station is to be added.

station A ctd object holding data for the station to be added.

#### Value

An object of class section.

### Historical note

Until March 2015, this operation was carried out with the + operator, but at that time, the syntax was flagged by the development version of R, so it was changed to the present form.

### Author(s)

Dan Kelley

### See Also

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionGrid, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method

sectionGrid 423

### **Examples**

```
library(oce)
data(ctd)
ctd2 <- ctd
ctd2[["temperature"]] <- ctd2[["temperature"]] + 0.5
ctd2[["latitude"]] <- ctd2[["latitude"]] + 0.1
section <- as.section(c("ctd", "ctd2"))
ctd3 <- ctd
ctd3[["temperature"]] <- ctd[["temperature"]] + 1
ctd3[["latitude"]] <- ctd[["latitude"]] + 0.1
ctd3[["station"]] <- "Stn 3"
sectionAddStation(section, ctd3)</pre>
```

sectionGrid

Grid a Section

## **Description**

Grid a section, by interpolating to fixed pressure levels. The "approx", "boxcar" and "lm" methods are described in the documentation for ctdDecimate, which is used to do this processing. The default "approx" method is best for bottle data, the "boxcar" is best for ctd data, and the "lm" method is probably too slow to recommend for exploratory work, in which it is common to do trials with a variety of "p" values.

## Usage

```
sectionGrid(section, p, method = "approx", debug = getOption("oceDebug"),
...)
```

#### **Arguments**

section

A section object containing the section to be gridded.

р

Optional indication of the pressure levels to which interpolation should be done. If this is not supplied, the pressure levels will be calculated based on the typical spacing in the ctd profiles stored within section. If p="levitus", then pressures will be set to be those of the Levitus atlas, given by standardDepths, trimmed to the maximum pressure in section. If p is a single numerical value, it is taken as the number of subdivisions to use in a call to seq that has range from 0 to the maximum pressure in section. Finally, if a vector numerical values is provided, then it is used as is.

method

The method to use to decimate data within the stations; see ctdDecimate, which is used for the decimation.

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces

424 sectionSmooth

the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

Optional arguments to be supplied to ctdDecimate, e.g. rule controls extrapolation beyond the observed pressure range, in the case where method equals "approx".

### Value

An object of section-class that contains stations whose pressure values match identically.

## A note about flags

Data-quality flags contained within the original object are ignored by this function, and the returned value contains no such flags. This is because such flags represent an assessment of the original data, not of quantities derived from those data. This function produces a warning to this effect. The recommended practice is to use handleFlags or some other means to deal with flags before calling the present function.

## Author(s)

Dan Kelley

#### See Also

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionAddStation, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method

## **Examples**

```
# Gulf Stream
library(oce)
data(section)
GS <- subset(section, 109<=stationId&stationId<=129)
GSg <- sectionGrid(GS, p=seq(0, 5000, 100))
plot(GSg, map.xlim=c(-80,-60))</pre>
```

sectionSmooth

Smooth a Section

### **Description**

Smooth a section in the lateral (alpha version that may change).

```
sectionSmooth(section, method = c("spline", "barnes"), xg, yg, xgl, ygl, xr,
  yr, gamma = 0.5, iterations = 2, trim = 0, pregrid = FALSE,
  debug = getOption("oceDebug"), ...)
```

sectionSmooth 425

## **Arguments**

section	A section object containing the section to be smoothed. For method="spline", the pressure levels must match for each station in the section.
method	Specifies the method to use; see 'Details'.
xg, xgl	passed to interpBarnes, if method="barnes"; ignored otherwise. If xg is supplied, it defines the x component of the grid, i.e. the resultant "stations". Alternatively, if xgl is supplied, the x grid is established using seq, to span the data with xgl elements. If neither of these is supplied, the output x grid will equal the input x grid.
yg, ygl	similar to xg and xg1.
xr, yr	influence ranges in x and y, passed to interpBarnes if method="barnes"; ignored otherwise.
gamma	scale-reduction parameter, passed to interpBarnes, if method="barnes"; ignored otherwise.
iterations	$number\ of\ iterations\ of\ Barnes\ algorithm,\ passed\ to\ \verb"interpBarnes";\ ignored\ otherwise.$
trim	passed to interpBarnes, if method="barnes"; ignored otherwise
pregrid	passed to interpBarnes, if method="barnes"; ignored otherwise
debug	A flag that turns on debugging. Set to 1 to get a moderate amount of debugging information, or to 2 to get more.
	Optional extra arguments, passed to either smooth.spline or interpBarnes.

## **Details**

This function should be used with caution, as should any operation that changes data. Although smoothing may be desirable to produce aesthetically-pleasing plots, it can also introduce artifacts that can lead to erroneous conclusions. The prudent analyst starts by comparing plots of the raw data with plots of the smoothed data.

For method="spline", the section is smoothed using smooth.spline on individual pressure levels, with any parameters listed in parameters being passed to that function. If df is not present in parameters, then this function sets it to the number of stations divided by 5. Smoothing is done separately for temperature, salinity, and sigma-theta.

For the (much slower) method="barnes" method, smoothing is done across both horizontal and vertical coordinates, using interpBarnes. The stations are changed to lie on the grid supplied defined xg and yg, or by xgl and ygl (see those arguments)

#### Value

An object of section-class that ordered in some way.

## Author(s)

Dan Kelley

426 sectionSort

## See Also

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSort, section, subset, section-method, summary, section-method

### **Examples**

```
library(oce)
data(section)
gs <- subset(section, 109<=stationId&stationId<=129)
gsg <- sectionGrid(gs, p=seq(0, 5000, 150))
gss1 <- sectionSmooth(gsg, "spline", df=16)
plot(gss1)
## Not run:
gss2 <- sectionSmooth(gsg, "barnes", xr=24, yr=100)
plot(gss2)
## End(Not run)</pre>
```

sectionSort

Sort a Section

### **Description**

Sections created with as.section have "stations" that are in the order of the CTD objects (or filenames for such objects) provided. Sometimes, this is not the desired order, e.g. if file names discovered with dir are in an order that makes no sense. (For example, a practioner might name stations "stn1", "stn2", etc., not realizing that this will yield an unhelpful ordering, by file name, if there are more than 9 stations.) The purpose of sectionSort is to permit reordering the constituent stations in sensible ways.

#### Usage

```
sectionSort(section, by)
```

### **Arguments**

section A section object containing the section whose stations are to be sorted.

by An optional string indicating how to reorder. If not provided, "stationID" will

be assumed. Other choices are "distance", for distance from the first station, "longitude", for longitude, "latitude" for latitude, and "time", for time.

## Value

An object of section-class that has less lateral variation than the input section.

shiftLongitude 427

### Author(s)

Dan Kelley

#### See Also

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags,section-method,plot,section-method,read.section,section-class,sectionAddStation,sectionGrid,sectionSmooth,section,subset,section-method,summary,section-method

## **Examples**

```
## Not run:
# Eastern North Atlantic, showing Mediterranean water;
# sorting by longitude makes it easier to compare
# the map and the section.
library(oce)
data(section)
s <- sectionGrid(subset(section, -30 <= longitude))
ss <- sectionSort(ss, by="longitude")
plot(ss)
## End(Not run)</pre>
```

shiftLongitude

Shift Longitude to Range -180 to 180

## **Description**

This is a utility function used by mapGrid. It works simply by subtracting 180 from each longitude, if any longitude in the vector exceeds 180.

## Usage

```
shiftLongitude(longitudes)
```

## Arguments

longitudes a numerical vector of longitudes

## Value

vector of longitudes, shifted to the desired range.

428 showMetadataItem

### See Also

matrixShiftLongitude and standardizeLongitude.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, usrLonLat, utm2lonlat

showMetadataItem

Show metadata item

## **Description**

This is a helper function for various summary functions.

### Usage

```
showMetadataItem(object, name, label = "", postlabel = "", isdate = FALSE,
quote = FALSE)
```

## Arguments

object an object inheriting from the base oce class.

name name of item

label label to print before item postlabel label to print after item

isdate boolean indicating whether the item is a time

quote boolean indicating whether to enclose the item in quotes

## Author(s)

Dan Kelley

```
library(oce)
data(ctd)
showMetadataItem(ctd, "ship", "ship")
```

siderealTime 429

siderealTime

Convert a POSIXt time to a sidereal time

# Description

Convert a POSIXt time to a sidereal time, using the method in Chapter 7 of Meeus (1982). The small correction that he discusses after his equation 7.1 is not applied here.

## Usage

```
siderealTime(t)
```

## **Arguments**

t

a time, in POSIXt format, e.g. as created by as.POSIXct, as.POSIXlt, or numberAsPOSIXct. If this is provided, the other arguments are ignored.

### Value

A sidereal time, in hours in the range from 0 to 24.

### Author(s)

Dan Kelley

### References

Meeus, Jean, 1982. Astronomical formuae for Calculators. Willmann-Bell. Richmond VA, USA. 201 pages

## See Also

Other things related to astronomy: eclipticalToEquatorial, equatorialToLocalHorizontal, julianCenturyAnomaly, julianDay, moonAngle, sunAngle

```
t <- ISOdatetime(1978, 11, 13, 0, 0, 0, tz="UTC") print(siderealTime(t))
```

430 standardize Longitude

standardDepths

Standard Oceanographic Depths

# Description

This returns so-called standard depths 0m, 10m, etc. below the sea surface.

# Usage

```
standardDepths()
```

### Value

```
A vector of depths, c(0, 10, ...).
```

## Author(s)

Dan Kelley

standardizeLongitude Put longitude in the range from -180 to 180

# **Description**

Put longitude in the range from -180 to 180

# Usage

```
standardizeLongitude(longitude)
```

# Arguments

longitude

in degrees East, possibly exceeding 180

## Value

longitude in signed degrees East

## See Also

 $\verb|matrixShiftLongitude| and \verb|shiftLongitude| are more powerful relatives to \verb|standardizeLongitude|.$ 

subset,adp-method 431

subset, adp-method

Subset an ADP Object

### **Description**

Subset an adp (acoustic Doppler profile) object, in a manner that is function is somewhat analogous to subset.data.frame. Subsetting can be by time or distance, but these may not be combined; use a sequence of calls to subset by both.

### Usage

```
## S4 method for signature 'adp'
subset(x, subset, ...)
```

## **Arguments**

```
x An adp object, i.e. one inheriting from adp-class.subset A condition to be applied to the data portion of x. See 'Details'.... Ignored.
```

#### Value

A new adp-class object.

#### Author(s)

Dan Kelley

### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

Other functions that subset oce objects: subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

```
library(oce)
data(adp)
# First part of time series
plot(subset(adp, time < mean(range(adp[['time']]))))</pre>
```

432 subset,adv-method

subset,adv-method

Subset an ADV Object

### **Description**

Subset an adv (acoustic Doppler profile) object. This function is somewhat analogous to subset.data.frame, except that subsets can only be specified in terms of time.

### Usage

```
## S4 method for signature 'adv'
subset(x, subset, ...)
```

# Arguments

```
x An adv object, i.e. one inheriting from adv-class.
subset a condition to be applied to the data portion of x. See 'Details'.
... ignored.
```

#### Value

A new adv-class object.

## Author(s)

Dan Kelley

## See Also

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

Other functions that subset oce objects: subset, adp-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

```
library(oce)
data(adv)
plot(adv)
plot(subset(adv, time < mean(range(adv[['time']]))))</pre>
```

subset,amsr-method 433

subset,amsr-method

Subset an amsr Object

### **Description**

This function is somewhat analogous to subset.data.frame, but only one independent variable may be used in subset in any call to the function, which means that repeated calls will be necessary to subset based on more than one independent variable (e.g. latitude and longitude).

### Usage

```
## S4 method for signature 'amsr'
subset(x, subset, ...)
```

### **Arguments**

```
x A amsr object, i.e. one inheriting from amsr-class.subset An expression indicating how to subset x.... Ignored.
```

#### Value

An amsr object.

### Author(s)

Dan Kelley

### See Also

```
Other things related to amsr data: [[<-,amsr-method, amsr-class, composite,amsr-method, download.amsr,plot,amsr-method,read.amsr,summary,amsr-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

## **Examples**

```
## Not run:
library(oce)
earth <- read.amsr("f34_20160102v7.2.gz") # not provided with oce
fclat <- subset(earth , 45<=latitude & latitude <= 49)
fc <- subset(fclat , longitude <= -47 & longitude <= -43)
plot(fc)
## End(Not run)</pre>
```

434 subset,argo-method

subset, argo-method

Subset an Argo Object

### **Description**

Subset an argo object, either by selecting just the "adjusted" data or by subsetting by pressure or other variables.

# Usage

```
## S4 method for signature 'argo'
subset(x, subset, ...)
```

### **Arguments**

x An object inheriting from argo-class.subset An expression indicating how to subset x.... Ignored.

#### **Details**

If subset is the string "adjusted", then subset replaces the station variables with their adjusted counterparts. In the argo notation, e.g. PSAL is replaced with PSAL\_ADJUSTED; in the present notation, this means that salinity in the data slot is replaced with salinityAdjusted, and the latter is deleted. Similar replacements are also done with the flags stored in the metadata slot.

If subset is an expression, then the action is somewhat similar to other subset functions, but with the restriction that only one independent variable may be used in in any call to the function, so that repeated calls will be necessary to subset based on more than one independent variable. Subsetting may be done by anything stored in the data, e.g. time, latitude, longitude, profile, dataMode, or pressure or by profile (a made-up variable) or id (from the metadata slot).

#### Value

An argo object.

### Author(s)

Dan Kelley

#### See Also

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, as.argo, handleFlags, argo-method, plot, argo-method, read.argo, summary, argo-method

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

subset,cm-method 435

### **Examples**

```
library(oce)
data(argo)

# Example 1: buset by time, longitude, and pressure
par(mfrow=c(2,2))
plot(argo)
plot(subset(argo, time > mean(time)))
plot(subset(argo, longitude > mean(longitude)))
plot(subset(argoGrid(argo), pressure > 500 & pressure < 1000), which=5)

# Example 2: restrict attention to delayed-mode profiles.
par(mfrow=c(1, 1))
plot(subset(argo, dataMode == "D"))

# Example 3: contrast corrected and uncorrected data
par(mfrow=c(1,2))
plotTS(argo)
plotTS(subset(argo, "adjusted"))</pre>
```

subset,cm-method

Subset a CM Object

## **Description**

This function is somewhat analogous to subset.data.frame.

## Usage

```
## S4 method for signature 'cm'
subset(x, subset, ...)
```

## Arguments

```
x a cm object, i.e. inheriting from cm-class.subset a condition to be applied to the data portion of x. See 'Details'.ignored.
```

#### Value

A new cm object.

## Author(s)

436 subset, coastline-method

### See Also

```
Other things related to cm data: [[,cm-method, [[<-,cm-method, as.cm, cm-class, cm, plot, cm-method, read.cm, summary, cm-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

### **Examples**

```
library(oce)
data(cm)
plot(cm)
plot(subset(cm, time < mean(range(cm[['time']]))))</pre>
```

```
subset, coastline-method
```

Subset a Coastline Object

## **Description**

Summarizes coastline length, bounding box, etc.

## Usage

```
## S4 method for signature 'coastline'
subset(x, subset, ...)
```

# Arguments

```
x A coastline object, i.e. one inheriting from coastline-class.subset An expression indicating how to subset x.... Ignored.
```

#### Value

A coastline object.

## Author(s)

subset,ctd-method 437

#### See Also

Other things related to coastline data: [[,coastline-method,[[<-,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, summary, coastline-method

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

subset, ctd-method

Subset a CTD Object

### Description

Return a subset of a section object.

#### Usage

```
## S4 method for signature 'ctd'
subset(x, subset, ...)
```

#### **Arguments**

x A ctd object, i.e. one inheriting from ctd-class.

subset An expression indicating how to subset x.

... optional arguments, of which only the first is examined. The only possibility is

that this argument be named indices. See "Details".

#### **Details**

This function is used to subset data within the levels of a ctd object. There are two ways of working. If subset is supplied, then it is a logical expression that is evaluated within the environment of the data slot of the object (see Example 1). Alternatively, if the . . . list contains an expression defining indices, then that expression is used to subset each item within the data slot (see Example 2).

#### Value

A ctd-class object.

## Author(s)

### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, summary,ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

### **Examples**

```
library(oce)
data(ctd)
plot(ctd)
## Example 1
plot(subset(ctd, pressure<10))
## Example 2
plot(subset(ctd, indices=1:10))</pre>
```

subset, echosounder-method

Subset an Echosounder Object

## **Description**

This function is somewhat analogous to subset.data.frame. Subsetting can be by time or depth, but these may not be combined; use a sequence of calls to subset by both.

### Usage

```
## S4 method for signature 'echosounder'
subset(x, subset, ...)
```

#### **Arguments**

```
x a echosounder object.subset a condition to be applied to the data portion of x. See 'Details'.ignored.
```

## Value

A new echosounder object.

subset,lobo-method 439

### Author(s)

Dan Kelley

#### See Also

```
Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, as.echosounder, echosounder-class, echosounder, findBottom, plot, echosounder-method, read.echosounder, summary, echosounder-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

## **Examples**

```
library(oce)
data(echosounder)
plot(echosounder)
plot(subset(echosounder, depth < 10))
plot(subset(echosounder, time < mean(range(echosounder[['time']]))))</pre>
```

subset, lobo-method

Subset a LOBO Object

# Description

Subset an lobo object, in a way that is somewhat analogous to subset.data.frame.

### Usage

```
## S4 method for signature 'lobo'
subset(x, subset, ...)
```

# Arguments

```
x a lobo object.subset a condition to be applied to the data portion of x. See 'Details'.ignored.
```

#### Value

A new lobo object.

### Author(s)

subset,met-method

#### See Also

```
Other things related to lobo data: [[,lobo-method, [[<-,lobo-method, as.lobo, lobo-class, lobo, plot,lobo-method, summary,lobo-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

subset, met-method

Subset a met Object

### Description

This function is somewhat analogous to subset.data.frame.

### Usage

```
## S4 method for signature 'met'
subset(x, subset, ...)
```

# **Arguments**

x An object inheriting from met-class.subset An expression indicating how to subset x.ignored.

### Value

A new met object.

#### Author(s)

Dan Kelley

### See Also

```
Other things related to met data: [[,met-method, [[<-,met-method, as.met, download.met, met-class, met, plot,met-method, read.met, summary,met-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

subset,oce-method 441

### **Examples**

```
library(oce)
data(met)
# Few days surrounding Hurricane Juan
plot(subset(met, time > as.POSIXct("2003-09-27", tz="UTC")))
```

subset, oce-method

Subset an oce Object

### **Description**

This is a basic class for general oce objects. It has specialised versions for most sub-classes, e.g. subset, ctd-method for ctd objects.

#### Usage

```
## S4 method for signature 'oce'
subset(x, subset, ...)
```

# Arguments

x an oce object.

subset a logical expression indicating how to take the subset; the form depends on the

sub-class.

... optional arguments, used in some specialized methods (e.g. subset, section-method).

### Value

An oce object.

#### See Also

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

### **Examples**

```
library(oce)
data(ctd)
# Select just the top 10 metres (pressure less than 10 dbar)
top10 <- subset(ctd, pressure < 10)
par(mfrow=c(1, 2))
plotProfile(ctd)
plotProfile(top10)</pre>
```

442 subset,rsk-method

subset, odf-method

Subset an ODF object

## **Description**

This function is somewhat analogous to subset.data.frame.

### Usage

```
## S4 method for signature 'odf'
subset(x, subset, ...)
```

### **Arguments**

x an odf object.

subset a condition to be applied to the data portion of x. See 'Details'.

... ignored.

### Value

A new odf object.

## Author(s)

Dan Kelley

## See Also

```
Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, [[<-,odf-method, odf-class, plot,odf-method, read.ctd.odf, read.odf, summary,odf-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, method, subset, oce-method, subset, rsk-method, subset, sealevel-method, subset, section-method, subset, topo-method

subset,rsk-method

Subset a Rsk Object

## **Description**

Subset a rsk object. This function is somewhat analogous to subset.data.frame, but subsetting is only permitted by time.

subset, sealevel-method 443

### Usage

```
## S4 method for signature 'rsk'
subset(x, subset, ...)
```

### **Arguments**

```
x a rsk object, i.e. inheriting from rsk-class.subset a condition to be applied to the data portion of x. See 'Details'.ignored.
```

### Value

A new rsk object.

### Author(s)

Dan Kelley

### See Also

```
Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rsk-class, rskPatm, rskToc, rsk, summary,rsk-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, sealevel-method, subset, section-method, subset, topo-method

# **Examples**

```
library(oce)
data(rsk)
plot(rsk)
plot(subset(rsk, time < mean(range(rsk[['time']]))))</pre>
```

```
subset, sealevel-method
```

Subset a Sealevel Object

## **Description**

This function is somewhat analogous to subset.data.frame, but subsetting is only permitted by time.

#### Usage

```
## S4 method for signature 'sealevel'
subset(x, subset, ...)
```

444 subset, section-method

#### **Arguments**

x A sealevel object, i.e. one inheriting from sealevel-class.subset a condition to be applied to the data portion of x.... ignored.

### Value

A new sealevel object.

### Author(s)

Dan Kelley

### See Also

```
Other things related to sealevel data: [[, sealevel-method, [[<-, sealevel-method, as.sealevel, plot, sealevel-method, read.sealevel, sealevel-class, sealevelTuktoyaktuk, sealevel, summary, sealevel-method
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, section-method, subset, topo-method

## **Examples**

```
library(oce)
data(sealevel)
plot(sealevel)
plot(subset(sealevel, time < mean(range(sealevel[['time']]))))</pre>
```

subset, section-method Subset a Section Object

### **Description**

Return a subset of a section object.

## Usage

```
## S4 method for signature 'section'
subset(x, subset, ...)
```

subset, section-method 445

### **Arguments**

x A section object, i.e. one inheriting from section-class.

subset an optional indication of either the stations to be kept, or the data to be kept

within the stations. See "Details".

.. optional arguments, of which only the first is examined. The only possibility is

that this argument be named indices. See "Details".

#### **Details**

This function is used to subset data within the stations of a section, or to choose a subset of the stations themselves. The first case is handled with the subset argument, while the second is handled if ... contains a vector named indices. Either subset or indices must be provided, but not both.

In the "subset" method, subset indicates either stations to be kept, or data to be kept within the stations.

The first step in processing is to check for the presence of certain key words in the subset expression. If distance is present, then stations are selected according to a condition on the distance (in km) from the first station to the given station (Example 1). If either longitude or latitude is given, then stations are selected according to the stated condition (Example 2). If stationId is present, then selection is in terms of the station ID (not the sequence number) is used (Example 3). In all of these cases, stations are either selected in their entirety or dropped in their entirety.

If none of these keywords is present, then the subset expression is evaluated in the context of the data slot of each of the CTD stations stored within x. (Note that this slot does not normally contain any of the keywords that are listed in the previous paragraph; it does, then odd results may occur.) Each station is examined in turn, with subset being evaluated individually in each. The evaluation produces a logical vector. If that vector has length 1 (Examples 4 and 5) then the station is retained or discarded, accordingly. If the vector is longer, then the logical vector is used as a sieve to subsample that individual CTD profile.

In the "indices" method, stations are selected using indices, which may be a vector of integers that indicate sequence number, or a logical vector, again indicating which stations to keep.

## Value

A section-class object.

#### Author(s)

Dan Kelley

#### See Also

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, topo-method

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, summary, section-method

446 subset,topo-method

### **Examples**

```
library(oce)
data(section)
# 1. Stations within 500 km of the first station
starting <- subset(section, distance < 500)</pre>
# 2. Stations east of 50W
east <- subset(section, longitude > (-50))
# 3. Gulf Stream
GS <- subset(section, 109 <= stationId & stationId <= 129)
# 4. Only stations with more than 5 pressure levels
long <- subset(section, length(pressure) > 5)
# 5. Only stations that have some data in top 50 dbar
surfacing <- subset(section, min(pressure) < 50)</pre>
# 6. Similar to #4, but done in more detailed way
long <- subset(section,</pre>
   indices=unlist(lapply(section[["station"]],
                   function(s)
                     5 < length(s[["pressure"]]))))</pre>
```

subset,topo-method

Subset a Topo Object

### **Description**

This function is somewhat analogous to subset.data.frame. Subsetting can be by time or distance, but these may not be combined; use a sequence of calls to subset by both.

# Usage

```
## S4 method for signature 'topo'
subset(x, subset, ...)
```

### **Arguments**

```
x A topo object, i.e. inheriting from topo-class.
subset A condition to be applied to the data portion of x. See 'Details'.
... Ignored.
```

#### Value

A new topo-class object.

#### Author(s)

Dan Kelley

#### See Also

```
Other things related to topo data: [[,topo-method,[[<-,topo-method,as.topo,download.topo,
plot, topo-method, read.topo, summary, topo-method, topo-class, topoInterpolate, topoWorld
```

Other functions that subset oce objects: subset, adp-method, subset, adv-method, subset, amsr-method, subset, argo-method, subset, cm-method, subset, coastline-method, subset, ctd-method, subset, echosounder-method, subset, ctd-method, subset, echosounder-method, subset, ctd-method, subset, echosounder-method, subset, ctd-method, subset, echosounder-method, subset, lobo-method, subset, met-method, subset, oce-method, subset, odf-method, subset, rsk-method, subset, sealevel-method, subset, section-method

# **Examples**

```
## northern hemisphere
library(oce)
data(topoWorld)
plot(subset(topoWorld, latitude > 0))
```

subtractBottomVelocity

Subtract Bottom Velocity from ADP

# Description

Subtracts bottom tracking velocities from an "adp" object. Works for all coordinate systems (beam, xyz, and enu).

### Usage

```
subtractBottomVelocity(x, debug = getOption("oceDebug"))
```

# **Arguments** х

an object of class "adp", which contains bottom tracking velocities.

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

#### Author(s)

Dan Kelley and Clark Richards

448 summary,adp-method

### See Also

See read.adp for notes on functions relating to "adp" objects, and adp-class for notes on the ADP object class.

summary, adp-method

Summarize an ADP Object

## **Description**

Summarize data in an adp object.

### Usage

```
## S4 method for signature 'adp'
summary(object, ...)
```

### Arguments

object an object of class "adp", usually, a result of a call to read.oce, read.adp.rdi,

or read.adp.nortek.

... further arguments passed to or from other methods.

#### **Details**

Pertinent summary information is presented.

### Value

A matrix containing statistics of the elements of the data slot.

### Author(s)

Dan Kelley

### See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp, subset,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

summary,adv-method 449

summary,adv-method

Summarize an ADV object

### **Description**

Summarize data in an adv object.

## Usage

```
## S4 method for signature 'adv'
summary(object, ...)
```

### **Arguments**

```
object an object of class "adv", usually, a result of a call to read.adv.
... further arguments passed to or from other methods.
```

# Author(s)

Dan Kelley

#### See Also

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot,adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset,adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

## **Examples**

```
library(oce)
data(adv)
summary(adv)
```

summary,amsr-method

Summarize an AMSR Object

# Description

Although the data are stored in raw form, the summary presents results in physical units.

# Usage

```
## S4 method for signature 'amsr'
summary(object, ...)
```

450 summary,argo-method

### **Arguments**

```
object The object to be summarized.
... Ignored.
```

#### Author(s)

Dan Kelley

#### See Also

Other things related to amsr data: [[<-,amsr-method, amsr-class, composite,amsr-method, download.amsr,plot,amsr-method,read.amsr,subset,amsr-method

summary,argo-method

Summarize an Argo Object

### **Description**

Summarizes some of the data in an argo object.

### Usage

```
## S4 method for signature 'argo'
summary(object, ...)
```

### Arguments

... Further arguments passed to or from other methods.

object anobject of class "argo", usually, a result of a call to read.argo.

### **Details**

Pertinent summary information is presented.

#### Value

A matrix containing statistics of the elements of the data slot.

### Author(s)

Dan Kelley

### See Also

Other things related to argo data: [[,argo-method, [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, as.argo, handleFlags, argo-method, plot, argo-method, read.argo, subset,argo-method

### **Examples**

```
library(oce)
data(argo)
summary(argo)
```

summary, bremen-method Summarize a Bremen Object

## **Description**

Pertinent summary information is presented, including the station name, sampling location, data ranges, etc.

# Usage

```
## S4 method for signature 'bremen'
summary(object, ...)
```

## Arguments

object A bremen object, i.e. one inheriting from bremen-class. call to read.bremen.
... Further arguments passed to or from other methods.

#### Author(s)

Dan Kelley

### See Also

Other things related to bremen data: [[,bremen-method, [[<-,bremen-method, bremen-class, plot,bremen-method, read.bremen

summary, cm-method

Summarize a CM Object

## **Description**

Summarizes some of the data in a cm object, presenting such information as the station name, sampling location, data ranges, etc.

# Usage

```
## S4 method for signature 'cm'
summary(object, ...)
```

### **Arguments**

object A cm object, i.e. one inheriting from cm-class.
... Further arguments passed to or from other methods.

#### Author(s)

Dan Kelley

#### See Also

The documentation for cm-class explains the structure of cm objects, and also outlines the other functions dealing with them.

Other things related to cm data: [[,cm-method, [[<-,cm-method, as.cm, cm-class, cm, plot, cm-method, read.cm, subset, cm-method

summary, coastline-method

Summarize a Coastline Object

# Description

Summarizes coastline length, bounding box, etc.

### Usage

```
## S4 method for signature 'coastline'
summary(object, ...)
```

# Arguments

object an object of class "coastline", usually, a result of a call to read.coastline

or read.oce.

... further arguments passed to or from other methods.

### Author(s)

Dan Kelley

#### See Also

Other things related to coastline data: [[,coastline-method, [[<-,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method

summary,ctd-method 453

summary,ctd-method

Summarize a CTD Object

### **Description**

Summarizes some of the data in a ctd object, presenting such information as the station name, sampling location, data ranges, etc. If the object was read from a .cnv file or a .rsk file, then the OriginalName column for the data summary will contain the original names of data within the source file.

## Usage

```
## S4 method for signature 'ctd'
summary(object, ...)
```

## **Arguments**

object A ctd object, i.e. one inheriting from ctd-class.

... Further arguments passed to or from other methods.

### Author(s)

Dan Kelley

### See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

## **Examples**

```
library(oce)
data(ctd)
summary(ctd)
```

454 summary,gps-method

```
summary, echosounder-method
```

Summarize an Echosounder Object

### **Description**

Summarizes some of the data in an echosounder object.

## Usage

```
## S4 method for signature 'echosounder'
summary(object, ...)
```

### **Arguments**

object an object of class "echosounder", usually, a result of a call to read. echosounder,

read.oce, or as.echosounder.

. . . further arguments passed to or from other methods.

### Author(s)

Dan Kelley

### See Also

Other things related to echosounder data: [[,echosounder-method, [[<-,echosounder-method, as.echosounder, echosounder-class, echosounder, findBottom, plot, echosounder-method, read.echosounder, subset, echosounder-method

summary, gps-method

Summarize a GPS Object

### **Description**

Summarize a gps object, i.e. one inheriting from gps-class.

# Usage

```
## S4 method for signature 'gps'
summary(object, ...)
```

### **Arguments**

object an object of class "gps"

... further arguments passed to or from other methods.

summary,ladp-method 455

### Author(s)

Dan Kelley

## See Also

Other things related to gps data: [[,gps-method,[[<-,gps-method,as.gps,gps-class,plot,gps-method,read.gps]]

summary,ladp-method

Summarize an ladp object

# Description

Pertinent summary information is presented, including the station name, sampling location, data ranges, etc.

# Usage

```
## S4 method for signature 'ladp'
summary(object, ...)
```

## Arguments

object An object of class "ladp", usually, a result of a call to as.ladp.

... Further arguments passed to or from other methods.

## Value

A matrix containing statistics of the elements of the data slot.

### Author(s)

Dan Kelley

# See Also

Other things related to ladp data: [[,ladp-method, as.ladp, ladp-class, plot,ladp-method

456 summary, lisst-method

```
summary,landsat-method
```

Summarize a landsat Object

## **Description**

Provides a summary of a some information about an object of landsat-class.

## Usage

```
## S4 method for signature 'landsat'
summary(object, ...)
```

## Arguments

```
object An object of landsat-class, usually a result of a call to read.landsat.
... Ignored.
```

#### Author(s)

Dan Kelley

### See Also

Other things related to landsat data: [[,landsat-method,landsat-class,landsatAdd,landsatTrim,landsat,plot,landsat-method,read.landsat

```
summary,lisst-method Summarize a LISST Object
```

## **Description**

Summarizes some of the data in a lisst object, presenting such information as the station name, sampling location, data ranges, etc.

## Usage

```
## S4 method for signature 'lisst'
summary(object, ...)
```

## **Arguments**

```
object An object of class lisst, usually, a result of a call to read.lisst or as.lisst.
... Ignored.
```

summary,lobo-method 457

### Author(s)

Dan Kelley

### See Also

```
Other things related to lisst data: [[,lisst-method, [[<-,lisst-method, as.lisst, lisst-class, plot,lisst-method, read.lisst
```

# **Examples**

```
library(oce)
data(lisst)
summary(lisst)
```

summary, lobo-method

Summarize a LOBO Object

# Description

Pertinent summary information is presented, including the sampling interval, data ranges, etc.

# Usage

```
## S4 method for signature 'lobo'
summary(object, ...)
```

### Arguments

```
object an object of class "lobo", usually, a result of a call to read.lobo or read.oce.
... further arguments passed to or from other methods.
```

### Value

A matrix containing statistics of the elements of the data slot.

# Author(s)

Dan Kelley

### References

```
http://lobo.satlantic.com http://www.mbari.org/lobo/
```

458 summary,met-method

### See Also

The documentation for lobo-class explains the structure of LOBO objects, and also outlines the other functions dealing with them.

Other things related to lobo data: [[,lobo-method, [[<-,lobo-method, as.lobo, lobo-class, lobo, plot,lobo-method, subset,lobo-method

### **Examples**

```
library(oce)
data(lobo)
summary(lobo)
```

summary,met-method

Summarize a met Object

## **Description**

Pertinent summary information is presented, including the sampling location, data ranges, etc.

# Usage

```
## S4 method for signature 'met'
summary(object, ...)
```

# **Arguments**

```
object A met object, i.e. one inheriting from met-class.
... further arguments passed to or from other methods.
```

# Author(s)

Dan Kelley

### See Also

```
Other things related to met data: [[,met-method, [[<-,met-method, as.met, download.met, met-class, met, plot,met-method, read.met, subset,met-method
```

summary,oce-method 459

summary, oce-method

Summarize an oce Object

### **Description**

Provide a textual summary of some pertinent aspects of the object, including selected components of its metadata slot, statistical and dimensional information on the entries in the data slot, and a listing of the contents of its processingLog slot. The details depend on the class of the object, especially for the metadata slot, so it can help to consult the specialized documentation, e.g. summary,ctd-method for CTD objects (i.e. objects inheriting from ctd-class.) It is important to note that this is not a good way to learn the details of the object contents. Instead, for an object named object, say, one might use str(object) to learn about all the contents, or str(object[["metadata"]]) to learn about the metadata, etc.

### Usage

```
## S4 method for signature 'oce'
summary(object, ...)
```

### **Arguments**

object The object to be summarized.
... Extra arguments (ignored)

### **Examples**

```
o <- new("oce")
summary(o)</pre>
```

summary, odf-method

Summarize an ODF Object

### **Description**

Pertinent summary information is presented, including the station name, sampling location, data ranges, etc.

### Usage

```
## S4 method for signature 'odf'
summary(object, ...)
```

### **Arguments**

```
object an object of class "odf", usually, a result of a call to read.odf or read.oce.
... further arguments passed to or from other methods.
```

460 summary,rsk-method

### Value

A matrix containing statistics of the elements of the data slot.

#### Author(s)

Dan Kelley

#### See Also

Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, [[<-,odf-method, odf-class, plot,odf-method, read.ctd.odf, read.odf, subset,odf-method

summary, rsk-method

Summarize a Rsk Object

## **Description**

Summarizes some of the data in a rsk object, presenting such information as the station name, sampling location, data ranges, etc.

# Usage

```
## S4 method for signature 'rsk'
summary(object, ...)
```

### **Arguments**

object An object of class "rsk", usually, a result of a call to read.rsk, read.oce, or as.rsk.

... Further arguments passed to or from other methods.

# Author(s)

Dan Kelley

## See Also

The documentation for rsk-class explains the structure of CTD objects, and also outlines the other functions dealing with them.

Other things related to rsk data: [[,rsk-method, [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rsk-class, rskPatm, rskToc, rsk, subset,rsk-method

### **Examples**

```
library(oce)
data(rsk)
summary(rsk)
```

```
summary, satellite-method
```

Summarize a satellite object

## **Description**

Summarize a satellite object

# Usage

```
## S4 method for signature 'satellite'
summary(object, ...)
```

## **Arguments**

object The object to be summarized.
... Ignored.

# Author(s)

Dan Kelley

## See Also

Other things related to satellite data: g1sst-class, plot, satellite-method, read.g1sst, satellite-class

```
summary, sealevel-method
```

Summarize a Sealevel Object

# Description

Summarizes some of the data in a sealevel object.

# Usage

```
## S4 method for signature 'sealevel'
summary(object, ...)
```

# Arguments

object A sealevel object, i.e. one inheriting from sealevel-class.

... further arguments passed to or from other methods.

## Value

A matrix containing statistics of the elements of the data slot.

### Author(s)

Dan Kelley

### See Also

Other things related to sealevel data: [[, sealevel-method, [[<-, sealevel-method, as.sealevel, plot, sealevel-method, read.sealevel, sealevel-class, sealevelTuktoyaktuk, sealevel, subset, sealevel-method

## **Examples**

```
library(oce)
data(sealevel)
summary(sealevel)
```

```
summary, section-method
```

Summarize a Section Object

## **Description**

Pertinent summary information is presented, including station locations, distance along track, etc.

### Usage

```
## S4 method for signature 'section'
summary(object, ...)
```

# Arguments

object An object of class "section", usually, a result of a call to read.section, read.oce, or as.section.

... Further arguments passed to or from other methods.

## Value

NULL

## Author(s)

### See Also

Other things related to section data: [[,section-method, [[<-,section-method, as.section, handleFlags,section-method,plot,section-method,read.section,section-class,sectionAddStation,sectionGrid,sectionSmooth,sectionSort,section,subset,section-method

## **Examples**

```
library(oce)
data(section)
summary(section)
```

summary, tidem-method Summarize a Tidem Object

## Description

By default, all fitted constituents are plotted, but it is quite useful to set e.g. p=0.05 To see just those constituents that are significant at the 5 percent level. Note that the p values are estimated as the average of the p values for the sine and cosine components at a given frequency.

### Usage

```
## S4 method for signature 'tidem'
summary(object, p, constituent, ...)
```

## **Arguments**

object an object of class "tidem", usually, a result of a call to tidem.

p optional value of the maximum p value for the display of an individual coeffi-

cient. If not given, all coefficients are shown.

constituent optional name of constituent on which to focus.
... further arguments passed to or from other methods.

# Value

NULL

# Author(s)

Dan Kelley

#### See Also

```
Other things related to tidem data: [[,tidem-method,[[<-,tidem-method,plot,tidem-method,predict.tidem,tidedata,tidem-class,tidemAstron,tidemVuf,tidem
```

### **Examples**

```
## Not run:
library(oce)
data(sealevel)
tide <- tidem(sealevel)
summary(tide)
## End(Not run)</pre>
```

summary, topo-method

Summarize A Topo Object

# **Description**

Pertinent summary information is presented, including the longitude and latitude range, and the range of elevation.

## Usage

```
## S4 method for signature 'topo'
summary(object, ...)
```

### **Arguments**

object A topo object, i.e. inheriting from topo-class.
... Further arguments passed to or from other methods.

### Value

A matrix containing statistics of the elements of the data slot.

## Author(s)

Dan Kelley

#### See Also

Other things related to topo data: [[,topo-method,[[<-,topo-method,as.topo,download.topo,plot,topo-method,read.topo,subset,topo-method,topo-class,topoInterpolate,topoWorld

### **Examples**

```
library(oce)
data(topoWorld)
summary(topoWorld)
```

summary, windrose-method

Summarize a windrose object

### Description

Summarizes some of the data in a windrose object.

### Usage

```
## S4 method for signature 'windrose'
summary(object, ...)
```

### **Arguments**

object An windrose object, i.e. inheriting from windrose-class.
... Further arguments passed to or from other methods.

#### Author(s)

Dan Kelley

#### See Also

The documentation for windrose-class explains the structure of windrose objects, and also outlines the other functions dealing with them.

Other things related to windrose data: [[,windrose-method, [[<-,windrose-method, as.windrose, plot,windrose-method, windrose-class

sunAngle

Solar Angle as Function of Space and Time

# **Description**

Solar angle as function of space and time.

#### Usage

```
sunAngle(t, longitude = 0, latitude = 0, useRefraction = FALSE)
```

#### **Arguments**

t time, a POSIXt object (converted to timezone "UTC", if it is not already in that

timezone), or a numeric value that corresponds to such a time.

longitude observer longitude in degrees east latitude observer latitude in degrees north

useRefraction boolean, set to TRUE to apply a correction for atmospheric refraction

466 sunAngle

#### **Details**

Based on NASA-provided Fortran program, in turn (according to comments in the code) based on "The Astronomical Almanac".

#### Value

A list containing the following.

time time

azimuth azimuth, in degrees eastward of north, from 0 to 360. (See diagram below.)

altitude altitude, in degrees above the horizon, ranging from -90 to 90. (See diagram

below.)

diameter solar diameter, in degrees

distance distance to sun, in astronomical units

### Author(s)

Dan Kelley

#### References

Based on Fortran code retrieved from ftp://climate1.gsfc.nasa.gov/wiscombe/Solar\_Rad/SunAngles/sunae.f on 2009-11-1. Comments in that code list as references:

Michalsky, J., 1988: The Astronomical Almanac's algorithm for approximate solar position (1950-2050), Solar Energy 40, 227-235

The Astronomical Almanac, U.S. Gov't Printing Office, Washington, D.C. (published every year).

The code comments suggest that the appendix in Michalsky (1988) contains errors, and declares the use of the following formulae in the 1995 version the Almanac:

- p. A12: approximation to sunrise/set times;
- p. B61: solar altitude (AKA elevation) and azimuth;
- p. B62: refraction correction;
- p. C24: mean longitude, mean anomaly, ecliptic longitude, obliquity of ecliptic, right ascension, declination, Earth-Sun distance, angular diameter of Sun;
- p. L2: Greenwich mean sidereal time (ignoring T^2, T^3 terms).

The code lists authors as Dr. Joe Michalsky and Dr. Lee Harrison (State University of New York), with modifications by Dr. Warren Wiscombe (NASA Goddard Space Flight Center).

# See Also

The equivalent function for the moon is moonAngle.

Other things related to astronomy: eclipticalToEquatorial, equatorialToLocalHorizontal, julianCenturyAnomaly, julianDay, moonAngle, siderealTime

swAbsoluteSalinity 467

### **Examples**

swAbsoluteSalinity

Seawater absolute salinity, in GSW formulation

# Description

Compute seawater absolute salinity, according to the GSW/TEOS-10 formulation.

#### Usage

```
swAbsoluteSalinity(salinity, pressure = NULL, longitude = NULL,
latitude = NULL)
```

### **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object (in which case salinity, etc. are inferred from the

object).

pressure pressure in dbar.

longitude longitude of observation.

latitude latitude of observation.

#### **Details**

The absolute salinity is calculated using the GSW function gsw\_SA\_from\_SP. Typically, this is a fraction of a unit higher than practical salinity as defined in the UNESCO formulae.

### Value

Absolute Salinity in g/kg.

### Author(s)

468 swAlpha

### References

McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

#### See Also

The related TEOS-10 quantity "conservative temperature" may be computed with swConservativeTemperature. For a ctd object, absolute salinity may also be recovered by indexing as e.g. ctd[["absoluteSalinity"]] or ctd[["SA"]].

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

## **Examples**

swAlpha

Seawater thermal expansion coefficient

# Description

Compute  $\alpha$ , the thermal expansion coefficient for seawater.

# Usage

```
swAlpha(salinity, temperature = NULL, pressure = 0, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

## **Arguments**

salinity	either practical salinity (in which case temperature and pressure must be provided) <b>or</b> an oce object (in which case salinity, etc. are inferred from the object).
temperature	$\it in\text{-}situ$ temperature [°C], defined on the ITS-90 scale; see "Temperature units" in the documentation for swRho.
pressure	pressure [dbar]
longitude	longitude of observation (only used if eos="gsw"; see 'Details').
latitude	latitude of observation (only used if eos="gsw"; see 'Details').
eos	equation of state, either "unesco" or "gsw".

swAlphaOverBeta 469

#### Value

Value in 1/degC.

#### Author(s)

Dan Kelley

#### References

The eos="unesco" formulae are based on the UNESCO equation of state, but are formulated empirically by Trevor J. McDougall, 1987, Neutral Surfaces, Journal of Physical Oceanography, volume 17, pages 1950-1964. The eos="gsw" formulae come from GSW; see references in the swRho documentation.

### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swAlphaOverBeta Ratio of seawater thermal expansion coefficient to haline contraction coefficient

# **Description**

Compute  $\alpha/\beta$  using McDougall's (1987) algorithm.

## Usage

```
swAlphaOverBeta(salinity, temperature = NULL, pressure = NULL,
longitude = NULL, latitude = NULL, eos = getOption("oceEOS", default =
    "gsw"))
```

#### **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object (in which case salinity, etc. are inferred from the

object).

temperature in-situ temperature [ $^{\circ}$ C]

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" or "gsw".

470 swBeta

#### Value

Value in psu/°C.

#### Author(s)

Dan Kelley

#### References

The eos="unesco" formulae are based on the UNESCO equation of state, but are formulated empirically by Trevor J. McDougall, 1987, Neutral Surfaces, Journal of Physical Oceanography, volume 17, pages 1950-1964. The eos="gsw" formulae come from GSW; see references in the swRho documentation.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
swAlphaOverBeta(40, 10, 4000, eos="unesco") # 0.3476
```

swBeta

Seawater haline contraction coefficient

# **Description**

Compute  $\beta$ , the haline contraction coefficient for seawater.

# Usage

```
swBeta(salinity, temperature = NULL, pressure = 0, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

### **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object (in which case salinity, etc. are inferred from the

object).

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho.

pressure seawater pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" or "gsw".

#### Value

Value in 1/psu.

# Author(s)

Dan Kelley

#### References

The eos="unesco" formulae are based on the UNESCO equation of state, but are formulaed empirically by Trevor J. McDougall, 1987, Neutral Surfaces, Journal of Physical Oceanography, volume 17, pages 1950-1964. The eos="gsw" formulae come from GSW; see references in the swRho documentation.

## See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swConservativeTemperature

Seawater conservative temperature, in GSW formulation

## **Description**

Compute seawater Conservative Temperature, according to the GSW/TEOS-10 formulation.

# Usage

```
swConservativeTemperature(salinity, temperature = NULL, pressure = NULL,
longitude = NULL, latitude = NULL)
```

### **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object (in which case salinity, etc. are inferred from the

object).

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho.

pressure pressure [dbar]

longitude longitude of observation.

latitude latitude of observation.

#### **Details**

If the first argument is an oce object, then values for salinity, etc., are extracted from it, and used for the calculation, and the corresponding arguments to the present function are ignored.

The conservative temperature is calculated using the TEOS-10 function <code>gsw\_CT\_from\_t</code> from the <code>gsw</code> package.

#### Value

Conservative temperature in degrees Celcius.

### Author(s)

Dan Kelley

# References

McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

# See Also

The related TEOS-10 quantity "absolute salinity" may be computed with swAbsoluteSalinity. For a ctd object, conservative temperature may also be recovered by indexing as e.g. ctd[["conservativeTemperature"]] or ctd[["CT"]].

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

swConservativeTemperature(35,10,1000,188,4) # 9.86883

swCSTp 473

swCSTp Electrical conductivity ratio from salinity, temperature and pressure
--

# Description

Compute electrical conductivity ratio based on salinity, temperature, and pressure (relative to the conductivity of seawater with salinity=35, temperature68=15, and pressure=0).

# Usage

```
swCSTp(salinity, temperature = 15, pressure = 0, eos = getOption("oceEOS",
   default = "gsw"))
```

# **Arguments**

salinity practical salinity, or a CTD object (in which case its temperature and pressure

are used, and the next two arguments are ignored)

temperature in-situ temperature [°C], defined on the ITS-90 scale; see the examples, as well

as the "Temperature units" section in the documentation for swRho.

pressure pressure [dbar]

eos equation of state, either "unesco" or "gsw".

### Details

If eos="unesco", the calculation is done by a bisection root search on the UNESCO formula relating salinity to conductivity, temperature, and pressure (see swSCTp). If it is "gsw" then the Gibbs-SeaWater formulation is used, via gsw\_C\_from\_SP.

### Value

Conductivity ratio [unitless], i.e. the ratio of conductivity to the conductivity at salinity=35, temperature=15 (IPTS-68 scale) and pressure=0, which has numerical value 42.9140 mS/cm = 4.29140 S/m (see Culkin and Smith, 1980, in the regression result cited at the bottom of the left-hand column on page 23).

#### Author(s)

Dan Kelley

### References

- 1. Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp.
- 2. Culkin, F., and Norman D. Smith, 1980. Determination of the concentration of potassium chloride solution having the same electrical conductivity, at 15 C and infinite frequency, as standard seawater of salinity 35.0000 ppt (Chlorinity 19.37394 ppt). *IEEE Journal of Oceanic Engineering*, **5**, pp 22-23.

474 swDepth

## See Also

For thermal (as opposed to electrical) conductivity, see swThermalConductivity. For computation of salinity from electrical conductivity, see swSCTp.

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

### **Examples**

```
expect_equal(1, swCSTp(35, T90fromT68(15), 0, eos="unesco")) # by definition of cond. ratio
expect_equal(1, swCSTp(34.25045, T90fromT68(15), 2000, eos="unesco"), tolerance=1e-7)
expect_equal(1, swCSTp(34.25045, T90fromT68(15), 2000, eos="gsw"), tolerance=1e-7)
```

swDepth

Water depth

# **Description**

Compute depth below the surface (i.e. a positive number within the water column) based on pressure and latitude. (Use swZ to get the vertical coordinate, which is negative within the water column.)

# Usage

```
swDepth(pressure, latitude = 45, eos = getOption("oceEOS", default = "gsw"))
```

### **Arguments**

pressure either pressure [dbar], in which case lat must also be given, or a ctd object, in

which case lat will be inferred from the object.

latitude Latitude in °N or radians north of the equator.

eos indication of formulation to be used, either "unesco" or "gsw".

### **Details**

If eos="unesco" then depth is calculated from pressure using Saunders and Fofonoff's method, with the formula refitted for 1980 UNESCO equation of state [1]. If eos="gsw", then gsw\_z\_from\_p from the gsw package [2,3] is used.

# Value

Depth below the ocean surface, in metres.

swDynamicHeight 475

### Author(s)

Dan Kelley

#### References

1. Unesco 1983. Algorithms for computation of fundamental properties of seawater, 1983. *Unesco Tech. Pap. in Mar. Sci.*, No. 44, 53 pp.

- 2. IOC, SCOR, and IAPSO (2010). The international thermodynamic equation of seawater-2010: Calculation and use of thermodynamic properties. Technical Report 56, Intergovernmental Oceanographic Commission, Manuals and Guide.
- 3. McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
d <- swDepth(10, 45)</pre>
```

swDynamicHeight

Dynamic height of seawater profile

## Description

Compute the dynamic height of a column of seawater.

# Usage

```
swDynamicHeight(x, referencePressure = 2000, subdivisions = 500,
  rel.tol = .Machine$double.eps^0.25, eos = getOption("oceEOS", default =
  "gsw"))
```

# **Arguments**

x a section object, **or** a ctd object.

referencePressure

reference pressure [dbar]. If this exceeds the highest pressure supplied to swDynamicHeight, then that highest pressure is used, instead of the supplied value of referencePressure.

476 swDynamicHeight

subdivisions number of subdivisions for call to integrate. (The default value is consider-

ably larger than the default for integrate, because otherwise some test profiles

failed to integrate.

rel.tol absolute tolerance for call to integrate. Note that this call is made in scaled

coordinates, i.e. pressure is divided by its maximum value, and dz/dp is also

divided by its maximum.

eos equation of state, either "unesco" or "gsw".

#### **Details**

If the first argument is a section, then dynamic height is calculated for each station within a section, and returns a list containing distance along the section along with dynamic height.

If the first argument is a ctd, then this returns just a single value, the dynamic height.

If eos="unesco", processing is as follows. First, a piecewise-linear model of the density variation with pressure is developed using approxfun. (The option rule=2 is used to extrapolate the uppermost density up to the surface, preventing a possible a bias for bottle data, in which the first depth may be a few metres below the surface.) A second function is constructed as the density of water with salinity 35PSU, temperature of 0°C, and pressure as in the ctd. The difference of the reciprocals of these densities, is then integrated with integrate with pressure limits 0 to referencePressure. (For improved numerical results, the variables are scaled before the integration, making both independent and dependent variables be of order one.)

If eos="gsw", gsw\_geo\_strf\_dyn\_height is used to calculate a result in m^2/s^2, and this is divided by  $9.7963m/s^2$ . If pressures are out of order, the data are sorted. If any pressure is repeated, only the first level is used. If there are under 4 remaining distinct pressures, NA is returned, with a warning.

#### Value

In the first form, a list containing distance, the distance [km] from the first station in the section and height, the dynamic height [m].

In the second form, a single value, containing the dynamic height [m].

# Author(s)

Dan Kelley

## References

Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.

# See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swLapseRate 477

## **Examples**

```
## Not run:
library(oce)
data(section)
# Dynamic height and geostrophy
par(mfcol=c(2,2))
par(mar=c(4.5,4.5,2,1))
# Left-hand column: whole section
# (The smoothing lowers Gulf Stream speed greatly)
westToEast <- subset(section, 1<=stationId&stationId<=123)</pre>
dh <- swDynamicHeight(westToEast)</pre>
plot(dh$distance, dh$height, type='p', xlab="", ylab="dyn. height [m]")
ok <- !is.na(dh$height)</pre>
smu <- supsmu(dh$distance, dh$height)</pre>
lines(smu, col="blue")
f <- coriolis(section[["station", 1]][["latitude"]])</pre>
g <- gravity(section[["station", 1]][["latitude"]])</pre>
v <- diff(smu$y)/diff(smu$x) * g / f / 1e3 # 1e3 converts to m
plot(smu$x[-1], v, type='l', col="blue", xlab="distance [km]", ylab="velocity [m/s]")
# right-hand column: gulf stream region, unsmoothed
gs <- subset(section, 102<=stationId&stationId<=124)
dh.gs <- swDynamicHeight(gs)</pre>
plot(dh.gs$distance, dh.gs$height, type='b', xlab="", ylab="dyn. height [m]")
v \leftarrow diff(dh.gs\height)/diff(dh.gs\distance) * g / f / 1e3
plot(dh.gs$distance[-1], v, type='1', col="blue",
  xlab="distance [km]", ylab="velocity [m/s]")
## End(Not run)
```

swLapseRate

Seawater lapse rate

#### **Description**

Compute adiabatic lapse rate

# Usage

```
swLapseRate(salinity, temperature = NULL, pressure = NULL,
longitude = NULL, latitude = NULL, eos = getOption("oceEOS", default =
"gsw"))
```

478 swLapseRate

# **Arguments**

salinity either salinity [PSU] (in which case temperature and pressure must be pro-

vided) **or** a ctd object (in which case salinity, temperature and pressure are determined from the object, and must not be provided in the argument list).

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

### **Details**

If eos="unesco", the density is calculated using the UNESCO equation of state for seawater [1,2], and if eos="gsw", the GSW formulation [3,4] is used.

#### Value

Lapse rate [degC/m].

# Author(s)

Dan Kelley

### References

Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp. (Section 7, pages 38-40)

### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

## **Examples**

```
lr <- swLapseRate(40, 40, 10000) # 3.255976e-4</pre>
```

swN2 479

swN2 Squar	ed buoyancy frequency for seawater
------------	------------------------------------

### **Description**

Compute  $N^2$ , the square of the buoyancy frequency for a seawater profile.

# Usage

```
swN2(pressure, sigmaTheta = NULL, derivs, df, eos = getOption("oceEOS",
   default = "gsw"), ...)
```

### Arguments

pressure	either pressure [dbar] (in which case sigmaTheta must be provided) <b>or</b> an object of class ctd object (in which case sigmaTheta is inferred from the object.
sigmaTheta	Surface-referenced potential density minus 1000 [kg/m³]
derivs	optional argument to control how the derivative $d\sigma_{\theta}/dp$ is calculated. This may be a character string or a function of two arguments. See "Details".
df	argument passed to <pre>smooth.spline</pre> if this function is used for smoothing; set to NA to prevent smoothing.
eos	equation of state, either "unesco" or "gsw".
• • •	additional argument, passed to smooth.spline, in the case that derivs="smoothing". See "Details".

# **Details**

Smoothing is often useful prior to computing buoyancy frequency, and so this may optionally be done with smooth.spline, unless df=NA, in which case raw data are used. If df is not provided, a possibly reasonable value computed from an analysis of the profile, based on the number of pressure levels.

If eos="gsw", then the first argument must be a ctd object, and processing is done with gsw\_Nsquared, based on extracted values of Absolute Salinity and Conservative Temperature (possibly smoothed, depending on df).

If eos="unesco", then the processing is as follows. The core of the method involves differentiating potential density (referenced to median pressure) with respect to pressure, and the derivs argument is used to control how this is done, as follows.

- if derivs is not supplied, the action is as though it were given as the string "smoothing"
- if derivs equals "simple", then the derivative of density with respect to pressure is calculated as the ratio of first-order derivatives of density and pressure, each calculated using diff. (A zero is appended at the top level.)

480 swN2

• if derivs equals "smoothing", then the processing depends on the number of data in the profile, and on whether df is given as an optional argument. When the number of points exceeds 4, and when df exceeds 1, smooth.spline is used to calculate smoothing spline representation the variation of density as a function of pressure, and derivatives are extracted from the spline using predict. Otherwise, density is smoothed using smooth, and derivatives are calculated as with the "simple" method.

• if derivs is a function taking two arguments (first pressure, then density) then that function is called directly to calculate the derivative, and no smoothing is done before or after that call.

For deep-sea work, the eos="gsw" option is the best scheme, because it uses derivatives of density computed with *local* reference pressure.

For precise work, it makes sense to skip swN2 entirely, choosing whether, what, and how to smooth based on an understanding of fundamental principles as well as data practicalities.

#### Value

Square of buoyancy frequency  $[radian^2/s^2]$ .

#### Author(s)

Dan Kelley

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
library(oce)
data(ctd)
# Illustrate difference between UNESCO and GSW
p <- ctd[["pressure"]]
ylim <- rev(range(p))
par(mfrow=c(1,3), mar=c(3, 3, 1, 1), mgp=c(2, 0.7, 0))
plot(ctd[["sigmaTheta"]], p, ylim=ylim, type='l', xlab=expression(sigma[theta]))
N2u <- swN2(ctd, eos="unesco")
N2g <- swN2(ctd, eos="gsw")
plot(N2u, p, ylim=ylim, xlab="N2 Unesco", ylab="p", type="l")
d <- 100 * (N2u - N2g) / N2g
plot(d, p, ylim=ylim, xlab="N2 UNESCO-GSW diff. [%]", ylab="p", type="l")
abline(v=0)</pre>
```

swPressure 481

|--|

### **Description**

Compute seawater pressure from depth by inverting swDepth using uniroot.

# Usage

```
swPressure(depth, latitude = 45, eos = getOption("oceEOS", default = "gsw"))
```

# Arguments

depth distance below the surface in metres.

latitude Latitude in °N or radians north of the equator.

eos indication of formulation to be used, either "unesco" or "gsw".

#### **Details**

If eos="unesco" this is done by numerical inversion of swDepth is done using uniroot. If eos="gsw", it is done using gsw\_p\_from\_z in the gsw package.

# Value

Pressure in dbar.

# Author(s)

Dan Kelley

#### References

Unesco 1983. Algorithms for computation of fundamental properties of seawater, 1983. *Unesco Tech. Pap. in Mar. Sci.*, No. 44, 53 pp.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
swPressure(9712.653, 30, eos="unesco") # 10000
swPressure(9712.653, 30, eos="gsw") # 9998.863
```

482 swRho

|--|

### **Description**

Compute  $\rho$ , the *in-situ* density of seawater.

# Usage

```
swRho(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

# **Details**

If eos="unesco", the density is calculated using the UNESCO equation of state for seawater [1,2], and if eos="gsw", the GSW formulation [3,4] is used.

#### Value

*In-situ* density [kg/m<sup>3</sup>].

# **Temperature units**

The UNESCO formulae are defined in terms of temperature measured on the IPTS-68 scale, whereas the replacement GSW formulae are based on the ITS-90 scale. Prior to the addition of GSW capabilities, the various sw\* functions took temperature to be in IPTS-68 units. As GSW capabilities were added in early 2015, the assumed unit of temperature was taken to be ITS-90. This change means that old code has to be modified, by replacing e.g. swRho(S, T, p) with swRho(S, T90fromT68(T), p). At typical oceanic values, the difference between the two scales is a few millidegrees.

swRrho 483

### Author(s)

Dan Kelley

#### References

1. Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp

- 2. Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.
- 3. IOC, SCOR, and IAPSO (2010). The international thermodynamic equation of seawater-2010: Calculation and use of thermodynamic properties. Technical Report 56, Intergovernmental Oceanographic Commission, Manuals and Guide.
- 4. McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

#### See Also

Related density routines include swSigma0 (and equivalents at other pressure horizons), swSigmaT, and swSigmaTheta.

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

swRrho

Density ratio

# **Description**

Compute density ratio

484 swRrho

#### Usage

```
swRrho(ctd, sense = c("diffusive", "finger"), smoothingLength = 10, df,
eos = getOption("oceEOS", default = "gsw"))
```

### **Arguments**

ctd an object of class ctd

sense an indication of the sense of double diffusion under study and therefore of the

definition of Rrho; see 'Details'

smoothingLength

ignored if df supplied, but otherwise the latter is calculated as the number of data points, divided by the number within a depth interval of smoothingLength

metres.

df if given, this is provided to smooth.spline.

eos equation of state, either "unesco" or "gsw".

#### **Details**

This computes Rrho (density ratio) from a ctd object.

If eos="unesco", this is done by calculating salinity and potential-temperature derivatives from smoothing splines whose properties are governed by smoothingLength or df. If sense="diffusive" the definition is (beta\*dS/dz)/(alpha\*d(theta)/dz) and the reciprocal for "finger".

If eos="gsw", this is done by extracting absolute salinity and conservative temperature, smoothing with a smoothing spline as in the "unesco" case, and then calling gsw\_Turner\_Rsubrho on these smoothed fields. Since the gsw function works on mid-point pressures, approx is used to interpolate back to the original pressures.

If the default arguments are acceptable, ctd[["Rrho"]] may be used instead of swRrho(ctd).

#### Value

Density ratio defined in either the "diffusive" or "finger" sense.

### Author(s)

Dan Kelley and Chantelle Layton

### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSCTp 485

## **Examples**

```
library(oce)
data(ctd)
u <- swRrho(ctd, eos="unesco")
g <- swRrho(ctd, eos="gsw")
p <- ctd[["p"]]
plot(u, p, ylim=rev(range(p)), type='l', xlab=expression(R[rho]))
lines(g, p, lty=2, col='red')
legend("topright", lty=1:2, legend=c("unesco", "gsw"), col=c("black", "red"))</pre>
```

swSCTp

Salinity from electrical conductivity, temperature and pressure

## **Description**

Compute salinity based on electrical conductivity, temperature, and pressure.

# Usage

```
swSCTp(conductivity, temperature = NULL, pressure = NULL, conductivityUnit,
eos = getOption("oceEOS", default = "gsw"))
```

# Arguments

conductivity a measure of conductivity (see also conductivityUnit) or an oce object hold-

ing hydrographic information. In the second case, all the other arguments to

swSCTp are ignored.

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho.

pressure pressure [dbar]

conductivityUnit

string indicating the unit used for conductivity. This may be "ratio" or "" (meaning conductivity ratio), "mS/cm" or "S/m". Note that the ratio mode assumes that measured conductivity has been divided by the standard conductivity

of 4.2914 S/m.

eos equation of state, either "unesco" or "gsw".

# **Details**

Calculate salinity from what is actually measured by a CTD, *i.e.* conductivity, *in-situ* temperature and pressure. Often this is done by the CTD processing software, but sometimes it is helpful to do this directly, *e.g.* when there is a concern about mismatches in sensor response times. If eos="unesco" then salinity is calculated using the UNESCO algorithm described by Fofonoff and Millard (1983); if it is "gsw" then the Gibbs-SeaWater formulation is used, via gsw\_SP\_from\_C.

## Value

Practical salinity.

# Author(s)

Dan Kelley

#### References

Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp

## See Also

For thermal (as opposed to electrical) conductivity, see swThermalConductivity. For computation of electrical conductivity from salinity, see swCSTp.

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
swSCTp(1, T90fromT68(15), 0, eos="unesco") # 35
swSCTp(1, T90fromT68(15), 0, eos="gsw") # 35
```

swSigma

Seawater density anomaly

# **Description**

Compute  $\sigma_{\theta}$ , the density of seawater, minus 1000 kg/m<sup>3</sup>.

# Usage

```
swSigma(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### Value

Density anomaly [kg/m<sup>3</sup>], defined as swRho - 1000 kg/m<sup>3</sup>.

### Author(s)

Dan Kelley

#### References

See citations provided in the swRho documentation.

### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# Examples

```
library(oce)
swSigma(35, 13, 1000, longitude=300, latitude=30, eos="gsw") # 30.82374
swSigma(35, T90fromT68(13), 1000, eos="unesco") # 30.8183
```

swSigma0

Seawater potential density anomaly referenced to surface pressure

# **Description**

Compute  $\sigma_{\theta}$ , the potential density of seawater (minus 1000 kg/m<sup>3</sup>), referenced to surface pressure.

### **Usage**

```
swSigma0(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

# **Details**

```
Definition: \sigma_0 = \sigma_\theta = \rho(S, \theta(S, t, p), 0 - 1000 \text{ kg/m}^3.
```

# Value

Potential density anomaly [kg/m<sup>3</sup>].

# Author(s)

Dan Kelley

# References

See citations provided in the swRho documentation.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSigma1

Seawater potential density anomaly referenced to 1000db pressure

## **Description**

Compute  $\sigma_{\theta}$ , the potential density of seawater (minus 1000 kg/m<sup>3</sup>), referenced to 1000db pressure.

# Usage

```
swSigma1(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

# Arguments

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

# **Details**

```
Definition: \sigma_1 = \sigma_\theta = \rho(S, \theta(S, t, p), 1000 - 1000 \text{ kg/m}^3.
```

#### Value

Potential density anomaly [kg/m<sup>3</sup>].

#### Author(s)

Dan Kelley

#### References

See citations provided in the swRho documentation.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSigma2

Seawater potential density anomaly referenced to 2000db pressure

# Description

Compute  $\sigma_{\theta}$ , the potential density of seawater (minus 1000 kg/m<sup>3</sup>), referenced to 2000db pressure.

# Usage

```
swSigma2(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

## Arguments

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### **Details**

```
Definition: \sigma_1 = \sigma_\theta = \rho(S, \theta(S, t, p), 1000 - 2000 \text{ kg/m}^3.
```

#### Value

Potential density anomaly [kg/m<sup>3</sup>].

# Author(s)

Dan Kelley

#### References

See citations provided in the swRho documentation.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSigma3

Seawater potential density anomaly referenced to 3000db pressure

# Description

Compute  $\sigma_{\theta}$ , the potential density of seawater (minus 1000 kg/m<sup>3</sup>), referenced to 3000db pressure.

# Usage

```
swSigma3(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

### **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

# **Details**

```
Definition: \sigma_1 = \sigma_\theta = \rho(S, \theta(S, t, p), 3000 - 1000 \text{ kg/m}^3.
```

#### Value

Potential density anomaly [kg/m<sup>3</sup>].

#### Author(s)

Dan Kelley

#### References

See citations provided in the swRho documentation.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSigma4

Seawater potential density anomaly referenced to 4000db pressure

## **Description**

Compute  $\sigma_{\theta}$ , the potential density of seawater (minus 1000 kg/m<sup>3</sup>), referenced to 4000db pressures.

# Usage

```
swSigma4(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### **Details**

```
Definition: \sigma_1 = \sigma_\theta = \rho(S, \theta(S, t, p), 4000 - 1000 \text{ kg/m}^3.
```

#### Value

Potential density anomaly [kg/m<sup>3</sup>].

#### Author(s)

Dan Kelley

### References

See citations provided in the swRho documentation.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSigmaT

Seawater quasi-potential density anomaly

# **Description**

Compute  $\sigma_t$ , a rough estimate of potential density of seawater, minus 1000 kg/m<sup>3</sup>.

### **Usage**

```
swSigmaT(salinity, temperature = NULL, pressure = NULL, longitude = NULL,
latitude = NULL, eos = getOption("oceEOS", default = "gsw"))
```

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

494 swSigmaTheta

```
longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].
```

#### **Details**

If the first argument is an oce object, then salinity, etc., are extracted from it, and used for the calculation.

#### Value

Quasi-potential density anomaly [kg/m³], defined as the density calculated with pressure set to zero.

# Author(s)

Dan Kelley

#### References

See citations provided in the swRho documentation.

## See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
swSigmaT(35, 13, 1000, longitude=300, latitude=30, eos="gsw") # 26.39623
swSigmaT(35, T90fromT68(13), 1000, eos="unesco") # 26.39354
```

swSigmaTheta

Seawater potential density anomaly

## **Description**

Compute the potential density (minus 1000 kg/m<sup>3</sup>) that seawater would have if raised adiabatically to the surface. In the UNESCO system, this quantity is is denoted  $\sigma_{\theta}$  (hence the function name), but in the GSW system, it is denoted sigma0.

# Usage

```
swSigmaTheta(salinity, temperature = NULL, pressure = NULL,
referencePressure = 0, longitude = NULL, latitude = NULL,
eos = getOption("oceEOS", default = "gsw"))
```

swSigmaTheta 495

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

referencePressure

The reference pressure, in dbar.

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

## **Details**

If the first argument is an oce object, then salinity, etc., are extracted from it, and used for the calculation instead of any values provided in the other arguments.

### Value

Potential density anomaly [kg/m<sup>3</sup>], defined as  $\sigma_{\theta} = \rho(S, \theta(S, t, p), 0 - 1000 \text{ kg/m}^3)$ .

## Author(s)

Dan Kelley

#### References

See citations provided in the swRho documentation.

### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigma7, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
expect_equal(26.4212790994, swSigmaTheta(35, 13, 1000, eos="unesco"))
```

496 swSoundAbsorption

swSoundAbsorption	Seawater sound absorption in dB/m
encouna acor peron	Seawarer serina description in aBini

# **Description**

Compute the sound absorption of seawater, in dB/m

## Usage

```
swSoundAbsorption(frequency, salinity, temperature, pressure, pH = 8,
  formulation = c("fisher-simmons", "francois-garrison"))
```

### **Arguments**

frequency The frequency of sound, in Hz.

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]
pH seawater pH

formulation character string indicating the formulation to use, either of "fischer-simmons"

or "francois-garrison"; see "References".

#### **Details**

Salinity and pH are ignored in this formulation. Several formulae may be found in the literature, and they give results differing by 10 percent, as shown at [3] for example. For this reason, it is likely that more formulations will be added to this function, and entirely possible that the default may change.

# Value

Sound absorption in dB/m.

# Author(s)

Dan Kelley

swSoundSpeed 497

#### References

- 1. F. H. Fisher and V. P. Simmons, 1977. Sound absorption in sea water. J. Acoust. Soc. Am., 62(3), 558-564.
- 2. R. E. Francois and G. R. Garrison, 1982. Sound absorption based on ocean measurements. Part II: Boric acid contribution and equation for total absorption. J. Acoust. Soc. Am., 72(6):1879-1890.

3. http://resource.npl.co.uk/acoustics/techguides/seaabsorption/

## See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

swSoundSpeed

Seawater sound speed

## **Description**

Compute the seawater speed of sound.

# Usage

```
swSoundSpeed(salinity, temperature = NULL, pressure = NULL,
longitude = NULL, latitude = NULL, eos = getOption("oceEOS", default =
    "gsw"))
```

498 swSoundSpeed

## **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object, in which case salinity, temperature (in the ITS-90

scale; see next item), etc. are inferred from the object.

temperature in-situ temperature [°C], defined on the ITS-90 scale. This scale is used by

GSW-style calculation (as requested by setting eos="gsw"), and is the value contained within ctd objects (and probably most other objects created with data acquired in the past decade or two). Since the UNESCO-style calculation is based on IPTS-68, the temperature is converted within the present function, us-

ing T68fromT90.

pressure pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### **Details**

If eos="unesco", the sound speed is calculated using the formulation in section 9 of Fofonoff and Millard (1983). If eos="gsw", then the gsw\_sound\_speed function from the gsw package is used.

## Value

Sound speed [m/s].

# Author(s)

Dan Kelley

#### References

Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp. (See section 9.)

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
swSoundSpeed(40, T90fromT68(40), 10000) # 1731.995 (p48 of Fofonoff + Millard 1983)
```

swSpecificHeat 499

swSpecificHeat	Seawater specific heat Source= http://sam.ucsd.edu/sio210/propseawater/ppsw_fortran/ppsw.f
	check value: $cpsw = 3849.500 \ j/(kg \ deg. \ c)$ for $s = 40 \ (ipss-78)$ ,

# **Description**

Compute specific heat of seawater.

# Usage

```
swSpecificHeat(salinity, temperature = NULL, pressure = 0,
longitude = NULL, latitude = NULL, eos = getOption("oceEOS", default =
"gsw"))
```

# **Arguments**

salinity either practical salinity (in which case temperature and pressure must be pro-

vided) or an oce object (in which case salinity, etc. are inferred from the

object).

temperature in-situ temperature [°C], defined on the ITS-90 scale.

pressure seawater pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" or "gsw".

# **Details**

If the first argument is a ctd object, then salinity, etc, are extracted from it, and used for the calculation.

# Value

```
Specific heat Jkg^{-1} \circ C^{-1}
```

# Author(s)

Dan Kelley

# References

```
Millero et. al., J. Geophys. Res. 78 (1973), 4499-4507
Millero et. al., UNESCO report 38 (1981), 99-188.
```

500 swSpice

## See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

# **Examples**

```
swSpecificHeat(40, T90fromT68(40), 10000, eos="unesco") # 3949.499
```

swSpice

Seawater spiciness

# **Description**

Compute seawater "spice" (a variable orthogonal to density in TS space).

### Usage

```
swSpice(salinity, temperature = NULL, pressure = NULL)
```

# **Arguments**

salinity either salinity [PSU] (in which case temperature and pressure must be pro-

vided) or a ctd object (in which case salinity, temperature and pressure

are determined from the object, and must not be provided in the argument list).

temperature in-situ temperature [°C] on the ITS-90 scale; see "Temperature units" in the

documentation for swRho.

pressure seawater pressure [dbar]

#### **Details**

If the first argument is a ctd object, then salinity, temperature and pressure values are extracted from it, and used for the calculation.

Roughly speaking, seawater with a high spiciness is relatively warm and salty compared with less spicy water. Another interpretation is that spice is a variable measuring distance orthogonal to isopycnal lines on TS diagrams (if the diagrams are scaled to make the isopycnals run at 45 degres). The definition used here is that of Pierre Flament. (Other formulations exist.) Note that pressure is ignored in the definition. Spiciness is sometimes denoted  $\pi(S,t,p)$ .

# Value

Spice [kg/m<sup>3</sup>].

swSTrho 501

# Author(s)

Dan Kelley

### References

P. Flament, 2002. A state variable for characterizing water masses and their diffusive stability: spiciness. *Progr. Oceanog.*, **54**, 493-501.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

swSTrho

Seawater salinity from temperature and density

## **Description**

Compute Practical or Absolute Salinity, given in-situ or Conservative Temperature, density, and pressure. This is mainly used to draw isopycnal lines on TS diagrams, hence the dual meanings for salinity and temperature, depending on the value of eos.

# Usage

```
swSTrho(temperature, density, pressure, eos = getOption("oceEOS", default =
   "gsw"))
```

# **Arguments**

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho.

density in-situ density or sigma value  $[kg/m^3]$ 

pressure *in-situ* pressure [dbar]

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### **Details**

For eos="unesco", finds the practical salinity that yields the given density, with the given in-situ temperature and pressure. The method is a bisection search with a salinity tolerance of 0.001. For eos="gsw", the function gsw\_SA\_from\_rho in the gsw package is used to infer Absolute Salinity from Conservative Temperature.

502 swTFreeze

#### Value

Practical Salinity, if eos="unesco", or Absolute Salinity, if eos="gsw".

### Author(s)

Dan Kelley

#### References

- 1. Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp
- 2. Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.
- 3. IOC, SCOR, and IAPSO (2010). The international thermodynamic equation of seawater-2010: Calculation and use of thermodynamic properties. Technical Report 56, Intergovernmental Oceanographic Commission, Manuals and Guide.
- 4. McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

#### See Also

#### swTSrho

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

## **Examples**

```
swSTrho(10, 22, 0, eos="gsw") # 28.76285
swSTrho(10, 22, 0, eos="unesco") # 28.651625
```

swTFreeze

Seawater freezing temperature

# **Description**

Compute freezing temperature of seawater.

#### **Usage**

```
swTFreeze(salinity, pressure = 0, longitude = NULL, latitude = NULL,
saturation_fraction = 1, eos = getOption("oceEOS", default = "gsw"))
```

swTFreeze 503

## **Arguments**

salinity either salinity [PSU] or a ctd object from which salinity will be inferred.

pressure seawater pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

saturation\_fraction

saturation fraction of dissolved air in seawater (used only if eos="gsw").

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### **Details**

In the first form, the argument is a ctd object, from which the salinity and pressure values are extracted and used to for the calculation.

### Value

Temperature [°C], defined on the ITS-90 scale.

#### Author(s)

Dan Kelley

### References

- [1] Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp
- [2] Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.
- [3] IOC, SCOR, and IAPSO (2010). The international thermodynamic equation of seawater-2010: Calculation and use of thermodynamic properties. Technical Report 56, Intergovernmental Oceanographic Commission, Manuals and Guide.
- [4] McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

# See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

## **Examples**

```
swTFreeze(salinity=40, pressure=500, eos="unesco") # -2.588567 degC
```

swThermalConductivity Seawater thermal conductivity

# **Description**

Compute seawater thermal conductivity, in  $Wm^{-1} \circ C^{-1}$ 

# Usage

```
swThermalConductivity(salinity, temperature = NULL, pressure = NULL)
```

# **Arguments**

salinity salinity [PSU], or a ctd object, in which case temperature and pressure will

be ignored.

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho.

pressure pressure [dbar]

#### **Details**

Caldwell's (1974) detailed formulation is used. To be specific, his equation 6 to calculate K, and his two sentences above that equation are used to infer this to be K(0,T,S) in his notation of equation 7. Then, application of his equations 7 and 8 is straightforward. He states an accuracy for this method of 0.3 percent. (See the check against his Table 1 in the "Examples".)

# Value

Conductivity of seawater in  $Wm^{-1} \circ C^{-1}$ .

To calculate thermal diffusivity in  $m^2/s$ , divide by the product of density and specific heat, as in the example.

### Author(s)

Dan Kelley

### References

Caldwell, Douglas R., 1974. Thermal conductivity of seawater, Deep-sea Research, 21, 131-137.

# See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swTheta, swViscosity, swZ

swTheta 505

### **Examples**

```
library(oce)
# Values in m^2/s, a unit that is often used instead of W/(m*degC).
swThermalConductivity(35, 10, 100) / (swRho(35,10,100) * swSpecificHeat(35,10,100)) # ocean
swThermalConductivity(0, 20, 0) / (swRho(0, 20, 0) * swSpecificHeat(0, 20, 0)) # lab
# Caldwell Table 1 gives 1478e-6 cal/(cm*sec*degC) at 31.5 o/oo, 10degC, 1kbar
joulePerCalorie <- 4.18400
cmPerM <- 100
swThermalConductivity(31.5,10,1000) / joulePerCalorie / cmPerM</pre>
```

swTheta

Seawater potential temperature

### **Description**

Compute the potential temperature of seawater, denoted  $\theta$  in the UNESCO system, and pt in the GSW system.

### Usage

```
swTheta(salinity, temperature = NULL, pressure = NULL,
referencePressure = 0, longitude = NULL, latitude = NULL,
eos = getOption("oceEOS", default = "gsw"))
```

### **Arguments**

salinity either salinity [PSU] (in which case temperature and pressure must be pro-

vided) or an oce object (in which case salinity, etc. are inferred from the

object).

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho, and the examples below.

pressure pressure [dbar]

referencePressure

reference pressure [dbar]

longitude longitude of observation (only used if eos="gsw"; see 'Details').

latitude latitude of observation (only used if eos="gsw"; see 'Details').

eos equation of state, either "unesco" [1,2] or "gsw" [3,4].

#### **Details**

Different formulae are used depending on the equation of state. If eos is "unesco", the method of Fofonoff *et al.* (1983) is used [1,2]. Otherwise, swTheta uses gsw\_pt\_from\_t from the gsw package.

If the first argument is a ctd or section object, then values for salinity, etc., are extracted from it, and used for the calculation, and the corresponding arguments to the present function are ignored.

506 swTheta

#### Value

Potential temperature [°C] of seawater, referenced to pressure referencePressure.

#### Author(s)

Dan Kelley

#### References

- [1] Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. *Unesco Technical Papers in Marine Science*, **44**, 53 pp
- [2] Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.
- [3] IOC, SCOR, and IAPSO (2010). The international thermodynamic equation of seawater-2010: Calculation and use of thermodynamic properties. Technical Report 56, Intergovernmental Oceanographic Commission, Manuals and Guide.
- [4] McDougall, T.J. and P.M. Barker, 2011: Getting started with TEOS-10 and the Gibbs Seawater (GSW) Oceanographic Toolbox, 28pp., SCOR/IAPSO WG127, ISBN 978-0-646-55621-5.

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swViscosity, swZ

## **Examples**

swTSrho 507

swTSrho	Seawater temperature from salinity and density	

### **Description**

Compute in-situ temperature, given salinity, density, and pressure.

## Usage

```
swTSrho(salinity, density, pressure = NULL, eos = getOption("oceEOS",
  default = "gsw"))
```

# **Arguments**

```
salinity in-situ salinity [PSU]

density in-situ density or sigma value [kg/m³]

pressure in-situ pressure [dbar]
```

eos equation of state to be used, either "unesco" or "gsw" (ignored at present).

#### **Details**

Finds the temperature that yields the given density, with the given salinity and pressure. The method is a bisection search with temperature tolerance  $0.001 \,^{\circ}C$ .

#### Value

*In-situ* temperature [ ${}^{\circ}C$ ] in the ITS-90 scale.

### Author(s)

Dan Kelley

### References

```
Fofonoff, P. and R. C. Millard Jr, 1983. Algorithms for computation of fundamental properties of seawater. Unesco Technical Papers in Marine Science, 44, 53 pp Gill, A.E., 1982. Atmosphere-ocean Dynamics, Academic Press, New York, 662 pp.
```

### See Also

```
swSTrho
```

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swThermalConductivity, swTheta, swViscosity, swZ

508 swViscosity

### **Examples**

```
swTSrho(35, 23, 0, eos="unesco") # 26.11301
```

swViscosity

Seawater viscosity

# Description

Compute viscosity of seawater, in  $Pa \cdot s$ 

### Usage

```
swViscosity(salinity, temperature)
```

### **Arguments**

salinity either salinity [PSU] (in which case temperature and pressure must be pro-

vided) **or** a ctd object (in which case salinity, temperature and pressure are determined from the object, and must not be provided in the argument list).

temperature in-situ temperature [°C], defined on the ITS-90 scale; see "Temperature units"

in the documentation for swRho, and the examples below.

## **Details**

If the first argument is a ctd object, then salinity, temperature and pressure values are extracted from it, and used for the calculation.

The result is determined from a regression of the data provided in Table 87 of Dorsey (1940). The fit matches the table to within 0.2 percent at worst, and with average absolute error of 0.07 percent. The maximum deviation from the table is one unit in the last decimal place.

No pressure dependence was reported by Dorsey (1940).

### Value

Viscosity of seawater in  $Pa \cdot s$ . Divide by density to get kinematic viscosity in  $m^2/s$ .

# Author(s)

Dan Kelley

### References

N. Ernest Dorsey (1940), *Properties of ordinary Water-substance*, American Chemical Society Monograph Series. Reinhold Publishing.

swZ 509

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swZ

### **Examples**

```
swViscosity(30, 10) # 0.001383779
```

swZ

Vertical coordinate

### **Description**

Compute height above the surface. This is the negative of depth, and so is defined simply in terms of swDepth.

### Usage

```
swZ(pressure, latitude = 45, eos = getOption("oceEOS", default = "gsw"))
```

## **Arguments**

pressure either pressure [dbar], in which case lat must also be given, or a ctd object, in

which case lat will be inferred from the object.

latitude in °N or radians north of the equator.

eos indication of formulation to be used, either "unesco" or "gsw".

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity

510 T68fromT90

T68fromT90

Convert from ITS-90 to IPTS-68 temperature

## **Description**

Today's instruments typically record in the ITS-90 scale, but some old datasets will be in the IPTS-68 scale. T90fromT68() converts from the IPTS-68 to the ITS-90 scale, using Saunders' (1990) formula, while T68fromT90() does the reverse. The difference between IPTS-68 and ITS-90 values is typically a few millidegrees (see 'Examples'), which is seldom visible on a typical temperature profile, but may be of interest in some precise work. Mostly for historical interest, T90fromT48() is provided to convert from the ITS-48 system to ITS-90.

#### Usage

T68fromT90(temperature)

### Arguments

temperature Vector of temperatures expressed in the ITS-90 scale.

#### Value

Temperature expressed in the IPTS-68 scale.

### Author(s)

Dan Kelley

#### References

P. M. Saunders, 1990. The international temperature scale of 1990, ITS-90. WOCE Newsletter, volume 10, September 1990, page 10. (http://www.nodc.noaa.gov/woce/wdiu/wocedocs/newsltr/news10/contents.htm)

# See Also

Other functions that calculate seawater properties: T90fromT48, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

T90fromT48 511

### **Examples**

```
library(oce)
T68 <- seq(3, 20, 1)
T90 <- T90fromT68(T68)
sqrt(mean((T68-T90)^2))</pre>
```

T90fromT48

Convert from ITS-48 to ITS-90 temperature

### **Description**

Today's instruments typically record in the ITS-90 scale, but some old datasets will be in the IPTS-68 scale. T90fromT68() converts from the IPTS-68 to the ITS-90 scale, using Saunders' (1990) formula, while T68fromT90() does the reverse. The difference between IPTS-68 and ITS-90 values is typically a few millidegrees (see 'Examples'), which is seldom visible on a typical temperature profile, but may be of interest in some precise work. Mostly for historical interest, T90fromT48() is provided to convert from the ITS-48 system to ITS-90.

#### **Usage**

T90fromT48(temperature)

# Arguments

temperature Vector of temperatures expressed in the ITS-48 scale.

### Value

Temperature expressed in the ITS-90 scale.

#### Author(s)

Dan Kelley

#### References

P. M. Saunders, 1990. The international temperature scale of 1990, ITS-90. WOCE Newsletter, volume 10, September 1990, page 10. (http://www.nodc.noaa.gov/woce/wdiu/wocedocs/newsltr/news10/contents.htm)

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT68, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

512 T90fromT68

### **Examples**

```
library(oce)
T68 <- seq(3, 20, 1)
T90 <- T90fromT68(T68)
sqrt(mean((T68-T90)^2))</pre>
```

T90fromT68

Convert from IPTS-68 to ITS-90 temperature

### **Description**

Today's instruments typically record in the ITS-90 scale, but some old datasets will be in the IPTS-68 scale. T90fromT68() converts from the IPTS-68 to the ITS-90 scale, using Saunders' (1990) formula, while T68fromT90() does the reverse. The difference between IPTS-68 and ITS-90 values is typically a few millidegrees (see 'Examples'), which is seldom visible on a typical temperature profile, but may be of interest in some precise work. Mostly for historical interest, T90fromT48() is provided to convert from the ITS-48 system to ITS-90.

#### **Usage**

T90fromT68(temperature)

# Arguments

temperature Vector of temperatures expressed in the IPTS-68 scale.

### Value

temperature Temperature expressed in the ITS-90 scale.

#### Author(s)

Dan Kelley

#### References

P. M. Saunders, 1990. The international temperature scale of 1990, ITS-90. WOCE Newsletter, volume 10, September 1990, page 10. (http://www.nodc.noaa.gov/woce/wdiu/wocedocs/newsltr/news10/contents.htm)

#### See Also

Other functions that calculate seawater properties: T68fromT90, T90fromT48, swAbsoluteSalinity, swAlphaOverBeta, swAlpha, swBeta, swCSTp, swConservativeTemperature, swDepth, swDynamicHeight, swLapseRate, swN2, swPressure, swRho, swRrho, swSCTp, swSTrho, swSigma0, swSigma1, swSigma2, swSigma3, swSigma4, swSigmaTheta, swSigmaT, swSigma, swSoundAbsorption, swSoundSpeed, swSpecificHeat, swSpice, swTFreeze, swTSrho, swThermalConductivity, swTheta, swViscosity, swZ

tail.oce 513

## **Examples**

```
library(oce)
T68 <- seq(3, 20, 1)
T90 <- T90fromT68(T68)
sqrt(mean((T68-T90)^2))</pre>
```

tail.oce

Extract the End of an Oce Object

## **Description**

Extract the End of an Oce Object

# Usage

```
## S3 method for class 'oce'
tail(x, n = 6L, ...)
```

# Arguments

x An oce object of a suitable class (presently only adp is permitted).

n Number of elements to extract.

... ignored

### See Also

head.oce, which yields the start of an oce object.

threenum

Calculate min, mean, and max values

# Description

This is a faster cousin of the standard fivenum function, used in generic summary functions for oce objects.

## Usage

threenum(x)

# Arguments

Χ

a vector or matrix of numerical values.

514 tidedata

#### Value

A character vector of four values: the minimum, the mean, the maximum, and an indication of the number of data.

#### Author(s)

Dan Kelley

#### **Examples**

library(oce)
threenum(1:10)

tidedata

Tidal Constituent Information

### **Description**

The tidedata dataset contains Tide-constituent information that is use by tidem to fit tidal models. tidedata is a list containing

const a list containing vectors name (a string with constituent name), freq (the frequency, in cycles per hour), kmpr (a string naming the comparison constituent, blank if there is none), ikmpr (index of comparison constituent, or 0 if there is none), df (frequency difference between constituent and its comparison, used in the Rayleigh criterion), d1 through d6 (the first through sixth Doodson numbers), semi, nsat (number of satellite constituents), ishallow, nshallow, doodsonamp, and doodsonspecies.

sat a list containing vectors deldood, phcorr, amprat, ilatfac, and iconst.

shallow a list containing vectors iconst, coef, and iname.

Apart from the use of d1 through d6, the naming and content follows T\_TIDE (see Pawlowicz et al. 2002), which in turn builds upon the analysis of Foreman (1977).

#### Author(s)

Dan Kelley

#### Source

The data come from the tide3.dat file of the T\_TIDE package (Pawlowicz et al., 2002), and derive from Appendices provided by Foreman (1977). The data are scanned using 'tests/tide.R' in this package, which also performs some tests using T\_TIDE values as a reference.

### References

Foreman, M. G. G., 1977. Manual for tidal heights analysis and prediction. Pacific Marine Science Report 77-10, Institute of Ocean Sciences, Patricia Bay, Sidney, BC, 58pp.

Pawlowicz, Rich, Bob Beardsley, and Steve Lentz, 2002. Classical tidal harmonic analysis including error estimates in MATLAB using T\_TIDE. Computers and Geosciences, 28, 929-937.

#### See Also

Other things related to tidem data: [[,tidem-method, [[<-,tidem-method, plot,tidem-method, predict.tidem, summary,tidem-method, tidem-class, tidemAstron, tidemVuf, tidem

tidem

Fit a Tidem (Tidal Model) to a Timeseries

# Description

The fit is done in terms of sine and cosine components at the indicated tidal frequencies, with the amplitude and phase being calculated from the resultant coefficients on the sine and cosine terms.

### Usage

```
tidem(t, x, constituents, infer = NULL, latitude = NULL, rc = 1,
  regress = lm, debug = getOption("oceDebug"))
```

### **Arguments**

t

Either a sealevel object (e.g. produced by read.sealevel or as.sealevel) or a vector of times. In the former case, time is part of the object, so t may not be given here. In the latter case, tidem needs a way to determine time, so t must be given.

Х

an optional numerical vector holding something that varies with time. This is ignored if t is a sealevel-class object, in which case it is inferred as t["elevation"]].

constituents

an optional vector of strings that name tidal constituents to which the fit is done (see "Details" and "Constituent Naming Convention".)

infer

a list of constituents to be inferred from fitted constituents according to the method outlined in Section 2.3.4 of Foreman (1977) [1]. If infer is NULL, the default, then no such inferences are made. Otherwise, some constituents are computed based on other constituents, instead of being determined by regression at the proper frequency. If provided, infer must be a list containing four elements: name, a vector of strings naming the constituents to be inferred; from, a vector of strings naming the fitted constituents used as the sources for those inferences (these source constituents are added to the regression list, if they are not already there); amp, a numerical vector of factors to be applied to the source amplitudes; and phase, a numerical vector of angles, in degrees, to be subtracted from the source phases. For example, Following Foreman (1997) [1], if any of the name items have already been computed, then the suggested inference is ignored, and the already-computed values are used.

> means that the amplitude of P1 will be set as 0.33093 times the calculated amplitude of K1, and that the P1 phase will be set to the K1 phase, minus an offset of -7.07 degrees. (This example is used in the Foreman (1977) [1] discussion of a Fortran analysis code and also in Pawlowicz et al. (2002) [4] discussion of the T TIDE Matlab code. Rounded to the 0.1mm resolution of values reported in [1] and [2], the tidem results have root-mean-square amplitude difference to Foreman's Appendix 7.3 of 0.06mm; by comparison, the results in Table 1 of Pawlowicz et al. (2002) agree with Foreman's results to RMS difference 0.04mm.)

latitude

if provided, the latitude of the observations. If not provided, tidem will try to infer this from s1.

rc

the value of the coefficient in the Rayleigh criterion.

regress

function to be used for regression, by default 1m, but could be for example r1m from the MASS package.

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

#### **Details**

The tidal constituents to be used in the analysis are specified as follows; see "Constituent Naming Convention".

• Case 1. If constituents is not provided, then the constituent list will be made up of the 69 constituents designated by Foreman as "standard". These include astronomical frequencies and some shallow-water frequencies, and are as follows: c("Z0", "SA", "SSA", "MSM", "MM", "MSF", "MF", "ALP1

- Case 2. If the first item in constituents is the string "standard", then a provisional list is set up as in Case 1, and then the (optional) rest of the elements of constituents are examined, in order. Each of these constituents is based on the name of a tidal constituent in the Foreman (1977) notation. (To get the list, execute data(tidedata) and then execute cat(tideData\$name).) Each named constituent is added to the existing list, if it is not already there. But, if the constituent is preceded by a minus sign, then it is removed from the list (if it is already there). Thus, for example, constituents=c("standard", "-M2", "ST32") would remove the M2 constituent and add the ST32 constituent.
- Case 3. If the first item is not "standard", then the list of constituents is processed as in Case 2, but without starting with the standard list. As an example, constituents=c("K1", "M2") would fit for just the K1 and M2 components. (It would be strange to use a minus sign to remove items from the list, but the function allows that.)

In each of the above cases, the list is reordered in frequency prior to the analysis, so that the results of summary, tidem-method will be in a familiar form.

Once the constituent list is determined, tidem prunes the elements of the list by using the Rayleigh criterion, according to which two constituents of frequencies  $f_1$  and  $f_2$  cannot be resolved unless the time series spans a time interval of at least  $rc/(f_1 - f_2)$ .

Finally, tidem looks in the remaining constituent list to check that the application of the Rayleigh criterion has not removed any of the constituents specified directly in the constituents argument. If any are found to have been removed, then they are added back. This last step was added on 2017-12-27, to make tidem behave the same way as the Foreman (1977) code [1], as illustrated in his Appendices 7.2 and 7.3. (As an aside, his Appendix 7.3 has some errors, e.g. the frequency for the 2SK5 constituent is listed there (p58) as 0.20844743, but it is listed as 0.2084474129 in his Appendix 7.1 (p41). For this reason, the frequency comparison is relaxed to a tol value of 1e-7 in a portion of the oce test suite (see tests/testthat/test\_tidem.R in the source).

A specific example may be of help in understanding the removal of unresolvable constitutents. For example, the data(sealevel) dataset is of length 6718 hours, and this is too short to resolve the full list of constituents, with the conventional (and, really, necessary) limit of rc=1. From Table 1 of [1], this timeseries is too short to resolve the SA constituent, so that SA will not be in the resultant. Similarly, Table 2 of [1] dictates the removal of PI1, S1 and PSI1 from the list. And, finally, Table 3 of [1] dictates the removal of H1, H2, T2 and R2. Also, since Table 3 of [1] indicates that GAM2 gets subsumed into H1, and if H1 is already being deleted in this test case, then GAM2 will also be deleted.

A list of constituent names is created by the following:

```
data(tidedata)
print(tidedata$const$name)
```

The text should include discussion of the (not yet performed) nodal correction treatment.

#### Value

An object of tidem-class, consisting of

constituent number, e.g. 1 for Z0, 1 for SA, etc.

model the regression model

name a vector of constituent names, in non-subscript format, e.g. "M2".

frequency a vector of constituent frequencies, in inverse hours.

amplitude a vector of fitted constituent amplitudes, in metres.

phase a vector of fitted constituent phase. NOTE: The definition of phase is likely to

change as this function evolves. For now, it is phase with respect to the first data

sample.

p a vector containing a sort of p value for each constituent. This is calculated as

the average of the p values for the sine() and cosine() portions used in fitting;

whether it makes any sense is an open question.

#### **Bugs**

- 1. This function is not fully developed yet, and both the form of the call and the results of the calculation may change.
- 2. Nodal correction is not done.
- 3. The reported p value may make no sense at all, and it might be removed in a future version of this function. Perhaps a significance level should be presented, as in the software developed by both Foreman and Pawlowicz.

#### **Constituent Naming Convention**

tidem uses constituent names that follow the convention set by Foreman (1977) [1]. This convention is slightly different from that used in the T-TIDE package of Pawlowicz et al. (2002) [4], with Foreman's UPS1 and M8 becoming UPSI and MS in T-TIDE. As a convenience, tidem converts from these T-TIDE names to the Foreman names, issuing warnings when doing so.

### **Agreement with T\_TIDE results**

The tidem amplitude and phase results, obtained with

are identical the T\_TIDE values listed in Table 1 of Pawlowicz et al. (2002), after rounding amplitude and phase to 4 and 2 digits past the decimal place, to match the format of the table.

#### Author(s)

Dan Kelley

#### References

- 1. Foreman, M. G. G., 1977. Manual for tidal heights analysis and prediction. Pacific Marine Science Report 77-10, Institute of Ocean Sciences, Patricia Bay, Sidney, BC, 58pp.
- 2. Foreman, M. G. G., Neufeld, E. T., 1991. Harmonic tidal analyses of long time series. International Hydrographic Review, 68 (1), 95-108.
- 3. Leffler, K. E. and D. A. Jay, 2009. Enhancing tidal harmonic analysis: Robust (hybrid) solutions. Continental Shelf Research, 29(1):78-88.
- 4. Pawlowicz, Rich, Bob Beardsley, and Steve Lentz, 2002. Classical tidal harmonic analysis including error estimates in MATLAB using T\_TIDE. Computers and Geosciences, 28, 929-937.

### See Also

Other things related to tidem data: [[,tidem-method, [[<-,tidem-method, plot,tidem-method, predict.tidem, summary,tidem-method, tidedata, tidem-class, tidemAstron, tidemVuf

### **Examples**

```
library(oce)
# The demonstration time series from Foreman (1977),
# also used in T_TIDE (Pawlowicz, 2002).
data(sealevelTuktoyaktuk)
tide <- tidem(sealevelTuktoyaktuk)
summary(tide)
# AIC analysis</pre>
```

tidem-class 519

```
extractAIC(tide[["model"]])

# Fake data at M2
t <- seq(0, 10*86400, 3600)
eta <- sin(0.080511401 * t * 2 * pi / 3600)
sl <- as.sealevel(eta)
m <- tidem(sl)
summary(m)</pre>
```

tidem-class

Class to Store Tidal Models

### **Description**

Class to store tidal-constituent models.

#### Author(s)

Dan Kelley

### See Also

```
Other functions that plot oce data: plot,adp-method, plot,adv-method, plot,amsr-method, plot,argo-method, plot, bremen-method, plot, cm-method, plot, coastline-method, plot,ctd-method, plot,gps-method, plot,ladp-method, plot,lisst-method, plot,lobo-method, plot,met-method, plot,odf-method, plot,rsk-method, plot,satellite-method, plot,sealevel-method, plot,section-method, plot,tidem-method, plot,tidem-method, plot,windrose-method, plotProfile, plotScan, plotTS

Other things related to tidem data: [[,tidem-method,[[<-,tidem-method,plot,tidem-method,plot,tidem-method,plot,tidem-method,plot,tidem-method,tidedata,tidemAstron,tidemVuf,tidem
```

tidemAstron

Astronomical Calculations for Tidem

## **Description**

Do some astronomical calculations for tidem. This function is based directly on  $t_astron$  in the  $t_astron$  in the  $t_astron$  matlab package [1].

#### **Usage**

```
tidemAstron(t)
```

# **Arguments**

t

Either a time in POSIXct format (with "UTC" timezone), or an integer. In the second case, it is converted to a time with numberAsPOSIXct(t,tz="UTC"). If t (It is **very** important to use tz="GMT" in constructing t.)

520 tidemVuf

#### Value

A list containing items named astro and ader (see T\_TIDE documentation).

#### Author(s)

Dan Kelley translated this from t\_astron in the T\_TIDE package.

#### References

1. Pawlowicz, Rich, Bob Beardsley, and Steve Lentz, 2002. Classical tidal harmonic analysis including error estimates in MATLAB using T\_TIDE. Computers and Geosciences, 28, 929-937.

#### See Also

```
Other things related to tidem data: [[,tidem-method, [[<-,tidem-method, plot,tidem-method, predict.tidem, summary,tidem-method, tidedata, tidem-class, tidemVuf, tidem
```

### **Examples**

```
tidemAstron(as.POSIXct("2008-01-22 18:50:24"))
```

tidemVuf

Nodal Modulation Calculations for Tidem

## **Description**

Do nodal modulation calculations for tidem. This function is based directly on t\_vuf in the T\_TIDE Matlab package [1].

## Usage

```
tidemVuf(t, j, latitude = NULL)
```

# **Arguments**

t The time in POSIXct format. (It is **very** important to use tz="GMT" in constructing t.)

j Indices of tidal constituents to use.

latitude Optional numerical value containing the latitude in degrees North.

### Value

A list containing items named v, u and f (see the T\_TIDE documentation).

### Author(s)

Dan Kelley translated this from t\_astron from the T\_TIDE package.

titleCase 521

### References

1. Pawlowicz, Rich, Bob Beardsley, and Steve Lentz, 2002. Classical tidal harmonic analysis including error estimates in MATLAB using T\_TIDE. Computers and Geosciences, 28, 929-937.

## See Also

Other things related to tidem data: [[,tidem-method, [[<-,tidem-method, plot,tidem-method, predict.tidem, summary,tidem-method, tidedata, tidem-class, tidemAstron, tidem

# **Examples**

```
tidemVuf(as.POSIXct("2008-01-22 18:50:24"), 43, 45.0)
```

titleCase

Capitalize first letter of each of a vector of words

## **Description**

This is used in making labels for data names in some ctd functions

## Usage

```
titleCase(w)
```

### **Arguments**

W

vector of character strings

### Value

vector of strings patterned on w but with first letter in upper case and others in lower case

toEnu

Rotate acoustic-Doppler data to the enu coordinate system

## Description

Rotate acoustic-Doppler data to the enu coordinate system

## Usage

```
toEnu(x, ...)
```

522 toEnuAdp

### Arguments

x an adp or adv object, i.e. one inheriting from adp-class or adv-class.
... extra arguments that are passed on to toEnuAdp or toEnuAdv.

#### Value

An object of the same type as x, but with velocities in the enu coordinate system

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset, adp-method, summary, adp-method, toEnuAdp, velocityStatistics, xyzToEnuAdp, xyzToEnu

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, velocityStatistics, xyzToEnuAdv, xyzToEnu

toEnuAdp

Convert an ADP Object to ENU Coordinates

## **Description**

Convert an ADP Object to ENU Coordinates

#### **Usage**

```
toEnuAdp(x, declination = 0, debug = getOption("oceDebug"))
```

### **Arguments**

x an adp object, i.e. one inheriting from adp-class.

declination magnetic declination to be added to the heading, to get ENU with N as "true"

north.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

#### Author(s)

Dan Kelley

toEnuAdv 523

#### References

http://www.nortek-as.com/lib/forum-attachments/coordinate-transformation

#### See Also

See read.adp for notes on functions relating to "adp" objects. Also, see beamToXyzAdp and xyzToEnuAdp.

Other things related to adp data: [[,adp-method, [[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

toEnuAdv

Convert an ADV Object to ENU Coordinates

### **Description**

Convert an ADV Object to ENU Coordinates

## Usage

```
toEnuAdv(x, declination = 0, debug = getOption("oceDebug"))
```

### **Arguments**

x An adv object, i.e. one inheriting from adv-class.

declination magnetic declination to be added to the heading, to get ENU with N as "true"

north.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

## Author(s)

Dan Kelley

### References

http://www.nortek-as.com/lib/forum-attachments/coordinate-transformation

524 topoInterpolate

#### See Also

See read.adv for notes on functions relating to "adv" objects. Also, see beamToXyzAdv and xyzToEnuAdv.

Other things related to adv data: [[,adv-method, [[<-,adv-method,adv-class,adv,beamName,beamToXyz,enuToOtherAdv,enuToOther,plot,adv-method,read.adv.nortek,read.adv.sontek.adr,read.adv.sontek.serial,read.adv.sontek.text,read.adv,subset,adv-method,summary,adv-method,toEnu,velocityStatistics,xyzToEnuAdv,xyzToEnu

topo-class

Class to Store Topographic Data

## **Description**

Topographic data may be read with read.topo or assembled with as.topo. Plotting are handled with plot, topo-method and summaries with summary, topo-method. Data retrieval may be done with [[, topo-method and replacement with [[<-, topo-method. The key data, stored within the data slot, are: longititude, latitude, and z.

### Author(s)

Dan Kelley

### See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, windrose-class

Other things related to topo data: [[,topo-method,[[<-,topo-method,as.topo,download.topo,plot,topo-method,read.topo,subset,topo-method,summary,topo-method,topoInterpolate,topoWorld

topoInterpolate

Interpolate Within a Topo Object

### **Description**

Bilinear interpolation is used so that values will vary smoothly within a longitude-latitude grid cell. Note that the sign convention for longitude and latitude must match that in topo.

#### **Usage**

topoInterpolate(longitude, latitude, topo)

topoWorld 525

## **Arguments**

longitude Vector of longitudes (in the same sign convention as used in topo).

Vector of latitudes (in the same sign convention as used in topo).

topo A topo object, i.e. inheriting from topo-class.

## Value

Vector of heights giving the elevation of the earth above means sea level at the indicated location on the earth.

### Author(s)

Dan Kelley

#### See Also

```
Other things related to topo data: [[,topo-method,[[<-,topo-method,as.topo,download.topo,plot,topo-method,read.topo,subset,topo-method,summary,topo-method,topo-class,topoWorld
```

## **Examples**

```
library(oce)
data(topoWorld)
# "The Gully", approx. 400m deep, connects Gulf of St Lawrence with North Atlantic
topoInterpolate(45, -57, topoWorld)
```

topoWorld

Global Topographic Dataset at Half-degree Resolution

# **Description**

Global topographic dataset at half-degree resolution, created by decimating the ETOPO5 dataset. Its longitude ranges from -179.5 to 180, and its latitude ranges from -89.5 to 90. Height is measured in metres above nominal sea level.

The coarse resolution can be a problem in plotting depth contours along with coastlines in regions of steep topography. For example, near the southeast corner of Newfoundland, a 200m contour will overlap a coastline drawn with coastlineWorldFine. The solution in such cases is to download a higher-resolution topography file and create a topo object with read. topo or as. topo.

### Usage

```
data(topoWorld)
```

526 trimString

### Source

The binary ETOPO5 dataset was downloaded in late 2009 from the NOAA website, 'http://www.ngdc.noaa.gov/mgg/glol decoded, decimated from 1/12th degree resolution to 1/2 degree resolution, and passed through matrixShiftLongitude so that longitude is between -180 and 180 degrees.

### See Also

```
Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, wind
```

Other things related to topo data: [[,topo-method,[[<-,topo-method,as.topo,download.topo,plot,topo-method,read.topo,subset,topo-method,summary,topo-method,topo-class,topoInterpolate

# **Examples**

```
## Not run:
library(oce)
data(topoWorld)
par(mfrow=c(2, 1))
plot(topoWorld, location=NULL)
imagep(topoWorld)
## End(Not run)
```

trimString

Remove leading and trailing whitespace from strings

# **Description**

Remove leading and trailing whitespace from strings

### Usage

```
trimString(s)
```

#### **Arguments**

s vector of character strings

### Value

a new vector formed by trimming leading and trailing whitespace from the elements of s.

unabbreviate Year 527

unabbreviateYear

Determine year from various abbreviations

### Description

Various data files may contain various abbreviations for years. For example, 99 refers to 1999, and 8 refers to 2008. Sometimes, even 108 refers to 2008 (the idea being that the "zero" year was 1900). This function deals with the three cases mentioned. It will fail if someone supplies 60, meaning year 2060 as opposed to 1960.

## Usage

```
unabbreviateYear(year)
```

### **Arguments**

year

a year, or vector of years, possibly abbreviated

### Author(s)

Dan Kelley

#### See Also

Other things related to time: ctimeToSeconds, julianCenturyAnomaly, julianDay, numberAsHMS, numberAsPOSIXct, secondsToCtime

### **Examples**

```
fullYear <- unabbreviateYear(c(99, 8, 108))</pre>
```

undriftTime

Correct for drift in instrument clock

### **Description**

It is assumed that the instrument clock matches the real time at the start of the sampling, and that the clock drifts linearly (i.e. is uniformly fast or slow) over the sampling interval. Linear interpolation is used to infer the values of all variables in the data slot. The data length is altered in this process, e.g. a slow instrument clock (positive slowEnd) takes too few samples in a given time interval, so undriftTime will increase the number of data.

### Usage

```
undriftTime(x, slowEnd = 0, tname = "time")
```

528 unduplicateNames

### **Arguments**

x an object of oce-class.

slowEnd number of seconds to add to final instrument time, to get the correct time of the

final sample. This will be a positive number, for a "slow" instrument clock.

tname Character string indicating the name of the time column in the data slot of x.

#### Value

An object of the same class as x, with the data slot adjusted appropriately.

# Author(s)

Dan Kelley

### **Examples**

```
## Not run:
library(oce)
rbr011855 <- read.oce(
   "/data/archive/sleiwex/2008/moorings/m08/pt/rbr_011855/raw/pt_rbr_011855.dat")
d <- subset(rbr011855, time < as.POSIXct("2008-06-25 10:05:00"))
x <- undriftTime(d, 1)  # clock lost 1 second over whole experiment
summary(d)
summary(x)
## End(Not run)</pre>
```

unduplicateNames

Rename duplicated items (used in reading CTD files)

# Description

Rename items to avoid name collision, by appending a 2 to the second occurrence of a name, etc.

## Usage

```
unduplicateNames(names)
```

### **Arguments**

names

Vector of strings with variable names.

## Value

names Vector of strings with numbered variable names.

ungrid 529

### See Also

```
used by read.ctd.sbe.
```

## **Examples**

```
unduplicateNames(c("a", "b", "a", "c", "b"))
```

ungrid

Extract(x, y, z) from(x, y, grid)

# **Description**

Extract the grid points from a grid, returning columns. This is useful for e.g. gridding large datasets, in which the first step might be to use binMean2D, followed by interpBarnes.

### Usage

```
ungrid(x, y, grid)
```

# **Arguments**

x a vector holding the x coordinates of grid.
y a vector holding the y coordinates of grid.
grid a matrix holding the grid.

### Value

A list containing three vectors: x, the grid x values, y, the grid y values, and grid, the grid values.

### Author(s)

Dan Kelley

### **Examples**

```
library(oce)
data(wind)
u <- interpBarnes(wind$x, wind$y, wind$z)
contour(u$xg, u$yg, u$zg)
U <- ungrid(u$xg, u$yg, u$zg)
points(U$x, U$y, col=oce.colorsJet(100)[rescale(U$grid, rlow=1, rhigh=100)], pch=20)</pre>
```

530 unitFromStringRsk

unitFromString

Decode units, from strings

### **Description**

Decode units, from strings

## Usage

```
unitFromString(s)
```

### **Arguments**

S

A string.

### Value

A list of two items: unit which is an expression, and scale, which is a string.

#### See Also

Other functions that interpret variable names and units from headers: ODFNames2oceNames, cnvName2oceName, oceNames2whpNames, oceUnits2whpUnits, unitFromStringRsk, woceNames2oceNames, woceUnit2oceUnit

## **Examples**

```
unitFromString("DB") # dbar
```

unitFromStringRsk

Infer Rsk units from a vector of strings

## **Description**

This is used by read.rsk to infer the units of data, based on strings stored in .rsk files. Lacking a definitive guide to the format of these file, this function was based on visual inspection of the data contained within a few sample files; unusual sensors may not be handled properly.

## Usage

```
unitFromStringRsk(s)
```

### **Arguments**

Vector of character strings, holding the 'units' entry in the channels table of the .rsk database.

unwrapAngle 531

#### Value

List of unit lists.

#### See Also

Other functions that interpret variable names and units from headers: ODFNames2oceNames, cnvName2oceName, oceNames2whpNames, oceUnits2whpUnits, unitFromString, woceNames2oceNames, woceUnit2oceUnit

unwrapAngle

Unwrap an angle that suffers modulo-360 problems

### **Description**

This is mostly used for instrument heading angles, in cases where the instrument is aligned nearly northward, so that small variations in heading (e.g. due to mooring motion) can yield values that swing from small angles to large angles, because of the modulo-360 cut point. The method is to use the cosine and sine of the angle, to construct "x" and "y" values on a unit circle, then to find means and medians of x and y respectively, and finally to use atan2 to infer the angles.

### Usage

```
unwrapAngle(angle)
```

### **Arguments**

angle

an angle (in degrees) that is thought be near 360 degrees, with added noise

### Value

A list with two estimates: mean is based on an arithmetic mean, and median is based on the median. Both are mapped to the range 0 to 360.

### Author(s)

Dan Kelley

## **Examples**

```
library(oce)
true <- 355
a <- true + rnorm(100, sd=10)
a <- ifelse(a > 360, a - 360, a)
a2 <- unwrapAngle(a)
par(mar=c(3, 3, 5, 3))
hist(a, breaks=360)
abline(v=a2$mean, col="blue", lty="dashed")
abline(v=true, col="blue")</pre>
```

532 usrLonLat

```
mtext("true (solid)\n estimate (dashed)", at=true, side=3, col="blue")
abline(v=mean(a), col="red")
mtext("mean", at=mean(a), side=3, col="red")
```

useHeading

Replace the Heading for One Instrument With That of Another

# Description

Replace the heading angles in one oce object with that from another, possibly with a constant adjustment.

## Usage

```
useHeading(b, g, add = 0)
```

## **Arguments**

b	object holding data from an instrument whose heading is bad, but whose other data are good.
g	object holding data from an instrument whose heading is good, and should be interpolated to the time base of b.
add	an angle, in degrees, to be added to the heading.

#### Value

A copy of b, but with b\$data\$heading replaced with heading angles that result from linear interpolation of the headings in g, and then adding the angle add.

### Author(s)

Dan Kelley

usrLonLat

Calculate lon-lat coordinates of plot-box trace

## **Description**

Trace along the plot box, converting from xy coordinates to lonlat coordinates. The results are used by mapGrid and mapAxis to ignore out-of-frame grid lines and axis labels.

### Usage

```
usrLonLat(n = 25, debug = getOption("oceDebug"))
```

utm2lonlat 533

### Arguments

n

number of points to check along each side of the plot box

debug

an integer specifying whether debugging information is to be printed during the processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by specifying higher debug values.

### **Details**

Note: this procedure does not work for projections that have trouble inverting points that are "off the globe". For this reason, this function examines .Projection()\$projection and if it contains the string "wintri", then the above-stated procedure is skipped, and the return value has each of the numerical quantities set to NA, and ok set to FALSE.

### Value

a list containing lonmin, lonmax, latmin, latmax, and ok; the last of which indicates whether at least one point on the plot box is invertible. Note that longitude are expressed in the range from -180 to 180 degrees.

#### Author(s)

Dan Kelley

#### See Also

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, utm2lonlat

utm2lonlat

Convert UTM to Longitude and Latitude

# Description

Convert UTM to Longitude and Latitude

### Usage

```
utm2lonlat(easting, northing, zone = 1, hemisphere = "N", km = FALSE)
```

534 utm2lonlat

# **Arguments**

easting easting coordinate (in km or m, depending on value of km). Alternatively, a list

containing items named easting, northing, and zone, in which case these are taken from the list and the arguments named northing, zone and are ignored.

northing northing coordinate (in km or m, depending on value of km).

zone UTM zone

hemisphere indication of hemisphere; "N" for North, anything else for South.

km logical value indicating whether easting and northing are in kilometers or

meters.

#### Value

A list containing longitude and latitude.

### Author(s)

Dan Kelley

#### References

http://en.wikipedia.org/wiki/Universal\_Transverse\_Mercator\_coordinate\_system, downloaded May 31, 2014.

#### See Also

lonlat2utm does the inverse operation. For general projections and their inverses, use lonlat2map and map2lonlat.

Other functions related to maps: lonlat2map, lonlat2utm, map2lonlat, mapArrows, mapAxis, mapContour, mapDirectionField, mapGrid, mapImage, mapLines, mapLocator, mapLongitudeLatitudeXY, mapPlot, mapPoints, mapPolygon, mapScalebar, mapText, mapTissot, oceCRS, shiftLongitude, usrLonLat

### **Examples**

```
library(oce)
## Cape Split, in the Minas Basin of the Bay of Fundy
utm2lonlat(852863, 5029997, 19)
```

vectorShow 535

vectorShow	Show some values from a vector

# Description

This is similar to str, but it shows data at the first and last of the vector, which can be quite helpful in debugging.

# Usage

```
vectorShow(v, msg, digits = 5, n = 2L)
```

# Arguments

V	the vector.
msg	a message to show, introducing the vector. If not provided, then a message is created from $\boldsymbol{v}$ .
digits	for numerical values of v, this is the number of digits to use, in formatting the numbers with format; otherwise, digits is ignored.
n	number of elements to at start and end. If n is negative, then all the elements are shown.

# Value

A string, suitable for using in cat or oceDebug.

## Author(s)

Dan Kelley

velocityStatistics Report Statistics of adp or adv Velocities

# Description

Report statistics of ADP or ADV velocities, such as means and variance ellipses.

# Usage

```
velocityStatistics(x, control, ...)
```

536 velocityStatistics

## Arguments

an adp or adv object, i.e. one inheriting from adp-class or adv-class.
 An optional list used to specify more information. This is presently ignored for adv objects. For adp objects, if control\$bin is an integer, it is taken as the bin to be selected (otherwise, an average across bins is used).
 additional arguments that are used in the call to mean.

#### Value

A list containing items the major and minor axes of the covariance ellipse (ellipseMajor and ellipseMinor), the angle of the major axis anticlockwise of the horizontal axis (ellipseAngle), and the x and y components of the mean velocity (uMean and vMean).

### Author(s)

Dan Kelley

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot, adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, xyzToEnuAdp, xyzToEnu

Other things related to adv data: [[,adv-method, [[<-,adv-method,adv-class,adv,beamName,beamToXyz,enuToOtherAdv,enuToOther,plot,adv-method,read.adv.nortek,read.adv.sontek.adr,read.adv.sontek.serial,read.adv.sontek.text,read.adv,subset,adv-method,summary,adv-method,toEnuAdv,toEnu,xyzToEnuAdv,xyzToEnu

## **Examples**

```
library(oce)
data(adp)
a <- velocityStatistics(adp)
print(a)
t <- seq(0, 2*pi, length.out=100)
theta <- a$ellipseAngle * pi / 180
y <- a$ellipseMajor * cos(t) * sin(theta) + a$ellipseMinor * sin(t) * cos(theta)
x <- a$ellipseMajor * cos(t) * cos(theta) - a$ellipseMinor * sin(t) * sin(theta)
plot(adp, which="uv+ellipse+arrow")
lines(x, y, col='blue', lty="dashed", lwd=5)
arrows(0, 0, a$uMean, a$vMean, lwd=5, length=1/10, col='blue', lty="dashed")</pre>
```

webtide 537

webtide	Get a Tidal Prediction from a WebTide Database
---------	--

#### **Description**

Get a tidal prediction from a WebTide database. There are two distinct cases.

Case 1: action="map". In this case, if plot is FALSE, a list is returned, containing all the nodes in the selected database, along with all the latitudes and longitudes. This value is also returned (silently) if plot is true, but in that case, a plot is drawn to indicate the node locations. If latitude and longitude are given, then the node nearest that spot is indicated on the map; otherwise, if node is given, then the location of that node is indicated. There is also a special case: if node is negative and interactive() is TRUE, then locator is called, and the node nearest the spot where the user clicks the mouse is indicated in the plot and in the return value.

Case 2: action="predict". If plot is FALSE, then a list is returned, indicating time, predicted elevation, velocity components u and v, node number, the name of the basedir, and the region. If plot is TRUE, this list is returned silently, and time-series plots are drawn for elevation, u, and v.

Naturally, webtide will not work unless WebTide has been installed on the computer.

### Usage

```
webtide(action = c("map", "predict"), longitude, latitude, node, time,
basedir = getOption("webtide"), region = "nwatl", plot = TRUE, tformat,
debug = getOption("oceDebug"), ...)
```

#### **Arguments**

action An indication of the action, either action="map" to draw a map or action="predict"

to get a prediction; see 'Details'.

longitude, latitude

optional location at which prediction is required (ignored if node is given).

node optional integer relating to a node in the database. If node is given, then neither

latitude nor longitude may be given. If node is positive, then specifies indicates the node. If it is negative, locator is called so that the user can click

(once) on the map, after which the node is displayed on the map.

time a vector of times at which prediction is to be made. If not supplied, this will be

the week starting at the present time, incrementing by 15 minutes.

basedir directory containing the WebTide application.

region database region, given as a directory name in the WebTide directory. For exam-

ple, h3o is for Halifax Harbour, nwatl is for the northwest Atlantic, and sshelf

is for the Scotian Shelf and Gulf of Maine.

plot boolean indicating whether to plot.

tformat optional argument passed to oce.plot.ts, for plot types that call that function.

(See strptime for the format used.)

538 webtide

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

... optional arguments passed to plotting functions. A common example is to set

xlim and ylim, to focus a map region.

#### Value

If action="map" the return value is a list containing the index of the nearest node, along with the latitude and longitude of that node. If plot is FALSE, this value is returned invisibly.

If action="predict", the return value is a list containing a vector of times (time), as well as vectors of the predicted elevation in metres and the predicted horizontal components of velocity, u and v, along with the node number, and the basedir and region as supplied to this function. If plot is FALSE, this value is returned invisibly.

a list containing node, longitude and latitude. If no node was provided to webtide then this list will cover the whole set of nodes in the WebTide model; otherwise, it will be just the node that was requested.

#### Caution

WebTide is not an open-source application, so the present function was designed based on little more than guesses about the WebTide file structure. Users should be on the lookout for odd results.

### Author(s)

Dan Kelley

#### Source

The WebTide software may be downloaded for free at the Department of Fisheries and Oceans (Canada) website at http://www.bio.gc.ca/science/research-recherche/ocean/webtide/index-en.php (checked February 2016 and May 2017).

### **Examples**

```
## Not run:
## needs WebTide at the system level
library(oce)
## 1. prediction at Halifax NS
longitude <- -63.57
latitude <- 44.65
prediction <- webtide("predict", longitude=longitude, latitude=latitude)
mtext(sprintf("prediction at %fN %fE", latitude, longitude), line=0.75, side=3)
## 2. map
webtide(lon=-63.57,lat=44.65,xlim=c(-64,-63),ylim=c(43.0,46))
## End(Not run)</pre>
```

wind 539

wind	Wind dataset

### **Description**

Wind data inferred from Figure 5 of Koch et al. (1983), provided to illustrate the interpBarnes function. Columns wind\$x and wind\$y are location, while wind\$z is the wind speed, in m/s.

#### References

S. E. Koch and M. DesJardins and P. J. Kocin, 1983. "An interactive Barnes objective map analysis scheme for use with satellite and conventional data," *J. Climate Appl. Met.*, vol 22, p. 1487-1503.

#### See Also

Other datasets provided with oce: adp, adv, argo, cm, coastlineWorld, colors, ctdRaw, ctd, echosounder, landsat, lisst, lobo, met, rsk, sealevelTuktoyaktuk, sealevel, section, topoWorld

window.oce

Window an Oce Object by Time or Distance

# **Description**

Windows x on either time or distance, depending on the value of which. In each case, values of start and end may be integers, to indicate a portion of the time or distance range. If which is "time", then the start and end values may also be provided as POSIX times, or character strings indicating times (in time zone given by the value of getOption("oceTz")). Note that subset may be more useful than this function.

## Usage

```
## S3 method for class 'oce'
window(x, start = NULL, end = NULL, frequency = NULL,
  deltat = NULL, extend = FALSE, which = c("time", "distance"),
  indexReturn = FALSE, debug = getOption("oceDebug"), ...)
```

### **Arguments**

X	an oce object.

start the start time (or distance) of the time (or space) region of interest. This may be

a single value or a vector.

end the end time (or distance) of the time (or space) region of interest. This may be

a single value or a vector.

frequency not permitted yet.

540 windrose-class

deltat not permitted yet extend not permitted yet

which string containing the name of the quantity on which sampling is done. Possi-

bilities are "time", which applies the windowing on the time entry of the data slot, and "distance", for the distance entry (for those objects, such as adp,

that have this entry).

indexReturn boolean flag indicating whether to return a list of the "kept" indices for the time

entry of the data slot, as well as the timeSlow entry, if there is one.. Either of

these lists will be NULL, if the object lacks the relevant items.

debug a flag that turns on debugging.

... ignored

#### Value

Normally, this is new oce object. However, if indexReturn=TRUE, the return value is two-element list containing items named index and indexSlow, which are the indices for the time entry of the data slot (and the timeSlow, if it exists).

#### Author(s)

Dan Kelley

#### See Also

subset provides more flexible selection of subsets.

## **Examples**

```
library(oce)
data(adp)
plot(adp)
early <- window(adp, start="2008-06-26 00:00:00", end="2008-06-26 12:00:00")
plot(early)
bottom <- window(adp, start=0, end=20, which="distance")
plot(bottom)</pre>
```

windrose-class

Class to Store Windrose Data

## **Description**

Windrose objects store statistical information about winds, mainly for plotting as "wind rose" plots (see plot, windrose-method. There is no reading method, because there is no standard way to store wind data in files; instead, as.windrose is provided to construct windrose objects. Data elements may be retrieved with [[,windrose-method or replaced with [[<-,windrose-method. Data summaries are provided with summary, windrose-method.

woceNames2oceNames 541

### See Also

Other classes provided by oce: adp-class, adv-class, argo-class, bremen-class, cm-class, coastline-class, ctd-class, echosounder-class, lisst-class, lobo-class, met-class, oce-class, odf-class, rsk-class, sealevel-class, section-class, topo-class

Other things related to windrose data: [[,windrose-method, [[<-,windrose-method, as.windrose, plot,windrose-method, summary,windrose-method

woceNames2oceNames

Translate WOCE Data Names to Oce Data Names

### **Description**

Translate WOCE-style names to oce names, using gsub to match patterns. For example, the pattern "CTDOXY.\*" is taken to mean oxygen.

## Usage

woceNames2oceNames(names)

## Arguments

names

vector of strings holding WOCE-style names.

#### Value

vector of strings holding oce-style names.

### Author(s)

Dan Kelley

## References

Several online sources list WOCE names. An example is https://geo.h2o.ucsd.edu/documentation/manuals/pdf/90\_1/chap4.pdf

## See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceUnit2oceUnit, write.ctd

Other functions that interpret variable names and units from headers: ODFNames2oceNames, cnvName2oceName, oceNames2whpNames, oceUnits2whpUnits, unitFromStringRsk, unitFromString, woceUnit2oceUnit

542 write.ctd

woceUnit2oceUnit

Translate WOCE units to oce units

## **Description**

Translate WOCE-style units to oce units.

## Usage

```
woceUnit2oceUnit(woceUnit)
```

## **Arguments**

woceUnit

string holding a WOCE unit

### Value

expression in oce unit form

## Author(s)

Dan Kelley

## See Also

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot,ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset,ctd-method, summary,ctd-method, woceNames2oceNames, write.ctd

Other functions that interpret variable names and units from headers: ODFNames2oceNames, cnvName2oceName, oceNames2whpNames, oceUnits2whpUnits, unitFromStringRsk, unitFromString, woceNames2oceNames

write.ctd

Write a CTD Data Object as a CSV File

## **Description**

Writes a comma-separated file containing the data frame stored in the data slot of the first argument. The file is suitable for reading with a spreadsheet, or with read.csv. This output file will contain some of the metadata in x, if metadata is TRUE.

## Usage

```
write.ctd(object, file, metadata = TRUE, flags = TRUE, format = "csv")
```

write.ctd 543

## **Arguments**

object A ctd object, i.e. one inheriting from ctd-class.

file Either a character string (the file name) or a connection. If not provided, file

defaults to stdout().

metadata a logical value indicating whether to put some selected metadata elements at the

start of the output file.

flags a logical value indicating whether to show data-quality flags as well as data.

format string indicating the format to use. This may be "csv" for a simple CSV for-

mat, or "whp" for the World Hydrographic Program format, described at [1] and

exemplified at [2].

## Author(s)

Dan Kelley

#### References

- 1. https://www.nodc.noaa.gov/woce/woce\_v3/wocedata\_1/whp/exchange/exchange\_format\_desc.htm
- 2. https://www.nodc.noaa.gov/woce/woce\_v3/wocedata\_1/whp/exchange/example\_ct1.csv

## See Also

The documentation for ctd-class explains the structure of CTD objects.

Other things related to ctd data: [[,ctd-method, [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit

### **Examples**

```
## Not run:
library(oce)
data(ctd)
write.ctd(ctd, "ctd.csv")
d <- read.csv("ctd.csv")
plot(as.ctd(d$salinity, d$temperature, d$pressure))
## End(Not run)</pre>
```

544 xyzToEnuAdp

xyzToEnu	Convert acoustic-Doppler data from xyz coordinates to enu coordinates

## **Description**

Convert acoustic-Doppler data from xyz coordinates to enu coordinates

## **Usage**

```
xyzToEnu(x, ...)
```

## **Arguments**

x an adp or adv object, i.e. one inheriting from adp-class or adv-class.
... extra arguments that are passed on to xyzToEnuAdp or xyzToEnuAdv.

## Value

An object of the same type as x, but with velocities in east-north-up coordinates instead of xyz coordinates.

### See Also

Other things related to adp data: [[,adp-method,[[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot, adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset, adv-method, summary, adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv

xyzToEnuAdp

Convert ADP From XYZ to ENU Coordinates

## **Description**

Convert ADP velocity components from a xyz-based coordinate system to an enu-based coordinate system, by using the instrument's recording of heading, pitch, and roll.

### Usage

```
xyzToEnuAdp(x, declination = 0, debug = getOption("oceDebug"))
```

xyzToEnuAdp 545

### **Arguments**

x An adp object, i.e. one inheriting from adp-class.

declination magnetic declination to be added to the heading after "righting" (see below), to

get ENU with N as "true" north.

debug an integer specifying whether debugging information is to be printed during the

processing. This is a general parameter that is used by many oce functions. Generally, setting debug=0 turns off the printing, while higher values suggest that more information be printed. If one function calls another, it usually reduces the value of debug first, so that a user can often obtain deeper debugging by

specifying higher debug values.

### **Details**

The first step is to convert the (x,y,z) velocity components (stored in the three columns of x[["v"]][,,1:3]) into what RDI [1, pages 11 and 12] calls "ship" (or "righted") components. For example, the z coordinate, which may point upwards or downwards depending on instrument orientation, is mapped onto a "mast" coordinate that points more nearly upwards than downward. The other ship coordinates are called "starboard" and "forward", the meanings of which will be clear to mariners. Once the (x,y,z) velocities are converted to ship velocities, the orientation of the instrument is extracted from heading, pitch, and roll vectors stored in the object. These angles are defined differently for RDI and Sontek profilers.

The code handles every case individually, based on the table given below. The table comes from Clark Richards, a former PhD student at Dalhousie University [2], who developed it based on instrument documentation, discussion on user groups, and analysis of measurements acquired with RDI and Sontek acoustic current profilers in the SLEIWEX experiment. In the table, (X, Y, Z) denote instrument-coordinate velocities, (S, F, M) denote ship-coordinate velocities, and (H, P, R) denote heading, pitch, and roll.

Case	Mfr.	Instr. Orient.	H	P	R	$\mathbf{S}$	$\mathbf{F}$	M	
1	RDI	ADCP	up	Н	arctan(tan(P)*cos(R))	R	-X	Y	-Z
2	RDI	ADCP	down	Н	arctan(tan(P)*cos(R))	-R	X	Y	Z
3	Nortek	ADP	up	H-90	R	-P	X	Y	Z
4	Nortek	ADP	down	H-90	R	-P	X	-Y	-Z
5	Sontek	ADP	up	H-90	-P	-R	X	Y	Z
6	Sontek	ADP	down	H-90	-P	-R	X	Y	Z
7	Sontek	PCADP	up	H-90	R	-P	X	Y	Z
8	Sontek	PCADP	down	H-90	R	-P	X	Y	$\mathbf{Z}$

Finally, a standardized rotation matrix is used to convert from ship coordinates to earth coordinates. As described in the RDI coordinate transformation manual [1, pages 13 and 14], this matrix is based on sines and cosines of heading, pitch, and roll If CH and SH denote cosine and sine of heading (after adjusting for declination), with similar terms for pitch and roll using second letters P and R, the rotation matrix is

```
rbind(c( CH*CR + SH*SP*SR, SH*CP, CH*SR - SH*SP*CR), c(-SH*CR
+ CH*SP*SR, CH*CP, -SH*SR - CH*SP*CR), c(-CP*SR, SP, CP*CR))
```

546 xyzToEnuAdv

This matrix is left-multiplied by a matrix with three rows, the top a vector of "starboard" values, the middle a vector of "forward" values, and the bottom a vector of "mast" values. Finally, the columns of data\$v[,,1:3] are filled in with the result of the matrix multiplication.

### Value

An object with datav[,,1:3] altered appropriately, and metadatace.orientation changed from xyz to enu.

## Author(s)

Dan Kelley and Clark Richards

### References

- 1. RD Instruments, 1998. *ADCP Coordinate Transformation, formulas and calculations*. P/N 951-6079-00 (July 1998).
- 2. Clark Richards, 2012, PhD Dalhousie University Department of Oceanography.

#### See Also

Other things related to adp data: [[,adp-method, [[<-,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnu

xyzToEnuAdv

Convert an ADP from XYZ to ENU Coordinates

## **Description**

Convert ADV velocity components from a xyz-based coordinate system to an enu-based coordinate system.

## Usage

```
xyzToEnuAdv(x, declination = 0, cabled = FALSE, horizontalCase,
  sensorOrientation, debug = getOption("oceDebug"))
```

xyzToEnuAdv 547

### **Arguments**

x An adv object, i.e. one inheriting from adv-class.

declination magnetic declination to be added to the heading, to get ENU with N as "true"

north.

cabled boolean value indicating whether the sensor head is connected to the pressure

case with a cable. If cabled=FALSE, then horizontalCase is ignored. See

"Details".

horizontalCase optional boolean value indicating whether the sensor case is oriented horizon-

tally. Ignored unless cabled is TRUE. See "Details".

sensorOrientation

optional string indicating the direction in which the sensor points. The value, which must be "upward" or "downward", over-rides the value of orientation, in the metadata slot, which will have been set by read.adv, provided that the

data file contained the full header. See "Details".

debug a flag that, if non-zero, turns on debugging. Higher values yield more extensive

debugging.

### **Details**

The coordinate transformation is done using the heading, pitch, and roll information contained within x. The algorithm is similar to that used for Teledyne/RDI ADCP units, taking into account the different definitions of heading, pitch, and roll as they are defined for the velocimeters.

Generally, the transformation must be done on a time-by-time basis, which is a slow operation. However, this function checks whether the vectors for heading, pitch and roll, are all of unit length, and in that case, the calculation is altered, resulting in shorter execution times. Note that the angles are held in (data\$time\$low, data\$heading\$low, ...) for Nortek instruments and (data\$time, data\$heading, ...) for Sontek instruments.

Since the documentation provided by instrument manufacturers can be vague on the coordinate transformations, the method used here had to be developed indirectly. (This is in contrast to the RDI ADCP instruments, for which there are clear instructions.) documents that manufacturers provide. If results seem incorrect (e.g. if currents go east instead of west), users should examine the code in detail for the case at hand. The first step is to set debug to 1, so that the processing will print a trail of processing steps. The next step should be to consult the table below, to see if it matches the understanding (or empirical tests) of the user. It should not be difficult to tailor the code, if needed.

The code handles every case individually, based on the table given below. The table comes from Clark Richards, a former PhD student at Dalhousie University [2], who developed it based on instrument documentation, discussion on user groups, and analysis of measurements acquired with Nortek and Sontek velocimeters in the SLEIWEX experiment.

The column labelled "Cabled" indicates whether the sensor and the pressure case are connected with a flexible cable, and the column labelled "H.case" indicates whether the pressure case is oriented horizontally. These two properties are not discoverable in the headers of the data files, and so they must be supplied with the arguments cabled and horizontalCase. The source code refers to the information in this table by case numbers. (Cases 5 and 6 are not handled.) Angles are abbreviated as follows:: heading "H," pitch "P," and roll "R". Entries X, Y and Z refer to instrument coordinates of the same names. Entries S, F and M refer to so-called ship coordinates starboard, forward, and

mast; it is these that are used together with a rotation matrix to get velocity components in the east, north, and upward directions.

Case	Mfr.	Instr.	Cabled	H. case	Orient.	Н	P	R	$\mathbf{S}$	$\mathbf{F}$	M
1	Nortek	vector	no	-	up	H-90	R	-P	X	-Y	-Z
2	Nortek	vector	no	-	down	H-90	R	-P	X	Y	Z
3	Nortek	vector	yes	yes	up	H-90	R	-P	X	Y	Z
4	Nortek	vector	yes	yes	down	H-90	R	P	X	-Y	-Z
5	Nortek	vector	yes	no	up	-	-	-	-	-	-
6	Nortek	vector	yes	no	down	-	-	-	-	-	-
7	Sontek	adv	-	-	up	H-90	R	-P	X	-Y	-Z
8	Sontek	adv	=	-	down	H-90	R	-P	X	Y	Z

## Author(s)

Dan Kelley, in collaboration with Clark Richards

### References

- 1. http://www.nortek-as.com/lib/forum-attachments/coordinate-transformation
- 2. Clark Richards, 2012, PhD Dalhousie University Department of Oceanography.

### See Also

See read.adv for notes on functions relating to adv objects.

Other things related to adv data: [[,adv-method, [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot,adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset,adv-method, summary,adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnu

[[,adp-method	Extract Parts of an ADP Object In addition to the usual extraction of elements by name, some shortcuts are also provided, e.g. $x[["u1"]]$ retrieves $v[,1]$ , and similarly for the other velocity components. The $a$ and $q$ data can be retrieved in raw form or numeric form (see examples). The coordinate system may be retrieved with e.g.
	x[["coordinate"]].

# Description

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ...

[[,adp-method 549

method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'adp'
x[[i, j, ...]]
```

## **Arguments**

x An adp object, i.e. one inheriting from adp-class.
 i Character string indicating the name of item to extract.
 j Optional additional information on the i item.
 ... Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

## Author(s)

Dan Kelley

### See Also

```
Other functions that extract parts of oce objects: [[,adv-method,[[,amsr-method,[[,argo-method, [[,bremen-method,[[,ctd-method,[[,echosounder-method, [[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method,
```

550 [[,adv-method

```
[[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method,
[[,topo-method,[[,windrose-method,[[<-,adv-method</pre>
```

Other things related to adp data: [[<-,adp-method, adp-class, adpEnsembleAverage, adp, as.adp, beamName, beamToXyzAdp, beamToXyzAdv, beamToXyz, beamUnspreadAdp, binmapAdp, enuToOtherAdp, enuToOther, plot,adp-method, read.ad2cp, read.adp.nortek, read.adp.rdi, read.adp.sontek.serial, read.adp.sontek, read.adp, read.aquadoppHR, read.aquadoppProfiler, read.aquadopp, subset,adp-method, summary,adp-method, toEnuAdp, toEnu, velocityStatistics, xyzToEnuAdp, xyzToEnu

## **Examples**

```
data(adp)
# Tests for beam 1, distance bin 1, first 5 observation times
adp[["v"]][1:5,1,1]
adp[["a"]][1:5,1,1]
adp[["a", "numeric"]][1:5,1,1]
as.numeric(adp[["a"]][1:5,1,1]) # same as above
```

[[,adv-method

Extract Parts of an ADV Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'adv' x[[i, j, ...]]
```

### **Arguments**

- x An adv object, i.e. one inheriting from adv-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- ... Optional additional information (ignored).

[[,adv-method 551

### Details of the specialized adv method

In addition to the usual extraction of elements by name, some shortcuts are also provided, e.g. u1 retrieves v[,1], and similarly for the other velocity components. The a and q data can be retrieved in raw form or numeric form; see "Examples".

It is also worth noting that heading, pitch, etc. may be stored in "slow" form in the object (e.g. in headingSlow within the data slot). In that case, accessing by full name, e.g. x[["headingSlow"]] retrieves the item as expected, but x[["heading"]] interpolates to the faster timescale, using approx(timeSlow, headingSlow, time).

## Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,amsr-method,[[,argo-method, [[,bremen-method,[[,cm-method,[[,coastline-method,[[,ctd-method,[[,echosounder-method, [[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method,[[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method,[[,topo-method,[[,windrose-method,[[<-,adv-method]]]]]]]
```

Other things related to adv data: [[<-,adv-method, adv-class, adv, beamName, beamToXyz, enuToOtherAdv, enuToOther, plot,adv-method, read.adv.nortek, read.adv.sontek.adr, read.adv.sontek.serial, read.adv.sontek.text, read.adv, subset,adv-method, summary,adv-method, toEnuAdv, toEnu, velocityStatistics, xyzToEnuAdv, xyzToEnu

552 [[,amsr-method

## **Examples**

```
data(adv)
head(adv[["q"]])  # in raw form
head(adv[["q", "numeric"]]) # in numeric form
```

[[,amsr-method

Extract Something From an amsr Object

## **Description**

Extract something from the metadata or data slot of an amsr-class object.

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

#### Usage

```
## S4 method for signature 'amsr'
x[[i, j, ...]]
```

## **Arguments**

X	An amsr object, i.e. one inheriting from amsr-class.
i	Character string indicating the name of item to extract.
j	Optional additional information on the i item.
	Optional additional information (ignored).

### **Details**

Partial matches for i are permitted for metadata, and j is ignored for metadata.

Data within the data slot may be found directly, e.g. j="SSTDay" will yield sea-surface temperature in the daytime satellite, and j="SSTNight" is used to access the nighttime data. In addition, j="SST" yields an average of the night and day values (using just one of these, if the other is missing). This scheme works for all the data stored in amsr objects, namely: time, SST, LFwind, MFwind, vapor, cloud and rain. In each case, the default is to calculate values in scientific units, unless j="raw", in which case the raw data are returned.

The "raw" mode can be useful in decoding the various types of missing value that are used by amsr data, namely as.raw(255) for land, as.raw(254) for a missing observation, as.raw(253) for a bad observation, as.raw(252) for sea ice, or as.raw(251) for missing SST due to rain

[[,amsr-method 553

or missing water vapour due to heavy rain. Note that something special has to be done for e.g. d[["SST", "raw"]] because the idea is that this syntax (as opposed to specifying "SSTDay") is a request to try to find good data by looking at both the Day and Night measurements. The scheme employed is quite detailed. Denote by "A" the raw value of the desired field in the daytime pass, and by "B" the corresponding value in the nighttime pass. If either A or B is 255, the code for land, then the result will be 255. If A is 254 (i.e. there is no observation), then B is returned, and the reverse holds also. Similarly, if either A or B equals 253 (bad observation), then the other is returned. The same is done for code 252 (ice) and code 251 (rain).

### Value

In all cases, the returned value is a matrix with with NA values inserted at locations where the raw data equal as.raw(251:255), as explained in "Details".

## Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

## Author(s)

Dan Kelley

## See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,argo-method, [[,bremen-method,[[,cm-method,[[,castline-method,[[,ctd-method,[[,echosounder-method, [[,g1sst-method,[[,gps-method,[[,lisst-method,[[,lobo-method,[[,met-method, [[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method, [[,topo-method,[[,windrose-method,[[,-adv-method]]]]]]]]
```

554 [[,argo-method

## **Examples**

```
## Not run:
# Show a daytime SST image, along with an indication of whether
# the NA values are from rain.
library(oce)
earth <- read.amsr("f34_20160102v7.2.gz")
fclat <- subset(earth , 35 <= latitude & latitude <= 55)
fc <- subset(fclat , -70 <= longitude & longitude <= -30)
par(mfrow=c(2, 1))
plot(fc, "SSTDay")
rainy <- fc[["SSTDay", "raw"]] == as.raw(0xfb)
lon <- fc[["longitude"]]
lat <- fc[["latitude"]]
asp <- 1 / cos(pi*mean(lat)/180)
imagep(lon, lat, rainy, asp=asp)
mtext("red: too rainy to sense SSTDay")
## End(Not run)</pre>
```

[[,argo-method

Extract Something From an Argo Object

## Description

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### Usage

```
## S4 method for signature 'argo' x[[i, j, ...]]
```

### **Arguments**

- x An argo object, i.e. one inheriting from argo-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- ... Optional additional information (ignored).

[[,argo-method 555

## Details of the specialized argo method

• If i is the string "SA", then the method computes Absolute Salinity using gsw\_SA\_from\_SP, using salinityAdjusted (etc) if available in the data slot of x, otherwise using salinity.

- Similarly, for "CT", Conservative Temperature is returned.
- Otherwise, if i is in the data slot of x, then it is returned, otherwise if it is in the metadata slot, then that is returned, otherwise NULL is returned.

## Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

## See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,bremen-method,[[,cm-method,[[,coastline-method,[[,ctd-method,[[,echosounder-method, [[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method, [[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method, [[,topo-method,[[,windrose-method,[[,-adv-method]]],topo-method,[[,windrose-method,[[,-adv-method]]]])

Other things related to argo data: [[<-,argo-method, argo-class, argoGrid, argoNames2oceNames, argo, as.argo, handleFlags, argo-method, plot,argo-method, read.argo, subset,argo-method,
```

### **Examples**

```
data(argo)
dim(argo[['temperature']])
```

summary, argo-method

556 [[,bremen-method

[[,bremen-method

Extract Something From a Bremen Object

## Description

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'bremen'
x[[i, j, ...]]
```

### **Arguments**

x A bremen object, i.e. one inheriting from bremen-class.

i Character string indicating the name of item to extract.

j Optional additional information on the i item.

... Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

[[,cm-method 557

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method,[[,cm-method,[[,castline-method,[[,ctd-method,[[,echosounder-method, [[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method, [[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method, [[,topo-method,[[,windrose-method,[[,-,adv-method]]]]]]]]
```

Other things related to bremen data: [[<-,bremen-method, bremen-class, plot,bremen-method, read.bremen, summary,bremen-method

[[,cm-method

Extract Something From a CM Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

## Usage

```
## S4 method for signature 'cm' x[[i, j, ...]]
```

## Arguments

- x A cm object, i.e. one inheriting from cm-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- . . . Optional additional information (ignored).

558 [[,coastline-method

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method,[[,bremen-method,[[,coastline-method,[[,ctd-method,[[,echosounder-method, [[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method, [[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method, [[,topo-method,[[,windrose-method,[[,-adv-method]]]]]]]]
```

Other things related to cm data: [[<-, cm-method, as.cm, cm-class, cm, plot, cm-method, read.cm, subset, cm-method, summary, cm-method

[[,coastline-method ]

Extract Something From a Coastline Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

[[,coastline-method 559

## Usage

```
## S4 method for signature 'coastline' x[[i, j, ...]]
```

## Arguments

X	A coastline object, i.e. one inheriting from coastline-class.
i	Character string indicating the name of item to extract.
j	Optional additional information on the i item.
	Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

## See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [,tidem-method, [[,tidem-method, [tidem-method, [[,tidem-method, [[,tidem-method, [[,tidem-method, [tidem-method, [[,tidem-method, [tidem-method, ```

560 [[,ctd-method

[[,ctd-method

Extract Parts of a CTD Object

### **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'ctd'
x[[i, j, ...]]
```

### **Arguments**

x A ctd object, i.e. one inheriting from ctd-class.

i Character string indicating the name of item to extract.

j Optional additional information on the i item.

... Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

[[,ctd-method 561

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

### Details of the specialized ctd method

Some uses of [[,ctd-method involve direct retrieval of items within the data slot of the ctd object, while other uses involve calculations based on items in that data slot. For an example, all ctd objects should hold an item named temperature in the data slot, so for example x[["temperature"]] will retrieve that item. By contrast, x[["sigmaTheta"]] is taken to be a request to compute  $\sigma_{\theta}$ , and so it yields a call to swTheta(x) even if the data slot of x might happen to contain an item named theta. This can be confusing at first, but it tends to lead to fewer surprises in everyday work, for otherwise the user would be forced to check the contents of any ctd object under analysis, to determine whether that item will be looked up or computed. Nothing is lost in this scheme, since the data within the object are always accessible with oceGetData.

It should be noted that the accessor is set up to retrieve quantities in conventional units. For example, read.ctd.sbe is used on a .cnv file that stores pressure in psi, it will be stored in the same unit within the ctd object, but x[["pressure"]] will return a value that has been converted to decibars. (Users who need the pressure in PSI can use x@data\$pressure.) Similarly, temperature is returned in the ITS-90 scale, with a conversion having been performed with T90fromT68, if the object holds temperature in IPTS-68. Again, temperature on the IPTS-68 scale is returned with x@data\$temperature.

This preference for computed over stored quantities is accomplished by first checking for computed quantities, and then falling back to the general [[ method if no match is found.

Some quantities are optionally computed. For example, some data files (e.g. the one upon which the section dataset is based) store nitrite along with the sum of nitrite and nitrate, the latter with name `NO2+NO3`. In this case, e.g. x[["nitrate"]] will detect the setup, and subtract nitrite from the sum to yield nitrate.

Below is a list of computed quantities, or at least quantities that are typically not stored in data files. (This is a vague statement because Seabird software permits calculation of many of these and hence storage within .cnv files.)

- CT or Conservative Temperature: Conservative Temperature, computed with gsw\_CT\_from\_t in the gsw package.
- density: seawater density, computed with swRho(x). (Note that it may be better to call that function directly, to gain control of the choice of equation of state, etc.)
- depth: Depth in metres below the surface, computed with swDepth(x).
- N2: Square of Brunt-Vaisala frequency, computed with swN2(x).
- potential temperature: Potential temperature in the UNESCO formulation, computed with swTheta(x). This is a synonym for theta.
- Rrho: Density ratio, computed with swRrho(x).
- SA or Absolute Salinity: Absolute Salinity, computed with gsw\_SA\_from\_SP in the gsw package. The calculation involves location as well as measured water properties. If the object x does not containing information on the location, then 30N and 60W is used for the calculation, and a warning is generated.

562 [[,ctd-method

- sigmaTheta: A form of potential density anomaly, computed with swSigmaTheta(x).
- sigma0 Equal to sigmaTheta, i.e. potential density anomaly referenced to a pressure of 0dbar, computed with swSigma0(x).
- sigma1: Potential density anomaly referenced to a pressure of 1000dbar, computed with swSigma1(x).
- sigma2: Potential density anomaly referenced to a pressure of 2000dbar, computed with swSigma2(x).
- sigma3: Potential density anomaly referenced to a pressure of 3000dbar, computed with swSigma3(x).
- sigma4: potential density anomaly referenced to a pressure of 4000dbar, computed with swSigma4(x).
- SP: Salinity on the Practical Salinity Scale, which is salinity in the data slot.
- spice: a variable that is in some sense orthogonal to density, calculated with swSpice(x).
- SR: Reference Salinity computed with gsw\_SR\_from\_SP in the gsw package.
- Sstar: Preformed Salinity computed with gsw\_SR\_from\_SP in the gsw package. See SA for a note on longitude and latitude.
- theta: potential temperature in the UNESCO formulation, computed with swTheta(x). This is a synonym for potential temperature.
- z: Vertical coordinate in metres above the surface, computed with swZ(x).

### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method,[[,argo-method,[[,bremen-method,[[,coastline-method,[[,echosounder-method,[[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method,[[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method,[[,topo-method,[[,windrose-method,[[,-,adv-method]]]]]]]]) and the section of the sec
```

Other things related to ctd data: [[<-,ctd-method, as.ctd, cnvName2oceName, ctd-class, ctdDecimate, ctdFindProfiles, ctdRaw, ctdTrim, ctd, handleFlags, ctd-method, oceNames2whpNames, oceUnits2whpUnits, plot, ctd-method, plotProfile, plotScan, plotTS, read.ctd.itp, read.ctd.odf, read.ctd.sbe, read.ctd.woce.other, read.ctd.woce, read.ctd, subset, ctd-method, summary, ctd-method, woceNames2oceNames, woceUnit2oceUnit, write.ctd

### **Examples**

```
data(ctd)
head(ctd[["temperature"]])
```

[[,echosounder-method

[[,echosounder-method Extract Parts of an Echosounder Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

563

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

## Usage

```
## S4 method for signature 'echosounder' x[[i, j, ...]]
```

## **Arguments**

- x A echosounder object, i.e. one inheriting from echosounder-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- ... Optional additional information (ignored).

## Details of the specialized echosounder method

```
If i is the string "Sv", the return value is calculated according to
```

```
Sv <- 20*log10(a) -
   (x@metadata$sourceLevel+x@metadata$receiverSensitivity+x@metadata$transmitPower) +
   20*log10(r) +
   2*absorption*r -
   x@metadata$correction +
   10*log10(soundSpeed*x@metadata$pulseDuration/1e6*psi/2)

If i is the string "TS",

TS <- 20*log10(a) -
   (x@metadata$sourceLevel+x@metadata$receiverSensitivity+x@metadata$transmitPower) +
   40*log10(r) +
   2*absorption*r +
   x@metadata$correction</pre>
```

Otherwise, the generic [[ is used.

564 [[,g1sst-method

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,g1sst-method, [[,g1sst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[,-,adv-method]]]]]]]]]]
```

Other things related to echosounder data: [[<-,echosounder-method, as.echosounder, echosounder-class, echosounder, findBottom, plot,echosounder-method, read.echosounder, subset,echosounder-method, summary,echosounder-method

[[,g1sst-method

Extract Something From a G1SST Object

#### Description

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

[[,g1sst-method 565

## Usage

```
## S4 method for signature 'g1sst' x[[i, j, ...]]
```

## **Arguments**

| X | A glsst object, i.e. one inheriting from glsst-class.    |
|---|----------------------------------------------------------|
| i | Character string indicating the name of item to extract. |
| j | Optional additional information on the i item.           |
|   | Optional additional information (ignored)                |

## Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

## See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[<-,adv-method]]]]]]]))))))))))))))
```

566 [[,gps-method

[[,gps-method

Extract Something From a GPS Object

### **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'gps'
x[[i, j, ...]]
```

### **Arguments**

x A gps object, i.e. one inheriting from gps-class.

i Character string indicating the name of item to extract.

j Optional additional information on the i item.

. . . Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

[[,ladp-method 567

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[<-,adv-method]]]]]]]]
```

Other things related to gps data: [[<-,gps-method,as.gps,gps-class,plot,gps-method,read.gps,summary,gps-method

[[,ladp-method

Extract Something From an ladp Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

## Usage

```
## S4 method for signature 'ladp'
x[[i, j, ...]]
```

## Arguments

- x A ladp object, i.e. one inheriting from ladp-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- ... Optional additional information (ignored).

568 [[,ladp-method

## Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

### Author(s)

Dan Kelley

## See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[<-,adv-method]]]]]]]
```

Other things related to ladp data: as.ladp, ladp-class, plot, ladp-method, summary, ladp-method

## **Examples**

```
data(ctd)
head(ctd[["temperature"]])
```

[[,landsat-method 569

[[,landsat-method

Extract Something From a landsat Object

### Description

Users are isolated from the details of the two-byte storage system by using the [[ operator.

### Usage

```
## S4 method for signature 'landsat' x[[i, j, ...]]
```

### **Arguments**

x An landsat object, i.e. one inheriting from landsat-class.

i The item to extract.

j Optional additional information on the i item (ignored).

... Optional additional information (ignored).

### **Details**

Accessing band data. The data may be accessed with e.g. landsat[["panchromatic"]], for the panchromatic band. If a new "band" is added with landsatAdd, it may be referred by name. In all cases, a second argument can be provided, to govern decimation. If this is missing, all the relevant data are returned. If this is present and equal to TRUE, then the data will be automatically decimated (subsampled) to give approximately 800 elements in the longest side of the matrix. If this is present and numerical, then its value governs decimation. For example, landsat[["panchromatic",TRUE]] will auto-decimate, typically reducing the grid width and height from 16000 to about 800. Similarly, landsat[["panchromatic",10]] will reduce width and height to about 1600. On machines with limited RAM (e.g. under about 6GB), decimation is a good idea in almost all processing steps. It also makes sense for plotting, and in fact is done through the decimate argument of plot,landsat-method.

Accessing derived data. One may retrieve several derived quantities that are calculated from data stored in the object: landsat[["longitude"]] and landsat[["latitude"]] give pixel locations. Accessing landsat[["temperature"]] creates an estimate of ground temperature as follows (see [4]). First, the "count value" in band 10, denoted  $b_{10}$  say, is scaled with coefficients stored in the image metadata using  $\lambda_L = b_{10}M_L + A_L$  where  $M_L$  and  $A_L$  are values stored in the metadata (e.g. the first in landsat@metadata\$header\$radiance\_mult\_band\_10) Then the result is used, again with coefficients in the metadata, to compute Celcius temperature  $T = K_2/ln(\epsilon K_1/\lambda_L + 1) - 273.15$ . The value of the emissivity  $\epsilon$  is set to unity by read.landsat, although it can be changed easily later, by assigning a new value to landsat@metadata\$emissivity. The default emissivity value set by read.landsat is from [11], and is within the oceanic range suggested by [5]. Adjustment is as simple as altering landsat@metadata\$emissivity. This value can be a single number meant to apply for the whole image, or a matrix with dimensions matching those of band 10. The matrix case is probably more useful for images of land, where one might wish to account for the different emissivities of soil and vegetation, etc.; for example, Table 4 of [9] lists

570 [[,lisst-method

0.9668 for soil and 0.9863 for vegetation, while Table 5 of [10] lists 0.971 and 0.987 for the same quantities.

Accessing metadata. Anything in the metadata can be accessed by name, e.g. landsat[["time"]]. Note that some items are simply copied over from the source data file and are not altered by e.g. decimation. An exception is the lat-lon box, which is altered by landsatTrim.

## Author(s)

Dan Kelley

#### See Also

Other things related to landsat data: landsat-class, landsatAdd, landsatTrim, landsat, plot, landsat-method, read.landsat, summary, landsat-method

[[,lisst-method

Extract Something From a LISST Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### Usage

```
## S4 method for signature 'lisst' x[[i, j, ...]]
```

## **Arguments**

| X | A lisst object, i.e. | one inheriting from | lisst-class |
|---|----------------------|---------------------|-------------|
|---|----------------------|---------------------|-------------|

i Character string indicating the name of item to extract.

j Optional additional information on the i item.

. . . Optional additional information (ignored).

[[,lobo-method 571

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method,[[,argo-method,[[,bremen-method,[[,cm-method,[[,coastline-method,[[,ctd-method,[[,echosounder-method,[[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lobo-method,[[,met-method,[[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method,[[,topo-method,[[,windrose-method,[[,-,adv-method]]]]]]]))))
```

Other things related to lisst data: [[<-,lisst-method, as.lisst, lisst-class, plot,lisst-method, read.lisst, summary,lisst-method

[[,lobo-method

Extract Something From a LOBO Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

572 [[,lobo-method

### Usage

```
## S4 method for signature 'lobo' x[[i, j, ...]]
```

### **Arguments**

x A lobo object, i.e. one inheriting from lobo-class.
 i Character string indicating the name of item to extract.
 j Optional additional information on the i item.
 ... Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method,[[,argo-method,[[,bremen-method,[[,cm-method,[[,coastline-method,[[,ctd-method,[[,echosounder-method,[[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,met-method,[[,odf-method,[[,rsk-method,[[,sealevel-method,[[,section-method,[[,tidem-method,[[,topo-method,[[,windrose-method,[[<,-,adv-method]]]]]]])
```

Other things related to lobo data: [[<-,lobo-method, as.lobo, lobo-class, lobo, plot, lobo-method, subset, lobo-method, summary, lobo-method

[[,met-method 573

[[,met-method

Extract Something From a met Object

### **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'met'
x[[i, j, ...]]
```

### **Arguments**

x A met object, i.e. one inheriting from met-class.

i Character string indicating the name of item to extract.

j Optional additional information on the i item.

. . . Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

574 [[,oce-method

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

## See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,tidem-method, [[,tidem-method, [[,windrose-method, [[<-,adv-method Other things related to met data: [[<-,met-method, as.met, download.met, met-class, met, plot,met-method, read.met, subset,met-method, summary,met-method
```

[[,oce-method

Extract Something From an oce Object

## **Description**

The named item is sought first in metadata, where an exact match to the name is required. If it is not present in the metadata slot, then a partial-name match is sought in the data slot. Failing both tests, an exact-name match is sought in a field named dataNamesOriginal in the object's metadata slot, if that field exists. Failing that, NULL is returned.

To get information on the specialized variants of this function, type e.g. ?"[[,adv-method" for information on extracting data from an object of adv-class.

## Usage

```
## S4 method for signature 'oce' x[[i, j, ...]]
```

### **Arguments**

| Х | An oce object                                  |
|---|------------------------------------------------|
| i | The item to extract.                           |
| j | Optional additional information on the i item. |
|   | Optional additional information (ignored).     |

## **Examples**

```
data(ctd)
ctd[["longitude"]] # in metadata
head(ctd[["salinity"]]) # in data
data(section)
summary(section[["station", 1]])
```

[[,odf-method 575

[[,odf-method

Extract Something From an ODF Object

### **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

### **Usage**

```
## S4 method for signature 'odf'
x[[i, j, ...]]
```

### **Arguments**

x an odf object, i.e. one inheriting from odf-class.

i Character string indicating the name of item to extract.

j Optional additional information on the i item.

... Optional additional information (ignored).

### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

576 [[,rsk-method

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[<-,adv-method
```

Other things related to odf data: ODF2oce, ODFNames2oceNames, [[<-,odf-method, odf-class, plot,odf-method, read.ctd.odf, read.odf, subset,odf-method, summary,odf-method

[[,rsk-method

Extract Something From a Rsk Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

## Usage

```
## S4 method for signature 'rsk'
x[[i, j, ...]]
```

## Arguments

- x A rsk object, i.e. one inheriting from rsk-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- . . . Optional additional information (ignored).

[[,sealevel-method 577

#### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method,[[,argo-method,[[,bremen-method,[[,cm-method,[[,coastline-method,[[,ctd-method,[[,echosounder-method,[[,g1sst-method,[[,gps-method,[[,ladp-method,[[,lisst-method,[[,lobo-method,[[,met-method,[[,odf-method,[[,sealevel-method,[[,section-method,[[,tidem-method,[[,topo-method,[[,windrose-method,[[<,-,adv-method]]]]]])
```

Other things related to rsk data: [[<-,rsk-method, as.rsk, plot,rsk-method, read.rsk, rsk-class, rskPatm, rskToc, rsk, subset,rsk-method, summary,rsk-method

[[,sealevel-method

Extract Something From a Sealevel Object

# **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

578 [[,sealevel-method

#### Usage

```
## S4 method for signature 'sealevel' x[[i, j, ...]]
```

# **Arguments**

A sealevel object, i.e. one inheriting from sealevel-class.
 Character string indicating the name of item to extract.
 Optional additional information on the i item.
 Optional additional information (ignored).

#### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

# See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,section-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[<-,adv-method]]]]]]]
```

Other things related to sealevel data: [[<-, sealevel-method, as.sealevel, plot, sealevel-method, read.sealevel, sealevel-class, sealevelTuktoyaktuk, sealevel, subset, sealevel-method, summary, sealevel-method

[[,section-method 579

[[,section-method

Extract Something From a Section Object

# **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

# Usage

```
## S4 method for signature 'section' x[[i, j, ...]]
```

#### **Arguments**

- x A section object, i.e. one inheriting from section-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- ... Optional additional information (ignored).

# Details of the specialized section method

There are several possibilities, depending on the nature of i.

- If i is the string "station", then the method will return a list of ctd-class objects holding the station data. If j is also given, it specifies a station (or set of stations) to be returned. If j contains just a single value, then that station is returned, but otherwise a list is returned. If j is an integer, then the stations are specified by index, but if it is character, then stations are specified by the names stored within their metadata. (Missing stations yield NULL in the return value.)
- If i is "station ID", then the IDs of the stations in the section are returned.
- If i is "dynamic height", then an estimate of dynamic height is returned (as calculated with swDynamicHeight(x)).
- If i is "distance", then the distance along the section is returned, using geodDist.
- If i is "depth", then a vector containing the depths of the stations is returned.
- If i is "z", then a vector containing the z coordinates is returned.
- If i is "theta" or "potential temperature", then the potential temperatures of all the stations are returned in one vector. Similarly, "spice" returns the property known as spice, using swSpice.

580 [[,section-method

• If i is a string ending with "Flag", then the characters prior to that ending are taken to be the name of a variable contained within the stations in the section. If this flag is available in the first station of the section, then the flag values are looked up for every station.

If none of the conditions listed above holds, the general method is used (see 'Details of the general method').

# Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

# Author(s)

Dan Kelley

#### See Also

Other things related to section data: [[<-, section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,tidem-method, [[,topo-method, [[,windrose-method, [[<-,adv-method]]]]]]]
```

[[,tidem-method 581

## **Examples**

```
data(section)
length(section[["latitude"]])
length(section[["latitude", "byStation"]])
data(section)
length(section[["latitude"]])
length(section[["latitude", "byStation"]])
```

[[,tidem-method

Extract Something From a Tidem Object

#### **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

#### Usage

```
## S4 method for signature 'tidem' x[[i, j, ...]]
```

## **Arguments**

- x A tidem object, i.e. one inheriting from tidem-class.
- i Character string indicating the name of item to extract.
- j Optional additional information on the i item.
- ... Optional additional information (ignored).

#### Details of the specialized tidem method

A vector of the frequencies of fitted constituents is recovered with e.g. x[["frequency"]]. Similarly, amplitude is recovered with e.g. x[["amplitude"]] and phase with e.g. x[["phase"]]. If any other string is specified, then the underlying accessor [[,oce-method)] is used.

582 [[,topo-method

#### Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,topo-method, [[,windrose-method, [[<-,adv-method]]]]]]])

Other things related to tidem data: [[<-,tidem-method, plot,tidem-method, predict.tidem,
```

[[,topo-method

Extract Something From a Topo Object

summary, tidem-method, tidedata, tidem-class, tidemAstron, tidemVuf, tidem

# **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

[[,topo-method 583

## Usage

```
## S4 method for signature 'topo'
x[[i, j, ...]]
```

#### **Arguments**

```
    A topo object, i.e. one inheriting from topo-class.
    Character string indicating the name of item to extract.
    Optional additional information on the i item.
    Optional additional information (ignored).
```

# Details of the specialized topo method

There are no special features for topo-class data; the general method is used directly.

# Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in " unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in " scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

# See Also

read.topo, subset, topo-method, summary, topo-method, topo-class, topoInterpolate, topoWorld

584 [[,windrose-method

## **Examples**

```
data(topoWorld)
dim(topoWorld[['z']])
```

[[,windrose-method

Extract Something From a Windrose Object

## **Description**

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

# Usage

```
## S4 method for signature 'windrose'
x[[i, j, ...]]
```

#### **Arguments**

| Χ | A windrose object, i.e. one inheriting from windrose-class. |
|---|-------------------------------------------------------------|
| i | Character string indicating the name of item to extract.    |
| j | Optional additional information on the i item.              |
|   | Optional additional information (ignored).                  |

### Details of the specialized windrose method

There are no special features for windrose-class data; the general method is used directly.

# Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string

[[<-,adp-method 585

describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### See Also

```
Other functions that extract parts of oce objects: [[,adp-method,[[,adv-method,[[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,topo-method, [[<-,adv-method]]]]]]]]
```

Other things related to windrose data: [[<-,windrose-method, as.windrose, plot,windrose-method, summary,windrose-method, windrose-class

[[<-,adp-method</pre>

Replace Parts of an ADP Object

#### Description

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'adp' x[[i, j, ...]] \leftarrow value
```

# **Arguments**

| X     | An adp object, i.e. one inheriting from adp-class. |
|-------|----------------------------------------------------|
| i     | The item to replace.                               |
| j     | Optional additional information on the i item.     |
|       | Optional additional information (ignored).         |
| value | The value to be placed into x, somewhere.          |

586 [[<-,adv-method

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

In addition to the usual insertion of elements by name, note that e.g. pitch gets stored into pitchSlow.

### Author(s)

Dan Kelley

### See Also

```
Other functions that replace parts of oce objects: [[<-,amsr-method, [[<-,argo-method, [[<-,bremen-method, [[<-,cd-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,gps-method, [[<-,lisst-method, [[<-,met-method, [[<-,oce-method, [[<-,oce-method, [[<-,rsk-method, [[<-,sealevel-method, [[<-,section-method, [[<-,tidem-method, [[<
```

Other things related to adp data: [[,adp-method,adp-class,adpEnsembleAverage,adp,as.adp,beamName,beamToXyzAdp,beamToXyzAdv,beamToXyz,beamUnspreadAdp,binmapAdp,enuToOtherAdp,enuToOther,plot,adp-method,read.ad2cp,read.adp.nortek,read.adp.rdi,read.adp.sontek.serial,read.adp.sontek,read.adp,read.adp,read.aquadoppHR,read.aquadoppProfiler,read.aquadopp,subset,adp-method,summary,adp-method,toEnuAdp,toEnu,velocityStatistics,xyzToEnuAdp,xyzToEnu

[[<-,adv-method 587

#### **Description**

Replace Parts of an ADV Object

The [[ method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related replacement method, [[<-, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be extracted, including derived data, units of measurement, and data-quality flags.

The method uses a two-step process to try to find the requested information. First, a class-specific function is used to try to access the requested information (see "Details of the specialized ... method"). Second, if no match is found, a general function is used (see 'Details of the general method'). If neither method can locates the requested item, NULL is returned.

# Usage

```
## S4 replacement method for signature 'adv' x[[i, j, ...]] \leftarrow value
```

# Arguments

An adv object, i.e. one inheriting from adv-class.
 Character string indicating the name of item to extract.
 Optional additional information on the i item.
 Optional additional information (ignored).

value The value to be inserted into x.

#### **Details**

If the adv object holds slow variables (i.e. if timeSlow is in the data slot), then assigning to .e.g. heading will not actually assign to a variable of that name, but instead assigns to headingSlow. To catch misapplication of this rule, an error message will be issued if the assigned value is not of the same length as timeSlow.

# Details of the general method

If the specialized method produces no matches, the following generalized method is applied. As with the specialized method, the procedure hinges first on the value of i.

First, a check is made as to whether i names one of the standard oce slots, and returns the slot contents if so. Thus, x[["metadata"]] will retrieve the metadata slot, while x[["data"]] and x[["processingLog"]] return those slots.

Next, if i is a string ending in the "Unit", then the characters preceding that string are taken to be the name of an item in the data object, and a list containing the unit is returned. This list consists of an item named unit, which is an expression, and an item named scale, which is a string describing the measurement scale. If the string ends in "unit", e.g. x[["temperature unit"]], then just the expression is returned, and if it ends in "scale", then just the scale is returned.

Next, if i is a string ending in "Flag", then the corresponding data-quality flag is returned (or NULL if there is no such flag). For example, x[["salinityFlag"]] returns a vector of salinity flags if x is a ctd object.

588 [[<-,amsr-method

If none of the preceding conditions are met, a check is done to see if the metadata slot contains an item with the provided name, and that is returned, if so. A direct match is required for this condition.

Finally, the data slot is checked to see if it contains an item with the name indicated by i. In this case, a partial match will work; this is accomplished by using pmatch.

If none of the above-listed conditions holds, then NULL is returned.

#### Author(s)

Dan Kelley

### See Also

```
Other functions that extract parts of oce objects: [[,adp-method, [[,adv-method, [[,amsr-method, [[,argo-method, [[,bremen-method, [[,cm-method, [[,coastline-method, [[,ctd-method, [[,echosounder-method, [[,g1sst-method, [[,gps-method, [[,ladp-method, [[,lisst-method, [[,lobo-method, [[,met-method, [[,odf-method, [[,rsk-method, [[,sealevel-method, [[,section-method, [[,tidem-method, [[,tidem-method, [[,tidem-method, [[,windrose-method]]]]]]])

Other things related to adv data: [[,adv-method,adv-class,adv,beamName,beamToXvz,enuToOtherAdv.]]]
```

Other things related to adv data: [[,adv-method,adv-class,adv,beamName,beamToXyz,enuToOtherAdv,enuToOther,plot,adv-method,read.adv.nortek,read.adv.sontek.adr,read.adv.sontek.serial,read.adv.sontek.text,read.adv,subset,adv-method,summary,adv-method,toEnuAdv,toEnu,velocityStatistics,xyzToEnuAdv,xyzToEnu

[[<-,amsr-method

Replace Parts of an AMSR Object

# Description

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'amsr' x[[i, j, ...]] \leftarrow value
```

# **Arguments**

| X     | An amsr object, i.e. inheriting from amsr-class |
|-------|-------------------------------------------------|
| i     | The item to replace.                            |
| j     | Optional additional information on the i item.  |
|       | Optional additional information (ignored).      |
| value | The value to be placed into x, somewhere.       |

[[<-,argo-method 589

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other things related to amsr data: amsr-class, composite, amsr-method, download.amsr, plot, amsr-method, read.amsr, subset, amsr-method, summary, amsr-method
```

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, argo-method, [[<-, bremen-method, [[<-, cm-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, g1sst-method, [[<-, g1sst-method, [[<-, met-method, [[<-, oce-method, [[<-, oce-method, [[<-, oce-method, [[<-, section-method, [[<-, tidem-method, [[<-, tidem-meth
```

[[<-,argo-method

Replace Parts of an Argo Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

### Usage

```
## S4 replacement method for signature 'argo' x[[i, j, ...]] \leftarrow value
```

590 [[<-,argo-method

### Arguments

| X     | An argo object, i.e. inheriting from argo-class |
|-------|-------------------------------------------------|
| i     | The item to replace.                            |
| j     | Optional additional information on the i item.  |
|       | Optional additional information (ignored).      |
| value | The value to be placed into x, somewhere.       |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

### See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method,[[<-,amsr-method,[[<-,bremen-method,[[<-,cd-method,[[<-,echosounder-method,[[<-,g1sst-method,[[<-,gps-method,[[<-,lisst-method,[[<-,met-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-m
```

Other things related to argo data: [[,argo-method,argo-class,argoGrid,argoNames2oceNames,argo,as.argo,handleFlags,argo-method,plot,argo-method,read.argo,subset,argo-method,summary,argo-method

[[<-,bremen-method 591

[[<-,bremen-method

Replace Parts of a Bremen Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'bremen' x[[i, j, ...]] \leftarrow value
```

# **Arguments**

| X     | An bremen object, i.e. inheriting from bremen-class |
|-------|-----------------------------------------------------|
| i     | The item to replace.                                |
| j     | Optional additional information on the i item.      |
|       | Optional additional information (ignored).          |
| value | The value to be placed into x, somewhere.           |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

592 [[<-,cm-method

## See Also

```
\label{thm:constraints} Other functions that replace parts of oce objects: $$ [[<-,adp-method,[[<-,amsr-method,[[<-,argo-method,[[<-,cd-method,[[<-,echosounder-method,[[<-,g1sst-method,[[<-,g1sst-method,[[<-,met-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,odf-method,[[<-,rsk-method,[[<-,sealevel-method,[[<-,section-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-m
```

Other things related to bremen data: [[,bremen-method, bremen-class, plot,bremen-method, read.bremen, summary,bremen-method

[[<-,cm-method

Replace Parts of a CM Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

## Usage

```
## S4 replacement method for signature 'cm' x[[i, j, ...]] \leftarrow value
```

#### Arguments

| Х     | An cm object, i.e. inheriting from cm-class    |
|-------|------------------------------------------------|
| i     | The item to replace.                           |
| j     | Optional additional information on the i item. |
| • • • | Optional additional information (ignored).     |
| value | The value to be placed into x, somewhere.      |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

[[<-,coastline-method 593

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method, [[<-,amsr-method, [[<-,argo-method, [[<-,bremen-method, [[<-,ctd-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,g1sst-method, [[<-,lisst-method, [[<-,lobo-method, [[<-,met-method, [[<-,oce-method, [[<-,odf-method, [[<-,rsk-method, [[<-,sealevel-method, [[<-,section-method, [[<-,tidem-method, [[<-,tidem-method, [[<-,windrose-method]]]]]])

Other things related to cm data: [[,cm-method, as.cm, cm-class, cm, plot,cm-method, read.cm, subset,cm-method, summary,cm-method]
```

[[<-,coastline-method Replace Parts of a Coastline Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'coastline' x[[i, j, ...]] \leftarrow value
```

### **Arguments**

| x     | An coastline object, i.e. inheriting from coastline-class |
|-------|-----------------------------------------------------------|
| i     | The item to replace.                                      |
| j     | Optional additional information on the i item.            |
|       | Optional additional information (ignored).                |
| value | The value to be placed into x, somewhere.                 |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

594 [[<-,ctd-method

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other things related to coastline data: [[,coastline-method, as.coastline, coastline-class, coastlineBest, coastlineCut, coastlineWorld, download.coastline, plot, coastline-method, read.coastline.openstreetmap, read.coastline.shapefile, subset, coastline-method, summary, coastline-method. Coastline-method, summary, coastline-method, c
```

[[<-,ctd-method

Replace Parts of a CTD Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

## Usage

```
## S4 replacement method for signature 'ctd' x[[i, j, ...]] \leftarrow value
```

# Arguments

| x     | A ctd object, i.e. one inheriting from ctd-class. |
|-------|---------------------------------------------------|
| i     | The item to replace.                              |
| j     | Optional additional information on the i item.    |
| • • • | Optional additional information (ignored).        |
| value | The value to be placed into x, somewhere.         |

[[<-,ctd-method 595

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method, [[<-,amsr-method, [[<-,argo-method, [[<-,coastline-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,g1sst-method, [[<-,lobo-method, [[<-,met-method, [[<-,met-method, [[<-,coastline-method, [[<-,sealevel-method, [[<-,met-method, [[<-,coastline-method, [[<-,sealevel-method, [salevel-method, [salevel
```

## **Examples**

```
data(ctd)
summary(ctd)
# Move the CTD profile a nautical mile north.
ctd[["latitude"]] <- 1/60 + ctd[["latitude"]] # acts in metadata
# Increase the salinity by 0.01.
ctd[["salinity"]] <- 0.01 + ctd[["salinity"]] # acts in data
summary(ctd)</pre>
```

```
[[<-,echosounder-method
```

Replace Parts of an Echosounder Object

## **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

## Usage

```
## S4 replacement method for signature 'echosounder' x[[i, j, ...]] \leftarrow value
```

# **Arguments**

| Χ     | An echosounder object, i.e. inheriting from echosounder-class |
|-------|---------------------------------------------------------------|
| i     | The item to replace.                                          |
| j     | Optional additional information on the i item.                |
|       | Optional additional information (ignored).                    |
| value | The value to be placed into x, somewhere.                     |

# Details

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

[[<-,g1sst-method 597

#### See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method,[[<-,amsr-method,[[<-,argo-method,[[<-,bremen-method,[[<-,cm-method,[[<-,coastline-method,[[<-,ctd-method,[[<-,g1sst-method,[[<-,g1sst-method,[[<-,met-method,[[<-,oce-method,[[<-,oce-method,[[<-,oce-method,[[<-,odf-method,[[<-,rsk-method,[[<-,sealevel-method,[[<-,section-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,tidem-method,[[<-,t
```

Other things related to echosounder data: [[,echosounder-method, as.echosounder, echosounder-class, echosounder, findBottom, plot, echosounder-method, read.echosounder, subset, echosounder-method, summary, echosounder-method

[[<-,g1sst-method

Replace Parts of a G1SST Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'g1sst' x[[i, j, ...]] \leftarrow value
```

#### **Arguments**

| x     | An g1sst object, i.e. one inheriting from g1sst-class |
|-------|-------------------------------------------------------|
| i     | The item to replace.                                  |
| j     | Optional additional information on the i item.        |
| • • • | Optional additional information (ignored).            |
| value | The value to be placed into x, somewhere.             |

# Details

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

598 [[<-,gps-method

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, gps-method, [[<-, lisst-method, [[<-, met-method, [[<-, oce-method, [[<-, odf-method, [[<-, rsk-method, [[<-, sealevel-method, [[<-, section-method, [[<-, tidem-method, [[<-, topo-method, [[<-, windrose-method]]]]]]]])
```

Other things related to g1sst data: [[,g1sst-method

[[<-,gps-method

Replace Parts of a GPS Object

# Description

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

### Usage

```
## S4 replacement method for signature 'gps' x[[i, j, ...]] \leftarrow value
```

### Arguments

| X     | An gps object, i.e. inheriting from gps-class  |
|-------|------------------------------------------------|
| i     | The item to replace.                           |
| j     | Optional additional information on the i item. |
|       | Optional additional information (ignored).     |
| value | The value to be placed into x, somewhere.      |

#### Details

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

[[<-,lisst-method 599

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] <- c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, g1sst-method, [[<-, lisst-method, [[<-, lobo-method, [[<-, met-method, [[<-, oce-method, [[<-, oce-method, [[<-, ctd-method, [[<-, ctd-method, [[<-, oce-method, [[<-, ctd-method, [[<-, oce-method, [[<-, ctd-method, [[<-, oce-method, [[<-, ctd-method, [[<-, ctd-
```

Other things related to gps data: [[,gps-method, as.gps,gps-class,plot,gps-method,read.gps,summary,gps-method]

[[<-,lisst-method</pre>

Replace Parts of a LISST Object

# **Description**

Replace Parts of a LISST Object

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

#### Usage

```
## S4 replacement method for signature 'lisst' x[[i, j, ...]] \leftarrow value
```

# Arguments

| x     | An lisst object, i.e. inheriting from lisst-class |
|-------|---------------------------------------------------|
| i     | The item to replace.                              |
| j     | Optional additional information on the i item.    |
|       | Optional additional information (ignored).        |
| value | The value to be placed into x, somewhere.         |

600 [[<-,lobo-method

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, glsst-method, [[<-, net-method, [[<-, net-method, [[<-, oce-method, [[<-, odf-method, [[<-, rsk-method, [[<-, sealevel-method, [[<-, section-method, [[<-, tidem-method, [[<-, topo-method, [[<-, windrose-method]]]]]]]])
```

Other things related to lisst data: [[,lisst-method, as.lisst, lisst-class, plot,lisst-method, read.lisst, summary,lisst-method

[[<-,lobo-method

Replace Parts of a LOBO Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

### Usage

```
## S4 replacement method for signature 'lobo' x[[i, j, ...]] \leftarrow value
```

[[<-,met-method 601

### Arguments

| X     | An lobo object, i.e. inheriting from lobo-class |
|-------|-------------------------------------------------|
| i     | The item to replace.                            |
| j     | Optional additional information on the i item.  |
|       | Optional additional information (ignored).      |
| value | The value to be placed into x, somewhere.       |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] <- c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

## See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method, [[<-,amsr-method, [[<-,argo-method, [[<-,cd-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,g1sst-method, [[<-,met-method, [[<-,oce-method, [[<-,oce-method, [[<-,oce-method, [[<-,section-method, [[<-,tidem-method, [[<-,ti
```

Other things related to lobo data: [[,lobo-method, as.lobo, lobo-class, lobo, plot, lobo-method, subset, lobo-method, summary, lobo-method

[[<-,met-method Replace Parts of a met Object

# Description

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

602 [[<-,met-method

### Usage

```
## S4 replacement method for signature 'met' x[[i, j, ...]] \leftarrow value
```

# **Arguments**

| x     | An met object, i.e. inheriting from met-class  |
|-------|------------------------------------------------|
| i     | The item to replace.                           |
| j     | Optional additional information on the i item. |
|       | Optional additional information (ignored).     |
| value | The value to be placed into x, somewhere.      |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

### See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, g1sst-method, [[<-, g1sst-method, [[<-, lisst-method, [[<-, lobo-method, [[<-, oce-method, [[<-, oce-method, [[<-, oce-method, [[<-, sealevel-method, [[<-, section-method, [[<-, tidem-method, [[<-, tidem-method, [[<-, tidem-method, [[<-, tidem-method, [[<-, windrose-method]]]]]]]])
```

Other things related to met data: [[,met-method, as.met, download.met, met-class, met, plot,met-method, read.met, subset,met-method, summary,met-method

[[<-,oce-method 603

[[<-,oce-method

Replace Parts of an Oce Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'oce' x[[i, j, ...]] \leftarrow value
```

#### **Arguments**

| X     | An oce object, i.e. inheriting from oce-class. |
|-------|------------------------------------------------|
| i     | The item to replace.                           |
| j     | Optional additional information on the i item. |
|       | Optional additional information (ignored).     |
| value | The value to be placed into x, somewhere.      |

# **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, g1sst-method, [[<-, g1sst-method, [[<-, lisst-method, [[<-, lobo-method, [[<-, met-method, [[<-, odf-method, [[<-, rsk-method, [[<-, sealevel-method, [[<-, section-method, [[<-, tidem-method, [[<-, topo-method, [[<-, windrose-method]]]]]])
```

604 [[<-,odf-method

[[<-,odf-method

Replace Parts of an ODF Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'odf' x[[i, j, ...]] \leftarrow value
```

# Arguments

| X     | an odf object, i.e. inheriting from odf-class  |
|-------|------------------------------------------------|
| i     | The item to replace.                           |
| j     | Optional additional information on the i item. |
| • • • | Optional additional information (ignored).     |
| value | The value to be placed into x, somewhere.      |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

[[<-,rsk-method 605

# See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method, [[<-,amsr-method, [[<-,argo-method, [[<-,coastline-method, [[<-,cd-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,g1sst-method, [[<-,net-method, [[<-,met-method, [[<-,met-method, [[<-,section-method, [[<-,tidem-method, [[<-,tidem-method, [[<-,topo-method, [[<-,windrose-method]]]]]]]]
```

Other things related to odf data: ODF2oce, ODFNames2oceNames, [[,odf-method, odf-class, plot,odf-method, read.ctd.odf, read.odf, subset,odf-method, summary,odf-method

[[<-,rsk-method

Replace Parts of a Rsk Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

## Usage

```
## S4 replacement method for signature 'rsk' x[[i, j, ...]] \leftarrow value
```

## **Arguments**

| X     | An rsk object, i.e. inheriting from rsk-class  |
|-------|------------------------------------------------|
| i     | The item to replace.                           |
| j     | Optional additional information on the i item. |
|       | Optional additional information (ignored).     |
| value | The value to be placed into x, somewhere.      |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

606 [[<-,sealevel-method

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method, [[<-,amsr-method, [[<-,argo-method, [[<-,coastline-method, [[<-,ctd-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,g1sst-method, [[<-,lisst-method, [[<-,net-method, [[<-,met-method, [[<-,odf-method, [[<-,section-method, [[<-,tidem-method, [[<-,topo-method, [[<-,windrose-method]]]]]]])

Other things related to rsk data: [[,rsk-method, as.rsk,plot,rsk-method,read.rsk,rsk-class, rskPatm,rskToc,rsk,subset,rsk-method,summary,rsk-method]
```

```
[[<-, sealevel-method Replace Parts of a Sealevel Object
```

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

#### Usage

```
## S4 replacement method for signature 'sealevel' x[[i, j, ...]] \leftarrow value
```

### **Arguments**

| Χ     | An sealevel object, i.e. inheriting from sealevel-class |
|-------|---------------------------------------------------------|
| i     | The item to replace.                                    |
| j     | Optional additional information on the i item.          |
|       | Optional additional information (ignored).              |
| value | The value to be placed into x, somewhere.               |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

[[<-,section-method 607

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, g1sst-method, [[<-, g1sst-method, [[<-, lobo-method, [[<-, met-method, [[<-, oce-method, [[<-, odf-method, [[<-, rsk-method, [[<-, section-method, [[<-, tidem-method, [[<-, topo-method, [[<-, windrose-method]]]]]]])
```

Other things related to sealevel data: [[, sealevel-method, as.sealevel, plot, sealevel-method, read.sealevel, sealevel-class, sealevelTuktoyaktuk, sealevel, subset, sealevel-method, summary, sealevel-method

[[<-, section-method Replace Parts of a Section Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

## Usage

```
## S4 replacement method for signature 'section' x[[i, j, ...]] \leftarrow value
```

# Arguments

| x     | A section object, i.e. inheriting from section-class |
|-------|------------------------------------------------------|
| i     | The item to replace.                                 |
| j     | Optional additional information on the i item.       |
|       | Optional additional information (ignored).           |
| value | The value to be placed into x, somewhere.            |

608 [[<-,section-method

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

## Author(s)

Dan Kelley

# See Also

```
Other things related to section data: [[,section-method, as.section, handleFlags, section-method, plot, section-method, read.section, section-class, sectionAddStation, sectionGrid, sectionSmooth, sectionSort, section, subset, section-method, summary, section-method
```

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, gps-method, [[<-, lisst-method, [[<-, lobo-method, [[<-, met-method, [[<-, oce-method, [[<-, odf-method, [[<-, rsk-method, [[<-, sealevel-method, [[<-, tidem-method, [[<-, topo-method, [[<-, windrose-method]]]]]]]]]
```

# **Examples**

[[<-,tidem-method 609

[[<-,tidem-method

Replace Parts of a Tidem Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

# Usage

```
## S4 replacement method for signature 'tidem' x[[i, j, ...]] \leftarrow value
```

# Arguments

| X     | An tidem object, i.e. inheriting from tidem-class |
|-------|---------------------------------------------------|
| i     | The item to replace.                              |
| j     | Optional additional information on the i item.    |
|       | Optional additional information (ignored).        |
| value | The value to be placed into x, somewhere.         |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

610 [[<-,topo-method

## See Also

```
Other functions that replace parts of oce objects: [[<-,adp-method, [[<-,amsr-method, [[<-,argo-method, [[<-,coastline-method, [[<-,ctd-method, [[<-,echosounder-method, [[<-,g1sst-method, [[<-,lobo-method, [[<-,met-method, [[<-,met-method, [[<-,oce-method, [[<-,oce-method, [[<-,rsk-method, [[<-,sealevel-method, [[<-,section-method, [[<-,topo-method, [[<-,windrose-method]]]]]]]))
Other things related to tidem data: [[,tidem-method, plot,tidem-method, predict.tidem,
```

Other things related to tidem data: [[,tidem-method, plot,tidem-method, predict.tidem, summary,tidem-method, tidedata, tidem-class, tidemAstron, tidemVuf, tidem

[[<-,topo-method

Replace Parts of a Topo Object

# **Description**

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

## Usage

```
## S4 replacement method for signature 'topo' x[[i, j, ...]] \leftarrow value
```

## **Arguments**

| x     | An topo object, i.e. inheriting from topo-class |
|-------|-------------------------------------------------|
| i     | The item to replace.                            |
| j     | Optional additional information on the i item.  |
| • • • | Optional additional information (ignored).      |
| value | The value to be placed into x, somewhere.       |

# Details

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F),scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

[[<-,windrose-method 611

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

#### See Also

```
Other things related to topo data: [[,topo-method,as.topo,download.topo,plot,topo-method,read.topo,subset,topo-method,summary,topo-method,topo-class,topoInterpolate,topoWorld Other functions that replace parts of oce objects: <math>[[<-,adp-method,[[<-,amsr-method,[[<-,argo-method,[[<-,bremen-method,[[<-,coastline-method,[[<-,ctd-method,[[<-,echosounder-method,[[<-,g1sst-method,[[<-,g1sst-method,[[<-,met-method,[[<-,met-method,[[<-,coe-method,[[<-,odf-method,[[<-,rsk-method,[[<-,sealevel-method,[[<-,section-method,[[<-,tidem-method,[[<-,windrose-method]]]]]])
```

```
[[<-,windrose-method Replace Parts of a Windrose Object
```

## Description

The [[<- method works for all oce objects, i.e. objects inheriting from oce-class. The purpose, as with the related extraction method, [[, is to insulate users from the internal details of oce objects, by looking for items within the various storage slots of the object. Items not actually stored can also be replaced, including units and data-quality flags.

#### Usage

```
## S4 replacement method for signature 'windrose' x[[i, j, ...]] \leftarrow value
```

### **Arguments**

| X     | An windrose object, i.e. inheriting from ${\tt windrose-class}$ |
|-------|-----------------------------------------------------------------|
| i     | The item to replace.                                            |
| j     | Optional additional information on the i item.                  |
|       | Optional additional information (ignored).                      |
| value | The value to be placed into x, somewhere.                       |

#### **Details**

As with [[ method, the procedure works in steps.

First, the metadata slot of x is checked to see whether it contains something named with i. If so, then the named item is replaced with value.

Otherwise, if the string value of i ends in Unit, then the characters preceding that are taken as the name of a variable, and the metadata slot of x is updated to store that unit, e.g.

612 [[<-,windrose-method

```
x[["temperatureUnits"]] <- list(unit=expression(degree*F), scale="")</pre>
```

Similarly, if i ends in Flag, then quality-control flags are set up as defined by result, e.g.

```
x[["temperatureFlags"]] \leftarrow c(2,4,2,2)
```

Otherwise, a partial string match is sought among the names of items in the data slot of x. (This is done with pmatch.) The first item found (if any) is then updated to hold the value result.

If none of these conditions is met, a warning is issued.

# See Also

```
Other functions that replace parts of oce objects: [[<-, adp-method, [[<-, amsr-method, [[<-, argo-method, [[<-, coastline-method, [[<-, ctd-method, [[<-, echosounder-method, [[<-, g1sst-method, [[<-, g1sst-method, [[<-, lisst-method, [[<-, lobo-method, [[<-, met-method, [[<-, oce-method, [[<-, odf-method, [[<-, rsk-method, [[<-, sealevel-method, [[<-, section-method, [[<-, tidem-method, [[<-, topo-method]]]]]]])
```

Other things related to windrose data: [[,windrose-method, as.windrose, plot,windrose-method, summary,windrose-method, windrose-class

## **Index**

| filled centeur 102                         | FFC mot mothed 601                                |
|--------------------------------------------|---------------------------------------------------|
| .filled.contour, 193 [[, 585, 586, 588–611 | [[<-,met-method, 601<br>[[<-,oce-method, 223, 603 |
|                                            |                                                   |
| [[,adp-method,548                          | [[<-,odf-method,604<br>[[<-,rsk-method,605        |
| [[,adv-method,550                          |                                                   |
| [[,amsr-method,552                         | [[<-, sealevel-method, 606                        |
| [[,argo-method,554                         | [[<-,section-method,607                           |
| [[,bremen-method,556                       | [[<-,tidem-method,609                             |
| [[,cm-method, 557                          | [[<-,topo-method,610                              |
| [[,coastline-method, 558                   | [[<-,windrose-method,611                          |
| [[,ctd-method,560                          |                                                   |
| [[,echosounder-method, 563                 | abbreviateTimeLabels, 12                          |
| [[,g1sst-method,564                        | addColumn, 12, 90, 99, 198, 213, 226              |
| [[,gps-method,566                          | adjustcolor, 287                                  |
| [[,ladp-method, 567                        | adp, 13, 17–19, 26, 32, 54, 55, 57–59, 65, 70,    |
| [[,landsat-method, 569                     | 78, 83, 86, 95, 122, 125, 126, 164,               |
| [[,lisst-method,570                        | 171, 172, 216, 262, 327, 329, 331,                |
| [[,lobo-method,571                         | 334, 335, 337, 363, 365, 367, 410,                |
| [[,met-method, 573                         | 416, 418, 420, 431, 448, 522, 523,                |
| [[,oce-method, 223, 574                    | 526, 536, 539, 544, 546, 550, 586                 |
| [[,odf-method,575                          | adp-class, 14                                     |
| [[,rsk-method,576                          | adpEnsembleAverage, 13, 17, 18, 32, 54, 55,       |
| [[,sealevel-method,577                     | 57–59, 65, 125, 126, 262, 327, 329,               |
| [[,section-method,579                      | 331, 334, 335, 337, 363, 365, 367,                |
| [[,tidem-method,581                        | 431, 448, 522, 523, 536, 544, 546,                |
| [[,topo-method,582                         | 550, 586                                          |
| [[,windrose-method,584                     | adv, 13, 19, 20, 26, 54, 55, 70, 78, 83, 86, 95,  |
| [[<-,adp-method, 585                       | 122, 125, 127, 164, 171, 172, 216,                |
| [[<-,adv-method, 586                       | 266, 341, 346, 351, 355, 360, 410,                |
| [[<-, amsr-method, 588]]                   | 416, 418, 420, 432, 449, 522, 524,                |
| [[<-,argo-method,589                       | 526, 536, 539, 544, 548, 551, 588                 |
| [[<-,bremen-method,591                     | adv-class, 20                                     |
| [[<-,cm-method,592]                        | airRho, 21                                        |
| [[<-,coastline-method,593                  | amsr-class, 22, 84                                |
| [[<-,ctd-method, 594                       | angleRemap, 23                                    |
| [[<-,echosounder-method, 596               | applyMagneticDeclination, 24, 179                 |
| [[<-,g1sst-method,597                      | approx, 28, 90, 91, 107, 108, 158, 281, 409,      |
| [[<-,gps-method, 598                       | 484, 551                                          |
| [[<-,lisst-method, 599                     | approx3d, 25                                      |
| [[<-,lobo-method, 600                      | approxfun, 476                                    |
|                                            |                                                   |

| argo, 13, 19, 26, 27, 28, 31, 34, 70, 78, 83, 86,                                                     | 524–526, 583, 611                                                                                             |
|-------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------|
| 95, 122, 147, 164, 171, 172, 216,                                                                     | as.unit, 51                                                                                                   |
| 269, 369, 410, 416, 418, 420, 434,                                                                    | as. vector, 93, 368                                                                                           |
| 450, 526, 539, 555, 590                                                                               | as.windrose, 52, 307, 465, 540, 541, 585, 612                                                                 |
| argo-class, 27                                                                                        | atan2, 23, 531                                                                                                |
| argoGrid, 26, 27, 28, 31, 34, 147, 269, 369,                                                          | axis, 185, 301                                                                                                |
| 434, 450, 555, 590                                                                                    | axis.POSIXct, 227, 228                                                                                        |
| argoNames2oceNames, 26–28, 29, 34, 147,                                                               | dx13.1 031xct, 227, 220                                                                                       |
| 269, 368, 369, 434, 450, 555, 590                                                                     | bandwidth.kernel, 180                                                                                         |
|                                                                                                       | bcdToInteger, 53                                                                                              |
| argShow, 31                                                                                           | beamName, 13, 17–20, 32, 54, 55, 57–59, 65,                                                                   |
| arrows, 117, 129, 183, 184, 189, 314, 315                                                             | 125–127, 262, 266, 327, 329, 331,                                                                             |
| as.adp, 13, 17, 18, 32, 54, 55, 57–59, 65, 125,                                                       | 334, 335, 337, 341, 346, 351, 355,                                                                            |
| 126, 262, 327, 329, 331, 334, 335,                                                                    | 360, 363, 365, 367, 431, 432, 448,                                                                            |
| <i>337</i> , <i>363</i> , <i>365</i> , <i>367</i> , <i>431</i> , <i>448</i> , <i>522</i> ,            | 449, 522–524, 536, 544, 546, 548,                                                                             |
| 523, 536, 544, 546, 550, 586                                                                          | 550, 551, 586, 588                                                                                            |
| as.argo, 26–28, 31, 33, 147, 269, 369, 434,                                                           | beamToXyz, 13, 17-20, 32, 54, 55, 57-59, 65,                                                                  |
| 450, 555, 590                                                                                         | 125–127, 262, 266, 327, 329, 331,                                                                             |
| as.cm, 34, 70, 71, 272, 372, 436, 452, 558, 593                                                       | 334, 335, 337, 341, 346, 351, 355,                                                                            |
| as.coastline, 35, 45, 76–78, 112, 272, 275,                                                           | 360, 363, 365, 367, 431, 432, 448,                                                                            |
| 374, 376, 437, 452, 559, 594                                                                          | 449, 522–524, 536, 544, 546, 548,                                                                             |
| as.ctd, 36, 45, 48, 69, 75, 86–88, 92, 94, 95,                                                        | 550, 551, 586, 588                                                                                            |
| 98, 149, 225, 247, 252, 280, 312,                                                                     | beamToXyzAdp, 13, 17, 18, 32, 54, 55, 56, 58,                                                                 |
| 314, 319, 377, 379, 380, 383, 385,                                                                    | 59, 65, 125, 126, 260, 262, 327, 329,                                                                         |
| 386, 401, 402, 411, 438, 453,                                                                         | 331, 334, 335, 337, 363, 365, 367,                                                                            |
| 541–543, 562, 595                                                                                     | 431, 448, 522, 523, 536, 544, 546,                                                                            |
| as.echosounder, 39, 122, 123, 131, 281, 282,                                                          | 550, 586                                                                                                      |
| 387, 439, 454, 564, 597                                                                               | beamToXyzAdv, <i>13</i> , <i>17</i> , <i>18</i> , <i>20</i> , <i>32</i> , <i>54</i> , <i>55</i> , <i>57</i> , |
| as.gps, 40, 142, 143, 283, 285, 389, 455, 567,                                                        | 57, 59, 65, 125, 126, 262, 327, 329,                                                                          |
| 599                                                                                                   | 331, 334, 335, 337, 363, 365, 367,                                                                            |
| as.ladp, 41, <i>163</i> , <i>285</i> , <i>455</i> , <i>568</i>                                        | 431, 448, 522–524, 536, 544, 546,                                                                             |
| as.lisst, 42, <i>171</i> , 289, 394, 456, 457, 571,                                                   | 550, 586                                                                                                      |
| 600                                                                                                   | beamUnspreadAdp, 13, 17, 18, 32, 54, 55, 57,                                                                  |
| as.lobo, 43, <i>172</i> , <i>173</i> , <i>290</i> , <i>440</i> , <i>458</i> , <i>572</i> , <i>601</i> | 58, 58, 65, 125, 126, 262, 327, 329,                                                                          |
| as.met, 44, 113, 114, 216, 291, 396, 440, 458,                                                        | 331, 334, 335, 337, 363, 365, 367,                                                                            |
| 574, 602                                                                                              | 431, 448, 522, 523, 536, 544, 546,                                                                            |
| as.oce, 45                                                                                            | 550, 586                                                                                                      |
| as.POSIXct, 37, 41, 105, 106, 162, 337, 338,                                                          | binApply1D, 60, 61, 63, 64, 67, 68                                                                            |
| 342, 347, 351, 352, 356, 371, 429                                                                     | binApply2D, 60, 61, 63, 64, 67, 68                                                                            |
| as.POSIXlt, <i>162</i> , <i>429</i>                                                                   | binAverage, 60, 61, 62, 64, 67, 68                                                                            |
| as.raw, 226                                                                                           | binCount1D, 60, 61, 63, 63, 64, 67, 68                                                                        |
| as.rsk, 38, 46, 295, 402, 410, 412, 413, 443,                                                         | binCount2D, 60, 61, 63, 64, 64, 67, 68                                                                        |
| 460, 577, 606                                                                                         | binmapAdp, 13, 17, 18, 32, 54, 55, 57–59, 65,                                                                 |
| as.sealevel, 47, 298, 402, 403, 416–418,                                                              | 125, 126, 262, 327, 329, 331, 334,                                                                            |
| 444, 462, 515, 578, 607                                                                               | 335, 337, 363, 365, 367, 431, 448,                                                                            |
| as.section, 48, 151, 181, 224, 299, 301, 404,                                                         | 522, 523, 536, 544, 546, 550, 586                                                                             |
| 420–422, 424, 426, 427, 445, 462,                                                                     | binMean1D, 60, 61, 63, 64, 66, 68                                                                             |
| 463, 580, 608                                                                                         | binMean2D, 60, 61, 63, 64, 67, 67, 159, 192,                                                                  |
| as.topo, 50, 116, 153, 305, 405, 447, 464,                                                            | 193, 529                                                                                                      |
| 1 - 1 1 1 1 1 1 1                                                                                     | · · , · ·                                                                                                     |

| bound125, 68 410, 416, 418, 420, 438, 453, 520                                        | 6,         |
|---------------------------------------------------------------------------------------|------------|
| bremen-class, 69 539, 541–543, 562, 595                                               | ,          |
| byteToBinary, 69, 225 ctd-class, 87                                                   |            |
| ctdAddColumn, 13, 89, 99, 198, 213, 226                                               |            |
| cat, 241, 535 ctdDecimate, 38, 75, 86, 88, 90, 94–96, 90                              | 8,         |
| ceiling, 333 103, 104, 149, 247, 252, 280, 31.                                        | 2,         |
| class, 13, 35, 40, 48, 59, 65, 103, 242, 243, 314, 319, 377, 379, 380, 383, 38.       | 5,         |
| 250, 387, 389, 395, 422                                                               | <i>3</i> , |
| cm, 13, 19, 26, 35, 70, 71, 78, 83, 86, 95, 122,  562, 595                            |            |
| 164, 171, 172, 216, 272, 372, 410, ctdFindProfiles, 38, 75, 86, 88, 92, 92,           | 95,        |
| 416, 418, 420, 436, 452, 526, 539, 98, 149, 247, 252, 280, 312, 314.                  |            |
| 210 277 270 280 285 28                                                                | 6,         |
| 336, 393<br>438, 453, 541, 543, 562, 505                                              |            |
| CH-Class, 71                                                                          | 88,        |
| Crivinalile 20 Centalile, 36, 71, 60, 66, 92, 94, 93,                                 |            |
| 96, 149, 247, 252, 257, 260, 312,                                                     |            |
| 314, 319, 377, 379, 380, 382, 383, 38, 38, 38, 38, 38, 38, 38, 38, 3                  |            |
| 363, 360, 396, 436, 433, 350, 351, 410, 416, 418, 420, 438, 453, 52                   |            |
| 541–543, 502, 595                                                                     | ,          |
| Coastilline-Class, 70 CtdTrim 38 75 86 88 02 04 05 06 14                              | 9.         |
| Coastiffiedest, 55, 70, 70, 77, 78, 112, 275,                                         |            |
| 3/4, 3/0, 43/, 452, 559, 594 319 377 379 380 383 385 38                               | ,          |
| coastiinecut, 33, 70, 77, 77, 78, 112, 273,                                           | ,          |
| 3/4, 3/0, 43/, 432, 339, 394 ctdlindateHeader 13 90 98 198 213 2                      | 26         |
| coastlineworld, 13, 19, 20, 33, 70, 70, 77, ctimeToSeconds 99, 161, 163, 220, 222,    |            |
| 78, 83, 80, 93, 112, 122, 104, 171, 527                                               | ,          |
| 172, 199, 216, 275, 374, 376, 410, CHINGLIN 158                                       |            |
| 410, 418, 420, 437, 432, 326, 339, curl 100 143                                       |            |
| 559, 594                                                                              |            |
| coastlineWorldFine, 525 data.frame, 254                                               |            |
| colormap, 79, 83, 119, 154, 192, 229, 230 dataLabel, 102                              |            |
| colorRampPalette, 80 decimate, 103, 122, 167, 392                                     |            |
| colors, 13, 19, 26, 70, 78, 81, 82, 86, 95, 122, decodeHeaderNortek, 104              |            |
| 164, 171, 172, 216, 229, 230, 410, decodeTime, 105, 142                               |            |
| 416, 418, 420, 526, 539 despike, 107, 235, 260, 327, 329, 330, 33.                    | 2.         |
| composite, 83, 84, 85 335, 363, 364, 366                                              | ,          |
| composite, amsr-method, 84 detrend, 108, 323                                          |            |
| composite, list-method, 84 diff, 93, 479                                              |            |
| confint, 133 dir, 426                                                                 |            |
| contour, 186, 231, 278, 301 download.amsr, 22, 84, 109, 112, 114, 116                 | 6.         |
| contourLines, 186 267, 361, 433, 450, 589                                             | -,         |
| convolve, 179, 238 download.coastline, 35, 76–78, 110, 11                             | 1.         |
| coplot, 312, 318 114, 116, 275, 374, 376, 437, 45.                                    |            |
| coriolis, 85 559, 594                                                                 | -,         |
| CRS, 200 download.file, 109, 112–116                                                  |            |
| ctd, 13, 19, 26, 38, 70, 75, 78, 83, 86, 88, 92, download.met, 44, 110, 112, 116, 21. | 5.         |
| 94, 95, 98, 122, 149, 164, 171, 172, 216, 291, 396, 440, 458, 574, 60.                |            |
| 176, 216, 247, 252, 280, 312, 314, download.topo, 51, 110, 112, 114, 114, 30          |            |
| 319, 377, 379, 380, 383, 385, 386, 405, 447, 464, 524–526, 583, 61                    |            |

| drawDirectionField, 116                                                                               | geodDist, 123, 136, 138-141, 579                          |
|-------------------------------------------------------------------------------------------------------|-----------------------------------------------------------|
| drawIsopycnals, 118                                                                                   | geodGc, 137, 138, 140, 141, 205                           |
| drawPalette, 80, 119, 153, 155, 156, 235                                                              | geodXy, <i>137</i> , <i>138</i> , 139, <i>141</i>         |
| , , , , , ,                                                                                           | geodXyInverse, <i>137</i> , <i>138</i> , <i>140</i> , 141 |
| echosounder, 13, 19, 26, 40, 70, 78, 83, 86,                                                          | getNOAA.bathy, <i>116</i>                                 |
| 95, 122, 123, 131, 164, 171, 172,                                                                     | getOption, 133, 145, 147, 149, 151, 227, 300,             |
| 216, 282, 387, 410, 416, 418, 420,                                                                    |                                                           |
|                                                                                                       | 408                                                       |
| 439, 454, 526, 539, 564, 597                                                                          | GMTOffsetFromTz, 106, 142                                 |
| echosounder-class, 122                                                                                | gps-class, 142                                            |
| eclipticalToEquatorial, 124, 128, 161,                                                                | grad, <i>102</i> , 143                                    |
| 163, 218, 219, 429, 466                                                                               | gravity, 144                                              |
| enuToOther, 13, 17–20, 32, 54, 55, 57–59, 65,                                                         | grep, 72                                                  |
| 125, 126, 127, 263, 266, 327, 329,                                                                    | grid, 190, 191, 233, 235, 260                             |
| 331, 334, 335, 337, 341, 346, 351,                                                                    | gsub, 29, 247, 541                                        |
| 355, 360, 363, 365, 367, 431, 432,                                                                    | gsw_C_from_SP, <i>473</i>                                 |
| 448, 449, 522–524, 536, 544, 546,                                                                     | gsw_CT_freezing, 318                                      |
| 548, 550, 551, 586, 588                                                                               | gsw_CT_from_t, 472, 561                                   |
| enuToOtherAdp, 13, 17, 18, 32, 54, 55, 57–59,                                                         | gsw_geo_strf_dyn_height, 476                              |
| 65, 125, 125, 260, 263, 327, 329,                                                                     | gsw_Nsquared, 479                                         |
| 331, 334, 335, 337, 363, 365, 367,                                                                    | gsw_p_from_z, 481                                         |
| 431, 448, 522, 523, 536, 544, 546,                                                                    |                                                           |
| 550, 586                                                                                              | gsw_pt_from_t, 505                                        |
| enuToOtherAdv, 19, 20, 54, 55, 125, 127, 266,                                                         | gsw_SA_from_rho, 501                                      |
|                                                                                                       | gsw_SA_from_SP, 467, 555, 561                             |
| 341, 346, 351, 355, 360, 432, 449,                                                                    | gsw_sound_speed, 498                                      |
| 522, 524, 536, 544, 548, 551, 588                                                                     | gsw_SP_from_C, <i>485</i>                                 |
| equatorialToLocalHorizontal, 124, 128,                                                                | gsw_SR_from_SP,562                                        |
| 161, 163, 218, 219, 429, 466                                                                          | gsw_Turner_Rsubrho,484                                    |
| errorbars, 129                                                                                        | gsw_z_from_p, <i>474</i>                                  |
| expression, <i>51</i> , <i>249</i> , <i>530</i> , <i>549</i> , <i>551</i> , <i>553</i> , <i>555</i> , |                                                           |
| 556, 558–560, 564–566, 568,                                                                           | handleFlags, 28, 91, 145, 147, 149, 151, 424              |
| 571–573, 575, 577, 578, 580,                                                                          | handleFlags,argo-method,146                               |
| 582–584, 587                                                                                          | handleFlags,ctd-method,148                                |
|                                                                                                       | handleFlags, section-method, 150                          |
| factor, 48                                                                                            | handleFlags, vector-method, 152                           |
| filled.contour, 156                                                                                   | head.oce, 152, <i>513</i>                                 |
| fillGap, 130                                                                                          | hist, 292                                                 |
| filter, 103, 177, 179, 180, 244                                                                       | hsv, 80                                                   |
| findBottom, 40, 122, 123, 131, 282, 387, 439,                                                         | 1134, 00                                                  |
| 454, 564, 597                                                                                         | image, 79-81, 153, 155, 156, 192, 262                     |
| findInOrdered, 131                                                                                    | image, 80, 81, 121, 153, 233, 235, 258–260,               |
|                                                                                                       | - · · · · · · · · · · · · · · · · · · ·                   |
| findInterval, 131, 132, 224                                                                           | 264, 267, 282, 286, 287, 296, 297,                        |
| firstFinite, 132                                                                                      | 300                                                       |
| fivenum, 52, 306, 513                                                                                 | integerToAscii, 157                                       |
| format, 12, 282, 535                                                                                  | integrate, 476                                            |
| formatCI, 133                                                                                         | <pre>integrateTrapezoid, 157</pre>                        |
| formatPosition, 134, 321                                                                              | interp, <i>192</i> , <i>193</i>                           |
| fullFilename, 135                                                                                     | interpBarnes, 158, 425, 529, 539                          |
| g1sst-class, 136                                                                                      | julian, <i>162</i>                                        |

| julianCenturyAnomaly, 100, 124, 128, 161,                                                | lookWithin, 176                             |
|------------------------------------------------------------------------------------------|---------------------------------------------|
| 163, 219, 220, 222, 419, 429, 466,                                                       | lowpass, 177                                |
| 527                                                                                      |                                             |
| julianDay, 100, 124, 128, 161, 162, 219, 220,                                            | magneticField, 24, 178                      |
| 222, 419, 429, 466, 527                                                                  | make.names, 372                             |
| 1                                                                                        | makeFilter, <i>104</i> , 179                |
| kernapply, 179, 180                                                                      | makeSection, 181                            |
| kernel, 180                                                                              | map2lonlat, 174, 176, 182, 184, 185, 187,   |
| ladp-class, 163                                                                          | 189, 191, 193, 195–197, 205,                |
| landsat, 13, 19, 26, 70, 78, 83, 86, 95, 122,                                            | 207–210, 212, 240, 428, 533, 534            |
| 164, 167–169, 171, 172, 216, 288,                                                        | mapArrows, 174, 176, 183, 183, 185, 187-189 |
| 393, 410, 416, 418, 420, 456, 526,                                                       | 191, 193, 195–197, 205, 207–210,            |
| 539, 570                                                                                 | 212, 240, 428, 533, 534                     |
| landsat-class, 164                                                                       | mapAxis, 174, 176, 183, 184, 184, 187, 189, |
| landsatAdd, 164, 165, 167, 167, 169, 288,                                                | 191, 193, 195–197, 200, 205,                |
| 393, 456, 569, 570                                                                       | 207–210, 212, 240, 428, 532–534             |
| landsatTrim, 164, 165, 167, 168, 168, 288,                                               | mapContour, 174, 176, 183–185, 186, 189,    |
| 392, 393, 456, 570                                                                       | 191, 193, 195–197, 205, 207–210,            |
| latFormat, 169, <i>170</i> , <i>173</i>                                                  | 212, 240, 278, 428, 533, 534                |
| latlonFormat, 169, 170, 173                                                              | mapCoordinateSystem, 187                    |
| layout, 120, 153, 156, 260                                                               | mapDirectionField, 174, 176, 183-185, 187   |
| legend, 209, 300                                                                         | 188, 191, 193, 195–197, 205,                |
| lines, 195, 198, 212                                                                     | 207–210, 212, 240, 428, 533, 534            |
| lisst, 13, 19, 26, 70, 78, 83, 86, 95, 122, 164,                                         | mapGrid, 174, 176, 183–185, 187, 189, 190,  |
| 170, 172, 216, 410, 416, 418, 420,                                                       | 193, 195–197, 199, 205, 207–213,            |
| 526, 539                                                                                 | 224, 240, 427, 428, 532–534                 |
| lisst-class, 171                                                                         | mapImage, 174, 176, 183–185, 187, 189, 191, |
| list, 37, 83, 85, 97, 145, 146, 148, 150, 151,                                           | 191, 195–197, 205, 207–210, 212,            |
| 249, 322, 376, 378, 379, 381, 383,                                                       | 240, 428, 533, 534                          |
| <i>385</i> , <i>398</i> , <i>421</i> , <i>520</i> , <i>530</i> , <i>536</i> , <i>579</i> | mapLines, 174, 176, 183–187, 189, 191, 193, |
| list.files, 376, 378, 379, 381, 383, 385                                                 | 194, 196, 197, 205, 207–210, 212,           |
| lm, 133, 414, 516                                                                        | 240, 428, 533, 534                          |
| load, 78                                                                                 | mapLocator, 174, 176, 183–185, 187, 189,    |
| lobo, 13, 19, 26, 43, 70, 78, 83, 86, 95, 122,                                           | 191, 193, 195, 196, 197, 205,               |
| 164, 171, 172, 173, 216, 290, 410,                                                       | 207–210, 212, 240, 428, 533, 534            |
| 416, 418, 420, 440, 458, 526, 539,                                                       | mapLongitudeLatitudeXY, 174, 176,           |
| 572, 601                                                                                 | 183–185, 187, 189, 191, 193, 195,           |
| lobo-class, 172                                                                          | 196, 196, 205, 207–210, 212, 240,           |
| locator, 196, 279, 537                                                                   | 428, 533, 534                               |
| log10, 281                                                                               | mapMeridians, 13, 90, 99, 197, 213, 226     |
| logical, 97                                                                              | mapPlot, 77, 174, 176, 182–185, 187,        |
| lonFormat, 169, 170, 173                                                                 | 189–191, 193, 195–197, 198,                 |
| lonlat2map, 174, 176, 182–185, 187, 189,                                                 | 207–210, 212, 225, 239, 240, 268,           |
| 191, 193, 195–197, 205, 207–210,                                                         | 273, 274, 278, 284, 299, 428, 533,          |
| 212, 240, 428, 533, 534                                                                  | 534                                         |
| lonlat2utm, 140, 174, 175, 183–185, 187,                                                 | mapPoints, 174, 176, 183-185, 187, 189, 191 |
| 189, 191, 193, 195–197, 205,                                                             | 193, 195–197, 205, 207, 208–210,            |
| 207–210, 212, 240, 428, 533, 534                                                         | 212, 240, 284, 428, 533, 534                |
| , , , , , , , , , , , , , , , , , , , ,                                                  | , , , , , , , , , , , , , , , , , , , ,     |

| mapPolygon, 174, 176, 183–185, 187, 189,      | oce.colorsCDOM(oce.colorsTwo), 229               |
|-----------------------------------------------|--------------------------------------------------|
| 191, 193, 195–197, 205, 207, 208,             | <pre>oce.colorsChlorophyll(oce.colorsTwo),</pre> |
| 209, 210, 212, 240, 428, 533, 534             | 229                                              |
| mapScalebar, 174, 176, 183–185, 187, 189,     | oce.colorsDensity(oce.colorsTwo), 229            |
| 191, 193, 195–197, 205, 207, 208,             | oce.colorsFreesurface(oce.colorsTwo),            |
| 209, 210, 212, 240, 428, 533, 534             | 229                                              |
| mapText, 174, 176, 183–185, 187, 189, 191,    | oce.colorsGebco, 81, 83, 229, 230, 305           |
| 193, 195–197, 205, 207–209, 210,              | oce.colorsJet, 119, 154, 192                     |
| 212, 240, 428, 533, 534                       | oce.colorsJet(oce.colorsTwo), 229                |
| mapTissot, 174, 176, 183-185, 187, 189, 191,  | oce.colorsOxygen (oce.colorsTwo), 229            |
| 193, 195–197, 200, 205, 207–210,              | oce.colorsPalette(oce.colorsTwo), 229            |
| 211, 240, 428, 533, 534                       | oce.colorsPAR (oce.colorsTwo), 229               |
| mapZones, 13, 90, 99, 198, 212, 226           | oce.colorsPhase(oce.colorsTwo), 229              |
| matchBytes, 213                               | oce.colorsSalinity(oce.colorsTwo), 229           |
| matrixShiftLongitude, 214, 428, 430, 526      | oce.colorsTemperature(oce.colorsTwo),            |
| matrixSmooth, 214                             | 229                                              |
| mean, 60, 61, 536                             | oce.colorsTurbidity(oce.colorsTwo), 229          |
| met, 13, 19, 26, 44, 70, 78, 83, 86, 95, 114, | oce.colorsTwo, 81, 83, 229, 229                  |
| 122, 164, 171, 172, 215, 216, 291,            | oce.colorsVelocity(oce.colorsTwo), 229           |
| 396, 410, 416, 418, 420, 440, 458,            | oce.colorsViridis(oce.colorsTwo), 229            |
| 526, 539, 574, 602                            | oce.colorsVorticity(oce.colorsTwo), 229          |
| met-class, 216                                | oce.contour, 231                                 |
| metNames2oceNames, 217                        | oce.convolve(oceConvolve), 238                   |
| moonAngle, 124, 128, 161, 163, 217, 429, 466  | oce.debug (oceDebug), 240                        |
| . 260                                         | oce.edit(oceEdit), 242                           |
| ncvar_get, 368                                | oce.filter(oceFilter), 243                       |
| nls, 97, 133                                  | oce.grid, 156, 233, 235, 262, 282, 318           |
| normalizePath, 135                            | oce.magic(oceMagic), 246                         |
| numberAsHMS, 100, 161, 163, 220, 222, 419,    | oce.plot.ts, 155, 228, 233, 234, 259, 264,       |
| 527                                           | 268, 271, 288, 291, 293, 295, 537                |
| numberAsPOSIXct, 100, 161–163, 220, 221,      | oce.pmatch, 268                                  |
| 419, 429, 519, 527                            | oce.pmatch(ocePmatch), 248                       |
| oce, <i>145</i> , 222                         | oce.smooth (oceSmooth), 250                      |
| oce-class, 83, 85, 223                        | oce.spectrum(oceSpectrum), 251                   |
| oce-defunct, 181                              | oce.write.table, 236                             |
| oce-defunct (oce-deprecated), 224             | oceApprox, 237                                   |
| oce-deprecated, 12, 69, 89, 98, 131, 197,     | oceColors(oce.colorsTwo), 229                    |
| 199, 212, 224, 225, 246, 278                  | oceColors9A (oce.colorsTwo), 229                 |
| oce-package (oce), 222                        | oceColors9B (oce.colorsTwo), 229                 |
| oce.approx, 90                                | oceColorsCDOM (oce.colorsTwo), 229               |
| oce.approx(oceApprox), 237                    | oceColorsChlorophyll (oce.colorsTwo),            |
| oce.as.POSIXlt, 13, 90, 99, 198, 213, 225     | 229                                              |
| oce.as.raw, 226                               | oceColorsDensity(oce.colorsTwo), 229             |
| oce.axis.POSIXct, 227, 232, 234, 235          | oceColorsFreesurface(oce.colorsTwo),             |
| oce.colors (oce.colorsTwo), 229               | 229                                              |
| oce.colors.gebco (oce.colorsGebco), 229       | oceColorsGebco (oce.colorsGebco), 229            |
| oce.colors9A (oce.colorsTwo), 229             | oceColorsJet (oce.colorsTwo), 229                |
| oce colors9B (oce colorsTwo) 229              | oceColorsOxygen(oce_colorsTwo) 229               |

| oceColorsPalette (oce.colorsTwo), 229                                             | optim, <i>141</i>                                         |
|-----------------------------------------------------------------------------------|-----------------------------------------------------------|
| oceColorsPAR (oce.colorsTwo), 229                                                 |                                                           |
| oceColorsPhase (oce.colorsTwo), 229                                               | pairs, 292, 293                                           |
| oceColorsSalinity (oce.colorsTwo), 229                                            | par, 120, 153, 155, 185, 200, 227, 233–235,               |
| oceColorsTemperature (oce.colorsTwo),                                             | 259, 264, 268, 271, 273, 278, 279,                        |
| 229                                                                               | 282, 284, 290, 291, 295, 297, 300,                        |
| oceColorsTurbidity (oce.colorsTwo), 229                                           | 303, 305, 306, 311, 313, 315, 317,                        |
| oceColorsTwo, 153                                                                 | 318                                                       |
| oceColorsTwo(oce.colorsTwo), 229                                                  | parse, <i>249</i>                                         |
| oceColorsVelocity (oce.colorsTwo), 229                                            | parse_date_time, 224, 225                                 |
| oceColorsViridis, 83                                                              | parseLatLon, 257                                          |
| oceColorsViridis (oce.colorsTwo), 229                                             | plot, 117, 225, 235, 263, 270, 271, 278, 279,             |
| oceColorsVorticity (oce.colorsTwo), 229                                           | 292, 295, 311                                             |
| oceContour (oce.contour), 231                                                     | plot,adp-method,258                                       |
|                                                                                   | plot,adv-method,263                                       |
| oceConvolve, 238                                                                  | plot,amsr-method,266                                      |
| oceCRS, 174, 176, 183–185, 187, 189, 191,                                         | plot, argo-method, 267                                    |
| 193, 195–197, 205, 207–210, 212,                                                  | plot, bremen-method, 269                                  |
| 239, 428, 533, 534                                                                | plot,cm-method, 270                                       |
| oceDebug, 240, <i>535</i>                                                         | plot, coastline-method, 272                               |
| oceDeleteData, 241                                                                | plot,ctd-method, 275                                      |
| oceDeleteMetadata, 242                                                            | plot, echosounder-method, 280                             |
| oceEdit, 242                                                                      | plot,gps-method, 283                                      |
| oceFilter, 243                                                                    | plot, ladp-method, 285                                    |
| oceGetData, 245, <i>561</i>                                                       | plot,landsat-method, 286                                  |
| oceGetMetadata, 245                                                               | plot,lisst-method,288                                     |
| oceMagic, 222, 224, 246, 338, 343, 348, 352,                                      | plot, lobo-method, 289                                    |
| 357, 397, 398                                                                     | plot, met-method, 290                                     |
| oceNames2whpNames, 38, 75, 86, 88, 92, 94,                                        | plot, oce-method, 292                                     |
| 95, 98, 149, 247, 252, 257, 280, 312,                                             | plot,odf-method, 293                                      |
| 314, 319, 377, 379–381, 383, 385,                                                 | plot,rsk-method, 294                                      |
| <i>386</i> , <i>438</i> , <i>453</i> , <i>530</i> , <i>531</i> , <i>541–543</i> , | plot, satellite-method, 296                               |
| 562, 595                                                                          | plot, sealevel-method, 297                                |
| ocePmatch, 248                                                                    | plot, section-method, 298                                 |
| oceSetData, 12, 13, 38, 88, 89, 224, 249                                          | plot, tidem-method, 302                                   |
| oceSetMetadata, 38, 88, 250                                                       | plot, topo-method, 304                                    |
| oceSmooth, 250                                                                    | plot, windrose-method, 306                                |
| oceSpectrum, 251                                                                  | plot.adp(plot,adp-method), 258                            |
| oceUnits2whpUnits, 38, 75, 86, 88, 92, 94,                                        | plot.adv (plot,adv-method), 263                           |
| 95, 98, 149, 247, 252, 257, 280, 312,                                             | plot.amsr(plot,amsr-method), 266                          |
| 314, 319, 377, 379–381, 383, 385,                                                 | plot.argo(plot,argo-method), 267                          |
| 386, 438, 453, 530, 531, 541–543,                                                 | plot.bremen (plot,bremen-method), 269                     |
| 562, 595                                                                          | plot.cm (plot, cm-method), 270                            |
| odf-class, 253                                                                    | plot.coastline (plot, coastline-method).                  |
| ODF2oce, 45, 253, 254, 257, 294, 381, 399,                                        | 272                                                       |
| 442, 460, 576, 605                                                                | plot.ctd(plot,ctd-method), 275                            |
| ODFNames2oceNames, 75, 217, 247, 252–254,                                         | plot.eta (plot,eta method), 273<br>plot.default, 155, 313 |
| 255, 294, 381, 398, 399, 442, 460,                                                | plot.derault, 133, 313<br>plot.echosounder                |
| 530, 531, 541, 542, 576, 605                                                      | (plot, echosounder-method), 280                           |
| 550, 551, 571, 572, 570, 005                                                      | (p±00,0011001 iiic c1100), 200                            |

| plot.gps (plot,gps-method), 283                | png, <i>193</i>                                                                                               |
|------------------------------------------------|---------------------------------------------------------------------------------------------------------------|
| plot.ladp(plot,ladp-method), 285               | points, 207, 284                                                                                              |
| plot.landsat(plot,landsat-method), 286         | polygon, 192, 193, 208, 225                                                                                   |
| plot.lisst(plot,lisst-method), 288             | POSIXct, 221, 413                                                                                             |
| plot.lobo(plot,lobo-method), 289               | POSIXt, 37                                                                                                    |
| plot.met(plot,met-method), 290                 | predict.tidem, 304, 319, 463, 515, 518-521                                                                    |
| plot.oce(plot,oce-method), 292                 | 582, 610                                                                                                      |
| plot.odf(plot,odf-method), 293                 | pretty, 60, 61, 63, 64, 66, 67, 79, 80, 154,                                                                  |
| plot.rsk(plot,rsk-method), 294                 | 192, 278                                                                                                      |
| plot.satellite(plot,satellite-method),         | prettyPosition, 320                                                                                           |
| 296                                            | processingLog<-, 321                                                                                          |
| plot.sealevel(plot,sealevel-method),           | processingLogAppend, 322, 322                                                                                 |
| 297                                            | processingLogItem, 322                                                                                        |
| plot.section(plot,section-method), 298         | processingLogShow, 323                                                                                        |
| plot.tidem (plot,tidem-method), 302            | project, 77, 182, 268                                                                                         |
| plot.topo(plot,topo-method), 304               | pwelch, 323                                                                                                   |
| plot.ts, 235                                   | •                                                                                                             |
| plot.windrose (plot,windrose-method),          | quantile, 159                                                                                                 |
| 306                                            | 444                                                                                                           |
| plotInset, 274, 279, 284, 307, 312, 318        | range, <i>79</i>                                                                                              |
| plotPolar, 308                                 | rangeExtended, 79, 325                                                                                        |
| plotProfile, 38, 75, 86, 88, 92, 94, 95, 98,   | rangeLimit, 325                                                                                               |
| 149, 247, 252, 262, 266, 267, 269,             | raw, 22, 32, 449, 548, 551                                                                                    |
| 270, 272, 275, 280, 285, 289–291,              | rawToBits, 70                                                                                                 |
| 294–296, 298, 301, 304, 305, 307,              | read.ad2cp, 13, 17, 18, 32, 54, 55, 57–59, 65                                                                 |
| 309, 313, 314, 319, 377, 379–381,              | 125, 126, 263, 326, 329, 331, 334,                                                                            |
| 383, 385, 386, 438, 453, 519,                  | 335, 337, 363, 365, 367, 431, 448,                                                                            |
| 541–543, 562, 595                              | 522, 523, 536, 544, 546, 550, 586                                                                             |
| plotScan, 38, 75, 86, 88, 92, 94–98, 149, 247, | read.adp, 13, 17, 18, 32, 54, 55, 57–59, 65,                                                                  |
| 252, 262, 266, 267, 269, 270, 272,             | 104, 105, 125, 126, 260, 263, 327,                                                                            |
| 275, 280, 285, 289–291, 294–296,               | 328, 331, 334, 335, 337, 363, 365,                                                                            |
| 298, 301, 304, 305, 307, 312, 313,             | 367, 431, 448, 522, 523, 536, 544,                                                                            |
| 319, 377, 379–381, 383, 385, 386,              | 546, 550, 586                                                                                                 |
| 438, 453, 519, 541–543, 562, 595               | read.adp.nortek, 13, 17, 18, 32, 54, 55,                                                                      |
| plotSticks, 314                                | 57–59, 65, 125, 126, 263, 327, 329,                                                                           |
| plotTaylor, 315                                | 329, 334, 335, 337, 342, 346, 351,                                                                            |
| plotTS, 38, 75, 86, 88, 92, 94, 95, 98, 118,   | 356, 363, 365, 367, 431, 448, 522,                                                                            |
| 119, 149, 233, 247, 252, 262, 266,             | 523, 536, 544, 546, 550, 586                                                                                  |
| 267, 269, 270, 272, 275, 280, 285,             | read.adp.rdi, <i>13</i> , <i>17</i> , <i>18</i> , <i>32</i> , <i>54</i> , <i>55</i> , <i>57</i> – <i>59</i> , |
| 289–291, 294–296, 298, 301, 304,               | 65, 125, 126, 263, 327, 329, 331,                                                                             |
| 305, 307, 312–314, 317, 377,                   | 331, 335, 337, 363, 365, 367, 431,                                                                            |
| 379–381, 383, 385, 386, 438, 453,              | 448, 522, 523, 536, 544, 546, 550,                                                                            |
| 519, 541–543, 562, 595                         | 586                                                                                                           |
| pmatch, 87, 239, 248, 549, 551, 553, 555,      | read.adp.sontek, 13, 17, 18, 32, 54, 55,                                                                      |
| 557–559, 561, 564, 565, 567, 568,              | 57–59, 65, 125, 126, 263, 327, 329,                                                                           |
| 571, 572, 574, 576–578, 580, 582,              | 331, 334, 334, 337, 342, 346, 351,                                                                            |
| 583, 585, 586, 588–591, 593–596,               | 356, 363, 365, 367, 431, 448, 522,                                                                            |
| 598–604 606–609 611 612                        | 523 536 544 546 550 586                                                                                       |

```
read.adp.sontek.serial, 13, 17, 18, 32, 54,
  read.coastline.openstreetmap, 35, 76–78,
         55, 57–59, 65, 125, 126, 263, 327,
  112, 275, 374, 376, 437, 452, 559,
         329, 331, 334, 335, 335, 363, 365,
  594
         367, 431, 448, 522, 523, 536, 544,
  read.coastline.shapefile, 35, 76–78, 112,
         546, 550, 586
  275, 374, 375, 437, 452, 559, 594
read.adv, 19, 20, 54, 55, 58, 104, 105, 125,
  read.csv, 542
         127, 266, 329, 337, 346, 351, 355,
  read.ctd, 12, 38, 75, 86, 88, 92, 94, 95, 98,
         360, 432, 449, 522, 524, 536, 544,
  149, 222, 224, 247, 252, 257, 280,
         547, 548, 551, 588
  312, 314, 319, 376, 379–381, 383,
read.adv.nortek, 19, 20, 54, 55, 125, 127,
  385, 386, 398, 438, 453, 541–543,
         266, 341, 342, 351, 355, 360, 432,
  562, 595
         449, 522, 524, 536, 544, 548, 551,
  read.ctd.itp, 38, 75, 86, 88, 92, 94, 95, 98,
         588
  149, 247, 252, 280, 312, 314, 319,
  377, 377, 380, 381, 383, 385, 386,
read.adv.sontek.adr, 19, 20, 54, 55, 125,
         127, 266, 341, 346, 346, 355, 360,
   438, 453, 541–543, 562, 595
         432, 449, 522, 524, 536, 544, 548,
  read.ctd.odf, 38, 75, 86, 88, 92, 94, 95, 98,
         551,588
  149, 247, 252–255, 257, 280, 294,
read.adv.sontek.serial, 19, 20, 54, 55,
  312, 314, 319, 376–379, 379, 381,
         125, 127, 266, 341, 346, 351, 351,
  383, 385, 386, 399, 438, 442, 453,
         360, 432, 449, 522, 524, 536, 544,
  460, 541–543, 562, 576, 595, 605
         548, 551, 588
  read.ctd.sbe, 38, 71, 75, 86-88, 92, 94, 95,
  98, 149, 222, 247, 252, 280, 312,
read.adv.sontek.text, 19, 20, 54, 55, 125,
  314, 319, 376–381, 381, 383, 385,
         127, 266, 341, 346, 351, 355, 356,
         432, 449, 522, 524, 536, 544, 548,
  386, 438, 453, 529, 541–543, 561,
  562, 595
         551, 588
read.amsr, 22, 84, 110, 267, 361, 433, 450,
  read.ctd.woce, 38, 75, 86, 88, 92, 94, 95, 98,
  149, 247, 252, 280, 312, 314, 319,
  377, 379–381, 383, 383, 386, 438,
read.aquadopp, 13, 17, 18, 32, 54, 55, 57–59,
  453, 541–543, 562, 595
         65, 125, 126, 263, 327, 329, 331,
         334, 335, 337, 362, 365, 367, 431,
  read.ctd.woce.other, 38, 75, 86, 88, 92, 94,
  95, 98, 149, 247, 252, 280, 312, 314,
         448, 522, 523, 536, 544, 546, 550,
  319, 377, 379–381, 383, 385, 385,
         586
   438, 453, 541–543, 562, 595
read.aquadoppHR, 13, 17, 18, 32, 54, 55,
  read.echosounder, 40, 122, 123, 131, 281,
         57–59, 65, 125, 126, 263, 327, 329,
         331, 334, 335, 337, 363, 363, 367,
  282, 386, 439, 454, 564, 597
  read.g1sst, 136, 296, 388, 415, 461
         431, 448, 522, 523, 536, 544, 546,
         550, 586
  read.gps, 40, 41, 142, 143, 283, 285, 389,
read.aquadoppProfiler, 13, 17, 18, 32, 54,
  455, 567, 599
  read.index, 390
         55, 57–59, 65, 125, 126, 263, 327,
         329, 331, 334, 335, 337, 363, 365,
  read.landsat, 164, 165, 167-169, 286, 288,
         365, 431, 448, 522, 523, 536, 544,
  391, 456, 569, 570
         546, 550, 586
  read.lisst, 42, 171, 288, 289, 393, 456, 457,
read.argo, 26–29, 31, 33, 34, 147, 269, 367,
  571,600
         434, 450, 555, 590
  read. lobo, 172, 289, 394, 398, 457
read.bremen, 69, 270, 370, 451, 557, 592
  read.met, 44, 114, 216, 291, 395, 440, 458,
read.cm, 35, 70, 71, 270, 272, 371, 436, 452,
   574, 602
         558, 593
  read.netcdf, 396
  read.oce, 17, 20, 54, 167, 222, 246, 338, 343,
read.coastline, 35, 76, 272, 373, 398, 452
```

| 348, 352, 357, 393, 394, 397, 448,             | 404, 410, 416, 418, 420, 421, 422,                 |
|------------------------------------------------|----------------------------------------------------|
| 452, 454, 457, 459, 460, 462                   | 424, 426, 427, 445, 463, 526, 539,                 |
| read.odf, 253, 254, 257, 294, 380, 381, 398,   | 561, 580, 608                                      |
| 442, 459, 460, 576, 605                        | section-class, 421                                 |
| read.rsk, 38, 47, 294, 295, 398, 400, 410,     | sectionAddCtd (sectionAddStation), 422             |
| 412, 413, 443, 460, 530, 577, 606              | sectionAddStation, 49, 151, 301, 404, 420,         |
| read.sealevel, 48, 297, 298, 398, 402,         | 421, 422, 424, 426, 427, 445, 463,                 |
| 416–418, 444, 462, 515, 578, 607               | 580, 608                                           |
| read.section, 49, 151, 299, 301, 403,          | sectionGrid, 28, 49, 151, 301, 404, 420-422,       |
| 420–422, 424, 426, 427, 445, 462,              | 423, 426, 427, 445, 463, 580, 608                  |
| 463, 580, 608                                  | sectionSmooth, 49, 151, 301, 404, 420–422,         |
| read.topo, 50, 51, 114–116, 153, 305, 405,     | 424, 424, 427, 445, 463, 580, 608                  |
| 447, 464, 524–526, 583, 611                    | sectionSort, 49, 151, 301, 404, 420–422,           |
| readTIFF, 391                                  | 424, 426, 426, 445, 463, 580, 608                  |
| renameData, 72, 406                            | segments, 129                                      |
| rep, 127, 315                                  | seq, 28, 80, 159, 423, 425                         |
| rescale, 406                                   | seq_along, 108, 158, 313                           |
| resizableLabel, 407                            | shiftLongitude, 174, 176, 183–185, 187,            |
| retime, 408                                    | 189, 191, 193, 195–197, 205,                       |
| rgb, 80, 287                                   |                                                    |
| round, <i>119</i>                              | 207–210, 212, 214, 240, 427, 430, 533, 534         |
| Rprofile, 78                                   |                                                    |
| rsk, 13, 19, 26, 47, 70, 78, 83, 86, 95, 122,  | show, 88, 123                                      |
| 164, 171, 172, 216, 295, 402, 409,             | showMetadataItem, 428                              |
| 410, 412, 413, 416, 418, 420, 443,             | siderealTime, 124, 128, 161, 163, 219, 429,<br>466 |
| 460, 526, 539, 577, 606                        |                                                    |
| rsk-class, 410                                 | smooth, 108, 250, 251, 281, 480                    |
| rsk2ctd, 38, 411                               | smooth.spline, 93, 425, 479, 480, 484              |
| rskPatm, 47, 295, 402, 410, 412, 413, 443,     | smoothScatter, 259, 261, 264, 265, 271, 278,       |
| 460, 577, 606                                  | 295, 311, 318                                      |
| rskToc, 47, 295, 402, 410, 412, 413, 443, 460, | spectrum, 251, 323, 324                            |
| 577, 606                                       | standardDepths, 28, 423, 430                       |
| runlm, 414                                     | standardizeLongitude, 214, 428, 430                |
| runmed, <i>107</i>                             | stdout, <i>543</i>                                 |
|                                                | str, 459, 535                                      |
| satellite-class, 415                           | strptime, 155, 259, 264, 268, 271, 282, 288,       |
| sealevel, 13, 19, 26, 48, 70, 78, 83, 86, 95,  | 291, 295, 537                                      |
| 122, 164, 171, 172, 216, 298, 403,             | subset, 409, 539, 540                              |
| 410, 416, 417, 418, 420, 444, 462,             | subset,adp-method,431                              |
| 526, 539, 578, 607                             | subset,adv-method,432                              |
| sealevel-class, 417                            | subset,amsr-method,433                             |
| sealevelTuktoyaktuk, 13, 19, 26, 48, 70, 78,   | subset, argo-method, 434                           |
| 83, 86, 95, 122, 164, 171, 172, 216,           | subset,cm-method,435                               |
| 298, 403, 410, 416, 417, 417, 420,             | subset, coastline-method, 436                      |
| 444, 462, 526, 539, 578, 607                   | subset,ctd-method,437                              |
| secondsToCtime, 100, 161, 163, 220, 222,       | subset, echosounder-method, 438                    |
| 419, 527                                       | subset,lobo-method,439                             |
| section, 13, 19, 26, 49, 70, 78, 83, 86, 95,   | subset, met-method, 440                            |
| 122 151 164 171 172 216 301                    | subset ace-method 223 441                          |

| subset, odf-method, 442                                           | swBeta, 468-470, 470, 472, 474-476, 478,    |
|-------------------------------------------------------------------|---------------------------------------------|
| subset, rsk-method, 442                                           | 480, 481, 483, 484, 486, 487,               |
| subset, sealevel-method, 443                                      | 489–495, 497, 498, 500–504, 506,            |
| subset, section-method, 444                                       | 507, 509–512                                |
| subset, topo-method, 446                                          | swConservativeTemperature, 468-471, 471,    |
| subset.data.frame, <i>431–433</i> , <i>435</i> , <i>438–440</i> , | 474–476, 478, 480, 481, 483, 484,           |
| 442, 443, 446                                                     | 486, 487, 489–495, 497, 498,                |
| subtractBottomVelocity, 447                                       | 500–504, 506, 507, 509–512                  |
| summary,adp,missing-method                                        | swCSTp, 468–472, 473, 475, 476, 478, 480,   |
| (summary,adp-method),448                                          | 481, 483, 484, 486, 487, 489–495,           |
| summary, adp-method, 448                                          | 497, 498, 500–504, 506, 507,                |
| summary, adv-method, 449                                          | 509–512                                     |
| summary, amsr-method, 449                                         | swDepth, 87, 300, 468-472, 474, 474, 476,   |
| summary, argo-method, 450                                         | 478, 480, 481, 483, 484, 486, 487,          |
| summary, bremen-method, 451                                       | 489–495, 497, 498, 500–504, 506,            |
| summary,cm-method,451                                             | 507, 509–512, 561                           |
| summary, coastline-method, 452                                    | swDynamicHeight, 468—472, 474, 475, 475,    |
| summary,ctd-method,453                                            | 478, 480, 481, 483, 484, 486, 487,          |
| summary, echosounder-method, 454                                  | 489–495, 497, 498, 500–504, 506,            |
| summary, gps-method, 454                                          | 507, 509–512, 579                           |
| summary, ladp-method, 455                                         | swLapseRate, 468–472, 474–476, 477, 480,    |
| summary, landsat-method, 456                                      | 481, 483, 484, 486, 487, 489–495,           |
| summary, lisst-method, 456                                        | 497, 498, 500–504, 506, 507,                |
| summary, lobo-method, 457                                         | 509–512                                     |
| summary, met-method, 458                                          | swN2, 88, 279, 310–312, 468–472, 474–476,   |
| summary, oce-method, 223, 459                                     | 478, 479, 481, 483, 484, 486, 487,          |
| summary, odf-method, 459                                          | 489–495, 497, 498, 500–504, 506,            |
| summary, rsk-method, 460                                          | 507, 509–512, 561                           |
| summary, satellite-method, 461                                    | swPressure, 372, 468–472, 474–476, 478,     |
| summary, sealevel-method, 461                                     | 480, 481, 483, 484, 486, 487,               |
| summary, section-method, 462                                      | 489–495, 497, 498, 500–504, 506,            |
| summary, tidem-method, 463                                        | 507, 509–512                                |
| summary, topo-method, 464                                         | swRho, 36, 72, 176, 468–476, 478, 480, 481, |
| summary, windrose-method, 465                                     | 482, 484–495, 497, 498, 500–512,            |
| summary, adp (summary, adp-method), 448                           | 561                                         |
| sunAngle, 124, 128, 161, 163, 219, 429, 465                       | swRrho, 468–472, 474–476, 478, 480, 481,    |
| swAbsoluteSalinity, 467, 469–472,                                 | 483, 483, 486, 487, 489–495, 497,           |
| 474–476, 478, 480, 481, 483, 484,                                 | 498, 500–504, 506, 507, 509–512,            |
| 486, 487, 489–495, 497, 498,                                      | 561                                         |
| 500–504, 506, 507, 509–512                                        | swSCTp, 36, 37, 87, 468–476, 478, 480, 481, |
| swAlpha, 468, 468, 470–472, 474–476, 478,                         | 483, 484, 485, 487, 489–495, 497,           |
| 480, 481, 483, 484, 486, 487,                                     | 498, 500–504, 506, 507, 509–512             |
| 489–495, 497, 498, 500–504, 506,                                  | swSigma, 468–472, 474–476, 478, 480, 481,   |
| 507, 509–512                                                      | 483, 484, 486, 486, 489–495, 497,           |
| swAlphaOverBeta, 468, 469, 469, 471, 472,                         | 498, 500–504, 506, 507, 509–512             |
| 474–476, 478, 480, 481, 483, 484,                                 | swSigma0, 468–472, 474–476, 478, 480, 481,  |
| 486, 487, 489–495, 497, 498,                                      | 483, 484, 486, 487, 488, 490–495,           |
| 500–504, 506, 507, 509–512                                        | 497, 498, 500–504, 506, 507,                |
| 500 50 <del>1</del> , 500, 507, 503–512                           | 777, 770, 500 <del>-</del> 507, 500, 507,   |

```
509–512, 562
  507, 509-512
  swThermalConductivity, 468-472, 474-476,
swSigma1, 468-472, 474-476, 478, 480, 481,
  478, 480, 481, 483, 484, 486, 487,
         483, 484, 486, 487, 489, 489,
  489-495, 497, 498, 500-503, 504,
         491-495, 497, 498, 500-504, 506,
         507, 509–512, 562
  506, 507, 509-512
   swTheta, 223, 468-472, 474-476, 478, 480,
swSigma2, 468-472, 474-476, 478, 480, 481,
  481, 483, 484, 486, 487, 489–495,
         483, 484, 486, 487, 489, 490, 490,
  497, 498, 500-504, 505, 507,
         492-495, 497, 498, 500-504, 506,
  509-512, 561, 562
         507, 509–512, 562
   swTSrho, 468–472, 474–476, 478, 480, 481,
swSigma3, 468-472, 474-476, 478, 480, 481,
  483, 484, 486, 487, 489-495, 497,
         483, 484, 486, 487, 489–491, 491,
  498, 500–504, 506, 507, 509–512
         493-495, 497, 498, 500-504, 506,
   swViscosity, 468-472, 474-476, 478, 480,
         507, 509–512, 562
  481, 483, 484, 486, 487, 489–495,
swSigma4, 468–472, 474–476, 478, 480, 481,
  497, 498, 500-504, 506, 507, 508,
         483, 484, 486, 487, 489–492, 492,
  509-512
         494, 495, 497, 498, 500–504, 506,
   swZ, 87, 468-472, 474-476, 478, 480, 481,
         507, 509-512, 562
  483, 484, 486, 487, 489–495, 497,
swSigmaT, 468-472, 474-476, 478, 480, 481,
  498, 500–504, 506, 507, 509, 509,
         483, 484, 486, 487, 489–493, 493,
  510-512, 562
         495, 497, 498, 500-504, 506, 507,
  Sys.time, 322
         509-512
swSigmaTheta, 468-472, 474-476, 478, 480,
  T68fromT90, 468–472, 474–476, 478,
         481, 483, 484, 486, 487, 489-494,
  480-484, 486-498, 500-504, 506,
         494, 497, 498, 500–504, 506, 507,
  507, 509, 510, 511, 512
         509-512, 562
  T90fromT48, 399, 468-472, 474-476, 478,
swSoundAbsorption, 468-472, 474-476, 478,
  480, 481, 483, 484, 486, 487,
         480, 481, 483, 484, 486, 487,
  489-495, 497, 498, 500-504, 506,
         489-495, 496, 498, 500-504, 506,
  507, 509, 510, 511, 512
         507, 509-512
  T90fromT68, 86, 87, 95, 176, 382, 399,
swSoundSpeed, 387, 468-472, 474-476, 478,
  468-472, 474-476, 478, 480, 481,
         480, 481, 483, 484, 486, 487,
  483, 484, 486, 487, 489-495, 497,
         489-495, 497, 497, 500-504, 506,
  498, 500-504, 506, 507, 509-511.
         507, 509-512
  512, 561
swSpecificHeat, 468-472, 474-476, 478,
  tail.oce, 152, 513
         480, 481, 483, 484, 486, 487,
   text, 210
         489–495, 497, 498, 499, 501–504,
   threenum, 513
         506, 507, 509-512
   tidedata, 303, 304, 320, 463, 514, 518-521,
swSpice, 468-472, 474-476, 478, 480, 481,
  582,610
         483, 484, 486, 487, 489-495, 497,
   tidem, 304, 316, 319, 320, 463, 514, 515, 515,
         498, 500, 500, 502–504, 506, 507,
  519–521, 582, 610
         509-512, 562, 579
   tidem-class, 519
swSTrho, 468-472, 474-476, 478, 480, 481,
   tidemAstron, 304, 320, 463, 515, 518, 519,
         483, 484, 486, 487, 489-495, 497,
  519, 521, 582, 610
         498, 500, 501, 501, 503, 504, 506,
   tidemVuf, 304, 320, 463, 515, 518–520, 520,
         507, 509-512
  582,610
  titleCase, 521
swTFreeze, 318, 468-472, 474-476, 478, 480,
         481, 483, 484, 486, 487, 489–495,
   toEnu, 13, 17-20, 32, 54, 55, 57-59, 65,
         497, 498, 500-502, 502, 504, 506,
  125–127, 263, 266, 327, 329, 331,
```

| 334, 335, 337, 341, 346, 351, 355,                                               | webtide, 537                                                                                                 |
|----------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------|
| 360, 363, 365, 367, 431, 432, 448,                                               | which, <i>213</i>                                                                                            |
| 449, 521, 523, 524, 536, 544, 546,                                               | wind, 13, 19, 26, 70, 78, 83, 86, 95, 122, 160,                                                              |
| 548, 550, 551, 586, 588                                                          | 164, 171, 172, 216, 410, 416, 418,                                                                           |
| toEnuAdp, 13, 17, 18, 32, 54, 55, 57–59, 65,                                     | 420, 526, 539                                                                                                |
| 125, 126, 263, 327, 329, 331, 334,                                               | window.oce, 539                                                                                              |
| 335, 337, 363, 365, 367, 431, 448,                                               | windrose-class, 540                                                                                          |
| 522, 522, 536, 544, 546, 550, 586                                                | woceNames2oceNames, 38, 75, 86, 88, 92, 94,                                                                  |
| toEnuAdv, 19, 20, 54, 55, 125, 127, 266, 341,                                    | 95, 98, 149, 247, 252, 257, 280, 312,                                                                        |
| 346, 351, 355, 360, 432, 449, 522,                                               | 314, 319, 377, 379–381, 383, 385,                                                                            |
| 523, 536, 544, 548, 551, 588                                                     | <i>386</i> , <i>404</i> , <i>438</i> , <i>453</i> , <i>530</i> , <i>531</i> , 541,                           |
| topo-class, 524                                                                  | 542, 543, 562, 595                                                                                           |
| topoInterpolate, <i>51</i> , <i>116</i> , <i>305</i> , <i>405</i> , <i>447</i> , | woceUnit2oceUnit, 38, 75, 86, 88, 92, 94, 95,                                                                |
| 464, 524, 524, 526, 583, 611                                                     | 98, 149, 247, 252, 257, 280, 312,                                                                            |
| topoWorld, 13, 19, 26, 51, 70, 78, 83, 86, 95,                                   | 314, 319, 377, 379–381, 383, 385,                                                                            |
| 116, 122, 164, 171, 172, 216, 305,                                               | <i>386</i> , <i>438</i> , <i>453</i> , <i>530</i> , <i>531</i> , <i>541</i> , 542,                           |
| 405, 410, 416, 418, 420, 447, 464,                                               | 543, 562, 595                                                                                                |
| 524, 525, 525, 539, 583, 611                                                     | write.ctd, 38, 75, 86, 88, 92, 94, 95, 98, 149,                                                              |
| trimString, 368, 526                                                             | 247, 252, 280, 312, 314, 319, 377,                                                                           |
| ts, 47                                                                           | 379–381, 383, 385, 386, 438, 453,                                                                            |
| txtProgressBar, 327, 329, 330, 332, 335,                                         | 541, 542, 542, 562, 595                                                                                      |
| 336, 363, 364, 366                                                               | write.table, 236                                                                                             |
| unabbreviateYear, 100, 161, 163, 220, 222,                                       | xyzToEnu, <i>13</i> , <i>17–20</i> , <i>32</i> , <i>54</i> , <i>55</i> , <i>57–59</i> , <i>65</i> ,          |
| 419, 527                                                                         | 125–127, 263, 266, 327, 329, 331,                                                                            |
| undriftTime, 527                                                                 | 334, 335, 337, 341, 346, 351, 355,                                                                           |
| unduplicateNames, 528                                                            | 360, 363, 365, 367, 431, 432, 448,                                                                           |
| ungrid, 529                                                                      | 449, 522–524, 536, 544, 546, 548,                                                                            |
| uniroot, 481                                                                     | 550, 551, 586, 588                                                                                           |
| unitFromString, 75, 247, 252, 257, 530, 531,                                     | xyzToEnuAdp, <i>13</i> , <i>17</i> , <i>18</i> , <i>32</i> , <i>54</i> , <i>55</i> , <i>57</i> – <i>59</i> , |
| 541, 542                                                                         | 65, 125, 126, 260, 263, 327, 329,                                                                            |
|                                                                                  | 331, 334, 335, 337, 363, 365, 367,                                                                           |
| unitFromStringRsk, 75, 247, 252, 257, 530,                                       | 431, 448, 522, 523, 536, 544, 544,                                                                           |
| 530, 541, 542                                                                    | 550, 586                                                                                                     |
| unwrapAngle, 531                                                                 | xyzToEnuAdv, 19, 20, 54, 55, 125, 127, 266,                                                                  |
| useHeading, 532                                                                  | 341, 346, 351, 355, 360, 432, 449,                                                                           |
| usrLonLat, 174, 176, 183–185, 187, 189, 191,                                     | 522, 524, 536, 544, 546, 551, 588                                                                            |
| 193, 195–197, 205, 207–210, 212,                                                 | 322, 324, 330, 344, 340, 331, 388                                                                            |
| 240, 428, 532, 534                                                               |                                                                                                              |
| utm2lonlat, 174, 176, 183–185, 187, 189,                                         |                                                                                                              |
| 191, 193, 195–197, 205, 207–210,                                                 |                                                                                                              |
| 212, 240, 428, 533, 533                                                          |                                                                                                              |
| vectorShow, 535                                                                  |                                                                                                              |
| velocityStatistics, 13, 17-20, 32, 54, 55,                                       |                                                                                                              |
| 57–59, 65, 125–127, 263, 266, 327,                                               |                                                                                                              |
| 329, 331, 334, 335, 337, 341, 346,                                               |                                                                                                              |
| 351, 355, 360, 363, 365, 367, 431,                                               |                                                                                                              |
| 432, 448, 449, 522–524, 535, 544,                                                |                                                                                                              |
| 546, 548, 550, 551, 586, 588                                                     |                                                                                                              |
| ,, , ,                                                                           |                                                                                                              |